# **Top-level components**

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\((cpython-main)\) (Doc) (reference) toplevel_components.rst, line 8)

Unknown directive type "index".

.. index:: single: interpreter
```

The Python interpreter can get its input from a number of sources: from a script passed to it as standard input or as program argument, typed in interactively, from a module source file, etc. This chapter gives the syntax used in these cases.

### **Complete Python programs**

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\((cpython-main)\) (Doc) (reference) toplevel_components.rst, line 21)

Unknown directive type "index".

.. index:: single: program
```

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\((cpython-main)\) (Doc) (reference) toplevel_components.rst, line 23)

Unknown directive type "index".

... index::
    module: sys
    module: __main__
    module: _builtins
```

While a language specification need not prescribe how the language interpreter is invoked, it is useful to have a notion of a complete Python program. A complete Python program is executed in a minimally initialized environment: all built-in and standard modules are available, but none have been initialized, except for :mod:'sys' (various system services), :mod:'builtins' (built-in functions, exceptions and None) and :mod:'\_\_main\_\_'. The latter is used to provide the local and global namespace for execution of the complete program.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\((cpython-main)\) (Doc) (reference) toplevel_components.rst, line 28); backlink Unknown interpreted text role "mod".
```

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\(cpython-main\) (Doc) (reference) toplevel_components.rst, line 28); backlink Unknown interpreted text role "mod".
```

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\((cpython-main)\) (Doc) (reference) toplevel_components.rst, line 28); backlink Unknown interpreted text role "mod".
```

The syntax for a complete Python program is that for file input, described in the next section.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\((cpython-main)\) (Doc) (reference) toplevel_components.rst, line 39)

Unknown directive type "index".

.. index::
    single: interactive mode
    module: __main__
```

The interpreter may also be invoked in interactive mode; in this case, it does not read and execute a complete program but reads and executes one statement (possibly compound) at a time. The initial environment is identical to that of a complete program; each statement is executed in the namespace of mod: main `.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\((cpython-main)\) (Doc) (reference) toplevel_components.rst, line 43); backlink Unknown interpreted text role "mod".
```

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\((cpython-main)\) (Doc) (reference) toplevel_components.rst, line 49)

Unknown directive type "index".

.. index::
    single: UNIX
    single: Windows
    single: command line
    single: standard input
```

A complete program can be passed to the interpreter in three forms: with the :option:'-c' string command line option, as a file passed as the first command line argument, or as standard input. If the file or standard input is a tty device, the interpreter enters interactive mode; otherwise, it executes the file as a complete program.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\((cpython-main)\) (Doc) (reference) toplevel_components.rst, line 55); backlink Unknown interpreted text role "option".
```

### File input

All input read from non-interactive files has the same form:

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\((cpython-main)\) (Doc) (reference) toplevel_components.rst, line 69)

Unknown directive type "productionlist".

.. productionlist:: python-grammar file_input: (NEWLINE | `statement`)*
```

This syntax is used in the following situations:

- when parsing a complete Python program (from a file or from a string);
- when parsing a module;
- when parsing a string passed to the :func:'exec' function;

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\(cpython-main\) (Doc) (reference) toplevel_components.rst, line 78); backlink

Unknown interpreted text role "fine".
```

## **Interactive input**

Input in interactive mode is parsed using the following grammar:

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\((cpython-main)\) (Doc) (reference) toplevel_components.rst, line 88)

Unknown directive type "productionlist".

.. productionlist:: python-grammar interactive_input: [`stmt_list`] NEWLINE | `compound_stmt` NEWLINE
```

Note that a (top-level) compound statement must be followed by a blank line in interactive mode; this is needed to help the parser detect the end of the input.

### **Expression input**

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\((cpython-main)(Doc)(reference)(cpython-main)(Doc)(cpython-main)(D

Unknown directive type "index".

.. index:: single: input

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\((cpython-main)\) (Doc) (reference) toplevel\_components.rst, line 101)

Unknown directive type "index".

.. index:: builtin: eval

:func:'eval' is used for expression input. It ignores leading whitespace. The string argument to :func:'eval' must have the following form:

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\((cpython-main)\) (Doc) (reference) toplevel\_components.rst, line 103); backlink

Unknown interpreted text role "func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\((cpython-main)(Doc)(reference)(cpython-main)(cp

Unknown interpreted text role "func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\reference\((cpython-main)(Doc)(reference)(cpython-main)(Doc)(cpython-main)(D

Unknown directive type "productionlist".

```
.. productionlist:: python-grammar
   eval_input: `expression_list` NEWLINE*
```