:mod:`cmd` --- Support for line-oriented command interpreters

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 1); backlink

Unknown interpreted text role "mod".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 4)

Unknown directive type "module".

```
.. module:: cmd
    :synopsis: Build line-oriented command interpreters.
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 7)

Unknown directive type "sectionauthor".

.. sectionauthor:: Eric S. Raymond <esr@snark.thyrsus.com>

Source code: :source:`Lib/cmd.py`

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 9); backlink

Unknown interpreted text role "source".

The :class: Cmd' class provides a simple framework for writing line-oriented command interpreters. These are often useful for test harnesses, administrative tools, and prototypes that will later be wrapped in a more sophisticated interface.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main) (Doc) (library) cmd.rst, line 13); backlink

Unknown interpreted text role "class".

A :class:'Cmd' instance or subclass instance is a line-oriented interpreter framework. There is no good reason to instantiate :class:'Cmd' itself; rather, it's useful as a superclass of an interpreter class you define yourself in order to inherit :class:'Cmd''s methods and encapsulate action methods.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main) (Doc) (library) cmd.rst, line 20); backlink

Unknown interpreted text role "class".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main) (Doc) (library) cmd.rst, line 20); backlink

Unknown interpreted text role "class".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 20); backlink

Unknown interpreted text role "class".

The optional argument *completekey* is the <u>mod: readline</u> name of a completion key; it defaults to <u>kbd: Tab</u>. If *completekey* is not <u>const: None</u> and <u>mod: readline</u> is available, command completion is done automatically.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-

main\Doc\library\(cpython-main) (Doc) (library)cmd.rst, line 25); backlink

Unknown interpreted text role 'mod'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 25); backlink

Unknown interpreted text role "kbd".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 25); backlink

Unknown interpreted text role "const".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 25); backlink

Unknown interpreted text role "mod".

The optional arguments *stdin* and *stdout* specify the input and output file objects that the Cmd instance or subclass instance will use for input and output. If not specified, they will default to 'data:'sys.stdin' and 'data:'sys.stdout'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main) (Doc) (library) cmd.rst, line 29); backlink

Unknown interpreted text role "data".

 $System\,Message: ERROR/3 \ (\cite{Continuous} and continuous ample-onboarding-resources \cite{Continuous} and continuous and continuous continuous and continuous and continuous continuou$

Unknown interpreted text role "data".

If you want a given *stdin* to be used, make sure to set the instance's <u>attr:`use_rawinput`</u> attribute to False, otherwise *stdin* will be ignored.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 34); backlink

Unknown interpreted text role "attr".

Cmd Objects

A :class:'Cmd' instance has the following methods:

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 44); backlink

Unknown interpreted text role "class".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 47)

Unknown directive type "method".

.. method:: Cmd.cmdloop(intro=None)

Repeatedly issue a prompt, accept input, parse an initial prefix off the received input, and dispatch to action methods, passing them the remainder of the line as argument.

The optional argument is a banner or intro string to be issued before the first prompt (this overrides the :attr:`intro` class attribute).

If the :mod: `readline` module is loaded, input will automatically inherit :program: `bash`\ -like history-list editing (e.g. :kbd: `Control-P` scrolls back to the last command, :kbd: `Control-N` forward to the next one, :kbd: `Control-F` moves the cursor to the right non-destructively, :kbd: `Control-B` moves the cursor to the left non-destructively, etc.).

An end-of-file on input is passed back as the string ``'EOF'``.

```
.. index::
    single: ? (question mark); in a command interpreter
    single: ! (exclamation); in a command interpreter
```

An interpreter instance will recognize a command name ``foo`` if and only if it has a method :meth:`do_foo`. As a special case, a line beginning with the character ``'?'`` is dispatched to the method :meth:`do_help`. As another special case, a line beginning with the character ``'!'`` is dispatched to the method :meth:`do shell` (if such a method is defined).

This method will return when the :meth:`postcmd` method returns a true value. The *stop* argument to :meth:`postcmd` is the return value from the command's corresponding :meth:`do $\$ method.

If completion is enabled, completing commands will be done automatically, and completing of commands args is done by calling :meth:`complete_foo` with arguments *text*, *line*, *begidx*, and *endidx*. *text* is the string prefix we are attempting to match: all returned matches must begin with it. *line* is the current input line with leading whitespace removed, *begidx* and *endidx* are the beginning and ending indexes of the prefix text, which could be used to provide different completion depending upon which position the argument is in.

All subclasses of :class:`Cmd` inherit a predefined :meth:`do_help`. This method, called with an argument ``'bar'``, invokes the corresponding method :meth:`help_bar`, and if that is not present, prints the docstring of :meth:`do_bar`, if available. With no argument, :meth:`do_help` lists all available help topics (that is, all commands with corresponding :meth:`help_*` methods or commands that have docstrings), and also lists any undocumented commands.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 95)

Unknown directive type "method".

.. method:: Cmd.onecmd(str)

Interpret the argument as though it had been typed in response to the prompt. This may be overridden, but should not normally need to be; see the :meth:`precmd` and :meth:`postcmd` methods for useful execution hooks. The return value is a flag indicating whether interpretation of commands by the interpreter should stop. If there is a :meth:`do_*` method for the command *str*, the return value of that method is returned, otherwise the return value from the :meth:`default` method is returned.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 106)

Unknown directive type "method".

.. method:: Cmd.emptyline()

Method called when an empty line is entered in response to the prompt. If this method is not overridden, it repeats the last nonempty command entered.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 112)

Unknown directive type "method".

.. method:: Cmd.default(line)

Method called on an input line when the command prefix is not recognized. If this method is not overridden, it prints an error message and returns.

main\Doc\library\(cpython-main) (Doc) (library) cmd.rst, line 118)

Unknown directive type "method".

.. method:: Cmd.completedefault(text, line, begidx, endidx)

Method called to complete an input line when no command-specific :meth:`complete *` method is available. By default, it returns an empty list.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 124)

Unknown directive type "method".

.. method:: Cmd.columnize(list, displaywidth=80)

Method called to display a list of strings as a compact set of columns. Each column is only as wide as necessary. Columns are separated by two spaces for readability.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 131)

Unknown directive type "method".

.. method:: Cmd.precmd(line)

Hook method executed just before the command line *line* is interpreted, but after the input prompt is generated and issued. This method is a stub in :class:`Cmd`; it exists to be overridden by subclasses. The return value is used as the command which will be executed by the :meth:`onecmd` method; the :meth:`precmd` implementation may re-write the command or simply return *line* unchanged.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 141)

Unknown directive type "method".

.. method:: Cmd.postcmd(stop, line)

Hook method executed just after a command dispatch is finished. This method is a stub in :class:`Cmd`; it exists to be overridden by subclasses. *line* is the command line which was executed, and *stop* is a flag which indicates whether execution will be terminated after the call to :meth:`postcmd`; this will be the return value of the :meth:`onecmd` method. The return value of this method will be used as the new value for the internal flag which corresponds to *stop*; returning false will cause interpretation to continue.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 152)

Unknown directive type "method".

.. method:: Cmd.preloop()

Hook method executed once when :meth:`cmdloop` is called. This method is a stub in :class:`Cmd`; it exists to be overridden by subclasses.

Unknown directive type "method".

.. method:: Cmd.postloop()

Hook method executed once when :meth:`cmdloop` is about to return. This method is a stub in :class:`Cmd`; it exists to be overridden by subclasses.

Instances of :class: 'Cmd' subclasses have some public instance variables:

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main) (Doc) (library) cmd.rst, line 164); backlink

Unknown interpreted text role "class".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 166)

Unknown directive type "attribute".

.. attribute:: Cmd.prompt
The prompt issued to solicit input.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 171)

Unknown directive type "attribute".

.. attribute:: Cmd.identchars

The string of characters accepted for the command prefix.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 176)

Unknown directive type "attribute".

.. attribute:: Cmd.lastcmd

The last nonempty command prefix seen.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 181)

Unknown directive type "attribute".

.. attribute:: Cmd.cmdqueue

A list of queued input lines. The cmdqueue list is checked in :meth:`cmdloop` when new input is needed; if it is nonempty, its elements will be processed in order, as if entered at the prompt.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 188)

Unknown directive type "attribute".

.. attribute:: Cmd.intro

A string to issue as an intro or banner. May be overridden by giving the :meth: `cmdloop` method an argument.

 $System\,Message: ERROR/3~(\texttt{D:}\conboarding-resources}\copython-main\coc\library\coc, (\texttt{Cpython-main})~(\texttt{Doc})~(\texttt{library})~\texttt{cmd.rst}, \\ \textit{line}~194)$

Unknown directive type "attribute".

.. attribute:: Cmd.doc_header

The header to issue if the help output has a section for documented commands.

 $System\,Message: ERROR/3~(\texttt{D:}\conboarding-resources}\copython-main\coc\library\coc, (\texttt{Cpython-main})~(\texttt{Doc})~(\texttt{library})~\texttt{cmd.rst}, \\ line~199)$

Unknown directive type "attribute".

.. attribute:: Cmd.misc header

The header to issue if the help output has a section for miscellaneous help topics (that is, there are :meth:`help_*` methods without corresponding :meth:`do_*` methods).

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main) (Doc) (library) cmd.rst, line 206)

Unknown directive type "attribute".

.. attribute:: Cmd.undoc header

The header to issue if the help output has a section for undocumented commands (that is, there are :meth: `do_*` methods without corresponding :meth: `help_*` methods).

Unknown directive type "attribute".

.. attribute:: Cmd.ruler

The character used to draw separator lines under the help-message headers. If empty, no ruler line is drawn. It defaults to ``!=!``.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main) (Doc) (library) cmd.rst, line 219)

Unknown directive type "attribute".

.. attribute:: Cmd.use_rawinput

A flag, defaulting to true. If true, :meth:`cmdloop` uses :func:`input` to display a prompt and read the next command; if false, :meth:`sys.stdout.write` and :meth:`sys.stdin.readline` are used. (This means that by importing :mod:`readline`, on systems that support it, the interpreter will automatically support :program:`Emacs`\ -like line editing and command-history keystrokes.)

Cmd Example

 $System\,Message: ERROR/3 \ (\mboarding-resources\spaces) convolved in System Message: ERROR/3 \ (\mboarding-resources) convolved in System Me$

Unknown directive type "sectionauthor".

.. sectionauthor:: Raymond Hettinger <python at rcn dot com>

The mod: cmd' module is mainly useful for building custom shells that let a user work with a program interactively.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 235); backlink

Unknown interpreted text role 'mod'.

This section presents a simple example of how to build a shell around a few of the commands in the .mod.'turtle' module.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 238); backlink

Unknown interpreted text role "mod".

Basic turtle commands such as meth: ~turtle.forward are added to a class: Cmd subclass with method named meth: do_forward. The argument is converted to a number and dispatched to the turtle module. The docstring is used in the help utility provided by the shell.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 241); backlink

Unknown interpreted text role "meth".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main) (Doc) (library) cmd.rst, line 241); backlink

Unknown interpreted text role "class".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main) (Doc) (library) cmd.rst, line 241); backlink

Unknown interpreted text role "meth".

The example also includes a basic record and playback facility implemented with the :meth: `~Cmd.precmd` method which is responsible for converting the input to lowercase and writing the commands to a file. The :meth: `do_playback` method reads the file and adds the recorded commands to the :attr: `cmdqueue` for immediate playback:

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main\) (Doc) (library) cmd.rst, line 246); backlink

Unknown interpreted text role 'meth'.

 $System\,Message: ERROR/3 \ (\cite{Continuous} and continuous ample-onboarding-resources \cite{Continuous} and continuous and continuous continuous and continuous and continuous continuou$

Unknown interpreted text role 'meth'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\library\(cpython-main) (Doc) (library) cmd.rst, line 246); backlink

Unknown interpreted text role "attr".

```
import cmd, sys
from turtle import *
class TurtleShell(cmd.Cmd):
    intro = 'Welcome to the turtle shell. Type help or ? to list commands.\n'
    prompt = '(turtle)
    file = None
    # ---- basic turtle commands ----
    def do forward(self, arg):
        'Move the turtle forward by the specified distance: FORWARD 10'
        forward(*parse(arg))
    def do right (self, arg):
        'Turn turtle right by given number of degrees: RIGHT 20'
        right(*parse(arg))
    def do left(self, arg):
        'Turn turtle left by given number of degrees: LEFT 90'
        left(*parse(arg))
    def do goto(self, arg):
        'Move turtle to an absolute position with changing orientation. GOTO 100 200'
        goto(*parse(arg))
    def do home(self, arg):
```

```
'Return turtle to the home position: HOME'
        home()
    def do circle(self, arg):
        'Draw circle with given radius an options extent and steps: CIRCLE 50'
        circle(*parse(arg))
    def do position(self, arg):
        'Print the current turtle position: POSITION'
        print('Current position is %d %d\n' % position())
    def do heading(self, arg):
        'Print the current turtle heading in degrees: HEADING'
        print('Current heading is %d\n' % (heading(),))
    def do color(self, arg):
        'Set the color: COLOR BLUE'
        color(arg.lower())
    def do_undo(self, arg):
        'Undo (repeatedly) the last turtle action(s): UNDO'
    def do reset(self, arg):
        'Clear the screen and return turtle to center: RESET'
        reset()
    def do bye(self, arg):
        'Stop recording, close the turtle window, and exit: BYE'
        print('Thank you for using Turtle')
        self.close()
       bye()
        return True
    # ---- record and playback ----
    def do record(self, arg):
        'Save future commands to filename: RECORD rose.cmd'
        self.file = open(arg, 'w')
    def do playback(self, arg):
        'Playback commands from a file: PLAYBACK rose.cmd'
        self.close()
        with open(arg) as f:
           self.cmdqueue.extend(f.read().splitlines())
    def precmd(self, line):
        line = line.lower()
        if self.file and 'playback' not in line:
           print(line, file=self.file)
        return line
    def close(self):
        if self.file:
            self.file.close()
            self.file = None
def parse(arg):
    'Convert a series of zero or more numbers to an argument tuple'
    return tuple(map(int, arg.split()))
          == ' main__':
    name
    TurtleShell().cmdloop()
```

Here is a sample session with the turtle shell showing the help functions, using blank lines to repeat commands, and the simple record and playback facility:

```
System Message: WARNING/2 (D:\onboarding-resources\sample-onboarding-
resources\cpython-main\Doc\library\(cpython-main) (Doc) (library) cmd.rst, line 330)
Cannot analyze code. No Pygments lexer found for "none".
   .. code-block:: none
       Welcome to the turtle shell. Type help or ? to list commands.
       (turtle) ?
       Documented commands (type help <topic>):
               color
                                home playback record right
                        goto
       circle forward heading left position reset
       (turtle) help forward
       Move the turtle forward by the specified distance: FORWARD 10
       (turtle) record spiral.cmd
       (turtle) position
       Current position is 0 0
       (turtle) heading
       Current heading is 0
```

```
(turtle) reset
(turtle) circle 20
(turtle) right 30
(turtle) circle 40
(turtle) right 30
(turtle) circle 60
(turtle) right 30
(turtle) circle 80
(turtle) right 30
(turtle) circle 100
(turtle) right 30
(turtle) circle 120
(turtle) right 30
(turtle) circle 120
(turtle) heading
Current heading is 180
(turtle) forward 100
(turtle)
(turtle) right 90
(turtle) forward 100
(turtle)
(turtle) right 90
(turtle) forward 400
(turtle) right 90
(turtle) forward 500
(turtle) right 90
(turtle) forward 400
(turtle) right 90
(turtle) forward 300
(turtle) playback spiral.cmd
Current position is 0 0
Current heading is 0
Current heading is 180
(turtle) bye
Thank you for using Turtle
```