# Including uAPI header files

Sometimes, it is useful to include header files and C example codes in order to describe the userspace API and to generate cross-references between the code and the documentation. Adding cross-references for userspace API files has an additional vantage: Sphinx will generate warnings if a symbol is not found at the documentation. That helps to keep the uAPI documentation in sync with the Kernel changes. The <a href="ref":parse\_headers.pl<parse\_headers">ref":parse\_headers.pl</a> provide a way to generate such cross-references. It has to be called via Makefile, while building the documentation. Please see <a href="Documentation/userspace-api/media/Makefile">Documentation/userspace-api/media/Makefile</a> for an example about how to use it inside the Kernel tree.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\doc-guide\[linux-master] [Documentation] [doc-guide] parseheaders.rst, line 5); backlink

Unknown interpreted text role "ref".

## parse\_headers.pl

## **NAME**

parse\_headers.pl - parse a C file, in order to identify functions, structs, enums and defines and create cross-references to a Sphinx book.

## **SYNOPSIS**

parse\_headers.pl [<options>] <C\_FILE> <OUT\_FILE> [<EXCEPTIONS\_FILE>]

Where <options> can be: --debug, --help or --usage.

## **OPTIONS**

#### -debug

Put the script in verbose mode, useful for debugging.

#### -usage

Prints a brief help message and exits.

#### -help

Prints a more detailed help message and exits.

#### DESCRIPTION

Convert a C header or source file (C\_FILE), into a ReStructured Text included via ..parsed-literal block with cross-references for the documentation files that describe the API. It accepts an optional EXCEPTIONS\_FILE with describes what elements will be either ignored or be pointed to a non-default reference.

The output is written at the (OUT FILE).

It is capable of identifying defines, functions, structs, typedefs, enums and enum symbols and create cross-references for all of them. It is also capable of distinguish #define used for specifying a Linux ioctl.

The EXCEPTIONS FILE contain two types of statements: ignore or replace.

The syntax for the ignore tag is:

## ignore type name

The **ignore** means that it won't generate cross references for a **name** symbol of type **type**.

The syntax for the replace tag is:

replace type name new\_value

The **replace** means that it will generate cross references for a **name** symbol of type **type**, but, instead of using the default replacement rule, it will use **new value**.

For both statements, type can be either one of the following:

## ioctl

The ignore or replace statement will apply to ioctl definitions like:

```
#define VIDIOC DBG S REGISTER IOW('V', 79, struct v412 dbg register)
```

#### define

The ignore or replace statement will apply to any other #define found at C\_FILE.

## typedef

The ignore or replace statement will apply to typedef statements at C\_FILE.

#### struct

The ignore or replace statement will apply to the name of struct statements at C FILE.

#### enum

The ignore or replace statement will apply to the name of enum statements at C FILE.

## symbol

The ignore or replace statement will apply to the name of enum value at C\_FILE.

For replace statements, **new\_value** will automatically use :c:type: references for **typedef**, **enum** and **struct** types. It will use ref. for **ioctl**, **define** and **symbol** types. The type of reference can also be explicitly defined at the replace statement.

## **EXAMPLES**

```
ignore define _VIDEODEV2_H at the C_FILE.

Ignore a #define _VIDEODEV2_H at the C_FILE.

ignore symbol PRIVATE

On a struct like:
enum foo { BAR1, BAR2, PRIVATE };

It won't generate cross-references for PRIVATE.

replace symbol BAR1 :c:type:`foo` replace symbol BAR2 :c:type:`foo`

On a struct like:
enum foo { BAR1, BAR2, PRIVATE };

It will make the BAR1 and BAR2 enum symbols to cross reference the foo symbol at the C domain.
```

## **BUGS**

Report bugs to Mauro Carvalho Chehab <mchehab@kernel.org>

## **COPYRIGHT**

Copyright (c) 2016 by Mauro Carvalho Chehab < mchehab + samsung@kernel.org>.

License GPLv2: GNU GPL version 2 <a href="https://gnu.org/licenses/gpl.htm">https://gnu.org/licenses/gpl.htm</a>.

This is free software: you are free to change and redistribute it. There is NO WARRANTY, to the extent permitted by law.