Extending/Embedding FAQ

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 5)

Unknown directive type "only".

.. only:: html

.. contents::
```

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\(cpython-main\) (Doc) (faq) extending.rst, line 9)

Unknown directive type "highlight".

.. highlight:: c
```

Can I create my own functions in C?

Yes, you can create built-in modules containing functions, variables, exceptions and even new types in C. This is explained in the document ref" extending-index.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\(cpython-main\) (Doc) (faq) extending.rst, line 18); backlink
Unknown interpreted text role "ref".
```

Most intermediate or advanced Python books will also cover this topic.

Can I create my own functions in C++?

Yes, using the C compatibility features found in C++. Place extern "C" { ... } around the Python include files and put extern "C" before each function that is going to be called by the Python interpreter. Global or static C++ objects with constructors are probably not a good idea.

Writing C is hard; are there any alternatives?

There are a number of alternatives to writing your own C extensions, depending on what you're trying to do.

Cython and its relative Pyrex are compilers that accept a slightly modified form of Python and generate the corresponding C code. Cython and Pyrex make it possible to write an extension without having to learn Python's C API.

If you need to interface to some C or C++ library for which no Python extension currently exists, you can try wrapping the library's data types and functions with a tool such as SWIG. SIP, CXX Boost, or Weave are also alternatives for wrapping C++ libraries.

How can I execute arbitrary Python statements from C?

The highest-level function to do this is c:func: PyRun_SimpleString` which takes a single string argument to be executed in the context of the module __main__ and returns 0 for success and -1 when an exception occurred (including :exc: SyntaxError`). If you want more control, use c:func: PyRun_String`; see the source for c:func: PyRun_SimpleString` in Python/pythonrun.c.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\(cpython-main)\ (Doc)\((faq)\) extending.rst, line 63); backlink

Unknown interpreted text role "c:fimc".
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 63); backlink

Unknown interpreted text role "exc".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 63); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\(cpython-main\) (Doc) (faq) extending.rst, line 63); backlink

Unknown interpreted text role "c:func".

How can I evaluate an arbitrary Python expression from C?

Call the function :c:func: PyRun_String` from the previous question with the start symbol :c:data: Py_eval_input`; it parses an expression, evaluates it and returns its value.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 74); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 74); backlink

Unknown interpreted text role "c:data".

How do I extract C values from a Python object?

That depends on the object's type. If it's a tuple, :c:func: PyTuple_Size` returns its length and :c:func: PyTuple_GetItem` returns the item at a specified index. Lists have similar functions, :c:func: PyListSize` and :c:func: PyList GetItem`.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 82); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 82); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 82); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 82); backlink

Unknown interpreted text role "c:func".

For bytes, :c:func: 'PyBytes_Size' returns its length and :c:func: 'PyBytes_AsStringAndSize' provides a pointer to its value and its length. Note that Python bytes objects may contain null bytes so C's :c:func: 'strlen' should not be used.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 87); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 87); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-

```
main\Doc\faq\(cpython-main) (Doc) (faq) extending.rst, line 87); backlink Unknown interpreted text role "c:fimc".
```

To test the type of an object, first make sure it isn't <code>NULL</code>, and then use <code>:c:func:'PyBytes_Check'</code>, <code>:c:func:'PyTuple_Check'</code>, <code>:c:func:'PyList_Check'</code>, etc.

 $System\ Message: ERROR/3\ (\texttt{D:\onboarding-resources\sample-onboarding-resources\cpython-main\space)} to be a considered and the properties of the propert$

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 92); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 92); backlink

Unknown interpreted text role "c:func".

There is also a high-level API to Python objects which is provided by the so-called 'abstract' interface -- read Include/abstract.h for further details. It allows interfacing with any kind of Python sequence using calls like :c:func:`PySequence_Length`, :c:func:`PySequence_GetItem`, etc. as well as many other useful protocols such as numbers (:c:func:`PyNumber_Index` et al.) and mappings in the PyMapping APIs.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 95); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 95); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 95); backlink

Unknown interpreted text role "c:func".

How do I use Py_BuildValue() to create a tuple of arbitrary length?

You can't. Use :c:func:`PyTuple Pack` instead.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 106); backlink

Unknown interpreted text role "c:func".

How do I call an object's method from C?

The :c:func: PyObject_CallMethod` function can be used to call an arbitrary method of an object. The parameters are the object, the name of the method to call, a format string like that used with :c:func: Py BuildValue`, and the argument values:

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 112); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 112); backlink

Unknown interpreted text role "c:func".

This works for any object that has methods -- whether built-in or user-defined. You are responsible for eventually :c:func: Py DECREF' ing the return value.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\(cpython-main\) (Doc) (faq) extending.rst, line 121); backlink
Unknown interpreted text role "c:fime".
```

To call, e.g., a file object's "seek" method with arguments 10, 0 (assuming the file object pointer is "f"):

Note that since :c:func:`PyObject_CallObject` always wants a tuple for the argument list, to call a function without arguments, pass " ()" for the format, and to call a function with one argument, surround the argument in parentheses, e.g. "(i)".

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\(cpython-main\) (Doc) (faq) extending.rst, line 135); backlink

Unknown interpreted text role "c:fimc".
```

How do I catch the output from PyErr_Print() (or anything that prints to stdout/stderr)?

In Python code, define an object that supports the write() method. Assign this object to :data:`sys.stdout` and :data:`sys.stderr`. Call print_error, or just allow the standard traceback mechanism to work. Then, the output will go wherever your write() method sends it.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\(cpython-main\) (Doc) (faq) extending.rst, line 144); backlink
Unknown interpreted text role "data".
```

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\(cpython-main\) (Doc) (faq) extending.rst, line 144); backlink
Unknown interpreted text role "data".
```

The easiest way to do this is to use the :class:'io.StringIO' class:

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\(cpython-main\) (Doc) (faq) extending.rst, line 149); backlink
Unknown interpreted text role "class".
```

```
>>> import io, sys
>>> sys.stdout = io.StringIO()
>>> print('foo')
>>> print('hello world!')
>>> sys.stderr.write(sys.stdout.getvalue())
foo
hello world!
```

A custom object to do the same would look like this:

```
>>> import io, sys
>>> class StdoutCatcher(io.TextIOBase):
...     def __init__(self):
...     self.data = []
...     def write(self, stuff):
```

```
... self.data.append(stuff)
...
>>> import sys
>>> sys.stdout = StdoutCatcher()
>>> print('foo')
>>> print('hello world!')
>>> sys.stderr.write(''.join(sys.stdout.data))
foo
hello world!
```

How do I access a module written in Python from C?

You can get a pointer to the module object as follows:

```
module = PyImport ImportModule("<modulename>");
```

If the module hasn't been imported yet (i.e. it is not yet present in :data:`sys.modules`), this initializes the module; otherwise it simply returns the value of sys.modules["<modulename>"]. Note that it doesn't enter the module into any namespace -- it only ensures it has been initialized and is stored in :data:`sys.modules`.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\(cpython-main) (Doc) (faq) extending.rst, line 188); backlink
Unknown interpreted text role "data".
```

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 188); backlink
```

Unknown interpreted text role "data".

You can then access the module's attributes (i.e. any name defined in the module) as follows:

```
attr = PyObject GetAttrString(module, "<attrname>");
```

Calling :c:func: PyObject SetAttrString` to assign to variables in the module also works.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\(cpython-main) (Doc) (faq) extending.rst, line 199); backlink
```

Unknown interpreted text role "c:func".

How do I interface to C++ objects from Python?

Depending on your requirements, there are many approaches. To do this manually, begin by reading ref: the "Extending and Embedding" document <extending-index>`. Realize that for the Python run-time system, there isn't a whole lot of difference between C and C++ -- so the strategy of building a new Python type around a C structure (pointer) type will also work for C++ objects.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 206); backlink
Unknown interpreted text role "ref".
```

For C++ libraries, see ref.'c-wrapper-software'.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\(cpython-main\) (Doc) (faq) extending.rst, line 212); backlink
Unknown interpreted text role "ref".
```

I added a module using the Setup file and the make fails; why?

Setup must end in a newline, if there is no newline there, the build process fails. (Fixing this requires some ugly shell script hackery, and this bug is so minor that it doesn't seem worth the effort.)

How do I debug an extension?

When using GDB with dynamically loaded extensions, you can't set a breakpoint in your extension until your extension is loaded. In your .gdbinit file (or interactively), add the command:

```
System Message: WARNING/2 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 231)

Cannot analyze code. No Pygments lexer found for "none".

.. code-block:: none

br _PyImport_LoadDynamicModule
```

Then, when you run GDB:

```
$ gdb /local/bin/python
gdb) run myscript.py
gdb) continue # repeat until your extension is loaded
gdb) finish # so that your extension is loaded
gdb) br myfunction.c:50
gdb) continue
```

I want to compile a Python module on my Linux system, but some files are missing. Why?

Most packaged versions of Python don't include the :file: \usr/lib/python2. \{x\}/config/\directory, which contains various files required for compiling Python extensions.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\(cpython-main\) (Doc) (faq) extending.rst, line 249); backlink
Unknown interpreted text role "file".
```

For Red Hat, install the python-devel RPM to get the necessary files.

For Debian, run apt-get install python-dev.

How do I tell "incomplete input" from "invalid input"?

Sometimes you want to emulate the Python interactive interpreter's behavior, where it gives you a continuation prompt when the input is incomplete (e.g. you typed the start of an "if" statement or you didn't close your parentheses or triple string quotes), but it gives you a syntax error message immediately when the input is invalid.

In Python you can use the <u>mod</u>: codeop module, which approximates the parser's behavior sufficiently. IDLE uses this, for example.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\(cpython-main)\Doc)\((faq)\) extending.rst, line 266); backlink
Unknown interpreted text role "mod".
```

The easiest way to do it in C is to call c:func: PyRun_InteractiveLoop` (perhaps in a separate thread) and let the Python interpreter handle the input for you. You can also set the :c:func: PyOS_ReadlineFunctionPointer` to point at your custom input function. See Modules/readline.c and Parser/myreadline.c for more hints.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\(cpython-main\) (Doc) (faq) extending.rst, line 269); backlink
Unknown interpreted text role "c:fime".
```

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\(cpython-main\) (Doc) (faq) extending.rst, line 269); backlink
Unknown interpreted text role "c:func".
```

How do I find undefined g++ symbols __builtin_new or __pure_virtual?

To dynamically load g++ extension modules, you must recompile Python, relink it using g++ (change LINKCC in the Python Modules Makefile), and link your extension module using g++ (e.g., g++ -shared -o mymodule.so mymodule.o).

Can I create an object class with some methods implemented in C and others

in Python (e.g. through inheritance)?

Yes, you can inherit from built-in classes such as :class:'int', :class:'list', :class:'dict', etc.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 286); backlink

Unknown interpreted text role "class".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\faq\((cpython-main)\) (Doc) (faq) extending.rst, line 286); backlink

Unknown interpreted text role "class".

 $System\,Message: ERROR/3~(\texttt{D:}\conboarding-resources}\copython-main\coc\faq\copython-main\coc\faq\copython-main\coc\faq\copython-main\coc\faq\copython-main\coc\faq\$

Unknown interpreted text role "class".

The Boost Python Library (BPL, http://www.boost.org/libs/python/doc/index.html) provides a way of doing this from C++ (i.e. you can inherit from an extension class written in C++ using the BPL).