Build scrcpy

Here are the instructions to build *scrcpy* (client and server).

Simple

If you just want to install the latest release from master, follow this simplified process.

First, you need to install the required packages:

Branches

master

The master branch concerns the latest release, and is the home page of the project on Github.

dev

dev is the current development branch. Every commit present in dev will be in the next release.

If you want to contribute code, please base your commits on the latest dev branch.

Requirements

You need adb. It is available in the Android SDK platform tools, or packaged in your distribution (adb).

On Windows, download the platform-tools and extract the following files to a directory accessible from your PATH: - adb.exe - AdbWinApi.dll - AdbWinUsbApi.dll

The client requires FFmpeg and LibSDL2. Just follow the instructions.

System-specific steps

Linux

Install the required packages from your package manager.

```
Debian/Ubuntu
```

```
# runtime dependencies
sudo apt install ffmpeg libsdl2-2.0-0 adb libusb-1.0-0
# client build dependencies
sudo apt install gcc git pkg-config meson ninja-build libsdl2-dev \
                 libavcodec-dev libavdevice-dev libavformat-dev libavutil-dev \
                 libusb-1.0-0-dev
# server build dependencies
sudo apt install openjdk-11-jdk
On old versions (like Ubuntu 16.04), meson is too old. In that case, install it
from pip3:
sudo apt install python3-pip
pip3 install meson
Fedora
# enable RPM fusion free
sudo dnf install https://download1.rpmfusion.org/free/fedora/rpmfusion-free-release-$(rpm --
# client build dependencies
sudo dnf install SDL2-devel ffms2-devel libusb-devel meson gcc make
# server build dependencies
sudo dnf install java-devel
Windows
Cross-compile from Linux This is the preferred method (and the way the
release is built).
From Debian, install mingw:
```

sudo apt install mingw-w64 mingw-w64-tools

```
You also need the JDK to build the server:
```

```
sudo apt install openjdk-11-jdk
```

Then generate the releases:

```
./release.sh
```

It will generate win32 and win64 releases into dist/.

In MSYS2 From Windows, you need MSYS2 to build the project. From an

```
MSYS2 terminal, install the required packages:
# runtime dependencies
pacman -S mingw-w64-x86_64-SDL2 \
          mingw-w64-x86_64-ffmpeg \
          mingw-w64-x86_64-libusb
# client build dependencies
pacman -S mingw-w64-x86_64-make \
          mingw-w64-x86_64-gcc \
          mingw-w64-x86_64-pkg-config \
          mingw-w64-x86_64-meson
For a 32 bits version, replace x86_64 by i686:
# runtime dependencies
pacman -S mingw-w64-i686-SDL2 \
          mingw-w64-i686-ffmpeg \
          mingw-w64-i686-libusb
# client build dependencies
pacman -S mingw-w64-i686-make \
          mingw-w64-i686-gcc \
          mingw-w64-i686-pkg-config \
          mingw-w64-i686-meson
Java (>= 7) is not available in MSYS2, so if you plan to build the server, install
it manually and make it available from the PATH:
export PATH="$JAVA_HOME/bin:$PATH"
Mac OS
Install the packages with Homebrew:
# runtime dependencies
brew install sdl2 ffmpeg libusb
# client build dependencies
brew install pkg-config meson
```

Additionally, if you want to build the server, install Java 8 from Caskroom, and make it available from the PATH:

```
brew tap homebrew/cask-versions
brew install adoptopenjdk/openjdk/adoptopenjdk11
export JAVA_HOME="$(/usr/libexec/java_home --version 1.11)"
export PATH="$JAVA_HOME/bin:$PATH"
```

Docker

See pierlon/scrcpy-docker.

Common steps

As a non-root user, clone the project:

```
git clone https://github.com/Genymobile/scrcpy
cd scrcpy
```

Build

You may want to build only the client: the server binary, which will be pushed to the Android device, does not depend on your system and architecture. In that case, use the prebuilt server (so you will not need Java or the Android SDK).

Option 1: Build everything from sources Install the Android SDK (*Android Studio*), and set ANDROID_SDK_ROOT to its directory. For example:

```
# Linux
export ANDROID_SDK_ROOT=~/Android/Sdk
# Mac
export ANDROID_SDK_ROOT=~/Library/Android/sdk
# Windows
set ANDROID_SDK_ROOT=%LOCALAPPDATA%\Android\sdk
Then, build:
meson x --buildtype=release --strip -Db_lto=true
ninja -Cx # DO NOT RUN AS ROOT
```

Note: ninja must be run as a non-root user (only ninja install must be run as root).

Option 2: Use prebuilt server

• scrcpy-server-v1.23 (SHA-256: 2a913fd47478c0b306fca507cb0beb625e49a19ff9fc7ab904e36ef5b9fe7e68)

Download the prebuilt server somewhere, and specify its path during the Meson configuration:

```
meson x --buildtype=release --strip -Db_lto=true \
    -Dprebuilt_server=/path/to/scrcpy-server
ninja -Cx # DO NOT RUN AS ROOT
```

The server only works with a matching client version (this server works with the master branch).

Run without installing:

```
./run x [options]
```

Install

After a successful build, you can install *scrcpy* on the system:

```
sudo ninja -Cx install # without sudo on Windows
```

This installs three files:

- /usr/local/bin/scrcpy
- /usr/local/share/scrcpy/scrcpy-server
- /usr/local/share/man/man1/scrcpy.1

You can then run screpy.

Uninstall

```
sudo ninja -Cx uninstall # without sudo on Windows
```