# ioctl VIDIOC\_G\_SELECTION, VIDIOC\_S\_SELECTION

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 2)

Unknown directive type "c:namespace".

.. c:namespace:: V4L

## Name

VIDIOC G SELECTION - VIDIOC S SELECTION - Get or set one of the selection rectangles

## **Synopsis**

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 18)

Unknown directive type "c:macro".

.. c:macro:: VIDIOC\_G\_SELECTION

int ioctl(int fd, VIDIOC G SELECTION, struct v412 selection \*argp)

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 22)

Unknown directive type "c:macro".

.. c:macro:: VIDIOC S SELECTION

int ioctl(int fd, VIDIOC S SELECTION, struct v412 selection \*argp)

## Arguments

fd

File descriptor returned by :c:func:'open()'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master\)
(Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 30); backlink

Unknown interpreted text role "c:func".

Unknown interpreted text role "c:type".

arqp

Pointer to struct :c:type:\v412 selection\.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master\) (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 33); backlink

## Description

The ioctls are used to query and configure selection rectangles.

To query the cropping (composing) rectangle set struct :c:type: v412\_selection` type field to the respective buffer type. The next step is setting the value of struct :c:type: v412\_selection` target field to V4L2\_SEL\_TGT\_CROP (V4L2\_SEL\_TGT\_COMPOSE). Please refer

to table ref: v4l2-selections-common' or ref: selection-api' for additional targets. The flags and reserved fields of struct retype: v4l2\_selection' are ignored and they must be filled with zeros. The driver fills the rest of the structure or returns EINVAL error code if incorrect buffer type or target was used. If cropping (composing) is not supported then the active rectangle is not mutable and it is always equal to the bounds rectangle. Finally, the struct retype: v4l2\_rect' rectangle is filled with the current cropping (composing) coordinates. The coordinates are expressed in driver-dependent units. The only exception are rectangles for images in raw formats, whose coordinates are always expressed in pixels.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master)\((Documentation\)\) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 40); backlink

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 40); backlink

Unknown interpreted text role "c:type".

 $System\,Message:\,ERROR/3~(\mbox{D:\nonlinear-resources}) ample-onboarding-resources $$\lim\max_{master\Documentation\userspace-api\mbox{media}\v41\(linux-master)~(\mbox{Documentation})~(userspace-api)~(media)~(v41)~vidioc-g-selection.rst, line~40); $backlink$$ 

Unknown interpreted text role 'ref'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 40); backlink

Unknown interpreted text role "ref".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 40); backlink

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 40); backlink

Unknown interpreted text role "c:type".

To change the cropping (composing) rectangle set the struct :c:type:'v412\_selection' type field to the respective buffer type. The next step is setting the value of struct :c:type:'v412\_selection' target to V4L2\_SEL\_TGT\_CROP (V4L2\_SEL\_TGT\_COMPOSE). Please refer to table :ref:'v412-selections-common' or :ref:'selection-api' for additional targets. The struct :c:type:'v412\_rect' r rectangle need to be set to the desired active area. Field struct :c:type:'v412\_selection' reserved is ignored and must be filled with zeros. The driver may adjust coordinates of the requested rectangle. An application may introduce constraints to control rounding behaviour. The struct :c:type:'v412\_selection' flags field must be set to one of the following:

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master)\( (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 58); backlink

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master)\( (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 58); backlink

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\((linux-master)\) (Documentation) (userspace-

```
api) (media) (v41) vidioc-g-selection.rst, line 58); backlink Unknown interpreted text role "ref".
```

Unknown interpreted text role 'ref'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master)\((Documentation\)\((userspace-api\)\)\((media)\((v41)\)\(vidioc-g-selection.rst, line 58);\)\(backlink

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master)\( (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 58); backlink

Unknown interpreted text role "c:type".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 58); backlink

Unknown interpreted text role "c:type".

- 0 The driver can adjust the rectangle size freely and shall choose a crop/compose rectangle as close as possible to the requested one.
- V4L2\_SEL\_FLAG\_GE The driver is not allowed to shrink the rectangle. The original rectangle must lay inside the adjusted one.
- V4L2\_SEL\_FLAG\_LE The driver is not allowed to enlarge the rectangle. The adjusted rectangle must lay inside the original
  one.
- V4L2\_SEL\_FLAG\_GE | V4L2\_SEL\_FLAG\_LE The driver must choose the size exactly the same as in the requested rectangle.

Please refer to ref. 'sel-const-adjust'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master)\( (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 85); backlink

Unknown interpreted text role "ref".

The driver may have to adjusts the requested dimensions against hardware limits and other parts as the pipeline, i.e. the bounds given by the capture/output window or TV display. The closest possible values of horizontal and vertical offset and sizes are chosen according to following priority:

1. Satisfy constraints from struct :c:type:\v412\_selection\` flags.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master\) (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 93); backlink Unknown interpreted text role "c:type".

- 2. Adjust width, height, left, and top to hardware limits and alignments.
- 3. Keep center of adjusted rectangle as close as possible to the original one.
- 4. Keep width and height as close as possible to original ones.
- 5. Keep horizontal and vertical offset as close as possible to original ones.

On success the struct <code>c.type:`v412\_rect`</code> r field contains the adjusted rectangle. When the parameters are unsuitable the application may modify the cropping (composing) or image parameters and repeat the cycle until satisfactory parameters have been negotiated. If constraints flags have to be violated at then <code>ERANGE</code> is returned. The error indicates that *there exist no rectangle* that satisfies the constraints.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master)\((Documentation\)\((userspace-api\)\)\((media)\((v41)\)\(vidioc-g-selection.rst, line 107)\);\(backlink\)

Unknown interpreted text role "c:type".

Selection targets and flags are documented in <a href="ref": v412-selections-common">: ref</a> v412-selections-common</a>.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 115); backlink

Unknown interpreted text role "ref".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 120)

Unknown directive type "kernel-figure".

```
.. kernel-figure:: constraints.svg
    :alt: constraints.svg
    :align: center
    Size adjustments with constraint flags.
Behaviour of rectangle adjustment for different constraint flags.
```

 $System\ Message:\ ERROR/3\ (\mbox{D:\noboarding-resources}\ \mbox{linux-master}) \ (\mbox{Documentation}\ \mbox{userspace-api\mbox{media}v41\ (linux-master)}\ (\mbox{Documentation}\ ) \ (\mbox{userspace-api}\ \mbox{media}\ ) \ (\mbox{v41}\ \mbox{vidioc-g-selection.rst},\ \mbox{line}\ 130)$ 

Unknown directive type "c:type".

```
.. c:type:: v412_selection
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 132)

Unknown directive type "tabularcolumns".

```
.. tabularcolumns:: |p{4.4cm}|p{4.4cm}|p{8.5cm}|
```

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 134)

Unknown directive type "flat-table".

```
- ``r``
- The selection rectangle.
- __u32
- ``reserved[9]``
- Reserved fields for future use. Drivers and applications must zero this array.
```

#### Note

Unfortunately in the case of multiplanar buffer types (V4L2\_BUF\_TYPE\_VIDEO\_CAPTURE\_MPLANE and V4L2\_BUF\_TYPE\_VIDEO\_OUTPUT\_MPLANE) this API was messed up with regards to how the :c:type:`v4l2\_selection` type field should be filled in. Some drivers only accepted the \_mplane buffer type while other drivers only accepted a non-multiplanar buffer type (i.e. without the \_mplane at the end).

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 160); backlink

Unknown interpreted text role "c:type".

Starting with kernel 4.13 both variations are allowed.

## Return Value

On success 0 is returned, on error -1 and the errno variable is set appropriately. The generic error codes are described at the ref. Generic Error Codes <gen-errors>` chapter.

Unknown interpreted text role 'ref'.

## **EINVAL**

Given buffer type type or the selection target target is not supported, or the flags argument is not valid.

### **ERANGE**

It is not possible to adjust struct :c:type:'v412\_rect' r rectangle to satisfy all constraints given in the flags argument.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\linux-master\Documentation\userspace-api\media\v41\(linux-master) (Documentation) (userspace-api) (media) (v41) vidioc-g-selection.rst, line 181); backlink Unknown interpreted text role "c:type".

#### **ENODATA**

Selection is not supported for this input or output.

### **EBUSY**

It is not possible to apply change of the selection rectangle at the moment. Usually because streaming is in progress.