This has a new binding scheme in building OpenSSL-3.0.0 library with Node.js. OpenSSL-3.0.0 uses a new build system with Perl for various supported platforms. See openssl/Configurations/README and openssl/Configurations/README-design.md in the OpenSSL source for details.

In order to build OpenSSL library without Perl in the build of Node.js for various supported platforms, platform dependent files (e.g. asm and header files ) are pre-generated and stored into the config/archs directory.

config/Makefile and config/generate gypi.pl

Makefile has supported platform list and generates and copies platform dependent files (e.g. asm files) into arch directory with <code>generate\_gypi.pl</code>. Platform dependent gypi files are also created obtaining build information from <code>configdata.pm</code> that is generated with <code>Configure</code> in the OpenSSL build system.

For Windows, Configure generates makefile that is only available to nmake command. config/Makefile\_VC-WIN32 and config/Makefile\_VC-WIN64A are made by hand for the use of GNU make. If makefile rules or targets are changed in the version up of OpenSSL, they should be also updated.

• gyp and gypi files ( openssl\*.{gyp,gypi} )

openssl.gyp has two targets of openssl and openssl-cli referred from <code>node.gyp</code>. They include asm and no\_asm gypi files with arch dependent gypi according to its build options and platforms. The gyp data which is common with asm and no\_asm are stored in <code>openssl common.gypi</code>.

• header files ( config/\*.{h,h.tmpl} )

 $bn\_conf.h$ ,  $dso\_conf.h$  and opensslconf.h are platform dependent in the OpenSSL sources. They are replaced with config/\*.h.tmpl files to include the file in the ../../config/ and referred to each arch file that depends on asm and no-asm option. These headers are generated by the make target generate\_headers .

## Supported architectures for use of ASM

Here is a list of supported architectures for use of ASM in OpenSSL.

dest-os	dest-cpu	OpenSSL target arch	CI
aix	ppc	aix-gcc	О
aix	ppc64	aix64-gcc	0
linux	ia32	linux-elf	0
linux	x32	linux-x32	-
linux	x64	linux-x86_64	0
linux	arm	linux-armv4	0
linux	arm64	linux-aarch64	0
linux	ppc	linux-ppc	0
linux	ppc64	linux-ppc64	0
linux	ppc64(*1)	linux-ppc64le	0

0
0
-
0
-
0
0
0
-
0
-
-
-

(\*1: This needs to be configured with the variable of node\_byteorder: little)

These are listed in <u>config/Makefile</u>. Please refer <u>config/opensslconf\_asm.h</u> for details.

## **Upgrading OpenSSL**

Please refer to maintaining-openssl.