Curses Programming with Python

Author: A.M. Kuchling, Eric S. Raymond

Release: 2.04

Abstract

This document describes how to use the <u>mod</u>: curses' extension module to control text-mode displays.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 13); hacklink

Unknown interpreted text role "mod".

What is curses?

The curses library supplies a terminal-independent screen-painting and keyboard-handling facility for text-based terminals; such terminals include VT100s, the Linux console, and the simulated terminal provided by various programs. Display terminals support various control codes to perform common operations such as moving the cursor, scrolling the screen, and erasing areas. Different terminals use widely differing codes, and often have their own minor quirks.

In a world of graphical displays, one might ask "why bother"? It's true that character-cell display terminals are an obsolete technology, but there are niches in which being able to do fancy things with them are still valuable. One niche is on small-footprint or embedded Unixes that don't run an X server. Another is tools such as OS installers and kernel configurators that may have to run before any graphical support is available.

The curses library provides fairly basic functionality, providing the programmer with an abstraction of a display containing multiple non-overlapping windows of text. The contents of a window can be changed in various ways---adding text, erasing it, changing its appearance---and the curses library will figure out what control codes need to be sent to the terminal to produce the right output. curses doesn't provide many user-interface concepts such as buttons, checkboxes, or dialogs; if you need such features, consider a user interface library such as Urwid.

The curses library was originally written for BSD Unix; the later System V versions of Unix from AT&T added many enhancements and new functions. BSD curses is no longer maintained, having been replaced by neurses, which is an open-source implementation of the AT&T interface. If you're using an open-source Unix such as Linux or FreeBSD, your system almost certainly uses neurses. Since most current commercial Unix versions are based on System V code, all the functions described here will probably be available. The older versions of curses carried by some proprietary Unixes may not support everything, though.

The Windows version of Python doesn't include the "mod' curses' module. A ported version called UniCurses is available.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 56); backlink

Unknown interpreted text role "mod".

The Python curses module

The Python module is a fairly simple wrapper over the C functions provided by curses; if you're already familiar with curses programming in C, it's really easy to transfer that knowledge to Python. The biggest difference is that the Python interface makes things simpler by merging different C functions such as :c:func:`addstr`, :c:func:`mvaddstr`, and :c:func:`mvwaddstr` into a single meth:`~curses, window, addstr` method. You'll see this covered in more detail later.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 64); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 64); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 64); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 64); backlink

Unknown interpreted text role "meth".

This HOWTO is an introduction to writing text-mode programs with curses and Python. It doesn't attempt to be a complete guide to the curses API; for that, see the Python library guide's section on neurses, and the C manual pages for neurses. It will, however, give you the basic ideas.

Starting and ending a curses application

Before doing anything, curses must be initialized. This is done by calling the :func:`~curses.initscr` function, which will determine the terminal type, send any required setup codes to the terminal, and create various internal data structures. If successful, :func:`initscr` returns a window object representing the entire screen; this is usually called stdscr after the name of the corresponding C variable.

 $System \, Message: ERROR/3 \, (\texttt{D:\noboarding-resources\sample-onboarding-resources\cpython-main\noc\howto\cpython-main\cite{Conton-main\noc\noc\color{Conton-main\noc\color{Conton-main\noc\noc\color{Conton-main\noc\color{Conton-main\noc\noc\color{Conton-main\noc\colo$

Unknown interpreted text role "func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 81); backlink

Unknown interpreted text role "func".

```
import curses
stdscr = curses.initscr()
```

Usually curses applications turn off automatic echoing of keys to the screen, in order to be able to read keys and only display them under certain circumstances. This requires calling the :func:`~curses.noecho` function.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 92); backlink

Unknown interpreted text role "func".

```
curses.noecho()
```

Applications will also commonly need to react to keys instantly, without requiring the Enter key to be pressed; this is called cbreak mode, as opposed to the usual buffered input mode.

```
curses.cbreak()
```

Terminals usually return special keys, such as the cursor keys or navigation keys such as Page Up and Home, as a multibyte escape sequence. While you could write your application to expect such sequences and process them accordingly, curses can do it for you, returning a special value such as <code>:const::curses.KEY_LEFT</code>. To get curses to do the job, you'll have to enable keypad mode.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 105); backlink

Unknown interpreted text role "const".

```
stdscr.keypad(True)
```

Terminating a curses application is much easier than starting one. You'll need to call:

```
curses.nocbreak()
stdscr.keypad(False)
curses.echo()
```

to reverse the curses-friendly terminal settings. Then call the :func:`~curses.endwin` function to restore the terminal to its original operating mode.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc][howto]curses.rst, line 121); backlink

Unknown interpreted text role "func".

```
curses.endwin()
```

A common problem when debugging a curses application is to get your terminal messed up when the application dies without restoring the terminal to its previous state. In Python this commonly happens when your code is buggy and raises an uncaught exception. Keys are no longer echoed to the screen when you type them, for example, which makes using the shell difficult.

In Python you can avoid these complications and make debugging much easier by importing the :func:'curses.wrapper' function and using it like this:

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 133); backlink

Unknown interpreted text role "func".

```
from curses import wrapper

def main(stdscr):
    # Clear screen
    stdscr.clear()

# This raises ZeroDivisionError when i == 10.
    for i in range(0, 11):
        v = i-10
        stdscr.addstr(i, 0, '10 divided by {} is {}'.format(v, 10/v))

stdscr.refresh()
    stdscr.getkey()

wrapper(main)
```

The :finc:`~curses.wrapper` function takes a callable object and does the initializations described above, also initializing colors if color support is present. :finc:`wrapper` then runs your provided callable. Once the callable returns, :finc:`wrapper` will restore the original state of the terminal. The callable is called inside a :keyword:`try`...:keyword:`except` that catches exceptions, restores the state of the terminal, and then re-raises the exception. Therefore your terminal won't be left in a funny state on exception and you'll be able to read the exception's message and traceback.

 $System\,Message:\,ERROR/3\, (\mbox{D:\nonlinear-resources}\xspace) ample-onboarding-resources\xspace \xspace, line\,152); \ backlink \xspace \xspace \xspace, backlink \xspace \xspace \xspace \xspace, backlink \xspace \xspace$

Unknown interpreted text role "func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 152); backlink

Unknown interpreted text role "func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 152); backlink

Unknown interpreted text role "func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 152); backlink

Unknown interpreted text role "keyword".

 $System\,Message: ERROR/3~(\texttt{D:}\onboarding-resources}\scales \c to main\c to chow to \c to boarding-resources. The sample-onboarding-resources \c to main\c to complete the sample-onboarding-resources \c to main\c to complete the sample-onboarding-resources \c to complete the sample-onboarding-resources \c$

Unknown interpreted text role "keyword".

Windows and Pads

Windows are the basic abstraction in curses. A window object represents a rectangular area of the screen, and supports methods to display text, erase it, allow the user to input strings, and so forth.

The stdscr object returned by the :func: `~curses.initscr` function is a window object that covers the entire screen. Many programs may need only this single window, but you might wish to divide the screen into smaller windows, in order to redraw or clear them separately. The :func: `~curses.newwin` function creates a new window of a given size, returning the new window object.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 170); backlink

Unknown interpreted text role "func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 170); backlink

Unknown interpreted text role "func".

```
begin_x = 20; begin_y = 7
height = 5; width = 40
win = curses.newwin(height, width, begin y, begin x)
```

Note that the coordinate system used in curses is unusual. Coordinates are always passed in the order y,x, and the top-left corner of a window is coordinate (0,0). This breaks the normal convention for handling coordinates where the x coordinate comes first. This is an unfortunate difference from most other computer applications, but it's been part of curses since it was first written, and it's too late to change things now.

Your application can determine the size of the screen by using the <u>xdata</u>: 'curses.LINES' and <u>xdata</u>: 'curses.COLS' variables to obtain the y and x sizes. Legal coordinates will then extend from (0,0) to (curses.LINES - 1, curses.COLS - 1).

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc][howto]curses.rst, line 189); backlink
```

Unknown interpreted text role "data".

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 189); backlink
```

Unknown interpreted text role "data".

When you call a method to display or erase text, the effect doesn't immediately show up on the display. Instead you must call the meth: `~curses.window.refresh` method of window objects to update the screen.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 194); backlink
```

Unknown interpreted text role 'meth'.

This is because curses was originally written with slow 300-baud terminal connections in mind; with these terminals, minimizing the time required to redraw the screen was very important. Instead curses accumulates changes to the screen and displays them in the most efficient manner when you call meth; refresh'. For example, if your program displays some text in a window and then clears the window, there's no need to send the original text because they're never visible.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 199); backlink
```

Unknown interpreted text role "meth".

In practice, explicitly telling curses to redraw a window doesn't really complicate programming with curses much. Most programs go into a flurry of activity, and then pause waiting for a keypress or some other action on the part of the user. All you have to do is to be sure that the screen has been redrawn before pausing to wait for user input, by first calling stdscr.refresh() or the :meth: refresh' method of some other relevant window.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 208); backlink
```

Unknown interpreted text role "meth".

A pad is a special case of a window; it can be larger than the actual display screen, and only a portion of the pad displayed at a time. Creating a pad requires the pad's height and width, while refreshing a pad requires giving the coordinates of the on-screen area where a subsection of the pad will be displayed.

```
pad = curses.newpad(100, 100)
# These loops fill the pad with letters; addch() is
# explained in the next section
for y in range(0, 99):
```

The :meth: refresh call displays a section of the pad in the rectangle extending from coordinate (5,5) to coordinate (20,75) on the screen; the upper left corner of the displayed section is coordinate (0,0) on the pad. Beyond that difference, pads are exactly like ordinary windows and support the same methods.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 237); backlink
Unknown interpreted text role "meth".
```

If you have multiple windows and pads on screen there is a more efficient way to update the screen and prevent annoying screen flicker as each part of the screen gets updated. meth: refresh` actually does two things:

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 243); backlink
Unknown interpreted text role "meth".
```

Calls the :meth:`~curses.window.noutrefresh` method of each window to update an underlying data structure representing
the desired state of the screen.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc][howto]curses.rst, line 248); backlink

Unknown interpreted text role "meth".
```

Calls the function: 'curses.doupdate' function to change the physical screen to match the desired state recorded in the data structure.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 251); backlink

Unknown interpreted text role "func".
```

Instead you can call meth: noutrefresh on a number of windows to update the data structure, and then call func: doupdate to update the screen.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc][howto]curses.rst, line 254); backlink

Unknown interpreted text role "meth".
```

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc][howto]curses.rst, line 254); backlink

Unknown interpreted text role "fine".
```

Displaying Text

From a C programmer's point of view, curses may sometimes look like a twisty maze of functions, all subtly different. For example, c:func:addstr displays a string at the current cursor location in the stdscr window, while c:func:mvaddstr moves to a given y,x coordinate first before displaying the string. c:func:addstr is just like c:func:addstr allows specifying a window to use instead of using stdscr by default. c:func:mvwaddstr allows specifying both a window and a coordinate.

main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 262); backlink Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 262); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 262); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 262); backlink

Unknown interpreted text role "c:func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 262); backlink

Unknown interpreted text role "c:func".

Fortunately the Python interface hides all these details. stdscr is a window object like any other, and methods such as meth: "curses.window.addstr" accept multiple argument forms. Usually there are four different forms.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 271); backlink

Unknown interpreted text role "meth".

Form	Description
str or ch	Display the string str or character ch at the current position
str or ch, attr	Display the string str or character ch , using attribute $attr$ at the current position
y, x, str or ch	Move to position y,x within the window, and display str or ch
y, x, str or ch , $attr$	Move to position y,x within the window, and display str or ch , using attribute $attr$

Attributes allow displaying text in highlighted forms such as boldface, underline, reverse code, or in color. They'll be explained in more detail in the next subsection.

The :meth: `~curses.window.addstr` method takes a Python string or bytestring as the value to be displayed. The contents of bytestrings are sent to the terminal as-is. Strings are encoded to bytes using the value of the window's :attr:`encoding` attribute; this defaults to the default system encoding as returned by :func:`locale.getpreferredencoding`.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 298); backlink

Unknown interpreted text role "meth".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 298); backlink

Unknown interpreted text role "attr".

 $System\,Message: ERROR/3~(\texttt{D:}\onboarding-resources}\cpython-main\Doc\howto\[cpython-main]~[Doc]~[howto]~curses.rst, line~298); \\ \textit{backlink}~$

Unknown interpreted text role "func".

The <u>meth</u>: ~curses.window.addch` methods take a character, which can be either a string of length 1, a bytestring of length 1, or an integer.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-

```
main\Doc\howto\[cpython-main][Doc][howto]curses.rst, line 305); backlink
Unknown interpreted text role "meth".
```

Constants are provided for extension characters; these constants are integers greater than 255. For example, :const:'ACS_PLMINUS' is a +/- symbol, and :const:'ACS_ULCORNER' is the upper left corner of a box (handy for drawing borders). You can also use the appropriate Unicode character.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 308); backlink

Unknown interpreted text role "const".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 308); backlink

Unknown interpreted text role "const".

Windows remember where the cursor was left after the last operation, so if you leave out the y,x coordinates, the string or character will be displayed wherever the last operation left off. You can also move the cursor with the move(y,x) method. Because some terminals always display a flashing cursor, you may want to ensure that the cursor is positioned in some location where it won't be distracting, it can be confusing to have the cursor blinking at some apparently random location.

If your application doesn't need a blinking cursor at all, you can call <code>curs_set</code> (False) to make it invisible. For compatibility with older curses versions, there's a <code>leaveok(bool)</code> function that's a synonym for <code>:func:`~curses.curs_set</code>'. When bool is true, the curses library will attempt to suppress the flashing cursor, and you won't need to worry about leaving it in odd locations.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 322); backlink

Unknown interpreted text role "func".

Attributes and Color

Characters can be displayed in different ways. Status lines in a text-based application are commonly shown in reverse video, or a text viewer may need to highlight certain words. curses supports this by allowing you to specify an attribute for each cell on the screen.

An attribute is an integer, each bit representing a different attribute. You can try to display text with multiple attribute bits set, but curses doesn't guarantee that all the possible combinations are available, or that they're all visually distinct. That depends on the ability of the terminal being used, so it's safest to stick to the most commonly available attributes, listed here.

ttribute	Description
System Message: ERROR/3 (D:\onboarding- resources\sample- onboarding- resources\cpython- main\Doc\howto\ [cpython-main][Doc] [howto] curses.rst, line 349); backlink Unknown interpreted text role "const".	Blinking text

Attribute	Description
System Message: ERROR/3 (D:\onboarding- resources\sample- onboarding- resources\cpython- main\Doc\howto\ [cpython-main] [Doc] [howto] curses.rst, line 351); backlink Unknown interpreted text role "const".	Extra bright or bold text
System Message: ERROR/3 (D:\onboarding- resources\sample- onboarding- resources\cpython- main\Doc\howto\ [cpython-main][Doc] [howto] curses.rst, line 353); backlink Unknown interpreted text role "const".	Half bright text
System Message: ERROR/3 (D:\onboarding- resources\sample- onboarding- resources\cpython- main\Doc\howto\ [cpython-main] [Doc] [howto] curses.rst, line 355); backlink Unknown interpreted text role "const".	Reverse-video text

Attribute	Description
System Message: ERROR/3 (D:\onboarding- resources\sample- onboarding- resources\cpython- main\Doc\howto\ [cpython-main] [Doc] [howto] curses.rst, line 357); backlink Unknown interpreted text role "const".	The best highlighting mode available
System Message: ERROR/3 (D:\onboarding- resources\sample- onboarding- resources\cpython- main\Doc\howto\ [cpython-main] [Doc] [howto] curses.rst, line 359); backlink Unknown interpreted text role "const".	Underlined text

So, to display a reverse-video status line on the top line of the screen, you could code:

The curses library also supports color on those terminals that provide it. The most common such terminal is probably the Linux console, followed by color xterms.

To use color, you must call the :func: `~curses.start_color` function soon after calling :func: `~curses.initscr`, to initialize the default color set (the :func: `~curses.wrapper` function does this automatically). Once that's done, the :func: `~curses.has_colors` function returns TRUE if the terminal in use can actually display color. (Note: curses uses the American spelling 'color', instead of the Canadian/British spelling 'colour'. If you're used to the British spelling, you'll have to resign yourself to misspelling it for the sake of these functions.)

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 372); backlink

Unknown interpreted text role "func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 372); backlink

Unknown interpreted text role "func".

 $System\,Message: ERROR/3~(\texttt{D:}\onboarding-resources}\scample-onboarding-resources\\\colored\c$

Unknown interpreted text role "func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 372); backlink

Unknown interpreted text role "func".

The curses library maintains a finite number of color pairs, containing a foreground (or text) color and a background color. You can get the attribute value corresponding to a color pair with the :func:`~curses.color_pair` function; this can be bitwise-OR'ed with other attributes such as :const:`A REVERSE`, but again, such combinations are not guaranteed to work on all terminals.

 $System\,Message:\,ERROR/3\, (\mbox{D:\nonlinear-resources}\scample-onboarding-resources\cpython-main\noc\howto\cpython-main$

Unknown interpreted text role "func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 382); backlink

Unknown interpreted text role "const".

An example, which displays a line of text using color pair 1:

```
stdscr.addstr("Pretty text", curses.color_pair(1))
stdscr.refresh()
```

As I said before, a color pair consists of a foreground and background color. The $init_pair(n, f, b)$ function changes the definition of color pair n, to foreground color f and background color b. Color pair 0 is hard-wired to white on black, and cannot be changed.

Colors are numbered, and :func: start_color' initializes 8 basic colors when it activates color mode. They are: 0:black, 1:red, 2:green, 3:yellow, 4:blue, 5:magenta, 6:cyan, and 7:white. The :mod:'curses' module defines named constants for each of these colors: const:'curses.COLOR BLACK', :const:'curses.COLOR RED', and so forth.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 399); backlink

Unknown interpreted text role "func".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 399); backlink

Unknown interpreted text role "mod".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 399); backlink

Unknown interpreted text role "const".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 399); backlink

Unknown interpreted text role "const".

Let's put all this together. To change color 1 to red text on a white background, you would call:

```
curses.init pair(1, curses.COLOR RED, curses.COLOR WHITE)
```

When you change a color pair, any text already displayed using that color pair will change to the new colors. You can also display new text in this color with:

```
stdscr.addstr(0,0, "RED ALERT!", curses.color pair(1))
```

Very fancy terminals can change the definitions of the actual colors to a given RGB value. This lets you change color 1, which is usually red, to purple or blue or any other color you like. Unfortunately, the Linux console doesn't support this, so I'm unable to try it out, and can't provide any examples. You can check if your terminal can do this by calling :func:`~curses.can_change_color`, which returns True if the capability is there. If you're lucky enough to have such a talented terminal, consult your system's man pages for more information.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 416); backlink

Unknown interpreted text role "func".

User Input

The C curses library offers only very simple input mechanisms. Python's <u>mod:'curses'</u> module adds a basic text-input widget. (Other libraries such as <u>Urwid</u> have more extensive collections of widgets.)

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 429); backlink

Unknown interpreted text role "mod".

There are two methods for getting input from a window:

• :meth:`~curses.window.getch` refreshes the screen and then waits for the user to hit a key, displaying the key if :func:`~curses.echo` has been called earlier. You can optionally specify a coordinate to which the cursor should be moved before pausing.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 436); backlink

Unknown interpreted text role "meth".

 $System\ Message: ERROR/3\ (\mbox{D:\noboarding-resources}\scample-onboarding-resources\cpython-main\noc\howto\[cpython-main]\ [Doc]\ [howto]\curses.rst,\ \mbox{line}\ 436); \\ backlink$

Unknown interpreted text role "func".

• meth: `~curses.window.getkey` does the same thing but converts the integer to a string. Individual characters are returned as 1-character strings, and special keys such as function keys return longer strings containing a key name such as KEY_UP or ^G.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 441); backlink

Unknown interpreted text role 'meth'.

It's possible to not wait for the user using the meth: curses.window.nodelay window method. After nodelay (True), meth: getch and meth: getkey for the window become non-blocking. To signal that no input is ready, meth: getch returns curses. ERR (a value of -1) and meth: getkey raises an exception. There's also a finc: curses. halfdelay function, which can be used to (in effect) set a timer on each meth: getch ; if no input becomes available within a specified delay (measured in tenths of a second), curses raises an exception.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 446); backlink

Unknown interpreted text role "meth".

 $System\ Message: ERROR/3\ (\texttt{D:\onboarding-resources}\ sample-onboarding-resources\ cpython-main\ [Doc\]\ (\texttt{D:\onboarding-resources}\ ,\ line\ 446); \ \textit{backlink}$

Unknown interpreted text role "meth".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 446); backlink

Unknown interpreted text role 'meth'.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 446); backlink

Unknown interpreted text role "meth".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 446); backlink

Unknown interpreted text role "meth".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 446); backlink
Unknown interpreted text role "func".

The :meth: 'getch' method returns an integer; if it's between 0 and 255, it represents the ASCII code of the key pressed. Values greater than 255 are special keys such as Page Up, Home, or the cursor keys. You can compare the value returned to constants such as :const: 'curses.KEY_PPAGE', :const: 'curses.KEY_HOME', or :const: 'curses.KEY_LEFT'. The main loop of your program may

 $System\,Message: ERROR/3~(\texttt{D:}\onboarding-resources}\cpython-main\Doc\howto\[cpython-main]~[Doc]~[howto]~curses.rst, line~456); \textit{backlink}$

Unknown interpreted text role "meth".

look something like this:

Unknown interpreted text role "meth".

 $System\,Message: ERROR/3~(\texttt{D:}\nonline) resources \verb|\sample-onboarding-resources| cpython-main| Doc|\nowto| [cpython-main] [Doc] [howto] curses.rst, line 456); \\building building bu$

Unknown interpreted text role "const".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 456); backlink

Unknown interpreted text role "const".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 456); backlink

Unknown interpreted text role "const".

```
while True:
    c = stdscr.getch()
    if c == ord('p'):
        PrintDocument()
    elif c == ord('q'):
        break # Exit the while loop
    elif c == curses.KEY_HOME:
        x = y = 0
```

The <u>mod</u>'curses.ascii' module supplies ASCII class membership functions that take either integer or 1-character string arguments; these may be useful in writing more readable tests for such loops. It also supplies conversion functions that take either integer or 1-character-string arguments and return the same type. For example, <u>:func</u>:'curses.ascii.ctrl' returns the control character corresponding to its argument.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 472); backlink

Unknown interpreted text role "mod".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 472); backlink

Unknown interpreted text role "func".

There's also a method to retrieve an entire string, .meth: `~curses.window.getstr`. It isn't used very often, because its functionality is quite limited; the only editing keys available are the backspace key and the Enter key, which terminates the string. It can optionally be limited to a fixed number of characters.

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-

```
\verb|main|Doc\howto|[cpython-main][Doc][howto]| curses.rst, line 479); \textit{backlink}|
```

Unknown interpreted text role "meth".

```
curses.echo()  # Enable echoing of characters

# Get a 15-character string, with the cursor on the top line
s = stdscr.getstr(0,0,15)
```

The mod: curses.textpad' module supplies a text box that supports an Emacs-like set of keybindings. Various methods of the class: `~curses.textpad.Textbox` class support editing with input validation and gathering the edit results either with or without trailing spaces. Here's an example:

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 490); backlink
```

Unknown interpreted text role "mod".

System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 490); backlink

Unknown interpreted text role "class".

```
import curses
from curses.textpad import Textbox, rectangle

def main(stdscr):
    stdscr.addstr(0, 0, "Enter IM message: (hit Ctrl-G to send)")

    editwin = curses.newwin(5,30, 2,1)
    rectangle(stdscr, 1,0, 1+5+1, 1+30+1)
    stdscr.refresh()

    box = Textbox(editwin)

    # Let the user edit until Ctrl-G is struck.
    box.edit()

# Get resulting contents
    message = box.gather()
```

See the library documentation on :mod:'curses.textpad' for more details.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main][Doc] [howto] curses.rst, line 514); backlink
```

Unknown interpreted text role "mod".

For More Information

This HOWTO doesn't cover some advanced topics, such as reading the contents of the screen or capturing mouse events from an xterm instance, but the Python library page for the mod: module is now reasonably complete. You should browse it next.

```
System Message: ERROR/3 (D:\onboarding-resources\sample-onboarding-resources\cpython-main\Doc\howto\[cpython-main] [Doc] [howto] curses.rst, line 520); backlink
```

Unknown interpreted text role 'mod'.

If you're in doubt about the detailed behavior of the curses functions, consult the manual pages for your curses implementation, whether it's neurses or a proprietary Unix vendor's. The manual pages will document any quirks, and provide complete lists of all the functions, attributes, and :const:`ACS_*` characters available to you.

```
System\,Message:\,ERROR/3\, (\mbox{D:\nonlinear-resources}\scample-onboarding-resources\cpython-main\noc\howto\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main\cpython-main
```

Unknown interpreted text role "const".

Because the curses API is so large, some functions aren't supported in the Python interface. Often this isn't because they're difficult to implement, but because no one has needed them yet. Also, Python doesn't yet support the menu library associated with neurses. Patches adding support for these would be welcome; see the Python Developer's Guide to learn more about submitting patches to

Python.

- Writing Programs with NCURSES: a lengthy tutorial for C programmers.
- The neurses man page
- The ncurses FAQ
- "Use curses... don't swear": video of a PyCon 2013 talk on controlling terminals using curses or Urwid.
- "Console Applications with Urwid": video of a PyCon CA 2012 talk demonstrating some applications written using Urwid.