contextBridge

Create a safe, bi-directional, synchronous bridge across isolated contexts

Process: Renderer

An example of exposing an API to a renderer from an isolated preload script is given below:

```
// Preload (Isolated World)
const { contextBridge, ipcRenderer } = require('electron')

contextBridge.exposeInMainWorld(
   'electron',
   {
      doThing: () => ipcRenderer.send('do-a-thing')
   }
)
```

```
// Renderer (Main World)
window.electron.doThing()
```

Glossary

Main World

The "Main World" is the JavaScript context that your main renderer code runs in. By default, the page you load in your renderer executes code in this world.

Isolated World

When contextIsolation is enabled in your webPreferences (this is the default behavior since Electron 12.0.0), your preload scripts run in an "Isolated World". You can read more about context isolation and what it affects in the security docs.

Methods

The contextBridge module has the following methods:

contextBridge.exposeInMainWorld(apiKey, api)

- apiKey string The key to inject the API onto window with. The API will be accessible on window [apiKey] .
- api any Your API, more information on what this API can be and how it works is available below.

Usage

API

The api provided to exposeInMainWorld must be a Function, string, number, Array, boolean, or an object whose keys are strings and values are a Function, string, number, Array, boolean, or another nested object that meets the same conditions.

Function values are proxied to the other context and all other values are **copied** and **frozen**. Any data / primitives sent in the API become immutable and updates on either side of the bridge do not result in an update on the other side.

An example of a complex API is shown below:

```
const { contextBridge } = require('electron')
contextBridge.exposeInMainWorld(
  'electron',
   doThing: () => ipcRenderer.send('do-a-thing'),
   myPromises: [Promise.resolve(), Promise.reject(new Error('whoops'))],
   anAsyncFunction: async () => 123,
   data: {
     myFlags: ['a', 'b', 'c'],
     bootTime: 1234
   },
   nestedAPI: {
     evenDeeper: {
       youCanDoThisAsMuchAsYouWant: {
         fn: () => ({
           returnData: 123
         })
       }
     }
   }
  }
```

API Functions

Function values that you bind through the <code>contextBridge</code> are proxied through Electron to ensure that contexts remain isolated. This results in some key limitations that we've outlined below.

Parameter / Error / Return Type support

Because parameters, errors and return values are **copied** when they are sent over the bridge, there are only certain types that can be used. At a high level, if the type you want to use can be serialized and deserialized into the same object it will work. A table of type support has been included below for completeness:

Туре	Complexity	Parameter Support	Return Value Support	Limitations
string	Simple	✓	~	N/A
number	Simple	✓	<u> </u>	N/A

boolean	Simple	✓	✓	N/A
Object	Complex	✓	✓	Keys must be supported using only "Simple" types in this table. Values must be supported in this table. Prototype modifications are dropped. Sending custom classes will copy values but not the prototype.
Array	Complex	✓	✓	Same limitations as the Object type
Error	Complex	✓	✓	Errors that are thrown are also copied, this can result in the message and stack trace of the error changing slightly due to being thrown in a different context, and any custom properties on the Error object will be lost
Promise	Complex	✓	~	N/A
Function	Complex	<u>~</u>	<u>~</u>	Prototype modifications are dropped. Sending classes or constructors will not work.
<u>Cloneable</u> <u>Types</u>	Simple	✓	✓	See the linked document on cloneable types
Element	Complex	✓	<u> </u>	Prototype modifications are dropped. Sending custom elements will not work.
Blob	Complex	✓	✓	N/A
Symbol	N/A	×	×	Symbols cannot be copied across contexts so they are dropped

If the type you care about is not in the above table, it is probably not supported.

Exposing Node Global Symbols

The <code>contextBridge</code> can be used by the preload script to give your renderer access to Node APIs. The table of supported types described above also applies to Node APIs that you expose through <code>contextBridge</code>. Please note that many Node APIs grant access to local system resources. Be very cautious about which globals and APIs you expose to untrusted remote content.

```
const { contextBridge } = require('electron')
const crypto = require('crypto')
contextBridge.exposeInMainWorld('nodeCrypto', {
    sha256sum (data) {
      const hash = crypto.createHash('sha256')
      hash.update(data)
      return hash.digest('hex')
    }
})
```