Objects Acting Like Values

Laurent Mathy

Object-Oriented Programming Projects

April 17, 2020

Doing more with our objects

So far we can *create*, *destroy*, *copy* and *assign* our objects.

Most built-in types support more operations:

- Rich set of operators (+, *, -=, etc.)
- Conversions between types (e.g. int to double)

Simple string class

```
class Str {
    public:
8
        typedef std::vector<char>::size_type size_type;
9
10
        Str() { }
11
12
        Str(size_type n, char c): data(n, c) { }
13
14
        Str(const char* cp) {
15
            std::copy(cp, cp + std::strlen(cp),
16
                        std::back inserter(data));
17
        }
18
19
        template < class In > Str(In i, In j) {
20
            std::copy(i, j, std::back_inserter(data));
21
        }
22
23
    private:
24
        std::vector<char> data;
25
    };
26
```

Str constructors

- Default constructor implicitly invokes default vector constructor:
 - Must be explicitly defined. (Why?)
 - Does exactly what the synthesised default would do.
- Constructor that takes a size and a character uses corresponding vector constructor as initialiser.
- Two other constructors do not have initialisers:
 - data is first implicitly initialised as empty vector.
 - Both then append to data.
 - Last constructor is a template so it defines a family of constructors. E.g. it can construct a Str from an array of char, from a vector<char>, from a substring, etc.

Copy, assignment and destructor

Our class does not define any copy constructor, assignment operator or destructor.

Why?

Copy, assignment and destructor

Our class does not define any copy constructor, assignment operator or destructor.

Why?

Because the defaults work!

The Str class itself does no memory management.

The synthesised operations will call corresponding vector operations: that's exactly what we want!

Bottom line: Str does not need a destructor – it would have nothing to do.

If you don't need a destructor, you don't need explicit copy constructor or assignment operator (rule of three).

Automatic conversions

```
Str s = "hello"; // Initialise s
```

Requires the copy constructor that takes a const Str& as argument.

```
s = "bye"; // Assign a new value to s
```

Requires the assignment operator that takes a const Str& as argument.

6

Automatic conversions

```
Str s = "hello"; // Initialise s
```

Requires the copy constructor that takes a const Str& as argument.

```
s = "bye"; // Assign a new value to s
```

Requires the assignment operator that takes a const Str& as argument.

But both statements specify a const **char***, not the expected const Str&!

6

Automatic conversions (2)

We already have a constructor that takes a const char* to create a Str.

Constructors that take a single argument acts as **user-defined conversion**.

- The compiler will use this constructor to convert a const char* into a Str.
- The compiler uses the Str(const char*) constructor to create a temporary of type Str, than calls the appropriate (synthesized) operation to copy/assign this temporary.

Str operations

We want to be able to write things like:

```
s[i]
cin >> s
cout << s
s1 + s2
```

Indexing is easy: just add two member functions overloading the index operator:

```
char& operator[](size_type i) { return data[i]; }
const char& operator[](size_type i) const {
    return data[i];
}
```

Input-output operators

Input operator will change the state of the object, so it appears it should be a member function.

But . . .

Input-output operators

Input operator will change the state of the object, so it appears it should be a member function.

```
But ...
    cin >> s;
is equivalent to
    cin.operator>>(s);
which calls the overloaded >> operator for the object cin.
```

But we do not own the definition of istream class, so we cannot add this overloaded operator!

Input-output operators (2)

But if we make operator>> a member of Str, then our users can only write

```
s >> cin;
which is equivalent to
s.operator>>(cin);
```

But that's not what we want!

So the input-output operators must be non-members. Add the following to Str.hpp.

```
46 std::istream& operator>>(std::istream&, Str&);
47 std::ostream& operator<<(std::ostream&, const Str&);
```

Output operator

```
ostream& operator<<(ostream& os, const Str& s) {
    for (Str::size_type i = 0; i != s.size(); ++i)
        os << s[i];
    return os;
}</pre>
```

Each time through the loop:

- Invoke Str::operator[] to fetch a character.
- Invoke the STL-provided operator<< that takes an ostream and a char.

Input operator

```
istream& operator>>(istream& is, Str& s) {
13
        // Obliterate existing value(s)
14
        s.data.clear();
15
        // Read and discard leading blanks
16
        char c:
17
        while (is.get(c) && isspace(c))
18
            ; // Nothing to do, except testing the condition
19
20
        // If we read a non-blank char, continue to read
21
        // until next whitespace character
22
        if (is) {
23
            do { s.data.push_back(c); }
24
            while (is.get(c) && !isspace(c));
25
            // If we read a blank, put it back on the stream
26
            if (is)
27
                is.unget();
28
        }
29
        return is;
30
31
```

Input operator

This is all well, but the code on previous slide will not compile!

Why?

Input operator (2)

Previous code will not compile, because operator>> is not a member function, yet it tries to access private data member directly!

But it **needs** to do so, and we do not want our users to have direct access to our private members through the interface!

Solution: make ther operator>> a friend of the Str class:

```
class Str {
friend std::istream& operator>>(std::istream&, Str&);
// As before
};
```

Friends can access private members of the class. friend declaration can appear anywhere in the class definition; but usually put near the public interface.

Other binary operators

Concatenation: + does not change the state of the concatenated object, so can be a non-member.

But compound concatenation += does change its left-hand side operand, so should be a member function:

And then implement + using +=:

```
Str operator+(const Str& lhs, const Str& rhs) {

Str res = lhs; // Copy constructor

res += rhs; // res.operator+=(rhs)

return res; // Copy constructor*

}
```

Mixed-type expressions

```
Str greeting = "Hello, " + name + "!";
is equivalent to:
   Str greeting = ("Hello, " + name) + "!";
```

Compiler will invoke conversion constructor on const char* and use Str operator+.

So the code is in fact equivalent to:

```
Str temp1("Hello, ");
Str temp2 = temp1 + name;
Str temp3("!");
Str greeting = temp2 + temp3;
```

In practice, to avoid cost of temps, one can define specific versions of operators (here concatenation) for every combination of operands (and not rely on automatic conversions).

Designing binary operators

Class membership is very important for conversions.

- If an operator is member of class, then left-hand operands cannot result from conversion – must be of class type.
 - Compiler only looks for non-member operators and for the corresponding class one.
- If operator is class member, then the operator is asymmetrical:
 - as right operand can be converted, but left-hand operand cannot;
 - Better to keep symmetry by making operator a non-member function.

Conversion hazards

- If a constructor defines the structure of the object constructed, not its content, the constructor should be explicit.
- If the constructor defines the content of the object, then it should not be explicit.
- Example:

```
vector<string> p = frame(42);
```

We get a vector with 42 empty rows. It is likely the user expected a framed number 42!

This single argument constructor is a structural constructor, so turn off automatic conversion by using explicit (as we did in lecture 6).

Conversion operators

We saw that some constructors allows conversion **to** the class type. **Conversion operators** define conversion **from** the class type.

Conversion operators must be class members and their name is operator followed by the target type name:

```
class Student_info {
public:
    operator double() const;

// ...
};
```

would be used whenever a Student_info object is used where a double is expected.

Conversion operators (2)

istream uses conversion operators to support expressions such as:

```
1 cin >> x;
2 if (cin) { /* ... */}
```

There is a conversion operator from istream to void*:

- Returns either nullptr or implementation-defined non-zero void*.
- void* is universal pointer, but can't be dereferenced.
- void* can be converted to a bool.

Why not support a direct conversion from istream to bool?

Conversion operators (2)

istream uses conversion operators to support expressions such as:

```
cin >> x;
if (cin) { /* ... */}
```

There is a conversion operator from istream to void*:

- Returns either nullptr or implementation-defined non-zero void*.
- void* is universal pointer, but can't be dereferenced.
- void* can be converted to a bool.

Why not support a direct conversion from istream to bool? Suppose one writes the following erroneous code:

```
int x;
cin << x; // Should have written cin >> x;
```

cin would get converted to a bool, then an int, then shifted left by x bits, then result discarded! On the other hand, void* cannot be converted to arithmetic value.

Conversion and memory management

Should Str support direct conversion to null-terminated array of characters?

```
operator char*();
operator const char*() const;
```

It turns out this is not a good idea:

- Can't return pointer to internal data: would violate encapsulation/protection.
- Even returning a const pointer does not work: object could be destroyed while pointer still alive.
- If we make a copy and return a pointer: implicit conversion creates copies, but never gives the user the corresponding pointer, so we can never reclaim the space!

```
1 Str s;
```

2 ifstream is(s); // Implicit conversion -- how can we free?

Conversion and memory management (2)

Solutions: use explicit member functions!

Example from STL (string):

- c_str() copies content of string into null-terminated char array:
 - The string class owns the array.
 - User expected not to delete it.
 - Data in array is ephemeral:
 - Only valid until next call to member function that might change the string.
 - Users expected to either use pointer immediately or copy content to user managed storage.
- data() same as c_str() but not null-terminated.
- copy takes a char* and an int: copies as many characters as indicated by int into space pointed to by char*.

Note that $c_{str}()$ and data() can still point into destroyed object, but reduced risk as calls are **explicit**.

Use **smart pointers** to explicitly give ownership back to caller.