


WINHELPONLINE

Windows Help, How-Tos & Tech Reviews

■ MENU Q

Set Command Prompt Default Window Size and Position



When you open Command Prompt by default, it's positioned randomly on the screen. Also, when you resize the Command Prompt window and close it, the setting is not retained the next time. This system managed positioning annoys many users

We use cookies to ensure that we give you the best experience on our website. If you continue to use this site we will assume that you are happy with it.

Ok

Read more

G+

customize the default Command Prompt window size (width and height), and set its default position screen coordinates.


Set Command Prompt Default Window Size & Position for a Particular Shortcut

You can customize the appearance of a Command Prompt window, changing its window size, position, font and colors. You can save these settings independently for each shortcut that launches a Command Prompt so that you can make appropriate settings for different tasks. Also you configure a global default window size, position and font settings which will apply when you launch Command Prompt window using other means — for example, when you run cmd.exe directly.

To customize a Command Prompt window for a particular shortcut, use these steps:

Right-click on a Command Prompt shortcut, and click Properties. Alternately, double-click the shortcut to launch Command Prompt. Right-click on the Command Prompt title bar and click Properties.

Click on the Layout tab.




Change the Window size and Window Position settings in that tab. As you alter the Width, Height, Left and Top values, you can see the Window preview which will help you set the desired size and position. Note that you'll need to first uncheck **Let system position window option** setting to input custom values.

Click OK. Changes made here affect all future Command Prompt sessions launched from that **particular** shortcut.

Set Command Prompt Global Default Window Size & Position

Open a Command Prompt window by running cmd.exe from the Start Run dialog. In Windows 8 and Windows 10, you can right-click on the Start button to open the Win + X menu, and select "Command Prompt" option to open it easily.



Difference between "Properties" and "Defaults" options

Right-clicking on the Command Prompt window title offers access to the Properties dialog box. (If Command Prompt is running in full-screen mode, press Alt+Enter to switch to window display.) Changes you make here affect the current session, and all future sessions launched only from that shortcut. The changes made are saved inside that particular shortcut (.lnk) file, instead of the registry.

Right-clicking on the Command Prompt window title and choosing Defaults from the Control menu lets you make changes that will not affect the current session but instead will affect all future sessions (except for those launched from a shortcut whose properties have been customized). These changes also affect future sessions in character-mode, MS-DOS-based applications that do not have a program-information file (PIF) and do not store their own settings. This setting is saved in the registry.


Right-click on the Command Prompt title bar, and click **Defaults**. Select the Layout tab and configure the size and position accordingly, as explained earlier.

The changes you make here affects all future sessions (except for CMD windows launched from a shortcut whose properties have been customized). These changes also affect future sessions in character-mode, MS-DOS-based applications that do not have a program-information file (PIF) and do not store their own settings. The global settings are used when you launch cmd.exe manually or via the Win + X menu.

Dogictor Vov

The global default settings are stored in the following per-user registry key, in case you want to propagate the changes to other systems.

HKEY_CURRENT_USER\Console



Reset Command Prompt Settings to Defaults

Windows Registry Editor Version 5.00 ;Reset Command Prompt settings to default [HKEY CURRENT USER\Console] "CtrlKeyShortcutsDisabled"=dword:00000000 "CursorSize"=dword:00000019 "EnableColorSelection"=dword:00000000 "ExtendedEditKey"=dword:00000001 "ExtendedEditKeyCustom"=dword:00000000 "FaceName"="__DefaultTTFont__" "FilterOnPaste"=dword:00000001 "FontFamily"=dword:00000000 "FontSize"=dword:00100000 "FontWeight"=dword:00000000 "ForceV2"=dword:00000001 "FullScreen"=dword:00000000 "HistoryBufferSize"=dword:00000032 "HistoryNoDup"=dword:00000000 "InsertMode"=dword:00000001 "LineSelection"=dword:00000001 "LineWrap"=dword:00000001 "LoadConIme"=dword:00000001 "NumberOfHistoryBuffers"=dword:00000004 "PopupColors"=dword:000000f5 "QuickEdit"=dword:00000001

```
"WindowAlpha"=dword:000000ff
"WindowSize"=dword:001e0078
"WordDelimiters"=dword:00000000
"ColorTable00"=dword:00000000
"ColorTable01"=dword:00800000
"ColorTable02"=dword:00008000
"ColorTable03"=dword:00808000
"ColorTable04"=dword:00000080
"ColorTable05"=dword:00800080
"ColorTable06"=dword:00008080
"ColorTable07"=dword:00c0c0c0
"ColorTable08"=dword:00808080
"ColorTable09"=dword:00ff0000
"ColorTable10"=dword:0000ff00
"ColorTable11"=dword:00ffff00
"ColorTable12"=dword:000000ff
"ColorTable13"=dword:00ff00ff
"ColorTable14"=dword:0000ffff
"ColorTable15"=dword:00ffffff
"CurrentPage"=-
"WindowPosition"=-
```

To reset Command Prompt preferences to defaults, copy the above contents to Notepad and save the file with <code>.reg</code> extension, say <code>reset_cmd.reg</code>. Double-click the file to apply the settings. The default colors, font face, font family, window size, position (system managed) and other settings are restored. As stated earlier, this is a per-user setting.



About the author

Ramesh Srinivasan founded Winhelponline.com back in 2005. He is passionate about Microsoft technologies and has a vast experience in the ITeS industry — delivering support for Microsoft's consumer products. He has been a Microsoft MVP [2003 to 2012] who contributes to various Windows support forums.

☐ by Ramesh Srinivasan

■ Windows

So useful, thank you!		
red		
Great! Thanks!		
eave a Comment		
eave a Comment		
Name *		
Name * Email *		

Subscribe

SUBSCRIBE TO BLOG VIA EMAIL TO RECEIVE NOTIFICATIONS OF NEW POSTS IN YOUR INBOX.

Enter your email address

Subscribe Now!

Articles of Interest

Remove "Edit with Paint 3D" & "Edit with Photos" from Right-click Menu in Windows	
OneDrive Files On-Demand Downloads - Block and Unblock Apps via Settings	
How to Run Programs as TrustedInstaller to Write to Certain Registry Keys or Files?	
[Fix] Turn Windows Features On Or Off is Empty in Windows 10	
Limit Windows Update Bandwidth for Background Downloads in Windows 10	
Get Windows 10 Official ISO Images Using Media Creation Tool or Direct Download	
Find the Windows version, build and edition from ISO or DVD	
Show "Copy as Path" Always in Right-Click Menu Without Shift Key	
Remove 3D Objects Folder from This PC in Windows 10	
How to Enable Blue Light Reduction in Windows 10?	

We use cookies to ensure that we give you the best experience on our website. If you continue to use this site we will assume that you are happy with it. Ok Read more

Restore or Reinstall Windows Store in Windows 10 after uninstalling it with

PowerShell

About us | Contact us | Disclaimer & Terms of Use | Privacy Policy | Subscribe





Copyright© 2018 Winhelponline

8