


Content

Objectives

1
1.1
1.2
2
2.1
2.2
3
4
5
6
7
8
9
10
11
11.1
12
13
14
14.1
14.2
15
16
17
18
19
20
21
22
22.1



Updating User Passwords

The `passwd` command is used to update a user's password. Users can only change their own passwords, whereas the root user can update the password for any user.

```
passwd [OPTIONS] [USER]
```

For example, since we are logged in as the `sysadmin` user we can change the password for that account. Execute the `passwd` command. You will be prompted to enter the existing password once and the new password twice. For security reasons, no output is displayed while the password is being typed. The output is shown as follows:

```
sysadmin@localhost:~$ passwd
Changing password for sysadmin.
(current) UNIX password: netlab123

Enter new UNIX password:
Retype new UNIX password:
passwd: password updated successfully
```

If the user wants to view *status* information about their password, they can use the `-S` option:

```
sysadmin@localhost:~$ passwd -S sysadmin
sysadmin P 12/20/2017 0 99999 7 -1
```

The output fields are explained below:

Field	Example	Meaning
User Name	sysadmin	The name of the user.
Password Status	P	P indicates a usable password. L indicates a locked password. NP indicates no password.
Change Date	03/01/2015	The date when the password was last changed.
Minimum	0	The minimum number of days that must pass before the current password can be changed by the user.
Maximum	99999	The maximum number of days remaining for the password to expire.
Warn	7	The number of days prior to password expiry that the user is warned.
Inactive	-1	The number of days after password expiry that the user account remains active.

Follow Along

Switch the `root` account using the following command. Use `netlab123` as the password:

```
sysadmin@localhost:~$ su root
Password:
root@localhost:~#
```

The root user can change the password of any user. If the root user wants to change the password for `sysadmin`, they would execute the following command:

```
root@localhost:~# passwd sysadmin
Enter new UNIX password:
Retype new UNIX password:
```

```
Retype new UNIX password:  
passwd: password updated successfully
```

Follow Along

Exit the `root` account using the `exit` command:

```
root@localhost:~# exit  
exit
```

[◀ Previous](#)

[Next ▶](#)