

리눅스

발표자: 201232038 이주형

201332012 김재현

201532038 정현진

201532056 박다솔

201532005 김도희



파일시스템 포맷하기

ext4(extended file system) 타입으로 파일시스템 포맷하기

mke2fs -t ext4 /dev/sdb1

ext3(extended file system) 타입으로 파일시스템 포맷하기

mke2fs -t ext3 /dev/sdb1

옵션 -t를 입력하지 않으면 기본적으로 ext2타입

옵션 -b: 블록크기를 지정, 기본 4096bytes

옵션 -c: 배드블록을 점검후 파일시스템 생성

옵션 -f: 프레그먼트 크기를 지정

zam2695@naver.cor



마운트

마운트란?

리눅스 시스템에서 사용하기를 원하는 특정장치(디바이스)를 시스템에 인식시키는 작업 디렉토리와 연결하는 작업 특정장치를 하나의 디렉토리처럼 사용하기 위한 작업



마운트 설정파일

```
[root@host ~]# mount
/dev/sda2 on / type ext4 (rw)
proc on /proc type proc (rw)
sysfs on /sys type sysfs (rw)
devpts on /dev/pts type devpts (rw,gid=5,mode=620)
tmpfs on /dev/shm type tmpfs (rw,rootcontext="system_u:object_r:tmpfs_t:s0")
/dev/sda1 on /boot type ext4 (rw)
none on /proc/sys/fs/binfmt_misc type binfmt_misc (rw)
vmware-vmblock on /var/run/vmblock-fuse type fuse.vmware-vmblock (rw,nosuid,nodev,default_permissions,allow_other)
```

```
[root@host ~]# cat _/etc/mtab_
/dev/sda2 / ext4 rw 0 0
proc /proc proc rw 0 0
sysfs /sys sysfs rw 0 0
devpts /dev/pts devpts rw,gid=5,mode=620 0 0
tmpfs /dev/shm tmpfs rw,rootcontext="system_u:object_r:tmpfs_t:s0" 0 0
/dev/sda1 /boot ext4 rw 0 0
none /proc/sys/fs/binfmt_misc binfmt_misc rw 0 0
vmware-vmblock /var/run/vmblock-fuse fuse.vmware-vmblock rw,nosuid,nodev,default_permissions,allow_other 0 0
```



마운트

국제 표준화 기구(ISO)에서 제정한 CD-ROM 매체 를 위한 파일 시스템 표준이다.

CD-ROM 마운트

mount -t iso9660 /dev/cdrom /media/cdrom

CD-ROM 언마운트

umount /media/cdrom

마운트 상태에서 CD-ROM을 뺄수 없음 /media/cdrom에서 다른곳으로 빠져 나와서 umount 해야한다.



마운트

옵션	설명
-r	특정장치를 마운트 할때 읽을수만 있도록 마운트(쓰기 금지)(read only)
-W	읽기,쓰기 모두 가능하도록 마운트



어떤 디바이스를 부팅과정에서 마운트 시킬것인가?

```
[root:~, 2]# cat /etc/fstab
# /etc/fstab
# Created by anaconda on Tue Oct 4 18:11:10 2016
# Accessible filesystems, by reference, are maintained under '/dev/disk'
# See man pages fstab(5), findfs(8), mount(8) and/or blkid(8) for more info
dev/mapper/YolGroup-ly root
                                                 ext4
                                                         defaults
                                                                        1 1
defaults
                                                                                    1 2
                                                              ext4
/dev/mapper/YolGroup-ly home //home
                                                         defaults
                                                 ext4
/dev/mapper/YolGroup-lv swap/swap
                                                 swap
                                                                        0 0
                                                         defaults
∦mpfs
                      7de√/shm
                                             tmpfs
                                                    defaults
                                                                   0 \quad 0
devpts
                      /dev/pts
                                                    gid=5.mode=620
                                                                   0 0
                                             devpts
sysfs
                      /sys
                                             sysfs
                                                    defaults
                                                                   0 0
                                                    defaults
proc
                      /proc
                                                                   0 0
                                             DFOC
[root:~. 3]#
                              마운트포인트
                                                    시스템타입
         디바이스명
                                     zam2695@naver.com
```



e2fsck

e2fsck: 파일시스템 점검과 복구

<점검 항목>InodeBlocksSizes디렉토리구조디렉토리 연결성파일 링크정보전체파일 개수전체 블록수중 사용중인 블록



파일 시스템 점검, 복구

파일시스템 강제 점검 및 복구하기

e2fsck –f /dev/hdc2

```
[root@host ~]# e2fsck /dev/sda1
e2fsck 1.41.12 (17-May-2010)
/dev/sda1 is mounted.

WARNING!!! The filesystem is mounted. If you continue you ***WILL***
cause ***SEYERE*** filesystem damage.

Do you really want to continue (y/n)? yes
/dev/sda1: recovering journal
/dev/sda1: clean, 39/76912 files, 39729/307200 blocks
```



디스크 사용량 점검 df

[root@localhost	~]# df -ah				
Filesystem	Size	Used	Avail	Use%	Mounted on
/dev/sda2	47G	2.2G	43G	5%	/
proc	0	0	0	_	/proc
sysfs	0	0	0	_	/sys
devpts	0	0	0	_	/dev/pts
tmpfs	504M	88K	504M	1%	/dev/shm
/dev/sda1	291M	30M	247M	11%	/boot
none	0	0	0	_	/proc/sys/fs/binfmt_misc
vmware-vmblock	_ 0	0	0	_	/var/run/vmblock-fuse

-h: 사람이 보기 쉽도록 최적의 용량단위로 표시 (human-readable)



디렉토리별 사용량 점검 du

[root@localhost etc]# du -sh /etc 32M /etc

-s: 지정된 디렉토리내에 존재하는 모든파일과 서브디렉토리들의 용량을 모두 합친 용량 (summary)



디렉토리별 사용량 점검 du

```
[root@localhost ~]# du -sh /tmp/
324K
        /tmp/
[root@localhost ~]# du -sh /tmp/*
        /tmp/ks-script-dvkD2x
4.0K
4.0K
        /tmp/ks-script-dvkD2x.log
8.0K
        /tmp/orbit-gdm
8.0K
        /tmp/pulse-s471oKtjECIJ
8.0K
        /tmp/pulse-u9usfHfl33FW
4.0K
        /tmp/virtual-lee.LMTGYe
8.0K
        /tmp/vmware-config0
4.0K
        /tmp/YMwareDnD
12K
        /tmp/vmware-lee
48K
        /tmp/vmware-root
196K
        /tmp/vmware-root-2794398616
        /tmp/yum.log
```



[root@host ~]# cat /proc/filesystems

sysfs

rootfs

nodev

nodev

/etc/fstab

✓ /etc/fstab 파일의 구성

▶ [파일시스템장치명] [마운트포인트] [파일시스템종류]

[옵션] [dump 관련설정] [파일점검옵션]

```
nodev
                                                                                    bdev
                                                                             nodev
                                                                                    DLOC
[root:~. 9]# cat /etc/fstab
                                                                             nodev
                                                                                    cgroup
                                                                             nodev
                                                                                    couset
                                                                             nodev
                                                                                    tmpfs
                                                                             nodev
                                                                                    devtmpfs
# /etc/fstab
                                                                             nodev
                                                                                    binfmt_misc
# Created by anaconda on Tue Oct 4 18:11:10 2016
                                                                             nodev
                                                                                    debuafs
                                                                             nodev
                                                                                    securityfs
                                                                             nodev
                                                                                    sockfs
# Accessible filesystems, by reference, are maintained under '/dev/di nodev
                                                                                    usbfs
 See man pages fstab(5), findfs(8), mount(8) and/or blkid(8) for mor nodev
                                                                                    pipefs
                                                                                    anon_inodefs
                                                                             nodev
                                                                             nodev
                                                                                    inotifyfs
/dev/mapper/VolGroup-ly root /
                                                                   defaults nodev
                                                           ext4
                                                                                    devpts
                                                                         ext
UUID=23bb8c47-14da-4a43-8b7f-e00c2f0b183d /boot
                                                                                    ramfs
                                                                                    huget lbfs
                                                                             nodev
/dev/mapper/VolGroup-Iv home /home
                                                           ext4
                                                                    defaults
                                                                                     iso9660
/dev/mapper/VolGroup-ly swap swap
                                                                   defaults nodev
                                                           swap
                                                                                    maueue
                                                                             nodev
                                                                                    selinuxfs
tmpfs
                          /dev/shm
                                                     tmpfs
                                                              defaults
                                                                                    ext4
                                                     devpts gid=5, mode=62 nodev
                          /dev/pts
devpts
                                                                                    vmhafs
                                                                                    fuse
sysfs
                          /svs
                                                     sysfs
                                                              defaults
                                                                                    fuseblk
                          /proc
                                                              defaults
Droc
                                                     DLOC
                                                                             nodev
                                                                                    fusectl
[root:~, 10]# \[
                                                                             [root@host ~]#
```



/etc/fstab

```
[root:~. 9]# cat /etc/fstab
 /etc/fstab
 Created by anaconda on Tue Oct 4 18:11:10 2016
 Accessible filesystems, by reference, are maintained under '/dev/disk'
 See man pages fstab(5), findfs(8), mount(8) and/or blkid(8) for more info
/dev/mapper/VolGroup-lv_root /
                                                       defaults
                                               ext4
                                                                   defaults
UUID=23bb{c47-14da-4a43-8b7f-e00c2f0b183d /boot
                                                                                 1 2
                                                           ext4
/dev/mapper/VolGroup-lv_home /home
                                                       defaults
                                                ext4
/dev/mapper/VolGroup-lv_swap_swap
                                                       defaults
                                                swap
tmofs
                     /dev/shm
                                           tmpfs
                                                  defaults
                                                                 0 0
                                                                 0 0
devots
                     /dev/pts
                                                  gid=5.mode=620
                                           devpts
sysfs
                     /sys
                                                  defaults
                                           sysfs
                                                                 0.0
                                                  defaults
                                                                 0.0
                     /proc
DEOC
                                           Droc
        0]#
[root:~.
                        ✔ [파일점검옵션] : /etc/fstab의 여섯번째 항목
                                      ▶ 0 : fsck가 실행되지 않음
                                         ▶ 1 : 루트파일시스템
                                      2 : 루트파일시스템 이외
```

2021-01-19



스왑메모리

✓ 스왑메모리란?

- ▶ 리눅스에서의 가상메모리
- ▶ 관련명령어
- I. mkswap : 리눅스의 스왑영역 지정(스왑공간 생성)
- II. swapon : 스왑공간 활성화
- III. sawpoff : 스왑공간 비활성화
- ▶ 스왑공간 추가
- I. 스왑파티션을 스왑공간으로 추가
- Ⅱ. 스왑파일 생성 후, 스왑공간으로 추가



스왑메모리

1. 현재 시스템 메모리 상태 확인

[root@localhost ~]# free

total used free
Mem: 1031204 362536 668668
-/+ buffers/cache: 156736 874468
Swap: 2064376 0 2064376



2. 스왑파티션 생성

[root@localhost ~]# fdisk /dev/sda

WARNING: DOS-compatible mode is deprecated. It's strongly recommended to switch off the mode (command 'c') and change display units to sectors (command 'u').

Command (m for help): p

Disk /dev/sda: 53.7 GB, 53687091200 bytes 255 heads, 63 sectors/track, 6527 cylinders Units = cylinders of 16065 * 512 = 8225280 bytes Sector size (logical/physical): 512 bytes / 512 bytes 1/0 size (minimum/optimal): 512 bytes / 512 bytes Disk identifier: 0x0003f428

Device Boot Start End Blocks ld System 83 Linux /dev/sda1 39 307200 Partition 1 does not end on cylinder boundary. /dev/sda2 6271 50056192 83 Linux /dev/sda3 6271 6528 2064384 82 Linux swap / Solaris

Command (m for help): t
Partition number (1-4): 1
Hex code (type L to list codes): 82
Changed events type of partition

Changed system type of partition 1 to 82 (Linux swap / Solaris)

Command (m for help): p

Disk /dev/sda: 53.7 GB, 53687091200 bytes 255 heads, 63 sectors/track, 6527 cylinders Units = cylinders of 16065 * 512 = 8225280 bytes Sector size (logical/physical): 512 bytes / 512 bytes 1/0 size (minimum/optimal): 512 bytes / 512 bytes Disk identifier: 0x0003f428

ld_System Device Boot Start End Blocks /dev/sda1 39 307200 82 Linux swap / Solaris Partition 1 does not end on cylinder boundary. /dev/sda2 50056192 83 Linux 39 6271 /dev/sda3 6271 6528 2064384 82 Linux swap / Solaris

Command (m for help: w
The partition table has been altered!

Calling ioctl() to re-read partition table.

WARNING: Re-reading the partition table failed with error 16: Device or resource busy. The kernel still uses the old table. The new table will be used at the next reboot or after you run partprobe(8) or kpartx(8) Syncing disks.

[root@localhost ~]#



스왑메모리

3. 스왑파티션을 스왑영역으로 생성하는 포맷작업

[root@host ~]# mkswap -c -v1 /dev/sda3 Setting up swapspace version 1, size = 2064380 KiB no label, UUID=b6083e5d-11b6-4509-bef1-212dfeb473a4

- 4. 스왑영역 활성화하기 [root@host ~]# swapon /dev/sda3
- 5. 파일시스템테이블 파일에 등록하는 작업



```
#!/bin/sh
# This script will be executed *after* all the other init scripts.
# You can put your own initialization stuff in here if you don't
# want to do the full Sys V style init stuff.
touch /var/lock/subsvs/local
swapon /dev/sda3
                      /dev/shm
tmpfs
                                             tmpfs
                                                     defaults
                                                                    0 0
                      /dev/pts
                                                     gid=5.mode=620
                                                                    0.0
devots
                                             devots
sysfs
                      /svs
                                             sysfs
                                                     defaults
                                                                    0 0
                                                                    0.0
                      /proc
                                                     defaults
DFOC
                                             DFOC
/dev/sda3
                                                                    0.0
                      swap
                                                     swap
                                             swap
```



dumpe2fs

✔ 특정 파일시스템의 상세정보와 사용내역

dumpe2fs

```
Journal backup: inode blocks
Journal features: (none)
Journal size: 8M

Journal length: 8192
Journal sequence: 0x0000001c
Journal start: 1
```

Group 0: (Blocks 1-8192) [ITABLE_ZEROED]
Checksum 0x6cf3, unused inodes 2007
Primary superblock at 1, Group descriptors at 2-3
Reserved GDT blocks at 4-259
Block bitmap at 260 (+259), Inode bitmap at 276 (+275)
Inode table at 292-544 (+291)
3836 free blocks, 2007 free inodes, 2 directories, 2007 unused inodes
Free blocks: 4357-8192
Free inodes: 18-2024
Group 1: (Blocks 8193-16384) [INODE_UNINIT, ITABLE_ZEROED]



dumpe2fs

- ✓ 파일시스템의 슈퍼블록
- > dumpe2fs -h

```
[root@localhost ~]# dumpe2fs /dev/sda1 | grep superblock
dumpe2fs 1.41.12 (17-May-2010)
Primary superblock at 1, Group descriptors at 2-3
Backup superblock at 8193, Group descriptors at 8194-8195
Backup superblock at 24577, Group descriptors at 24578-24579
Backup superblock at 40961, Group descriptors at 40962-40963
Backup superblock at 57345, Group descriptors at 57346-57347
Backup superblock at 73729, Group descriptors at 73730-73731
Backup superblock at 204801, Group descriptors at 204802-204803
Backup superblock at 221185, Group descriptors at 221186-221187
[root@localhost ~]# []
```

Reserved GDT blocks: 256
Blocks per group: 8192
Fragments per group: 2024
Inodes per group: 253
Flex block group size: 16

Filesystem created: Wed Jan 18 05:41:56 2017
Last mount time: Sun Jan 22 20:32:46 2017
Last write time: Sun Jan 22 20:32:46 2017

Mount count: 5



tune2fs

- ✓파일시스템 튜닝명령어(tune2fs)
- ▶ 파일 시스템의 슈퍼블록 정보 확인

```
[root@localhost ~]# tune2fs -1 /dev/sda1
tune2fs 1.41.12 (17-May-2010)
Filesystem volume name:
                          <none>
Last mounted on:
                  /boot
Filesystem UUID:
                          c09c792a-b0de-4e70-9242-39a5bcdafc0a
Filesystem magic number: 0xEF53
Filesystem revision #: 1 (dynamic)
Filesystem features:
                          has_journal ext_attr resize_inode dir
_bg sparse_super huge_file uninit_bg dir_nlink extra_isize
Filesystem flags:
                          signed directory hash
Default mount options:
                          user xattr acl
Filesystem state:
                          clean
Errors behavior:
                          Continue
Filesystem OS type:
                          Linux
Inode count:
                          76912
                          307200
Block count:
```



tune2fs

✓ 파일시스템의 최대 마운트 횟수 지정

```
[root@localhost ~]# tune2fs -c 828 /dev/sda1
tune2fs 1.41.12 (17-May-2010)
Setting maximal mount count to 828
[root@localhost ~]# [

[root@localhost ~]# tune2fs -l /dev/sda1 | grep mount
Last mounted on: /boot

Default mount options: user_xattr acl
Last mount time: Sun_Jan 22 20:32:46 2017

Maximum mount count: 828

[root@localhost ~]# [

// ONLHI = F 74 ^ 0 ITAM F A1A
```

✔ 예비물독 개수 & 퍼센트 설성

```
[root@localhost ~] # tune2fs -r 25000 /dev/sda1 [root@localhost ~] # tune2fs -m 28 /dev/sda1 tune2fs 1.41.12 (17-May-2010)

Setting reserved blocks count to 25000 Setting reserved blocks percentage to 28% (86016 blocks) [root@localhost ~] # [
```



tune2fs

✓ 예비블록 사용자 & 그룹설정

```
Lroot@localhost ~]# tune2fs -1 /dev/sda1 |
                                          grep Reserved
Reserved block count:
                         86016
                         256
Reserved GDT blocks:
Reserved blocks uid:
                         0 (user root)
                         0 (group root)
Reserved blocks gid:
[root@localhost ~]# tune2fs -u lee /dev/sda1
tune2fs 1.41.12 (17-May-2010)
Setting reserved blocks uid to 500
[root@localhost ~]# tune2fs -1 /dev/sda1
                                           grep Reserved
Reserved block count:
                         86016
                         256
Reserved GDT blocks:
                    500 (user lee)
Reserved blocks uid:
Reserved blocks gid: 0 (group root)
[root@localhost ~]# tune2fs -g root /dev/sda1
tune2fs 1.41.12 (17-May-2010)
Setting reserved blocks gid to 0
[root@localhost ~]# tune2fs -1 /dev/sda1
                                          grep Reserved
Reserved block count:
                         86016
                         256
Reserved GDT blocks:
Reserved blocks uid: 500 (user lee)
Reserved blocks gid:
                         0 (group root)
[root@localhost ~]# ||
```



debugfs

✓파일시스템 디버거(debugfs)

- ➤ debugfs는 root 전용명령어
- ➤ 슈퍼블럭과 inode를 조작
- ▶ 장치명은 실제 장치명으로
- ➤ ext2 ext3로 생성된 파일시스템만을 대상으로 디버깅하거나 삭제파 일 보구
- ➤ native filesystem 모드 : 쉘프롬프트가 존재하는 쉘상태
- -> 전용 명령어 : 1cd
- ➤ debugfs 모드 -> 전용 명령어 : cd

```
[root@localhost ~]# debugfs debugfs 1.41.12 (17-May-2010) debugfs: debugfs: q [root@localhost ~]# [
```



debugfs

✓ debugfs 전용모드에서 파일시스템 열고 닫기

```
[root@localhost ~]# debugfs
debugfs 1.41.12 (17-May-2010)
debuafs:
debugfs: open -w /dev/sda1
debugfs:
debugfs: Is
             2 (12) .. 11 (20) lost+found 32385 (12) grub
 2 (12) .
 32387 (56) efi 12 (48) .vmlinuz-2.6.32-131.0.15.el6.i686.hmac
     (44) System.map-2.6.32-131.0.15.el6.i686
     (40) config-2.6.32-131.0.15.el6.i686
     (44) symvers-2.6.32-131.0.15.el6.i686.gz
     (40) vmlinuz-2.6.32-131.0.15.el6.i686
     (696) initramfs-2.6.32-131.0.15.el6.i686.img
debugfs:
         close filesvs
debugfs∶
debugfs:
debugfs: Is
ls: Filesystem not open
debugfs:
```



debugfs

- ✔ debugfs 읽기 모드와 쓰기모드
- ➤ 옵션 : -w의 유무에 따라 읽기모드와 쓰기모드로 나뉜다.

✓ 현재 작업 디렉토리 출력

```
[root@localhost ~]# debugfs -w /dev/sda1
debugfs 1.41.12 (17-May-2010)
debugfs:
debugfs: pwd
[bwq]
        INODE:
                    2 PATH: /
                    2 PATH: /
[root]
      INODE:
debugfs:
debugfs: print_working_directory
        INODE:
                    2
[bwd]
                       PATH: /
                    2
      INODE:
                       PATH: /
[root]
debugfs:
```



debugfs

✔ 디렉토리 리스트 확인

```
debugfs Is
2 (12) . 2 (12) . . 11 (20) lost+found 32385 (12) grub
32387 (56) efi 12 (48) .vmlinuz-2.6.32-131.0.15.el6.i686.hmac
13 (44) System.map-2.6.32-131.0.15.el6.i686
14 (40) config-2.6.32-131.0.15.el6.i686
15 (44) symvers-2.6.32-131.0.15.el6.i686
16 (40) vmlinuz-2.6.32-131.0.15.el6.i686
17 (696) initramfs-2.6.32-131.0.15.el6.i686.img
debugfs:
debugfs:
```

✓ 파라미트 보기

```
[root@localhost ~]# debugfs
debugfs 1.41.12 (17-May-2010)
debugfs:
debugfs: params
Filesystem in use: --none--
debugfs:
```



debugfs

✔ 새 디렉토리 만들기

```
[root@localhost ~]# debugfs -w /dev/sda1
debugfs 1.41.12 (17-May-2010)
debugfs:
debugfs: mkdir newdir1
debugfs:
debugfs: a
[root@localhost ~]# Is -I /boot
total 19284
                          104961 Nov 12 2011 config-2.6.32-131.0.15.el6.i686
-rw-r--r--. 1 root root
drwxr-xr-x. 3 root root
                          1024 Jan 18 05:50 efi
drwxr-xr-x. 2 root root
                            1024 Jan 17 20:57 grub
-rw-r--r-. 1 root root 13910411 Jan 18 05:57 initramfs-2.6.32-131.0.15.el6.i686.img
drwx----. 2 root root
                           12288 Jan 18 05:41 lost+found
                           1024 Jan 22 22:33 newdir
drwxr-xr-x. 2 root root
                           1024 Jan 22 22:38 newdir1
drwxr-xr-x. 2 root root
-rw-r--r--. 1 root root
                          162891 Nov 12 2011 symvers-2.6.32-131.0.15.el6.i686.gz
-rw-r--r-. 1 root root 1796044 Nov 12 2011 System.map-2.6.32-131.0.15.el6.i686
-rwxr-xr-x. 1 root root 3745664 Nov 12 2011 vmlinuz-2.6.32-131.0.15.el6.i686
[root@localhost ~]#
```

✔ 현재 작업디렉토리 변경

```
debugfs: Is
             2 (12) .. 11 (20) lost+found
2 (12) .
                                                 32385 (12) grub
32387 (12) efi 18 (16) newdir
                                   19 (28) newdir1
    (48) .vmlinuz-2.6.32-131.0.15.el6.i686.hmac
    (44) System.map-2.6.32-131.0.15.el6.i686
    (40) config-2.6.32-131.0.15.el6.i686
 15
    (44) symvers-2.6.32-131.0.15.el6.i686.gz
    (40) vmlinuz-2.6.32-131.0.15.el6.i686
    (696) initramfs-2.6.32-131.0.15.el6.i686.img
debugfs cd newdir
debugfs pwd
                  18 PATH: /newdir
[bwq]
       INODE:
program_1aNODE:
                   2 PATH: /
                                      zam2695@naver.com
ďebugťs∷`
```



debugfs

✓ 실행 전 디렉토리로 이동

```
debugfs: | lcd /tmp
debugfs:
debugfs:
          bwd
[bwq]
         INODE:
                    18 PATH: /newdir
[root]
        INODE:
                        PATH: /
debugfs:
          Icd /boot
debugfs:
debugfs:
debugfs:
          bwq
                  18 PATH: /newdir
[bwa]
        INODE:
                        PATH: /
[root]
       INODE:
debugfs:
debugfs:
          \mathbf{a}
```

- ➤ native filesystem -> 쉘프롬프트가 존재하는 디렉토리 경로
- ➤ "cd" -> debugfs에서의 현재작업위치 변경
- ➤ "lcd"-> "native filesystem"위치를 변경
- ▶ 따라서, 작업위치는 변하지 않았다.



debugfs

✓ 특정 디렉토리 삭제

```
debugfs: Is
               2 (12) .. 11 (20) lost+found 32385
                                                           (12) grub
  2 (12) .
  32387 (12) efi 18 (16) newdir 19 (28) newdir1
      (48) .vmlinuz-2.6.32-131.0.15.el6.i686.hmac
      (44) System.map-2.6.32-131.0.15.el6.i686
      (40) config-2.6.32-131.0.15.el6.i686
     (44) symvers-2.6.32-131.0.15.el6.i686.gz
      (40) vmlinuz-2.6.32-131.0.15.el6.i686
      (696) initramfs-2.6.32-131.0.15.el6.i686.img
 debugfs:
 debugfs: rmdir newdir1
 debugfs:
 debugfs:
         ١s
  2 (12) . 2 (12) . . 11 (20) lost+found 32385 (12) grub
  32387 (12) efi 18 (44) newdir
[root@localhost ~]# Is -I /boot
total 19283
-rw-r--r--. 1 root root
                       104961 Nov 12 2011 config-2.6.32-131.0.15.el6.i686
drwxr-xr-x. 3 root root
                      1024 Jan 18 05:50 efi
                      1024 Jan 17 20:57 grub
drwxr-xr-x. 2 root root
-rw-r--r. 1 root root 13910411 Jan 18 05:57 initramfs-2.6.32-131.0.15.el6.i686.img
                      12288 Jan 18 05:41 lost+found
drwx----. 2 root root
                      1024 Jan 22 22:33 newdir
drwxr-xr-x. 2 root root
-rw-r--r-. 1 root root
                       162891 Nov 12 2011 symvers-2.6.32-131.0.15.el6.i686.gz
-rw-r--r--. 1 root root
                     1796044 Nov 12 2011 System.map-2.6.32-131.0.15.el6.i686
-rwxr-xr-x, 1 root root 3745664 Nov 12 2011 vmlinuz-2.6.32-131.0.15.el6.i686
[root@localhost ~]# |
```



debugfs

✓ 파일복사하기

```
debugfs: write test test2
                                                                                  [root@localhost ~]# |s -| /boot
Allocated inode: 18
                                                                                  total 19283
debugfs:
                                                                                  -rw-r--r-. 1 root root 104961 Nov 12 2011 config-2.6.32-131.0.15.el6.i686
debugfs: Is
                                                                                                       1024 Jan 18 05:50 efi
                                                                                  drwxr-xr-x. 3 root root
               2 (12) .. 11 (20) lost+found
                                                         32385 (12) grub
 2 (12) .
                                                                                  drwxr-xr-x. 2 root root
                                                                                                       1024 Jan 17 20:57 grub
 32387 (12) efi 18 (44) test2
                                                                                  -rw-r--r-. 1 root root 13910411 Jan 18 05:57 initramfs-2.6.32-131.0.15.el6.i686.img
     (48) .vmlinuz-2.6.32-131.0.15.el6.i686.hmac
                                                                                  drwx-----. 2 root root 12288 Jan 18 05:41 lost+found
     (44) System.map-2.6.32-131.0.15.el6.i686
                                                                                                       162891 Nov 12 2011 symvers-2.6.32-131.0.15.el6.i686.gz
                                                                                  -rw-r--r-. 1 root root
    (40) config-2.6.32-131.0.15.el6.i686
                                                                                  -rw-r--r-. 1 root root 1796044 Nov 12 2011 System.map-2.6.32-131.0.15.el6.i686
    (44) symvers-2.6.32-131.0.15.el6.i686.gz
                                                                                                       1024 Jan 22 22:5 test2
                                                                                  drwxr-xr-x. 2 root root
    (40) vmlinuz-2.6.32-131.0.15.el6.i686
                                                                                  -rwxr-xr-x, 1 root root 3745664 Nov 12 2011 vmlinuz-2.6.32-131.0.15.e16.i686
 17 (696) initramfs-2.6.32-131.0.15.el6.i686.img
                                                                                  [root@localhost ~]#
debugfs: |
```

✓ 삭제된 파일의 inode 목록 확인

```
debugfs: Isdel
Inode Owner Mode Size Blocks Time deleted
19 0 40755 1024 1/ 1 Sun Jan 22 22:48:22 2017
1 deleted inodes found.
debugfs:
```

➤ inode 정보를 알고 있는 경우, 삭제된 파일을 복구할 수도 있다.



debugfs

✔ 슈퍼블럭 정보 및 상태 확인

debugts: stats Filesystem volume name: <none> Last mounted on: /boot Filesystem UUID: c09c792a-b0de-4e70-9242-39a5bcdafc0a Filesystem magic number: 0xEF53 Filesystem revision #: 1 (dynamic) Filesystem features: has_journal ext_attr resize_inode dir_index fi _bg sparse_super huge_file uninit_bg dir_nlink extra_isize Filesystem flags: signed directory hash Default mount options: user xattr acl Filesystem state: clean Frrors behavior: Continue

✔ 특정파일의 inode 상세정보 확인

```
debugfs: stat grub
Inode: 32385 Type: directory Mode: 0755
                                            Flags: 0x80000
Generation: 376332824 Version: 0x00000019
User: 0 Group:
                       0 Size: 1024
File ACL: 4354 Directory ACL: 0
Links: 2 Blockcount: 4
Fragment: Address: 0 Number: 0
ctime: 0x587ef5a3 -- Tue Jan 17 20:57:07 2017
atime: 0x5885a453 -- Sun Jan 22 22:36:03 2017
mtime: 0x587ef5a3 -- Tue Jan 17 20:57:07 2017
EXTENTS:
```

2021-0(0)9 135153 debugfs:



debugfs

✓ 현재 사용가능한 debugfs 명령어

```
debugfs: Ir
Available debugfs requests:
show_debugfs_params, params
                         Show debugfs parameters
open_filesys, open
                         Open a filesystem
                         Close the filesystem
close_filesys, close
                         Set/print superblock features
feature, features
dirty_filesys, dirty
                         Mark the filesystem as dirty
init_filesys
                         Initialize a filesystem (DESTROYS DATA)
show super stats, stats
                         Show superblock statistics
ncheck
                         Do inode->name translation
icheck
                         Do block->inode translation
change_root_directory, chroot
                         Change root directory
change working directory, cd
                         Change working directory
list_directory, ls
                         List directory
show_inode_info, stat
                         Show inode information
dump_extents, extents, ex
                         Dump extents information
link, In
                         Create directory link
unlink
                         Delete a directory link
mkdir
                         Create a directory
rmdir
                         Remove a directory
```

✓ 현재위치에서 가장 가까운 빈 블록 찾기

```
debugfs: ffb
Free blocks found: 4357
debugfs: •
```



33

debugfs

✓ 현재 위치에서 빈 inode 찾기

```
debugfs: ffi
Free inode found: 19
debugfs: •
```

✓ 파일링크 삭제하기

```
[root@localhost ~]# |s -| /boot
total 19282
drwxr-xr-x. 3 root root 1024 Jan 18 05:50 efi
drwxr-xr-x. 2 root root
                      1024 Jan 17 20:57 grub
-rw-r--r--. 1 root root 13910411 Jan 18 05:57 initramfs-2.6.32-131.0.15.el6.i686.img
drwx-----. 2 root root 12288 Jan 18 05:41 lost+found
-rw-r--r--. 1 root root 1796044 Nov 12
                                2011 System.map-2.6.32-131.0.15.el6.i686
                   3745664 Nov 12 2011 vmlinuz-2.6.32-131.0.15.el6.i686
-rwxr-xr-x. 1 root root
[root@localhost ~]#
   (4U) CONTIG-2.b.32-131.U.15.e1b.1b0b
    (44) symvers-2.6.32-131.0.15.el6.i686.gz
    (40) vmlinuz-2.6.32-131.0.15.el6.i686
    (696) initramfs-2.6.32-131.0.15.el6.i686.img
debugfs:
```



debugfs

✔ 파일링크 생성하기

```
debugfs: Is
                 2 (12) ... 11 (20) lost+found
 2 (12)
                                                              32385 (12) grub
 32387 (56) efi 12 (48) .ymlinuz-2.6.32-131.0.15.el6.i686.hmac
      (44) System.map-2.6.32-131.0.15.el6.i686
      (40) config-2.6.32-131.0.15.el6.i686
      (44) symvers-2.6.32-131.0.15.el6.i686.gz
 15
 16
      (40) vmlinuz-2.6.32-131.0.15.el6.i686
      (696) initramfs-2 6 32-131.0.15.el6.i686.img
 17
           link efi efi_new
debugfs:
debugfs:
debugfs:
                    (12) ..
 2 (12) .
                                 11 (20) lost+found
                                                              32385 (12) grub
 32387 (12) efi
                        32387 (44) efi new
      (48) .vmlinuz-2.6.32-131.0.15.el6.i686.hmac
 12
       44) System.map-2.6.32-131.0.15.el6.i686
 13
 14
      (40) config-2.6.32-131.0.15.el6.i686
 15
      (44) symyers-2.6.32-131.0.15.el6.i686.gz
      (40) vmlinuz-2.6.32-131.0.15.el6.i686
 16
      (696) initramfs-2.6.32-131.0.15.el6.i686.img
 17
debugfs:
[root@localhost boot]# Is -I /boot
total 19284
                      104961 Nov 12 2011 config-2.6.32-131.0.15.el6.i686
-rw-r--r--. 1 root root
drwxr-xr-x. 3 root root
                        1024 Jan 18 05:50 efi
drwxr-xr-x. 3 root root
                         1024 Jan 18 05:50 efi_new
drwxr-xr-x. 2 root root
                         1024 Jan 17 20:57 grub
-rw-r--r-. 1 root root 13910411 Jan 18 05:57 initramfs-2.6.32-131.0.15.el6.i686.img
drwx----. 2 root root
                        12288 Jan 18 05:41 lost+found
                       162891 Nov 12 2011 symmetrs = 2.6.32 = 131.0.15.el6.i686.gz
-rw-r--r--. 1 root root
-rw-r---. 1 root root 1796044 Nov 12 2011 System.map-2.6.32-131.0.15.el6.i686
-rwxr-xr-x. 1 root root 3745664 Nov 12 2011 vmlinuz-2.6.32-131.0.15.el6.i686
[root@localhost boot]# Is -li /boot
total 19284
  <u> 14</u> -rw-r--r--. 1 root root
                             104961 Nov 12 2011 config-2.6.32-131.0.15.el6.i686
32387 drwxr-xr-x. 3 root root
                               1024 Jan 18 05:50 efi
32387 drwxr-xr-x. 3 root root
                               1024 Jan 18 05:50 efi_new
32385 drwxr-xr-x. 2 root root
                               1024 Jan 17 20:57 grub
  17 -rw-r---. 1 root root 13910411 Jan 18 05:57 initramfs-2.6.32-131.0.15.el6.i686.img
  11 drwx----. 2 root root
                              12288 Jan 18 05:41 lost+found
                             162891 Nov 12 2011 symvers-2.6.32-131.0.15.el6.i686.gz
  15 -rw-r--r--. 1 root root
                            1796044 Nov 12
                                           2011 System.map-2.6.32-131.0.15.el6.i686
  13 -rw-r--r--. 1 root root
  16 - rwxr-xr-x. 1 root root 3745664 Nov 12 2011 vmlinuz-2.6.32-131.0.15.el6.i686
oct@locaUhost boot]# [] zam2695@naver.com
[roo4@KobaUhostDboot]# |
```



프로세스 관리 실무

프로세스 관리 실무



프로세스 확인

- Ps
 - 프로세스의 상태 확인

```
\Sigma S
cn1238@localhost:~
                                                                       login as: cn1238
cn1238@117.17.73.143's password:
Last login: Tue Jan 17 15:38:24 2017 from 117.17.73.145
[cn1238:~, 1]$ ps
  PID TTY
                   TIME CMD
12027 pts/7 00:00:00 bash
12052 pts/7 00:00:00 ps
[cn1238:~, 2]$ 🗍
```



프로세스 확인

• Ps -ef | grep 프로세스명

```
[cn1238:~, 8]$ ps -ef | grep bash
         5551 5549 0 Jan16 pts/2
ROOT
                                     00:00:00 bash
cn1238 6048 6046 0 Jan16 pts/5
                                     NA:NA:NA bash
       6540 6538
                    O Jan16 pts/9
                                     00:00:00 bash
admin
root 6557 6554
                    0 Jan16 pts/9
                                     00:00:00 bash
cn1447 9704 1
                    0 2016 ?
                                     00:00:00 -bash
      21634 21633 | O 10:32 pts/1
cn1238
                                     00:00:00 -bash
                    0 10:47 pts/1
      21816 21634
cn1238.
                                     00:00:00 grep bash
```



프로세스 트리 확인

Pstree

```
[cn1238:~, 9]$ pstree init—NetworkManager
       -abrtd
        -acpid
        -atd
        -auditd----{auditd}
-automount----4+[{automount}]
        -avahi-daemon---avahi-daemon
       -bash
       -4+[bonobo-activati——{bonobo-activat}]
        -3*[clock-applet]
                             -63*[{console-kit-da}]
        -console-kit-dae—
        -crond
        -cupsd
        -5*[dbus-daemon]
        -7*[dbus-launch]
       -devkit-power-da
        -3*[gconf-im-settin]
       -4*[gconfd-2]
        -gdm-binary<del>---</del>gdm-simple-slav<del>---</del>Xorg
                                             -gdm-session-wor---gnome-session-
                                                                                       -abrt-ap+
                                                                                       -bluetoo+
                                                                                       -adu-not+
                                                                                       gnome-p+
                                                                                       -gnome-p+
                                                                                       -anome-v+
                                                                                       -gpk-upd+
                                                                                       -metacity
                                                                                       -nautilus
                                                                                       -nm-appl+
                                                                                      -polkit-+
                                                                                      -python
                                                                                       -{gnome-+
                       -2*[gdm-simple-slav--Xorg]
                                                 -gdm-session-wor----gnome-session-
                                                                                          -abrt+
                                                                                           -blue+
                                                                                           -gdu-+
                                                                                          gnom+
                                                                                           gnom+
                                                                                          gnom+
                                                                                           -apk-+
                                                                                          -meta+
                                                                                          -naut+
                                                                                          -polk+
                                                                                          -pvth+
                                                                                          -{gno+
```



프로세스 트리 확인

• Pstree -up 사용자이름

```
[cn1238:~, 10]$ pstree -up cn1238
bonobo-activati(5812)—{bonobo-activat}(5813)
clock-applet (5898)
dbus-daemon(5696)
dbus-launch(5695)
gconf-im-settin(6023)
gconfd-2(5769)
gnome-session(5686)—abrt-applet(5818)
                      -bluetooth-apple(5824)
                      -gdu-notificatio(5833)
                       -anome-panel(5808)
                      -gnome-power-man(5830)
                      -gnome-volume-co(5822)
                      -gpk-update-icon(5819)---{gpk-update-ico}(8380)
                      -metacity(5803)
                     —nautilus(5810)
                      -polkit-gnome-au(5820)
                      -python(5832)
                       -{anome-session}(5771)
```



진행 프로세스

- jobs
 - 현재 진행중이거나 멈춘 프로세스 표시

```
[root@host_backup]# jobs
[1]- Stopped
[2]+ Stopped
```

```
tar -cvf boot.tar.gz boot
tar -cvf boot.tar.gz boot
```



백그라운드

- 명령어 &
 - 명령어 행 마지막에 &를 붙이면 백그라운드 실행

```
[root@host backup]# tar -cf boot.tar.gz boot &
[1] 7907
[root@host backup]# jobs
[1]+ Done tar -cf boot.tar.gz boot
```



백그라운드

- Ctrl + Z
 - 현재 진행중인 프로세스 일시중지
- bg %번호
 - 일시정지된 프로세스를 백그라운드에서 실행

```
^Z
[2]+ Stopped
                              tar -cvf boot.tar.gz boot
[root@host_backup]# iobs
[1]- Stopped
                              tar -cvf boot.tar.gz boot
[2]+ Stopped
                              tar -cvf boot.tar.gz boot
[root@host_backup]#_bg%1
bash: bg%1: command not found
[root@host_backup]# bg %1
[1]- tar -cvf boot.tar.gz boot &
[root@host_backup]#_iobs
[1]- Done
                              tar -cvf boot.tar.gz boot
                              tar -cvf boot.tar.gz boot
[2]+ Stopped
```



포그라운드

- fg %번호
 - 일시정지된 프로세스를 포그라운드에서 실행

```
[root@host backup]# jobs
[1]- Done
[2]+ Stopped
[root@host backup]# fg %2
tar -cvf boot.tar.gz boot
[root@host backup]# Is
[root@host backup]# jobs
[root@host backup]# ]
```

```
tar -cvf boot.tar.gz boot
tar -cvf boot.tar.gz boot
```



프로세스 제거

- Kill -9 PID
 - 해당 프로세스를 제거
 - --9는 프로세스를 제거하라는 시그널



프로세스 제거

- Killall 프로세스명
 - 해당 프로세스들을 모두 제거
 - - | 실행할지 확인 옵션

```
[root@host backup]# jobs
[1]+ Running shutdown -h +100 &
[root@host backup]# killall shutdown
shutdown: Shutdown cancelled
[1]+ Done shutdown -h +100
```



퍼미션과 SetUID,속성관리 실무

17장. 퍼미션과 SetUID,속성관리 실



1. 파일에 대한 허가권의 종류와 기본 개념

파일의 허가권 : 파일이나 디렉토리가 읽혀지거나 쓰여지거나 실행되려고 할 때, 그리고 옮겨지거나 삭제되는 등의 action 이 발생하려고 할 때 그 action에 대한 허가를 설정 하고 있는 것

- →action 에 대한 허가: 1) 퍼미션
 - 2) SetUID, SetGID, Sticky Bit
 - 3) 속성

17장. 퍼미션과 SetUID ,속성관리실 NYANGUNIVERSITY

2. 파일과 디렉토리의 퍼미션

chmod : 특정파일 또는 디렉토리의 퍼미션을 변경하는 명령어

<파일과 디렉토리의 퍼미션(권한)의 의미>

퍼미션	일반적인 의미	파일	디렉토리
r	읽기권한	파일을 읽을 수 있음	디렉토리의 내용을 볼 수 있음(ls)
W	쓰기권한	파일에 저장,삭제 할 수 있음	디렉토리에 파일저장, 디렉토리 이름변경,삭제
X	실행권한	파일 실행 가능	디렉토리에 접근할 수 있음(cd)
S	SetUID, SetGID	파일소유자(SetUID) 권한으로 실행함	, 그룹소유자(SetGID)의
t	Sticky Bit	공유디렉토리로 사용됨	

17장. 퍼미션과 SetUID, 속성관리



2-1. 파일의 퍼미션의 이해와 설정법

```
[root@localhost ~]# ls -l
total 60
         1 root root 2671 Jan 18 05:54 anaconda-ks.cfg
rw-r--r-. 1 root root 38587 Jan 18 05:54 install.log
-rw-r--r-. 1 root root 10067 Jan 18 05:53 install.log.syslog
            rw-
 (파일 유형) (소유자권한) (그룹소속자권한) (일반다른사용자권한)
 *파일유형: b: 블럭구조의 특수파일
         c: 입출력에 사용되는 특수파일
         p: 파이프파일임
         s: 소켓파일임
         -: 일반파일
         l: 심벌릭링크파일
         d: 디렉토리
```

17장. 퍼미션과 SetUID, 속성관리실 (ATYANG UNIVERSITY

3. SetUID 에 대한 이해와 설정법

-SetUID가 설정된 파일을 실행하였을 경우:

실행되는 동안에는 실행시킨 사용자의 권한이 아닌 파일의 소유자 권한으로 실행된다 (=실행시작부터 실행 종료 할 때 까지 실행시킨 사용자의 권한이 아닌 그 파일의 소유자 권한으로 실행이 된다)

SetUID 퍼미션 설정 방법: 일반 퍼미션 앞에 4를 붙인다

```
[root@localhost ~]# Is -I install.log

-rw-r--r--. 1 root root 38587 Jan 18 05:54 install.log

[root@localhost ~]# chmod 4755 install.log

[root@localhost ~]# Is -I install.log

-rwsr-xr-x. 1 root root 38587 Jan 18 05:54 install.log
```

소유자 실행퍼미션 자리에 s라는 문자가 설정됨 다른 사용자들이 이 파일을 실행하더라도 파일의 소유자 권한으로 실행 됨

17장. 퍼미션과 SetUID , 속성관리



3. SetGID 에 대한 이해와 설정법

```
-SetGID 설정 파일 실행:
어떤 누가 실행하더라도 그 파일의 그룹권한으로 실행된다

SetGID 설정 방법: 일반 퍼미션 앞에 2를 붙인다

[root@localhost ~]# ls -l install.log
-rwsr-xr-x. 1 root root 38587 Jan 18 05:54 install.log
[root@localhost ~]# chmod 2755 install.log
[root@localhost ~]# ls -l install.log
-rwxr-sr-x. 1 root root 38587 Jan 18 05:54 install.log
-rwxr-sr-x. 1 root root 38587 Jan 18 05:54 install.log
-rwxr-sr-x. 1 root root 38587 Jan 18 05:54 install.log
-rwxr-sr-x. 1 root root 38587 Jan 18 05:54 install.log
```

17장. 퍼미션과 SetUID, 속성관리



3. Sticky Bit에 대한 이해와 설정법

```
[root@localhost ~]# ls -l /| grep tmp
  drwxrwxrwt. 19 root_root 4096 Jan 22 21:54 tmp
    일반 퍼미션:777, 맨 끝에 t라는 소문자 마킹
     공유디렉토리: 파일생성을 아무나 할 수 있으며 생성된 파일은 각
     각 생성한 소유자의 소유로 되며 수정, 삭제 또한 생성한 사용자만
     이 그 파일을 수정하고 지울 수 있도록 되어있다
     Sticky Bit 설정 방법: 일반 퍼미션 앞에 1을 붙임
[root@localhost ~]# chmod 1777 test
[root@localhost ~]# Is -I
total 60
-rw----. 1 root root 2671 Jan 18 05:54 anaconda-ks.cfg
-rwxr-sr-x. 1 root root 38587 Jan 18 05:54 install.log
-rw-r--r-. 1 root root 10067 Jan 18 05:53 install.log.syslog
                    0 Jan 22 22:50 test
-rwxrwxrwt. 1 root root
         실행 퍼미션자리에 t라는 문자로 셋팅
         즉, test파일이 공유 목적으로 사용 가능
```

17장. 퍼미션과 SetUID , 속성관리설



4. 파일과 디렉토리의 속성에 대한 이해와 활용

-chattr: 특정 속성을 부여하거나 제거할 수 있는 명령어

-lsattr: 파일에 부여되어있는 특정 속성을 확인하는 명령어

<속성>

1) a속성: 해당 파일을 추가만 할 수 있다

- 2) c속성: 커널에 의해 디스크상에 자동적으로 압축된 상태
- 3) d 속성: dump 프로그램(명령어)으로 백업되지 않는다
- 4) i 속성: 해당파일의 변경,삭제,파일추가,링크파일도 만들 수 없다
- 5) s 속성: 파일삭제시 해당블럭이 모두 0, 디스크에 다시 쓰기가 발생함
- 6) S 속성: 파일 변경시 디스크동기화 발생
- 7) u 속성: 삭제시 그 내용이 저장되며 삭제 전 데이터로 복구 가능
- 8) j 속성: 저널링 파일시스템의 파일을 대상으로 설정
- 9) A 속성:access 가 발생하더라도 저장되는 atime값은 갱신되지 않음
- 10)D 속성: 변경사항을 동기화시킴
- 11)T 속성: 최상휘 디렉토리로 인식되어 간주됨
- ✔ Chattr로 파일가 디렉토리의 속성을 지정하는 주된 이유는 허가되지 않은 사용자가 파일의 변경을 못하도록 설정하여 파일보안을 하기 위해서이다 zam2695@naver.com

17장. 퍼미션과 SetUID, 속성관리



4. 속성 부여하기와 제거하기

```
-속성 부여하기: chattr +속성 파일이름
-속성 제거하기: Isattr -속성 파일이름
-여러 개의 속성 동시에 부여하기: 각각의 속성은 독립적이기 때문에 여러
개의 속성을 동시에 설정 가능 +원하는 속성 이어서 사용
[root@localhost ~]# ls -l
total 60
-rw----. 1 root root 2671 Jan 23 2017 anaconda-ks.cfg
-rw-r--r-. 1 root root 38587 Jan 23 2017 install.log
-rw-r--r-. 1 root root 10179 Jan 23 2017 install.log.syslog
[root@localhost ~]# Is -I install.log
-rw-r--r-. 1 root root 38587 Jan 23 2017 install.log
[root@localhost ~]# Isattr install.log
       ----e- install.log
[root@localhost ~]# chattr +aisSu messages
chattr: No such file or directory while trying to stat messages
[root@localhost ~]# chattr <u>+aisSu</u> install.log
[root@localhost ~]# Isattr install.log
suS-ia----e- install.log
```

Install.log 파일에 a i s S u 속성 동시 설정

17장. 퍼미션과 SetUID , 속성관리



4. 파일(디렉토리)의 소유자 및 소유그룹 변경하기 실무

chown(Change OWNer) : 파일이나 디렉토리의 소유자와 소유그룹을 변경할때에 사용하는 명령어

<소유자를 변경하고 싶을 때> chown 변경할 소유자 이름 파일이름 예) chown bible test : test 파일의 소유자를 bible로 변경

<파일의 소유자와 소유그룹 동시 변경> chown 소유자:소유그룹 파일이름 예) chown bible1:bible2 test : test 파일의 소유자를 bible1으로,소유그룹 을 bible2로 변경함



로그인과 원격접속



가장 기본적인 로컬시스템

/bin/login

```
[root:~, 14]# strings /bin/login
           /lib/ld-linux.so.2
           ₩y7!
           ₩+F1
           PTRh
           d$$[]
           Ť$4ū
           execf
           LOGIN FAILURE FROM %s, %s
           LOGIN FAILURE ON %s, %s
모든 로그인은 /bin/login 이라는 로그인과정을 전담하고 있는
               프로세스에 의해서 진행
```



가장 기본적인 로컬시스템

/etc/securetty

```
[root:~, 16]# cat /etc/securetty console vc/1 vc/2 vc/3 vc/4 vc/5 vc/6 vc/7 vc/8 vc/9
```

Root에 대한 로그인이 허용되는 터미널 장치명이 설정되어있는 파일



가장 기본적인 로컬시스템

/var/log/secure, /var/log/messages

```
[root:~, 18]# tail -f /var/log/secure
Jan 23 14:08:07 localhost login: pam_unix(remote:auth): authentication failure; logname= uid=0 euid=0 tty=pts/6 ruser= rhost=171.249.29.65 user=root
Jan 23 14:08:09 localhost login: FAILED LÒGIN 2 FROM 171.249.29.65 FOR root, Authentication failure
Jan 23 14:08:09 localhost login: pam securetty(remote:auth): access denied: tty 'pts/6' is not secure !
Jan 23 14:08:11 localhost login: FAILED LOGIN´3 FROM 171.249.29.65 FOR root, Authentication failure
Jan 23 14:08:11 localhost login: pam securetty(remote:auth): access denied: tty 'pts/6' is not secure !
Jan 23 14:08:11 localhost login: pam unix(remote:auth): check pass; user unknown
Jan 23 14:08:11 localhost login: pam_unix(remote:auth): authentication failure; logname= uid=0 euid=0 tty=pts/6 ruser= rhost=171.249.29.65
Jan 23 14:08:11 localhost login: pam_succeed_if(remote:auth): error retrieving information about user guest
Jan 23 14:08:13 localhost login: FAILED LOGIN SESSION FROM 171.249.29.65 FOR guest, User not known to the underlying authentication module
Jan 23 14:08:13 localhost login: PAM 1 more authentication failure: logname= uid=0 euid=0 tty=pts/6 ruser= rhost=171.249.29.65 user=root
[root:~, 19]# tail -10 /var/log/messages
Jan 23 14:08:02 localhost xinetd[i667]: $TABT: telnet pid=24366 from=::ffff:171.249.29.65
Jan 23 14:08:13 localhost xinetd[1667]: EXIT: telnet status=0 pid=24366 duration=11(sec)
Jan 23 14:08:16 localhost telnetd[24361]: ttloop: peer died: EOF
Jan 23 14:08:16 localhost xinetd[1667]: EXIT: telnet status=1 pid=24361 duration=32(sec)
Jan 23 14:08:50 localhost xinetd[1667]: START: telnet pid=24370 from=::ffff:68.43.9.85
Jan 23 14:08:50 localhost telnetd[24368]: ttloop: peer died: EOF
Jan 23 14:08:50 localhost xinetd[1667]: EXIT: telnet status=1 pid=24368 duration=31(sec)
Jan 23 14:09:21 localhost telnetd[24370]: ttloop: peer died: EOF
Jan 23 14:09:21 localhost xinetd[1667]: EXIT: telnet status=1 pid=24370 duration=31(sec)
```

<u>위의 두 경로에서 로그인 관련 기록 확인 가능</u> <u>(단, messages경로는 접속기록뿐 아니라 시스템전체 로그가 기록됨)</u>



ssh를 이용한 원격접속

ps -ef | grep ssh

```
[root:~, 24]# ps -ef | grep ssh
         1659
                     0 2016 ?
                                      00:00:00 /usr/sbin/sshd
root
        21629 1659
                     0 10:32 ?
                                      00:00:00 sshd: cn1238 [priv]
root
cn1238
        21633 21629
                     0 10:32
                                      00:00:00 sshd: cn1238@pts/1
         24079 1659
                     0 13:46 ?
                                      00:00:00 sshd: root@pts/4
root
        24420 24081
                     0 14:17 pts/4
                                      00:00:00 grep ssh
root
[root:~, 26]# /etc/rc.d/init.d/sshd restart
Stopping sshd:
                                                             OK.
Starting sshd:
[root:~, 27]# ps -ef | grep ssh
        21629
                                      00:00:00 sshd: cn1238 [priv]
root
cn1238
        21633 21629
                                      00:00:00 sshd: cn1238@pts/1
                                      00:00:00 sshd: root@pts/4
        24079
                     0 13:46 ?
root
        24435
                     0 14:18 ?
                                      00:00:00 <u>/usr/shin/sshd</u>
root
        24438 24081
                     0 14:18 pts/4
                                      00:00:00 grep ssh
root
```

ssh서버에는 sshd라는 데몬이 실행되어 있어야만 다른 곳에서 이 서버로 ssh원격 접속이 가능하다



ssh를 이용한 원격접속

/etc/ssh/ssh_config

```
[root:~, 28]# cat /etc/ssh/ssh_config
       $OpenBSD: ssn contig.v 1.25 2009/02/17 01:28:32 dim Exp $
# This is the ssh client system-wide configuration file. See
# ssh_config(5) for more information. This file provides defaults for
# users, and the values can be changed in per-user configuration files
# or on the command line
# Configuration data is parsed as follows:
# 1. command line options
# 2. user-specific file
# 3. system-wide file
# Any configuration value is only changed the first time it is set.
# Thus, host-specific definitions should be at the beginning of the
# configuration file, and defaults at the end.
# Site-wide defaults for some commonly used options. For a comprehensive
# list of available options, their meanings and defaults, please see the
# ssh config(5) man page.
# Host *
   ForwardAgent no
   ForwardX11 no
   RhostsRSAAuthentication no
   RSAAuthentication ves
   PasswordAuthentication ves
   HostbasedAuthentication no
   GSSAPIAuthentication no
   GSSAPIDelegateCredentials no
   GSSAPIKeyExchange no
```

클라이언트측 설정파일



ssh를 이용한 원격접속

/etc/ssh/sshd_config

```
[root:~, 29]# cat<u>/etc/ssh/sshd config</u>
       $OpenBSD: sshd config.v 1.80 2008/07/02 02:24:18 djm Exp $
# This is the sshd server system-wide configuration file. See
# sshd config(5) for more information.
# This sshd was compiled with PATH=/usr/local/bin:/bin:/usr/bin
# The strategy used for options in the default sshd_config shipped with
# OpenSSH is to specify options with their default value where
# possible, but leave them commented. Uncommented options change a
# default value.
#Port 22
#AddressFamily anv
# istenAddress 0.0.0.0
# istenAddress ::
# Disable legacy (protocol version 1) support in the server for new
# installations. In future the default will change to require explicit
# activation of protocol 1
Protocol 2
# HostKey for protocol version 1
#HostKev /etc/ssh/ssh host kev
# HostKeys for protocol version 2
```

서버측 설정파일



ssh를 이용한 원격접속

ssh IP주소

```
[root:~, 30]# ssh 117.17.73.201
root@117.17.73.201's password:
Last login: Sun Jan 22 21:11:39 2017 from 117.17.73.205
[root@localhost ~]#
```

ssh을 이용하여 원격접속 (143에서 201로)



ssh를 이용한 원격접속

ssh 니 IP주소

[root:~, 34]#_ssh_-L_root_117.17.73.201 root@117.17.73.201's password: Last login: Sun Jan 22 21:27:20 2017 from 117.17.73.143 [root@localhost ~]#

> <u>지정한 사용자로 원격접속</u> (143에서 201로)



telnet을 이용한 원격접속

telnet IP주소

```
[root:~, 20]#_telnet 117.17.73.201
Trying 117.17.73.201...
Connected to 117.17.73.201.
Escape character is '^]'.
CentOS release 6.1 (Final)
Kernel 2.6.32-131.0.15.el6.i686 on an i686
login: dasol
Password:
Last login: Sun Jan 22 22:19:17 from 117.17.73.143
[dasol@localhost ~]$
```

<u>telnet을 이용하여 원격접속</u> (143에서 201로)



telnet을 이용한 원격접속

telnet -l

```
[root:~, 48]# telnet -I dasol 117.17.73.201
Trying 117.17.73.201...
Connected to 117.17.73.201.
Escape character is '^]'.
Password:
Last login: Sun Jan 22 22:19:34 from 117.17.73.143
[dasol@host ~]$
```

지정한 계정명으로 원격접속



원격파일복사

```
scp
```

```
[ds1556:~, 5]$ Is
ass_t22.c book.c
ass_t23.c dada
```

원격파일복사



원격파일복사

```
scp -r
  [ds1556:~/winter, 13]$ Is
 a.out prac1.c prac2.c prac3.c prac4.c prac5.c prac6.c tree1.c
  [ds1556:~/winter, 14]$ pwd
 /home/ds-51/ds1556/winter
   [root@localhost ~]# Is
   anaconda-ks.cfg dada install.log install.log.syslog test test3
   [root@localhost ~]# scp -r 117.17.73.143:/home/ds-51/ds1556/winter .
   root@117.17.73.143's password:
                                                                0.3KB/s
   prac3.c
                                                   100%
                                                        304
                                                                         00:00
   prac1.c
                                                   100%
                                                        143
                                                                0.1KB/s
                                                                         00:00
                                                   100%
                                                        410
                                                                0.4KB/s
                                                                         00:00
   prac5.c
                                                   100% 5160
                                                                5.0KB/s
                                                                         00:00
   a.out
                                                                         00:00
                                                   100% 2447
                                                                2.4KB/s
   tree1.c
                                                                0.2KB/s
                                                                         00:00
   prac4.c
                                                   100% 168
                                                   100%
                                                        386
                                                                0.4KB/s
                                                                         00:00
   prac6.c
                                                   100%
   prac2.c
                                                        132
                                                                0.1KB/s
                                                                         00:00
   [root@localhost ~]# Is
```

<u>원격파일복사(디렉토리)</u>

anaconda-ks.cfg dada install.log install.log.syslog test test3 <u>winter</u>



원격로그인

slogin

```
[root@localhost ~]# slogin -1 ds1556 117.17.73.143 ds1556@117.17.73.143's password:
Last login: Mon Jan 23 16:10:35 2017 from 117.17.73.201 [ds1556:~, 1]$ [
```

<u>원격로그인</u>