DataBaseFns makes the construction and maintenance of MasterScope data bases essentially an automatic process.

DataBaseFns modifies the behavior of the Lisp functions MAKEFILE, LOAD and LOADFROM, such that writing out a file also updates and saves a MasterScope data base, and loading the file also loads the data base for you to use.

For example,

(LOAD 'FILE1)

loads FILE1, then looks for the corresponding data base file FILE1.DATABASE. If the data base exists, it is also loaded. The result is the same as if you had typed:

(LOAD 'FILE1)
.ANALYZE ALL ON FILE1

The data base will be maintained automatically for any file (containing functions) whose file name has the property DATABASE with value YES. Whenever such a file is dumped via MAKEFILE, MasterScope will analyze any new or changed functions on the file, and a data base for all of the functions on the file will be written on a separate file whose name is of the form FILE.DATABASE. Whenever a file that has a data base property with value YES is loaded via LOAD or LOADFROM, then the corresponding data base file, if any, is also loaded. The data base will not be dumped or loaded if the value of the DATABASE property for the file is NO. The DATABASE property is considered to be NO if the file is loaded with LDFLG = SYSLOAD.

If you change some of the functions defined in FILE1, and perhaps add new ones, then do:

(MAKEFILE 'FILE1)

Then FILE1 is written out. MasterScope analyzes all changed or new functions and writes FILE1.DATABASE, which contains MasterScope data for all functions on FILE1.

Requirements

MASTERSCOPE

Installation

Load MASTERCOPE.DFASL from the library, then load DATABASEFNS.LCOM.

User Interface

If DataBaseFns is loaded, the first LOAD of a file will ask if you want to load the corresponding data base:

(LOAD 'FILE1)

Do you want to load the data base for FILE1?

And MAKEFILEing a new file will ask if you want to save the data base:

(MAKEFILE 'FILE1)

Save the data base for FILE1?

Once you tell the system YES or NO for a particular file, it will remember and will not ask you again (until you load a new sysout).

Functions

You can set up default answers to these questions by means of the following variables:

LOADDBFLG

[Variable]

This controls whether you are asked before the data base file is loaded:

Yes Always try to load the data base when a file is loaded.

No Never try to load the data base when a file is loaded.

Ask (default) Ask whether to load the data base when a file is loaded.

SAVEDBFLG

[Variable]

This controls whether you are asked before the data base file is saved:

Yes Always try to save the data base when a file is saved.

No Never try to save the data base when a file is saved.

Ask (default) Ask whether to save the data base when a file is saved.

(DUMPDB FILE PROPFLG)

[Function]

Dumps a data base for *FILE* then sets the *DATABASE* property to YES, so that data base maintenance for *FILE* will subsequently be automatic.

(LOADDB FILE ASKFLG)

[Function]

Loads the file FILE.DATABASE if one exists. After the data base is loaded, the *DATABASE* property for *FILE* is set to YES, so that maintenance will be thereafter automatic.

Data base files include the date and full file name of the file to which they correspond. LOADDB will print out a warning

message if it loads a data base that does not correspond to the in-core version of the file, and will ask you if you approve.

Note: LOADDB is the only approved way of loading a data base. Attempting to LOAD a data base file will cause an error.