```
30-Jun-2022 22:42:02 {DSK}<users>kaplan>local>medley3.5>working-medley>sources>LLINTERP.
 File created:
;4
previous date:
               30-Jun-2022 18:04:04 {DSK}<users>kaplan>local>medley3.5>working-medley>sources>LLINTERP.;3
 Read Table:
               INTERLISP
    Package:
               INTERLISP
      Format:
                XCCS
 Copyright (c) 1981-1988, 1990-1992, 1994-1995 by Venue & Xerox Corporation.
 The following program was created in 1981 but has not been published
;; within the meaning of the copyright law, is furnished under license,
;; and may not be used, copied and/or disclosed except in accordance
;; with the terms of said license.
(RPAQQ LLINTERPCOMS
                                                                      : Compilation pre-requisites
       [(COMS
               (DECLARE%: EVAL@COMPILE DONTCOPY (FILES (LOADCOMP)
                                                          LLBASIC LLSTK LLCODE LLPARAMS ACODE)))
                                                                     ; Don't fontify these common functions
         ſΕ
            (SETO FNSLST
                  (LDIFFERENCE FNSLST
                          '(EVALV PROG SET SETQ RETURN GO QUOTE AND OR PROGN COND PROG1 FUNCTION EVAL APPLY]
                                                                      ; For calling interpreted functions
         (COMS
               (FNS \INTERPRETER \INTERPRETER1 \SETUP-COMPILED-CLOSURE-CALL \STKNAME))
                                                                     ; EVCALL ufn.
         (COMS
               (FNS \ENVCALL.UFN \SETUP-ENVIRONMENT-CALL))
         (COMS
                                                                      : recursive interpreter
               (FNS EVAL \EVALFORM \EVALFORMASLAMBDA \EVALOTHER APPLY APPLY* \CHECKAPPLY* \CKAPPLYARGS
                    DEFEVAL)
               (P (MOVD? 'APPLY* 'SPREADAPPLY*))
               (DECLARE%: DONTCOPY (MACROS .APPLY.))
               (COMS
                                                                      ; Free variable manipulation
                      (FNS EVALV \EVALV1 \EVALVAR BOUNDP SET \SETVAR SETQ \STKSCAN \SETFVARSLOT))
                                                                      ; PROG and friends
               (COMS
                      (FNS PROG \PROG0 \EVPROG1 RETURN GO EVALA \EVALA ERRORSET SI::ERRORSET-PRINT-FUNCTION))
               (COMS
                                                                     ; LET and friends -- need these in the init
                      (FNS LET LET* \LET0 \LET*))
               (FNS QUOTE AND OR PROGN COND \EVPROGN PROG1)
               (COMS (VARS (\DEFEVALFNS NIL)
                            (\EVALHOOK))
                      (SPECVARS *EVALHOOK*)
                      (ADDVARS (LAMBDASPLST LAMBDA NLAMBDA CL:LAMBDA OPENLAMBDA))
                      (GLOBALVARS \DEFEVALFNS \EVALHOOK LAMBDASPLST CLISPARRAY)
                      (DECLARE%: DONTEVAL@LOAD DOCOPY (VARS (CLISPARRAY))
                             (P (MOVD? 'SETQ 'SETN NIL T)))
                      (GLOBALVARS CLISPARRAY))
               [COMS
                                                                      ; Evaluating in different stack environment
                      (FNS ENVEVAL ENVAPPLY FUNCTION \FUNCT1 \MAKEFUNARGFRAME STKEVAL STKAPPLY RETEVAL RETAPPLY)
                                                                       For bootstrapping, IL:FUNCTION is as good as CL:FUNCTION
                      (DECLARE%: DONTEVAL@LOAD DOCOPY
                             (P (MOVD? 'FUNCTION 'CL:FUNCTION NIL T
                                                                      ; Blip and other stack funniness
               (COMS
                      (FNS BLIPVAL SETBLIPVAL BLIPSCAN)
                      (FNS \REALFRAMEP)
                      [INITVARS (OPENFNS '(APPLY* SETO AND OR COND SELECTO PROG PROGN PROG1 ARG SETARG ERSETO
                                                  NLSETQ RESETFORM RESETLST RESETVARS RPTQ SAVESETQ SETN UNDONLSETQ
                                                   XNLSETO1
                      (VARS \BLIPNAMES)
                      (GLOBALVARS BRKINFOLST)
                      (GLOBALVARS \BLIPNAMES OPENFNS)))
         (COMS (FNS
                    RAIDCOMMAND RAIDSHOWFRAME RAIDSTACKCMD RAIDROOTFRAME PRINTADDRS PRINTVA READVA READATOM
                    READOCT SHOWSTACKBLOCKS SHOWSTACKBLOCK1 PRINCOPY NOSUCHATOM)
               (FNS BACKTRACE \BACKTRACE \SCANFORNTENTRY \PRINTSTK \PRINTFRAME \PRINTBF)
               (DECLARE%: EVAL@COMPILE DONTCOPY (COMS * RAIDCOMS)))
         (COMS
               (FNS CCODEP EXPRP SUBRP FNTYP ARGTYPE NARGS ARGLIST \CCODEARGLIST \CCODEIVARSCAN)
               (COMS
                                                                      ; Translation machinery for new LAMBDA words
                      (PROP VARTYPE LAMBDATRANFNS)
                      (ALISTS (LAMBDATRANFNS)))
               (DECLARE%: DONTCOPY (MACROS \CCODENARGS \CCODEFNTYP \CCODEARGTYPE)))
                                                                     ; CONSTANTS mechanism
         (COMS
               (FNS CONSTANTS CONSTANTEXPRESSIONP)
               (INITVARS (COMPVARMACROHASH (HASHARRAY 100)))
                                                                      ; We need this initialized for the INIT, so don't put it off. (It used
                                                                      ; to start out NIL and get set later)
               (ADDVARS (CONSTANTFOLDENS PLUS IPLUS TIMES ITIMES DIFFERENCE IDIFFERENCE QUOTIENT IQUOTIENT IMIN
                                IMAX IABS LLSH LRSH LOGOR LOGXOR LOGAND OR AND))
               (GLOBALVARS COMPVARMACROHASH CONSTANTFOLDFNS))
         (DECLARE%: EVAL@COMPILE DONTCOPY DONTEVAL@LOAD (LOCALVARS . T))
         (SPECVARS *TAIL* *FN* *FORM* *ARGVAL*)
         (DECLARE%: EVAL@COMPILE DONTCOPY (ADDVARS (LAMS FAULTEVAL FAULTAPPLY)))
         (DECLARE%: DONTEVAL@LOAD DOEVAL@COMPILE DONTCOPY COMPILERVARS
                (ADDVARS (NLAMA CONSTANTS PROG1 COND PROGN OR AND QUOTE LET* LET GO PROG SETQ)
                        (NLAML FUNCTION RETURN)
```

(PROG1 (SETQ NTSIZE (CEIL [ADD1 (UNFOLD NA (CONSTANT (

WORDSPERQUAD))

WORDSPERNAMEENTRY

;; round number of nametable entries up to next quadword, leaving room for a zero. add in overhead. ;; NA is now in units of 'cells' since there two words in a cell.

```
(FOLDHI (fetch (FNHEADER OVERHEADWORDS) of T)
WORDSPERCELL)
(SUB1 CELLSPERQUAD))))
(GO ERR))
(NINTERPRETER1 ARGLIST NNILS NTSIZE NACTUAL NEXTRA FN DEF)))
```

```
{MEDLEY} < sources > LLINTERP.; 1 (\INTERPRETER cont.)
                                                                                                                                 Page 3
       FUN
     ;; FUNARG -- Interlisp "closure" of form (FUNARG fn stackptr). Subsumed by common lisp lexical closures.
             [RETURN (PROGN (\SMASHLINK NIL (\STACKARGPTR (CADDR DEF)))
                                (SPREADAPPLY (CADR DEF)
                                        (for I from 1 to (SUB1 N) collect (ARG N I]
        ERR (RETURN (FAULTAPPLY FN (for I from 1 to NACTUAL collect (ARG N I])
(\INTERPRETER1
           (ARGLIST NNILS NTSIZE NACTUAL NPVARARGS FN DEF)
  [LAMBDA
                                                                             ; Edited 27-Jan-91 12:48 by jds
    (PROG `((*TAIL* (CDDR DEF))
              (INTERPFRAME (\MYALINK))
              HEADER NT NILSTART)
             (SETQ HEADER (fetch (FX FNHEADER) of INTERPFRAME))
                                                                              ; The function header of code for \INTERPRETER
     ;; Build a nametable for INTERPFRAME that identifies the vars in ARGLIST as the NACTUAL IVAR's that were passed to it as arguments plus
     ;; the NPVARARGS extra NIL's that we implement as PVAR's. We build the nametable out of space that was allocated on the stack by
     ;; \INTERPRETER pushing many NIL's
             (SETQ NT (ADDSTACKBASE (CEIL (+ (SETQ NILSTART (- (fetch (FX NEXTBLOCK) of INTERPFRAME)
                                                                           (UNFOLD NNILS WORDSPERCELL)))
                                                    (UNFOLD NPVARARGS WORDSPERCELL))
                                                WORDSPERQUAD)))
     ;; Address of our synthesized nametable: NNILS cells back from the end of INTERPFRAME, leaving space for additional 'PVARs' we are using as
     ;; extra NIL args, rounded up to quadword
             (UNINTERRUPTABLY
                  [COND
                     ((NOT ARGLIST)
                                                                              ; No args, no nametable
                     ((LISTP ARGLIST)
                       (for arg in arglist as arg# from 0 as NT1 from (fetch (fnheader overheadwords) of T)
                          by (CONSTANT (WORDSPERNAMEENTRY)) as NT2 from (+ (fetch (FNHEADER OVERHEADWORDS)
                                                                                        of T)
                                                                                     NTSIZE)
                          by (CONSTANT (WORDSPERNTOFFSETENTRY))
                              (SETSTKNAME-RAW NT NT1 (\ATOMVALINDEX ARG))
                              [SETSTKNTOFFSET-RAW NT NT2 (COND
                                                                  ((< ARG# NACTUAL)
                                                                   IVARCODE)
                                                                               Say it's the nth PVAR, where n is out of the range of the real
                                                                   (T
                                                                              PVARs
                                                                     PVARCODE))
                                      (COND
                                          ((< ARG# NACTUAL)
                                           ARG#)
                                                                              ; Say it's the nth PVAR, where n is out of the range of the real
                                          (T
                                                                              PVARs
                                              (IPLUS (FOLDLO (- NILSTART (fetch (FX FIRSTPVAR) of INTERPFRAME))
                                                              WORDSPERCELL)
                                                                                SETSTKNTOFFSET-RAW NT NT2 (COND ((< ARG#
                                                      (- ARG# NACTUAL]
                                                                              NACTUAL) (+ IVARCODE ARG#)) (T; Say it's the nth PVAR, where n is out of the range of the real PVARs (+ PVARCODE; (FOLDLO (- NILSTART (fetch (FX FIRSTPVAR) of; INTERPFRAME)) WORDSPERCELL) (- ARG# NACTUAL)))))
                                                                              ; Note: area is initialize to NIL's (zero), so end of nametable
                                                                              ; already has its zeroes
                     (T
                                                                              ; Nospread. Store lone arg in nametable
                         (SETSTKNAME-RAW NT (fetch (FNHEADER OVERHEADWORDS) of T)
                                 (\ATOMVALINDEX ARGLIST))
                         (SETSTKNTOFFSET-RAW NT (+ (fetch (FNHEADER OVERHEADWORDS) of T)
                                                        NTSIZE)
                                 IVARCODE
                                 (COND
                                     ((EQ
                                           (CAR DEF)
                                           'NLAMBDA)
                                                                              ; It's the first (and only) arg
                                      0)
                                                                              ; Use the n+1'st arg, which currently is our framename (FN)
                                     (T
                                         (\PUTBASEPTR \STACKSPACE (+ (fetch (BF IVAR) of (fetch (FX BLINK) of INTERPFRAME)
                                                                           (UNFOLD NACTUAL WORDSPERCELL))
                                                 NACTUAL)
                                                                             ; set arg's value to be number of real args
                                        NACTUAL]
                 ;; now fix up header of NT
                  (replace (FNHEADER %#FRAMENAME) of NT with FN)
                                                                              ; use #FRAMENAME to denote no reference counting
                  (replace (FNHEADER NTSIZE) of NT with NTSIZE)
                  (replace (FNHEADER NLOCALS) of NT with (fetch (FNHEADER NLOCALS) of HEADER))
                                                                              Probably doesn't matter, since there are no FVARS in that
                                                                               frame
                                                                               Do I need to worry about STK, NA, PV, START, ARGTYPE?
                                                                               --- probably not
```

(replace (FX NAMETABLE) of INTERPFRAME with NT))

```
EVLP
     ;; Now that we have 'bound' the arguments, just evaluate the forms in the LAMBDA/NLAMBDA as progn
             (COND
                       *TAIL*)
                  (\EVAL (CAR *TAIL*))
(SETQ *TAIL* (CDR *TAIL*))
                  (GO EVLP))
                 (T (RETURN (\EVAL (CAR *TAIL*])
(\SETUP-COMPILED-CLOSURE-CALL
                                                                              (* bvm%: "21-Jul-86 11:12")
 Called in the misc context by \INTERPRETER when the function being called is a closure. Replace the interpreter frame by the frame that would result if we had correctly called the closure in microcode. This is a normal function call of the code body in the closure with the one additional wrinkle that
::: the CLOSURE object is stored in PVAR1.
    (LET ((INTERPFRAME (fetch (IFPAGE MiscFXP) of \InterfacePage))
            (CODE (fetch (COMPILED-CLOSURE FNHEADER) of CLOSURE))
           NA NACTUALS INTERPEF INTERPIVAR INTERPALINK INTERPCLINK SP NEWFX NPVARS STKEND SLOWP OLDBF ENV)
(SETQ OLDBF (SETQ INTERPBF (fetch (FX BLINK) of INTERPFRAME)))
           (SETQ INTERPIVAR (fetch (BF IVAR) of INTERPBF))
                                                                              ; Note that this is the 'raw' ALINK -- we never look at it, just
           (SETQ INTERPALINK (fetch (FX %#ALINK) of INTERPFRAME))
                                                                              ; update it in new FX
           [ COND
               ((SETQ SLOWP (fetch (FX SLOWP) of INTERPFRAME))
               ;; Usually false, because \INTERPRETER hasn't had any reason to make itself slow. But it's not uninterruptable, so arbitrary things
               ;; could happen to it
                (SETQ INTERPCLINK (fetch (FX %#CLINK) of INTERPFRAME]
           (SETQ STKEND (fetch (FX NEXTBLOCK) of INTERPFRAME))
           [COND
              ((fetch (BF PADDING) of INTERPBF)
                                                                               Forget padding. I don't think anyone pads anymore, except
                                                                               ; maybe Lisp stack mungers
                 SETQ INTERPBF (IDIFFERENCE INTERPBF WORDSPERCELL]
           (SETQ NACTUALS (FOLDLO (IDIFFERENCE INTERPBF INTERPIVAR)
                                      WORDSPERCELL))
           (SETQ NA (fetch (FNHEADER NA) of CODE))
               ((OR SLOWP (ILESSP (IDIFFERENCE STKEND INTERPBF)
                                     (fetch (FNHEADER STKMIN) of CODE)))
               ;; No space for frame, or interpreter frame is slow, do slow case. This computation is quite conservative, since we aren't counting the
               ;; args
                (LET ((NEWSTACK (\FREESTACKBLOCK (IPLUS (fetch (FNHEADER STKMIN) of CODE)
                                                                 (UNFOLD NACTUALS WORDSPERCELL))
                                            INTERPFRAME)))
                      (SETQ STKEND (IPLUS NEWSTACK (fetch (FSB SIZE) of NEWSTACK)))
                      [while (type? FSB STKEND) do (SETQ STKEND (add STKEND (fetch (FSB SIZE) of STKEND]
                             (ADDSTACKBASE NEWSTACK)
                              (ADDSTACKBASE INTERPIVAR)
                             (UNFOLD NACTUALS WORDSPERCELL))
                      (SETQ INTERPBF (IPLUS NEWSTACK (UNFOLD NACTUALS WORDSPERCELL)))
                      COND
                          ((NEQ (fetch (FX USECNT) of INTERPFRAME)
                           (add (fetch (FX USECNT) of INTERPFRAME)
                          (T [COND
                                 ((NEQ (fetch (BF USECNT) of OLDBF)
                                  (add (fetch (BF USECNT) of OLDBF)
                                                                               ; Normal slow case, can flush BF
                                     (\MAKEFREEBLOCK INTERPIVAR (IPLUS
                                                                              (IDIFFERENCE OLDBF INTERPIVAR)
                                                                              WORDSPERCELL]
                                                                              ; Finally, flush FX. Has to be separate free block because FX
                                                                              ; and BF not necessarily contiguous
                             (LET [(START (COND
                                                 ((EQ OLDBF (fetch (FX DUMMYBF) of INTERPFRAME))
                                                                              ; Normal contiguous case
                                                  INTERPFRAME)
                                                                              ; Have to blow away the dummy BF in front of the FX
                                                 (T
                                                     (fetch (FX DUMMYBF) of INTERPFRAME]
                                    (\MAKEFREEBLOCK START (IDIFFERENCE (fetch (FX NEXTBLOCK) of INTERPFRAME)
                                                                       START]
                      (SETQ INTERPIVAR NEWSTACK)
                      (SETQ SLOWP T]
           [PROGN
                                                                              ; Do argument adjustment. In general we should pop excess
                                                                              ; args, but there's really no need for that
                   (COND
                       ((GREATERP NA NACTUALS)
                                                                              : Push extra NILs for missing args
                        (FRPTQ (DIFFERENCE NA NACTUALS)
                                 (\PUTBASEPTR (STACKADDBASE INTERPBF)
                                         0 NIL)
```

```
(add INTERPBF WORDSPERCELL]
            (PROGN
                                                                                  Fix up BF trailer cell
                    (\PUTBASE \STACKSPACE INTERPBF 0)
                                                                                 ; Clear BF flags
                    (replace (BF IVAR) of INTERPBF with INTERPIVAR) (replace (BF FLAGS) of INTERPBF with \STK.BF)
                     (CHECK (fetch (BF CHECKED) of INTERPBF)))
            (PROGN
                    ;; Fix up FX header. Some of this work is redundant in the case where NEWFX is the same as the old, but in general we did some
                    ;; arg adjusting or did the slow case
                    (SETQ NEWFX (IPLUS INTERPBF WORDSPERCELL))
                    (\PUTBASE \STACKSPACE NEWFX 0)
                                                                                 ; Clear FX flags
                    (replace (FX FLAGS) of NEWFX with \STK.FX)
                    (replace (FX NOPUSH) of NEWFX with T)
                                                                                  ; When we return to the user context, don't want any value to
                                                                                 ; appear on stack
                    (COND
                        (SLOWP (replace (FX % #BLINK) of NEWFX with INTERPBF)
                                 (replace (FX %#CLINK) of NEWFX with (OR INTERPCLINK INTERPALINK))
                                 ;; If INTERPCLINK is NIL, the original frame was not SLOW, so ALINK = CLINK and INTERPALINK has its low bit off
                                 (replace (FX % #ALINK) of NEWFX with (LOGOR INTERPALINK 1)))
                    (T (replace (FX %#ALINK) of NEWFX with INTERPALINK)))
(replace (FX FNHEADER) of NEWFX with CODE)
                     (replace (FX PC) of NEWFX with (fetch (FNHEADER STARTPC) of CODE)))
           [PROGN
                                                                                 ; Initialize PVAR region
                    (SETQ SP (fetch (FX FIRSTPVAR) of NEWFX))
(SETQ NPVARS (UNFOLD (ADD1 (fetch (FNHEADER PV) of CODE))
                                              CELLSPERQUAD))
                    (COND
                        ((SETQ ENV (fetch (COMPILED-CLOSURE ENVIRONMENT) of CLOSURE))
                                                                                 ; Set first pvar to closure environment
                          (\PUTBASEPTR \STACKSPACE SP ENV)
                          (add SP WORDSPERCELL)
                          (add NPVARS -1)))
                    (RPTQ NPVARS (PROGN
                                                                                 ; Fill in rest of Pvar region with 'unbound'
                                             (\PUTBASE \STACKSPACE SP 65535)
                                             (add SP WORDSPERCELL]
            (PROGN
                                                                                 ; Make free block after this frame
                    (replace (FX NEXTBLOCK) of NEWFX with (add SP (fetch (FX PADDING) of NEWFX)))
                                                                                 ; Need extra junk quad after the pvar region
                    (\MAKEFREEBLOCK SP (IDIFFERENCE STKEND SP))
                    (CHECK (fetch (FX CHECKED) of NEWFX)))
            (replace (IFPAGE MiscFXP) of \InterfacePage with NEWFX])
(\STKNAME
                                                                                 ; Edited 27-Jan-91 14:20 by jds
   [LAMBDA (POS)
     ;; Get the frame name from the stack frame at POS. If that's an interpreter frame, get it's caller's frame name.
     (LET ((NAME (fetch (FX FRAMENAME) of POS))) (if (EQ NAME '\INTERPRETER)
                then [\GETBASEPTR \STACKSPACE (LET ((BFLINK (fetch (FX BLINK) of POS))))
                                                            (+ (fetch (BF IVAR) of BFLINK)
(TIMES (CL:1- (fetch (BF NARGS) of BFLINK))
                                                                         WORDSPERCELL1
              else NAME])
;; EVCALL ufn.
(DEFINEO
(\ENVCALL.UFN
  [LAMBDA (\INTERRUPTABLE)
                                                                                 ; Edited 18-Apr-88 18:25 by bvm
     (\MISCAPPLY* (FUNCTION \SETUP-ENVIRONMENT-CALL])
(\SETUP-ENVIRONMENT-CALL
                                                                                 ; Edited 4-Aug-88 11:39 by bvm
  [LAMBDA NIL
;;; Called in the misc context by ufn for ENVCALL, a variant on APPLYFN that takes on the stack: ..args.. #args codeblock environment. Replace the ufn
;;; frame by the frame that would result if we had correctly done the call in microcode. This is a normal function call of the codeblock with the one
;;; additional wrinkle that the environment is stored in PVAR0.
     (\textbf{LET}^* ((UFNFX (\textbf{fetch} (IFPAGE MiscFXP) \textbf{of} \InterfacePage))
              (UFNNEXT (fetch (FX NEXTBLOCK) of UFNFX))
              (UFNBF (fetch (FX BLINK) of UFNFX))
              (UFNIVAR (fetch (BF IVAR) of UFNBF))
(CALLER (fetch (FX CLINK) of UFNFX))
             (CALLNEXT (fetch (FX NEXTBLOCK) of CALLER))

CODE ENV NA NACTUALS STKEND SLOWP LOCNARGS FREESIZE NEEDEDSIZE ARGSTART NEWSTACK IVAR)
            [SETQ LOCNARGS (STACKADDBASE (- CALLNEXT (UNFOLD 3 WORDSPERCELL]
                                                                                 ; Location in caller's stack of number of args, followed by
                                                                                  CODEBLOCK and ENV
             (SETQ NACTUALS (\GETBASEPTR LOCNARGS 0))
                                                                                 ; Fetch nargs, codeblock and environment from caller's stack
             (SETQ ENV (\GETBASEPTR LOCNARGS 4))
```

```
(SETQ CODE (\GETBASEPTR LOCNARGS 2))
(SETQ NA (fetch (FNHEADER NA) of CODE))
                                                                 ; Number args expected
(SETQ NEEDEDSIZE (fetch (FNHEADER STKMIN) of CODE))
(SETQ ARGSTART (- CALLNEXT (UNFOLD (+ NACTUALS 3)
                                         WORDSPERCELL)))
                                                                 ; Address of first argument to function
          (> NACTUALS NA)
          (>= NA 0))
    then
                                                                 ; More args than expected. No need to retain/copy them (and it's
                                                                 ; best not to, since STKMIN calculation assumes expected args,
                                                                 ; not lots more)
          (SETQ NACTUALS NA))
(if (AND
          (if (EQ UFNBF (fetch (FX DUMMYBF) of UFNFX))
              then
                                                                 ; BF and FX contiguous
            else
                                                                 ; Yecch. Non-contiguous BF and FX. Toss the BF and do slow
                                                                 : case
                  (\MAKEFREEBLOCK UFNIVAR (+ WORDSPERCELL
                                                                 (- UFNBF UFNIVAR)))
                  (SETQ UFNIVAR (fetch (FX DUMMYBF) of UFNFX))
                                                                 ; For next \makefreeblock -- have to blow away this dummybf
                 NTT.)
          (EQ UFNIVAR CALLNEXT)
          PROGN
                                                                 : Caller contiguous with ufn frame
                   (SETQ FREESIZE (- UFNNEXT UFNIVAR))
                                                                  Add up the lengths of all the contiguous free blocks
                   (bind SZ while (type? FSB UFNNEXT) do
                                                              (add FREESIZE (SETQ SZ (fetch (FSB SIZE) of UFNNEXT)))
                                                              (add UFNNEXT SZ))
                  (> FREESIZE NEEDEDSIZE)))
    then
                                                                 ; Normal case: there's enough space to build the frame on top of
                                                                  ufn frame. Args are already there (we will lop them from
                                                                 ; caller's frame), so no copying to do.
          (SETQ STKEND UFNNEXT)
          (SETQ NEWSTACK ARGSTART)
                                                                  Have to make a discontinuous frame elsewhere
  else
       (\MAKEFREEBLOCK UFNIVAR (- UFNNEXT UFNIVAR))
                                                                  Discard ufn frame (and dummy bf before it in the
                                                                  non-contiguous case)
       (SETQ NEWSTACK (\FREESTACKBLOCK (+ NEEDEDSIZE
                                                              (UNFOLD NACTUALS WORDSPERCELL))
                                                                  Get a free block big enough for fn plus the args we'll have to
                                  UFNIVAR))
                                                                  copy
       (SETQ STKEND (+ NEWSTACK (fetch (FSB SIZE) of NEWSTACK)))
              (STACKADDBASE NEWSTACK)
               (STACKADDBASE ARGSTART)
              (UNFOLD NACTUALS WORDSPERCELL))
                                                                  Copy args to new frame
       (\MAKEFREEBLOCK ARGSTART (- CALLNEXT ARGSTART))
                                                                 ; Free up space taken in caller by args
       (SETQ SLOWP T))
(SETQ IVAR NEWSTACK)
(add NEWSTACK (UNFOLD NACTUALS WORDSPERCELL))
(replace (FX NEXTBLOCK) of CALLER with ARGSTART)
                                                                 ; Shorten caller's frame to account for args removed
(if (>= NA 0)
    then
                                                                 ; Fill in NIL for defaulted args
          (RPTO
                 (- NA NACTUALS)
                 (\PUTBASEPTR (STACKADDBASE NEWSTACK)
                         0 NTT.)
                 (add NEWSTACK WORDSPERCELL)))
(PROGN
                                                                 ; Fix up BF trailer cell
        (\PUTBASE (STACKADDBASE NEWSTACK)
        0 \STK.BF.WORD)
(replace (BF IVAR) of NEWSTACK with IVAR)
(CHECK (fetch (BF CHECKED) of NEWSTACK)))
                                                                 : Clear BF flags
(PROGN
        ;; Now build the FX header
        (add NEWSTACK WORDSPERCELL)
        (\PUTBASE (STACKADDBASE NEWSTACK)
                (LLSH \STK.FX \STK.FLAGS.SHIFT))
                                                                  Clear FX flags
        (replace (FX NOPUSH) of NEWSTACK with T)
                                                                  When we return to the user context, don't want any value to
                                                                  appear on stack
        [LET ((ALINK (+ CALLER \#ALINK.OFFSET)))
                                                                  ALINK field for fast case
              (COND
                                                                 ; Have to make non-contiguous frame slow. Set each piece
                  (SLOWE
                                                                  manually to avoid redundant computation from the computed
                                                                  record fields
                          (replace (FX %#BLINK) of NEWSTACK with (fetch (FX DUMMYBF) of NEWSTACK))
                          (replace (FX %#CLINK) of NEWSTACK with ALINK)
                          (replace (FX %#ALINK) of NEWSTACK with (LOGOR ALINK 1))
                                                                 ; 1 is the slow bit
                  (T (replace (FX %#ALINK) of NEWSTACK with ALINK]
        (replace (FX FNHEADER) of NEWSTACK with CODE)
        (replace (FX PC) of NEWSTACK with (fetch (FNHEADER STARTPC) of CODE)))
[LET ((SP (fetch (FX FIRSTPVAR) of NEWSTACK))
(NPVARS (UNFOLD (ADD1 (fetch (FNHEADER PV) of CODE))
                         CELLSPERQUAD)))
      ;; Fill in rest of FX
```

```
{MEDLEY}<sources>LLINTERP.;1 (\SETUP-ENVIRONMENT-CALL cont.)
                                                                                                                             Page 7
                 [PROGN
                                                                            ; Initialize PVAR region
                          (if ENV
                              then
                                                                            ; Set first pvar to closure environment
                                    (\PUTBASEPTR (STACKADDBASE SP)
                                            0 ENV)
                                    (add SP WORDSPERCELL)
                                    (SETQ NPVARS (SUB1 NPVARS)))
                          (RPTQ NPVARS (PROGN
                                                                            ; Fill in rest of Pvar region with 'unbound'
                                                 (\PUTBASE (STACKADDBASE SP)
                                                         0 65535)
                                                 (add SP WORDSPERCELL]
                 (PROGN
                                                                            ; Make free block after this frame
                          (replace (FX NEXTBLOCK) of NEWSTACK with (add SP (fetch (FX PADDING) of NEWSTACK)))
                                                                            ; Need extra junk quad after the pvar region
                          (CHECK (> STKEND SP))
                          (\MAKEFREEBLOCK SP (- STKEND SP))
                          (CHECK (fetch (FX CHECKED) of NEWSTACK]
            (replace (IFPAGE MiscFXP) of \InterfacePage with NEWSTACK])
;; recursive interpreter
(DEFINEQ
(EVAL
  [LAMBDA (U \INTERNAL)
(DECLARE (SPECVARS \INTERNAL))
                                                                            (* lmm "19-AUG-81 23:04")
     (\EVAL U])
(\EVAL
  [LAMBDA (FORM)
                                                                            (* lmm " 3-NOV-81 15:42")
    ;; ufn for Interlisp EVAL opcode.
     (COND
        ((LISTP FORM)
         (\EVALFORM FORM))
        ((LITATOM FORM)
         (\EVALVAR FORM))
        ((NUMBERP FORM)
         FORM)
        (T (\EVALOTHER FORM])
(\EVALFORM
  [LAMBDA (*FORM* TEMP)
(DECLARE (SPECVARS *FORM*)
             (ADDTOVAR LAMS FAULTEVAL))
                                                                            ; Edited 29-Jun-87 16:42 by amd
;;; eval of LISTP
     (PROG NIL
             [COND
                 ((LITATOM (SETQ TEMP (CAR *FORM*)))
                  COND
                     ((fetch (LITATOM CCODEP) of TEMP)
                      (SELECTO (fetch (LITATOM ARGTYPE) of TEMP)
(1 (GO NLSPREAD))
(3 (GO NLNOSPREAD))
                            (GO EVLAM)))
                                                                            ; EXPR OR UDF
                     (T
                         (SETQ TEMP (fetch (LITATOM DEFPOINTER) of TEMP]
                                                                            ; TEMP is now definition of EXPR
             (CL:TYPECASE TEMP
                                                                            ; falls out
                  ((OR COMPILED-CLOSURE CLOSURE)
                 (CONS (SELECTQ (CAR TEMP)
```

;; THIS FUNCTION'S DEFINITION VERY DEPENDENT ON THE SPECIAL MACRO IN ALAP FOR COMPILING IT. --- SEE CEVALFORM

((OR (LISTP (SETQ TEMP (CADR TEMP)))
(NULL TEMP))

((CL:LAMBDA LAMBDA OPENLAMBDA))

(GO NLSPREAD)) (T (GO NLNOSPREAD))))

(NLAMBDA (COND

(GO FAULT)))

(T (GO FAULT)))

E.V.T.AM

(ARG U 2) (ARG U 3) (ARG U 4)))

(SPREADAPPLY (ARG U 1)

```
{MEDLEY} < sources > LLINTERP.; 1 (APPLY* cont.)
                                                                                                                                   Page 9
                                       (for I from 2 to U collect (ARG U I]
        FAULT
             [RETURN (FAULTAPPLY DEF (for I from 2 to U collect (ARG U I]
        NOSPR
                                                                                ; NLAMBDA*
              (RETURN (SPREADAPPLY* (ARG U 1)
                                 (for I from 2 to U collect (ARG U I])
(\CHECKAPPLY*
                                                                                (* bvm%: " 7-Jul-86 17:13")
  [LAMBDA (FN)
;;; APPLY* compiles open as: [PUSH each arg, PUSH #args, PUSH FN, CHECKAPPLY*, APPLYFN] CHECKAPPLY* should merely return FN in the ;;; case where FN is a LAMBDA or a NLAMBDA spread. The only case it needs to handle special is NLAMBDA nospread.
     \begin{array}{cc} (\textbf{PROG} & (\;(\texttt{DEF} \;\;\texttt{FN})\;) \\ & [\,\textbf{COND} \,\; \end{array}
                 [(LITATOM DEF)
                  COND
                        (NOT (fetch (LITATOM CCODEP) of DEF)) (SETQ DEF (fetch (LITATOM DEFPOINTER) of DEF)))
                                                                                : EXPR
                      ((NOT
                      ((EQ (fetch (LITATOM ARGTYPE) of DEF)
                       (GO NOSPR))
                      (T (RETURN FN]
                 ((AND NIL (TYPEP DEF 'COMPILED-CLOSURE))
                  ;; Give a symbol this definition so APPLYFN can call it. This is an utter kludge. It can never work with preemptive scheduling, and
                  ;; even without it is vulnerable to an interrupt between CHECKAPPLY* and APPLYFN
                  (\PUTD '*\CHECKAPPLY*\HACK DEF)
(RETURN '*\CHECKAPPLY*\HACK]
             (COND
                 ((AND (LISTP DEF)
                         (EQ (CAR DEF)
'NLAMBDA)
                         (LISTP (SETQ DEF (CDR DEF)))
                         (CAR DEF)
                         (NLISTP (CAR DEF)))
                  (GO NOSPR))
                 (T (RETURN FN)))
        NOSPR
              (RETURN (LIST 'LAMBDA NIL (LIST 'QUOTE (SPREADAPPLY* FN (\CKAPPLYARGS])
(\CKAPPLYARGS
  [LAMBDA NIL
                                                                                (* lmm "10-NOV-81 22:26")
     (PROG ((FRAME (fetch (FX ALINK) of (\MYALINK)))
              ACNT PTR VAL)
              [SETQ ACNT (STACKGETBASEPTR (SETQ PTR (IDIFFERENCE (fetch (FX NEXTBLOCK) of FRAME)
                                                                      WORDSPERCELL1
             (CHECK (SMALLPOSP ACNT))
             [FRPTO ACNT (push VAL (STACKGETBASEPTR (SETQ PTR (IDIFFERENCE PTR WORDSPERCELL]
             (RETURN VAL])
(DEFEVAL
                                                                                (* edited%: "13-DEC-78 23:18")
  [LAMBDA (TYPE FN)
     (PROG ((F (FASSOC TYPE \DEFEVALFNS)))
             COND
                    (SETQ \DEFEVALFNS (DREMOVE F \DEFEVALFNS]
             COND
                 (FN (SETQ \DEFEVALFNS (CONS (CONS TYPE FN)
                                                    \DEFEVALFNS]
             (RETURN (CDR F])
(MOVD? 'APPLY* 'SPREADAPPLY*)
(DECLARE%: DONTCOPY
(DECLARE%: EVAL@COMPILE
(PUTPROPS .APPLY. MACRO [(U V)
                                                                               (* body for APPLY, used by RETAPPLY too)
                                (PROG ((DEF U))
                                        COND
                                   LP
                                            ((LITATOM DEF)
                                              COND
                                                 ((NOT (fetch (LITATOM CCODEP) of DEF))
                                                                                (* ÉXPR)
                                                  (SETQ DEF (fetch (LITATOM DEFPOINTER) of DEF)))
                                                 ((EQ (fetch (LITATOM ARGTYPE) of DEF)
                                                  (GO NLSTAR))
                                                 (T (GO NORMAL]
                                        COND
```

((LISTP DEF)

```
(SELECTQ (CAR DEF)
                                                (NLAMBDA (AND
                                                                (NLISTP (CADR DEF))
                                                                 (CADR DEF)
                                                                 (GO NLSTAR)))
                                                (FUNARG (SETQ DEF (CADR DEF))
                                                         (GO LP))
                                               NIL))
                                         ((NULL DEF)
                                          (RETURN (FAULTAPPLY U V]
                                 NORMAL
                                      (RETURN (SPREADAPPLY U V))
                                 NLSTAR
                                                                           (* NLAMBDA*)
                                      (RETURN (SPREADAPPLY* U V])
;; Free variable manipulation
(DEFINEQ
(EVALV
  [LAMBDA (VAR POS RELFLG)
                                                                           (* lmm " 6-Apr-84 16:37")
    ;; EVAL of a LITATOM without uba error
        (POS (\SMASHLINK NIL (\STACKARGPTR POS]
            (\EVALV1 VAR)
     (PROG1
         (COND
             (RELFLG (RELSTK POS))))])
(\EVALV1
  [LAMBDA (VAR)
                                                                          (* lmm "24-DEC-81 00:08")
     (COND
        ((\mathbf{OR} (NULL (\DTEST VAR 'LITATOM))
              (EQ VAR T))
         VAR)
        (T (\GETBASEPTR (\STKSCAN VAR)
                   01)
(\EVALVAR
                                                                           ; Edited 30-Jan-87 13:28 by Pavel
  [LAMBDA (VAR)
    :; EVAL of a LITATOM
    (COND
        ((OR (NULL VAR)
              (EQ VAR T))
         VAR)
        (T (LET ((VP (\STKSCAN VAR))
                  VAL)
                  (COND
                     ((EQ (SETQ VAL (\GETBASEPTR VP 0))
                           NOBIND)
                                                                           ; Value is NOBIND, even if it was not found as the top-level
                                                                           ; value. This is consistent with BOUNDP.
                      (FAULTEVAL VAR))
                     (T VAL])
(BOUNDP
  [CL:LAMBDA (CL::VAR)
                                                                           ; Edited 30-Jan-87 16:59 by Pavel
          ;; True if VAR is bound or has top level value
          (AND (CL:SYMBOLP CL::VAR)
                 (NOT (EQ (\GETBASEPTR (\STKSCAN CL::VAR)
                                   0)
                           'NOBIND])
(SET
                                                                           (* lmm "24-FEB-82 16:11")
  [LAMBDA (VAR VALUE)
     COND
        ((NULL VAR)

(AND VALUE (LISPERROR "ATTEMPT TO SET NIL OR T" VALUE)))

(T (PROG [(VP (\STKSCAN (\DTEST VAR 'LITATOM]
                    COND
                       ((EQ (\HILOC VP)
                             \STACKHI)
                        (\PUTBASEPTR VP 0 VALUE))
                       ((EQ VAR T)
(OR (EQ VALUE T)
                             (LISPERROR "ATTEMPT TO SET NIL OR T" VALUE)))
                          (\RPLPTR VP 0 VALUE)))
                    (RETURN VALUE])
```

```
(\SETVAR
  [LAMBDA
          (VAR VALUE)
                                                                        (* lmm "24-FEB-82 16:11")
    (COND
        (AND VALUE (LISPERROR "ATTEMPT TO SET NIL OR T" VALUE)))
        (T (PROG [ (VP (\STKSCAN (\DTEST VAR 'LITATOM]
                   (COND
                      ((EQ (\HILOC VP)
                            \STACKHI)
                       (\PUTBASEPTR VP 0 VALUE))
                      ((EQ VAR T)
                       (OR (EQ VALUE T)
                            (LISPERROR "ATTEMPT TO SET NIL OR T" VALUE)))
                          (\RPLPTR VP 0 VALUE)))
                   (RETURN VALUE])
(SETQ
  [NLAMBDA U
                                                                        (* lmm "24-DEC-81 00:19")
    (\SETVAR (CAR U)
            (PROG ((*TAIL* (CDR U)))
(DECLARE (SPECVARS
                                          *TAIL*))
                    (RETURN (PROG1 (\EVAL (CAR *TAIL*))
                                  [PROG NIL
                                                                        ; (SETQ X Y + 3) must try to eval + in order to get dwim involved.
                                          (COND
                                     LΡ
                                             ((LISTP (SETQ *TAIL* (CDR *TAIL*)))
(\EVAL (CAR *TAIL*))
                                               (GO LP])])
(\STKSCAN
                                                                        ; Edited 27-Oct-2021 20:51 by larry
  [LAMBDA (VAR)
                                                                        ; Edited 27-Jan-91 14:48 by jds
    ;; Returns pointer to place where VAR is bound
    (PROG ((FX (fetch (FX ALINK) of (\MYALINK)))
             (ATOM# (\ATOMVALINDEX VAR))
            NTSIZE A VARINFO PVAROFFSET NT FVAR)
       FRAMELP
           [COND
               ((fetch (FX INVALIDP) of FX)
                                                                        ; Reached top of stack without finding a binding
                (RETURN (\VALCELL VAR]
            (SETQ NT (fetch (FX NAMETABLE) of FX))
            (SETQ NTSIZE (fetch (FNHEADER NTSIZE) of NT))
            (SETQ NT (\ADDBASE NT (fetch (FNHEADER OVERHEADWORDS) of T)))
       TABLELP
            COND
               ((EQP (SETQ A (GETNAMEENTRY NT 0))
                                                                        ; End of name table
                (GO ENDTABLE))
               ((EOP A ATOM#)
                                                                        ; Found ATOM#. See if it is really bound here
                (SELECTC (NTSLOT-VARTYPE (SETQ VARINFO (GETNTOFFSETENTRY NT NTSIZE)))
                                                                        ; Is bound in BF
                     (TVARCODE
                                                                        IVAR
                                 [\textbf{RETURN} \text{ (stackaddbase (iplus (unfold (\loloc (ntslot-offset varinfo)))}\\
                                                                          WORDSPERCELL)
                                                                   (fetch (BF IVAR) of (fetch (FX BLINK) of FX])
                     (PVARCODE
                                                                        ; Local may or may not be bound yet
                                 (SETQ PVAROFFSET (IPLUS (UNFOLD (\LOLOC (NTSLOT-OFFSET VARINFO))
                                                                    WORDSPERCELL)
                                                            (fetch (FX FIRSTPVAR) of FX)))
                                 COND
                                    ((fetch (PVARSLOT BOUND) of (STACKADDBASE PVAROFFSET))
                                                                        ; PVAR
                                     (RETURN (STACKADDBASE PVAROFFSET])
                                                                        ; If FVAR is looked up, we can use it.
                     (FVARCODE
                                 [SETQ FVAR (ADDSTACKBASE (IPLUS (UNFOLD (\LOLOC (NTSLOT-OFFSET VARINFO))
                                                                             WORDSPERCELL)
                                                                     (fetch (FX FIRSTPVAR) of FX]
                                    ((fetch (FVARSLOT LOOKEDUP) of FVAR)
                                     (SETQ FVAR (fetch (FVARSLOT BINDINGPTR) of FVAR))
                                     (RETURN FVAR))
                                    (T (GO ENDTABLE))))
                     (SHOULDNT]
            [SETQ NT (\ADDBASE NT (CONSTANT (WORDSPERNAMEENTRY]
            (GO TABLELP)
       ENDTABLE
            (SETQ FX (fetch (FX ALINK) of FX))
            (GO FRAMELP])
(\SETFVARSLOT
  [LAMBDA (VAR NEWBINDING)
                                                                        ; Edited 20-Feb-91 01:07 by ids
    ;; Sets the freevar binding slot of VAR in caller's frame to point at NEWBINDING
    (PROG ((FX (\MYALINK))
```

```
{MEDLEY} < sources > LLINTERP.; 1 (\SETFVARSLOT cont.)
                                                                                                                     Page 12
             (ATOM# (NEW-SYMBOL-CODE VAR (\ATOMVALINDEX VAR)))
             NTSIZE A VARINFO NT)
            (SETQ NT (fetch (FX NAMETABLE) of FX))
            (SETQ NTSIZE (fetch (FNHEADER NTSIZE) of NT))
            (SETQ NT (\ADDBASE NT (fetch (FNHEADER OVERHEADWORDS) of T)))
       TABLELP
            (COND
                ((NULL-NTENTRY (SETQ A (GETSTKNAMEENTRY NT 0)))
                                                                       : End of name table
                 (ERROR "Binding slot not found in caller's frame" VAR))
                ((AND (EQP A ATOM#)
                      (EQP (NTSLOT-VARTYPE (SETQ VARINFO (GETSTKNTOFFSETENTRY NT NTSIZE)))
                            FVARCODE))
                (replace (FVARSLOT BINDINGPTR) of (ADDSTACKBASE (IPLUS (UNFOLD (\LoLoC (NTSLOT-OFFSET VARINFO))
                                                                                   WORDSPERCELL)
                                                                            (fetch (FX FIRSTPVAR) of FX)))
                    with NEWBINDING)
                 (RETURN NEWBINDING)))
            [SETQ NT (\ADDBASE NT (CONSTANT (WORDSPERNAMEENTRY]
            (GO TABLELP])
)
;; PROG and friends
(DEFINEQ
(PROG
                                                                       ; Edited 21-Jan-91 18:33 by jds
  [NLAMBDA U
    ;; PROG unpacks the argument list and changes any EVAL type forms by evaluating the form and then smashing the name and value
    ;; NOTE --- this mechanism might confuse DWIM someday because the arguments inside the PROG are evaluated at a time when the PROG
    ;; frame is in a very funny state: the 'values' are the variables, and the variables are NIL
    (PROG ((NVARS 0)
             (VARLST (CAR U))
             NTSIZE NNILS)
            (for VAR in VARLST do
                                                                       ; Count number of vars to bind, check validity
                                   (COND
                                      ((OR (NULL (\DTEST (COND
                                                                ((LISTP VAR)
                                                                 (SETQ VAR (CAR VAR)))
                                                                (T VAR))
                                                           'LITATOM))
                                             (EQ VAR T))
                                        (LISPERROR "ATTEMPT TO BIND NIL OR T" VAR)))
                                   (add NVARS 1))
            (RETURN (.CALLAFTERPUSHINGNILS. (SETQ NNILS (IPLUS NVARS (SETQ NTSIZE
                                                                              (CEIL [ADD1 (UNFOLD NVARS (CONSTANT (
                                                                                                          WORDSPERNAMEENTRY
                                                                                     WORDSPEROUAD))
                                                                       (FOLDHI (fetch (FNHEADER OVERHEADWORDS)
                                                                                  of T)
                                                                              WORDSPERCELL)
                                                                       (SUB1 CELLSPERQUAD)))
                              (\PROG0 U U NNILS NVARS NTSIZE VARLST])
(\PROG0
           (*FIRSTTAIL* *TAIL* NNILS NVARS NTSIZE VARLST)
                                                                       ; Edited 27-Jan-91 14:32 by jds
  [T.AMRDA
     (DECLARE (SPECVARS *TAIL* *FIRSTTAIL*))
     (PROG NII
            [COND
                (VARLST
                       ;; Create a nametable inside progframe where PROG pushed all those nils
                       (PROG ((PROGFRAME (\MYALINK))
                                HEADER NT NILSTART)
                               (SETQ HEADER (fetch (FX FNHEADER) of PROGFRAME))
                               (SETQ NT (ADDSTACKBASE (CEIL (IPLUS (SETQ NILSTART (IDIFFERENCE (fetch (FX NEXTBLOCK
                                                                                                          of PROGFRAME)
                                                                                                 (UNFOLD NNILS
                                                                                                        WORDSPERCELL)))
                                                                        (UNFOLD NVARS WORDSPERCELL))
                                                               WORDSPERQUAD)))
                        ;; NT is address of our synthesized nametable: beginning of NIL's, not counting additional PVARs we are about to bind,
                        ;; rounded up to quadword
                               [for var in varlst as valueoff from nilstart by wordspercell
                                                                       ; evaluate initial values first
                                  do
                                      (COND
                                         ((LISTP VAR)
                                          (PUTBASEPTR \STACKSPACE VALUEOFF (\EVPROG1 (CDR VAR)
                                                                       ; then build NT
                               (UNINTERRUPTABLY
```

(for var in varlst as var# from (foldlo (idifference nilstart (fetch (fx firstpvar)

```
of PROGFRAME))
                                                                              WORDSPERCELL)
                                       as NT1 from (fetch (FNHEADER OVERHEADWORDS) of T) by (WORDSPERNAMEENTRY)
                                       as NT2 from (IPLUS (fetch (FNHEADER OVERHEADWORDS) of T)
                                                            NTSIZE)
                                           (CONSTANT (WORDSPERNTOFFSETENTRY))
                                       do [SETSTKNAME-RAW NT NT1 (\ATOMVALINDEX (COND
                                                                                         ((LISTP VAR)
                                                                                          (CAR VAR))
                                                                                         (T VAR]
                                           (SETSTKNTOFFSET-RAW NT NT2 PVARCODE VAR#))
                                    (replace (FNHEADER %#FRAMENAME) of NT with 'PROG)
                                    (replace (FNHEADER NTSIZE) of NT with NTSIZE)
                                                                         ; Do I need to worry about STK, NA, PV, START, ARGTYPE
                                                                         ; NLOCALS ? --- no
                                    (replace (FX NAMETABLE) of PROGFRAME with NT))]
       EVLP
            (COND
                ((NULL (SETQ *TAIL* (CDR *TAIL*)))
                 (RETURN NIL))
                (T (\EVAL (OR (LISTP (CAR *TAIL*))
                                (GO EVLP)))
                   (GO EVLP1)
(\EVPROG1
           (*TAIL*)
                                                                         (* lmm "14-MAY-80 13:00")
  [LAMBDA
    (DECLARE (SPECVARS *TAIL*))
(PROG1 (\EVAL (CAR *TAIL*))
[PROG NIL
            LP (COND
                    ((LISTP (SETQ *TAIL* (CDR *TAIL*)))
(\EVAL (CAR *TAIL*))
                      (GO LP])])
(RETURN
  [NLAMBDA
            (FORM)
     (DECLARE (LOCALVARS . T))
                                                                         (* bvm%: "10-Nov-86 18:22")
     (PROG ((MV (CL:MULTIPLE-VALUE-LIST (\EVAL FORM)))
             (FRAME (\MYALINK)))
            (COND
                ((EQ (fetch
                            (FNHEADER FRAMENAME) of (fetch (FX NAMETABLE) of FRAME))
                     (FUNCTION \PROG0))
                 (SETQ FRAME (fetch (FX CLINK) of FRAME))
                                                                         Its caller, i.e. PROG
                 (\SMASHRETURN NIL FRAME)
                                                                         : Make us return to PROG with this value
                 (RETURN (CL:VALUES-LIST MV))
                ([NOT (fetch (FX INVALIDP) of (SETQ FRAME (fetch (FX CLINK) of FRAME]
                 (GO LP))
                (T (LISPERROR "ILLEGAL RETURN"])
(GO
  [NLAMBDA U
                                                                         (* bvm%: "10-Nov-86 18:17")
    (PROG ((FRAME (\MYALINK))
             (LABEL (CAR U))
             GOTAIL FIRSTARG)
            [COND
       LΡ
                     (fetch (FNHEADER FRAMENAME) of (fetch (FX NAMETABLE) of FRAME))
                ((EQ
                     (FUNCTION \PROG0))
                 COND
                    ([SETQ GOTAIL (FMEMB LABEL (CDR (STACKGETBASEPTR (SETQ FIRSTARG (fetch (BF IVAR)
                                                                                                 of (fetch (FX BLINK)
                                                                                                       of FRAME]
                     ;; first argument of \PROG0 is the actual tail of the prog, which can contain the labels. Second argument is the 'current' *TAIL*
                     (STACKPUTBASEPTR (IPLUS FIRSTARG WORDSPERCELL)
                                                                          Reset *TAIL* in the \PROG0 frame
                             GOTAIL)
                      (\SMASHRETURN NIL FRAME)
                                                                         ; Fix it so we return to \PROG0 to continue evaluating after label
                     (RETURN NIL]
            (COND
                ([NOT (fetch (FX INVALIDP) of (SETQ FRAME (fetch (FX CLINK) of FRAME]
                (T (LISPERROR "UNDEFINED OR ILLEGAL GO" LABEL])
(EVALA
  [LAMBDA (X A)
                                                                         ; Edited 21-Jan-91 18:13 by jds
;;; Evaluate X after spreading alist A on stack
     (PROG ((NVARS 0)
             NTSIZE NNILS TMP)
            (for VAR in A do
                                                                        : Count number of vars to bind, check validity
                              (COND
                                 ((OR [NULL (SETQ TMP (\DTEST (CAR (\DTEST VAR 'LISTP))
'LITATOM]
```

```
(EQ TMP T))
                                 (LISPERROR "ATTEMPT TO BIND NIL OR T" TMP)))
                             (add NVARS 1))
            (RETURN (.CALLAFTERPUSHINGNILS. (SETQ NNILS (IPLUS NVARS (SETQ NTSIZE
                                                                            (CEIL [ADD1 (UNFOLD NVARS (CONSTANT (
                                                                                                       WORDSPERNAMEENTRY
                                                                                                                    1
                                                                                  WORDSPERQUAD))
                                                                     (FOLDHI (fetch (FNHEADER OVERHEADWORDS)
                                                                                of T)
                                                                            WORDSPERCELL)
                                                                     (SUB1 CELLSPERQUAD)))
                             (\EVALA NNILS NVARS NTSIZE X A])
(\EVALA
          (NNILS NVARS NTSIZE FORM ALIST)
                                                                     ; Edited 27-Jan-91 16:39 by jds
  [LAMBDA
    (PROG ((CALLER (\MYALINK))
            NILSTART NT HEADER)
     ;; Create a nametable inside CALLER where EVALA pushed all those nils
            (SETQ HEADER (fetch (FX FNHEADER) of CALLER))
                                                                      : The function header of code for EVALA
            (SETQ NT (ADDSTACKBASE (CEIL (IPLUS (SETQ NILSTART (IDIFFERENCE (fetch (FX NEXTBLOCK) of CALLER)
                                                                            (UNFOLD NNILS WORDSPERCELL)))
                                                   (UNFOLD NVARS WORDSPERCELL))
                                           WORDSPERQUAD)))
     ;; Address of our synthesized nametable: beginning of NIL's, not counting additional PVARs we are about to bind, rounded up to quadword
            (UNINTERRUPTABLY
                (for pair in alist as var# from (foldlo (idifference nilstart (fetch (fx firstpvar) of caller))
                                                        WORDSPERCELL)
                   as NT1 from (fetch (FNHEADER OVERHEADWORDS) of T) by (WORDSPERNAMEENTRY) as NT2
                   from (IPLUS (fetch (FNHEADER OVERHEADWORDS) of T)
                               NTSIZE)
                   by (constant (wordsperntoffsetentry)) as valueoff from nilstart by wordspercell
                   do (PUTBASEPTR \STACKSPACE VALUEOFF (CDR PAIR))
                       (SETSTKNAME-RAW NT NT1 (\ATOMVALINDEX (CAR PAIR)))
                       (SETSTKNTOFFSET-RAW NT NT2 PVARCODE VAR#))
                ;; now fix up header of NT
                (replace (FNHEADER %#FRAMENAME) of NT with 'EVALA)
                (replace (FNHEADER NTSIZE) of NT with NTSIZE)
                                                                     ; Do I need to worry about STK, NA, PV, START, ARGTYPE?
                                                                     ; --- probably not
                 replace (FX NAMETABLE) of CALLER with NT))
            (RETURN (\EVAL FORM])
(ERRORSET
  [LAMBDA (FORM FLAG)
                                                                     ; Edited 6-Mar-87 14:39 by amd
    ;; (proceed-case (handler-bind ...)), but open-coded to aviod a proceed-case literal
    (LET (SI::NLSETQ-VALUE)
          (*CONDITION-HANDLER-BINDINGS* (CL:IF FLAG
                                                                 *CONDITION-HANDLER-BINDINGS*
                                                                 (CONS '(CL:ERROR . SI::NLSETQHANDLER)
                                                                        *CONDITION-HANDLER-BINDINGS*))]
                           (DECLARE (SPECVARS SI::*NLSETQFLAG*))
(CL:CATCH *PROCEED-CASES*
                               (CL:SETQ SI::NLSETQ-VALUE (LIST (\EVAL FORM)))
                               :NORMAL))
                     : NORMAL)
              SI::NLSETQ-VALUE
              NIL)])
(SI::ERRORSET-PRINT-FUNCTION
  [LAMBDA (DATUM STREAM)
    (DECLARE (IGNORE DATUM))
                                                                     (* bvm%: "11-Nov-86 21:40")
    (PRIN1 "Unwind to ERRORSET" STREAM])
;; LET and friends -- need these in the init
(DEFINEO
(LET
  [NLAMBDA II
                                                                     ; Edited 21-Jan-91 18:14 by jds
    (DECLARE (LOCALVARS . T))
    ;; LET unpacks the argument list and changes any EVAL type forms by evaluating the form and then smashing the name and value
    (LET ((NVARS 0)
           (VARLST (CAR U))
           NTSIZE NNILS)
          (for VAR in VARLST do
                                                                     ; Count number of vars to bind, check validity
```

```
{MEDLEY} < sources > LLINTERP.; 1
                                (LET cont.)
                                                                                                                   Page 15
                                (COND
                                    ((OR (NULL (\DTEST (COND
                                                            ((LISTP VAR)
                                                             (SETQ VAR (CAR VAR)))
                                                            (T VAR))
                                                        'LITATOM))
                                          (EQ VAR T))
                                                "ATTEMPT TO BIND NIL OR T" VAR)))
                                     (LISPERROR
                                (add NVARS 1))
          (.CALLAFTERPUSHINGNILS. (SETQ NNILS (IPLUS NVARS (SETQ NTSIZE (CEIL [ADD1 (UNFOLD NVARS (CONSTANT
                                                                                                        WORDSPERNAMEENTRY
                                                                                                             1
                                                                                     WORDSPERQUAD))
                                                         (FOLDHI (fetch (FNHEADER OVERHEADWORDS) of T)
                                                                 WORDSPERCELL)
                                                         (SUB1 CELLSPEROUAD)))
                 (\LETO (CDR U)
                        NNILS NVARS NTSIZE VARLST])
(LET*
  INT.AMBDA II
    ({\sf DECLARE} (LOCALVARS . T))
                                                                      ; Edited 21-Jan-91 23:02 by ids
    ;; LET* unpacks the argument list and changes any EVAL type forms by evaluating the form and then smashing the name and value
    (LET* ((NVARS 0)
           (VARLST (CAR U))
           NTSIZE NNILS)
          (for VAR in VARLST do
                                                                      ; Count number of vars to bind, check validity
                                 (COND
                                    ((OR (NULL (\DTEST (COND
                                                             ((LISTP VAR)
                                                              (SETQ VAR (CAR VAR)))
                                                             (T VAR))
                                                        'LITATOM))
                                           (EQ VAR T))
                                      (LISPERROR "ATTEMPT TO BIND NIL OR T" VAR)))
                                 (add NVARS 1))
          (.CALLAFTERPUSHINGNILS. (SETQ NNILS (IPLUS NVARS (SETQ NTSIZE (CEIL [ADD1 (UNFOLD NVARS (CONSTANT
                                                                                                        WORDSPERNAMEENTRY
                                                                                                              1
                                                                                      WORDSPERQUAD))
                                                          (FOLDHI (fetch (FNHEADER OVERHEADWORDS) of T)
                                                                 WORDSPERCELL)
                                                          (SUB1 CELLSPERQUAD)))
                  (\LET* (CDR U)
                        NNILS NVARS NTSIZE VARLST])
(\LET0
          (*TAIL* NNILS NVARS NTSIZE VARLST)
  [ T.AMBDA
    (DECLARE (LOCALVARS . T)
                                                                      : Edited 27-Jan-91 14:35 by ids
           (SPECVARS *TAIL*))
    (PROG NIL
           COND
               (VARLST (PROG ((PROGFRAME (\MYALINK))
                                HEADER NT NILSTART)
                               (SETQ HEADER (fetch (FX FNHEADER) of PROGFRAME))
                               (SETQ NT (ADDSTACKBASE (CEIL (IPLUS (SETQ NILSTART (IDIFFERENCE
                                                                                         (fetch (FX NEXTBLOCK)
                                                                                            of PROGFRAME)
                                                                                         (UNFOLD NNILS WORDSPERCELL)))
                                                                       (UNFOLD NVARS WORDSPERCELL))
                                                               WORDSPERQUAD)))
                         ;; NT is address of our synthesized nametable: beginning of NIL's, not counting additional PVARs we are about to bind,
                        ;; rounded up to quadword
                               [for var in varlst as valueoff from nilstart by wordspercell
                                  do
                                                                      ; evaluate initial values first
                                      (COND
                                         ((LISTP VAR)
                                          (PUTBASEPTR \STACKSPACE VALUEOFF (\EVPROG1 (CDR VAR)
                                                                      ; then build NT
                               (UNINTERRUPTABLY
                                    (for var in varlst as var# from (foldlo (idifference nilstart (fetch (fx firstpvar
                                                                                                         of PROGFRAME))
                                                                            WORDSPERCELL)
                                      as NT1 from (fetch (FNHEADER OVERHEADWORDS) of T) by (CONSTANT (
                                                                                                        WORDSPERNAMEENTRY
                                                                                                          ))
                                      as NT2 from (IPLUS (fetch (FNHEADER OVERHEADWORDS) of T)
                                                           NTSIZE)
                                       bv (CONSTANT (WORDSPERNTOFFSETENTRY))
                                          [SETSTKNAME-RAW NT NT1 (\ATOMVALINDEX (COND
```

(AND

```
((LISTP VAR)
                                                                                               (CAR VAR))
                                                                                              (T VAR]
                                             (SETSTKNTOFFSET-RAW NT NT2 PVARCODE VAR#))
                                      (replace (FNHEADER %#FRAMENAME) of NT with 'LET)
                                      (replace (FNHEADER NTSIZE) of NT with NTSIZE)
                                                                           ; Do I need to worry about STK, NA, PV, START, ARGTYPE
                                                                            NLOCALS? --- no
                                      (replace (FX NAMETABLE) of PROGFRAME with NT))]
       EVLP
            (COND
                [(NULL (CDR *TAIL*))
                 (RETURN (\EVAL (CAR *TAIL*]
                   (\EVAL (CAR *TAIL*))
(SETQ *TAIL* (CDR *TAIL*))
                    (GO EVLP1)
(\LET*
  [LAMBDA (*TAIL* NNILS NVARS NTSIZE VARLST)
    (DECLARE (LOCALVARS . T)
            (SPECVARS *TAIL*))
                                                                           ; Edited 27-Jan-91 14:37 by jds
    (PROG NIL
            COND
                (VARLST (PROG ((PROGFRAME (\MYALINK))
                                  HEADER NT NILSTART)
                                  (SETQ HEADER (fetch (FX FNHEADER) of PROGFRAME))
                                  (SETQ NT (ADDSTACKBASE (CEIL (IPLUS (SETQ NILSTART (IDIFFERENCE
                                                                                                (fetch (FX NEXTBLOCK)
                                                                                                   of PROGFRAME)
                                                                                                (UNFOLD NNILS WORDSPERCELL)))
                                                                             (UNFOLD NVARS WORDSPERCELL))
                                                                    WORDSPERQUAD)))
                           ;; NT is address of our synthesized nametable: beginning of NIL's, not counting additional PVARs we are about to bind,
                          ;; rounded up to quadword
                          ;; First build the nametable. This differs from LET in that the nametable is built in reverse order and the PVARs are
                           ;; marked unbound before we start evaluating the forms. This way, we get the right semantics of nested LET's.
                                      (FOR VAR IN VARLST AS VAR# FROM (FOLDLO (IDIFFERENCE NILSTART
                                                                                               (FETCH (FX FIRSTPVAR)
                                                                                                   OF PROGFRAME))
                                                                                      WORDSPERCELL)
                                          AS VALUEOFF FROM NILSTART BY WORDSPERCELL AS NT1
                                          FROM (IPLUS (UNFOLD (SUB1 NVARS)
                                                         (CONSTANT (WORDSPERNAMEENTRY)))
(FETCH (FNHEADER OVERHEADWORDS) OF T))
                                          BY (IMINUS (CONSTANT (WORDSPERNAMEENTRY))) AS NT2
                                          FROM (IPLUS (UNFOLD (SUB1 NVARS)
                                                                 (CONSTANT (WORDSPERNAMEENTRY)))
                                                         (FETCH (FNHEADER OVERHEADWORDS) OF T)
                                                         NTSIZE)
                                          BY (IMINUS (CONSTANT (WORDSPERNTOFFSETENTRY)
                                          DO [SETSTKNAME-RAW NT NT1 (\ATOMVALINDEX (COND
                                                                                              ((LISTP VAR)
                                                                                               (CAR VAR))
                                                                                              (T VAR]
                                              (SETSTKNTOFFSET-RAW NT NT2 PVARCODE VAR#)
                                      (PUTBASE \STACKSPACE VALUEOFF 65535))
(replace (FNHEADER %#FRAMENAME) of NT with 'LET*)
                                       (REPLACE (FNHEADER NTSIZE) OF NT WITH NTSIZE)
                                                                           ; Do I need to worry about STK, NA, PV, START, ARGTYPE
; NLOCALS ? --- no
                                      (REPLACE (FX NAMETABLE) OF PROGFRAME WITH NT))
                                  (FOR VAR IN VARLST AS VALUEOFF FROM NILSTART BY WORDSPERCELL
                                                                           ; evaluate initial values first
                                         (PUTBASEPTR \STACKSPACE VALUEOFF (IF
                                                                                    (LISTP VAR)
                                                                                     THEN (\EVPROG1 (CDR VAR))
                                                                                  ELSE NIT.1
       EVLP
             (COND
                [(NULL (CDR *TAIL*))
                 (NOLL (CDR TIALL ),
(RETURN (\EVAL (CAR *TAIL*)

T (\EVAL (CAR *TAIL*))
(SETQ *TAIL* (CDR *TAIL*))
                    (GO EVLP])
(DEFINEQ
QUOTE
  [NLAMBDA U
    (CAR U])
```

```
{MEDLEY}<sources>LLINTERP.;1 (AND cont.)
                                                                                                                                 Page 17
  [NLAMBDA U
     (DECLARE (SPECVARS *TAIL*))
     (OR (NLISTP U)
          (PROG ((*TAIL* U))
                  (RETURN (COND
                                 ((NLISTP (CDR *TAIL*))
                                 (\EVAL (CAR *TAIL*)))
((\EVAL (CAR *TAIL*))
                                   (SETQ *TAIL* (CDR *TAIL*))
                                   (GO LP])
OR
  [NLAMBDA U
     (DECLARE (SPECVARS *TAIL*))
                                                                              (* lmm " 9-May-86 13:45")
     (AND (LISTP U) (PROG ((*TAIL* U))
                   (RETURN (COND
                                  ((NLISTP (CDR *TAIL*))
(\EVAL (CAR *TAIL*))
(T (OR (\EVAL (CAR *TAIL*))
(PROGN (SETQ *TAIL* (CDR *TAIL*))
(GO LP])
(PROGN
                                                                               ; MUST be a NLAMBDA* with internal call to EVAL for dwimsake
  [NLAMBDA U
     (DECLARE (SPECVARS *TAIL*))
     (AND (LISTP U) (PROG ((*TAIL* U))
                    (COND
              LP
                       [(NLISTP (CDR *TAIL*))
(RETURN (\EVAL (CAR *TAIL*]
                        (T (\EVAL (CAR *TAIL*))
(SETQ *TAIL* (CDR *TAIL*))
                           (GO LP])
(COND
  [NLAMBDA U
     (DECLARE (SPECVARS *TAIL*))
                                                                              (* lmm "25-APR-80 18:03")
     (PROG ((*TAIL* U)
             (RETURN (COND
                            ((NLISTP *TAIL*)
                             COND
                                 (*TAIL* (LISPERROR "UNUSUAL CDR ARG LIST" *TAIL*))
                                 (T NIL)))
                           ((SETQ VAL (\EVAL (CAAR *TAIL*)))
(COND
                                 ((CDAR *TAIL*)
                                  (\EVPROGN (CDAR *TAIL*)))
                            (T VAL)))
(T (SETQ *TAIL* (CDR *TAIL*))
                               (GO LP])
(\EVPROGN
  [LAMBDA (*TAIL*)
(DECLARE (SPECVARS *TAIL*))
                                                                               (* lmm "18-Feb-86 01:44")
     PROG NIL
            (COND
        T.P
                 ((CDR *TAIL*)
                  (\EVAL (CAR *TAIL*))
(SETQ *TAIL* (CDR *TAIL*))
                  (GO LP))
                 (T (RETURN (\EVAL (CAR *TAIL*])
(PROG1
  [NLAMBDA U
     (DECLARE (SPECVARS *TAIL*))
                                                                               (* lmm "14-MAY-80 12:59")
     (AND (LISTP U)
           (PROG ((*TAIL* U))
                    (RETURN (PROG1 (\EVAL (CAR *TAIL*))
                                    [PROG NIL
                                       LP
                                            COND
                                                ((LISTP (SETQ *TAIL* (CDR *TAIL*)))
(\EVAL (CAR *TAIL*))
```

(**GO** LP])])

)

(RPAQQ \DEFEVALFNS NIL)
(RPAGO \EVALHOOK NIL)

```
{MEDLEY} < sources>LLINTERP.;1
(DECLARE%: DOEVAL@COMPILE DONTCOPY
(SPECVARS *EVALHOOK*)
(ADDTOVAR LAMBDASPLST LAMBDA NLAMBDA CL:LAMBDA OPENLAMBDA)
(DECLARE%: DOEVAL@COMPILE DONTCOPY
(GLOBALVARS \DEFEVALFNS \EVALHOOK LAMBDASPLST CLISPARRAY)
(DECLARE%: DONTEVAL@LOAD DOCOPY
(RPAQQ CLISPARRAY NIL)
(MOVD? 'SETQ 'SETN NIL T)
(DECLARES: DOEVAL@COMPILE DONTCOPY
(GLOBALVARS CLISPARRAY)
;; Evaluating in different stack environment
(DEFINEQ
(ENVEVAL
  [LAMBDA (FORM APOS CPOS AFLG CFLG)
                                                                      (* bvm%: "18-AUG-81 23:29")
    (\CALLME '*ENV*)
    (\SMASHLINK NIL (AND APOS (\STACKARGPTR APOS))
           (AND CPOS (\STACKARGPTR CPOS)))
    (COND
        (AFLG (RELSTK APOS)))
    COND
        (CFLG (RELSTK CPOS)))
    (\EVAL FORM])
(ENVAPPLY
  [LAMBDA (FN ARGS APOS CPOS AFLG CFLG) (\CALLME '*ENV*)
                                                                      (* lmm "15-Aug-84 17:53")
    (\SMASHLINK NIL (AND APOS (\STACKARGPTR APOS))
           (AND CPOS (\STACKARGPTR CPOS)))
    COND
        (AFLG (RELSTK APOS)))
    (COND
        (CFLG (RELSTK CPOS)))
    (.APPLY. FN ARGS])
(FUNCTION
  [NLAMBDA (FN ENV)
                                                                      (* bvm%: "11-Nov-86 21:23")
    (COND
        (ENV (if NIL
                 then (LIST 'FUNARG FN (STKNTH -1 'FUNCTION))
               else (ERROR "FUNARGS no longer supported--use Common Lisp lexical closures" FN)))
        (T FN])
(\FUNCT1
          (NNILS NVARS NTSIZE VARLST)
                                                                      ; Edited 27-Jan-91 14:39 by jds
  [LAMBDA
    (PROG ((FUNCTFRAME (\MYALINK))
             HEADER NT NILSTART)
            (SETQ HEADER (fetch (FX FNHEADER) of FUNCTFRAME))
            (SETQ NT (ADDSTACKBASE (CEIL (IPLUS (SETQ NILSTART (IDIFFERENCE (fetch (FX NEXTBLOCK) of FUNCTFRAME)
                                                                             (UNFOLD NNILS WORDSPERCELL)))
                                                    (UNFOLD NVARS WORDSPERCELL))
                                            WORDSPERQUAD)))
     ;; NT is address of our synthesized nametable: beginning of NIL's, not counting additional PVARs we are about to bind, rounded up to quadword
            (for var in varlst as valueoff from nilstart by wordspercell do (\putbaseptr (addstackbase valueoff)
                                                                                        (\EVAL VAR)))
                                                                      : then build NT
            (UNINTERRUPTABLY
                (for var in varlst as var# from (foldlo (idifference nilstart (fetch (fx firstpvar) of functframe))
                                                         WORDSPERCELL)
                   as NT1 from (fetch (FNHEADER OVERHEADWORDS) of T) by (CONSTANT (WORDSPERNAMEENTRY)) as NT2 from (IPLUS (fetch (FNHEADER OVERHEADWORDS) of T)
                                NTSIZE)
                   by (Constant (Wordsperntoffsetentry)) do (Setstkname-raw nt nt1 (\atomvalindex var))
                                                                 (SETSTKNTOFFSET-RAW NT NT2 PVARCODE VAR#))
                (replace (FNHEADER %#FRAMENAME) of NT with '*FUNARG*)
                (replace (FNHEADER NTSIZE) of NT with NTSIZE)
                (replace (FX NAMETABLE) of FUNCTFRAME with NT))
```

:: Blip and other stack funniness

```
(RETURN (\MAKESTACKP NIL FUNCTFRAME])
```

```
(\MAKEFUNARGFRAME
  [LAMBDA (ENV)
                                                                       ; Edited 21-Jan-91 18:19 by jds
    (\CALLME 'FUNARG)
    (PROG ((NVARS 0)
             NTSIZE NNILS)
            (for VAR in ENV do
                                                                       ; Count number of vars to bind, check validity
                               (COND
                                   ((OR (NULL (\DTEST VAR 'LITATOM))
                                         (EQ VAR T))
                                    (LISPERROR "ATTEMPT TO BIND NIL OR T" VAR)))
                                (add NVARS 1))
            (SETQ ENV (.CALLAFTERPUSHINGNILS. (SETQ NNILS (IPLUS NVARS (SETQ NTSIZE
                                                                                (CEIL [ADD1 (UNFOLD NVARS (CONSTANT
                                                                                                          WORDSPERNAMEENTRY
                                                                                                               ]
                                                                                      WORDSPEROUAD))
                                                                        (FOLDHI (fetch (FNHEADER OVERHEADWORDS)
                                                                                    of T)
                                                                               WORDSPERCELL)
                                                                       (SUB1 CELLSPERQUAD))); ENV POINTS TO COPY OF FUNCTION FRAME
                               (\FUNCT1 NNILS NVARS NTSIZE ENV)))
            (\SMASHLINK (fetch (STACKP EDFXP) of ENV)
                   0 0)
            (RETURN ENV])
(STKEVAL
  [LAMBDA (POS FORM FLG INTERNALFLG)
                                                                       (* lmm "25-APR-80 00:08")
    (\SMASHLINK NIL (\STACKARGPTR POS))
    (AND FLG (RELSTK POS))
    (\EVAL FORM])
(STKAPPLY
  [LAMBDA (POS FN ARGS FLG)
                                                                       (* lmm "15-Aug-84 17:55")
    (\CALLME '*ENV*)
     \SMASHLINK NIL (\STACKARGPTR POS))
    (AND FLG (RELSTK POS))
    (.APPLY. FN ARGS])
(RETEVAL
  [LAMBDA (POS FORM FLG INTERNALFLG)
                                                                       (* bvm%: "11-Nov-86 20:53")
    ;; Return from POS with the value of evaluating FORM in the dynamic context of POS
    ;; Anyone know what INTERNALFLG is for?
    (\CALLME '*ENV*)
    (LET ((FX (\STACKARGPTR POS))
           RETURNEE)
          (if (fetch (FX INVALIDP) of (SETQ RETURNEE (fetch (FX CLINK) of FX)))
              then (LISPERROR "ILLEGAL STACK ARG" POS))
          (\SMASHRETURN NIL FX)
                                                                       ; unwind stack back to POS--we need to keep that dynamic
                                                                        : environment
          (AND FLG (RELSTK POS))
          (CL:MULTIPLE-VALUE-PROG1 (\EVAL FORM)
                                                                       ; finally, return from POS
                 (SI::UNWIND RETURNEE])
(RETAPPLY
  [LAMBDA (POS FN ARGS FLG)
                                                                       (* bvm%: "11-Nov-86 12:04")
    ;; Return from POS with the value of applying FN to ARGS in the dynamic context of POS
    (\CALLME '*ENV*)
    (LET ((FX (\STACKARGPTR POS))
          RETURNEE)
          (if (fetch (FX INVALIDP) of (SETQ RETURNEE (fetch (FX CLINK) of FX)))
              then (LISPERROR "ILLEGAL STACK ARG" POS))
                                                                       ; unwind stack back to POS--we need to keep that dynamic
          (\SMASHRETURN NIL FX)
                                                                       : environment
          (AND FLG (RELSTK POS))
          (CL:MULTIPLE-VALUE-PROG1 (.APPLY. FN ARGS)
                                                                       ; finally, return from POS
                  (SI::UNWIND RETURNEE))
(DECLARE%: DONTEVAL@LOAD DOCOPY
(MOVD? 'FUNCTION 'CL:FUNCTION NIL T)
```

(DEFINEQ

```
(BLIPVAL
  [LAMBDA (BLIPTYP IPOS FLG)
                                                                      ; Edited 18-Feb-91 16:48 by jds
    (PROG ([FRAME (COND
                       ((NULL IPOS)
                         (\MYALINK))
                        (T (\STACKARGPTR IPOS]
             (A (NEW-SYMBOL-CODE BLIPTYP (\ATOMVALINDEX BLIPTYP)))
            I)
            (SELECTQ BLIPTYP
                   TAIL* *FORM* *FN* *ARGVAL*))
                 (RETURN (AND (EQ FLG T)
                                0)))
            (RETURN
             (COND
                ((EO FLG T)
                                                                      ; Count number of blips of type BLIPTYP at FRAME
                 COND
                    ((NOT (SETQ I (\VAROFFSET FRAME A)))
                    ((EQ BLIPTYP '*ARGVAL*)
                                                                      ; the value of *ARGVAL* is the number of *ARGVAL* blips in this
                                                                      : frame
                     (OR (\GETBASEPTR \STACKSPACE I)
                          0))
                       1)))
                (T (PROG NIL
                          (OR FLG (SETQ FLG 1))
                      FRAMELP
                          [COND
                              ((SETQ I (\VAROFFSET FRAME A))
                               (SELECTQ BLIPTYP
                                    (*ARGVAL* [COND
                                                  ((IGREATERP FLG (SETQ I (OR (\GETBASEPTR \STACKSPACE I)
                                                                                  0)))
                                                                      ; Fewer blips here than FLG
                                                    (SETQ FLG (IDIFFERENCE FLG I)))
                                                                       Scan the temporary region for the value of the FLG'th
                                                                       *ARGVAL* blip
                                                      (RETURN (PROG
                                                                       ((NXT (fetch (FX NEXTBLOCK) of FRAME))
                                                                        (P (fetch (FX FIRSTTEMP) of FRAME)))
                                                                       (CHECK (ILESSP P NXT))
                                                                       COND
                                                                          ((EQ (\GETBASEPTR \STACKSPACE P)
'*ARGVAL*)
                                                           ;; \EVALFORM pushes the atom *ARGVAL*, then each argument. We want
                                                           ;; the FLG'th arg, counting from the end backwards
                                                                           (add P (UNFOLD (ADD1 (IDIFFERENCE I FLG))
                                                                                          WORDSPERCELL))
                                                                           (CHECK (ILESSP P NXT))
                                                                           (RETURN (\GETBASEPTR \STACKSPACE P]
                                                                       (add P WORDSPERCELL)
                                                                       (GO LP])
                                    COND
                                       ((ILESSP (SETQ FLG (SUB1 FLG))
                                        (RETURN (\GETBASEPTR \STACKSPACE I]
                      NEXT
                           COND
                              ([NOT (fetch (FX INVALIDP) of (SETQ FRAME (fetch (FX CLINK) of FRAME]
                               (GO FRAMELP])
(SETBLIPVAL
                                                                      ; Edited 18-Feb-91 16:49 by jds
  [LAMBDA (BLIPTYP IPOS N VAL)
    (PROG ([FRAME (COND
                        ((NULL IPOS)
                         (\MYALINK))
                        (T (\STACKARGPTR IPOS]
             (A (NEW-SYMBOL-CODE BLIPTYP (\ATOMVALINDEX BLIPTYP)))
            I)
            (SELECTQ BLIPTYP
                  (*TAIL* *FORM* *FN* *ARGVAL*))
                 (RETURN))
            (COND
               ((NOT N)
                (SETQ N 1))
               ((ILESSP N 1)
                (\ILLEGAL.ARG N)))
       FRAMELP
           [COND
               ((SETQ I (\VAROFFSET FRAME A))
(SELECTQ BLIPTYP
                     (*ARGVAL* [COND
                                   ((NOT (SETQ I (\GETBASEPTR \STACKSPACE I)))
                                                                      ; No argvals
```

```
((IGREATERP N I)
                                    (SETQ N (IDIFFERENCE N I)))
                                                                      ; Scan the temporary region for the value of the Nth *ARGVAL*
                                                                      ; blip
                                       (RETURN (PROG ((NXT (fetch (FX NEXTBLOCK) of FRAME))
                                                         (P (fetch (FX FIRSTTEMP) of FRAME)))
                                                        (CHECK (ILESSP P NXT))
                                                        COND
                                                           ((EQ (\GETBASEPTR \STACKSPACE P)
'*ARGVAL*)
                                                                       \EVALFORM pushes the atom *ARGVAL*, then each
                                                                      ; argument. We want the N'th arg from the end
                                                             (add P (UNFOLD (ADD1 (IDIFFERENCE I N))
                                                                           WORDSPERCELL))
                                                             (CHECK (ILESSP P NXT))
                                                             (RETURN (\PUTBASEPTR \STACKSPACE P VAL]
                                                        (add P WORDSPERCELL)
                                                        (GO LP])
                     COND
                        ((ILESSP (SETQ N (SUB1 N))
                                                                      ; All other blip types are just the value of the blip binding
                         (RETURN (\PUTBASEPTR \STACKSPACE I VAL)
            (COND
               ([NOT (fetch (FX INVALIDP) of (SETQ FRAME (fetch (FX CLINK) of FRAME]
                (GO FRAMELP])
(BLIPSCAN
                                                                      ; Edited 18-Feb-91 16:50 by jds
  [LAMBDA (BLIPTYP IPOS)
    (PROG ([FRAME (COND
                        ((NULL IPOS)
                         (\MYALINK))
                        (T (\STACKARGPTR IPOS]
            OFF A)
            (SETQ A (SELECTQ BLIPTYP
                          ((*FORM* *TAIL* *FN* *ARGVAL*)
                               (NEW-SYMBOL-CODE BLIPTYP (\ATOMVALINDEX BLIPTYP))))
                          (RETURN)))
       LΡ
            (COND
               ([AND (SETQ OFF (\VAROFFSET FRAME A))
                      (NOT (AND (EQ BLIPTYP '*ARGVAL*)
                                  (NULL (GETBASEPTR \STACKSPACE OFF]
                (RETURN (\MAKESTACKP NIL FRAME)))
               ([NOT (fetch (FX INVALIDP) of (SETQ FRAME (fetch (FX CLINK) of FRAME]
               (T (RETURN])
)
(DEFINEO
○NEALFRAMEP
  [LAMBDA (FRAME INTERPFLG)
                                                                      (* Imm " 7-Nov-86 01:53")
    (LET ((NAME (fetch (FNHEADER FRAMENAME) of (fetch (FX FNHEADER) of FRAME))))
          BFLINK)
         ;; note that the selection is on the fnheader's name rather than the nametable name. \REALFRAMEP is thus not affected by SETSTKNAME
          (AND (CL:SYMBOLP NAME)
                (SELECTO NAME
                                                                      ; *ENV* is used by ENVEVAL etc.
                     (*ENV*
                            NIL)
                     (\INTERPRETER T)
                     (ERRORSET (NEQ (\STKARG 2 FRAME)
   'INTERNAL))
                     ((EVAL APPLY)
                          (\SMASHLINK NIL FRAME)
                          (SELECTQ \INTERNAL
                              ((INTERNAL SELECTQ)
                                   NIL)
                              T))
                     (OR (NOT (LITATOM NAME))
                          (COND
                             ((FMEMB NAME OPENFNS)
                              INTERPFLG)
                             (T (OR (NEQ (CHCON1 NAME)
                                           (CHARCODE \))
                                     (EXPRP NAME)
                                     (FASSOC NAME BRKINFOLST])
(RPAQ? OPENFNS '(APPLY* SETQ AND OR COND SELECTQ PROG PROGN PROG1 ARG SETARG ERSETQ NLSETQ RESETFORM RESETLST
                          RESETVARS RPTQ SAVESETQ SETN UNDONLSETQ XNLSETQ))
(RPAOO \BLIPNAMES (*TAIL* *FORM* *FN* *ARGVALS*))
```

)

```
"Lisp stack " NOECHOFLG T EXPLAINSTRING "^L -- Lisp stack from arbitrary frame or context" RETURN '^L) (F "rame ")
"Next frame " EXPLAINSTRING "LF - next frame" RETURN 'LF)
                                                                       (^ " Previous frame ")
                                                                       (A "tom top-level value of atom: ")
                                                                       (D "efinition for atom: ")
                                                                       (P "roperty list for atom: ")
                                                                       (V " -- show object at Virtual address: ")
                                                                       (B "lock of storage starting at address: ")
                                                                       (S "how raw stack from address: ")
                                                                       (C "ode for function:")
                                                                       (%Ã "Basic frame at: " EXPLAINSTRING "^F - print
                                                                          basic frame at octal address" RETURN
                                                                          '^F)
                                                                       (%Û "frame extension at: " EXPLAINSTRING "^X -
                                                                          print frame extension at octal address" RETURN
'^X)
                                                                       (W "alk stack blocks starting at: ")
(K "" EXPLAINSTRING "K -- Set linktype for stack
                                                                          ops")
                                                                      (_ " Set word at address: ")
(%- " Set value of atom " EXPLAINSTRING "^V -- Set
   value of atom" RETURN '^V)
(% i "atom number for atom: " EXPLAINSTRING "^O -
   look up atom" RETURN '^O)
                                                                       (Z "Zap Print level to: ")
                                                                       (I "nspect InterfacePage [confirm]" CONFIRMFLG T)
                                                                       (U " -- Show remote screen [confirm] " CONFIRMFLG T
                                                                         )
                                                                      " "" RETURN NIL)
(%Ü " Enter Lisp " EXPLAINSTRING "^Y -- Enter
Lisp" RETURN '^Y))
                                                    T)))
                 (^N (RETURN 'RETURN))
                (Q (TERPRI T)
(RETURN 'QUIT))
                 (NIL
                (A (PRINCOPY (GETTOPVAL (READATOM))))
(P (PRINCOPY (GETPROPLIST (READATOM))))
                (C (PRINTCODE (READATOM)
                T RAIDIX))
(V (PRINCOPY (READVA)))
                (B (PRINTADDRS (READVA)
                            (READOCT " for (number of words): ")))
                (S (PRINTADDRS (ADDSTACKBASE (READOCT))
                            (READOCT " for (number of words): ")))
                (D (PRINTADDRS (fetch (LITATOM DEFINITIONCELL) of (READATOM))
                            2))
                (^O (PRINTNUM .12 (\ATOMVALINDEX (READATOM))
                             T))
                (^V (PROG ((ATM (READATOM)))
                             (printout T " to be ")
                             (SETTOPVAL ATM (READ T T))))
                ((L ^L)
                (RAIDSTACKCMD CMD))
(F [RAIDSHOWFRAME (SETQ FRAME# (PROG1 (READ T T)
                                                               (READC T1)
                (LF (OR FRAME# (SETQ FRAME# 0))
                     (printout T "(" .I1 (add FRAME# 1)
                     (RAIDSHÓWFRAME FRAME#))
                   COND
                       ((OR (NULL FRAME#)
                              (ILEQ FRAME# 1))
                       (^F (\PRINTBF (READOCT)
                            NI
                             (FUNCTION PRINCOPY)))
                (Z [ALLOCAL (LET [ (A (PROG1 (READ T T)
                                                (READC T)))
                                     (D (PROG1 (READ T T)
                                                (READC T]
                                    (COND
                                        ((AND (FIXP A)
                                               (FIXP D))
                                         (SETQ VPRINTLEVEL (CONS A D)))
                                        (T (PRINTOUT T "Must be two integers, car level then cdr level" T)
                                           (ERROR!])
                (W | SHOWSTACKBLOCKS (COND
                                              ((EQ (PEEKC T)
```

```
(READC T)
(fetch (IFPAGE StackBase) of \InterfacePage))
(T (READOCT])
                  (^X (\PRINTFRAME (READOCT)
                               'PRINCOPY))
                      (TERPRI T)
                  (^Y
                       (USEREXEC ':%:))
                    (SETQ ALINKS? (EQ (ASKUSER NIL NIL " Set link type for stack operations to "
                                                    '((A "links
                                                         ")
                                                      (C "links
                                                         "))
                                                   T)
                                           'A)))
                  (_ (PROG ((VA (READVA))))
                             (printout T " Currently ")
(PRINTNUM .17 (GETBASE VA 0)
                                     T)
                              (printout T " to be "
                              (PUTBASE VA 0 (READOCT))))
                  (I [ALLOCAL (COND
                                    [(NULL (GETD 'INSPECT] ((RECLOOK 'IFPAGE)
                                     (INSPECT [COND
                                                   ((LISTP VMEMFILE)
((MAPPAGE (fetch (POINTER PAGE#) of \InterfacePage)))
(T (PROG [(PAGE (NCREATE 'VMEMPAGEP]
(SETVMPTR (VGETTOPVAL '\InterfacePage))
                                                               (\BINS (GETSTREAM VMEMFILE)
                                                                       PAGE 0 BYTESPERPAGE)
                                                               (RETURN PAGE]
                                             'IFPAGE))
                                    (T (PRIN1 " Can't -- no record for IFPAGE"]
                      (TERPRI T))
                  (U (SHOWREMOTESCREEN))
                  (HELP))
             (RETURN NIL])
(RAIDSHOWFRAME
                                                                            (* bvm%: "27-Jan-85 15:27")
  [LAMBDA (N) (PROG [(FRAME (OR ROOTFRAME]
            [FRPTQ (SUB1 N)
                     COND
                        ([fetch (FX INVALIDP) of (SETQ FRAME (COND
                                                                       (ALINKS? (fetch (FX ALINK) of FRAME))
                                                                       (T (fetch (FX CLINK) of FRAME]
                          (RETURN (printout T N " is beyond the bottom of the stack" T]
             (\BACKTRACE FRAME FRAME T NIL T T NIL (FUNCTION PRINCOPY)
                    NIL RAIDIX1)
(RAIDSTACKCMD
                                                                            (* bvm%: "28-Jan-85 12:16")
  [LAMBDA (CMD)
    (DECLARE (USEDFREE FRAME# ROOTFRAME))
(PROG (FRAME)
             (SETQ FRAME# 0)
             COND
                ((EQ CMD 'L
                 (RAIDROOTFRAME))
                (T (SETQ ROOTFRAME (SELECTQ (SETQ FRAME (ASKUSER NIL NIL "in context (? for help): " ' ((P "age fault")
                                                                            (G "arbage collection")
                                                                            (K "eyboard handler")
                                                                            (H "ard Return")
                                                                            (S "tack manipulator")
                                                                            (R "eset")
                                                                            (M "iscellaneous")
                                                                            (F "rame at location: "))
                                                                         T))
                                             (P (fetch (IFPAGE FAULTFXP) of \InterfacePage))
(G (fetch (IFPAGE GCFXP) of \InterfacePage))
                                                (fetch (IFPAGE KbdFXP) of \InterfacePage))
                                                (fetch (IFPAGE HardReturnFXP) of \InterfacePage))
                                                (fetch (IFPAGE SubovFXP) of \InterfacePage))
                                             (S
                                             (R (fetch (IFPAGE ResetFXP) of \InterfacePage))
                                                (fetch (IFPAGE MiscFXP) of \InterfacePage))
                                             COND
                                                ((AND (ILESSP (SETQ FRAME (READOCT))
                                                                WORDSPERPAGE)
                                                        (ILESSP (\GETBASE \InterfacePage FRAME)
                                                        (fetch (IFPAGE EndOfStack) of \InterfacePage))
(type? FX (\GETBASE \InterfacePage FRAME)))
                                                 (\GETBASE \InterfacePage FRAME))
                                                ((type? FX FRAME)
                                                 FRAME)
                                                (T (PRINTNUM .17 FRAME)
```

```
(printout T " not a valid frame." T)
(RETURN]
            (FRESHLINE T)
            (\BACKTRACE ROOTFRAME NIL T NIL NIL ALINKS? (FUNCTION PRINCOPY)
(RAIDROOTFRAME
  [LAMBDA NIL
                                                                       (* bvm%: "27-Jan-85 15:26")
    (SETQ ROOTFRAME (PROG1 (COND
                                  ((ALLOCAL (LISTP VMEMFILE))
                                    (PRIN1 "in TeleRaid Context" T)
                                    (fetch (IFPAGE TELERAIDFXP) of \InterfacePage))
                                  (T (fetch (IFPAGE CurrentFXP) of \InterfacePage)))
                              (TERPRI T])
(PRINTADDRS
 [LAMBDA (BASE CNT)
(PRIN1 "words from ")
                                                                       (* bvm%: "13-Feb-85 22:42")
    (PRINTVA BASE)
    (PRIN1 " to ")
(PRINTVA (\ADDBASE BASE (SUB1 CNT)))
    (TERPRI)
    (SPACES 7)
    (for I from 0 to 7 do (PRINTNUM .I7 I))
(PROG ((NB (\VAG2 (\HILOC BASE)
                         (FLOOR (\LOLOC BASE)
                                8)))
             (LB (\ADDBASE BASE CNT)))
            (do (COND
                   ((EVENP (\LOLOC NB)
                           8)
                     (TAB 0 0)
                     (PRINTNUM .I5 (\LOLOC NB))
(PRIN1 ": ")))
                [COND
                    ((PTRGTP BASE NB)
                     (SPACES 7))
                      (PRINTNUM .I7 (\GETBASE NB 0]
                (SETQ NB (\ADDBASE NB 1)) repeatwhile (PTRGTP LB NB))
(PRINTVA
  [LAMBDA (X) (PRIN1 "{")
                                                                       (* bvm%: "12-Feb-85 10:41")
    (PRINTNUM .12 (HILOC X))
    (PRIN1 ",")
    (PRINTNUM .I2 (LOLOC X))
    (PRIN1 "}"])
(READVA
  [LAMBDA NIL
                                                                       (* lmm "21-AUG-81 12:55")
    (VAG2 (READOCT)
           (READOCT1)
(READATOM
                                                                       ; Edited 16-Feb-87 15:44 by raf
  [LAMBDA NIL
    (ALLOCAL (PROG1 (HANDLER-BIND [[XCL:MISSING-EXTERNAL-SYMBOL #' (LAMBDA (CONDITION)
                                                                            ;; MAKE AN INTERNAL SYMBOL INSTEAD
                                                                            (CL:INTERN (
                                                                                         XCL:MISSING-EXTERNAL-SYMBOL-NAME
                                                                                         CONDITION)
                                                                                    (XCL:MISSING-EXTERNAL-SYMBOL-PACKAGE
                                                                                     CONDITION]
                                        (XCL:MISSING-PACKAGE #'(LAMBDA (CONDITION)
                                                                   ;; FAKE A PACKAGE BY THIS NAME AND MAKE THE SYMBOL IN
                                                                   ;; IT
                                                                   (CL:INTERN (XCL:MISSING-PACKAGE-SYMBOL-NAME
                                                                                       CONDITION)
                                                                           (CL:MAKE-PACKAGE (
                                                                                        XCL:MISSING-PACKAGE-PACKAGE-NAME
                                                                                               CONDITION)
                                                                                   :USE NIL]
                              (CL:READ T))
                      (READC T])
(READOCT
  [LAMBDA (PROMPT)
                                                                       (* bvm%: "28-Jan-85 11:51")
    (DECLARE (USEDFREE RAIDIX))
    COND
```

(NOSUCHATOM | LAMBDA (ATM)

; Edited 9-Nov-92 15:24 by sybalsky:mv:envos

^{;;} Called only under TeleRaid when V\MKATOM fails to find atom ATM. JDS: And in MAKEINIT, ditto. For Makeinit (since Teleraid is essentially ;; dead), changed ERROR! to ERROR.

```
{MEDLEY}<sources>LLINTERP.;1 (NOSUCHATOM cont.)
    (printout T "No such atom: " ATM T)
    (ERROR "No such atom: "])
(DEFINEQ
(BACKTRACE
  [LAMBDA (IPOS EPOS FLAGS FILE PRINTFN)
                                                                        (* bvm%: "13-Feb-85 22:42")
    (RESETFORM (OUTPUT FILE)
            (\BACKTRACE (\STACKARGPTR (OR IPOS -1))
                    (\STACKARGPTR (OR EPOS T))
                    [EQ 0 (LOGAND 8 (OR FLAGS (SETQ FLAGS 0]
                    (NEQ 0 (LOGAND FLAGS 1))
                    (NEQ 0 (LOGAND FLAGS 4))
                    (NEQ 0 (LOGAND FLAGS 32))
                    (EO 0 (LOGAND FLAGS 16))
                    (OR PRINTFN (FUNCTION PRINT))
                   NIL])
∆BACKTRACE
  [LAMBDA (IPOS EPOS NAMES VARS LOCALS JUNK ALINKS PRINTFN CNT RADIX)
                                                                        (* lmm " 2-Jul-86 13:00")
    (OR RADIX (SETQ RADIX 8))
(PROG [NARGS NPVARS NAME ARGNAME BLINK (.17 (NUMFORMATCODE (LIST 'FIX 7 RADIX]
(DECLARE (SPECVARS .17))
       POSLP
            (COND
               (CNT (printout NIL .I3 CNT ": ")
            (add CNT 1)))
(SETQ NAME (\STKNAME IPOS))
            (COND
               (JUNK (TERPRI)
                      (TERPRI)
                      (PRIN1 "Basic frame at ")
                      (PRINTNUM . 17 (SETQ BLINK (fetch (FX BLINK) of IPOS)))
                      (\PRINTBF BLINK (fetch (FX NAMETABLE) of IPOS)
                             PRINTFN)
                      (PROGN (TERPRI)
                              (PRIN1 "Frame xtn at ")
                      (PRINTNUM .17 IPOS)
(PRIN1 ", frame name= "))
(APPLY* PRINTFN NAME)
                      (\PRINTFRAME IPOS PRINTFN))
               [(OR VARS LOCALS)
(\PRINTBF (fetch (FX BLINK) of IPOS)
                        (fetch (FX NAMETABLE) of IPOS)
                        PRINTFN
                        (COND
                            (LOCALS 'LOCALS)
                            (T T)))
                (COND
                    (NAMES (APPLY* PRINTFN NAME)
                            (TERPRI)))
                (\PRINTFRAME IPOS PRINTFN (COND
                                                 (LOCALS 'LOCALS)
                                                 (T T]
               (NAMES (APPLY* PRINTFN NAME)))
            (COND
               ([AND (NEQ EPOS IPOS)
                       (NOT (fetch (FX INVALIDP) of (SETQ IPOS (COND
                                                                      (ALINKS (fetch (FX ALINK) of IPOS))
                                                                      (T (fetch (FX CLINK) of IPOS]
                 (GO POSLP)))
            (RETURN T])
(\SCANFORNTENTRY
                                                                        ; Edited 18-Feb-91 15:18 by jds
    ;; Scan thru the name table pointedto by NMT, looking for the name of the variable with offset entry NTENTRY, which must be in the form
    ;; appropriate to the architecture (2- or 3-byte).
    (bind NM for NT1 from (fetch (FNHEADER OVERHEADWORDS) of T) by (CONSTANT (WORDSPERNAMEENTRY)) as NT2
       from (IPLUS (fetch (FNHEADER OVERHEADWORDS) of T)
                    (fetch (FNHEADER NTSIZE) of NMT))
       by (CONSTANT (WORDSPERNTOFFSETENTRY)) do (COND
                                                         ((NULL-NTENTRY (SETQ NM (GETSTKNAMEENTRY NMT NT1)))
                                                          (RETURN)))
                                                      (COND
                                                         ((IEOP NTENTRY (GETSTKNTOFFSETENTRY NMT NT2))
                                                          (RETURN (\INDEXATOMVAL NM])
```

Page 27

```
{MEDLEY}<sources>LLINTERP.;1 (\PRINTSTK cont.)
                                                                                                                               Page 28
    (PRINTNUM .17 I)
(PRIN1 ": ")
     (PRINTNUM .17 (GETBASE \STACKSPACE I))
     (PRINTNUM .17 (GETBASE \STACKSPACE (ADD1 I)))
(\PRINTFRAME
  [LAMBDA (FRAME PRINTFN VARSONLY)
                                                                              ; Edited 30-Jan-91 01:48 by jds
    (PROG ((NMT (fetch (FX NAMETABLE) of FRAME))
              (I 0)
              (FT (fetch (FX FIRSTTEMP) of FRAME))
              TMP NLOCALS)
             COND
                ((NOT VARSONLY)
                  (\PRINTSTK FRAME)
                  (PRIN1 "[")
                  (PROGN (PSTKFLD FAST "F, " FAST)

(PSTKFLD INCALL "C, " INCALL)

(PSTKFLD VALIDNAMETABLE "V, " VALIDNAMETABLE)
                          (PSTKFLD NOPUSH "N, " NOPUSH)
(PSTKFLD USECNT "USE=" (NEQ USECNT 0)
                                  NIL ", ")
                          (PSTKFLD SLOWP "X, " SLOWP)
                          (PSTKFLD ALINK " alink] " T))
                  (TERPRI)
                  (PSTK 2 (FNHEADER "[fn header] T))
                 (PSTK 4 (NEXTBLOCK "[next, pc]" T))
(PSTK 6 (NAMETABLE "[nametable]" T))
(PSTK 8 (BLINK "[blink, clink]" T]
             (SETQ NLOCALS (fetch (FNHEADER NLOCALS) of NMT))
             [for old I from (fetch (FX FIRSTPVAR) of FRAME) by WORDSPERCELL while (ILESSP I FT) as J from 0
                do (OR VARSONLY (\PRINTSTK I))
                    (COND
                        [(ILESSP J NLOCALS)
                         COND
                             ((OR (SETQ TMP (\SCANFORNTENTRY NMT (MAKE-NTENTRY PVARCODE J)))
(AND (NEQ VARSONLY T)
                                          (SETQ TMP "local")))
                              (COND
                                  ((fetch (PVARSLOT BOUND) of (ADDSTACKBASE I))
                                   (AND VARSONLY (SPACES 3))
                                   (PRIN2 TMP)
                                   (SPACES 1)
(APPLY* PRINTFN (\GETBASEPTR (ADDSTACKBASE I)
                                                              0)))
                                  ((NOT VARSONLY)
                                   (printout NIL TMP " [unbound] " T]
                        ((NOT VARSONLY)
                         COND
                             ((fetch (FVARSLOT LOOKEDUP) of (ADDSTACKBASE I))
                                                                              COND
                                                                                 ((EQ [SETQ TMP (\HILOC (fetch (FVARSLOT
                                                                                                                            BINDINGPTR
                                                                                                                 of (ADDSTACKBASE
                                                                                                                     I]
                                                                                      \STACKHI)
                                                                                  " on stack]")
                                                                              ((NEQ (FLOOR TMP 2)
(\HILOC \VALSPACE)); See comment in BOUNDP
                                                                                 " non-stack binding]")
(T " top value]")))
                                                                            (T " not looked up]"))
                                      T))
                             (T (printout NIL "[padding]" T]
             (COND
                 ((NOT VARSONLY)
                  (SETQ FT (fetch (FX NEXTBLOCK) of FRAME))
                                                                              ; 2 = WORDSPERCELL but for doesn't translate correctly with ; WORDSPERCELL
                  (for old I by 2 while (ILESSP I FT) do
                                                               (\PRINTSTK I)
                                                                   (fetch (PVARSLOT BOUND) of (ADDSTACKBASE I))
(APPLY* PRINTFN (\GETBASEPTR (ADDSTACKBASE I)
                                                                  (T (TERPRI])
(\PRINTBF
  [LAMBDA (BL NMT PRINTFN VARSONLY)
                                                                              : Edited 30-Jan-91 01:49 by ids
    [bind NM for I from (fetch (BF IVAR) of BL) by 2 as J from 0 to (SUB1 (fetch (BF NARGS) of BL)) do (OR VARSONLY (\PRINTSTK I))
            COND
```

```
{MEDLEY}<sources>LLINTERP.;1 (\PRINTBF cont.)
```

```
([OR (SETQ NM (\SCANFORNTENTRY [OR NMT (RETURN (OR VARSONLY (TERPRI]
                                    (MAKE-NTENTRY IVARCODE J)))
                   (AND (NEQ VARSONLY T)
                         (SETQ NM '*local*]
               (AND VARSONLY (SPACES 3))
               (PRIN2 NM)
              (SPACES 1)
(APPLY* PRINTFN (GETBASEPTR \STACKSPACE I
       finally (OR VARSONLY (while (ILESSP I BL) do (\PRINTSTK I)
                                                   (printout NIL "[padding]" T)
                                                   (add I 2]
    (COND
       ((NOT VARSONLY)
        (\PRINTSTK BL)
        COND
           ((fetch (BF RESIDUAL) of BL) (PRIN1 "residual ")))
        (COND
           ((NEQ (fetch (BF USECNT) of BL)
                 0)
            (printout NIL "usecnt= " (fetch (BF USECNT) of BL)
        (TERPRII)
)
(DECLARE%: EVAL@COMPILE DONTCOPY
(RPAQQ RAIDCOMS
       ((MACROS PSTKFLD PRINTSTKFIELDS PSTK PRINTVA)
        (ADDVARS (RDCOMS (FNS RAIDCOMMAND RAIDSHOWFRAME RAIDSTACKCMD RAIDROOTFRAME PRINTADDRS PRINTVA READVA
                               READOCT READATOM SHOWSTACKBLOCKS SHOWSTACKBLOCK1 PRINCOPY NOSUCHATOM)
                         (FNS \BACKTRACE \STKNAME \PRINTBF \PRINTFRAME \SCANFORNTENTRY \PRINTSTK))
               (EXPANDMACROFNS PSTKFLD PRINTSTKFIELDS PSTK PRINTVA))
        (ADDVARS (DONTCOMPILEFNS RAIDCOMMAND RAIDSHOWFRAME RAIDSTACKCMD RAIDROOTFRAME PRINTADDRS PRINTVA READVA
                        READATOM READOCT SHOWSTACKBLOCKS SHOWSTACKBLOCK1 PRINCOPY NOSUCHATOM)))))
(DECLARE%: EVAL@COMPILE
(PUTPROPS PSTKFLD MACRO [(FLD STR TEST FMT STR2)
                            (PROG ((FLD (fetch (FX FLD) of FRAME)))
                                   (DECLARE (LOCALVARS FLD))
                                   COND
                                      (TEST (PRIN1 'STR)
                                            (SELECTQ (CONSTANT (NTHCHAR 'STR -1))
                                                 (= (printout NIL %, FLD STR2))
                                                 NIL)
                                            T])
(PUTPROPS PRINTSTKFIELDS MACRO [FIELDS (CONS 'PROGN (MAPCAR FIELDS (FUNCTION (LAMBDA (X)
                                                                                    (CONS 'PSTKFLD X1)
(PUTPROPS PSTK MACRO ((N . FIELDS)
                         (\PRINTSTK (IPLUS FRAME N))
                         (PRINTSTKFIELDS . FIELDS)
                         (TERPRI)))
(PUTPROPS PRINTVA MACRO [LAMBDA (X)
                            (printout NIL "{" (HILOC X)
                                    (LOLOC X)
                                    "}"])
(ADDTOVAR RDCOMS (FNS RAIDCOMMAND RAIDSHOWFRAME RAIDSTACKCMD RAIDROOTFRAME PRINTADDRS PRINTVA READVA READOCT
                        READATOM SHOWSTACKBLOCKS SHOWSTACKBLOCK1 PRINCOPY NOSUCHATOM)
                   (FNS \BACKTRACE \STKNAME \PRINTBF \PRINTFRAME \SCANFORNTENTRY \PRINTSTK))
(ADDTOVAR EXPANDMACROFNS PSTKFLD PRINTSTKFIELDS PSTK PRINTVA)
(ADDTOVAR DONTCOMPILEFNS RAIDCOMMAND RAIDSHOWFRAME RAIDSTACKCMD RAIDROOTFRAME PRINTADDRS PRINTVA READVA
                                 READATOM READOCT SHOWSTACKBLOCKS SHOWSTACKBLOCK1 PRINCOPY NOSUCHATOM)
(DEFINEQ
(CCODEP
  [LAMBDA (FN)
                                                                  ; Edited 30-Jan-87 13:36 by Pavel
    (COND
       [(LITATOM FN)
           ((fetch (LITATOM CCODEP) of FN)
            (NOT (fetch (LITATOM PSEUDOCODEP) of FN)))
           (T (TYPEP (fetch (LITATOM DEFPOINTER) of FN)
                     'COMPILED-CLOSURE]
       (T (CL:COMPILED-FUNCTION-P FN])
```

```
(EXPRP
  [LAMBDA (FN)
                                                                             (* lmm "17-FEB-82 23:50")
    (PROG ((DEF FN))
             COND
                ((LITATOM DEF)
                 COND
                     ((fetch (LITATOM CCODEP) of DEF)
(RETURN (fetch (LITATOM PSEUDOCODEP) of DEF]
                  (SETQ DEF (fetch (LITATOM DEFPOINTER) of DEF]
             (RETURN (COND
                           ((LISTP DEF)
                            T])
(SUBRP
  [LAMBDA (FN)
                                                                             (* lmm "17-AUG-81 21:57")
    NIL1)
(FNTYP
  [LAMBDA
    AMBDA (FN)
(PROG ((DEF FN))
[COND
                                                                             (* bvm%: " 7-Jul-86 16:43")
                ((LITATOM DEF)
                  (SETQ DEF (fetch (LITATOM DEFINITIONCELL) of DEF))
                     ((fetch (DEFINITIONCELL PSEUDOCODEP) of DEF)
                     (SETQ DEF (\PSEUDOCODE.REALDEF DEF))
((PROG1 (fetch (DEFINITIONCELL CCODEP) of DEF)
(SETQ DEF (fetch (DEFINITIONCELL DEFPOINTER) of DEF)))
(RETURN (\CCODEFNTYP DEF]
             (RETURN (COND
                           ((LISTP DEF)
                            (SELECTQ (CAR DEF)
                                  (CL:LAMBDA 'EXPR*)
                                  ([LAMBDA OPENLAMBDA]
                                           ((AND (NLISTP (SETQ DEF (CADR DEF)))
                                                  DEF)
                                            'EXPR*)
                                           (T 'EXPR)))
                                  (NLAMBDA (COND
                                                ((AND (NLISTP (SETQ DEF (CADR DEF)))
                                                        DEF)
                                                 'FEXPR*)
                                                (T 'FEXPR)))
                                  (FUNARG 'EXPR)
                                 NIL))
                           ((TYPEP DEF 'COMPILED-CLOSURE)
                            (\CCODEFNTYP (fetch (COMPILED-CLOSURE FNHEADER) of DEF])
(ARGTYPE
  [LAMBDA (FN)
(LET ((DEF FN))
                                                                             (* bvm%: "16-Jul-86 22:47")
           (CL:TYPECASE DEF
               (CL:SYMBOL (COND
                                ((PROG1 (fetch (LITATOM CCODEP) of DEF)
(SETQ DEF (fetch (LITATOM DEFPOINTER) of DEF)))
                                  (\CCODEARGTYPE DEF))
                                (DEF (ARGTYPE DEF))))
               (CONS (SELECTQ (CAR DEF)
                            (CL:LAMBDA 2)
                            ([LAMBDA OPENLAMBDA]
                                  (COND
                                     ((AND (NLISTP (SETQ DEF (CADR DEF)))
                                            DEF)
                                      2)
                                     (T 0)))
                            (NLAMBDA (COND
                                           ((AND (NLISTP (SETQ DEF (CADR DEF)))
                                                  DEF)
                                           3)
                                           (T 1)))
                            (FUNARG (ARGTYPE (CADR DEF)))
                            (SELECTQ (FNTYP DEF)
                                  (EXPR 0)
                                 (FEXPR 1)
                                  (EXPR* 2)
                                 (FEXPR* 3)
                                 NIL)))
               (CLOSURE 2)
                (COMPILED-CLOSURE (\CCODEARGTYPE (fetch (COMPILED-CLOSURE FNHEADER) of DEF))))])
```

```
{MEDLEY} < sources > LLINTERP.; 1 (NARGS cont.)
  [LAMBDA (FN)
                                                                         (* bvm%: " 7-Jul-86 17:07")
    (LET ((DEF FN))
          (COND
             ([AND (LITATOM DEF)
                     (PROG1 (fetch (LITATOM CCODEP) of DEF)
                         (SETQ DEF (fetch (LITATOM DEFPOINTER) of DEF)))]
              (\CCODENARGS DEF))
              ((LISTP DEF)
              (SELECTQ (CAR DEF)
                    (CL:LAMBDA 1)
                    ([LAMBDA NLAMBDA OPENLAMBDA]
                         (COND
                            ((NULL (SETQ DEF (CADR DEF)))
                            ((NLISTP DEF)
                             1)
                            (T (in DEF sum 1))))
                    (FUNARG (NARGS (CADR DEF)))
                   NIL))
             ((TYPEP DEF 'COMPILED-CLOSURE)
              (\CCODENARGS (fetch (COMPILED-CLOSURE FNHEADER) of DEF])
(ARGLIST
  [LAMBDA (FN SMARTE
(PROG ((DEF FN)
          (FN SMARTP)
                                                                         ; Edited 15-Jan-88 15:10 by bvm:
             TEMP)
            [COND
                ((LITATOM DEF)
                 COND
                             (fetch (LITATOM CCODEP) of DEF)
                     (SETQ DEF (fetch (LITATOM DEFPOINTER) of DEF)))
(RETURN (\CCODEARGLIST DEF SMARTP)))
                    ((NULL DEF)
                     (SETQ DEF
                                 (GETPROP FN 'EXPR]
            [RETURN (COND
                          ((LISTP DEF)
                           (SELECTQ (CAR DEF)
                                (CL:LAMBDA 'U)
                                ([LAMBDA NLAMBDA OPENLAMBDA]
                                     (CADR DEF)
                                (FUNARG (ARGLIST (CADR DEF)))
                                (GO UNDEF)))
                          ((TYPEP DEF 'COMPILED-CLOSURE)
                           (\CCODEARGLIST (fetch (COMPILED-CLOSURE FNHEADER) of DEF)
                                  SMARTP))
                         (T (GO UNDEF)
       UNDEF
            (COND
                ((AND (SETQ DEF (FNCHECK FN T))
                       (NEQ DEF FN))
               (RETURN (ARGLIST DEF)))
(T (ERROR '"Args not available:" FN])
(\CCODEARGLIST
                                                                         ; Edited 10-May-88 12:18 by MASINTER
  [LAMBDA (FNHD SMARTP)
    ;; Computes the arglist for raw code object FNHD. If SMARTP is true, we're allowed to return a Common Lisp arg list if we find one; otherwise, we
    ;; have to comply with Interlisp arglist semantics.
    (PROG ((N (fetch (FNHEADER NA) of FNHD))
             IVARS SIZE LOCALSIZE ENDT)
            COND
                                                                         ; No args
                 (RETURN NIL))
                ((AND (< N 0)
                       (NOT SMARTP))
                                                                         ; LAMBDA*
                 (RETURN 'U]
            (SETQ SIZE (fetch (FNHEADER NTSIZE) of FNHD))
            [COND
                ((EQ [SETQ LOCALSIZE (- (FOLDLO (if (fetch (FNHEADER NATIVE) of FNHD)
                                                         then (- (fetch (FNHEADER STARTPC) of FNHD)
                                                      else (fetch (FNHEADER STARTPC) of FNHD))
                                                   BYTESPERWORD)
                                           (SETQ ENDT (+
                                                            (fetch (FNHEADER OVERHEADWORDS) of T)
                                                            COND
                                                               ((EQ SIZE 0)
                                                                        : No nametable, but there's a guad of zeros there anyway
                                                                WORDSPERQUAD)
                                                               (T (UNFOLD SIZE 2]
                                                                        ; Nothing extra here
                     0)
                   LOCALSIZE WORDSPERCELL)
                                                                         ; There is a second nametable between the first and the code.
                 (SETQ IVARS (\CCODEIVARSCAN FNHD ENDT (FOLDLO LOCALSIZE 21
                ((AND (LISTP (SETQ ENDT (\GETBASEPTR FNHD ENDT)))
```

(fetch (FNHEADER ARGTYPE) of FNH)))

;; CONSTANTS mechanism

(PUTPROPS \CCODEARGTYPE MACRO ((FNH)

(DEFINEQ

```
(CONSTANTS
  [NLAMBDA VARS
                                                                        (* rmk%: " 3-Jan-84 13:20")
     (OR COMPVARMACROHASH (SETQ COMPVARMACROHASH (HASHARRAY 100)))
    [for x in VARS do (COND
                          ((LISTP X)
                            (PUTHASH (CAR X)
                                   (LIST 'CONSTANT (CADR X))
                                   COMPVARMACROHASH))
                           (T (PUTHASH X (LIST 'CONSTANT X)
                                     COMPVARMACROHASH]
    VARS])
(CONSTANTEXPRESSIONP
  [LAMBDA (FORM)
(COND
                                                                        ; Edited 21-Jan-91 23:45 by jds
        [(LITATOM FORM)
         COND
            ((OR (NULL FORM)
                  (EQ FORM T))
            (LIST FORM))
((AND COMPVARMACROHASH (SETQ FORM (GETHASH FORM COMPVARMACROHASH)))
(CONSTANTEXPRESSIONP FORM]
       [(LISTP FORM)
(SELECTQ (CAR FORM)
              (QUOTE (CDR FORM))
              (FUNCTION (AND (LITATOM (CADR FORM))
                                (NULL (CDDR FORM))
(CDR FORM)))
              (CONSTANT [LET
                               (VALUE)
                                SETQ VALUE (NLSETQ (EVAL (CADR FORM)
                               (COND
                                  (VALUE
                                         (LIST (CAR VALUE)))
                                  (T (SETQ FORM (COMPILER: OPTIMIZE-AND-MACROEXPAND (CADR FORM)
                                                          *BC-MACRO-ENVIRONMENT*
                                                          (COMPILER: MAKE-CONTEXT : VALUES-USED 1 : PREDICATE-P NIL)))
                                      (LIST (EVAL FORM])
              (COND
                 [(FMEMB (CAR FORM)
                          CONSTANTFOLDFNS)
                  (for x in (CDR FORM) collect (CAR (OR (CONSTANTEXPRESSIONP X)
                                                          (RETURN)))
                     finally (RETURN (LIST (APPLY (CAR FORM)
                                                    $$VAL]
                 ((NOT (GETD (CAR FORM)))
                   (PROG ((MAC (GETMACROPROP (CAR FORM)
                                        COMPILERMACROPROPS)))

D MAC [NOT (EQUAL FORM (SETQ FORM (MACROEXPANSION FORM MAC]
(CONSTANTEXPRESSIONP FORM]
                          (RETURN (AND MAC
        ((NUMBERP FORM)
         (LIST FORM])
(RPAQ? COMPVARMACROHASH (HASHARRAY 100))
;; We need this initialized for the INIT, so don't put it off. (It used to start out NIL and get set later)
(ADDTOVAR CONSTANTFOLDENS PLUS IPLUS TIMES ITIMES DIFFERENCE IDIFFERENCE QUOTIENT IQUOTIENT IMIN IMAX IABS
                                     LLSH LRSH LOGOR LOGXOR LOGAND OR AND)
(DECLARE%: DOEVAL@COMPILE DONTCOPY
(GLOBALVARS COMPVARMACROHASH CONSTANTFOLDFNS)
(DECLARE%: EVAL@COMPILE DONTCOPY DONTEVAL@LOAD
(DECLARE%: DOEVAL@COMPILE DONTCOPY
(LOCALVARS . T)
(DECLARE%: DOEVAL@COMPILE DONTCOPY
(SPECVARS *TAIL* *FN* *FORM* *ARGVAL*)
(DECLARE%: EVAL@COMPILE DONTCOPY
(ADDTOVAR LAMS FAULTEVAL FAULTAPPLY)
(DECLARE%: DONTEVAL@LOAD DOEVAL@COMPILE DONTCOPY COMPILERVARS
```

(ADDTOVAR LAMA APPLY* \INTERPRETER)

(PUTPROPS **LLINTERP COPYRIGHT** ("Venue & Xerox Corporation" T 1981 1982 1983 1984 1985 1986 1987 1988 1990 1991 1992 1994 1995))

{MEDLEY}<sources>LLINTERP.;1 28-Jun-2024 18:34:03 -- Listed on 30-Jun-2024 13:16:02 --

FUNCTION INDEX

	FUNCTION INDEX	
AND 16 APPLY 8 APPLY 8 APPLY* 8 ARGLIST 31 ARGTYPE 30 BACKTRACE 27 BLIPSCAN 21 BLIPVAL 20 BOUNDP 10 CCODEP 29 COND 17 CONSTANTEXPRESSIONP 33 CONSTANTS 33 DEFEVAL 9 ENVAPPLY 18 ERRORSET 14 SI::ERRORSET-PRINT-FUNCTION 14 EVAL 7 EVALA 13 EVALV 10 EXPRP 30 FNTYP 30 FUNCTION 18 GO 13 LET 14 LET* 15 NARGS 30 NOSUCHATOM 26 OR 17	PRINCOPY 26 PRINTADDRS 25 PROG 12 PROG1 17 PROGN 17 PROGN 16 RAIDCOMMAND 22 RAIDROOTFRAME 25 RAIDSHOWFRAME 24 RAIDSTACKCMD 24 READATOM 25 READATOM 25 READVA 25 RETAPPLY 19 RETEVAL 19 RETEVAN 13 SET 10 SETBLIPVAL 20 SETQ 11 SHOWSTACKBLOCK1 26 STKAPPLY 19 STKEVAL 19 SUBRP 30 \BACKTRACE 27 \CCODEARGLIST 31 \CKAPPLYARGS 9	\ENVCALL.UFN
	VARIABLE INDEX	
CLISPARRAY18 DONTCOMPILEFNS COMPVARMACROHASH .33 EXPANDMACROFNS CONSTANTFOLDFNS .33 LAMBDASPLST	329 LAMS	MS29 \DEFEVALFNS1729 \EVALHOOK17 AMES21
	MACRO INDEX	
PROPERTY INDEX		
LAMBDATRANFNS32		

LAMBDATRANFNS32