```
7-Feb-2021 11:52:02 {DSK}<home>larry>ilisp>medley>sources>LLPARAMS.;3
 File created:
  changes to:
                (MACROS EMADDRESS)
previous date:
               31-Jan-98 09:16:51 {DSK}<home>larry>ilisp>medley>sources>LLPARAMS.;2
 Read Table:
               INTERLISP
    Package:
               INTERLISP
       Base:
               10
     Format:
               XCCS
(RPAQQ LLPARAMSCOMS
        :: This file defines the constants that control how a SYSOUT is laid out.
         (FNS MAKERECORD)
         ;; When you change the SYSOUT's layout in this file, you must also
         ;; Recreate RDSYS in the library, using (DORENAME 'R)
         ;; Recompile DLFIXINIT and anything else that uses the constants defined here.
         ;; Recompile LLFAULT. recompile VMEM
         (DECLARE%: DONTCOPY (EXPORT (CONSTANTS (WINDFLG T))
                                       ;; INITCONSTANTS are constants (e.g. \LISTPDTD) to be defined at init time.
                                       (VARS INITCONSTANTS MISCSTATSLAYOUT IFPAGELAYOUT MAIKO.IFPAGELAYOUT
                                              IOPAGELAYOUT)
                                       [CONSTANTS * (for X in INITCONSTANTS when (FIXP (CADR X))
                                                           collect
                                                            (LIST (CAR X)
                                                                   (CADR X]
                                        (CONSTANTS * \MPERRORS) (GLOBALVARS * (for X in INITCONSTANTS when [AND (NEQ (CAR X)
                                                                                              (NOT (FIXP (CADR X]
                                                             collect
                                                             (CAR X)))
                                          * (LIST (MAKERECORD 'MISCSTATS MISCSTATSLAYOUT)
                                                    (COND ((EQ \MACHINETYPE \MAIKO)
                                                            (MAKERECORD 'IFPAGE MAIKO.IFPAGELAYOUT))
                                                          (T (MAKERECORD 'IFPAGE IFPAGELAYOUT)))
                                                    (MAKERECORD 'IOPAGE IOPAGELAYOUT)))
                                        (MACROS EMADDRESS EMGETBASE EMPUTBASE EMULATORSEGMENT EMPOINTER EMADDRESSP)))
         (PROP MAKEFILE-ENVIRONMENT LLPARAMS)))
;; This file defines the constants that control how a SYSOUT is laid out.
(DEFINEQ
(MAKERECORD
  [LAMBDA (NAME LAYOUT)
                                                                        (* bvm%: "29-NOV-82 17:40")
    (PROG ((I 0)
            PTRS M NAM)
           (RETURN
             '(BLOCKRECORD %, NAME %,
                     [for X in LAYOUT
                        collect (CONS (SETQ NAM (CAR X))
                                       (COND
                                          ((EQ NAM '*)
                                           (CDR X))
                                          (T (PROG1 [COND
                                                         [[FIXP (SETQ M (CAR (SETQ X (CDR X]
                                                         (LIST M (CAR (SETQ X (CDR X)
(T (SETQ M (SELECTQ (CAR X)
                                                                          ((FIXP FULLXPOINTER)
                                                                               (OR (EVENP I WORDSPERCELL)
                                                                                    (ERROR "Record field not aligned"
                                                                                            (CONS NAM X)))
                                                                          2)
(WORD 1)
                                                                          (SHOULDNT)))
                                                            (LIST (CAR X]
                                                  [COND
                                                     ((CADDR X)
                                                       (SETQ PTRS (CONS (LIST (PACK* NAM 'PTR)
                                                                                 (\ADDBASE DATUM %, I))
                                                                         PTRS1
                                                  (add I M))]
                     [AND PTRS '((ACCESSFNS %, NAME %, PTRS]
                     (CREATE (\ALLOCBLOCK %, (FOLDHI I WORDSPERCELL])
)
```

;; backspace kludge

```
;; When you change the SYSOUT's layout in this file, you must also
  Recreate RDSYS in the library, using (DORENAME 'R)
  Recompile DLFIXINIT and anything else that uses the constants defined here.
  Recompile LLFAULT. recompile VMEM
(DECLARE%: DONTCOPY
;; FOLLOWING DEFINITIONS EXPORTED
(DECLARE%: EVAL@COMPILE
(RPAQQ WINDFLG T)
(CONSTANTS (WINDFLG T))
(RPAQQ INITCONSTANTS
;;; (LISPNAME VALUE BCPLNAME UCODENAME)
         (CDRCODING 1 T T)
                                                                       ; IF CDRCODING=0, CDR CODING IS OFF, OTHERWISE ON
        ;; type numbers -- repeated on LLBASIC too
         (\SMALLP 1 SMALLTYPE SmallType)
         (\FIXP 2 INTEGERTYPE FixpType)
         (\FLOATP 3 FLTPTTYPE FloatpType)
         (\LITATOM 4 ATOMTYPE AtomType)
         (\LISTP 5 LISTTYPE ListType)
         (\ARRAYP 6 ARRAYPTRTYPE ArrayType)
         (\STRINGP 7 STRINGPTRTYPE)
         (\STACKP 10Q)
         (\CHARACTERP 11Q)
         (\VMEMPAGEP 12Q NIL VMemPagePType)
         (\STREAM 13Q NIL STREAMTYPE)
        :: TYPE TABLE CONSTANTS - - - - -
         (\TT.TYPEMASK 3777Q TTTypeMask T)
         (\TT.NOREF 100000Q NIL T)
         (\TT.SYMBOLP 40000Q NIL T)
         (\TT.FIXP 20000Q)
         (\TT.NUMBERP 10000Q)
         (\TT.ATOM 4000Q)
        (\PMblockSize 40Q PMBLOCKSIZE) (\STATSsize 10Q T)
         (\NumPMTpages 10Q)
         (\EmptyPMTEntry 177777Q T)
(\FirstVmemBlock 2 T)
(\MAXVMPAGE 377775Q)
         (\MAXVMSEGMENT 377Q)
        ;; interface page
         (\IFPValidKey 12743Q T)
        ;; MDS
         (\FirstMDSPage 77776Q)
                                                                       ; Was 37776Q pre 16-meg intiial
         (\MaxMDSPage 1777775Q)
         (\DefaultSecondMDSPage
                                 177774Q)
         (\MDSIncrement 1000Q)
         (\PagesPerMDSUnit 2)
                                                                       ; (FOLDLO \MDSIncrement WORDSPERPAGE)
        ;; arrays
         (\ARRAYSPACE (56Q 0))
         (\FirstArraySegment 56Q)
         (\FirstArrayPage 27000Q)
         (\ARRAYSPACE2 (100Q 0))
         (\DefaultSecondArrayPage 100000Q)
                                                                       ; Was 40000Q before 16meg initial
        ;; stack block constants
         (\StackMask 160000Q T T)
         (\FxtnBlock 1400000 T T)
         (\GuardBlock 160000Q T T)
         (\BFBlock 100000Q T T)
         (\FreeStackBlock 120000Q T T)
         (\NotStackBlock 0)
                                                                       ; none of the above
         (\MinExtraStackWords 40Q T T)
```

(\LastStackAddr 177776Q)

```
(ERASECHARCODE 0 T)
:: GC constants
(\HT1CNT 2000Q NIL T)
(\HTSTKBIT 1000Q NIL T)
(\HTCNTMASK 176000Q NIL T)
(\HTMAINSIZE 200000Q NIL T)
(\HTCOLLSIZE 4000000Q NIL T)
                                                                    ; HTCOLL size in words
(\HTENDFREE 1 NIL T)
(\HTFREEPTR 0 NIL T)
;; pointers and lengths of various data spaces
(\ATOMSPACE (0 0)
        (ATOMspace NIL)
        (atomHiVal NIL))
(\AtomHI 0)
(\CHARHI 7)
                                                                    ; overlap character space and the atom hash table space
(\AtomHashTable (25Q 0)
(AHTspace AHTbase))
(\AtomHTpages 400Q AHTSIZE)
(\LastAtomPage 377Q)
(\MaxAtomFrLst 177777Q)
(\SMALLPOSPSPACE (16Q 0))
(\SmallPosHi 16Q SMALLPOSspace smallpl)
(\SMALLNEGSPACE (17Q 0))
(\SmallNegHi 17Q SMALLNEGspace smallneg)
(\NumSmallPages 1000Q)
;; PNAME SPACEin the old world; used for initial atoms now.
(\PNPSPACE (10Q 0)
        (PNPspace PNPbase))
(\PNAME.HI 10Q)
(\OLDATOMSPACE (54Q 0))
                                                                    ; NEW ATOM SPACE
(\ATOM.HI 54Q)
                                                                    ; HI PART OF NEW ATOM SPACE
;; Definitions in old atom world
(\DEFSPACE (12Q 0)
        (DEFspace DEFbase)
        (DEFspace DEFbase))
(\DEF.HI 12Q)
(\VALSPACE (14Q 0)
        (TOPVALspace TOPVALbase)
(VALspace VALbase))
(\VAL.HI 14Q)
(\PLISTSPACE (2 0)
(PLISTspace PLISTbase))
(\PLIST.HI 2)
(\PAGEMAP (5 0)
        (PAGEMAPspace PAGEMAPbase))
(\NumPageMapPages 400Q)
(\PageMapTBL (24Q 1000Q)
(PMTspace PMTbase))
(\InterfacePage (24Q 0)
(INTERFACEspace INTERFACEbase)
        (INTERFACEspace INTERFACEbase))
(\IOPAGE (0 177400Q))
(\DoveIORegion (0 40000Q))
(\IOCBPAGE (0 400Q))
(\FPTOVP (2 0))
(\MDSTypeTable (30Q 0)
        (MDSTYPEspace MDSTYPEbase)
         (MDSTYPEspace MDSTYPEbase))
(\MDSTTsize 2000Q T)
                                                                    ; in Pages
(\MISCSTATS (24Q 5000Q)
        (STATSspace MISCSTATSbase))
(\UFNTable (24Q 6000Q)
        NIL
        (STATSspace UFNTablebase))
(\UFNTableSize 2)
(\DTDSpaceBase (24Q 10000Q)
        (DTDspace DTDbase)
        (DTDspace DTDbase))
(\DTDSize 22Q T)
(\LISTPDTD (24Q 10132Q))
(\EndTypeNumber 3777Q)
(\LOCKEDPAGETABLE (24Q 70000Q))
(\NumLPTPages 20Q)
(\STACKSPACE (1 0)
        (STACKspace NIL)
(STACKspace NIL))
(\GuardStackAddr 170000Q)
```

```
(\STACKHI 1 T T)
(\HTMAIN (26Q 0)
         (HTMAINspace HTMAINbase)
         (HTMAINspace HTMAINbase))
(\HTMAINnpages 400Q T)
(\HTOVERFLOW (27Q 0)
        NIL
        (NIL HTOVERFLOWbase))
(\HTBIGCOUNT (27Q 100000Q))
(\HTCOLL (34Q 0)
        NIL
        (HTCOLLspace HTCOLLbase))
(\DISPLAYREGION (22Q 0))
(\D1BCPLspace 0 T LEmubrHiVal)
(\D0BCPLspace 0 T)
;; Interface Page locations
(\CurrentFXP 0 T T)
(\ResetFXP 1 T T)
(\SubovFXP 2 T T)
(\KbdFXP 3 T T)
(\HardReturnFXP 4 T T)
(\GCFXP 5)
(\FAULTFXP 6 T T)
(\MiscFXP 16Q T T)
(\TeleRaidFXP 30Q T T)
;; emulator segment locations
(DCB.EM 420Q)
(DISPINTERRUPT.EM 421Q)
(CURSORBITMAP.EM 431Q)
(KBDAD0.EM 177034Q)
(KBDAD1.EM 177035Q)
(KBDAD2.EM 177036Q)
(KBDAD3.EM 177037Q)
(UTILIN.EM 177030Q)
(CURSORX.EM 426Q)
(CURSORY.EM 427Q)
(MOUSEX.EM 424Q)
(MOUSEY.EM 425Q)
(\LispKeyMask 20000Q T T)
(\BcplKeyMask 10400Q T T)
                                                                     ; Machine types
(\MAIKO 3)
(\DOLPHIN 4)
(\DORADO 5)
(\DANDELION 6)
(\DAYBREAK 10Q)
;; FOR DLION (AND DAYBREAK)
(\VP.DISPLAY 11000Q)
(\NP.DISPLAY 312Q)
                                                                      ; for Dorado display 1024x808 pixels / (16 pixels/word x 256
                                                                      ; words/page)
(\NP.WIDEDOVEDISPLAY 3630)
                                                                     ; Wide Dove display 1152x864 pixels
(\WIDEDOVEDISPLAYWIDTH 22000)
(\RP.AFTERDISPLAY 316Q)
                                                                      ; Includes 4 pages for cursor
(\RP.AFTERDOVEDISPLAY 363Q)
                                                                      ; if big screen
(\RP.DISPLAY 0)
(\RP.TEMPDISPLAY 5001Q)
(\RP.MISCLOCKED 5364Q)
                                                                      ; (+ \RP.TEMPDISPLAY \NP.WIDEDOVEDISPLAY)
(\RP.STACK 1400Q)
(\VP.STACK 400Q)
(\RP.MAP 400Q)
(\NP.MAP 400Q)
(\RP.IOPAGE 1000Q)
                                                                      ; The DOVE IOCBPAGE can go anywhere, but should be under
                                                                      ; the 1mbyte range
(\RP.DOVEIOCBPAGE 1037Q)
(\RP.DOVEIORGN 1040Q)
(\VP.DOVEIORGN 100Q)
(\DOVEIORGNSIZE 100Q)
(\VP.IOPAGE 377Q)
(\VP.IFPAGE 12000Q)
(\VP.FPTOVP 10000)
(\NP.FPTOVP 10000Q)
(\RP.FPTOVP 2000Q)
(\RP.STARTBUFFERS 1200Q)
(\VP.TYPETABLE 14000Q)
(\NP.TYPETABLE 2000Q)
(\RP.TYPETABLE 12000Q)
(\RP.TYPETABLE 13000Q)
(\VP.GCTABLE 13000Q)
(\NP.GCTABLE 400Q)
```

Page 5

(KEYBOARDWAITTIME FIXP T) (GCTIME FIXP T) (NETIOTIME FIXP T) (NETIOOPS FIXP T) (SWAPTEMPO FIXP) (SWAPTEMP1 FIXP) (RCLKSECOND FIXP) (SECONDSCLOCK FIXP) (MILLISECONDSCLOCK FIXP) (BASECLOCK FIXP) (RCLKTEMP0 FIXP) (SECONDSTMP FIXP) (MILLISECONDSTMP FIXP) (BASETMP FIXP) (EXCESSTIMETMP FIXP) (CLOCKTEMP0 FIXP) (DISKTEMP0 FIXP) (DISKTEMP1 FIXP)

(TOTALTIME FIXP)
(SWAPWAITTIME FIXP T)
(PAGEFAULTS FIXP T)
(SWAPWRITES FIXP T)
(DISKIOTIME FIXP T)
(DISKOPS FIXP T)

(RPAQQ IFPAGELAYOUT

((CurrentFXP WORD)

(ResetFXP WORD) (SubovFXP WORD) (KbdFXP WORD) (HardReturnFXP WORD) (GCFXP WORD) (FAULTFXP WORD) (EndOfStack WORD)

(TELERAIDTEMP1 FIXP) (TELERAIDTEMP2 FIXP) (TELERAIDTEMP3 FIXP) (LASTUSERACTION FIXP) (DLMOUSETIMER FIXP) (DLMOUSETEMP FIXP)))

(LVersion WORD)

(MinRVersion WORD)
(MinBVersion WORD)
(RVersion WORD)

(BVersion WORD) (MachineType WORD) (MiscFXP WORD)

(Key WORD)

(SerialNumber WORD)

(EmulatorSpace WORD)

(ScreenWidth WORD)
(NxtPMAddr WORD)

(NActivePages WORD)

(NDirtyPages WORD)

; First 7 items are FX values for user and 6 system contexts.

; Stack high-water mark: address of guard block at current end of : stack

; Lisp version, followed by min versions of microcode and Bcpl ; compatible with this Lisp

; Bcpl fills in the actual microcode, Bcpl versions.

; FX for MISC context

; = IFPValidKey if vmem consistent.

; Pup host number (Dorado/Dolphin)

; Hiloc of bcpl space (always zero now)

; Next page to be allocated in secondary page map table

; Length of vmem in use

(XVmemFmapBase WORD)

; not used, but maintained as = NActivePages (filePnPMP0 WORD) Sysout page number of first page of secondary page map table (\PAGEMAP), which is where the secondary map pages ; themselves live (filePnPMT0 WORD) ; Sysout page number of first page of primary page map table (TELERAIDFXP WORD) ; FX for TeleRaid server context (NATIVE-START-MEM-PAGE WORD) ; Unix page where native code starts (NATIVE-LENGTH-PAGE WORD) : Unix page length of native code (NATIVE-PAGE-OFFSET WORD) ; Lisp Disk Page offset of native code (UserNameAddr WORD) ; Addresses in bcpl space (seg 0) of global user name and : password (UserPswdAddr WORD) (StackBase WORD) : Stack address where user stack starts (FAULTHI WORD) ; Microcode for page fault stores fault address here, then does ; context switch to $\ensuremath{\mathsf{FAULTFXP}}$ (FAULTLO WORD) (DEVCONFIG WORD) ; IT'S FOR KB, DISP TYPE Formerly REALPAGETABLE, back when it was always in Bcpl : space. (RPTSIZE WORD) ; Number of entries in Real Page Table (RPOFFSET WORD) ; RP-RPOFFSET => index in table (MAXETHERBYTES WORD) ; Number of bytes available in a pbi, not counting encapsulation (EMBUFVP WORD) ; VP of a one-page emulator buffer (NSHost0 WORD) ; Machine's 48-bit NS host number. Lisp manages to compute ; this on all machines except Dolphin, where Bopl fills it in. (NSHost1 WORD) (NSHost2 WORD) (MDSZone WORD) ; Obsolete -- was used by Dolphin 10MB network code. (MDSZoneLength WORD) (EMUBUFFERS WORD) ; Buffer space in segment 0 for swapping/disk activity (EMUBUFLENGTH WORD) ; Number of words of said space (LASTNUMCHARS WORD) ; No longer used? (SYSDISK WORD) ; Address of sysDisk in Bcpl space -- disk obj for boot partition. (ISFMAP WORD) ;; The following 4 are for \MISCAPPLY* -- note that they are not ref counted, so don't pass the only pointer to something this way! (MISCSTACKFN FULLXPOINTER) (MISCSTACKARG1 FULLXPOINTER) (MISCSTACKARG2 FULLXPOINTER) (MISCSTACKRESULT FULLXPOINTER) (NRealPages WORD) ; Number pages of real memory (LastLockedFilePage WORD) ; Last page of vmem that is locked--booting has to load at least ; that far. (LastDominoFilePage WORD) ; Last sysout page reserved for Dandelion microcode (FPTOVPStart WORD) ; Sysout page where FPTOVP starts (FAKEMOUSEBITS WORD) ; Used to implement fake middle button on 2-button Dandelion. (DL24BitAddressable WORD) ; non-zero if DLion capable of addressing 32MB virtual memory (REALPAGETABLEPTR FULLXPOINTER) Address of real page table, set up by Bcpl (but not chained ; together) (DLLastVmemPage WORD) ; DLion booting microcode puts length of vmem file here. (FullSpaceUsed WORD) ; Non-zero if vmem beyond initial 8MB has been allocated. (FAKEKBDAD4 WORD) (FAKEKBDAD5 WORD) ;; The following 9 items (6 words and 3 pointers) are 3 3-element vectors for the Dorado extended virtual memory code--indexed by 0,1,2 ;; according to which of up to 3 virtual memory backing files you're working with.

```
(NIL WORD)
        (NIL WORD)
        (XVmemFmapHighBase WORD)
        (NIL WORD)
        (NIL WORD)
        (XVmemDiskBase FULLXPOINTER)
        (NIL FULLXPOINTER)
        (NIL FULLXPOINTER)))
(RPAQO MAIKO.IFPAGELAYOUT
       ((CurrentFXP WORD)
        (ResetFXP WORD)
        (SubovFXP WORD)
        (KbdFXP WORD)
        (HardReturnFXP WORD)
        (GCFXP WORD)
        (FAULTFXP WORD)
        (EndOfStack WORD)
        (LVersion WORD)
        (MinRVersion WORD)
        (MinBVersion WORD)
        (RVersion WORD)
        (BVersion WORD)
        (MachineType WORD)
        (MiscFXP WORD)
        (Key WORD)
        (SerialNumber WORD)
        (EmulatorSpace WORD)
        (ScreenWidth WORD)
        (NxtPMAddr WORD)
        (NIL WORD)
        (NIL WORD)
        (filePnPMP() WORD)
        (filePnPMT0 WORD)
        (TELERAIDFXP WORD)
        (NATIVE-START-MEM-PAGE WORD)
        (NATIVE-LENGTH-PAGE WORD)
        (NATIVE-PAGE-OFFSET WORD)
        (UserNameAddr WORD)
        (UserPswdAddr WORD)
        (StackBase WORD)
        (FAULTHI WORD)
        (FAULTLO WORD)
        (DEVCONFIG WORD)
        (RPTSIZE WORD)
        (RPOFFSET WORD)
        (MAXETHERBYTES WORD)
```

```
Page 7
; Bcpl stores isf map pointer to each partition here. First is ; redundant with ISFMAP field above.
; Bcpl stores the highest vm page contained in this or earlier
; partition.
; Lisp stores disk objects here (just a convenient non-faulting
; contiguous block of storage).
; First 7 items are FX values for user and 6 system contexts.
; Stack high-water mark: address of guard block at current end of
: stack
; Lisp version, followed by min versions of microcode and Bcpl
; compatible with this Lisp
; Bcpl fills in the actual microcode, Bcpl versions.
; FX for MISC context
; = IFPValidKey if vmem consistent.
; Pup host number (Dorado/Dolphin)
; Hiloc of bcpl space (always zero now)
; Next page to be allocated in secondary page map table
; WAS NActivePages, Length of vmem in use
 WAS NDirtyPages, not used, but maintained as =
: NActivePages
; Sysout page number of first page of secondary page map table ; (NPAGEMAP), which is where the secondary map pages
; themselves live
; Sysout page number of first page of primary page map table
; FX for TeleRaid server context
; Unix page where native code starts
; Unix page length of native code
; Lisp Disk Page offset of native code
; Addresses in bcpl space (seg 0) of global user name and
; Stack address where user stack starts
; Microcode for page fault stores fault address here, then does
; context switch to FAULTFXP
; IT'S FOR KB, DISP TYPE
; Formerly REALPAGETABLE, back when it was always in Bcpl
space.
; Number of entries in Real Page Table
; RP-RPOFFSET => index in table
; Number of bytes available in a pbi, not counting encapsulation
```

: (Dorado)

((NIL 22Q WORD)

(DLMAINTPANEL WORD NIL T)
(DLFLOPPYCMD WORD)
(DLTTYPORTCMD WORD)
(DLPROCESSORCMD WORD)
(NEWMOUSESTATE WORD)
(DLBEEPCMD WORD)

(DLRS232CMISCCOMMAND WORD) (DLRS232CPUTFLAG WORD) (DLRS232CGETFLAG WORD)

```
(NIL 6 WORD)
        (DLFLOPPY WORD)
        (DLTTYOUT WORD)
        (NIL 1 WORD)
        (DLTTYIN WORD)
        (NIL 1 WORD)
        (DLPROCESSOR2 WORD)
        (DLPROCESSOR1 WORD)
        (DLPROCESSORO WORD)
        (NEWMOUSEX WORD)
        (NEWMOUSEY WORD)
        (DLBEEPFREQ WORD)
        (DLRS232CPARAMETERCSBLO WORD)
        (DLRS232CPARAMETERCSBHI WORD)
        (DLRS232CSETRS366STATUS 3 WORD)
        (DLRS232CPUTCSBLO WORD)
        (DLRS232CPUTCSBHI WORD)
        (DLRS232CGETCSBLO WORD)
        (DLRS232CGETCSBHI WORD)
        (DLRS232CDEVICESTATUS WORD)
        (DLRS232CPARAMETEROUTCOME WORD)
        (DLTODVALID WORD)
        (DLTODLO WORD NIL T)
        (DLTODHI WORD)
        (DLTODLO2 WORD)
        (DLMOUSEX WORD NIL T)
        (DLMOUSEY WORD NIL T)
        (DLUTILIN WORD NIL T)
        (DLKBDAD0 WORD NIL T)
        (DLKBDAD1 WORD NIL T)
        (DLKBDAD2 WORD NIL T)
        (DLKBDAD3 WORD NIL T)
        (DLKBDAD4 WORD NIL T)
        (DLKBDAD5 WORD NIL T)
        (DLLSEPIMAGECSB 40Q WORD)
        (DLIOPHARDWARECONFIG WORD)
        (NIL 13Q WORD)
        (DLRS232CPARAMETERCSBLO.11 WORD)
        (DLRS232CPARAMETERCSBHI.11 WORD)
        (DLRS232CSETRS366STATUS.11 16Q WORD)
        (NIL 74Q WORD)
        (DLMAGTAPE 4 WORD)
        (DLETHERNET 14Q WORD NIL T)
        (NIL 37Q WORD)
        (DLDISPINTERRUPT WORD NIL T)
        (DLDISPCONTROL WORD)
        (DLDISPBORDER WORD)
        (DLCURSORX WORD NIL T)
        (DLCURSORY WORD NIL T)
        (DLCURSORBITMAP 20Q WORD NIL T)))
(DECLARE%: EVAL@COMPILE
(RPAQO CDRCODING 1)
(RPAQQ \SMALLP 1)
(RPAQQ \FIXP 2)
(RPAQQ \FLOATP 3)
(RPAQQ \LITATOM 4)
(RPAQQ \LISTP 5)
(RPAQQ \ARRAYP 6)
(RPAQQ \STRINGP 7)
(RPAQQ \STACKP 10Q)
(RPAQQ \CHARACTERP 11Q)
(RPAQQ \VMEMPAGEP 12Q)
(RPAQQ \STREAM 13Q)
(RPAQQ \TT.TYPEMASK 3777Q)
(RPAQQ \TT.NOREF 100000Q)
(RPAQO \TT.SYMBOLP 400000)
(RPAQO \TT.FIXP 200000)
(RPA00 \TT.NUMBERP 100000)
```

- {MEDLEY}<sources>LLPARAMS.;1
 (RPAQQ \TT.ATOM 4000Q)
- (RPAQQ **\PMblockSize** 40Q)
 (RPAQQ **\STATSsize** 10Q)
- (RPAQQ \NumPMTpages 10Q)
- (RPAQQ \EmptyPMTEntry 177777Q)
- (RPAQQ \FirstVmemBlock 2)
- (RPAQQ \MAXVMPAGE 377775Q)
- (RPAQQ \MAXVMSEGMENT 377Q)
- (RPAQQ \IFPValidKey 12743Q)
- (RPAQQ \FirstMDSPage 77776Q)
- (RPAQQ \MaxMDSPage 1777775Q)
- (RPAQQ \DefaultSecondMDSPage 177774Q)
- (RPAQQ \MDSIncrement 1000Q)
- (RPAQQ \PagesPerMDSUnit 2)
- (RPAQQ \FirstArraySegment 56Q)
- (RPAQQ \FirstArrayPage 27000Q)
- (RPAQQ \DefaultSecondArrayPage 100000Q)
- (RPAQQ \StackMask 160000Q)
- (RPAQQ \FxtnBlock 140000Q)
- (RPAQQ \GuardBlock 160000Q)
- (RPAQQ \BFBlock 100000Q)
- (RPAQQ \FreeStackBlock 120000Q)
- (RPAQQ \NotStackBlock 0)
- (RPAQQ \MinExtraStackWords 40Q)
- (RPAOO ERASECHARCODE 0)
- (RPAQQ \HT1CNT 2000Q)
- (RPAQQ \HTSTKBIT 1000Q)
- (RPAQQ \HTCNTMASK 176000Q)
- (RPAQQ \HTMAINSIZE 200000Q)
- (RPAQQ \HTCOLLSIZE 4000000Q)
- (RPAQQ \HTENDFREE 1)
- (RPAQQ \HTFREEPTR 0)
- (RPAQQ \AtomHI 0)
- (RPAQQ \CHARHI 7)
- (RPAQQ \AtomHTpages 400Q)
- (RPAQQ \LastAtomPage 377Q)
- (RPAQQ \MaxAtomFrLst 177777Q)
- (RPAQQ \SmallPosHi 16Q)
- (RPAQQ \SmallNegHi 17Q)
- (RPAQQ \NumSmallPages 1000Q)
- (RPAQQ \PNAME.HI 10Q)
- (RPAQQ \ATOM.HI 54Q)
- (RPAQQ \DEF.HI 12Q)
- (RPAQQ \VAL.HI 14Q)

- (RPAQQ \PLIST.HI 2)
- (RPAQQ \NumPageMapPages 400Q)
- (RPAQQ \MDSTTsize 2000Q)
- (RPAQQ \UFNTableSize 2)
- (RPAQQ \DTDSize 22Q)
- (RPAQQ \EndTypeNumber 3777Q)
- (RPAQQ \NumLPTPages 20Q)
- (RPAQQ \GuardStackAddr 170000Q)
- (RPAQQ \LastStackAddr 177776Q)
- (RPAQQ \STACKHI 1)
- (RPAQQ \HTMAINnpages 400Q)
- (RPAQQ \D1BCPLspace 0)
- (RPAQQ \D0BCPLspace 0)
- (RPAQQ \CurrentFXP 0)
- (RPAQQ \ResetFXP 1)
- (RPAQQ \SubovFXP 2)
- (RPAQQ \KbdFXP 3)
- (RPAQQ \HardReturnFXP 4)
- (RPAQQ \GCFXP 5)
- (RPAQQ \FAULTFXP 6)
- (RPAQQ \MiscFXP 16Q)
- (RPAQQ \TeleRaidFXP 30Q)
- (RPAQQ DCB.EM 420Q)
- (RPAQQ DISPINTERRUPT.EM 421Q)
- (RPAQQ CURSORBITMAP.EM 431Q)
- (RPAQQ **KBDAD0.EM** 177034Q)
- (RPAQQ KBDAD1.EM 177035Q)
- (RPAQQ KBDAD2.EM 177036Q)
- (RPAQQ **KBDAD3.EM** 177037Q)
- (RPAQQ UTILIN.EM 177030Q)
- (RPAQQ CURSORX.EM 426Q)
- (RPAQQ CURSORY.EM 427Q)
- (RPAQQ MOUSEX.EM 424Q)
- (RPAQQ MOUSEY.EM 425Q)
- (RPAQQ \LispKeyMask 20000Q)
- (RPAQQ \BcplKeyMask 10400Q)
- (RPAQQ \MAIKO 3)
- (RPAQQ \DOLPHIN 4)
- (RPAQQ \DORADO 5)
- (RPAQQ \DANDELION 6)
- (RPAQQ \DAYBREAK 10Q)
- (RPAQQ \VP.DISPLAY 11000Q)
- (RPAQQ \NP.DISPLAY 312Q)

- (RPAQQ \NP.WIDEDOVEDISPLAY 363Q)
- (RPAQQ \WIDEDOVEDISPLAYWIDTH 2200Q)
- (RPAQQ \RP.AFTERDISPLAY 316Q)
- (RPAQQ \RP.AFTERDOVEDISPLAY 363Q)
- (RPAQQ \RP.DISPLAY 0)
- (RPAQQ \RP.TEMPDISPLAY 5001Q)
- (RPAQO \RP.MISCLOCKED 53640)
- (RPAQQ \RP.STACK 1400Q)
- (RPAQQ \VP.STACK 400Q)
- (RPAQQ \RP.MAP 400Q)
- (RPAQQ \NP.MAP 400Q)
- (RPAQQ \RP.IOPAGE 1000Q)
- (RPAQQ \RP.DOVEIOCBPAGE 1037Q)
- (RPAQQ \RP.DOVEIORGN 1040Q)
- (RPAQQ \VP.DOVEIORGN 100Q)
- (RPAQQ \DOVEIORGNSIZE 100Q)
- (RPAQQ \VP.IOPAGE 377Q)
- (RPAQQ \VP.IFPAGE 12000Q)
- (RPAQQ \VP.FPTOVP 1000Q)
- (RPAQQ \NP.FPTOVP 10000Q)
- (RPAQQ \RP.FPTOVP 2000Q)
- (RPAQQ \RP.STARTBUFFERS 1200Q)
- (RPAQQ \VP.TYPETABLE 14000Q)
- (RPAQQ \NP.TYPETABLE 2000Q)
- (RPAQO \RP.TYPETABLE 120000)
- (RPAOO \VP.GCTABLE 130000)
- (RPAQQ \NP.GCTABLE 400Q)
- (RPAQO \RP.GCTABLE 140000)
- (RPAQO \VP.GCOVERFLOW 134000)
- (RPAQQ \NP.GCOVERFLOW 1)
- (RPAQQ \RP.GCOVERFLOW 14400Q)
- (RPAQQ \FP.IFPAGE 2)
- (RPAQQ \VP.IOCBS 1)
- (RPAQQ \VP.PRIMARYMAP 12002Q)
- (RPAQQ \VP.SECONDARYMAP 2400Q)
- (RPAQQ **VP.LPT** 12160Q)
- (RPAQQ \VP.INITSCRATCH 10Q)
- (RPAQQ \VP.RPT 200Q)
- (RPAQQ \VP.BUFFERS 332Q)
- (RPAQQ \DL.PROCESSORBUSY 100000Q)
- (RPAQQ \DL.SETTOD 100001Q)
- (RPAQQ \DL.READTOD 100002Q)
- (RPAQQ \DL.READPID 100003Q)
- (RPAQQ \DL.BOOTBUTTON 100004Q)

```
(CONSTANTS (CDRCODING 1)
        (\SMALLP 1)
        (\FIXP 2)
        (\FLOATP 3)
        (\LITATOM 4)
        (\LISTP 5)
        (\ARRAYP 6)
        (\STRINGP 7)
        (\STACKP 10Q)
        (\CHARACTERP 11Q)
        (\VMEMPAGEP 12Q)
        (\STREAM 130)
        (\TT.TYPEMASK 3777Q)
        (\TT.NOREF 100000Q)
        (\TT.SYMBOLP 40000Q)
        (\TT.FIXP 20000Q)
        (\TT.NUMBERP 10000Q)
        (\TT.ATOM 4000Q)
(\PMblockSize 40Q)
(\STATSSize 10Q)
        (\NumPMTpages 10Q)
        (\EmptyPMTEntry 177777Q)
        (\Emptyrentiality 1...
(\FirstVmemBlock 2)
(\MAXVMPAGE 37775Q)
        (\MAXVMSEGMENT 377Q)
        (\IFPValidKey 12743Q)
(\FirstMDSPage 77776Q)
(\MaxMDSPage 1777775Q)
        (\DefaultSecondMDSPage 177774Q)
        (\MDSIncrement 1000Q)
        (\PagesPerMDSUnit 2)
        (\FirstArraySegment 56Q)
        (\FirstArrayPage 27000Q)
        (\DefaultSecondArrayPage 100000Q)
        (\StackMask 160000Q)
        (\FxtnBlock 140000Q)
        (\GuardBlock 160000Q)
        (\BFBlock 100000Q)
        (\FreeStackBlock 120000Q)
        (\NotStackBlock 0)
        (\MinExtraStackWords 40Q)
        (ERASECHARCODE 0)
        (\HT1CNT 2000Q)
        (\HTSTKBIT 1000Q)
        (\HTCNTMASK 176000Q)
        (\HTMAINSIZE 200000Q)
(\HTCOLLSIZE 400000Q)
        (\HTENDFREE 1)
        (\HTFREEPTR 0)
        (\AtomHI 0)
(\CHARHI 7)
        (\AtomHTpages 400Q)
        (\LastAtomPage 377Q)
        (\MaxAtomFrLst 177777Q)
        (\SmallPosHi 16Q)
        (\SmallNegHi 17Q)
        (\NumSmallPages 1000Q)
        (\PNAME.HI 10Q)
(\ATOM.HI 54Q)
        (\DEF.HI 12Q)
(\VAL.HI 14Q)
        (\PLIST.HI 2)
        (\NumPageMapPages 400Q)
        (\MDSTTsize 2000Q)
        (\UFNTableSize 2)
        (\DTDSize 22Q)
        (\EndTypeNumber 3777Q)
        (\NumLPTPages 20Q)
        (\GuardStackAddr 170000Q)
(\LastStackAddr 177776Q)
        (\STACKHI 1)
        (\HTMAINnpages 400Q)
        (\D1BCPLspace 0)
        (\D0BCPLspace 0)
        (\CurrentFXP 0)
        (\ResetFXP 1)
        (\SubovFXP 2)
        (\KbdFXP 3)
        (\HardReturnFXP 4)
        (\GCFXP 5)
        (\FAULTFXP 6)
(\MiscFXP 16Q)
        (\TeleRaidFXP 30Q)
        (DCB.EM 420Q)
        (DISPINTERRUPT.EM 421Q)
        (CURSORBITMAP.EM 431Q)
```

(\MP.PNAMESFULL 27Q)

```
(KBDAD0.EM 177034Q)
        (KBDAD1.EM 177035Q)
        (KBDAD2.EM 177036Q)
        (KBDAD3.EM 177037Q)
        (UTILIN.EM 177030Q)
        (CURSORX.EM 426Q)
        (CURSORY.EM 427Q)
        (MOUSEX.EM 424Q)
        (MOUSEY.EM 425Q)
        (\LispKeyMask 20000Q)
(\BcplKeyMask 10400Q)
        (\MAIKO 3)
        (\DOLPHIN 4)
        (\DORADO 5)
        (\DANDELION 6)
        (\DAYBREAK 10Q)
(\VP.DISPLAY 11000Q)
(\NP.DISPLAY 312Q)
        (\NP.WIDEDOVEDISPLAY 363Q)
        (\WIDEDOVEDISPLAYWIDTH 2200Q)
        (\RP.AFTERDISPLAY 316Q)
        (\RP.AFTERDOVEDISPLAY 363Q)
        (\RP.DISPLAY 0)
        (\RP.TEMPDISPLAY 5001Q)
        (\RP.MISCLOCKED 5364Q)
        (\RP.STACK 1400Q)
        (\VP.STACK 400Q)
        (\RP.MAP 400Q)
(\NP.MAP 400Q)
        (\RP.IOPAGE 1000Q)
        (\RP.DOVEIOCBPAGE 1037Q)
        (\RP.DOVEIORGN 1040Q)
(\VP.DOVEIORGN 100Q)
        (\DOVEIORGNSIZE 100Q)
        (\VP.IOPAGE 377Q)
        (\VP.IFPAGE 12000Q)
        (\VP.FPTOVP 1000Q)
        (\NP.FPTOVP 10000Q)
        (\RP.FPTOVP 2000Q)
        (\RP.STARTBUFFERS 1200Q)
        (\VP.TYPETABLE 14000Q)
        (\NP.TYPETABLE 2000Q)
        (\RP.TYPETABLE 12000Q)
        (\VP.GCTABLE 13000Q)
        (\NP.GCTABLE 400Q)
        (\RP.GCTABLE 140000)
        (\VP.GCOVERFLOW 13400Q)
        (\NP.GCOVERFLOW 1)
        (\RP.GCOVERFLOW 14400Q)
        (\FP.IFPAGE 2)
        (\VP.IOCBS 1)
        (\VP.PRIMARYMAP 12002Q)
        (\VP.SECONDARYMAP 2400Q)
(\VP.LPT 12160Q)
        (\VP.INITSCRATCH 10Q)
(\VP.RPT 200Q)
        (\VP.BUFFERS 332Q)
        (\DL.PROCESSORBUSY 100000Q)
         (\DL.SETTOD 100001Q)
        (\DL.READTOD 1000020)
         (\DL.READPID 100003Q)
        (\DL.BOOTBUTTON 100004Q))
(RPAQQ \MPERRORS
        ((\MP.OBSOLETEVMEM 1)
         (\MP.INVALIDVMEM 2 "Vmem inconsistent at startup")
         (\MP.IOCBPAGE 3 "No place for IOCB page at startup")
         (\MP.MOB 4 "Map out of bounds")
         (\MP.INVALIDADDR 5)
         (\MP.INVALIDVP 6)
         (\MP.CHAIN.UNAVAIL 7 "Unavailable page on real page table chain")
         (\MP.SELECTLOOP 10Q "Loop in \SELECTREALPAGE") (\MP.NEWPAGE 11Q "Attempt to allocate already existing page")
         (\MP.NEWMAPPAGE 12Q "\DONEWPAGE failed to allocate new map page")
         (\MP.BADLOCKED 13Q "Locked page occupies a file page needed to lock another") (\MP.CLOCKO 14Q "Arg to CLOCKO not an integer box")
         (\MP.RESIDENT 15Q "Fault on resident page")
         (\MP.STACKFAULT 16Q "Fault on stack")
         (\MP.VMEMTOOLONG 200 "Attempt to extend Vmem File beyond fixed limit (8mb)") (\MP.WRITING.LOCKED.PAGE 210 "Writing a locked page with UPDATEKEY = T")
         (\MP.UNINTERRUPTABLE 22Q "Error in uninterruptable system code")
         (\MP.STACKFULL 23Q)
         (\MP.MDSFULL 24Q)
(\MP.UNKNOWN.UFN 25Q)
         (\MP.ATOMSFULL 26Q)
```

```
(\MP.USECOUNTOVERFLOW 30Q)
        (\MP.MDSFULLWARNING 31Q)
        (\MP.BADMDSFREELIST 32Q)
        (\MP.BADARRAYBLOCK 33Q)
        (\MP.BADDELETEBLOCK 34Q)
        (\MP.BADARRAYRECLAIM 35Q)
        (\MP.BIGREFCNTMISSING 36Q "PTR refcnt previously overflowed, but not found in table.")
        (\MP.BIGREFCNTALREADYPRESENT 37Q "PTR already in overflow table")
        (\MP.DELREF0 40Q)
        (\MP.PROCERROR 41Q)
        (\MP.PROCNOFRAME 42Q "Failed to build frame for PROCESS use")
        (\MP.32MBINUSE 43Q)
        (\MP.TOPUNWOUND 44Q "Unexpected (RETTO T)")
        (\MP.STACKRELEASED 45Q)
        (\MP.FLUSHLOCKED 46Q)
        (\MP.MAPNOTLOCKED 470)
        (\MP.UNLOCKINGMAP 50Q)
        (\MP.SWAPDISKERROR 51Q "Hard Disk Error in swapper")
(\MP.BADRUNTABLE 52Q "Malformed run table for vmem file")))
(DECLARE%: EVAL@COMPILE
(RPAQQ \MP.OBSOLETEVMEM 1)
(RPAQ \MP.INVALIDVMEM 2 "Vmem inconsistent at startup")
(RPAQ \MP.IOCBPAGE 3 "No place for IOCB page at startup")
(RPAQ \MP.MOB 4 "Map out of bounds")
(RPAQQ \MP.INVALIDADDR 5)
(RPAQQ \MP.INVALIDVP 6)
(RPAQ \MP.CHAIN.UNAVAIL 7 "Unavailable page on real page table chain")
(RPAQ \MP.SELECTLOOP 10Q "Loop in \SELECTREALPAGE")
(RPAQ \MP.NEWPAGE 11Q "Attempt to allocate already existing page")
(RPAQ \MP.NEWMAPPAGE 12Q "\DONEWPAGE failed to allocate new map page")
(RPAQ \MP.BADLOCKED 130 "Locked page occupies a file page needed to lock another")
(RPAQ \MP.CLOCKO 14Q "Arg to CLOCKO not an integer box")
(RPAQ \MP.RESIDENT 15Q "Fault on resident page")
(RPAO \MP.STACKFAULT 160 "Fault on stack")
(RPAQ \MP.VMEMTOOLONG 20Q "Attempt to extend Vmem File beyond fixed limit (8mb)")
(RPAQ \MP.WRITING.LOCKED.PAGE 21Q "Writing a locked page with UPDATEKEY = T")
(RPAQ \mbox{MP.UNINTERRUPTABLE} 22Q "Error in uninterruptable system code")
(RPAQO \MP.STACKFULL 230)
(RPAQQ \MP.MDSFULL 24Q)
(RPAQQ \MP.UNKNOWN.UFN 25Q)
(RPAQQ \MP.ATOMSFULL 26Q)
(RPAQQ \MP.PNAMESFULL 27Q)
(RPAQQ \MP.USECOUNTOVERFLOW 30Q)
(RPAQQ \MP.MDSFULLWARNING 31Q)
(RPAQQ \MP.BADMDSFREELIST 32Q)
(RPAQQ \MP.BADARRAYBLOCK 33Q)
(RPAQO \MP.BADDELETEBLOCK 340)
(RPAQQ \MP.BADARRAYRECLAIM 35Q)
(RPAQ \MP.BIGREFCNTMISSING 36Q "PTR refent previously overflowed, but not found in table.")
(RPAQ \MP.BIGREFCNTALREADYPRESENT 37Q "PTR already in overflow table")
(RPAQQ \MP.DELREFO 40Q)
(RPAQO \MP.PROCERROR 410)
(RPAQ \MP.PROCNOFRAME 42Q "Failed to build frame for PROCESS use")
```

```
(RPAQQ \MP.32MBINUSE 43Q)
(RPAQ \MP.TOPUNWOUND 44Q "Unexpected (RETTO T)")
(RPAQQ \MP.STACKRELEASED 45Q)
(RPAQQ \MP.FLUSHLOCKED 46Q)
(RPAQQ \MP.MAPNOTLOCKED 47Q)
(RPAQQ \MP.UNLOCKINGMAP 50Q)
(RPAQ \MP.SWAPDISKERROR 51Q "Hard Disk Error in swapper")
(RPAQ \MP.BADRUNTABLE 52Q "Malformed run table for vmem file")
(CONSTANTS (\MP.OBSOLETEVMEM 1)
         (\MP.IOSOLETEVERM 1)
(\MP.INVALIDVMEM 2 "Vmem inconsistent at startup")
(\MP.IOCBPAGE 3 "No place for IOCB page at startup")
(\MP.MOB 4 "Map out of bounds")
          (\MP.INVALIDADDR 5)
          (\MP.INVALIDVP 6)
         (\MP.INVALIDVP 6)

(\MP.CHAIN.UNAVAIL 7 "Unavailable page on real page table chain")

(\MP.SELECTLOOP 10Q "Loop in \SELECTREALPAGE")

(\MP.NEWPAGE 11Q "Attempt to allocate already existing page")

(\MP.NEWMAPPAGE 12Q "\DONEWPAGE failed to allocate new map page")

(\MP.BADLOCKED 13Q "Locked page occupies a file page needed to lock another")

(\MP.CLOCKO 14Q "Arg to CLOCKO not an integer box")

(\MP.RESIDENT 15Q "Fault on resident page")

(\MP.STACKFAULT 16O "Fault on stack")
          (\MP.STACKFAULT 16Q "Fault on stack")
         (\MP.VMEMTOOLONG 200 "Attempt to extend Vmem File beyond fixed limit (8mb)") (\MP.WRITING.LOCKED.PAGE 210 "Writing a locked page with UPDATEKEY = T")
          (\MP.UNINTERRUPTABLE 22Q "Error in uninterruptable system code")
          (\MP.STACKFULL 23Q)
          (\MP.MDSFULL 24Q)
          (\MP.UNKNOWN.UFN 250)
          (\MP.ATOMSFULL 26Q)
          (\MP.PNAMESFULL 27Q)
          (\MP.USECOUNTOVERFLOW 30Q)
          (\MP.MDSFULLWARNING 31Q)
          (\MP.BADMDSFREELIST 32Q)
          (\MP.BADARRAYBLOCK 33Q)
          (\MP.BADDELETEBLOCK 34Q)
          (\MP.BADARRAYRECLAIM 35Q)
          (\MP.BIGREFCNTMISSING 360 "PTR refcnt previously overflowed, but not found in table.")
          (\MP.BIGREFCNTALREADYPRESENT 37Q "PTR already in overflow table")
          (\MP.DELREF0 40Q)
          (\MP.PROCERROR 410)
          (\MP.PROCNOFRAME 42Q "Failed to build frame for PROCESS use")
          (\MP.32MBINUSE 43Q)
          (\MP.TOPUNWOUND 44Q "Unexpected (RETTO T)")
          (\MP.STACKRELEASED 45Q)
          (\MP.FLUSHLOCKED 46Q)
         (\MP.MAPNOTLOCKED 47Q)
(\MP.UNLOCKINGMAP 50Q)
          (\MP.SWAPDISKERROR 510 "Hard Disk Error in swapper")
         (\MP.BADRUNTABLE 52Q "Malformed run table for vmem file"))
(DECLARE%: DOEVAL@COMPILE DONTCOPY
(GLOBALVARS \ARRAYSPACE \ARRAYSPACE2 \ATOMSPACE \AtomHashTable \SMALLPOSPSPACE \SMALLNEGSPACE \PNPSPACE
         \OLDATOMSPACE \DEFSPACE \VALSPACE \PLISTSPACE \PAGEMAP \PageMapTBL \InterfacePage \IOPAGE \DoveIORegion \IOCBPAGE \FPTOVP \MDSTypeTable \MISCSTATS \UFNTable \DTDSpaceBase \LISTPDTD \LOCKEDPAGETABLE \STACKSPACE \HTMAIN \HTOVERFLOW \HTBIGCOUNT \HTCOLL \DISPLAYREGION)
(BLOCKRECORD MISCSTATS ((STARTTIME FIXP)
                                  (TOTALTIME FIXP)
                                  (SWAPWAITTIME FIXP)
                                  (PAGEFAULTS FIXP)
                                 (SWAPWRITES FIXP)
                                  (DISKIOTIME FIXP)
                                 (DISKOPS FIXP)
                                  (KEYBOARDWAITTIME FIXP)
                                  (GCTIME FIXP)
                                  (NETIOTIME FIXP)
                                  (NETIOOPS FIXP)
                                  (SWAPTEMPO FIXP)
                                  (SWAPTEMP1 FIXP)
                                  (RCLKSECOND FIXP)
                                  (SECONDSCLOCK FIXP)
                                  (MILLISECONDSCLOCK FIXP)
                                  (BASECLOCK FIXP)
                                  (RCLKTEMP() FIXP)
                                  (SECONDSTMP FIXP)
```

(FPTOVPStart WORD)

```
(MILLISECONDSTMP FIXP)
                              (BASETMP FIXP)
                              (EXCESSTIMETMP FIXP)
                              (CLOCKTEMP0 FIXP)
                              (DISKTEMPO FIXP)
                              (DISKTEMP1 FIXP)
                              (TELERAIDTEMP1 FIXP)
                              (TELERAIDTEMP2 FIXP)
                              (TELERAIDTEMP3 FIXP)
                              (LASTUSERACTION FIXP)
                              (DLMOUSETIMER FIXP)
                              (DLMOUSETEMP FIXP))
         (CREATE (\ALLOCBLOCK 370)))
(BLOCKRECORD IFPAGE ((CurrentFXP WORD)
                                                                                 ; First 7 items are FX values for user and 6 system contexts.
                           (Reset.FXP WORD)
                          (SubovFXP WORD)
                           (KbdFXP WORD)
                          (HardReturnFXP WORD)
                           (GCFXP WORD)
                          (FAULTFXP WORD)
                                                                                  ; Stack high-water mark: address of guard block at current end of
                          (EndOfStack WORD)
                                                                                  stack
                          (LVersion WORD)
                                                                                  Lisp version, followed by min versions of microcode and Bcpl
                                                                                 ; compatible with this Lisp
                           (MinRVersion WORD)
                          (MinBVersion WORD)
                                                                                 ; Bcpl fills in the actual microcode, Bcpl versions.
                           (RVersion WORD)
                           (BVersion WORD)
                           (MachineType WORD)
                           (MiscFXP WORD)
                                                                                 ; FX for MISC context
                           (Key WORD)
                                                                                  = IFPValidKey if vmem consistent.
                                                                                  Pup host number (Dorado/Dolphin)
                           (SerialNumber WORD)
                           (EmulatorSpace WORD)
                                                                                  ; Hiloc of bcpl space (always zero now)
                           (ScreenWidth WORD)
                           (NxtPMAddr WORD)
                                                                                  Next page to be allocated in secondary page map table
                                                                                  WAS NActivePages, Length of vmem in use
                           (NIL WORD)
                          (NIL WORD)
                                                                                  WAS NDirtyPages, not used, but maintained as =
                                                                                  NActivePages
                          (filePnPMP0 WORD)
                                                                                   Sysout page number of first page of secondary page map table (\PAGEMAP), which is where the secondary map pages
                                                                                   themselves live
                          (filePnPMT0 WORD)
                                                                                   Sysout page number of first page of primary page map table
                          (TELERAIDFXP WORD)
                                                                                  FX for TeleRaid server context
                           (NATIVE-START-MEM-PAGE WORD)
                                                                                   Unix page where native code starts
                                                                                  Unix page length of native code
                          (NATIVE-LENGTH-PAGE WORD)
                                                                                   Lisp Disk Page offset of native code
                           (NATIVE-PAGE-OFFSET WORD)
                                                                                  Addresses in bcpl space (seg 0) of global user name and
                          (UserNameAddr WORD)
                                                                                  password
                          (UserPswdAddr WORD)
                           (StackBase WORD)
                                                                                  Stack address where user stack starts
                                                                                 ; Microcode for page fault stores fault address here, then does ; context switch to FAULTFXP
                          (FAULTHI WORD)
                          (FAULTLO WORD)
                                                                                  IT'S FOR KB.DISP TYPE
                          (DEVCONFIG WORD)
                                                                                  Formerly REALPAGETABLE, back when it was always in Bcpl
                                                                                  space.
                                                                                  Number of entries in Real Page Table RP-RPOFFSET => index in table
                          (RPTSIZE WORD)
                           (RPOFFSET WORD)
                                                                                  Number of bytes available in a pbi, not counting encapsulation
                           (MAXETHERBYTES WORD)
                                                                                   (Dorado)
                                                                                  VP of a one-page emulator buffer
Machine's 48-bit NS host number. Lisp manages to compute
                          (EMBUFVP WORD)
                          (NSHost0 WORD)
                                                                                  this on all machines except Dolphin, where Bcpl fills it in.
                           (NSHost1 WORD)
                           (NSHost2 WORD)
                           (MDSZone WORD)
                                                                                 ; Obsolete -- was used by Dolphin 10MB network code.
                           (MDSZoneLength WORD)
                          (EMUBUFFERS WORD)
                                                                                 ; Buffer space in segment 0 for swapping/disk activity
                                                                                 ; Number of words of said space
                          (EMUBUFLENGTH WORD)
                          ;; The following 2 are available if NEW_STOARGE is specified in C
                          (ProcessSize WORD)
                                                                                  Process size for which can be use as LISP space
                          (StorageFullState WORD)
                                                                                  ; Save last storage state
                          ;; The following 4 are for \MISCAPPLY* -- note that they are not ref counted, so don't pass the only pointer to something this
                          (MISCSTACKFN FULLXPOINTER)
                           (MISCSTACKARG1 FULLXPOINTER)
                          (MISCSTACKARG2 FULLXPOINTER)
                           (MISCSTACKRESULT FULLXPOINTER)
                                                                                  ; Number pages of real memory
                           (NRealPages WORD)
                                                                                  Last page of vmem that is locked--booting has to load at least
                           (LastLockedFilePage WORD)
                                                                                  that far.
                                                                                  Last sysout page reserved for Dandelion microcode
                           (LastDominoFilePage WORD)
                                                                                  Sysout page where FPTOVP starts
```

```
(FAKEMOUSEBITS WORD)
                        (DL24BitAddressable WORD)
                        (REALPAGETABLEPTR FULLXPOINTER)
                        (SYSDISK WORD)
                        (FullSpaceUsed WORD)
                        (FAKEKBDAD4 WORD)
                       ;; The following 9 items (6 words and 3 pointers) are 3 3-element vectors for the Dorado extended virtual memory
                       ;; code--indexed by 0,1,2 according to which of up to 3 virtual memory backing files you're working with.
                       (XVmemFmapBase WORD)
                        (NIL WORD)
                        (NIL WORD)
                        (XVmemFmapHighBase WORD)
                        (NIL WORD)
                        (NTI, WORD)
                        (XVmemDiskBase FULLXPOINTER)
                        (NIL FULLXPOINTER)
                        (NIL FULLXPOINTER)
                        (DLLastVmemPage FIXP)
                        (NActivePages FIXP)
                        (NDirtyPages FIXP)
        (CREATE (\ALLOCBLOCK 53Q)))
(BLOCKRECORD IOPAGE ((NIL 22Q WORD)
                        (DLMAINTPANEL WORD)
                        (DLFLOPPYCMD WORD)
                        (DLTTYPORTCMD WORD)
                        (DLPROCESSORCMD WORD)
                        (NEWMOUSESTATE WORD)
                        (DLBEEPCMD WORD)
                        (DLRS232CMISCCOMMAND WORD)
                        (DLRS232CPUTFLAG WORD)
                        (DLRS232CGETFLAG WORD)
                        (NIL 6 WORD)
                        (DLFLOPPY WORD)
                        (DLTTYOUT WORD)
                        (NIL 1 WORD)
                        (DLTTYIN WORD)
                        (NIL 1 WORD)
                        (DLPROCESSOR2 WORD)
                        (DLPROCESSOR1 WORD)
                        (DLPROCESSORO WORD)
                        (NEWMOUSEX WORD)
                        (NEWMOUSEY WORD)
                        (DIBEEPFREO WORD)
                        (DLRS232CPARAMETERCSBLO WORD)
                        (DLRS232CPARAMETERCSBHI WORD)
                        (DLRS232CSETRS366STATUS 3 WORD)
                        (DLRS232CPUTCSBLO WORD)
                        (DLRS232CPUTCSBHI WORD)
                        (DLRS232CGETCSBLO WORD)
                        (DLRS232CGETCSBHI WORD)
                        (DLRS232CDEVICESTATUS WORD)
                        (DLRS232CPARAMETEROUTCOME WORD)
                        (DLTODVALID WORD)
                        (DLTODLO WORD)
                        (DLTODHI WORD)
                        (DLTODLO2 WORD)
                        (DLMOUSEX WORD)
                        (DLMOUSEY WORD)
                        (DLUTILIN WORD)
                        (DLKBDAD0 WORD)
                        (DLKBDAD1 WORD)
                        (DLKBDAD2 WORD)
                        (DLKBDAD3 WORD)
                        (DLKBDAD4 WORD)
                        (DLKBDAD5 WORD)
                        (DLLSEPIMAGECSB 40Q WORD)
                        (DLIOPHARDWARECONFIG WORD)
                        (NIL 13Q WORD)
                        (DLRS232CPARAMETERCSBLO.11 WORD)
                       (DLRS232CPARAMETERCSBHI.11 WORD)
(DLRS232CSETRS366STATUS.11 16Q WORD)
                        (NIL 74Q WORD)
                        (DLMAGTAPE 4 WORD)
(DLETHERNET 14Q WORD)
                        (NIL 370 WORD)
                        (DLDISPINTERRUPT WORD)
                        (DLDISPCONTROL WORD)
```

non-zero if DLion capable of addressing 32MB virtual memory Address of real page table, set up by Bcpl (but not chained WAS DLLastVmemPage, DLion booting microcode puts length of vmem file here. ; Non-zero if vmem beyond initial 8MB has been allocated. ; Bcpl stores isf map pointer to each partition here. First is ; redundant with ISFMAP field above. ; Bcpl stores the highest vm page contained in this or earlier : partition. ; Lisp stores disk objects here (just a convenient non-faulting ; contiguous block of storage). ; DLion booting microcode puts length of vmem file here. Length of vmem in use ; not used, but maintained as = NActivePages

; Used to implement fake middle button on 2-button Dandelion.

```
{MEDLEY} < sources > LLPARAMS.; 1 (IOPAGE cont.)
                      (DLDISPBORDER WORD)
                      (DLCURSORX WORD)
                      (DLCURSORY WORD)
                      (DLCURSORBITMAP 20Q WORD))
       [ACCESSFNS IOPAGE ((DLCURSORBITMAPPTR (\ADDBASE DATUM 360Q))
                           (DLCURSORYPTR (\ADDBASE DATUM 357Q))
                           (DLCURSORXPTR (\ADDBASE DATUM 356Q))
                           (DLDISPINTERRUPTPTR (\ADDBASE DATUM 353Q))
                           (DLETHERNETPTR (\ADDBASE DATUM 300Q))
                           (DLKBDAD5PTR (\ADDBASE DATUM 103Q))
                           (DLKBDAD4PTR (\ADDBASE DATUM 102Q))
                           (DLKBDAD3PTR (\ADDBASE DATUM 101Q))
                           (DLKBDAD2PTR (\ADDBASE DATUM 1000))
                           (DLKBDAD1PTR (\ADDBASE DATUM 77Q))
                           (DLKBDADOPTR (\ADDBASE DATUM 76Q))
                           (DLUTILINPTR (\ADDBASE DATUM 750))
                           (DLMOUSEYPTR (\ADDBASE DATUM 74Q))
                           (DLMOUSEXPTR (\ADDBASE DATUM 73Q))
                           (DLTODLOPTR (\ADDBASE DATUM 70Q))
                           (DLMAINTPANELPTR (\ADDBASE DATUM 22Q]
       (CREATE (\ALLOCBLOCK 2000)))
(DECLARE%: EVAL@COMPILE
(PUTPROPS EMADDRESS MACRO [ARGS ([LAMBDA (ADDR)
                                        (COND
                                          [(EQ \D1BCPLspace \D0BCPLspace)
                                            (LIST (LIST 'OPCODES 'GCONST 0 0 (LRSH ADDR 10Q)
                                                         (LOGAND ADDR 377Q]
                                           (T '(\VAG2 (fetch EmulatorSpace of \InterfacePage)
                                                      %, ADDR]
                                     (EVAL (CAR ARGS])
(PUTPROPS EMGETBASE MACRO ((OFFSET)
                               (\GETBASE (EMADDRESS OFFSET)
                                      0)))
(PUTPROPS EMPUTBASE MACRO ((OFFSET VAL)
                               (\PUTBASE (EMADDRESS OFFSET)
                                      0 VAL)))
(PUTPROPS EMULATORSEGMENT MACRO (NIL (fetch EmulatorSpace of \InterfacePage)))
(PUTPROPS EMPOINTER MACRO [X (COND
                                    ((NEQ \D1BCPLspace \D0BCPLspace)
(LIST '\VAG2 '(fetch (IFPAGE EmulatorSpace) of \InterfacePage)
                                           (CAR X)))
                                    ((ZEROP (CAR X))
                                    NIL)
                                    (T (LIST '\VAG2 \D0BCPLspace (CAR X])
(PUTPROPS EMADDRESSP MACRO [X (LIST 'EQ (LIST '\HILOC (CAR X))
                                         (COND
                                            ((EQ \D1BCPLspace \D0BCPLspace)
                                             \D0BCPLspace)
```

Page 19

;; END EXPORTED DEFINITIONS

(PUTPROPS LLPARAMS MAKEFILE-ENVIRONMENT (:READTABLE "INTERLISP" :PACKAGE "INTERLISP" :BASE 10Q))

(T '(fetch (IFPAGE EmulatorSpace) of \InterfacePage])

FUNCTION INDEX

CONSTANT INDEX

CDRCODING15	\IFPValidKey15	\NP.WIDEDOVEDISPLAY15	
CURSORBITMAP.EM	\KbdFXP	\NumLPTPages	
CURSORY.EM	\LastStackAddr15	\NumPMTpages	
DCB.EM	\LispKeyMask15	\NumSmallPages15	
DISPINTERRUPT.EM15	\LISTP15	\PagesPerMDSUnit15	
ERASECHARCODE	\LITATOM15	\PLIST.HI15	
KBDAD0.EM	\MAIKO	\PMblockSize	
KBDAD1.EM	\MaxAtomFrLst	\ResetFXP	
KBDAD3.EM	\MAXVMPAGE	\RP.AFTERDISPLAY	
MOUSEX.EM15	\MAXVMSEGMENT15	\RP.AFTERDOVEDISPLAY15	
MOUSEY.EM15	\MDSIncrement15	\RP.DISPLAY15	
UTILIN.EM15	\MDSTTsize15	\RP.DOVEIOCBPAGE	
WINDFLG	\MinExtraStackWords	\RP.DOVEIORGN	
\ATOM.HI	\MP.32MBINUSE20	\RP.GCOVERFLOW	
\AtomHI	\MP.ATOMSFULL20	\RP.GCTABLE	
\AtomHTpages15	\MP.BADARRAYBLOCK20	\RP.IOPAGE15	
\BcplKeyMask15	\MP.BADARRAYRECLAIM20	\RP.MAP	
\BFBlock	\MP.BADDELETEBLOCK	\RP.MISCLOCKED	
\CHARHI	\MP.BADMDSFREELIST20	\RP.STARTBUFFERS	
\CurrentFXP15	\MP.BADRUNTABLE20	\RP.TEMPDISPLAY	
\D0BCPLspace15	\MP.BIGREFCNTALREADYPRESENT20	\RP.TYPETABLE15	
\D1BCPLspace15	\MP.BIGREFCNTMISSING20	\SmallNegHi15	
\DANDELION15	\MP.CHAIN.UNAVAIL20	\SMALLP	
\DAYBREAK	\MP.CLOCK0	\STACKHI	
\DefaultSecondArrayPage15	\MP.FLUSHLOCKED20	\StackMask15	
\DefaultSecondMDSPage15	\MP.INVALIDADDR20	\STACKP15	
\DL.BOOTBUTTON15	\MP.INVALIDVMEM20	\STATSsize15	
\DL.PROCESSORBUSY15	\MP.INVALIDVP20	\STREAM	
\DL.READPID	\MP.IOCBPAGE	\STRINGP	
\DL.SETTOD15	\MP.MDSFULL20	\TeleRaidFXP	
\DOLPHIN	\MP.MDSFULLWARNING20	\TT.ATOM	
\DORADO15	\MP.MOB20	\TT.FIXP15	
\DOVEIORGNSIZE	\MP.NEWMAPPAGE20	\TT.NOREF	
\DTDSize	\MP.NEWPAGE	\TT.NUMBERP	
\EndTypeNumber15	\MP.PNAMESFULL20	\TT.TYPEMASK	
\FAULTFXP	\MP.PROCERROR20	\UFNTableSize	
\FirstArrayPage15	\MP.PROCNOFRAME20	\VAL.HI15	
\FirstArraySegment15	\MP.RESIDENT20	\VMEMPAGEP15	
\FirstMDSPage15	\MP.SELECTLOOP20	\VP.BUFFERS15	
\FirstVmemBlock	\MP.STACKFAULT20	VP.DISPLAY	
\FIXP	\MP.STACKFULL 20 \MP.STACKRELEASED 20	\VP.DOVEIORGN	
\FP.IFPAGE15	\MP.SWAPDISKERROR20	\VP.GCOVERFLOW	
\FreeStackBlock	\MP.TOPUNWOUND20	VP.GCTABLE	
\FxtnBlock15	\MP.UNINTERRUPTABLE20	\VP.IFPAGE15	
\GCFXP15	\MP.UNKNOWN.UFN20	\VP.INITSCRATCH15	
\GuardBlock	\MP.UNLOCKINGMAP20	\VP.IOCBS	
\GuardStackAddr15	\MP.USECOUNTOVERFLOW20	\VP.IOPAGE15	
\HardReturnFXP	\MP.VMEMTOOLONG	\VP.LPT	
\HTCNTMASK	\NotStackBlock	\VP.RPT	
\HTCOLLSIZE	\NP.DISPLAY15	\VP.SECONDARYMAP	
\HTENDFREE	\NP.FPTOVP15	\VP.STACK15	
\HTFREEPTR15	\NP.GCOVERFLOW15	\VP.TYPETABLE15	
\HTMAINnpages15	\NP.GCTABLE15	\WIDEDOVEDISPLAYWIDTH15	
\htmainsize	\NP.MAP		
(MISIABII	(NF.11FETABLE		
MACRO INDEX			
EMADDRESS	EMGETBASE	EMPUTBASE	

VARIABLE INDEX			
5	IOPAGELAYOUT		
RECORD INDEX			
IFPAGE21	IOPAGE22	MISCSTATS20	
	PROPERTY INDEX		
LLPARAMS23			