```
25-Aug-87 14:23:20 {ERINYES}<LISPUSERS>KOTO>PATCH-LARGEIPBITMAP.;1
 File created:
  changes to:
                  (VARS PATCH-LARGEIPBITMAPCOMS)
                  (FNS SHOWBITMAP1.IP)
 Read Table:
                 OLD-INTERLISP-FILE
    Package:
                 TNTERLISP
       Format:
                   XCCS
            (* * Copyright (c) 1987 by Xerox Corporation. All rights reserved.)
(RPAQQ PATCH-LARGEIPBITMAPCOMS ((* * Fix problem of SHOWBITMAP1.IP in Koto placing the parts of a large bitmap
                                               in the wrong order)
                                            (FNS SHOWBITMAP1.IP)))
            (* * Fix problem of SHOWBITMAP1.IP in Koto placing the parts of a large bitmap in the wrong order)
(DEFINEQ
(SHOWBITMAP1.IP
  [LAMBDA (IPSTREAM BITMAP LEFT FIRSTROW XPIXELS YPIXELS SCALEFACTOR ROTATION HEIGHT XBYTES REGIONBOTTOM)
                                                                                   (* N.H.Briggs "25-Aug-87 14:06")
                                                                                   (* jds "13-Jan-86 18:13")
    ;; Move a segment of bitmap to an INTERPRESS file.
    :: FIRSTROW is the row count -- STARTING FROM THE TOP OF THE BITMAP AS ZERO -- for the first row to be displayed.
    ;; By the time we get here, XBYTES should have been raised to the next multiple of 32-bits-worth, since that's the required width of packed pixel
    ;; vectors.
     (PROG
           [(TOTALBYTES (ITIMES XBYTES YPIXELS))
              (SCRATCHBM (BITMAPCREATE (CEIL XPIXELS BITSPERCELL)
              (BMBASE (\ADDBASE (fetch (BITMAP BITMAPBASE) of BITMAP)
(ITIMES (IDIFFERENCE (IPLUS HEIGHT (OR REGIONBOTTOM 0))
                                                     (IPLUS FIRSTROW YPIXELS))
                                          (fetch (BITMAP BITMAPRASTERWIDTH) of BITMAP]
            (APPENDOP.IP IPSTREAM DOSAVESIMPLEBODY)
(APPENDOP.IP IPSTREAM ()
                                                                                    Start the SIMPLEBODY for displaying this part of the bitmap.
             (TRANS.IP IPSTREAM)
                                                                                    Translate to the current position
                                                                                    For the master, this is the number of pixels in the slow direction
             (APPENDNUMBER.IP IPSTREAM YPIXELS)
             (APPENDNUMBER.IP IPSTREAM (CEIL XPIXELS BITSPERCELL))
                                                                                    Number of pixels in the master's fast direction
             (APPENDINTEGER.IP IPSTREAM 1)
                                                                                    Reserved for future expansion
             (APPENDINTEGER.IP IPSTREAM 1)
(APPENDINTEGER.IP IPSTREAM 1)
             (SELECTQ (IMOD (OR ROTATION 0)
                                360)
                  (0
                                                                                   ; Bitmaps are really shown on their sides, hanging from the
                                                                                   ; upper left corner (I think--JDS)
                      (ROTATE.IP IPSTREAM -90)
                      (TRANSLATE.IP IPSTREAM 0 (IPLUS FIRSTROW YPIXELS))
                      ;; Push this segment up to its 'true' height -- i.e., The first segment gets pushed up all the way (since it's the top of the bitmap), ;; the next segment gets pushed up HEIGHT-#ofRowsIn1stSeg (to account for the first segment), and so on.
                      (CONCAT.IP IPSTREAM))
                  (90
                                                                                   ; need nop
                        (TRANSLATE.IP IPSTREAM (IDIFFERENCE HEIGHT (IPLUS FIRSTROW YPIXELS))
                       ;; Push this segment up to its 'true' bottom -- i.e., The first segment gets pushed up to bitmapHeight-HeightOfSegment (since ;; it's the top of the bitmap), the next segment gets pushed up HEIGHT-RowsIn1stSeg-RowsThisSeg (to account for the first
                       ;; segment), and so on.
                  ^{(180)};; The translation for this hasn't been tested yet. It may well be the inverse of the rotation-0 correction
                         (ROTATE.IP IPSTREAM 90)
                         (TRANSLATE.IP IPSTREAM 0 (IPLUS FIRSTROW YPIXELS))
                         (CONCAT.IP IPSTREAM))
                        ;; The translation for this hasn't been tested yet. It may well be the inverse of the rotation-90 correction
                         (ROTATE.IP IPSTREAM 180)
                         (TRANSLATE.IP IPSTREAM (IDIFFERENCE HEIGHT (IPLUS FIRSTROW YPIXELS))
                                 0)
                         (CONCAT.IP IPSTREAM))
                  (ERROR ROTATION "rotation by other than multiples of 90 degrees not implemented"))
                                                                                   : Scale the bitmap to its final size
             (SCALE.IP IPSTREAM SCALEFACTOR)
             (CONCAT.IP IPSTREAM)
             (APPENDSEQUENCEDESCRIPTOR.IP IPSTREAM SEQPACKEDPIXELVECTOR (IPLUS 4 TOTALBYTES))
            (APPENDINT.IP IPSTREAM 1 2)
(APPENDINT.IP IPSTREAM (CEIL XPIXELS BITSPERCELL)
                     2)
      ;; Now put put the bitmap -- each line must be a 32-bit multiple long
             (for Y (XWORDS _ (FOLDHI XBYTES BYTESPERWORD)) from 1 to YPIXELS
```

```
\label{thm:local_maple} $$\{$MEDLEY\}$$-obsolete>lispusers>PATCH-LARGEIPBITMAP.;1 ($$SHOWBITMAP1.IP cont.)$
```

```
Page 2
```

{MEDLEY}<obsolete>lispusers>PATCH-LARGEIPBITMAP.;1 28-Jun-2024 18:34:03 -- Listed on 30-Jun-2024 13:23:26 --

FUNCTION INDEX	
SHOWBITMAP1.IP1	