```
17-Apr-2023 08:04:06 {DSK}<home>larry>il>medley>sources>LLDATATYPE.;2
 File created:
      edit by:
               1 mm
  changes to:
               (VARS LLDATATYPECOMS)
               (FNS \SET.STORAGE.STATE \MAPMDS)
               28-Jun-99 16:57:50 {DSK}<home>larry>il>medley>sources>LLDATATYPE.;1
previous date:
 Read Table:
               INTERLISP
    Package:
               INTERLISP
      Format:
                XCCS
"... Copyright (c) 1982-1995, 1999 by VENUE, Oakland, CA.
(RPAOO LLDATATYPECOMS
                                                                      ; Because we use the UNLESSINEW macro in this file, we need
        ((COMS
                                                                      : it when compiling.
               (DECLARE%: EVAL@COMPILE DONTCOPY (FILES (SOURCE)
                                                          RENAMEMACROS)))
                                                                      ; Storage management
        (COMS
               (FNS NTYPX \TYPEMASK.UFN \TYPEP.UFN \ALLOCMDSPAGE \ALLOCPAGEBLOCK \ALLOCVIRTUALPAGEBLOCK \MAPMDS
                    \CHECKFORSTORAGEFULL \DOSTORAGEFULLINTERRUPT \SET.STORAGE.STATE \SETTYPEMASK
                    \ADVANCE.STORAGE.STATE \NEW2PAGE \MAKEMDSENTRY \INITMDSPAGE \ASSIGNDATATYPE1
                    RESOLVE.TYPENUMBER \TYPENUMBERFROMNAME CREATECELL \CREATECELL)
               ;; For NEW STORAGE option was set in Maiko, then \maiko.set.storage.state is active
               SP
               (INITVARS (CROSSCOMPILING)
                       (ASSIGNDATATYPE.ASKUSERWAIT 300)
                       (\STORAGEFULLSTATE)
                       (\STORAGEFULL))
               (GLOBALVARS CROSSCOMPILING \STORAGEFULLSTATE \STORAGEFULL \SYSTEMCACHEVARS \NxtArrayPage)
               (SPECVARS ASSIGNDATATYPE.ASKUSERWAIT))
        (COMS
                                                                     ; fetch and replace
               (FNS FETCHFIELD REPLACEFIELD BOXCOUNT CONSCOUNT \DTEST \TYPECHECK \DTEST.UFN \INSTANCEP.UFN
                     \INSTANCE-P \TYPECHECK.UFN GETDESCRIPTORS GETSUPERTYPE GETFIELDSPECS NCREATE NCREATE2
                    REPLACEFIELDVAL PUTBASEPTRX /REPLACEFIELD TYPENAME TYPENAMEP \TYPENAMEFROMNUMBER \BLOCKDATAP
                    USERDATATYPES DATATYPEP DATATYPES)
                  (MOVD? 'FETCHFIELD 'FFETCHFIELD NIL T)
                  (MOVD? 'REPLACEFIELD 'FREPLACEFIELD NIL T)
                  (MOVD? 'REPLACEFIELDVAL 'FREPLACEFIELDVAL NIL T))
               (OPTIMIZERS TYPENAMEP \INSTANCE-P))
        [COMS
                                                                     ; STORAGE
               (FNS STORAGE STORAGE.LEFT \STORAGE.TYPE \STLINP \STMDSTYPE \STMDS.APPROX \STORAGE.HUNKTYPE) (DECLARE%: DONTCOPY (RECORDS HUNKSTAT))
               (INITVARS (STORAGE.ARRAYSIZES '(4 16 64 256 1024 4096 16384 NIL)
        (DECLARE%: (EXPORT (OPTIMIZERS PUTBASEPTRX)
                            (CONSTANTS \SMALLP \FIXP \FLOATP \LITATOM \LISTP \ARRAYP \STACKP \VMEMPAGEP \STREAM
                                    \NEW-ATOM)
                            ;; This is the list of datatypes whos type #s must be known to microcode or to C.
                            ;; It is used in \SETUP.HUNK.TYPENUMBERS (in LLARRAYELT) to create the list INITIALDTDCONTENTS for
                            ;; INITDATATYPES.
                            ;; Changes to this lit need to be reflected in C and maybe in microcode.
                            (VARS \BUILT-IN-SYSTEM-TYPES))
                DONTCOPY
                (EXPORT (RECORDS DTD)
                        (MACROS \GETDTD)
                        (OPTIMIZERS \TYPEMASK.UFN)
                        (CONSTANTS \GUARDSTORAGEFULL \GUARD1STORAGEFULL)
                        (GLOBALVARS \NxtMDSPage \LeastMDSPage \SecondArrayPage \SecondMDSPage \MDSFREELISTPAGE
                               \MaxSysTypeNum \MaxTypeNumber \STORAGEFULL \INTERRUPTSTATE \PENDINGINTERRUPT))
                (CONSTANTS * STORAGEFULLSTATES))
        [COMS
                                                                      ; for MAKEINIT
               (FNS CREATEMDSTYPETABLE INITDATATYPES INITDATATYPENAMES)
               (DECLARE%: DONTCOPY
                       (ADDVARS (INITVALUES (\NxtMDSPage \FirstMDSPage)
                                        (\LeastMDSPage \FirstMDSPage)
                                        (\SecondMDSPage \DefaultSecondMDSPage)
                                        (\SecondArrayPage \DefaultSecondArrayPage)
                                        (\MDSFREELISTPAGE)
                                        (\MaxSysTypeNum 0)
                                        (\MaxTypeNumber))
                              (INITPTRS
                                         (\FINALIZATION.FUNCTIONS))
                              (INEWCOMS (FNS NTYPX \ALLOCMDSPAGE \MAKEMDSENTRY \INITMDSPAGE \ASSIGNDATATYPE1
                                              \TYPENUMBERFROMNAME \CREATECELL \NEW2PAGE)
                                      (FNS CREATEMDSTYPETABLE INITDATATYPES INITDATATYPENAMES)
                                      (VARS \BUILT-IN-SYSTEM-TYPES))
                              (RDCOMS (FNS NTYPX TYPENAME \TYPENAMEFROMNUMBER))
                              (RDVALS (\MaxTypeNumber))
                              (RD.SUBFNS (\ARRAYTYPENAME LAMBDA (X)
```

```
'ARRAYP))
                              (EXPANDMACROFNS \GETDTD PUTBASEPTRX REPLACEFIELD FETCHFIELD \GETBITS \PUTBITS
                                      \TESTBITS GETBASEBITS PUTBASEBITS FFETCHFIELD FREPLACEFIELD FREPLACEFIELDVAL
                                     REPLACEFIELDVAL NCREATE)
                              (MKI.SUBFNS (\GCDISABLED . NILL)
                                      (CREATECELL . I.\CREATECELL)
                                      (\CHECKFORSTORAGEFULL . NILL)))
                      EVAL@COMPILE
                      (ADDVARS (DONTCOMPILEFNS CREATEMDSTYPETABLE INITDATATYPES INITDATATYPENAMES]
        (LOCALVARS
                      T)
        (PROP FILETYPE LLDATATYPE)
         (DECLARE%: EVAL@COMPILE DONTCOPY (FILES (LOADCOMP)
                                                   DTDECLARE))))
;; Because we use the UNLESSINEW macro in this file, we need it when compiling.
(DECLARE%: EVAL@COMPILE DONTCOPY
(FILESLOAD (SOURCE)
       RENAMEMACROS)
;; Storage management
(DEFINEO
(NTYPX
                                                                     (* JonL "10-Nov-84 21:51")
  [LAMBDA (X)
                                                                     ; usually done in microcode --- this def used by MAKEINIT too
    (LOGAND [\GETBASE \MDSTypeTable (FOLDLO (fetch (POINTER PAGE#) of X)
                                              (CONSTANT (IQUOTIENT \MDSIncrement WORDSPERPAGE]
           \TT.TYPEMASK])
(\TYPEMASK.UFN
  [LAMBDA (X N)
                                                                     (* lmm "22-Mar-85 16:37")
    (COND
       ((NEQ 0 (LOGAND N (LRSH [\GETBASE \MDSTypeTable (FOLDLO (fetch (POINTER PAGE#) of X)
                                                                   (CONSTANT (IQUOTIENT \MDSIncrement WORDSPERPAGE]
                                 8)))
        X])
(\TYPEP.UFN
  [LAMBDA (X N)
                                                                     (* lmm "22-Mar-85 10:07")
    (COND
       ((EQ (NTYPX X)
            N)
        X])
(\ALLOCMDSPAGE
  [LAMBDA (TYP)
                                                                     ; Edited 25-Apr-94 10:39 by jds
    (PROG (VP VPTR)
      BEG [COND
              [(SETQ VP \MDSFREELISTPAGE)
               (SETQ VPTR (create POINTER
               PAGE# _ VP))
(PROG ((NXT (\GETBASEPTR VPTR 0)))
                     (COND
                         ((AND NXT (NOT (SMALLP NXT)))
                          (\MP.ERROR \MP.BADMDSFREELIST "MDS Free Page link bad. 'N to continue"
                                 (PROG1 \MDSFREELISTPAGE (SETQ \MDSFREELISTPAGE)))
                          (GO BEG))
                         (T (SETQ \MDSFREELISTPAGE NXT]
              (T (\CHECKFORSTORAGEFULL)
                 (SETQ VP \NxtMDSPage)
                 [UNLESSINEW (\PUTBASEFIXP \NxtMDSPage 0 (IDIFFERENCE VP (FOLDLO \MDSIncrement PAGESPERSEGMENT)))
                         (SETQ \NxtMDSPage (IDIFFERENCE VP (FOLDLO \MDSIncrement PAGESPERSEGMENT]
                                                                     ; Allocates 2 MDS pages
                 (SETQ VPTR (create POINTER
                                    PAGE# _ VP))
                 (\NEWPAGE (\ADDBASE (\NEWPAGE VPTR)
                                   WORDSPERPAGE]
           (\MAKEMDSENTRY VP TYP)
           (RETURN VPTR])
(\ALLOCPAGEBLOCK
  [LAMBDA (NPAGES)
                                                                     (* ejs%: "11-Aug-85 15:02")
    (UNINTERRUPTABLY
        ;; Allocates a continguous chunk of NPAGES pages. Currently there is no provision for giving them back.
        (LET ((RESULT (\ALLOCVIRTUALPAGEBLOCK NPAGES)))
              (COND
                 (RESULT (to NPAGES as (BASE _ RESULT) by (\ADDBASE BASE WORDSPERPAGE) do
```

```
; Allocate the new pages. Leave them having the default type,
                                                                                    ; namely type 0, don't refent
                                                                                                                   (\NEWPAGE BASE))
                             RESULT)))))))
(\ALLOCVIRTUALPAGEBLOCK
                                                                                   ; Edited 4-Jan-93 02:03 by jds
   [LAMBDA (NPAGES)
     (UNINTERRUPTABLY
          ;; Allocates a continguous chunk of NPAGES virtual pages. Does not actually allocate the memory, just removes them from the set of pages
          ;; that the allocator will use
          (PROG (FIRSTPAGE)
                  (COND
                      ([ILEQ (IPLUS \NxtArrayPage \GUARDSTORAGEFULL)
                               (SETQ FIRSTPAGE (IDIFFERENCE (IPLUS \NxtMDSPage \PagesPerMDSUnit) (SETQ NPAGES (CEIL NPAGES \PagesPerMDSUnit]
                                                                                   ; Plenty of space
                        (\PUTBASEFIXP \NxtMDSPage 0 (IDIFFERENCE FIRSTPAGE
                                                                                         \PagesPerMDSUnit)))
                      [(NEQ (OR \STORAGEFULLSTATE (\SET.STORAGE.STATE))
                              \SFS.SWITCHABLE)
                       (COND
                                  (EQ \STORAGEFULLSTATE \SFS.ARRAYSWITCHED)
                           ([AND
                                   (ILESSP (IPLUS \SecondArrayPage \GUARDSTORAGEFULL)
(SETQ FIRSTPAGE (IDIFFERENCE (IPLUS \SecondMDSPage \PagesPerMDSUnit)
                                                                         NPAGES 1
                            ;; Arrays have been switched, but we're still allocating MDS in low space. Just bump the variable that says where MDS in ;; high space will start
                            (\PUTBASEFIXP \SecondMDSPage 0 (IDIFFERENCE FIRSTPAGE \PagesPerMDSUnit)))
                           (T
                                                                                   ; Can't switch to the higher area
                               (RETURN NIL)
                      ((ILESSP \NxtArrayPage FIRSTPAGE)
                                                                                   ; Safe to go ahead anyway. We'll be pretty short of space in the
                                                                                   ; first 8mb, but it's switchable
                        (\PUTBASEFIXP \NxtMDSPage 0 (IDIFFERENCE FIRSTPAGE \PagesPerMDSUnit)))
                      ((ILESSP (IPLUS (SETQ FIRSTPAGE \SecondArrayPage)
                                          NPAGES)
                                \SecondMDSPage)
                       ;; There is space in upper area. So advance the pointer that says where array space will start when we switch later on
                       (\PUTBASEFIXP \SecondArrayPage 0 (IPLUS FIRSTPAGE NPAGES))
(replace (IFPAGE FullSpaceUsed) of \InterfacePage with 65535))
                      (T (RETURN NIL)))
                  (RETURN (create POINTER
                                     PAGE# _ FIRSTPAGE))))])
(\MAPMDS
                                                                                    Edited 17-Apr-2023 07:49 by Imm
   [LAMBDA (TYPE FN)
                                                                                    Edited 19-Oct-94 09:29 by sybalsky
;;; Applies FN to each virtual page number that is of type TYPE, or to all MDS pages if TYPE is NIL
     (OR (NULL TYPE)
          (FIXP TYPE)
                        (\TYPENUMBERFROMNAME TYPE)))
          (SETO TYPE
             ((VP (\CREATECELL \FIXP))
     (LET*
                    (IMAX \DefaultSecondArrayPage \MaxMDSPage))
              (END
             (\PUTBASEFIXP VP 0 (IMIN \NxtMDSPage \LeastMDSPage))
             (WHILE (ILEQ VP END) DO (COND
                                                 ((OR (EQ (SETQ TYP (\mathsf{NTYPX} (create POINTER
                                                                                            PAGE# _ VP)))
                                                            TYPE)
                                                        (AND (NULL TYPE)
                                                              (NEQ TYP 0)
                                                              (NEQ TYP \SMALLP)))
                                                   (SPREADAPPLY* FN VP)))
                                             (\BOXIPLUS VP 2])
(\CHECKFORSTORAGEFULL
                                                                                   ; Edited 4-Jan-93 02:04 by jds
     (DECLARE (GLOBALVARS \INTERRUPTSTATE \PENDINGINTERRUPT))
 ; Take appropriate action if storage is getting full. NPAGES is size of attempted allocation or NIL for MDS requests. Complications here because array
  space and MDS grow toward each other in two separate areas: the first 8MB of vmem and the remaining 24MB. Some machines cannot use the
;;; latter, so have to signal storage full when the first fills up. Other machines have to know when to switch over. Array space usually gets switched to ;;; the high segment before MDS, since MDS can eat the lo space in small increments all the way to the end --- Returns T if storage is ok, 0 if storage is
;;; ok buť \NxtĂrrayPage changed, and NIL if storage is nearly full
     (UNINTERRUPTABLY
          [PROG (PAGESLEFT)
                  (RETURN (COND
                                ((OR (ILESSP (SETQ PAGESLEFT (IPLUS (IDIFFERENCE \NxtMDSPage \NxtArrayPage)
                                                                               \PagesPerMDSUnit))
                                                \GUARDSTORAGEFULL)
```

```
NPAGES)
                              (SELECTC (OR \STORAGEFULLSTATE (\SET.STORAGE.STATE))
                                   ((LIST \SFS.NOTSWITCHABLE \SFS.FULLYSWITCHED)
                                           ((ILESSP PAGESLEFT 0)
                                             (while T do (\MP.ERROR \MP.MDSFULL "Storage completely full")))
                                            ((AND (ILEQ PAGESLEFT \GUARD1STORAGEFULL)
                                                  (NEQ \STORAGEFULL 0))
                                             (SETQ \STORAGEFULL 0)
                                             (\MP.ERROR \MP.MDSFULLWARNING "Space getting VERY full. Please save and
                                                    reload a.s.a.p. Type control-N to continue now."))
                                            ((NOT \STORAGEFULL)
                                             (SETO \STORAGEFULL T)
                                                                          : Note this is uninterruptable
                                             (replace STORAGEFULL of \INTERRUPTSTATE with T)
                                             (SETQ \PENDINGINTERRUPT T)))
                                        (\DORECLAIM)
                                       NIL)
                                   (\SFS.SWITCHABLE
                                                                          : We have verified that we can use the full 32MB, but haven't
                                                                          ; switched there yet
                                        (OR [COND
                                                [(NULL NPAGES)
                                                                          : Want MDS
                                                 (COND
                                                    ((ILEQ PAGESLEFT 0)
                                                      (\PUTBASEFIXP \LeastMDSPage 0 \NxtArrayPage) (\PUTBASEFIXP \NxtMDSPage 0 \SecondMDSPage) (\ADVANCE.STORAGE.STATE \SFS.FULLYSWITCHED)
                                                      (\ADVANCE.ARRAY.SEGMENTS \SecondArrayPage]
                                                (T
                                                                         ; Want array space
                                                    (COND
                                                       ((IGREATERP NPAGES PAGESLEFT)
                                                                          ; Have to switch array space over, but leave MDS to fill the rest
                                                                          ; of the low pages
                                                        (\PUTBASEFIXP \LeastMDSPage 0 \NxtArrayPage)
                                                        (\ADVANCE.STORAGE.STATE \SFS.ARRAYSWITCHED)
                                                        (\ADVANCE.ARRAY.SEGMENTS \SecondArrayPage]
                                   (\SFS.ARRAYSWITCHED
                                        (COND
                                           ((ILESSP \NxtMDSPage \LeastMDSPage)
                                                                         ; Finally used up to MDS, so switch over to hi
                                             (\PUTBASEFIXP \NxtMDSPage 0 \SecondMDSPage)
                                             (\ADVANCE.STORAGE.STATE \SFS.FULLYSWITCHED)
                                            T)
                                            ((AND NPAGES (IGEQ (IPLUS NPAGES \GUARDSTORAGEFULL)
                                                                 (IDIFFERENCE \SecondMDSPage \NxtArrayPage)))
                                            ;; MDS still in lo area, arrays in hi area, and we're asking for too big an array! Unlikely, but handle it
                                            ;; as a storage full case
                                            (T T)))
                                   (SHOULDNT])])
(\DOSTORAGEFULLINTERRUPT
  [LAMBDA NIL
                                                                          (* bvm%: "13-Feb-85 16:28")
    (replace Storagefull of \interruptstate with nil)
    (PROG ((HELPFLAG 'BREAK!))
           (LISPERROR "STORAGE FULL" '"save your work & reload a.s.a.p." T])
(\SET.STORAGE.STATE
  [LAMBDA NIL
                                                                          ; Edited 24-May-90 19:11 by Takeshi
    (COND
             (FETCH (IFPAGE DL24BitAddressable) OF \InterfacePage)
       ((EQ
             0)
         (SETQ \STORAGEFULLSTATE \SFS.NOTSWITCHABLE))
    (T (SETQ \STORAGEFULLSTATE \SFS.SWITCHABLE)))
(PUSH \SYSTEMCACHEVARS '\STORAGEFULLSTATE)
    \STORAGEFULLSTATE])
(\SETTYPEMASK
  [LAMBDA (NTYPX BITS)
           ((DTD (\GETDTD NTYPX)))
           (change (fetch DTDTYPEENTRY of DTD)
                   (LOGOR DATUM BITS))
           (\MAPMDS NTYPX (FUNCTION (LAMBDA (PAGE)
                                           (\PUTBASE \MDSTypeTable (SETQ PAGE (FOLDLO PAGE (IQUOTIENT \MDSIncrement
                                                                                                           WORDSPERPAGE)))
                                                   (LOGOR (\GETBASE \MDSTypeTable PAGE)
                                                           BITS1)
(\ADVANCE.STORAGE.STATE
                                                                          (* bvm%: " 9-Jan-85 15:30")
  [LAMBDA (FLG)
     Bump the flag that tells what state storage allocation is in with respect to the 8MB -- 32MB distinction. Also remove flag from
    ;;\SYSTEMCACHEVARS since it can no longer get recomputed
```

```
(SETQ \STORAGEFULLSTATE FLG)
      (replace (IFPAGE FullSpaceUsed) of \InterfacePage with 65535)
      (SETQ \SYSTEMCACHEVARS (DREMOVE '\STORAGEFULLSTATE \SYSTEMCACHEVARS])
(\NEW2PAGE
                                                                                          (* edited%: " 6-SEP-83 16:05")
   [LAMBDA (BASE)
      (\NEWPAGE (\ADDBASE (\NEWPAGE BASE)
                             WORDSPERPAGE])
(\MAKEMDSENTRY
                                                                                          ; Edited 25-Oct-92 23:12 by sybalsky:mv:envos
   [LAMBDA (VP V)
     ;; Set up the MDE-type-table entry for page VP. Set the bits in V (e.g., the bit that says "I'm a number")
     (\PUTBASE \MDSTypeTable (LRSH VP 1)
               (COND
                   ((\GCDISABLED)
                     (LOGOR \TT.NOREF V))
                    (T V1)
(\INITMDSPAGE
   [LAMBDA (BASE SIZE PREV)
                                                                                          (* bvm%: " 6-Jan-85 22:24")
;;; chain free list thru page at BASE of items SIZE long --- return last element
      (PROG ((SLOP (IREMAINDER WORDSPERPAGE SIZE))
               NPAGES LIMIT)
      ;; Refinement, mostly for benefit of hunking: try to keep objects from straddling page boundaries. SLOP is how much is left over on a page after ;; you have filled it with objects. If this SLOP is less than half the size of an object, then you can start your next allocation at the beginning of the ;; next page without any loss. Thus, the algorithm here either allocates several pages individually, or treats the entire expanse as one big block to ;; slice up. Computation here assumes \MDSIncrement is 2 pages. Might want to have the AND test actually be a flag in the DTD once and for all
              (COND
                  ((AND (NEQ SLOP 0)
                           (ILESSP SLOP (LRSH SIZE 1))
                           (ILESSP SIZE WORDSPERPAGE))
                                                                                          ; Make everyone start at page boundaries. Third condition
                                                                                          , needed for datatypes bigger than a page
                    (SETQ NPAGES (IQUOTIENT \MDSIncrement WORDSPERPAGE))
                   (SETQ LIMIT WORDSPERPAGE))
                  (T (SETQ NPAGES 1)
                      (SETQ LIMIT \MDSIncrement)))
              (to NPAGES do (for (DISP _ 0) while (ILEQ (add DISP SIZE)
                                                                     LIMIT)
                                     do (\PUTBASEPTR BASE 0 PREV)
                                         (SETQ PREV BASE)
                                         (SETQ BASE (\ADDBASE BASE SIZE)))
                                 (SETQ BASE (\ADDBASE BASE SLOP)))
              (RETURN PREVI)
(\ASSIGNDATATYPE1
   [LAMBDA (NAME DESCRIPTORS SIZE SPECS PTRFIELDS SUPERTYPE)
                                                                                         ; Edited 2-Apr-91 00:32 by sybalsky
  Declare type NAME to have the indicated DESCRIPTORS, SIZE (in words), SPECS (type specifiers for FETCHFIELD), PTRFIELDS (list of offsets of fields that contain reference-counted pointers) and SUPERTYPE (a type number that shares an initial prefix of DESCRIPTORS with us, or NIL).
;;; Returns two values: the type number assigned, and whether the type was redeclared in the process.
      (PROG ((NTYPX (\TYPENUMBERFROMNAME NAME))
               (SUPERTYPENUMBER (COND
                                           (SUPERTYPE (OR (\TYPENUMBERFROMNAME SUPERTYPE)
                                                                (ERROR SUPERTYPE ":INCLUDEd datatype but not currently declared"))
                                           (T 0)))
               DTD REDECLARED NEWTYPENUM NEWDTD)
              [COND
                  (NTYPX
                                                                                          ; a datatype of this name already allocated
                            (SETQ DTD (\GETDTD NTYPX))
                                ((AND (EQUAL PTRFIELDS (fetch DTDPTRS of DTD))
                                        (EQUAL SIZE (fetch DTDSIZE of DTD))); has same shape, can reuse DTD
                                  (replace DTDDESCRS of DTD with DESCRIPTORS)
                                  (replace DTDSUPERTYPE of DTD with SUPERTYPENUMBER)
                                  (RETURN NTYPX))
                                ((EQ (fetch DTDSIZE of DTD)
                                       0)
                                                                                          ; Type name to number is assigned, but no declaration yet --
                                                                                          ; proceed to allocate this type number
                                ([OR (EQ CROSSCOMPILING T)
                                       (AND CROSSCOMPILING (NEQ 'Y (ASKUSER 30 (SELECTQ CROSSCOMPILING
                                                                                                     (Y
                                                                                                          'Y)
                                                                                                     'N)
                                                                                        (LIST (COND
                                                                                                    (SIZE "OK TO REDECLARE DATATYPE ")
```

```
(T "OK to deallocate DATATYPE "))
                                                                                        NAME]
                                                                                   ; don't redeclare
                               (RETURN NTYPX))
                              ((IGREATERP NTYPX \MaxSysTypeNum)
                                                                                  ; Can redeclare 'user' types, i.e., anything not in the makeinit
                               (SETQ REDECLARED T))
                                                                                   ; can't mess with sys types
                                 (ERROR "ILLEGAL DATA TYPE" NAME]
      ;; If we get this far, we're about to create a for-real new datatype (we may need to deallocate the old version of this one...)
                 ((NOT SIZE)
                                                                                   ; only called to deallocate old datatype
                 (T
                    (COND
                        ((AND (EQ \MaxTypeNumber \EndTypeNumber)
(OR (NULL NTYPX)
                                     REDECLARED))
                          (LISPERROR "DATA TYPES FULL" NAME)))
                     (UNINTERRUPTABLY
                          [COND
                              ((OR (NULL NTYPX)
                                                                                   ; Bump the global count of types assigned, and grab the latest.
                                   REDECLARED)
                               (SETQ NEWTYPENUM (add \MaxTypeNumber 1))
                                                                                   ; Build a new DTD for it.
                               (SETQ NEWDTD (\GETDTD NEWTYPENUM))
                               (COND
                                   ((IGEQ (IPLUS (fetch WORDINPAGE of NEWDTD)
                                                     \DTDSize)
                                                                                   ; if this is the last one which would fit on a page, create a new
                                           WORDSPERPAGE)
                                    (\NEWPAGE (\ADDBASE NEWDTD \DTDSize)
                                             T)))
                               (COND
                                   [REDECLARED
                                           ;; When redeclaring a datatype, have to change the type of all old instances to be a new obsoleted type so ;; that the garbage collector will still collect them properly. Keep the original type number, because the ;; name -> type number mapping has already happened to compiled code
                                            (LET ([NEWTYPEENTRY (LOGOR NEWTYPENUM (LOGAND (fetch DTDTYPEENTRY of DTD)
                                                                                                      (LOGNOT \TT.TYPEMASK]
                                                  [\MAPMDS NTYPX (FUNCTION (LAMBDA
                                                                                      (\MAKEMDSENTRY PAGE NEWTYPEENTRY)
                                                                                      (SETQ FOUNDSOME T]
                                                  (COND
                                                      ((NOT FOUNDSOME)
                                                ;; Optimization: if no objects of the old type have been allocated (or all have been reclaimed and the
                                                ;; pages detyped), then don't need a new type number for them
                                                       (add \MaxTypeNumber −1))
                                                          (replace DTDDESCRS of DTD with NIL)
                                                          (replace DTDTYPESPECS of DTD with NIL)
                                                          (\BLT NEWDTD DTD \DTDSize)
                                                ;; Copy old DTD to new. Be careful about the pointer fields -- we haven't incremented their reference
                                                ;; counts. Those fields are DTDDESCRS, DTDTYPESPECS and DTDPTRS, the first two of which we
                                                ;; have conveniently smashed to NIL before copying.
                                                          (\ADDREF (fetch DTDPTRS of NEWDTD))
                                                          (replace DTDOBSOLETE of NEWDTD with T)
(replace DTDTYPEENTRY of NEWDTD with NEWTYPEENTRY)
                                                          [replace DTDNAME of NEWDTD with (NEW-SYMBOL-CODE (PACK* "Obsolete-"
                                                                                                                              NAME)
                                                                                                         (\ATOMPNAMEINDEX (PACK*
                                                                                                                                        "Obsol
ete-" NAMEl
                                                          (replace DTDFREE of DTD with NIL)
                                                                                   Replacement type has no free list--just the old type, now in
                                                                                   NEWDTD
                                                                                  ; Normal case of a new type
                                       (SETQ NTYPX NEWTYPENUM)
                                       (replace DTDNAME of (SETQ DTD NEWDTD) with (NEW-SYMBOL-CODE NAME
                                                                                                                      (\ATOMPNAMEINDEX
                                                                                                                        NAME 1
                          (COND
                              ((NEQ SIZE 0)
                                                                                   ; If the datum takes up any space, remember what it looks like
                               (replace DTDSIZE of DTD with SIZE)
                               (replace DTDDESCRS of DTD with (COPY DESCRIPTORS))
                               (replace DTDTYPESPECS of DTD with (COPY SPECS))
                               (replace DTDPTRS of DTD with PTRFIELDS)
                               (replace DTDSUPERTYPE of DTD with SUPERTYPENUMBER)
                                                                                  ; The type-masked type#, for fast type checking
                               (replace DTDTYPEENTRY of DTD with NTYPX)
                         ;; NOTE: If the redeclared type has subtypes, we have to redeclare them, too!
```

```
(RPAQQ SP NOBIND)
(RPAQ? CROSSCOMPILING )
(RPAQ? ASSIGNDATATYPE.ASKUSERWAIT 300)
(RPAQ? \STORAGEFULLSTATE )
(RPAQ? \STORAGEFULL )
(DECLARE%: DOEVAL@COMPILE DONTCOPY
(GLOBALVARS CROSSCOMPILING \STORAGEFULLSTATE \STORAGEFULL \SYSTEMCACHEVARS \NxtArrayPage)
```

```
{MEDLEY} < sources > LLDATATYPE.; 1
                                                                                                                     Page 8
(DECLARE%: DOEVAL@COMPILE DONTCOPY
(SPECVARS ASSIGNDATATYPE.ASKUSERWAIT)
;; fetch and replace
(DEFINEO
(FETCHFIELD
                                                                       (* edited%: " 7-JUN-83 10:23")
  [LAMBDA (DESCRIPTOR DATUM)
    ;; retrieves a data field from a user data structure.
    (PROG ((TN (fetch fdTypeName of DESCRIPTOR))
           (OFFSET (fetch fdOffset of DESCRIPTOR)))
(AND TN (SETQ DATUM (\DTEST DATUM TN)))
           (RETURN (SELECTQ (fetch fdType of DESCRIPTOR)
                         ((POINTER XPOINTER FULLPOINTER FULLXPOINTER)
                              (\GETBASEPTR DATUM OFFSET))
                        (FLOATP (MAKEFLOATNUMBER (\GETBASE DATUM OFFSET) (\GETBASE (\ADDBASE DATUM 1)
                                                OFFSET)))
                         (FIXP (\MAKENUMBER (\GETBASE DATUM OFFSET)
                                       (\GETBASE (ADDBASE DATUM 1)
                                              OFFSET)))
                         (SWAPPEDFIXP (\MAKENUMBER (\GETBASE (\ADDBASE DATUM 1)
                                                            OFFSET)
                                               (\GETBASE DATUM OFFSET)))
                         (PROG ((FT (fetch fdType of DESCRIPTOR))
                                (OFF OFFSET))
                               (RETURN (SELECTO (CAR FT)
                                             (BITS (LOGAND (LRSH (\GETBASE DATUM OFF)
                                                                   (BitFieldShift (CDR FT)))
                                                           (BitFieldMask (CDR FT))))
                                             (SIGNEDBITS ([LAMBDA (N WIDTH)
                                                              (COND
                                                                 [[IGREATERP N (SUB1 (LLSH 1 (SUB1 WIDTH]
                                                                  (SUB1 (IDIFFERENCE N (SUB1 (LLSH 1 WIDTH)
                                                                 (T N]
                                                           (LOGAND (LRSH (\GETBASE DATUM OFF)
                                                                           (BitFieldShift (CDR FT)))
                                                                   (BitFieldMask (CDR FT)))
                                                           (BitFieldWidth (CDR FT))))
                                             (LONGBITS (\MAKENUMBER (LOGAND (LRSH (\GETBASE DATUM OFF)
                                                                                      (BitFieldShift (CDR FT)))
                                                                              (BitFieldMask (CDR FT)))
                                                                (\GETBASE (ADDBASE DATUM 1)
                                                                       OFF)))
                                             (FLAGBITS (NEQ (LOGAND (\GETBASE DATUM OFF)
                                                                     (BitFieldShiftedMask (CDR FT)))
                                                             0))
                                             (LISPERROR "ILLEGAL ARG" DESCRIPTOR])
(REPLACEFIELD
  [LAMBDA (DESCRIPTOR DATUM NEWVALUE)
                                                                       (* lmm " 1-Jan-85 23:09")
                                                                       ; replace a field in a user data structure. return coerced value.
    (PROG ((OFFSET (fetch fdOffset of DESCRIPTOR))
            (FT (fetch fdType of DESCRIPTOR))
            (TN (fetch fdTypeName of DESCRIPTOR))
           SHIFT MASK)
           (AND TN (SETQ DATUM (\DTEST DATUM TN)))
           (RETURN
            (SELECTO FT
                 ((POINTER FULLPOINTER)
                      (\RPLPTR DATUM OFFSET NEWVALUE))
                                                                       ; no ref count, hi bits used
                 (XPOINTER
                            (PUTBASEPTRX DATUM OFFSET NEWVALUE))
                 (FULLXPOINTER (\PUTBASEPTR DATUM OFFSET NEWVALUE))
                 (FLOATP (\PUTBASEFLOATP DATUM OFFSET NEWVALUE))
                 (FIXP (\PUTFIXP (\ADDBASE DATUM OFFSET)
                              NEWVALUE)
                       NEWVALUE)
                 (SWAPPEDFIXP (\PUTSWAPPEDFIXP (\ADDBASE DATUM OFFSET)
                                       NEWVALUE)
                               NEWVALUE)
                 (SELECTQ (CAR FT)
                      (BITS (LOGAND (LRSH (\PUTBASE DATUM OFFSET (LOGOR [LOGAND
                                                                              (\GETBASE DATUM OFFSET)
                                                                              (LOGXOR 65535
                                                                                      (LLSH (SETQ MASK
                                                                                              (BitFieldMask (CDR FT)))
                                                                                             (SETQ SHIFT
                                                                                              (BitFieldShift (CDR FT]
```

(LLSH (LOGAND NEWVALUE MASK)

```
SHIFT)))
                                          SHIFT)
                                  MASK))
                     (SIGNEDBITS ([LAMBDA (X)
                                        [[IGREATERP X (SUB1 (LLSH 1 (SUB1 (BitFieldWidth (CDR FT]
                                         (SUB1 (IDIFFERENCE X (SUB1 (LLSH 1 (BitFieldWidth (CDR FT)
                                        (T X]
                                   (LOGAND
                                    (LRSH (\PUTBASE DATUM OFFSET
                                                 (LOGOR [LOGAND (\GETBASE DATUM OFFSET)
                                                                (LOGXOR 65535 (LLSH (SETQ MASK (BitFieldMask
                                                                                                   (CDR FT)))
                                                                                      (SETQ SHIFT (BitFieldShift
                                                                                                   (CDR FT]
                                                         (LLSH (LOGAND [LOGAND NEWVALUE
                                                                               (SUB1 (LLSH 1 (BitFieldWidth
                                                                                               (CDR FT1
                                                                      MASK)
                                                               SHIFT)))
                                          SHIFT)
                                   MASK)))
                     (FLAGBITS (\PUTBASE DATUM OFFSET (LOGOR [LOGAND (\GETBASE DATUM OFFSET)
                                                                       (LOGXOR 65535 (LLSH (SETQ MASK
                                                                                             (BitFieldMask
                                                                                              (CDR FT)))
                                                                                            (SETQ SHIFT
                                                                                             (BitFieldShift
                                                                                              (CDR FT]
                                                               (LLSH (LOGAND (COND
                                                                                 (NEWVALUE 65535)
                                                                                  (T 0))
                                                                             MASK)
                                                                      SHIFT)))
                                (AND NEWVALUE T))
                     (LONGBITS (PROG (LO HI)
                                      (.UNBOX. NEWVALUE HI LO)
                                      (UNINTERRUPTABLY
                                          (\PUTBASE DATUM OFFSET (LOGOR [LOGAND
                                                                           (\GETBASE DATUM OFFSET)
                                                                           (LOGXOR 65535
                                                                                  (LLSH (SETQ MASK
                                                                                          (BitFieldMask (CDR FT)))
                                                                                         (SETQ SHIFT
                                                                                          (BitFieldShift (CDR FT]
                                                                          (LLSH (LOGAND HI MASK)
                                                                                SHIFT)))
                                          (\PUTBASE DATUM (ADD1 OFFSET)
                                                 LO)))
                               NEWVALUE)
                     (LISPERROR "ILLEGAL ARG" DESCRIPTOR])
(BOXCOUNT
  [LAMBDA (TYPE N)
                                                                    (* lmm "20-OCT-81 20:27")
    (PROG [(DTD (\GETDTD (OR (SMALLP TYPE)
                              (COND
                                  ((NULL TYPE)
                                   \FIXP)
                                 (T (\TYPENUMBERFROMNAME TYPE)
          (RETURN (PROG1 (fetch DTDCNT of DTD)
                       (AND (NUMBERP N)
                            (replace DTDCNT of DTD with N)))])
(CONSCOUNT
 [LAMBDA (N)
(BOXCOUNT \LISTP N])
                                                                    (* lmm "13-MAY-80 23:02")
(\DTEST
 [LAMBDA
         (OBJ TYPE)
                                                                    (* lmm "22-Mar-85 12:29")
    (\DTEST.UFN OBJ TYPE])
(\TYPECHECK
 [LAMBDA (OBJ TYPE)
                                                                    (* lmm "22-Mar-85 12:29")
    (\DTEST.UFN OBJ TYPE])
(\DTEST.UFN
  [LAMBDA (OBJ TYPEN)
                                                                    (* gbn " 3-Oct-86 10:49")
   ;; ufn for DTEST opcode
   ;; coerce into desired type
    (PROG ((N (NTYPX OBJ)))
     LP (COND
```

```
((EQ (fetch DTDNAME of (\GETDTD N))
                    TYPEN)
                                                                         ; should be happening in microcode
                (RETURN OBJ))
               ([NEQ 0 (SETQ N (fetch DTDSUPERTYPE of (\GETDTD N]
               (T (RETURN (SELECTQ (\INDEXATOMPNAME TYPEN)
                                (FLOATP (\FLOAT OBJ))
                                                                          ; Should be able to get at the INPUT/OUTPUT flg--a second arg
                                (STREAM
                                                                         to \DTEST?
                                          (\GETSTREAM OBJ (SELECTQ (STKNTHNAME -1 '\DTEST.UFN)
                                                                 ((\BINS \BIN BIN)
                                                                      'INPUT)
                                                                 ((\BOUTS \BOUT BOUT)
                                                                      'OUTPUT)
                                                                 NIL)))
                                (HARRAYP (DECLARE (GLOBALVARS SYSHASHARRAY))
                                           (COND
                                              [(NULL OBJ)
                                               (COND
                                                   (SYSHASHARRAY (\DTEST SYSHASHARRAY 'HARRAYP))
(T (LISPERROR "ARG NOT HARRAY" OBJ T]
                                              ((AND (LISTP OBJ)
                                                     (TYPENAMEP (CAR OBJ)
                                                             'HARRAYP))
                                               (CAR OBJ))
                                              (T (LISPERROR "ARG NOT HARRAY" OBJ T))))
                                 (FONTDESCRIPTOR
                                      (\COERCEFONTDESC OBJ))
                                 (SMALLP [PROG (HI LO)
                                                 (.UNBOX. OBJ HI LO)
                                                 (RETURN (OR (SMALLP (\MAKENUMBER HI LO))
                                                              (LISPERROR "ILLEGAL ARG" OBJ T])
                                (LISTP (LISPERROR "ARG NOT LIST" OBJ T))
                                (LITATOM (LISPERROR "ARG NOT LITATOM" OBJ T)) (STACKP (LISPERROR "ILLEGAL STACK ARG" OBJ T))
                                 (READTABLEP (LISPERROR "ILLEGAL READTABLE" OBJ T))
                                 (TERMTABLEP (LISPERROR "ILLEGAL TERMINAL TABLE" OBJ T))
                                 (ARRAYP (LISPERROR "ARG NOT ARRAY" OBJ T))
                                 (\DISPLAYDATA
                                                                         ; Should be able to get at the stream--a second arg to \DTEST?
                                                 (ERROR "ARG NOT DISPLAY STREAM" NIL))
                                 (\LISPERROR OBJ (CONCAT "ARG NOT " (\INDEXATOMPNAME TYPEN))
                                        T])
(\INSTANCEP.UFN
  [LAMBDA (OBJ TYPEN)
                                                                         ; Edited 2-Apr-91 00:40 by sybalsky
;;; ufn for INSTANCEP opcode
     (PROG ((N (NTYPX OBJ)))
           (NEW-SYMBOL-CODE (COND
                                  ([AND (FIXP TYPEN)
                                         (EQ (\VAG2 \AtomHI TYPEN)
                                              (fetch DTDNAME of (\GETDTD N]
                                   (RETURN T)
                                  ((EQ (fetch DTDNAME of (\GETDTD N))
                                        TYPEN)
                                   (RETURN T))
                                  ([NEQ 0 (SETQ N (fetch DTDSUPERTYPE of (\GETDTD N]
                                   ;; recur on the supertype
                                   (GO LP))
                                  (T (RETURN NIL)))
                   (COND
                       ((IEQP (fetch DTDNAME of (\GETDTD N))
                              TYPEN)
                        (RETURN T))
                       ([NEQ 0 (SETQ N (fetch DTDSUPERTYPE of (\GETDTD N]
                       ;; recur on the supertype
                        (GO LP))
                       (T (RETURN NIL])
(\INSTANCE-P
  [LAMBDA (OBJECT TYPE)
                                                                         (* gbn "26-Sep-86 17:07")
    ;; should be phased out in favor of calls to typenamep, which shares the definition.
     (\INSTANCEP.UFN OBJECT (\ATOMPNAMEINDEX TYPE])
(\TYPECHECK.UFN
                                                                         (* gbn "23-Sep-86 20:06")
  [LAMBDA (OBJ TYPEN)
    ;; ufn for TYPECHECK opcode --- cause error if not of right type
     (PROG ((N (NTYPX OBJ)))
      LP (COND
```

(/REPLACEFIELD [LAMBDA (DESCRIPTOR DATUM NEWVALUE) (* Imm%: "23-AUG-76 00:01:53") [AND LISPXHIST (UNDOSAVE (LIST '/REPLACEFIELD DESCRIPTOR DATUM (FETCHFIELD DESCRIPTOR DATUM)]

(LOLOC NEWVALUE))

NEWVALUE)])

(REPLACEFIELD DESCRIPTOR DATUM NEWVALUE])

```
(TYPENAME
  [LAMBDA (X)
                                                                       ; Edited 28-Jun-99 16:56 by rmk:
                                                                        Edited 28-Jun-99 16:55 by rmk:
                                                                       ; Edited 11-Nov-98 12:14 by rmk:
    (LET ((N (NTYPX X)))
         (COND
             ((EQ N \ARRAYP)
              (\ARRAYTYPENAME X))
                                                                       ; Common lisp strings report as STRINGP's.
             ((%%STRINGP X)
              'STRINGP)
             ([EQ 'NEW-ATOM (SETQ N (\INDEXATOMPNAME (fetch DTDNAME of (\GETDTD N]
              ;; Large atom space returns NEW-ATOM instead of LITATOM
              'LITATOM)
             (T N])
(TYPENAMEP
                                                                       ; Edited 18-Dec-86 16:33 by jop
  [LAMBDA (DATUM TYPE)
    (COND
       ((EQ TYPE 'STRINGP)
        (%%STRINGP DATUM)
       (T (\INSTANCEP.UFN DATUM TYPE])
(\TYPENAMEFROMNUMBER
                                                                       (* lmm "13-FEB-83 14:13")
  [LAMBDA (N)
    (COND
       ((ILESSP N (ADD1 \MaxTypeNumber))
        (\INDEXATOMPNAME (fetch DTDNAME of (\GETDTD N])
(\BLOCKDATAP
  [LAMBDA (X)
                                                                       (* JonL "22-Sep-84 23:15")
    (PROG ((TYPENO (NTYPX X)))
           (RETURN (COND
                       ((EQ 0 TYPENO)
(type? ARRAYBLOCK X))
                       (T (fetch DTDHUNKP of (\GETDTD TYPENO])
(USERDATATYPES
                                                                       (* rrb "16-JUL-80 13:17")
  [LAMBDA NI]
    (DATATYPES T])
(DATATYPEP
  [LAMBDA (DATATYPESPEC)
                                                                       (* bvm%: "12-Feb-85 17:29")
    ;; returns the type name of a data type spec if it is a datatype.
       [(SMALLP DATATYPESPEC)
        (PROG ((DTD (\GETDTD DATATYPESPEC))
                NAME)
               (RETURN (AND (NOT (fetch DTDHUNKP of DTD))
                              (SETO NAME (\INDEXATOMPNAME (fetch DTDNAME of DTD))) (NEO NAME '**DEALLOC**)
                             NAME ]
       ((NOT (LITATOM DATATYPESPEC))
        NIL)
        ((FMEMB DATATYPESPEC '(CCODEP HARRAYP))
                                                                       ; handle subtypes of arrayp specially.
        DATATYPESPEC)
       ((for I from 1 to \MaxTypeNumber thereis (EQ (\INDEXATOMPNAME (fetch DTDNAME of (\GETDTD I)))
                                                      DATATYPESPEC))
        DATATYPESPEC])
(DATATYPES
  [LAMBDA (USERSFLG)
                                                                       (* rrb "16-JUL-80 13:20")
    (bind N for I from (COND
                           (USERSFLG (ADD1 \MaxSysTypeNum))
                           (T 1))
       to \MaxTypeNumber when (SETQ N (DATATYPEP I)) collect N])
(MOVD? 'FETCHFIELD 'FFETCHFIELD NIL T)
(MOVD? 'REPLACEFIELD 'FREPLACEFIELD NIL T)
(MOVD? 'REPLACEFIELDVAL 'FREPLACEFIELDVAL NIL T)
(DEFOPTIMIZER TYPENAMEP (DATUM TYPE & ENVIRONMENT ENV)
```

```
(LET [ (TYPE-NAME (CL:IF (AND (CL:CONSP TYPE)
                                                                  (EQ (CAR TYPE)
                                                                      'QUOTE)
                                                                  (CL:SYMBOLP (CADR TYPE)))
                                                            (CADR TYPE]
                                      (CL:IF [AND TYPE-NAME (NOT (EQ TYPE-NAME 'STRINGP]
                                              [(FMEMB:4-BYTE (COMPILER::ENV-TARGET-ARCHITECTURE ENV))
                                                '((OPCODES INSTANCEP 0 0 0 (ATOM \, (CADR TYPE)))
                                                  ,DATUM]
                                              [(FMEMB:3-BYTE (COMPILER::ENV-TARGET-ARCHITECTURE ENV))
                                                ((OPCODES INSTANCEP 0 0 (ATOM \, (CADR TYPE)))
                                                  ,DATUM]
                                                 '((OPCODES INSTANCEP 0 (ATOM \, (CADR TYPE)))
                                                    ,DATUM]
                                          'COMPILER: PASS)))
(DEFOPTIMIZER \INSTANCE-P (&BODY BODY &ENVIRONMENT ENV)
                                 (COND
                                    [[AND (EQ (CAADR BODY)
                                               'QUOTE)
                                           (CL:SYMBOLP (CADR (CADR BODY]
                                     (COND
                                         [(FMEMB:4-BYTE (COMPILER::ENV-TARGET-ARCHITECTURE ENV))
                                          '([OPCODES INSTANCEP 0 0 0 (ATOM \, (CADR (CADR BODY]
                                             (CAR BODY)
                                         [(FMEMB:3-BYTE (COMPILER::ENV-TARGET-ARCHITECTURE ENV))
                                           ([OPCODES INSTANCEP 0 0 (ATOM \, (CADR (CADR BODY]
                                             (CAR BODY]
                                            '([OPCODES INSTANCEP 0 (ATOM \, (CADR (CADR BODY]
                                              , (CAR BODY]
                                    (T 'IGNOREMACRO)))
;; STORAGE
(DEFINEO
(STORAGE
  [LAMBDA (TYPES PAGE-THRESHOLD IN-USE-THRESHOLD)
                                                                          ; Edited 8-Jan-88 14:39 by bvm
    (PROG ((TOTALALLOCMDS (CREATECELL \FIXP))

(FREE (CREATECELL \FIXP))
             (HUNKSTATS (from 0 to 2 collect (create HUNKSTAT)))
             TYPE TYPENAME DOBLOCKSFLG)
            (DECLARE (SPECVARS HUNKSTATS))
            (printout NIL "Type" 17 "Assigned" 30 "Free items" 45 "In use" 55 "Total alloc" T 15 "pages [items]" T
            (COND
               [(AND TYPES (NEQ TYPES T))
                (for TYPE HFLG inside TYPES when [COND
                                                        ((FIXP TYPE)
                                                         (COND
                                                            ((OR (< TYPE 0)
                                                                  (> TYPE \MaxTypeNumber))
; An explicit type number ought to be 'right'
                                                              (ERROR "Not a type number" TYPE))
                                                             ((EQ TYPE 0)
                                                             (SETQ DOBLOCKSFLG T)
                                                             NIL)
                                                             (T T)))
                                                        (T (SETO TYPE (\TYPENUMBERFROMNAME TYPE]
                   do (COND
                          ((fetch DTDHUNKP of (\GETDTD TYPE))
                       (SETO HFLG T)))
(\STORAGE.TYPE TYPE FREE TOTALALLOCMDS PAGE-THRESHOLD IN-USE-THRESHOLD)
                   finally (COND
               (HFLG (\STORAGE.HUNKTYPE TOTALALLOCMDS PAGE-THRESHOLD IN-USE-THRESHOLD]
(T (for I from 1 to \MaxTypeNumber do (\STORAGE.TYPE I FREE TOTALALLOCMDS PAGE-THRESHOLD)
                                                                 IN-USE-THRESHOLD))
                   (\STORAGE.HUNKTYPE TOTALHUNKS PAGE-THRESHOLD IN-USE-THRESHOLD)
                   (printout NIL T "TOTAL" 15 .I5 (+ TOTALALLOCMDS TOTALHUNKS)
                          TT)
                  (printout NIL "Data Spaces Summary" T)
(printout NIL 30 "Allocated" 50 "Remaining" T)
(printout NIL 32 "Pages" 52 "Pages" T)
                  (printout NIL "Datatypes (incl. LISTP etc.)" 30 .18 TOTALALLOCMDS 50 "\" T) ; Arrayspace and MDS come out of the same pot, so lump their
                                                                          ; 'remaining' pages together
                  (printout NIL "ArrayBlocks" (COND
                                                      ((NOT (= TOTALHUNKS 0))
                                                      " (variable)")
(T ""))
                          30 .18 (SELECTC \STORAGEFULLSTATE
                                        ((LIST \SFS.FULLYSWITCHED \SFS.ARRAYSWITCHED)
                                             (+ (- \LeastMDSPage \FirstArrayPage)
                                                 (- \NxtArrayPage \SecondArrayPage)))
```

```
(- \NxtArrayPage \FirstArrayPage))
50 "--" .16 (CAR (STORAGE.LEFT))
                          T)
                  (COND
                      ((NOT (= TOTALHUNKS 0))
                       (printout NIL "ArrayBlocks (chunked)" 30 .18 TOTALHUNKS 50 "/" T)))
                  ;; \LastATOMpage marks off atom indexes as if they were word addresses; but the space behind a litatom is one cell in each of ;; the four spaces: DEFSPACE, VALSPACE, PNAMESPACE, and PROPSPACE
                  (\STLINP "Symbols" (TIMES (FOLDHI \AtomFrLst CELLSPERPAGE)
                                               4)
                          (TIMES (UNFOLD (ADD1 \LastAtomPage)
                                          WORDSPERCELL)
                                  4))
                  (SETQ DOBLOCKSFLG T)))
            (COND
               (DOBLOCKSFLG (\SHOW.ARRAY.FREELISTS1)
(STORAGE.LEFT
                                                                          ; Edited 18-Aug-93 14:28 by sybalskY:MV:ENVOS
  [LAMBDA NIL
;;; Return a list MDS+Arrays left in 8mb, in 24mb, litatoms left, pnames left and the same as fractions
     (PROG ((MDSFREE (IPLUS (IDIFFERENCE (SELECTC (OR \STORAGEFULLSTATE (\SET.STORAGE.STATE))
                                                   (\SFS.ARRAYSWITCHED
                                                           ;; There's free space in two places: some leftover MDS in the lo region, and the
                                                           ;; space beyond allocated arrays in the hi
                                                        \SecondMDSPage)
                                                   \NxtMDSPage)
                                       \NxtArrayPage)
                               \PagesPerMDSUnit
                               (SELECTC \STORAGEFULLSTATE
                                    (\SFS.SWITCHABLE
                                                                          ; We have another 24MB to work with
                                         (IPLUS (IDIFFERENCE \SecondMDSPage \SecondArrayPage)
                                                  \PagesPerMDSUnit))
                                    (\SFS.ARRAYSWITCHED
                                                                          ; Account for the space left behind after array allocation moved
                                         (IPLUS (IDIFFERENCE \NxtMDSPage \LeastMDSPage)
                                                 \PagesPerMDSUnit))
                               (for (FREE _ \MDSFREELISTPAGE) by (SMALLP (\GETBASEPTR (create POINTER
                                                                                                     PAGE# _ FREE)
                                                                                      0))
                                  while FREE sum 1)))
             (ATOMTOTAL (ITIMES (UNFOLD (ADD1 \LastAtomPage)
                                          WORDSPERCELL)
                                 4))
            ATOMSLEFT MDSFRAC)
           [SETQ MDSFRAC (FQUOTIENT MDSFREE (IPLUS (IDIFFERENCE (IPLUS \FirstMDSPage \PagesPerMDSUnit)
                                                                 \FirstArrayPage)
                                                          (COND
                                                             ((EQ \STORAGEFULLSTATE \SFS.NOTSWITCHABLE)
                                                              0)
                                                             (T (IDIFFERENCE (IPLUS \SecondMDSPage \PagesPerMDSUnit)
                                                                        \SecondArrayPage]
            (RETURN (LIST MDSFREE MDSFRAC (SELECTC \STORAGEFULLSTATE
                                                   (\SFS.NOTSWITCHABLE
                                                        MDSFRAC)
                                                   (\SFS.SWITCHABLE
                                                         (FQUOTIENT (IDIFFERENCE (IPLUS \NxtMDSPage \PagesPerMDSUnit)
                                                                             \NxtArrayPage)
                                                                (IDIFFERENCE (IPLUS \FirstMDSPage \PagesPerMDSUnit)
                                                                        \FirstArrayPage)))
                                                   0])
(\STORAGE.TYPE
  [LAMBDA (TYPE FREE TOTALALLOCMDS PAGE-THRESHOLD IN-USE-THRESHOLD)
                                                                          ; Edited 8-Jan-88 14:39 by bvm
     (DECLARE (USEDFREE HUNKSTATS))
     (PROG ((ALLOCMDS 0)
              IZE NAME ALLOC INUSE ITEMSPERMDS INUSEPAGES NPAGESALLOCATED HUNKP DTD STAT)
            (DECLARE (SPECVARS ALLOCMDS))
           (SETQ DTD (\GETDTD TYPE))
           (COND
               ([NOT (SETQ NAME (\INDEXATOMPNAME (fetch DTDNAME of DTD]
                                                                          ; Nameless type?
                (RETURN)))
           (SETQ HUNKP (fetch DTDHUNKP of DTD))
(SETQ SIZE (fetch DTDSIZE of DTD))
            (CHECK (EVENP SIZE WORDSPERCELL))
           [SETO ITEMSPERMDS (SELECTO NAME
                                     ((LITATOM SMALLP)
                                                                          : These are not allocated
                                          (RETURN))
                                     (LISTP [COND
                                                 ((EQ CDRCODING 0)
```

```
(IQUOTIENT \MDSIncrement SIZE))
                                               (T (CONSTANT (FIX (FQUOTIENT \MDSIncrement 2.2])
                                    (COND
                                       ((EQ SIZE 0)
                                                                       ; Undeclared, or not allocated
                                        (RETURN))
                                       (T (IQUOTIENT \MDSIncrement SIZE]
          [\MAPMDS TYPE (FUNCTION (LAMBDA NIL
                                         (add ALLOCMDS 1]
           (SETQ NPAGESALLOCATED (TIMES ALLOCMDS \PagesPerMDSUnit))
           (COND
              ((SETQ HUNKP (fetch DTDHUNKP of DTD))
               (add [fetch (HUNKSTAT NPAGES) of (SETQ STAT (CAR (NTH HUNKSTATS (ADD1 (fetch DTDGCTYPE of DTD]
                    NPAGESALLOCATED))
              (T (\BOXIPLUS TOTALALLOCMDS NPAGESALLOCATED)))
           (COND
              ((< NPAGESALLOCATED (OR PAGE-THRESHOLD 1))
               (RETURN)))
           (\PUTBASEFIXP (\DTEST FREE 'FIXP)
                  0 0)
           [ COND
              [(AND (NEQ CDRCODING 0)
                     (EQ TYPE \LISTP))
                                                                       ; CONS pages have a different kind of free list
               (for (LSTPAG _ (create POINTER
                                      PAGE# _ (fetch DTDNEXTPAGE of \LISTPDTD)))
                  by (create POINTER
                             PAGE#
                                      (fetch (CONSPAGE NEXTPAGE) of LSTPAG)
                  while LSTPAG do (\BOXIPLUS FREE (fetch (CONSPAGE CNT) of LSTPAG]
              (T (for (PTR
                             (fetch DTDFREE of DTD)) by (\GETBASEPTR PTR 0) while PTR
                    do (CHECK (EQ (NTYPX PTR)
                                    TYPE))
                        (\BOXIPLUS FREE 1]
           (SETQ INUSE (-
                          (SETQ ALLOC (TIMES ALLOCMDS ITEMSPERMDS))
                           FREE))
           (COND
              ((fetch DTDHUNKP of DTD)
                                                                        Keep a cumulative table to be printed out at the end of this all
                                                                       ; by \STORAGE.HUNKTYPE
               (add (fetch (HUNKSTAT NITEMS) of STAT)
                    ALLOC)
               (add
                    (fetch (HUNKSTAT NFREE) of STAT)
                    (fetch (HUNKSTAT NINUSE) of STAT)
                    INUSE)
               (add
                    (fetch (HUNKSTAT NALLOCATED) of STAT)
                     (BOXCOUNT TYPE)))
              ((OR (NOT IN-USE-THRESHOLD)
                       INUSE IN-USE-THRESHOLD))
               (\STMDSTYPE NAME NPAGESALLOCATED ALLOC FREE INUSE (BOXCOUNT TYPE])
(\STLINP
  [LAMBDA (STR ALLOC TOT)
                                                                       (* bvm%: " 9-Feb-85 15:23")
    (printout NIL STR 30 .18 ALLOC 50 .18 (IDIFFERENCE TOT ALLOC)
           T1)
(\STMDSTYPE
  [LAMBDA (NAME NPAGESALLOCATED ALLOC FREE INUSE BOXCOUNT)
                                                                       ; Edited 8-Jan-88 14:33 by bvm
    (PRIN2 NAME)
    (LET ((COL (POSITION))
          NC)
          (if (AND (>= COL 15)
                   (< COL 19)
                   (> (SETQ COL (- 20 COL (NCHARS NPAGESALLOCATED)))
              then
                                                                        Past the point we allocated for starting the #pages field, but
                                                                       ; #pages is small, so we can squeak in.
                   (SPACES COL)
                   (printout NIL .I1 NPAGESALLOCATED)
           else (printout NIL 15 .I5 NPAGESALLOCATED)))
    (if (EQ NAME 'LISTP)
                                                                       ; Indicate that LISTP numbers for total & in use are approximate
             (\STMDS.APPROX ALLOC)
      else (printout NIL .18 ALLOC))
     printout NIL 30 .18 FREE 43)
    (if (EQ NAME 'LISTP)
        then (\STMDS.APPROX INUSE)
      else (printout NIL .18 INUSE))
    (printout NIL 56 .I10 BOXCOUNT T])
(\STMDS.APPROX
                                                                       ; Edited 8-Jan-88 14:33 by bvm
  [LAMBDA (N)
    ;; Print n in an 8-col field preceded by a ~ to indicate approximation
    (SPACES (- 7 (NCHARS N)))
(printout NIL "~" .I1 N])
```

```
(\STORAGE.HUNKTYPE
  [LAMBDA (TOTAL PAGE-THRESHOLD IN-USE-THRESHOLD)
                                                                    ; Edited 8-Jan-88 14:39 by bvm
    (DECLARE (USEDFREE HUNKSTATS))
    (PROG (NPAGESALLOCATED STAT)
          (for gctype.name in [constant (list unboxedblock.gct 'unboxedhunk)
                                               (LIST PTRBLOCK.GCT 'PTRHUNK)
                                               (LIST CODEBLOCK.GCT 'CODEHUNK]
             do [SETQ STAT (CAR (NTH HUNKSTATS (ADD1 (CAR GCTYPE.NAME]
                 (SETQ NPAGESALLOCATED (fetch (HUNKSTAT NPAGES) of STAT))
                 (\BOXIPLUS TOTAL NPAGESALLOCATED)
                 (COND
                    ((AND (NEQ NPAGESALLOCATED 0)
                          (OR (NOT PAGE-THRESHOLD)
                               (>= NPAGESALLOCATED PAGE-THRESHOLD))
                          (OR (NOT IN-USE-THRESHOLD)
                              (>= (fetch (HUNKSTAT NINUSE) of STAT)
                                  IN-USE-THRESHOLD)))
                     (\STMDSTYPE (CADR GCTYPE.NAME)
                            NPAGESALLOCATED
                            (fetch (HUNKSTAT NITEMS) of STAT)
                             (fetch (HUNKSTAT NFREE) of STAT)
                            (fetch (HUNKSTAT NINUSE) of STAT)
                            (fetch (HUNKSTAT NALLOCATED) of STAT])
(DECLARE%: DONTCOPY
(DECLARE%: EVAL@COMPILE
(RECORD HUNKSTAT (NPAGES NITEMS NFREE NINUSE NALLOCATED)
       NPAGES _ 0 NITEMS _ 0 NFREE _ 0 NINUSE _ 0 NALLOCATED _ 0)
(RPAQ? STORAGE.ARRAYSIZES '(4 16 64 256 1024 4096 16384 NIL))
(DECLARE%:
;; FOLLOWING DEFINITIONS EXPORTED
(DEFOPTIMIZER PUTBASEPTRX (&REST ARGS)
(CONS '(OPENLAMBDA (DATUM OFFSET NEWVALUE)
                                          (UNINTERRUPTABLY
                                              (\PUTBASE DATUM OFFSET (LOGOR (LOGAND 61440 (\GETBASE DATUM OFFSET))
                                                                             (LOGAND (\HILOC NEWVALUE)
                                                                                    4095)))
                                              (\PUTBASE DATUM (ADD1 OFFSET)
                                                     (\LOLOC NEWVALUE))
                                             NEWVALUE))
                                      ARGS))
(DECLARE%: EVAL@COMPILE
(RPAQQ \SMALLP 1)
(RPAQQ \FIXP 2)
(RPAQQ \FLOATP 3)
(RPAQQ \LITATOM 4)
(RPAQQ \LISTP 5)
(RPAQO \ARRAYP 6)
(RPAOO \STACKP 8)
(RPAQO \VMEMPAGEP 10)
(RPAQO \STREAM 11)
(RPAOO \NEW-ATOM 21)
(CONSTANTS \SMALLP \FIXP \FLOATP \LITATOM \LISTP \ARRAYP \STACKP \VMEMPAGEP \STREAM \NEW-ATOM)
(RPAQQ \BUILT-IN-SYSTEM-TYPES
       ((SMALLP)
        (FIXP 2)
        (FLOATP 2)
        (LITATOM)
        (LISTP 4 (0 2))
        (ARRAYP 6 (0))
(STRINGP 6 (0))
```

```
(STACKP 2 NIL \RECLAIMSTACKP)
         (CHARACTER)
         (VMEMPAGEP 256 NIL RELEASINGVMEMPAGE)
         (STREAM)
         (BITMAP)
         (COMPILED-CLOSURE 4 (0 2))
         (ONED-ARRAY 8 (0))
         (TWOD-ARRAY 10 (0))
         (GENERAL-ARRAY 10 (0 8))
         (BIGNUM)
         (RATIO)
         (COMPLEX)
         (PATHNAME)
         (NEW-ATOM 10 (2 4 6))
         (FILLER22)
         (FILLER23)
         (FILLER24)
         (FILLER25)
         (FILLER26)
         (FILLER27)
         (FILLER28)
         (FILLER29)
         (FILLER30)))
;; END EXPORTED DEFINITIONS
;; FOLLOWING DEFINITIONS EXPORTED
(DECLARE%: EVAL@COMPILE
[BLOCKRECORD DTD ((NIL BITS 2)
                     (DTDOBSOLETE FLAG)
                                                                           ; True for type of a redeclared datatype--not allowed to allocate
                                                                            more of these
                     (DTDFINALIZABLE FLAG)
                                                                            True if finalization exists for this type
                     (DTDNAME POINTER)
                                                                            Type name -- a symbol
                     (DTDCNT0 WORD)
                                                                            Incremental box count -- this plus DTDOLDCNT is the true box
                     (DTDSIZE WORD)
                                                                            Length of datum in words
                     (DTDFREE FULLXPOINTER)
                                                                            Pointer to first object on free chain, or NIL. Not used for LISTP
                                                                            True if objects of this type must be locked down (not pagefault)
                     (DTDLOCKEDP FLAG)
                                                                            True if this type is used as an array hunk type
                     (DTDHUNKP FLAG)
                     (DTDGCTYPE BITS 2)
                                                                           ; For hunk datatypes, is analogous to arrayblock's GCTYPE
                     (DTDDESCRS POINTER)
                     (DTDTYPESPECS POINTER)
                     (DTDPTRS POINTER)
                                                                           ; List of word offsets inside datum where reference-counted
                                                                            pointers are stored -- used by GC
                                                                            Box count' -- number of objects of this type ever allocated
                     (DTDOLDCNT FIXP)
                                                                            Currently only for LISTP pages -- page number of next page on
                     (DTDNEXTPAGE FIXP)
                                                                           chain of non-full cons pages
                     (DTDTYPEENTRY WORD)
                     ;; The word stored in the type table for objects of this type. Hi bits have numberp tags, ref countable, etc.
                     (DTDSUPERTYPE WORD)
                                                                           ; Type number of immediate supertype, or zero if none
        (ACCESSFNS DTD ((DTDCNTLOC (\ADDBASE DATUM 4))
                           (DTDCNT (IPLUS (fetch DTDOLDCNT DATUM)
                                            (fetch DTDCNT0 DATUM))
                                   (UNINTERRUPTABLY
                                        (replace DTDOLDCNT of DATUM with NEWVALUE)
                                        (replace DTDCNT0 of DATUM with 0))]
(DECLARE%: EVAL@COMPILE
(PUTPROPS \GETDTD MACRO ((typeNum)
                               (ADDBASE \DTDSpaceBase (ITIMES typeNum 18))))
(DEFORTIMIZER \TYPEMASK.UFN
                                     (&REST X)
                                           [(CE (CONSTANTEXPRESSIONP (CADR X]
                                           (if CE
                                               then '((OPCODES TYPEMASK.N , (CAR CE))
                                                       , (CAR X))
                                             else 'IGNOREMACRO)))
(DECLARE%: EVAL@COMPILE
(RPAQQ \GUARDSTORAGEFULL 128)
(RPAQQ \GUARD1STORAGEFULL 64)
(CONSTANTS \GUARDSTORAGEFULL \GUARD1STORAGEFULL)
```

```
{MEDLEY} < sources > LLDATATYPE.; 1
                                                                                                                            Page 18
(DECLARE%: DOEVAL@COMPILE DONTCOPY
(GLOBALVARS \NxtMDSPage \LeastMDSPage \SecondArrayPage \SecondMDSPage \MDSFREELISTPAGE \MaxSysTypeNum
        \MaxTypeNumber \STORAGEFULL \INTERRUPTSTATE \PENDINGINTERRUPT)
:: END EXPORTED DEFINITIONS
(RPAQQ STORAGEFULLSTATES ((\SFS.NORMAL NIL)
                                  (\SFS.NOTSWITCHABLE 1)
                                 (\SFS.SWITCHABLE 2)
                                 (\SFS.ARRAYSWITCHED 3)
                                 (\SFS.FULLYSWITCHED 4)))
(DECLARE%: EVAL@COMPILE
(RPAQQ \SFS.NORMAL NIL)
(RPAQQ \SFS.NOTSWITCHABLE 1)
(RPAQQ \SFS.SWITCHABLE 2)
(RPAQO \SFS.ARRAYSWITCHED 3)
(RPAQO \SFS.FULLYSWITCHED 4)
(CONSTANTS (\SFS.NORMAL NIL)
        (\SFS.NOTSWITCHABLE 1)
        (\SFS.SWITCHABLE 2)
        (\SFS.ARRAYSWITCHED 3)
        (\SFS.FULLYSWITCHED 4))
;; for MAKEINIT
(DEFINEQ
(CREATEMDSTYPETABLE
                                                                            ; Edited 8-Feb-91 16:10 by jds
  [LAMBDA NIL
    ;; called only under MAKEINIT to initialize the main data space type table
    ;; This isn't the only place data-type entries get initialized in the INIT.
    ;; --\CREATE.SYMBOL takes care of initing atom pages.
    ;; -- POSTINITARRAYS does some array-space initing
    ;; -- \ALLOCBLOCK of course creates new pages & inits their entries
    ;; -- \ALLOCMDSPAGE ditto
     (CREATEPAGES \MDSTypeTable \MDSTTsize NIL T)
    [PROG (VP)
     ;; FIRST SET ALL TO NOREF
            (SETQ VP 0)
            (FRPTQ (UNFOLD \MDSTTsize WORDSPERPAGE)
                    (\PUTBASE \MDSTypeTable VP \TT.NOREF)
                    (add VP 1))
     :; NOW SET UP SMALLPS
           [for SEGMENT in (LIST \SmallPosHi \SmallNegHi)
               do (for PAGE from 0 to (SUB1 PAGESPERSEGMENT) by (FOLDLO \MDSIncrement WORDSPERPAGE)
                      do (\MAKEMDSENTRY (LOGOR PAGE (UNFOLD SEGMENT PAGESPERSEGMENT))
(LOGOR \TT.NOREF \TT.FIXP \TT.NUMBERP \TT.ATOM \SMALLP]
               r PAGE from 0 to (SUB1 PAGESPERSEGMENT) by (FOLDLO \MDSIncrement WORDSPERPAGE) do (\MAKEMDSENTRY (LOGOR PAGE (UNFOLD \CHARHI PAGESPERSEGMENT))
            (for PAGE from 0 to
                           (LOGOR \TT.NOREF \CHARACTERP]
     (CREATEPAGES \MISCSTATS (FOLDLO \MDSIncrement WORDSPERPAGE)
     (\MAKEMDSENTRY (PAGELOC \MISCSTATS)
             (LOGOR \TT.NOREF \TT.FIXP \TT.NUMBERP \TT.ATOM \FIXP])
(INITDATATYPES
                                                                            ; Edited 9-Feb-91 17:49 by jds
  [LAMBDA NIL
  Called only under MAKEINIT. Create the initial data type table from the info in the list INITIALDTDCONTENTS, whose elements are in type number
 order and of the form (name size pointer-fields finalization). Called before it is possible to make new atoms, so the DTDNAME field will not be filled in
;;; until INITDATATYPENAMES runs. We have to run this before turning on atoms so that we can create strings and pnames.
     (LET [(NSYSTYPES (ALLOCAL (LENGTH INITIALDTDCONTENTS]
           (CREATEPAGES \DTDSpaceBase 1 NIL T)
          ;; First DTD page is locked, probably because CONS microcode touches the listp dtd. Not sure this is essential
           (CREATEPAGES (\ADDBASE \DTDSpaceBase WORDSPERPAGE)
                   (SUB1 (FOLDHI (ADD1 (TIMES (ADD1 NSYSTYPES)
                                                   \DTDSize))
```

(if FINAL then

(PROGN

(replace DTDFINALIZABLE of DTD with T)

(\PUTBASEPTR \FINALIZATION.FUNCTIONS 0 (COPY '\RECLAIMARRAYBLOCK])

(COPY FINAL]

(replace DTDFINALIZABLE of (\GETDTD 0) with T)

(\PUTBASEPTR \FINALIZATION.FUNCTIONS (UNFOLD NTYPX WORDSPERCELL)

```
{MEDLEY}<sources>LLDATATYPE.;1 (INITDATATYPES cont.)
                                                                                                                                    Page 19
                                    WORDSPERPAGE)))
           ;; Create the rest of the pages we will need for initial dtd. They need not be locked. (ADD1 NSYSTYPES) is because nonexistent type zero
           :: occupies table space
           ;; (ADD1 (TIMES ...)) is because you've got to create the next page for DTD's if you allocate the last one on a page. This arose when I ;; icreased the # of system types, and we wound up with NSYSTYPES = 63. Result: Illegal addr in the INIT when it tried to allocate the next
           [for D in (LOCAL INITIALDTDCONTENTS) bind DTD as TYPENO from 1
              do
                  ;; Run thru the initial data type decls (the gut-level system datatypes), and declare them in the INIT.DLINIT.
                   (SETQ DTD (\GETDTD TYPENO))
                                                                                 ; Create a Data-Type-Descriptor for the new type
                   [replace DIDTYPEENTRY of DID with (LOGOR TYPENO (COND
                                                                                ([ALLOCAL (FMEMB (CAR D)
                                                                                                      '(SMALLP FIXP FLOATP)
                                                                                 \TT.NUMBERP)
                                                                                (T 0))
                                                                    (COND
                                                                       ([ALLOCAL (FMEMB (CAR D)
                                                                                             '(SMALLP FIXP FLOATP LITATOM NEW-ATOM)
                                                                        \TT.ATOM)
                                                                       (T 0))
                                                                    (COND
                                                                       ([ALLOCAL (FMEMB (CAR D)
                                                                                              (SMALLP FIXP]
                                                                        \TT.FIXP)
                                                                       (T 0))
                                                                    (COND
                                                                       ((ALLOCAL (EQ (CAR D)
                                                                                         NEW-ATOM))
                                                                                 ; Add NewAtom Entry '90/07/18 ON
                                                                        \TT.NOREF)
                                                                       (T 0))
                                                                    (COND
                                                                       ([ALLOCAL (FMEMB (CAR D)
                                                                                             (LITATOM NEW-ATOM)
                                                                                 : FOR TYPE TESTING BY TYPEMASK.
                                                                         (CONSTANT \TT.SYMBOLP))
                                                                       (T 0))
                                                                   (COND
                                                                       ((ALLOCAL (NOT (CADR D)))
                                                              ;; no size, no ref. For those types that are really declared later on,
                                                              ;; \ASSIGNDATATYPE1 will fix DTDTYPEENTRY to be correct
                                                                        \TT.NOREF)
                                                                       (T 0]
                                                                                ; Set up the type-mask field with the appropriate meta-type bits
                   (COND
                      ((EQ (CAR D)
'NEW-ATOM)
                       ;; For NEW-ATOM, mark it a subtype of LITATOM.
                        (replace DTDSUPERTYPE of DTD with \LITATOM)))
                   (COND
                      ((ALLOCAL (AND (CAR D)
                                         (CADR D)))
                                                                                 ; Set the data type's size
                        (replace DTDSIZE of DTD with (LOCAL (CADR D]
           [COND
               ((NEQ CDRCODING 0)
                (SETQ.NOREF \LISTPDTD (\GETDTD \LISTP]
           (SETQ \MaxSysTypeNum (SETQ \MaxTypeNumber NSYSTYPES))
          NIL1)
(INITDATATYPENAMES
                                                                                ; Edited 2-Apr-91 02:17 by sybalsky
  [LAMBDA NIL
 ; Called in MAKEINIT after it is ok to create arrays and new atoms. Here we finish initializing the data type tables -- fill in type names and the list of
;;; pointers. Also set finalization for built-in types.
    ;; Because this is running in the INIT, everything really HAS to be atom numbers, so leave the \ATOMPNAMEINDEX call alone in tjhis function.
    (SETQ \FINALIZATION.FUNCTIONS (\ALLOCBLOCK (ADD1 \EndTypeNumber)
                                                   T))
    [for D in (LOCAL INITIALDTDCONTENTS) as NTYPX from 1
        do (LET [(DTD (\GETDTD NTYPX))
                    (FINAL (LOCAL (CADDDR D
                                                                                 ; d = (name size ptrs finalization)
                   [replace DTDNAME of DTD with (\ATOMPNAMEINDEX (LOCAL (CAR D]
                                                                                  Smash the name from our world into his
                   [replace DTDPTRS of DTD with (COPY (LOCAL (CADDR D]; And the list of pointer offsets
```

; Set finalization for this type

; Do finalization for array blocks (type 0) specially to avoid ; incompatible change to BUILT-IN-SYSTEM-TYPES

```
{MEDLEY} < sources > LLDATATYPE.; 1
                                                                                                             Page 20
(DECLARE%: DONTCOPY
(ADDTOVAR INITVALUES (\NxtMDSPage \FirstMDSPage)
                      (\LeastMDSPage \FirstMDSPage)
                      (\SecondMDSPage \DefaultSecondMDSPage)
                      (\SecondArrayPage \DefaultSecondArrayPage)
                     (\MDSFREELISTPAGE)
                      (\MaxSysTypeNum 0)
                     (\MaxTypeNumber))
(ADDTOVAR INITPTRS (\FINALIZATION.FUNCTIONS))
(ADDTOVAR INEWCOMS (FNS NTYPX \ALLOCMDSPAGE \MAKEMDSENTRY \INITMDSPAGE \ASSIGNDATATYPE1 \TYPENUMBERFROMNAME
                          \CREATECELL \NEW2PAGE)
                     (FNS CREATEMDSTYPETABLE INITDATATYPES INITDATATYPENAMES)
                     (VARS \BUILT-IN-SYSTEM-TYPES))
(ADDTOVAR RDCOMS (FNS NTYPX TYPENAME \TYPENAMEFROMNUMBER))
(ADDTOVAR RDVALS (\MaxTypeNumber))
(ADDTOVAR RD.SUBFNS (\ARRAYTYPENAME LAMBDA (X)
                            'ARRAYP))
(ADDTOVAR EXPANDMACROFNS \GETDTD PUTBASEPTRX REPLACEFIELD FETCHFIELD \GETBITS \PUTBITS \TESTBITS GETBASEBITS
                                  PUTBASEBITS FFETCHFIELD FREPLACEFIELD FREPLACEFIELDVAL REPLACEFIELDVAL NCREATE
(ADDTOVAR MKI.SUBFNS (\GCDISABLED . NILL)
                      (CREATECELL . I.\CREATECELL)
                      (\CHECKFORSTORAGEFULL . NILL))
(ADDTOVAR DONTCOMPILEFNS CREATEMDSTYPETABLE INITDATATYPES INITDATATYPENAMES)
(DECLARE%: DOEVAL@COMPILE DONTCOPY
(LOCALVARS . T)
(PUTPROPS LLDATATYPE FILETYPE CL:COMPILE-FILE)
(DECLARE%: EVAL@COMPILE DONTCOPY
(FILESLOAD (LOADCOMP)
      DTDECLARE)
(PUTPROPS LLDATATYPE COPYRIGHT ("VENUE, Oakland, CA" 1982 1983 1984 1985 1986 1987 1988 1989 1990 1991 1992 1993 1994 1995 1999))
```

{MEDLEY}<sources>LLDATATYPE.;1 28-Jun-2024 18:34:03

-- Listed on 30-Jun-2024 13:15:59 --

FUNCTION INDEX /REPLACEFIELD11 \ASSIGNDATATYPE15 \SET.STORAGE.STATE4 NCREATE211 BOXCOUNT9 NTYPX2 \BLOCKDATAP12 \SETTYPEMASK4 PUTBASEPTRX11 CONSCOUNT9 \CHECKFORSTORAGEFULL3 \STLINP15 REPLACEFIELD8 \CREATECELL7 \STMDS.APPROX15 CREATEMDSTYPETABLE18 REPLACEFIELDVAL11 \DOSTORAGEFULLINTERRUPT .4 \STMDSTYPE15 \STORAGE.HUNKTYPE16 \DTEST9 \DTEST.UFN9 STORAGE.LEFT14 \STORAGE.TYPE14 FETCHFIELD8 \INITMDSPAGE5 \INSTANCE-P10 TYPENAME12 \TYPECHECK9 GETDESCRIPTORS11 TYPENAMEP \TYPECHECK.UFN1012 USERDATATYPES12 \INSTANCEP.UFN10 GETFIELDSPECS11 \TYPEMASK.UFN2 \MAKEMDSENTRY5 \TYPENAMEFROMNUMBER12 GETSUPERTYPE11 \ADVANCE.STORAGE.STATE ...4 INITDATATYPENAMES19 \ALLOCMDSPAGE2 \MAPMDS3 \TYPENUMBERFROMNAME7 INITDATATYPES18 \ALLOCPAGEBLOCK2 NEW2PAGE5 \TYPEP.UFN2 \RESOLVE.TYPENUMBER7 \ALLOCVIRTUALPAGEBLOCK ..3 NCREATE11 VARIABLE INDEX INITVALUES20 ASSIGNDATATYPE.ASKUSERWAIT7 STORAGE.ARRAYSIZES16 CROSSCOMPILING7 MKI.SUBFNS20 STORAGEFULLSTATES18 \BUILT-IN-SYSTEM-TYPES16 DONTCOMPILEFNS20 RD.SUBFNS20 \STORAGEFULL7 EXPANDMACROFNS20 RDCOMS20 \STORAGEFULLSTATE7 INEWCOMS20 RDVALS20 INITPTRS20 **CONSTANT INDEX** \ARRAYP16 \LISTP16 \SFS.NORMAL18 \STREAM16 \SFS.NOTSWITCHABLE18 \VMEMPAGEP16 \LITATOM16 \FIXP16 \SFS.SWITCHABLE18 \FLOATP16 \NEW-ATOM16 \GUARD1STORAGEFULL17 SFS.ARRAYSWITCHED18 \SMALLP16 \GUARDSTORAGEFULL17 \SFS.FULLYSWITCHED18 \STACKP16 **OPTIMIZER INDEX RECORD INDEX** PROPERTY INDEX LLDATATYPE20

MACRO INDEX

\GETDTD17