

# Class overview today - November 21, 2016

- Lecture: Advection of the Earth's surface
  - The advection equation
    - Application: Bedrock river incision

• Exercise II: River advection



# Introduction to Quantitative Geology

# Advection of the Earth's surface: Fluvial incision and rock uplift

Lecturer: Jorina Schütt jorina.schutt@helsinki.fi

21.11.2016




# Goals of this lecture

• Introduce the advection equation

 Discuss application of the advection equation to bedrock river erosion




## What is advection?



- Advection involves a lateral translation of some quantity
  - For example, the transfer of heat by physical movement of molecules or atoms within a material. A type of convection, mostly applied to heat transfer in solid materials.



## What is advection?



- Advection involves a lateral translation of some quantity
  - For example, the transfer of heat by physical movement of molecules or atoms within a material. A type of convection, mostly applied to heat transfer in solid materials.



# Diffusion equation

$$q = -\rho \kappa \frac{\partial h}{\partial x}$$

$$\frac{\partial h}{\partial t} = -\frac{1}{\rho} \frac{\partial q}{\partial x}$$

- Last week we were introduced to the diffusion equation
  - Flux (transport of mass or transfer of energy)
     <u>proportional to a gradient</u>
  - Conservation of mass: Any change in flux results in a change in mass/energy



# Diffusion equation

## Diffusion

$$\frac{\partial h}{\partial t} = -\kappa \frac{\partial^2 h}{\partial x^2}$$

$$q = -\rho \kappa \frac{\partial h}{\partial x}$$

$$\frac{\partial h}{\partial t} = -\frac{1}{\rho} \frac{\partial q}{\partial x}$$

- Substitute the upper equation on the left into the lower to get the classic diffusion equation
  - q = sediment flux per unit length
    - $\rho$  = bulk sediment density
    - $\kappa$  = sediment diffusivity
    - h = elevation
    - x =distance from divide
    - t = time



Diffusion

$$\frac{\partial h}{\partial t} = -\kappa \frac{\partial^2 h}{\partial x^2}$$

Advection

$$\frac{\partial h}{\partial t} = c \frac{\partial h}{\partial x}$$

This week we meet the advection equation



## **Diffusion**

$$\frac{\partial h}{\partial t} = -\kappa \frac{\partial^2 h}{\partial x^2}$$

$$\frac{\partial h}{\partial t} = c \frac{\partial h}{\partial x}$$

- This week we meet the advection equation
- Two key differences:
  - Change in mass/energy with time proportional to gradient, rather than curvature (or change in gradient)
  - Advection coefficient c has units of  $\lfloor L/T \rfloor$ , rather than  $\lfloor L^2/T \rfloor$



River channel profiles

## Diffusion

$$\frac{\partial h}{\partial t} = -\kappa \frac{\partial^2 h}{\partial x^2}$$

$$\frac{\partial h}{\partial t} = c \frac{\partial h}{\partial x}$$

- This week we meet the advection equation
- Two key differences:
  - Change in mass/energy with time proportional to gradient, rather than curvature (or change in gradient)
  - Advection coefficient c has units of  $\lfloor L/T \rfloor$ , rather than  $\lfloor L^2/T \rfloor$




Fig. 1.7, Pelletier, 2008




River channel profiles

### Diffusion

$$\frac{\partial h}{\partial t} = -\kappa \frac{\partial^2 h}{\partial x^2}$$

$$\frac{\partial h}{\partial t} = c \frac{\partial h}{\partial x}$$



- Two key differences:
  - Change in mass/energy with time proportional to gradient, rather than curvature (or change in gradient)
  - Advection coefficient c has units of  $\lfloor L/T \rfloor$ , rather than  $\lfloor L^2/T \rfloor$




Fig. 1.7, Pelletier, 2008



River channel profiles

## Diffusion

$$\frac{\partial h}{\partial t} = -\kappa \frac{\partial^2 h}{\partial x^2}$$

$$\frac{\partial h}{\partial t} = c \frac{\partial h}{\partial x}$$



- (b) Two key differences:
  - Change in mass/energy with time proportional to gradient, rather than curvature (or change in gradient)
  - Advection coefficient c has units of  $\lfloor L/T \rfloor$ , rather than  $\lfloor L^2/T \rfloor$




Fig. 1.7, Pelletier, 2008



## River channel profiles

Advection




Fig. 1.7, Pelletier, 2008

## Diffusion

$$\frac{\partial h}{\partial t} = -\kappa \frac{\partial^2 h}{\partial x^2}$$

### Advection

$$\frac{\partial h}{\partial t} = c \frac{\partial h}{\partial x}$$

- This week we meet the advection equation
  - Two key differences:
    - Change in mass/energy with time proportional to gradient, rather than curvature (or change in gradient)
    - Advection coefficient c has units of  $\lfloor L/T \rfloor$ , rather than  $\lfloor L^2/T \rfloor$

(a)



## River channel profiles

Advection




Fig. 1.7, Pelletier, 2008

## Diffusion

$$\frac{\partial h}{\partial t} = -\kappa \frac{\partial^2 h}{\partial x^2}$$

$$\frac{\partial h}{\partial t} = c \frac{\partial h}{\partial x}$$

- This week we meet the advection equation
  - Two key differences:
    - Change in mass/energy with time proportional to gradient, rather than curvature (or change in gradient)
  - Advection coefficient c has units of  $\lfloor L/T \rfloor$ , rather than  $\lfloor L^2/T \rfloor$



# River channel profiles Advection




Fig. 1.7, Pelletier, 2008

## Diffusion

$$\frac{\partial h}{\partial t} = -\kappa \frac{\partial^2 h}{\partial x^2}$$

$$\frac{\partial h}{\partial t} = c \frac{\partial h}{\partial x}$$

- This week we meet the advection equation
  - Two key differences:
    - Change in mass/energy with time proportional to gradient, rather than curvature (or change in gradient)
    - Advection coefficient c has units of  $\lfloor L/T \rfloor$ , rather than  $\lfloor L^2/T \rfloor$



## River channel profiles

Advection




Fig. 1.7, Pelletier, 2008

## Diffusion

$$\frac{\partial h}{\partial t} = -\kappa \frac{\partial^2 h}{\partial x^2}$$

### Advection

$$\frac{\partial h}{\partial t} = c \frac{\partial h}{\partial x}$$


Diffusion: Rate of erosion <u>depends on change</u> in hillslope gradient (curvature)

- Advection: Rate of erosion is <u>directly</u> proportional to hillslope gradient
  - Also, no conservation of mass (deposition)



## Advection at a constant rate c

River channel profile



- Surface elevation changes in <u>direct proportion to surface slope</u>
- Result is lateral propagation of the topography or river channel profile
- Although this is interesting, it is not that common in nature



# Advection of the Earth's surface: An example




## Bedrock river erosion

Purely an advection problem with a <u>spatially variable</u> advection coefficient



## Bedrock river erosion

## Drainage basin




HELSINGIN YLIOPISTO
HELSINGFORS UNIVERSITET
UNIVERSITY OF HELSINKI



Not much bedrock being eroded here...

## Bedrock river erosion

## Drainage basin




HELSINGIN YLIOPISTO
HELSINGFORS UNIVERSITET
UNIVERSITY OF HELSINKI



 Rapid bedrock incision has formed a steep gorge in this case




# River erosion as an advection process



• With a constant advection coefficient c, we predict <u>lateral</u> migration of the river profile at a constant rate (c)



## River erosion as an advection process




- With a constant advection coefficient c, we predict <u>lateral</u> migration of the river profile at a constant rate (c)
  - Do you think this works in real (bedrock) rivers?

Intro to Quantitative Geology




## River erosion as an advection process



- With a constant advection coefficient c, we predict <u>lateral</u> migration of the river profile at a constant rate (c)
  - Do you think this works in real (bedrock) rivers?
  - What might affect the rate of lateral migration?




# What affects the efficiency of river erosion?



- The amount of water flowing in the river (discharge) and sediment
- The slope of the river channel
- The strength of the underlying bedrock



# What affects the efficiency of river erosion?




- The amount of water flowing in the river (discharge) and sediment
- The slope of the river channel
- The strength of the underlying bedrock

• Are these constant?



# Stream-power model of river incision




 Rather than being constant, the rate of lateral advection in river systems is <u>spatially variable</u>

$$\frac{\partial h}{\partial t} = \frac{k_f}{w} Q \frac{\partial h}{\partial x}$$

where  $k_f$  is a material property of the bedrock (erodibility), w is the channel width, and Q is discharge



# Stream-power model of river incision



 Rather than being constant, the rate of lateral advection in river systems is <u>spatially variable</u>

$$\frac{\partial h}{\partial t} = \frac{k_f}{w} Q \frac{\partial h}{\partial x}$$

where  $k_f$  is a material property of the bedrock (erodibility), w is the channel width, and Q is discharge

This is known as the stream-power erosion model



# Stream-power model of river incision

 If we <u>assume precipitation is uniform</u> in the drainage basin, discharge Q will <u>scale with drainage basin area</u>, so we can modify our equation to read

$$\frac{\partial h}{\partial t} = \frac{k_f}{w} Q \frac{\partial h}{\partial x} \longrightarrow \frac{\partial h}{\partial t} = KA^m S^n$$


where K is an erosional efficiency factor (accounts for lithology, climate, channel geometry, sediment supply, etc. (!)), A is upstream drainage area, S is channel slope, and M are area and slope exponents

• If we assume the drainage basin area increases with distance from the drainage divide x, we can replace the area with an estimate  $A = x^{5/3}$ 



# Test your might


$$\frac{\partial h}{\partial t} = U - KA^m S^r$$



- Based on our stream-power erosion equation, what general form would a channel profile take?
  - If we assume we have reached a steady state  $(\partial h/\partial t = 0)$  and n = 1, erosion must balance uplift U everywhere
  - If we further assume precipitation is constant, bedrock erodibility is constant and  $A = x^{5/3}$ , how would the channel steepness vary as you move downstream from the divide?
  - Think about how S would change as x increases



# Evolution of a channel profile



- A few stream-power erosion observations:
  - Stream power <u>increases</u>
     <u>downstream as the discharge</u>
     grows
  - Steeper slopes occur upstream where the discharge is low
  - Incision <u>migrates upstream</u> until a balance is attained between erosion and uplift



What is the main difference between the advection and diffusion equations?

• What is special about the stream power erosion model compared to the general advection equation?

 Why does the rate of advection matter in heat transfer problems?



 What is the main difference between the advection and diffusion equations?

What is special about the stream power erosion model compared to the general advection equation?

 Why does the rate of advection matter in heat transfer problems?



 What is the main difference between the advection and diffusion equations?

• What is special about the stream power erosion model compared to the general advection equation?

 Why does the rate of advection matter in heat transfer problems?



## References

Allen, P.A. (1997). Earth Surface Processes (First edition.). Wiley-Blackwell.

Pelletier, J. D. (2008). Quantitative modeling of earth surface processes (Vol. 304). Cambridge University Press.