Preparing for a Session

To communicate, you can open a port for your application and make it available to receive session requests, to initiate sessions, or both. Applications that are able to receive session requests can choose to accept or reject incoming session requests.

Before an application can accept and establish a session with another application, the **PPC Toolbox** authenticates the initiating user (unless guest access is enabled or the applications are located on the same computer). Once a session begins, the two applications can exchange data with each other.

Initiating a PPC Session


Once you have established the name and the location of the port that you want to communicate with, you can initiate a session. You can use either the StartSecureSession function or the PPCStart function to initiate a session. The StartSecureSession function displays several dialog boxes on the user's screen to identify each user who requests a session. You may prefer to use the PPCStart function for low-level code such as that used for drivers, which typically do not provide a user interface. You may also prefer to use PPCStart when the application you are initiating a session with does not require authentication. The IPCListPorts and PPCBrowser functions return information about whether a particular port requires authentication.

Note: Do not call the <u>StartSecureSession</u> function from an application that is running in the background, since it requires that several dialog boxes appear on the user's screen.

The <u>StartSecureSession</u> function provides authentication services to identify each user who requests a session. This function combines the processes of prompting for user name and password and initiating a session into one synchronous procedure call. If <u>authentication</u> fails, the <u>PPC Toolbox</u> rejects the incoming session request.

err = <u>StartSecureSession</u> (&pb, &<u>userName</u>, <u>useDefault</u>, <u>allowGuest</u>, <u>guestSelected</u>, <u>prompt</u>);

Set the <u>useDefault</u> parameter to <u>TRUE</u> if you want the <u>StartSecureSession</u> function to use the default user identity (described later in this section). If the default user identity cannot be authenticated, the <u>StartSecureSession</u> function displays a dialog box to allow a user to log on. The following picture shows the user identity dialog box.



The user identity dialog box

The <u>prompt</u> parameter of the <u>StartSecureSession</u> function allows you to specify a line of text that the dialog box can display. The <u>allowGuest</u> parameter specifies whether to enable the Guest radio button. If a port requires authentication, you should set this parameter to <u>FALSE</u>.

The <u>userName</u> parameter specifies the name of the user who is attempting to initiate a session. If the user name is not specified, the user identity dialog box appears on the user's screen with the owner name provided from the Sharing Setup control panel.

If the user enters an invalid password, the **<u>StartSecureSession</u>** function displays the dialog box shown in the next picture:



The incorrect password dialog box

After the user clicks OK, the user identity dialog box reappears in the foreground so that the user can enter the password again.

If the user's name is invalid, the **<u>StartSecureSession</u>** function displays the dialog box shown in the following picture:



The invalid user name dialog box

After the user clicks OK, the user identity dialog box reappears so that the user can enter a new user name.

The <u>StartSecureSession</u> function remains in this loop until a secure session is initiated or the user clicks Cancel in the user identity dialog box. If a secure session is initiated, <u>StartSecureSession</u> returns the user reference number in the corresponding field in the <u>PPCStart</u> parameter block. The user reference number represents the user name and password. A user reference number of 0 indicates that a session has been initiated with <u>guest access</u>.

Before your application quits, you need to invalidate all user reference numbers obtained with the **StartSecureSession** function except for the default user reference number and the guest reference number (0).

The following program illustrates how to use the <u>StartSecureSession</u> function to establish an authenticated session. This listing shows only one session, although your application may conduct multiple sessions at one time.

```
// Using the StartSecureSession function to establish a session
// Assuming inclusion of macheaders
#include <PPCToolBox.h>

// Prototype code like this prior to calling it:
OSErr MyStartSecureSession

(PortInfoPtr,
LocationNamePtr,
PPCPortRefNum,
PPCSessRefNum *,
long *, long *, Str32, Boolean *);

OSErr MyStartSecureSession
(PortInfoPtr thePortInfoPtr,
```

LocationNamePtr

PPCPortRefNum

theLocationNamePtr,

thePortRefNum,

}

```
*theSessRefNum,
              PPCSessRefNum
              long
                                           *theUserRefNum,
                                           *theRejectInfo,
              <u>long</u>
              Str32
                                           userName.
              Boolean
                                           *guestSelected)
{
   PPCStartPBRec thePPCStartPBRec;
   <u>Boolean</u>
              useDefault;
   <u>Boolean</u>
              allowGuest:
   OSErr
              err;
   thePPCStartPBRec.ioCompletion = NULL;
   thePPCStartPBRec.portRefNum = thePortRefNum;
                                           // from the PPCOpen function
   thePPCStartPBRec.serviceType = ppcServiceRealTime;
   thePPCStartPBRec.resFlag = 0;
   thePPCStartPBRec.portName = &thePortInfoPtr->name;
                                           // from PPCBrowser function
   thePPCStartPBRec.<u>locationName</u> = theLocationNamePtr;
                                           // from PPCBrowser function
   thePPCStartPBRec.userData = 0;
   // try to connect with default user identity
   useDefault = TRUE;
   // highlight the Guest button appropriately
   allowGuest = !thePortInfoPtr->authRequired;
   err = <u>StartSecureSession</u>(&thePPCStartPBRec, userName, useDefault,
                                allowGuest, guestSelected, NULL);
   if ( err == <u>noErr</u> ) {
       *theSessRefNum = thePPCStartPBRec.sessRefNum;
       *theUserRefNum = thePPCStartPBRec.userRefNum;
   }
   else if (err == <u>userRejectErr</u>)
       // return rejectInfo from the PPCReject function
       *theRejectInfo = thePPCStartPBRec.rejectInfo;
   return err;
```

For low-level code such as that used for drivers (which typically do not provide a user interface), you can use the **PPCStart** function instead of the StartSecureSession function to initiate a session. You can also use the **IPCListPorts** function (instead of displaying the program linking dialog box) to obtain a list of ports.

If the <u>authRequired</u> field of the port information record contains <u>FALSE</u>, the port allows guest access. If the authRequired field of the port information record contains TRUE, use the PPCStart function and the user reference number obtained previously from the StartSecureSession function to

reestablish an authenticated session.

You can also attempt to log on as the default user using the **GetDefaultUser** function to obtain the default user reference number and the default <u>userName</u>. The default <u>userName</u> is established after the owner starts up the computer.

```
err = GetDefaultUser (&userRef, userName);
```

The userRef parameter is a reference number that represents the user name and password of the default user. The userName parameter contains the owner name that is specified in the Sharing Setup control panel.

The <u>GetDefaultUser</u> function returns an error when the default user identity does not exist (no name is specified in the Sharing Setup control panel) or the user is not currently logged on.

The following program illustrates how you use the **PPCStart** function to initiate a session. The **PPCStart** function uses the port information record and the <u>location name</u> record to attempt to open a session with the selected PPC port.

```
// Initiating a session using the PPCStart function
// Assuming inclusion of MacHeaders
#include < PPCToolBox.h>
// Prototype your function like this prior to calling it
OSErr MyPPCStart(PortInfoPtr, LocationNamePtr, PPCPortRefNum,
                    PPCSessRefNum *, long *, long *);
OSErr MyPPCStart
                     (PortInfoPtr
                                          thePortInfoPtr,
                     LocationNamePtr
                                          theLocationNamePtr,
                     PPCPortRefNum
                                          thePortRefNum,
                     PPCSessRefNum
                                          *theSessRefNum,
                                          *theUserRefNum,
                     <u>long</u>
                     long
                                          *theRejectInfo)
{
   PPCStartPBRec
                     thePPCStartPBRec;
   Str32
                     userName;
   <u>OSErr</u>
                     err:
   thePPCStartPBRec.ioCompletion
                                         = NULL;
   thePPCStartPBRec.portRefNum
                                         = thePortRefNum;
                                         // from PPCOpen function
   thePPCStartPBRec.serviceType
                                         = ppcServiceRealTime;
   thePPCStartPBRec.resFlag
                                         = 0;
   thePPCStartPBRec.portName
                                         = &thePortInfoPtr->name;
                                         // destination port
   thePPCStartPBRec.locationName
                                         = theLocationNamePtr;
                                         // destination location
```

}

```
// application-specific data for PPCInform
thePPCStartPBRec.userData = 0;
   err = <u>GetDefaultUser</u>(&thePPCStartPBRec.<u>userRefNum</u>, <u>userName</u>);
   if (err!= noErr)
    thePPCStartPBRec.userRefNum = 0;
   if (thePortInfoPtr->authRequired && !thePPCStartPBRec.userRefNum)
    // port selected does not allow guests and you do not have a default
    // user reference number, so you cannot log on to this port
     err = authFailErr;
   else
    // attempt to log on
     err = PPCStart(&thePPCStartPBRec, <u>FALSE</u>);
   if ( err == noErr ) {
     *theSessRefNum = thePPCStartPBRec.sessRefNum;
     *theUserRefNum = thePPCStartPBRec.userRefNum;
   }
   else if ( err == <u>userRejectErr</u> )
      // return rejectInfo from the PPCReject function
      *theRejectInfo = thePPCStartPBRec.rejectInfo;
   return err;
```

The port to which you wish to connect must have an outstanding **PPCInform** function to successfully start a session. You cannot initiate a session with a port that is not able to receive session requests.

If the port is open, has an outstanding **PPCInform** posted, and accepts your session request, the **PPCStart** function returns a <u>noErr</u> result code and a valid session reference number. This session reference number is used to identify the session during the exchange of data.