

## Network topology diagram:



### **VLSM** tree:



## **Router configuration commands:**

#### Headquarters (H):

enable configure terminal hostname H enable secret head service password-encryption access-list 1 permit host 1.1.16.5 0.0.0.0 access-list 1 deny any line vty 04 access-class 1 in password leader login transport input telnet exit interface GigabitEthernet0/1 ip address 1.1.16.1 255.255.248.0 no shutdown exit interface Serial0/0/0 ip address 1.1.28.65 255.255.255.252 no shutdown exit interface Serial0/0/1 ip address 1.1.28.69 255.255.255.252 no shutdown exit interface Serial0/1/0 ip address 1.1.28.73 255.255.255.252 no shutdown interface Serial0/1/1 ip address 1.1.28.77 255.255.255.252 no shutdown exit router rip version 2 network 1.1.28.64 network 1.1.28.68 network 1.1.28.72 network 1.1.28.76 passive-interface GigabitEthernet0/1 no auto-summary exit ip route 1.1.0.0 255.255.240.0 Serial0/0/0 ip route 1.1.24.0 255.255.252.0 Serial0/1/0 ip route 1.1.28.0 255.255.255.224 Serial0/0/1 ip route 1.1.28.32 255.255.255.224 Serial0/1/1

end

copy run start

#### Lobby (L):

enable

configure terminal

hostname L

interface GigabitEthernet0/1

ip address 1.1.0.1 255.255.240.0

ip helper-address 1.1.16.2

no shutdown

exit

interface Serial0/0/0

ip address 1.1.28.66 255.255.255.252

no shutdown

exit

interface Serial0/0/1

ip address 1.1.28.94 255.255.255.252

no shutdown

exit

interface Serial0/1/0

ip address 1.1.28.81 255.255.255.252

no shutdown

exit

ip route 1.1.28.32 255.255.255.224 Serial0/0/1 12

ip route 1.1.28.0 255.255.255.224 Serial0/1/0 12

ip route 1.1.24.0 255.255.252.0 Serial0/1/0 12

ip route 1.1.28.32 255.255.255.224 Serial0/0/0

ip route 1.1.28.0 255.255.255.224 Serial0/0/0

ip route 1.1.24.0 255.255.252.0 Serial0/0/0

ip route 1.1.16.0 255.255.248.0 Serial0/0/0

router rip

version 2

network 1.1.28.64

network 1.1.28.80

network 1.1.28.92

passive-interface GigabitEthernet0/1

no auto-summary

exit

end

copy run start

#### Mercenary (M):

enable configure terminal hostname M interface GigabitEthernet0/1 ip address 1.1.28.1 255.255.255.224 ip helper-address 1.1.16.2 no shutdown exit interface Serial0/0/1 ip address 1.1.28.70 255.255.255.252 no shutdown exit interface Serial0/1/0 ip address 1.1.28.82 255.255.255.252 no shutdown exit interface Serial0/1/1 ip address 1.1.28.85 255.255.255.252 no shutdown exit router rip version 2 network 1.1.28.68 network 1.1.28.80 network 1.1.28.84 passive-interface GigabitEthernet0/1 no auto-summary exit ip route 1.1.24.0 255.255.252.0 Serial0/1/1 12 ip route 1.1.0.0 255.255.240.0 Serial0/1/0 12 ip route 1.1.28.32 255.255.255.224 Serial0/1/0 12 ip route 1.1.24.0 255.255.252.0 Serial0/0/1 ip route 1.1.0.0 255.255.240.0 Serial0/0/1 ip route 1.1.28.32 255.255.255.224 Serial0/0/1 ip route 1.1.16.0 255.255.248.0 Serial0/0/1 end copy run start

#### Intelligence (I):

enable configure terminal hostname I interface GigabitEthernet0/1 ip address 1.1.24.1 255.255.252.0 ip helper-address 1.1.16.2 no shutdown exit interface Serial0/1/0 ip address 1.1.28.74 255.255.255.252 no shutdown exit interface Serial0/1/1 ip address 1.1.28.86 255.255.255.252 no shutdown exit ip route 1.1.28.0 255.255.255.224 Serial0/1/1 12 ip route 1.1.28.32 255.255.255.224 Serial0/0/0 12 ip route 1.1.0.0 255.255.240.0 Serial0/1/1 12 ip route 1.1.28.0 255.255.255.224 Serial0/1/0 ip route 1.1.28.32 255.255.255.224 Serial0/1/0 ip route 1.1.0.0 255.255.240.0 Serial0/1/0 ip route 1.1.16.0 255.255.248.0 Serial0/1/0 router rip version 2 passive-interface GigabitEthernet0/1 no auto-summary network 1.1.28.72 network 1.1.28.84 network 1.1.28.78 end copy run start

## **Undertaking (U):**

enable

configure terminal

hostname U

interface GigabitEthernet0/1

ip address 1.1.28.33 255.255.255.224

ip helper-address 1.1.16.2

no shutdown

exit

interface Serial0/0/1

ip address 1.1.28.93 255.255.255.252

no shutdown

exit

interface Serial0/1/1

ip address 1.1.28.78 255.255.255.252

no shutdown

exit

interface Serial0/0/0

ip address 1.1.28.90 255.255.255.252

no shutdown

#### exit

ip route 1.1.0.0 255.255.240.0 Serial0/0/1 12

ip route 1.1.24.0 255.255.252.0 Serial0/0/0 12

ip route 1.1.28.0 255.255.255.224 Serial0/0/1 12

ip route 1.1.0.0 255.255.240.0 Serial0/1/1

ip route 1.1.24.0 255.255.252.0 Serial0/1/1

ip route 1.1.28.0 255.255.255.224 Serial0/1/1

ip route 1.1.16.0 255.255.248.0 Serial0/1/1

router rip

version 2

passive-interface GigabitEthernet0/1

no auto-summary

network 1.1.28.76

network 1.1.28.88

network 1.1.28.92

end

copy run start

# IP address table:

Device	Interface	IP Address	Subnet Mask	Default
				Gateway
Router Headquarters (H)	S0/0/0	1.1.28.65	255.255.255.252	N/A
	S0/0/1	1.1.28.69	255.255.255.252	
	S0/1/0	1.1.28.73	255.255.255.252	
	S0/1/1	1.1.28.77	255.255.255.252	
	G0/1	1.1.16.1	255.255.248.0	
Router Lobby (L)	S0/0/0	1.1.28.66	255.255.255.252	N/A
	S0/0/1	1.1.28.94	255.255.255.252	
	S0/1/0	1.1.28.81	255.255.255.252	
	G0/1	1.1.0.1	255.255.240.0	
Router Mercenary (M)	s0/1/0	1.1.28.82	255.255.255.252	N/A
	S0/1/1	1.1.28.85	255.255.255.252	
	S0/0/1	1.1.28.70	255.255.255.252	
	G0/1	1.1.28.1	255.255.255.224	
Router Intelligence (I)	S0/0/0	1.1.28.89	255.255.255.252	N/A
	S0/1/0	1.1.28.74	255.255.255.252	
	S0/1/1	1.1.28.86	255.255.255.252	
	G0/1	1.1.24.1	255.255.252.0	
Router Undertaking (U)	S0/0/0	1.1.28.90	255.255.255.252	N/A
	S0/0/1	1.1.28.93	255.255.255.252	
	S0/1/1	1.1.28.78	255.255.255.252	
	G0/1	1.1.28.33	255.255.255.224	
Server DHCP	Fa0	1.1.16.2	255.255.248.0	1.1.16.1
Server DNS	Fa0	1.1.16.3	255.255.248.0	1.1.16.1
Server	Fa0	1.1.16.4	255.255.248.0	1.1.16.1
mail.headquarters.org				
PC Leader	Fa0	1.1.16.5	255.255.248.0	1.1.16.1
PC H1	Fa0	DHCP	255.255.248.0	1.1.16.1
Printer	Fa0	1.1.0.2	255.255.240.0	1.1.0.1
PC L1	Fa0	DHCP	255.255.240.0	1.1.0.1
PC L2	Fa0	DHCP	255.255.240.0	1.1.0.1
Server Web	Fa0	1.1.28.2	255.255.255.224	1.1.28.1
mercenary.information.org				
PC M1	Fa0	DHCP	255.255.255.224	1.1.28.1
PC M2	Fa0	DHCP	255.255.255.224	1.1.28.1
Server mail.intelligence.org	Fa0	1.1.24.2	255.255.252.0	1.1.24.1
PC i1	Fa0	DHCP	255.255.252.0	1.1.24.1
PC i2	Fa0	DHCP	255.255.252.0	1.1.24.1
Server	Fa0	1.1.28.34	255.255.255.224	1.1.28.33
assignments.undertaking.org				
PC U1	Fa0	DHCP	255.255.255.224	1.1.28.33
PC U2	Fa0	DHCP	255.255.255.224	1.1.28.33