Smart Pointers in C++

Jonas R. Glesaaen glesaaen@th.physik.uni-frankfurt.de

September 24th 2014

Literature

- [1] Boost c++ library.
 http://www.boost.org.
- [2] C++ reference.
 http://cppreference.com.
- [3] E. Gamma, R. Helm, R. Johnson, and J. Vlissides. Design Patterns: Elements of Reusable Object-Oriented Software. Pearson Education, 1994.
- [4] S. Meyers.
 More Effective C++: 35 New Ways to Improve Your Programs and Designs.
 Pearson Education, 1995.
- [5] S. Meyers.
 Effective C++: 55 Specific Ways to Improve Your Programs and Designs.
 Pearson Education, 2005.
- [6] H. Sutter. Gotw #89 solution: Smart pointers. http://herbsutter.com/2013/05/29/gotw-89-solution-smart-pointers/.

What are smart pointers?

Objects designed to act like pointers, but provide extended functionality. Example of the proxy pattern [3].

```
MyClass * ptr = new MyClass();
ptr->Function();
delete ptr;
```

Smart pointers can manipulate three aspects of pointer behaviour:

- Construction
- Dereferencing
- Destruction

Why use smart pointers?

Primarily to avoid memory leaks, which can come from a myriad of different sources;

```
Memory leak sources

MyClass * ptr = new MyClass();
//... (1)
ptr->Function(); //(2)
//...
delete ptr; //(3)
```

- Might have multiple return paths
- 2 Might throw an exception
- 3 One might simply forget to free the resource

Why use smart pointers?

Primarily to avoid memory leaks, which can come from a myriad of different sources;

```
Memory leak sources

MyClass * ptr = new MyClass();
//... (1)
ptr->Function(); //(2)
//...
delete ptr; //(3)
```

- 1 Might have multiple return paths
- 2 Might throw an exception
- 3 One might simply forget to free the resource

Solution: Wrap the resource in a class which frees it on destruction.

Types of smart pointers

Smart pointers where one object singularly owns a resource

Smart pointers where the resource is shared by multiple objects.

Shared smart pointers utilising the *copy-on-write* technique.



 \sqsubseteq Types of smart pointers

Types of smart pointers

Smart pointers where one object singularly owns a resource

Smart pointers where the resource is shared by multiple objects

Shared unsert pointers utilizing the cape do write technique.

The copy-on-write technique is an optimisation technique where if two objects are initialised to have the same value to begin with, they both "point to" the same resource (shared smart resource), but the moment one of them edits its own version, a copy is made before it is written to, and the two objects do not point to the same resource any more. std::string followed this principle up to C++03, but after the introduction of move semantics, they went away from that.

Smart pointer implementations

All following smart pointers do "garbage collection", but they differ in how they are assigned:

std	boost	Qt
std::unique_ptr		
std::shared_ptr	boost::shared_ptr	QSharedPointer
std::weak_ptr	boost::weak_ptr	QWeakPointer
std::auto_ptr	boost::scoped_ptr	QScopedPointer

Smart pointer implementations

	mart point re assigned	ers do "garbage co :	llection", but th	vey diffe
enment				
_	and	hoost	Ot.	
		boost	Qt	
	std salque_ptr	boost boostrishared.ytr	Qt QtharedPointer	
4541	unique_ptr			_

Qt handles memory through the parent-child relationship of QObjects and the smart pointers are not as frequently used. unique_ptr forbids copy assignment and copy construction, while shared_ptr keeps a reference count of how many objects point to a specific resource. A weak pointer has a non-owning reference to a shared_ptr, but one must "lock" the object before one can use the resource. First and foremost, auto_ptr's are deprecated and shouldn't be used. They handle copy assignment/construction by handing over the pointer, setting it's own pointer to null. It does therefore not have a const assignment operator / copy constructor.

Example: std::unique_ptr

```
MyClass * CreateObject()
  std::unique_ptr < MyClass > new_object(new MyClass());
 //...
                                Release ownership of resource
 return new_object.release(); ← and sets own pointer to
};
                                nullptr
int main()
  std::unique_ptr < MyClass > p1( CreateObject() );
  std::unique_ptr <MyClass > p2 = CreateObject(); - Compilation error!
 //...
 std::unique_ptr <MyClass > q1 = p1; ← Compilation error!
  std::unique_ptr < MyClass > q2 = std::move(p1); ← OK!
 //...
```

```
Example: std::unique_ptr
```

```
Framework and consequence of the second of t
```

The std::unique_ptr<T> ptr = new T() can't compile as we would have to write a converter from a raw pointer to std::unique_ptr for it to work, something which could in general have unexpected consequences. As usual, do not provide a cast operator (or an implicit cast) unless there is a good reason for it. Smart pointers should never allow to be implicitly converted to or from raw pointers.

Example: std::shared_ptr and std::weak_ptr

```
std::shared_ptr < MyClass > p1 (new MyClass());
std::shared_ptr < MyClass > p2 = p1;
  std::shared_ptr < MyClass > p3 = p2;
  std::weak_ptr < MyClass > wp = p2;
  if(auto p = wp.lock()) {
  // ...
// ...
```


Example: std::shared_ptr and std::weak_ptr

```
std::shared_ptr<MyClass> p1(new MyClass()); ← use count: 1
if(auto p = wp.lock()) {
// ... ←
                 use count: 4
                 — use count: 2
```

Example: std::shared_ptr and std::weak_ptr


```
std::weak_ptr<MyClass> wp;
  std::shared_ptr < MyClass > sp =
        std::make_shared < MyClass > ();
  wp = sp;
  if(auto wsp = wp.lock()) {
  // ...
if(wp.expired()) {
 // Managed resource has been deleted
```

std::unique_ptr symbolises owning a resource.




The resource can be shared through references or raw pointers

std::unique_ptr symbolises owning a resource.




The resource can be shared through references or raw pointers

std::shared_ptr on the other hand symbolises sharing a
resource with other objects.




The resource can still be shared through pointers and references, but also using the std::shared_ptr copy constructor and copy assignment operator.

std::shared_ptr on the other hand symbolises sharing a
resource with other objects.



The resource can still be shared through pointers and references, but also using the std::shared_ptr copy constructor and copy assignment operator.

std::shared_ptr on the other hand symbolises sharing a
resource with other objects.



The resource can still be shared through pointers and references, but also using the std::shared_ptr copy constructor and copy assignment operator.

Example: Abstract Factory 1

```
class ShapeFactory
  Shape * CreateShape() = 0;
};
class CircleFactory : public ShapeFactory
  Shape * CreateShape()
    std::unique_ptr<Shape> shape_ptr(new Circle());
                     The pointer will be deleted if
                      something happens in between
    return shape_ptr.release();
 };
};
```

Hope that whoever takes ownership over the newly created Shape object manages it properly.

Example: Abstract Factory 1



Factory methods can also obviously return pointers with shared ownership. Unless the return type tells you whether it is shared or unique ownership, whoever calls the function has no way of knowing. Factory methods should return unique pointers unless the resource is shared by the factory itself.

Example: Abstract Factory 2

```
class ShapeFactory
 std::unique_ptr <Shape > CreateShape() = 0;
};
class CircleFactory : public ShapeFactory
 std::unique_ptr <Shape > CreateShape()
   std::unique ptr <Shape > shape ptr(new Circle());
   // ...
   };
};
```

The new owner of the Shape object is forced to manage its memory properly.

Example: Abstract Factory 2

Example: Abstract Factory 2

that Reports your control of the Cont

Apparently whether the return is turned into an rvalue is compiler dependent, but it should.

Problems with explicit new's: #1

constructor

Consider creating a std::shared_ptr with a new statement

```
Naïve construction

std::shared_ptr<MyClass> ptr(new MyClass());

pass pointer
to newly constructed
MyClass object

Call MyClass

Call std::shared_ptr
```

constructor

The constructors are called separately and the compiler cannot optimise memory location.

Problems with explicit new's: #2

```
void ProcessObject(std::shared_ptr<MyClass> obj,
                      int process_id);
ProcessObject(std::shared_ptr < MyClass > (new MyClass()),
                GetProcessID());
                      MyClass
                                                GetProcessID()
                    constructor
        std::shared_ptr
                                                   MyClass
                            GetProcessID()
                                                  constructor
           constructor
                                     std::shared_ptr
        GetProcessID()
                                        constructor
```

Problems with explicit new's: #2

```
void ProcessObject(std::shared_ptr<MyClass> obj,
                      int process_id);
ProcessObject(std::shared_ptr < MyClass > (new MyClass()),
                GetProcessID());
                      MyClass
                                                GetProcessID()
                    constructor
        std::shared_ptr
                                                   MyClass
                            GetProcessID()
                                                  constructor
           constructor
                                     std::shared_ptr
        GetProcessID()
                                        constructor
```

Problems with explicit new's: #2



We have no control over the order in which the compiler carries out the three processes (other than that calling MyClass's creator has to happen before std::shared_ptr's).

Create using std::make_unique and std::make_shared

Both these problems can be remedied by using std::make_shared and std::make_unique (C++14).

Constructor calls cannot be intertwined with the GetProcessID() anymore.

Create using std::make_unique and std::make shared



On top of fixing these types of issues, using make_shared and make_unique doesn't reveal the underlying pointer, and therefore one cannot misuse the raw pointer without actively calling .get() or .release(), in which case it is easy to spot ones mistakes.

Create using std::make_unique and std::make_shared

Guideline

Don't use explicit new, delete, and owning * pointers, except in rare cases encapsulated inside the implementation of a low-level data structure.

Herb Sutter [6] -

Match constructors with destructors

Smart pointers have a control block which also keeps track of an allocator and a deleter

```
std::shared_ptr constructor

template <class Type, class Deleter, class Alloc>
std::shared_ptr(Type * p, Deleter d, Alloc a);
```

Very important that the deleter doesn't throw.

Passing smart pointers

There are many options for passing smart pointers to functions (and classes).

```
Passing smart pointers

void foo(MyClass *);
void foo(MyClass &);
void foo(std::unique_ptr<MyClass>);
void foo(std::unique_ptr<MyClass> &);
void foo(std::shared_ptr<MyClass>);
void foo(std::shared_ptr<MyClass> &);
```

All of these has a distinct meaning, use them to express yourself.

Passing smart pointers

Then are many options for passing smart pointers to functions (and cleans).

Private passing and property of the passing passing and passi

Passing smart pointers


Pointer vs reference boils down to the usual "Is no-value a valid option?", and in classes pointers can be rebound, references not. Passing smart pointers by reference limits the function to only accept one type of smart pointers, while passing shared pointers by value has a cost (as the object needs to be constructed and destructed).

Using smart pointers and polymorphic classes as template arguments works as expected because one of the smart pointer constructors read:

```
template < class T, class U>
std::shared_ptr < T > (const std::shared_ptr < U > &)
```

This costructor can be used to convert between std::shared_ptr's if T* is implicitly convertible to U*.

Assume we have a class hierarchy:



Where Derived overloads the print() function but not the const variant.

```
std::shared_ptr<Derived> d_ptr =
    std::make_shared<Derived>();

std::shared_ptr<Base> b_ptr = d_ptr;
std::shared_ptr<Const Base> b_const_ptr = d_ptr;

std::shared_ptr<Derived> d_err_ptr = b_ptr; 	— Compilation error
std::shared_ptr<Base> b_err_ptr = b_const_ptr; 	— Compilation error
b_ptr->print(); 	— Calls Derived::print()
b_const_ptr->print(); 	— Calls Base::print()const

//use count: 3
```

```
std::shared ptr < Derived > d ptr =
  std::make shared < Derived > ():
std::shared ptr <Base> b ptr = d ptr;
std::shared_ptr<const Base> b_const_ptr = d_ptr;
std::shared ptr < Derived > d new ptr =
  std::dynamic_pointer_cast < Derived > (b_ptr); \leftarrow OK!
std::shared_ptr <Base > b_new_ptr =
  std::const_pointer_cast <Base > (b_const_ptr); ← OK!
d_new_ptr -> sum(); 		 Calls Derived::sum()
b new ptr→print(); ← Calls Derived::print()
//use count: 5
```

Smart pointers and polymorphic classes

Smart pointers and polymorphic classes

stitutanes jurifications 2 july *

stitutanes 2 july *

stitutanes

This is a more error safe way of working with pointer casts as one never has to access the underlying raw pointer and explicitly own raw pointers as one would have to do with .get() together with standard C++ casts. It would also not be possible to re-own the result of the standard cast as one has extraced it out of the reference counting object. This is inteded to use with std::shared_ptr's, and doesn't work with std::unique_ptr.

Smart pointers and the STL

- Smart pointers can be stored in the STL containers.
- However, not all algorithms work with the resulting containers.
 - E.g. std::unique_ptr is MoveConstructible and MoveAssignable
 - But not CopyConstructable or CopyAssignable

Thus if an algorithm requires CopyConstructability and a std::unique_ptr is given, it should fail to compile.

std::auto_ptr on the other hand is a bit more unreliable.



Smart pointers and the STL

Smart pointers can be stored in the STL containers.
However, not all algorithms work with the resulting containers.

E.g. ntd::unique_ptr in MoveConstructible and

Smart pointers and the STL

"But not Cop/Constructable or Cop/Assignable

Thus if an algorithm requires Cop/Constructability and a add::unique_ptr is given, it should fail to compile.

add::auto_ptr on the other hand is a bit more unreliable.

std::auto_ptr is technically not CopyConstructable and CopyAssignable as the copied object is changed, but this won't always result in a compilation error (or even a compilation warning) as it should. It depends on your compiler, but is not a risk one should take regardless. Before the introduction of move semantics for example, an iterator needed to be CopyConstructable and assignable for it to be used with the sort-algorithm. auto_ptr's would therefore not be usable in this case, but not all compilers would warn you of that.

The boost pointer container library

Library inteded to provide a STL-like library for single ownership pointers.

Advantages

- Simplifies the container-of-pointer syntax.
- Notational convenience
 - Dereferencing an iterator returns a dereferenced pointer
- Introduces "Clonability" to do deep copies.
- Faster and has a small memory overhead.

Disadvantages -

- Not very compatible with the algorithm library
- Not as flexible as a container of smart pointers

Summary

- Use smart pointers to manage dynamic resources so that they are freed when they aren't used anymore.
 - Use std::unique_ptr to signal singular ownership
 - Use std::shared_ptr to signal shared ownership
 - Use std::weak_ptr to signal uncommitted shared ownership
- Avoid using explicit new and delete statements, and explicit ownership of raw pointers.