Python Library Reference

Release 2.4.2

Guido van Rossum Fred L. Drake, Jr., editor

28 September 2005

Python Software Foundation

Email: docs@python.org

Copyright © 2001-2004 Python Software Foundation. All rights reserved.

Copyright © 2000 BeOpen.com. All rights reserved.

Copyright © 1995-2000 Corporation for National Research Initiatives. All rights reserved.

Copyright © 1991-1995 Stichting Mathematisch Centrum. All rights reserved.

See the end of this document for complete license and permissions information.

Abstract

Python is an extensible, interpreted, object-oriented programming language. It supports a wide range of applications, from simple text processing scripts to interactive Web browsers.

While the *Python Reference Manual* describes the exact syntax and semantics of the language, it does not describe the standard library that is distributed with the language, and which greatly enhances its immediate usability. This library contains built-in modules (written in C) that provide access to system functionality such as file I/O that would otherwise be inaccessible to Python programmers, as well as modules written in Python that provide standardized solutions for many problems that occur in everyday programming. Some of these modules are explicitly designed to encourage and enhance the portability of Python programs.

This library reference manual documents Python's standard library, as well as many optional library modules (which may or may not be available, depending on whether the underlying platform supports them and on the configuration choices made at compile time). It also documents the standard types of the language and its built-in functions and exceptions, many of which are not or incompletely documented in the Reference Manual.

This manual assumes basic knowledge about the Python language. For an informal introduction to Python, see the *Python Tutorial*; the *Python Reference Manual* remains the highest authority on syntactic and semantic questions. Finally, the manual entitled *Extending and Embedding the Python Interpreter* describes how to add new extensions to Python and how to embed it in other applications.

CONTENTS

1	Intro	oduction 1	
2	Built	ilt-In Objects	
	2.1	Built-in Functions	3
	2.2	Non-essential Built-in Functions	14
	2.3	Built-in Types	15
	2.4	Built-in Exceptions	33
	2.5	Built-in Constants	38
3	Pytho	on Runtime Services	41
	3.1	sys — System-specific parameters and functions	41
	3.2	gc — Garbage Collector interface	47
	3.3	weakref — Weak references	49
	3.4	fpect1 — Floating point exception control	54
	3.5	atexit — Exit handlers	55
	3.6	types — Names for built-in types	56
	3.7	UserDict — Class wrapper for dictionary objects	58
	3.8	UserList — Class wrapper for list objects	59
	3.9	UserString — Class wrapper for string objects	59
	3.10	operator — Standard operators as functions	60
	3.11	inspect — Inspect live objects	64
	3.12	traceback — Print or retrieve a stack traceback	69
	3.13	linecache — Random access to text lines	71
	3.14	pickle — Python object serialization	72
	3.15	cPickle — A faster pickle	81
	3.16	copy_reg — Register pickle support functions	81
	3.17	shelve — Python object persistence	82
	3.18	copy — Shallow and deep copy operations	84
	3.19	marshal — Internal Python object serialization	85
	3.20	warnings — Warning control	86
	3.21	imp — Access the import internals	89
	3.22	zipimport — Import modules from Zip archives	91
	3.23	pkgutil — Package extension utility	93
	3.24	modulefinder — Find modules used by a script	93
	3.25	code — Interpreter base classes	94
	3.26	codeop — Compile Python code	95
	3.27	pprint — Data pretty printer	97
	3.28	repr — Alternate repr() implementation	99
	3.29	new — Creation of runtime internal objects	100
	3.30	site — Site-specific configuration hook	
	3.31	user — User-specific configuration hook	102
	3.32	builtin — Built-in objects	102
	3.33	main — Top-level script environment	103

	3.34	future — Future statement definitions	103
4	Strin	g Services	105
	4.1	string — Common string operations	105
	4.2	re — Regular expression operations	110
	4.3	struct — Interpret strings as packed binary data	120
	4.4	difflib — Helpers for computing deltas	122
	4.5	fpformat — Floating point conversions	130
	4.6	StringIO — Read and write strings as files	131
	4.7	cStringIO — Faster version of StringIO	131
	4.8	textwrap — Text wrapping and filling	131
	4.9	codecs — Codec registry and base classes	133
	4.10	unicodedata — Unicode Database	142
	4.11	stringprep — Internet String Preparation	143
5	Misc	ellaneous Services	145
	5.1	pydoc — Documentation generator and online help system	145
	5.2	doctest — Test interactive Python examples	
	5.3	unittest — Unit testing framework	170
	5.4	test — Regression tests package for Python	
	5.5	test.test_support — Utility functions for tests	
	5.6	decimal — Decimal floating point arithmetic	
	5.7	math — Mathematical functions	
	5.8	cmath — Mathematical functions for complex numbers	201
	5.9	random — Generate pseudo-random numbers	
	5.10	whrandom — Pseudo-random number generator	205
	5.11	bisect — Array bisection algorithm	206
	5.12	collections — High-performance container datatypes	206
	5.13	heapq — Heap queue algorithm	210
	5.14	array — Efficient arrays of numeric values	212
	5.15	sets — Unordered collections of unique elements	214
	5.16	itertools — Functions creating iterators for efficient looping	217
	5.17	ConfigParser — Configuration file parser	226
	5.18	fileinput — Iterate over lines from multiple input streams	
	5.19	calendar — General calendar-related functions	230
	5.20	cmd — Support for line-oriented comm00(.)-500Interprebers	131

	6.21	optparse — More powerful command line option parser
	6.22	tempfile — Generate temporary files and directories
	6.23	errno — Standard errno system symbols
	6.24	glob — UNIX style pathname pattern expansion
	6.25	fnmatch — UNIX filename pattern matching
	6.26	shutil — High-level file operations
	6.27	locale — Internationalization services
	6.28	gettext — Multilingual internationalization services
	6.29	logging — Logging facility for Python
	6.30	platform — Access to underlying platform's identifying data
7	Ontic	onal Operating System Services 385
′	7.1	signal — Set handlers for asynchronous events
	7.2	socket — Low-level networking interface
	7.3	select — Waiting for I/O completion
	7.4	thread — Multiple threads of control
	7.5	threading — Higher-level threading interface
	7.6	dummy_thread — Drop-in replacement for the thread module
	7.7	dummy_threading — Drop-in replacement for the threading module
	7.8	Queue — A synchronized queue class
	7.9	mmap — Memory-mapped file support
	7.10	anydbm — Generic access to DBM-style databases
	7.11	dbhash — DBM-style interface to the BSD database library
	7.12	whichdb — Guess which DBM module created a database
	7.13	bsddb — Interface to Berkeley DB library
	7.14	dumbdbm — Portable DBM implementation
	7.15	zlib — Compression compatible with gzip
	7.16	gzip — Support for gzip files
	7.17	bz2 — Compression compatible with bzip2
	7.18	zipfile — Work with ZIP archives
	7.19	tarfile — Read and write tar archive files
	7.20	readline — GNU readline interface
	7.21	rlcompleter — Completion function for GNU readline
8		Specific Services 43
	8.1	posix — The most common POSIX system calls
	8.2	pwd — The password database
	8.3	grp — The group database
	8.4	crypt — Function to check UNIX passwords
	8.5	d1 — Call C functions in shared objects
	8.6	dbm — Simple "database" interface
	8.7	gdbm — GNU's reinterpretation of dbm
	8.8	termios — POSIX style tty control
	8.9	tty — Terminal control functions
	8.10	pty — Pseudo-terminal utilities
	8.11	fcntl — The fcntl() and ioctl() system calls
	8.12	pipes — Interface to shell pipelines
	8.13	posixfile — File-like objects with locking support
	8.14	resource — Resource usage information
	8.15	nis — Interface to Sun's NIS (Yellow Pages)
	8.16	syslog — UNIX syslog library routines
	8.17	commands — Utilities for running commands
9	The F	Python Debugger 449
	9.1	Debugger Commands
	9.2	How It Works
10		Python Profiler 455
	10.1	Introduction to the profiler

	10.2	How Is This Profiler Different From The Old Profiler?	-55
	10.3	Instant Users Manual	
	10.4	What Is Deterministic Profiling?	-58
	10.5	Reference Manual	58
	10.6	Limitations	61
	10.7	Calibration	61
		Extensions — Deriving Better Profilers	
		hotshot — High performance logging profiler	
		timeit — Measure execution time of small code snippets	
	10.10	camero inclusive execution time of small code simplets	٠.
11	Interi	net Protocols and Support 4	69
		webbrowser — Convenient Web-browser controller	69
		cgi — Common Gateway Interface support	
		cgitb — Traceback manager for CGI scripts	
		urllib — Open arbitrary resources by URL	
		urllib2 — extensible library for opening URLs	
		httplib — HTTP protocol client	
		ftplib—FTP protocol client	
		gopherlib — Gopher protocol client	
		poplib — POP3 protocol client	
		imaplib — IMAP4 protocol client	
		nntplib — NNTP protocol client	
		smtplib — SMTP protocol client	
		smtpd — SMTP Server	
	11.14	telnetlib — Telnet client 5	14
	11.15	urlparse — Parse URLs into components	16
	11.16	SocketServer — A framework for network servers	18
	11.17	BaseHTTPServer — Basic HTTP server	21
		SimpleHTTPServer — Simple HTTP request handler 5	
		CGIHTTPServer — CGI-capable HTTP request handler	
		cookielib — Cookie handling for HTTP clients	
		Cookie — HTTP state management	
		xmlrpclib — XML-RPC client access	
		SimpleXMLRPCServer — Basic XML-RPC server	
		DocXMLRPCServer — Self-documenting XML-RPC server	
		asyncore — Asynchronous socket handler	
		asynchat — Asynchronous socket command/response handler	
	11.20	asynchat — Asynchronous socket command/response nandier	
12	Inter		49
	12.1		49
	12.2	email — An email and MIME handling package	
	12.3	mailcap — Mailcap file handling	
	12.4	mailbox — Read various mailbox formats	
		mhlib — Access to MH mailboxes	
		mimetools — Tools for parsing MIME messages	
	12.7	mimetypes — Map filenames to MIME types	
		MimeWriter — Generic MIME file writer	
		mimify — MIME processing of mail messages	
		multifile — Support for files containing distinct parts	
		rfc822 — Parse RFC 2822 mail headers	
		base64 — RFC 3548: Base16, Base32, Base64 Data Encodings	
		binascii — Convert between binary and ASCII	
		binhex — Encode and decode binhex4 files	
		quopri — Encode and decode MIME quoted-printable data	
		uu — Encode and decode uuencode files	
		xdrlib — Encode and decode XDR data 6	
	12.18	netrc — netrc file processing	02
	12.19	robotparser — Parser for robots.txt	603

	12.20 CS	v — CSV File Reading and Writing	04
13	Structure	ed Markup Processing Tools 6	09
	13.1 HT	MLParser — Simple HTML and XHTML parser	09
	13.2 sg	mllib — Simple SGML parser	11
	13.3 ht	mllib — A parser for HTML documents	13
	13.4 ht	mlentitydefs — Definitions of HTML general entities 6	15
		1.parsers.expat — Fast XML parsing using Expat	
	13.6 xm	1.dom — The Document Object Model API	23
	13.7 xm	1.dom.minidom — Lightweight DOM implementation	33
	13.8 xm	1.dom.pulldom — Support for building partial DOM trees 6	37
	13.9 xm	1.sax — Support for SAX2 parsers	38
	13.10 xm	1.sax.handler — Base classes for SAX handlers	39
	13.11 xm	l.sax.saxutils — SAX Utilities 6	43
	13.12 xm	1.sax.xmlreader — Interface for XML parsers	44
		llib — A parser for XML documents	
14	Multime	dia Services 6	51
14		dioop — Manipulate raw audio data	
		ageop — Manipulate raw image data	
		fc — Read and write AIFF and AIFC files	
		nau — Read and write Sun AU files	
		ve — Read and write WAV files	
		unk — Read IFF chunked data	
		lorsys — Conversions between color systems	
		bimg — Read and write "SGI RGB" files	
		ghdr — Determine the type of an image	
		dhdr — Determine type of sound file	
		saudiodev — Access to OSS-compatible audio devices	
		1	
15		· · · · · · · · · · · · · · · · · · ·	69
15		raphic Services 6 ac — Keyed-Hashing for Message Authentication 6	
15	15.1 hm 15.2 md	ac — Keyed-Hashing for Message Authentication	69 69
15	15.1 hm 15.2 md	ac — Keyed-Hashing for Message Authentication	69 69
	15.1 hm 15.2 md 15.3 sh	ac — Keyed-Hashing for Message Authentication	69 69
	15.1 hm 15.2 md 15.3 sh Graphica	ac — Keyed-Hashing for Message Authentication	669 669 670
	15.1 hm 15.2 md 15.3 sh Graphica 16.1 Tk	ac	669 670 6 73
	15.1 hm 15.2 md 15.3 sh Graphica 16.1 Tk 16.2 Ti	ac — Keyed-Hashing for Message Authentication 6 5 — MD5 message digest algorithm 6 a — SHA-1 message digest algorithm 6 al User Interfaces with Tk 6 inter — Python interface to Tcl/Tk 6 x — Extension widgets for Tk 6	669 670 6 73 673
	15.1 hm 15.2 md 15.3 sh Graphica 16.1 Tk 16.2 Ti 16.3 Sc	ac — Keyed-Hashing for Message Authentication 6 5 — MD5 message digest algorithm 6 a — SHA-1 message digest algorithm 6 al User Interfaces with Tk 6 inter — Python interface to Tcl/Tk 6 x — Extension widgets for Tk 6 rolledText — Scrolled Text Widget 6	669 670 6 73 673 684 689
	15.1 hm 15.2 md 15.3 sh Graphics 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu	ac — Keyed-Hashing for Message Authentication 6 5 — MD5 message digest algorithm 6 a — SHA-1 message digest algorithm 6 al User Interfaces with Tk 6 inter — Python interface to Tcl/Tk 6 x — Extension widgets for Tk 6 rolledText — Scrolled Text Widget 6 rtle — Turtle graphics for Tk 6	669 669 670 673 684 689
	15.1 hm 15.2 md 15.3 sh Graphica 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu 16.5 Idl	ac — Keyed-Hashing for Message Authentication 6 5 — MD5 message digest algorithm 6 a — SHA-1 message digest algorithm 6 al User Interfaces with Tk 6 inter — Python interface to Tcl/Tk 6 x — Extension widgets for Tk 6 rolledText — Scrolled Text Widget 6	569 570 573 573 584 589 590
16	15.1 hm 15.2 md 15.3 sh Graphics 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu 16.5 Idl 16.6 Otl	ac — Keyed-Hashing for Message Authentication 6 5 — MD5 message digest algorithm 6 a — SHA-1 message digest algorithm 6 al User Interfaces with Tk 6 inter — Python interface to Tcl/Tk 6 x — Extension widgets for Tk 6 rolledText — Scrolled Text Widget 6 rtle — Turtle graphics for Tk 6 e 6 her Graphical User Interface Packages 6	569 569 570 573 573 584 589 589 590
16	15.1 hm 15.2 md 15.3 sh Graphica 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu 16.5 Idl 16.6 Otl	ac — Keyed-Hashing for Message Authentication 6 5 — MD5 message digest algorithm 6 a — SHA-1 message digest algorithm 6 al User Interfaces with Tk 6 inter — Python interface to Tcl/Tk 6 x — Extension widgets for Tk 6 rolledText — Scrolled Text Widget 6 rtle — Turtle graphics for Tk 6 e 6 her Graphical User Interface Packages 6 od Execution 6	569 569 570 573 573 584 589 590 594
16	15.1 hm 15.2 md 15.3 sh Graphics 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu 16.5 Idl 16.6 Oth Restricte 17.1 re	ac — Keyed-Hashing for Message Authentication 6 5 — MD5 message digest algorithm 6 a — SHA-1 message digest algorithm 6 al User Interfaces with Tk 6 inter — Python interface to Tcl/Tk 6 x — Extension widgets for Tk 6 rolledText — Scrolled Text Widget 6 rtle — Turtle graphics for Tk 6 e 6 her Graphical User Interface Packages 6 dd Execution 6 xec — Restricted execution framework 6	669 670 673 673 684 689 694 695
16	15.1 hm 15.2 md 15.3 sh Graphics 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu 16.5 Idl 16.6 Oth Restricte 17.1 re	ac — Keyed-Hashing for Message Authentication 6 5 — MD5 message digest algorithm 6 a — SHA-1 message digest algorithm 6 al User Interfaces with Tk 6 inter — Python interface to Tcl/Tk 6 x — Extension widgets for Tk 6 rolledText — Scrolled Text Widget 6 rtle — Turtle graphics for Tk 6 e 6 her Graphical User Interface Packages 6 od Execution 6	669 670 673 673 684 689 694 695
16 17	15.1 hm 15.2 md 15.3 sh Graphica 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu 16.5 Idl 16.6 Oth Restricte 17.1 re 17.2 Ba Python I	ac — Keyed-Hashing for Message Authentication 65 — MD5 message digest algorithm 66 a — SHA-1 message digest algorithm 66 al User Interfaces with Tk 66 inter — Python interface to Tcl/Tk 66 x — Extension widgets for Tk 67 x — Extension widgets for Tk 67 x — Extension widgets for Tk 68 x — Extension widgets for Tk 68 x — Extension widgets for Tk 69 x — Extension widgets for Tk 69 x — Extension widgets for Tk 69 x — Extension widgets for Tk 60 x	669 669 670 673 684 689 689 694 695 698
16 17	15.1 hm 15.2 md 15.3 sh Graphics 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu 16.5 Idl 16.6 Otl Restricte 17.1 re 17.2 Ba Python I 18.1 pa	ac — Keyed-Hashing for Message Authentication 6 5 — MD5 message digest algorithm 6 a — SHA-1 message digest algorithm 6 al User Interfaces with Tk 6 inter — Python interface to Tcl/Tk 6 x — Extension widgets for Tk 6 rolledText — Scrolled Text Widget 6 rtle — Turtle graphics for Tk 6 e 6 her Graphical User Interface Packages 6 dd Execution 6 xec — Restricted execution framework 6 stion — Restricting access to objects 6 Language Services 7 rser — Access Python parse trees 7	669 670 673 673 684 689 690 694 695 698 701
16 17	15.1 hm 15.2 md 15.3 sh Graphics 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu 16.5 Idl 16.6 Otl Restricte 17.1 re 17.2 Ba Python I 18.1 pa 18.2 sy	ac — Keyed-Hashing for Message Authentication 65 — MD5 message digest algorithm 66 a — SHA-1 message digest algorithm 66 al User Interfaces with Tk 66 inter — Python interface to Tcl/Tk 66 inter — Python widgets for Tk 66 rolledText — Scrolled Text Widget 66 rtle — Turtle graphics for Tk 66 mer Graphical User Interface Packages 66 mer Graphical User Interface Packages 66 mer Graphical User Interface Packages 67 meser — Restricted execution framework 67 stion — Restricting access to objects 78 mbol — Constants used with Python parse trees 79 mbol — Constants used with Python parse trees 79 mbol — Constants used with Python parse trees 79 mbol — Constants used with Python parse trees 79 mbol — Constants used with Python parse trees 79 mbol — Constants used with Python parse trees 79 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Py	669 670 673 673 684 689 690 694 695 698 701
16 17	15.1 hm 15.2 md 15.3 sh Graphica 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu 16.5 Idl 16.6 Otl Restricte 17.1 re 17.2 Ba Python I 18.1 pa 18.2 sy 18.3 to	ac — Keyed-Hashing for Message Authentication 65 — MD5 message digest algorithm 66 a — SHA-1 message digest algorithm 66 al User Interfaces with Tk 66 inter — Python interface to Tcl/Tk 66 inter — Python widgets for Tk 66 rolledText — Scrolled Text Widget 66 rtle — Turtle graphics for Tk 66 mer Graphical User Interface Packages 66 mer Graphical User Interface Packages 66 mer Graphical User Interface Packages 67 meser — Restricted execution framework 67 stion — Restricting access to objects 67 meser — Access Python parse trees 78 mbol — Constants used with Python parse trees 79 ken — Constants used with Python parse trees 79 mbol — Constants used with Python parse trees 79 mbol — Constants used with Python parse trees 79 mbol — Constants used with Python parse trees 79 mbol — Constants used with Python parse trees 79 mbol — Constants used with Python parse trees 79 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 70 mbol — Constants used with Python parse trees 71 meser — Access Python Parse trees 71 meser — Access Python Parse trees 71 meser — Access Python Parse trees 72 meser — Access Python Parse trees 73 meser — Access Python Parse trees 74 meser — Access Python Parse trees 75 meser — Access Python Pa	669 670 673 673 684 689 689 690 695 698 701 710 710
16 17	15.1 hm 15.2 md 15.3 sh Graphica 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu 16.5 Idl 16.6 Otl Restricte 17.1 re 17.2 Ba Python I 18.1 pa 18.2 sy 18.3 to 18.4 ke	ac — Keyed-Hashing for Message Authentication 65 — MD5 message digest algorithm 66 a — SHA-1 message digest algorithm 66 al User Interfaces with Tk 66 inter — Python interface to Tcl/Tk 66 inter — Python interface to Tcl/Tk 66 inter — Scrolled Text Widget 66 retle — Turtle graphics for Tk 66 rolledText — Scrolled Text Widget 66 retle — Turtle graphics for Tk 66 mer Graphical User Interface Packages 66 de Execution framework 66 stion — Restricting access to objects 66 reser — Access Python parse trees 77 mbol — Constants used with Python parse trees 77 yword — Testing for Python keywords 77	569 570 573 573 584 589 590 595 595 598 701 710 711
16 17	15.1 hm 15.2 md 15.3 sh Graphica 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu 16.5 Idl 16.6 Otl Restricte 17.1 re 17.2 Ba Python I 18.1 pa 18.2 sy 18.3 to 18.4 ke 18.5 to	ac — Keyed-Hashing for Message Authentication 5 — MD5 message digest algorithm 6 a — SHA-1 message digest algorithm 6 inter — Python interface to Tcl/Tk 7 — Extension widgets for Tk 7 — Extension widgets for Tk 8 — Turtle graphics for Tk 9 — 6 — 6 — 6 — 6 — 6 — 6 — 6 — 6 — 6 —	569 570 573 584 589 595 598 701 710 711
16 17	15.1 hm 15.2 md 15.3 sh Graphica 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu 16.5 Idl 16.6 Otl Restricte 17.1 re 17.2 Ba Python I 18.1 pa 18.2 sy 18.3 to 18.4 ke 18.5 to 18.6 ta	ac — Keyed-Hashing for Message Authentication 5 — MD5 message digest algorithm 6 a — SHA-1 message digest algorithm 6 al User Interfaces with Tk 6 inter — Python interface to Tcl/Tk 7 — Extension widgets for Tk 7 colledText — Scrolled Text Widget 7 crle — Turtle graphics for Tk 8 e 9 e 9 e 9 e 9 e 9 e 9 e 9 e 9 e 9 e 9	669 669 670 673 673 684 689 694 695 695 695 701 710 711 711 712
16 17	15.1 hm 15.2 md 15.3 sh Graphica 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu 16.5 Idl 16.6 Otl Restricte 17.1 re 17.2 Ba Python I 18.1 pa 18.2 sy 18.3 to 18.4 ke 18.5 to 18.6 ta 18.7 py	ac — Keyed-Hashing for Message Authentication 5 — MD5 message digest algorithm 6 a — SHA-1 message digest algorithm 6 inter — Python interface to Tcl/Tk 7 — Extension widgets for Tk 7 — Extension widgets for Tk 7 — Turtle graphics for Tk 8 — Turtle graphics for Tk 9 — 6 — 6 — 6 — 6 — 6 — 6 — 6 — 6 — 6 —	669 669 670 673 684 689 690 694 695 695 701 710 711 712 712
16 17	15.1 hm 15.2 md 15.3 sh Graphica 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu 16.5 Idl 16.6 Otl Restricte 17.1 re 17.2 Ba Python I 18.1 pa 18.2 sy 18.3 to 18.4 ke 18.5 to 18.6 ta 18.7 py 18.8 py	ac — Keyed-Hashing for Message Authentication 5 — MD5 message digest algorithm 6 a — SHA-1 message digest algorithm 6 inter — Python interface to Tcl/Tk 6 inter — Python interface to Tcl/Tk 7 — Extension widgets for Tk 7 — Extension widgets for Tk 8 — Extension widgets for Tk 9 — Turtle graphics for Tk 9 — 6 — 6 — 6 — 6 — 6 — 6 — 6 — 6 — 6 —	569 570 573 573 573 573 573 573 584 589 595 595 598 701 711 712 712 712 713
16 17	15.1 hm 15.2 md 15.3 sh Graphica 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu 16.5 Idl 16.6 Otl Restricte 17.1 re 17.2 Ba Python I 18.1 pa 18.2 sy 18.3 to 18.4 ke 18.5 to 18.6 ta 18.7 py 18.8 py 18.9 co	ac — Keyed-Hashing for Message Authentication 5 — MD5 message digest algorithm 6 a — SHA-1 message digest algorithm 6 inter — Python interfaces to Tcl/Tk 7 Extension widgets for Tk 7 ColledText — Scrolled Text Widget 8 crule — Turtle graphics for Tk 8 crolledText — Scrolled Text Widget 9 crolled Text Widget	569 570 573 573 573 584 589 595 594 595 598 701 710 711 712 712 713 714
16 17	15.1 hm 15.2 md 15.3 sh Graphica 16.1 Tk 16.2 Ti 16.3 Sc 16.4 tu 16.5 Idl 16.6 Otl Restricte 17.1 re 17.2 Ba Python I 18.1 pa 18.2 sy 18.3 to 18.4 ke 18.5 to 18.6 ta 18.7 py 18.8 py 18.9 co 18.10 di	ac — Keyed-Hashing for Message Authentication 5 — MD5 message digest algorithm 6 a — SHA-1 message digest algorithm 6 inter — Python interface to Tcl/Tk 6 inter — Python interface to Tcl/Tk 7 — Extension widgets for Tk 7 — Extension widgets for Tk 8 — Extension widgets for Tk 9 — Turtle graphics for Tk 9 — 6 — 6 — 6 — 6 — 6 — 6 — 6 — 6 — 6 —	569 570 573 573 584 589 594 595 598 701 710 711 712 713 714 714

	18.12 distutils — Building and installing Python modules	. 722
19	Python compiler package	723
	19.1 The basic interface	. 723
	19.2 Limitations	. 724
	19.3 Python Abstract Syntax	. 724
	19.4 Using Visitors to Walk ASTs	
	19.5 Bytecode Generation	
20	SGI IRIX Specific Services	731
20	20.1 al — Audio functions on the SGI	
	20.2 AL — Constants used with the al module	
	20.3 cd — CD-ROM access on SGI systems	
	20.4 f1 — FORMS library for graphical user interfaces	
	· · · · · · · · · · · · · · · · · · ·	
	20.6 flp — Functions for loading stored FORMS designs	
	20.7 fm — Font Manager interface	
	20.8 gl — Graphics Library interface	
	20.9 DEVICE — Constants used with the gl module	
	20.10 GL — Constants used with the gl module	
	20.11 imgfile — Support for SGI imglib files	
	20.12 jpeg — Read and write JPEG files	. 745
21	SunOS Specific Services	747
	21.1 sunaudiodev — Access to Sun audio hardware	. 747
	21.2 SUNAUDIODEV — Constants used with sunaudiodev	
22	MS Windows Specific Services	749
	22.1 msvcrt – Useful routines from the MS VC++ runtime	749
	22.2 _winreg – Windows registry access	
	22.3 winsound — Sound-playing interface for Windows	
	22.5 willsound — Sound-playing interface for windows	. 134
A	Undocumented Modules	757
	A.1 Frameworks	. 757
	A.2 Miscellaneous useful utilities	. 757
	A.3 Platform specific modules	. 757
	A.4 Multimedia	
	A.5 Obsolete	
	A.6 SGI-specific Extension modules	
В	Reporting Bugs	761
		= (2
C	History and License	763
	C.1 History of the software	
	C.2 Terms and conditions for accessing or otherwise using Python	
	C.3 Licenses and Acknowledgements for Incorporated Software	. 766
Mo	dule Index	775
Inc	AV	770

CHAPTER

ONE

Introduction

The "Python library" contains several different kinds of components.

It contains data types that would normally be considered part of the "core" of a language, such as numbers and lists. For these types, the Python language core defines the form of literals and places some constraints on their semantics, but does not fully define the semantics. (On the other hand, the language core does define syntactic properties like the spelling and priorities of operators.)

The library also contains built-in functions and exceptions — objects that can be used by all Python code without the need of an import statement. Some of these are defined by the core language, but many are not essential for the core semantics and are only described here.

The bulk of the library, however, consists of a collection of modules. There are many ways to dissect this collection. Some modules are written in C and built in to the Python interpreter; others are written in Python and imported in source form. Some modules provide interfaces that are highly specific to Python, like printing a stack trace; some provide interfaces that are specific to particular operating systems, such as access to specific hardware; others provide interfaces that are specific to a particular application domain, like the World Wide Web. Some modules are available in all versions and ports of Python; others are only available when the underlying system supports or requires them; yet others are available only when a particular configuration option was chosen at the time when Python was compiled and installed.

This manual is organized "from the inside out:" it first describes the built-in data types, then the built-in functions and exceptions, and finally the modules, grouped in chapters of related modules. The ordering of the chapters as well as the ordering of the modules within each chapter is roughly from most relevant to least important.

This means that if you start reading this manual from the start, and skip to the next chapter when you get bored, you will get a reasonable overview of the available modules and application areas that are supported by the Python library. Of course, you don't *have* to read it like a novel — you can also browse the table of contents (in front of the manual), or look for a specific function, module or term in the index (in the back). And finally, if you enjoy learning about random subjects, you choose a random page number (see module random) and read a section or two. Regardless of the order in which you read the sections of this manual, it helps to start with chapter 2, "Built-in Types, Exceptions and Functions," as the remainder of the manual assumes familiarity with this material.

Let the show begin!

Built-In Objects

Names for built-in exceptions and functions and a number of constants are found in a separate symbol table. This table is searched last when the interpreter looks up the meaning of a name, so local and global user-defined names can override built-in names. Built-in types are described together here for easy reference.¹

The tables in this chapter document the priorities of operators by listing them in order of ascending priority (within a table) and grouping operators that have the same priority in the same box. Binary operators of the same priority group from left to right. (Unary operators group from right to left, but there you have no real choice.) See chapter 5 of the *Python Reference Manual* for the complete picture on operator priorities.

2.1 Built-in Functions

The Python interpreter has a number of functions built into it that are always available. They are listed here in alphabetical order.

```
__import__(name[, globals[, locals[, fromlist]]])
```

This function is invoked by the import statement. It mainly exists so that you can replace it with another function that has a compatible interface, in order to change the semantics of the import statement. For examples of why and how you would do this, see the standard library modules ihooks and rexec. See also the built-in module imp, which defines some useful operations out of which you can build your own __import__() function.

For example, the statement 'import spam' results in the following call: __import__('spam', globals(), locals(), []); the statement 'from spam.ham import eggs' results in '__import__('spam.ham', globals(), locals(), ['eggs'])'. Note that even though locals() and ['eggs'] are passed in as arguments, the __import__() function does not set the local variable named eggs; this is done by subsequent code that is generated for the import statement. (In fact, the standard implementation does not use its *locals* argument at all, and uses its *globals* only to determine the package context of the import statement.)

When the *name* variable is of the form package.module, normally, the top-level package (the name up till the first dot) is returned, *not* the module named by *name*. However, when a non-empty *fromlist* argument is given, the module named by *name* is returned. This is done for compatibility with the bytecode generated for the different kinds of import statement; when using 'import spam.ham.eggs', the top-level package spam must be placed in the importing namespace, but when using 'from spam.ham import eggs', the spam.ham subpackage must be used to find the eggs variable. As a workaround for this behavior, use getattr() to extract the desired components. For example, you could define the following helper:

```
def my_import(name):
   mod = __import__(name)
   components = name.split('.')
   for comp in components[1:]:
      mod = getattr(mod, comp)
   return mod
```

¹Most descriptions sorely lack explanations of the exceptions that may be raised — this will be fixed in a future version of this manual.

abs(x)

Return the absolute value of a number. The argument may be a plain or long integer or a floating point number. If the argument is a complex number, its magnitude is returned.

basestring()

This abstract type is the superclass for str and unicode. It cannot be called or instantiated, but it can be used to test whether an object is an instance of str or unicode. isinstance(obj, basestring) is equivalent to isinstance(obj, (str, unicode)). New in version 2.3.

bool([x])

Convert a value to a Boolean, using the standard truth testing procedure. If x is false or omitted, this returns False; otherwise it returns True. bool is also a class, which is a subclass of int. Class bool cannot be subclassed further. Its only instances are False and True.

New in version 2.2.1. Changed in version 2.3: If no argument is given, this function returns False.

callable(object)

Return true if the *object* argument appears callable, false if not. If this returns true, it is still possible that a call fails, but if it is false, calling *object* will never succeed. Note that classes are callable (calling a class returns a new instance); class instances are callable if they have a <code>__call__()</code> method.

$\mathtt{chr}(i)$

Return a string of one character whose ASCII code is the integer i. For example, chr(97) returns the string 'a'. This is the inverse of ord(). The argument must be in the range [0..255], inclusive; ValueError will be raised if i is outside that range.

classmethod(function)

Return a class method for function.

A class method receives the class as implicit first argument, just like an instance method receives the instance. To declare a class method, use this idiom:

```
class C:
    @classmethod
    def f(cls, arg1, arg2, ...): ...
```

The @classmethod form is a function decorator – see the description of function definitions in chapter 7 of the *Python Reference Manual* for details.

It can be called either on the class (such as C.f()) or on an instance (such as C().f()). The instance is ignored except for its class. If a class method is called for a derived class, the derived class object is passed as the implied first argument.

Class methods are different than C++ or Java static methods. If you want those, see staticmethod() in this section. New in version 2.2. Changed in version 2.4: Function decorator syntax added.

cmp(x, y)

Compare the two objects x and y and return an integer according to the outcome. The return value is negative if x < y, zero if x == y and strictly positive if x > y.

```
compile (string, filename, kind[, flags[, dont_inherit]])
```

Compile the *string* into a code object. Code objects can be executed by an exec statement or evaluated by a call to eval(). The *filename* argument should give the file from which the code was read; pass some recognizable value if it wasn't read from a file ('<string>' is commonly used). The *kind* argument specifies what kind of code must be compiled; it can be 'exec' if *string* consists of a sequence of statements, 'eval' if it consists of a single expression, or 'single' if it consists of a single interactive statement (in the latter case, expression statements that evaluate to something else than None will be printed).

When compiling multi-line statements, two caveats apply: line endings must be represented by a single newline character (' \n'), and the input must be terminated by at least one newline character. If line endings are represented by ' \n' , use the string replace() method to change them into ' \n' .

The optional arguments *flags* and *dont_inherit* (which are new in Python 2.2) control which future statements (see PEP 236) affect the compilation of *string*. If neither is present (or both are zero) the code is compiled with those future statements that are in effect in the code that is calling compile. If the *flags* argument is given and *dont_inherit* is not (or is zero) then the future statements specified by the *flags* argument

are used in addition to those that would be used anyway. If *dont_inherit* is a non-zero integer then the *flags* argument is it – the future statements in effect around the call to compile are ignored.

Future statements are specified by bits which can be bitwise or-ed together to specify multiple statements. The bitfield required to specify a given feature can be found as the compiler_flag attribute on the _Feature instance in the __future__ module.

complex([real[, imag]])

Create a complex number with the value $real + imag^*j$ or convert a string or number to a complex number. If the first parameter is a string, it will be interpreted as a complex number and the function must be called without a second parameter. The second parameter can never be a string. Each argument may be any numeric type (including complex). If imag is omitted, it defaults to zero and the function serves as a numeric conversion function like int(), long() and float(). If both arguments are omitted, returns 0 j.

delattr(object, name)

This is a relative of setattr(). The arguments are an object and a string. The string must be the name of one of the object's attributes. The function deletes the named attribute, provided the object allows it. For example, delattr(x, 'foobar') is equivalent to del x.foobar.

dict([mapping-or-sequence])

Return a new dictionary initialized from an optional positional argument or from a set of keyword arguments. If no arguments are given, return a new empty dictionary. If the positional argument is a mapping object, return a dictionary mapping the same keys to the same values as does the mapping object. Otherwise the positional argument must be a sequence, a container that supports iteration, or an iterator object. The elements of the argument must each also be of one of those kinds, and each must in turn contain exactly two objects. The first is used as a key in the new dictionary, and the second as the key's value. If a given key is seen more than once, the last value associated with it is retained in the new dictionary.

If keyword arguments are given, the keywords themselves with their associated values are added as items to the dictionary. If a key is specified both in the positional argument and as a keyword argument, the value associated with the keyword is retained in the dictionary. For example, these all return a dictionary equal to { "one": 2, "two": 3}:

```
•dict({'one': 2, 'two': 3})
•dict({'one': 2, 'two': 3}.items())
•dict({'one': 2, 'two': 3}.iteritems())
•dict(zip(('one', 'two'), (2, 3)))
•dict([['two', 3], ['one', 2]])
•dict(one=2, two=3)
•dict([(['one', 'two'][i-2], i) for i in (2, 3)])
```

New in version 2.2. Changed in version 2.3: Support for building a dictionary from keyword arguments added.

dir([object])

Without arguments, return the list of names in the current local symbol table. With an argument, attempts to return a list of valid attributes for that object. This information is gleaned from the object's <code>__dict__</code> attribute, if defined, and from the class or type object. The list is not necessarily complete. If the object is a module object, the list contains the names of the module's attributes. If the object is a type or class object, the list contains the names of its attributes, and recursively of the attributes of its bases. Otherwise, the list contains the object's attributes' names, the names of its class's attributes, and recursively of the attributes of its class's base classes. The resulting list is sorted alphabetically. For example:

```
>>> import struct
>>> dir()
['__builtins__', '__doc__', '__name__', 'struct']
>>> dir(struct)
['__doc__', '__name__', 'calcsize', 'error', 'pack', 'unpack']
```

2.1. Built-in Functions 5

Note: Because dir() is supplied primarily as a convenience for use at an interactive prompt, it tries to supply an interesting set of names more than it tries to supply a rigorously or consistently defined set of names, and its detailed behavior may change across releases.

divmod(a, b)

Take two (non complex) numbers as arguments and return a pair of numbers consisting of their quotient and remainder when using long division. With mixed operand types, the rules for binary arithmetic operators apply. For plain and long integers, the result is the same as $(a \mid b, a \nmid b)$. For floating point numbers the result is $(q, a \nmid b)$, where q is usually math.floor $(a \mid b)$ but may be 1 less than that. In any case $q \nmid b \mid a \mid b$ is very close to a, if $a \mid b$ is non-zero it has the same sign as b, and $0 \le abs(a) \le abs(b)$.

Changed in version 2.3: Using divmod() with complex numbers is deprecated.

enumerate(iterable)

Return an enumerate object. *iterable* must be a sequence, an iterator, or some other object which supports iteration. The next() method of the iterator returned by enumerate() returns a tuple containing a count (from zero) and the corresponding value obtained from iterating over *iterable*. enumerate() is useful for obtaining an indexed series: (0, seq[0]), (1, seq[1]), (2, seq[2]), New in version 2.3.

eval(expression[, globals[, locals]])

The arguments are a string and optional globals and locals. If provided, *globals* must be a dictionary. If provided, *locals* can be any mapping object. Changed in version 2.4: formerly *locals* was required to be a dictionary.

The *expression* argument is parsed and evaluated as a Python expression (technically speaking, a condition list) using the *globals* and *locals* dictionaries as global and local name space. If the *globals* dictionary is present and lacks '__builtins__', the current globals are copied into *globals* before *expression* is parsed. This means that *expression* normally has full access to the standard __builtin__ module and restricted environments are propagated. If the *locals* dictionary is omitted it defaults to the *globals* dictionary. If both dictionaries are omitted, the expression is executed in the environment where eval is called. The return value is the result of the evaluated expression. Syntax errors are reported as exceptions. Example:

```
>>> x = 1
>>> print eval('x+1')
2
```

This function can also be used to execute arbitrary code objects (such as those created by compile()). In this case pass a code object instead of a string. The code object must have been compiled passing 'eval' as the *kind* argument.

Hints: dynamic execution of statements is supported by the exec statement. Execution of statements from a file is supported by the execfile() function. The globals() and locals() functions returns the current global and local dictionary, respectively, which may be useful to pass around for use by eval() or execfile().

execfile(filename[, globals[, locals]])

This function is similar to the exec statement, but parses a file instead of a string. It is different from the import statement in that it does not use the module administration — it reads the file unconditionally and does not create a new module.²

The arguments are a file name and two optional dictionaries. The file is parsed and evaluated as a sequence of Python statements (similarly to a module) using the *globals* and *locals* dictionaries as global and local namespace. If provided, *locals* can be any mapping object. Changed in version 2.4: formerly *locals* was required to be a dictionary. If the *locals* dictionary is omitted it defaults to the *globals* dictionary. If both dictionaries are omitted, the expression is executed in the environment where <code>execfile()</code> is called. The return value is <code>None</code>.

Warning: The default *locals* act as described for function locals() below: modifications to the default *locals* dictionary should not be attempted. Pass an explicit *locals* dictionary if you need to see effects of the code on *locals* after function execfile() returns. execfile() cannot be used reliably to modify a function's locals.

²It is used relatively rarely so does not warrant being made into a statement.

file(filename[, mode[, bufsize]])

Return a new file object (described in section 2.3.9, "File Objects"). The first two arguments are the same as for stdio's fopen(): *filename* is the file name to be opened, *mode* indicates how the file is to be opened: 'r' for reading, 'w' for writing (truncating an existing file), and 'a' opens it for appending (which on *some* UNIX systems means that *all* writes append to the end of the file, regardless of the current seek position).

Modes 'r+', 'w+' and 'a+' open the file for updating (note that 'w+' truncates the file). Append 'b' to the mode to open the file in binary mode, on systems that differentiate between binary and text files (else it is ignored). If the file cannot be opened, IOError is raised.

In addition to the standard fopen() values mode may be 'U' or 'rU'. If Python is built with universal newline support (the default) the file is opened as a text file, but lines may be terminated by any of '\n', the Unix end-of-line convention, '\r', the Macintosh convention or '\r\n', the Windows convention. All of these external representations are seen as '\n' by the Python program. If Python is built without universal newline support mode 'U' is the same as normal text mode. Note that file objects so opened also have an attribute called newlines which has a value of None (if no newlines have yet been seen), '\n', '\r', '\r\n', or a tuple containing all the newline types seen.

If *mode* is omitted, it defaults to 'r'. When opening a binary file, you should append 'b' to the *mode* value for improved portability. (It's useful even on systems which don't treat binary and text files differently, where it serves as documentation.) The optional *bufsize* argument specifies the file's desired buffer size: 0 means unbuffered, 1 means line buffered, any other positive value means use a buffer of (approximately) that size. A negative *bufsize* means to use the system default, which is usually line buffered for tty devices and fully buffered for other files. If omitted, the system default is used.³

The file() constructor is new in Python 2.2 and is an alias for open(). Both spellings are equivalent. The intent is for open() to continue to be preferred for use as a factory function which returns a new file object. The spelling, file is more suited to type testing (for example, writing 'isinstance(f, file)').

filter(function, list)

Construct a list from those elements of *list* for which *function* returns true. *list* may be either a sequence, a container which supports iteration, or an iterator, If *list* is a string or a tuple, the result also has that type; otherwise it is always a list. If *function* is None, the identity function is assumed, that is, all elements of *list* that are false (zero or empty) are removed.

Note that filter(function, *list*) is equivalent to [item for item in *list* if function(item)] if function is not None and [item for item in *list* if item] if function is None.

float(|x|)

Convert a string or a number to floating point. If the argument is a string, it must contain a possibly signed decimal or floating point number, possibly embedded in whitespace. Otherwise, the argument may be a plain or long integer or a floating point number, and a floating point number with the same value (within Python's floating point precision) is returned. If no argument is given, returns 0.0.

Note: When passing in a string, values for NaN and Infinity may be returned, depending on the underlying C library. The specific set of strings accepted which cause these values to be returned depends entirely on the C library and is known to vary.

frozenset([iterable])

Return a frozenset object whose elements are taken from *iterable*. Frozensets are sets that have no update methods but can be hashed and used as members of other sets or as dictionary keys. The elements of a frozenset must be immutable themselves. To represent sets of sets, the inner sets should also be frozenset objects. If *iterable* is not specified, returns a new empty set, frozenset([]). New in version 2.4.

getattr(object, name[, default])

Return the value of the named attributed of *object. name* must be a string. If the string is the name of one of the object's attributes, the result is the value of that attribute. For example, getattr(x, 'foobar')

2.1. Built-in Functions 7

³Specifying a buffer size currently has no effect on systems that don't have setvbuf(). The interface to specify the buffer size is not done using a method that calls setvbuf(), because that may dump core when called after any I/O has been performed, and there's no reliable way to determine whether this is the case.

is equivalent to x.foobar. If the named attribute does not exist, *default* is returned if provided, otherwise AttributeError is raised.

globals()

Return a dictionary representing the current global symbol table. This is always the dictionary of the current module (inside a function or method, this is the module where it is defined, not the module from which it is called).

hasattr(object, name)

The arguments are an object and a string. The result is True if the string is the name of one of the object's attributes, False if not. (This is implemented by calling getattr(object, name) and seeing whether it raises an exception or not.)

hash(object)

Return the hash value of the object (if it has one). Hash values are integers. They are used to quickly compare dictionary keys during a dictionary lookup. Numeric values that compare equal have the same hash value (even if they are of different types, as is the case for 1 and 1.0).

help([object])

Invoke the built-in help system. (This function is intended for interactive use.) If no argument is given, the interactive help system starts on the interpreter console. If the argument is a string, then the string is looked up as the name of a module, function, class, method, keyword, or documentation topic, and a help page is printed on the console. If the argument is any other kind of object, a help page on the object is generated. New in version 2.2.

$\mathbf{hex}(x)$

Convert an integer number (of any size) to a hexadecimal string. The result is a valid Python expression. Changed in version 2.4: Formerly only returned an unsigned literal..

id(object)

Return the "identity" of an object. This is an integer (or long integer) which is guaranteed to be unique and constant for this object during its lifetime. Two objects with non-overlapping lifetimes may have the same id() value. (Implementation note: this is the address of the object.)

input(|prompt|)

Equivalent to eval(raw_input(prompt)). Warning: This function is not safe from user errors! It expects a valid Python expression as input; if the input is not syntactically valid, a SyntaxError will be raised. Other exceptions may be raised if there is an error during evaluation. (On the other hand, sometimes this is exactly what you need when writing a quick script for expert use.)

If the readline module was loaded, then input() will use it to provide elaborate line editing and history features.

Consider using the raw_input() function for general input from users.

int([x[, radix]])

Convert a string or number to a plain integer. If the argument is a string, it must contain a possibly signed decimal number representable as a Python integer, possibly embedded in whitespace. The *radix* parameter gives the base for the conversion and may be any integer in the range [2, 36], or zero. If *radix* is zero, the proper radix is guessed based on the contents of string; the interpretation is the same as for integer literals. If *radix* is specified and *x* is not a string, TypeError is raised. Otherwise, the argument may be a plain or long integer or a floating point number. Conversion of floating point numbers to integers truncates (towards zero). If the argument is outside the integer range a long object will be returned instead. If no arguments are given, returns 0.

isinstance(object, classinfo)

Return true if the *object* argument is an instance of the *classinfo* argument, or of a (direct or indirect) subclass thereof. Also return true if *classinfo* is a type object and *object* is an object of that type. If *object* is not a class instance or an object of the given type, the function always returns false. If *classinfo* is neither a class object nor a type object, it may be a tuple of class or type objects, or may recursively contain other such tuples (other sequence types are not accepted). If *classinfo* is not a class, type, or tuple of classes, types, and such tuples, a TypeError exception is raised. Changed in version 2.2: Support for a tuple of type information was added.

issubclass(class, classinfo)

Return true if *class* is a subclass (direct or indirect) of *classinfo*. A class is considered a subclass of itself. *classinfo* may be a tuple of class objects, in which case every entry in *classinfo* will be checked. In any other case, a TypeError exception is raised. Changed in version 2.3: Support for a tuple of type information was added.

iter(o[, sentinel])

Return an iterator object. The first argument is interpreted very differently depending on the presence of the second argument. Without a second argument, o must be a collection object which supports the iteration protocol (the __jetitem__() method), or it must support the sequence protocol (the __getitem__() method with integer arguments starting at 0). If it does not support either of those protocols, TypeError is raised. If the second argument, *sentinel*, is given, then o must be a callable object. The iterator created in this case will call o with no arguments for each call to its next() method; if the value returned is equal to *sentinel*, StopIteration will be raised, otherwise the value will be returned. New in version 2.2.

len(s)

Return the length (the number of items) of an object. The argument may be a sequence (string, tuple or list) or a mapping (dictionary).

list([sequence])

Return a list whose items are the same and in the same order as *sequence*'s items. *sequence* may be either a sequence, a container that supports iteration, or an iterator object. If *sequence* is already a list, a copy is made and returned, similar to *sequence*[:]. For instance, list('abc') returns ['a', 'b', 'c'] and list((1, 2, 3)) returns [1, 2, 3]. If no argument is given, returns a new empty list, [].

locals()

Update and return a dictionary representing the current local symbol table. **Warning:** The contents of this dictionary should not be modified; changes may not affect the values of local variables used by the interpreter.

long([x[, radix]])

Convert a string or number to a long integer. If the argument is a string, it must contain a possibly signed number of arbitrary size, possibly embedded in whitespace. The radix argument is interpreted in the same way as for int(), and may only be given when x is a string. Otherwise, the argument may be a plain or long integer or a floating point number, and a long integer with the same value is returned. Conversion of floating point numbers to integers truncates (towards zero). If no arguments are given, returns 0L.

map(function, list, ...)

Apply function to every item of list and return a list of the results. If additional list arguments are passed, function must take that many arguments and is applied to the items of all lists in parallel; if a list is shorter than another it is assumed to be extended with None items. If function is None, the identity function is assumed; if there are multiple list arguments, map() returns a list consisting of tuples containing the corresponding items from all lists (a kind of transpose operation). The list arguments may be any kind of sequence; the result is always a list.

$\max(s[, args...])$

With a single argument s, return the largest item of a non-empty sequence (such as a string, tuple or list). With more than one argument, return the largest of the arguments.

min(s|, args...|)

With a single argument *s*, return the smallest item of a non-empty sequence (such as a string, tuple or list). With more than one argument, return the smallest of the arguments.

object()

Return a new featureless object. object() is a base for all new style classes. It has the methods that are common to all instances of new style classes. New in version 2.2.

Changed in version 2.3: This function does not accept any arguments. Formerly, it accepted arguments but ignored them.

oct(x)

Convert an integer number (of any size) to an octal string. The result is a valid Python expression. Changed in version 2.4: Formerly only returned an unsigned literal..

open(filename[, mode[, bufsize]])

An alias for the file() function above.

2.1. Built-in Functions 9

ord(c)

Given a string of length one, return an integer representing the Unicode code point of the character when the argument is a unicode object, or the value of the byte when the argument is an 8-bit string. For example, ord('a') returns the integer 97, ord(u'\u2020') returns 8224. This is the inverse of chr() for 8-bit strings and of unichr() for unicode objects. If a unicode argument is given and Python was built with UCS2 Unicode, then the character's code point must be in the range [0..65535] inclusive; otherwise the string length is two, and a TypeError will be raised.

pow(x, y[, z])

Return x to the power y; if z is present, return x to the power y, modulo z (computed more efficiently than $pow(x, y) \ \, ^*z$). The arguments must have numeric types. With mixed operand types, the coercion rules for binary arithmetic operators apply. For int and long int operands, the result has the same type as the operands (after coercion) unless the second argument is negative; in that case, all arguments are converted to float and a float result is delivered. For example, 10**2 returns 100, but 10**-2 returns 0.01. (This last feature was added in Python 2.2. In Python 2.1 and before, if both arguments were of integer types and the second argument was negative, an exception was raised.) If the second argument is negative, the third argument must be omitted. If z is present, x and y must be of integer types, and y must be non-negative. (This restriction was added in Python 2.2. In Python 2.1 and before, floating 3-argument pow() returned platform-dependent results depending on floating-point rounding accidents.)

property([fget[, fset[, fdel[, doc]]]])

Return a property attribute for new-style classes (classes that derive from object).

fget is a function for getting an attribute value, likewise fset is a function for setting, and fdel a function for del'ing, an attribute. Typical use is to define a managed attribute x:

```
class C(object):
    def __init__(self): self.__x = None
    def getx(self): return self.__x
    def setx(self, value): self.__x = value
    def delx(self): del self.__x
    x = property(getx, setx, delx, "I'm the 'x' property.")
```

New in version 2.2.

range([start,]stop[,step])

This is a versatile function to create lists containing arithmetic progressions. It is most often used in for loops. The arguments must be plain integers. If the *step* argument is omitted, it defaults to 1. If the *start* argument is omitted, it defaults to 0. The full form returns a list of plain integers [start, start + step, start + 2 * step, . . .]. If step is positive, the last element is the largest start + i * step less than stop; if step is negative, the last element is the smallest start + i * step greater than stop. step must not be zero (or else ValueError is raised). Example:

```
>>> range(10)
[0, 1, 2, 3, 4, 5, 6, 7, 8, 9]
>>> range(1, 11)
[1, 2, 3, 4, 5, 6, 7, 8, 9, 10]
>>> range(0, 30, 5)
[0, 5, 10, 15, 20, 25]
>>> range(0, 10, 3)
[0, 3, 6, 9]
>>> range(0, -10, -1)
[0, -1, -2, -3, -4, -5, -6, -7, -8, -9]
>>> range(0)
[]
>>> range(1, 0)
[]
```

raw_input([prompt])

If the *prompt* argument is present, it is written to standard output without a trailing newline. The function then reads a line from input, converts it to a string (stripping a trailing newline), and returns that. When EOF

is read, EOFError is raised. Example:

```
>>> s = raw_input('--> ')
--> Monty Python's Flying Circus
>>> s
"Monty Python's Flying Circus"
```

If the readline module was loaded, then $raw_input()$ will use it to provide elaborate line editing and history features.

```
\begin{tabular}{ll} \bf reduce (\it function, \it sequence [, \it initializer]) \\ Apply \it function \end{tabular}
```

If a module instantiates instances of a class, reloading the module that defines the class does not affect the method definitions of the instances — they continue to use the old class definition. The same is true for derived classes.

repr(object)

Return a string containing a printable representation of an object. This is the same value yielded by conversions (reverse quotes). It is sometimes useful to be able to access this operation as an ordinary function. For many types, this function makes an attempt to return a string that would yield an object with the same value when passed to eval().

reversed(seq)

Return a reverse iterator. *seq* must be an object which supports the sequence protocol (the __len__() method and the __getitem__() method with integer arguments starting at 0). New in version 2.4.

round(x[, n])

Return the floating point value x rounded to n digits after the decimal point. If n is omitted, it defaults to zero. The result is a floating point number. Values are rounded to the closest multiple of 10 to the power minus n; if two multiples are equally close, rounding is done away from 0 (so. for example, round (0.5) is 1.0 and round (-0.5) is -1.0).

set([iterable])

Return a set whose elements are taken from *iterable*. The elements must be immutable. To represent sets of sets, the inner sets should be frozenset objects. If *iterable* is not specified, returns a new empty set, set ([]). New in version 2.4.

setattr(object, name, value)

This is the counterpart of getattr(). The arguments are an object, a string and an arbitrary value. The string may name an existing attribute or a new attribute. The function assigns the value to the attribute, provided the object allows it. For example, setattr(x, 'foobar', 123) is equivalent to x.foobar = 123.

slice([start,] stop[, step])

Return a slice object representing the set of indices specified by range(start, stop, step). The start and step arguments default to None. Slice objects have read-only data attributes start, stop and step which merely return the argument values (or their default). They have no other explicit functionality; however they are used by Numerical Python and other third party extensions. Slice objects are also generated when extended indexing syntax is used. For example: 'a[start:stop:step]' or 'a[start:stop, i]'.

sorted(iterable[, cmp[, key[, reverse]]])

Return a new sorted list from the items in *iterable*. The optional arguments *cmp*, *key*, and *reverse* have the same meaning as those for the list.sort() method. New in version 2.4.

staticmethod(function)

Return a static method for function.

A static method does not receive an implicit first argument. To declare a static method, use this idiom:

```
class C:
    @staticmethod
    def f(arg1, arg2, ...): ...
```

The @staticmethod form is a function decorator – see the description of function definitions in chapter 7 of the *Python Reference Manual* for details.

It can be called either on the class (such as C.f()) or on an instance (such as C().f()). The instance is ignored except for its class.

Static methods in Python are similar to those found in Java or C++. For a more advanced concept, see classmethod() in this section. New in version 2.2. Changed in version 2.4: Function decorator syntax added.

str([object])

Return a string containing a nicely printable representation of an object. For strings, this returns the string itself. The difference with repr(object) is that str(object) does not always attempt to return a string that is acceptable to eval(); its goal is to return a printable string. If no argument is given, returns the

```
empty string, ''.
```

sum(sequence[, start])

Sums *start* and the items of a *sequence*, from left to right, and returns the total. *start* defaults to 0. The *sequence*'s items are normally numbers, and are not allowed to be strings. The fast, correct way to concatenate sequence of strings is by calling ''.join(sequence). Note that sum(range(n), m) is equivalent to reduce(operator.add, range(n), m) New in version 2.3.

```
super(type[, object-or-type])
```

Return the superclass of type. If the second argument is omitted the super object returned is unbound. If the second argument is an object, isinstance(obj, type) must be true. If the second argument is a type, issubclass(type2, type) must be true. super() only works for new-style classes.

A typical use for calling a cooperative superclass method is:

```
class C(B):
    def meth(self, arg):
        super(C, self).meth(arg)
```

Note that super is implemented as part of the binding process for explicit dotted attribute lookups such as 'super(C, self).__getitem__(name)'. Accordingly, super is undefined for implicit lookups using statements or operators such as 'super(C, self)[name]'. New in version 2.2.

tuple([sequence])

Return a tuple whose items are the same and in the same order as *sequence*'s items. *sequence* may be a sequence, a container that supports iteration, or an iterator object. If *sequence* is already a tuple, it is returned unchanged. For instance, tuple('abc') returns ('a', 'b', 'c') and tuple([1, 2, 3]) returns (1, 2, 3). If no argument is given, returns a new empty tuple, ().

type(object)

Return the type of an *object*. The return value is a type object. The isinstance() built-in function is recommended for testing the type of an object.

With three arguments, type functions as a constructor as detailed below.

type (name, bases, dict)

Return a new type object. This is essentially a dynamic form of the class statement. The *name* string is the class name and becomes the __name__ attribute; the *bases* tuple itemizes the base classes and becomes the __bases__ attribute; and the *dict* dictionary is the namespace containing definitions for class body and becomes the __dict__ attribute. For example, the following two statements create identical type objects:

New in version 2.2.

unichr(i)

Return the Unicode string of one character whose Unicode code is the integer *i*. For example, unichr(97) returns the string u'a'. This is the inverse of ord() for Unicode strings. The valid range for the argument depends how Python was configured – it may be either UCS2 [0..0xFFFF] or UCS4 [0..0x10FFFF]. ValueError is raised otherwise. New in version 2.0.

```
unicode([object[, encoding[, errors]]])
```

Return the Unicode string version of *object* using one of the following modes:

If encoding and/or errors are given, unicode() will decode the object which can either be an 8-bit string or a character buffer using the codec for encoding. The encoding parameter is a string giving the name of an encoding; if the encoding is not known, LookupError is raised. Error handling is done according to errors; this specifies the treatment of characters which are invalid in the input encoding. If errors is 'strict' (the default), a ValueError is raised on errors, while a value of 'ignore' causes errors to be silently ignored, and a value of 'replace' causes the official Unicode replacement character, U+FFFD, to be used to replace input characters which cannot be decoded. See also the codecs module.

2.1. Built-in Functions

If no optional parameters are given, unicode() will mimic the behaviour of str() except that it returns Unicode strings instead of 8-bit strings. More precisely, if *object* is a Unicode string or subclass it will return that Unicode string without any additional decoding applied.

For objects which provide a __unicode__() method, it will call this method without arguments to create a Unicode string. For all other objects, the 8-bit string version or representation is requested and then converted to a Unicode string using the codec for the default encoding in 'strict' mode.

New in version 2.0. Changed in version 2.2: Support for __unicode__() added.

vars([object])

Without arguments, return a dictionary corresponding to the current local symbol table. With a module, class or class instance object as argument (or anything else that has a __dict__ attribute), returns a dictionary corresponding to the object's symbol table. The returned dictionary should not be modified: the effects on the corresponding symbol table are undefined.⁴

```
xrange([start,]stop[,step])
```

This function is very similar to range(), but returns an "xrange object" instead of a list. This is an opaque sequence type which yields the same values as the corresponding list, without actually storing them all simultaneously. The advantage of xrange() over range() is minimal (since xrange() still has to create the values when asked for them) except when a very large range is used on a memory-starved machine or when all of the range's elements are never used (such as when the loop is usually terminated with break).

Note: xrange() is intended to be simple and fast. Implementations may impose restrictions to achieve this. The C implementation of Python restricts all arguments to native C longs ("short" Python integers), and also requires that the number of elements fit in a native C long.

This function returns a list of tuples, where the i-th tuple contains the i-th element from each of the argument sequences or iterables. The returned list is truncated in length to the length of the shortest argument sequence. When there are multiple arguments which are all of the same length, zip() is similar to map() with an initial argument of None. With a single sequence argument, it returns a list of 1-tuples. With no arguments, it returns an empty list. New in version 2.0.

Changed in version 2.4: Formerly, zip() required at least one argument and zip() raised a TypeError instead of returning an empty list..

2.2 Non-essential Built-in Functions

There are several built-in functions that are no longer essential to learn, know or use in modern Python programming. They have been kept here to maintain backwards compatibility with programs written for older versions of Python.

Python programmers, trainers, students and bookwriters should feel free to bypass these functions without concerns about missing something important.

```
apply(function, args[, keywords])
```

The function argument must be a callable object (a user-defined or built-in function or method, or a class object) and the args argument must be a sequence. The function is called with args as the argument list; the number of arguments is the length of the tuple. If the optional keywords argument is present, it must be a dictionary whose keys are strings. It specifies keyword arguments to be added to the end of the argument list. Calling apply() is different from just calling function(args), since in that case there is always exactly one argument. The use of apply() is equivalent to function(*args, **keywords). Use of apply() is not necessary since the "extended call syntax," as used in the last example, is completely equivalent.

Deprecated since release 2.3. Use the extended call syntax instead, as described above.

```
buffer(object[, offset[, size]])
```

The *object* argument must be an object that supports the buffer call interface (such as strings, arrays, and buffers). A new buffer object will be created which references the *object* argument. The buffer object will

⁴In the current implementation, local variable bindings cannot normally be affected this way, but variables retrieved from other scopes (such as modules) can be. This may change.

be a slice from the beginning of *object* (or from the specified *offset*). The slice will extend to the end of *object* (or will have a length given by the *size* argument).

coerce(x, y)

Return a tuple consisting of the two numeric arguments converted to a common type, using the same rules as used by arithmetic operations. If coercion is not possible, raise TypeError.

intern(string)

Enter *string* in the table of "interned" strings and return the interned string – which is *string* itself or a copy. Interning strings is useful to gain a little performance on dictionary lookup – if the keys in a dictionary are interned, and the lookup key is interned, the key comparisons (after hashing) can be done by a pointer compare instead of a string compare. Normally, the names used in Python programs are automatically interned, and the dictionaries used to hold module, class or instance attributes have interned keys. Changed in version 2.3: Interned strings are not immortal (like they used to be in Python 2.2 and before); you must keep a reference to the return value of intern() around to benefit from it.

2.3 Built-in Types

The following sections describe the standard types that are built into the interpreter. Historically, Python's built-in types havethon's bbuilt-

2.3.2 Boolean Operations — and, or, not

These are the Boolean operations, ordered by ascending priority:

Operation	Result	Notes
x or y	if x is false, then y, else x	(1)
x and y	if x is false, then x , else y	(1)
not x	if x is false, then True, else False	(2)

Notes:

- (1) These only evaluate their second argument if needed for their outcome.
- (2) 'not' has a lower priority than non-Boolean operators, so not a == b is interpreted as not (a == b), and a ==not b is a syntax error.

2.3.3 Comparisons

Comparison operations are supported by all objects. They all have the same priority (which is higher than that of the Boolean operations). Comparisons can be chained arbitrarily; for example, x < y <= z is equivalent to x < y and y <= z, except that y is evaluated only once (but in both cases z is not evaluated at all when x < y is found to be false).

This table summarizes the comparison operations:

Operation	Meaning	Notes
<	strictly less than	
<=	less than or equal	
>	strictly greater than	
>=	greater than or equal	
==	equal	
! =	not equal	(1)
<>	not equal	(1)
is	object identity	
is not	negated object identity	

Notes:

(1) <> and != are alternate spellings for the same operator. != is the preferred spelling; <> is obsolescent.

Objects of different types, except different numeric types and different string types, never compare equal; such objects are ordered consistently but arbitrarily (so that sorting a heterogeneous array yields a consistent result). Furthermore, some types (for example, file objects) support only a degenerate notion of comparison where any two objects of that type are unequal. Again, such objects are ordered arbitrarily but consistently. The <, <=, > and >= operators will raise a TypeError exception when any operand is a complex number.

Instances of a class normally compare as non-equal unless the class defines the __cmp__() method. Refer to the *Python Reference Manual* for information on the use of this method to effect object comparisons.

Implementation note: Objects of different types except numbers are ordered by their type names; objects of the same types that don't support proper comparison are ordered by their address.

Two more operations with the same syntactic priority, 'in' and 'not in', are supported only by sequence types (below).

2.3.4 Numeric Types — int, float, long, complex

There are four distinct numeric types: *plain integers*, *long integers*, *floating point numbers*, and *complex numbers*. In addition, Booleans are a subtype of plain integers. Plain integers (also just called *integers*) are implemented

using long in C, which gives them at least 32 bits of precision. Long integers have unlimited precision. Floating point numbers are implemented using double in C. All bets on their precision are off unless you happen to know the machine you are working with.

Complex numbers have a real and imaginary part, which are each implemented using double in C. To extract these parts from a complex number z, use z. real and z. imag.

Numbers are created by numeric literals or as the result of built-in functions and operators. Unadorned integer literals (including hex and octal numbers) yield plain integers unless the value they denote is too large to be represented as a plain integer, in which case they yield a long integer. Integer literals with an 'L' or 'l' suffix yield long integers ('L' is preferred because 'll' looks too much like eleven!). Numeric literals containing a decimal point or an exponent sign yield floating point numbers. Appending 'j' or 'J' to a numeric literal yields a complex number with a zero real part. A complex numeric literal is the sum of a real and an imaginary part.

Python fully supports mixed arithmetic: when a binary arithmetic operator has operands of different numeric types, the operand with the "narrower" type is widened to that of the other, where plain integer is narrower than long integer is narrower than floating point is narrower than complex. Comparisons between numbers of mixed type use the same rule. The constructors int(), long(), float(), and complex() can be used to produce numbers of a specific type.

All numeric types (except complex) support the following operations, sorted by ascending priority (operations in the same box have the same priority; all numeric operations have a higher priority than comparison operations):

Operation	Result	Notes
x + y	sum of x and y	
x - y	difference of x and y	
x * y	product of x and y	
x / y	quotient of x and y	(1)
x % y	remainder of $x \neq y$	(4)
-x	x negated	
+x	x unchanged	
abs(x)	absolute value or magnitude of x	
int(x)	x converted to integer	(2)
long(x)	x converted to long integer	(2)
float(x)	x converted to floating point	
<pre>complex(re,im)</pre>	a complex number with real part re, imaginary part im. im defaults to zero.	
$c.\mathtt{conjugate()}$	conjugate of the complex number <i>c</i>	
divmod(x, y)	the pair $(x // y, x \% y)$	(3)(4)
pow(x, y)	x to the power y	
x ** y	x to the power y	

Notes:

- (1) For (plain or long) integer division, the result is an integer. The result is always rounded towards minus infinity: 1/2 is 0, (-1)/2 is -1, 1/(-2) is -1, and (-1)/(-2) is 0. Note that the result is a long integer if either operand is a long integer, regardless of the numeric value.
- (2) Conversion from floating point to (long or plain) integer may round or truncate as in C; see functions floor() and ceil() in the math module for well-defined conversions.
- (3) See section 2.1, "Built-in Functions," for a full description.
- (4) Complex floor division operator, modulo operator, and divmod().

 $\label{lem:decomposition} \textbf{Deprecated since release 2.3.} \ \ \textbf{Instead convert to float using abs ()} \ \ \textbf{if appropriate.}$

Bit-string Operations on Integer Types

2.3. Built-in Types 17

⁶As a consequence, the list [1, 2] is considered equal to [1.0, 2.0], and similarly for tuples.

Plain and long integer types support additional operations that make sense only for bit-strings. Negative numbers are treated as their 2's complement value (for long integers, this assumes a sufficiently large number of bits that

Python's generators provide a convenient way to implement the iterator protocol. If a container object's __iter__() method is implemented as a generator, it will automatically return an iterator object (technically, a generator object) supplying the __iter__() and next() methods.

2.3.6 Sequence Types — str, unicode, list, tuple, buffer, xrange

There are six sequence types: strings, Unicode strings, lists, tuples, buffers, and xrange objects.

String literals are written in single or double quotes: 'xyzzy', "frobozz". See chapter 2 of the *Python Reference Manual* for more about string literals. Unicode strings are much like strings, but are specified in the syntax using a preceding 'u' character: u'abc', u"def". Lists are constructed with square brackets, separating items with commas: [a, b, c]. Tuples are constructed by the comma operator (not within square brackets), with or without enclosing parentheses, but an empty tuple must have the enclosing parentheses, such as a, b, c or (). A single item tuple must have a trailing comma, such as (d,).

Buffer objects are not directly supported by Python syntax, but can be created by calling the builtin function buffer (). They don't support concatenation or repetition.

Xrange objects are similar to buffers in that there is no specific syntax to create them, but they are created using the xrange() function. They don't support slicing, concatenation or repetition, and using in, not in, min() or max() on them is inefficient.

Most sequence types support the following operations. The 'in' and 'not in' operations have the same priorities as the comparison operations. The '+' and '*' operations have the same priority as the corresponding numeric operations.

This table lists the sequence operations sorted in ascending priority (operations in the same box have the same priority). In the table, s and t are sequences of the same type; n, i and j are integers:

Operation	Result	Notes
x in s	True if an item of s is equal to x , else False	(1)
x not in s	False if an item of s is equal to x , else True	(1)
s + t	the concatenation of s and t	(6)
s * n, n * s	n shallow copies of s concatenated	(2)
s[i]	i'th item of s, origin 0	(3)
s[i:j]	slice of s from i to j	(3), (4)
s[i:j:k]	slice of s from i to j with step k	(3), (5)
len(s)	length of s	
min(s)	smallest item of s	
$\max(s)$	largest item of s	

Notes:

- (1) When *s* is a string or Unicode string object the in and not in operations act like a substring test. In Python versions before 2.3, *x* had to be a string of length 1. In Python 2.3 and beyond, *x* may be a string of any length.
- (2) Values of *n* less than 0 are treated as 0 (which yields an empty sequence of the same type as *s*). Note also that the copies are shallow; nested structures are not copied. This often haunts new Python programmers; consider:

```
>>> lists = [[]] * 3
>>> lists
[[], [], []]
>>> lists[0].append(3)
>>> lists
[[3], [3], [3]]
```

2.3. Built-in Types 19

⁷They must have since the parser can't tell the type of the operands.

What has happened is that [[]] is a one-element list containing an empty list, so all three elements of [[]] * 3 are (pointers to) this single empty list. Modifying any of the elements of lists modifies this single list. You can create a list of different lists this way:

```
>>> lists = [[] for i in range(3)]
>>> lists[0].append(3)
>>> lists[1].append(5)
>>> lists[2].append(7)
>>> lists
[[3], [5], [7]]
```

- (3) If i or j is negative, the index is relative to the end of the string: len(s) + i or len(s) + j is substituted. But note that -0 is still 0.
- (4) The slice of s from i to j is defined as the sequence of items with index k such that $i \le k \le j$. If i or j is greater than len(s), use len(s). If i is omitted, use 0. If j is omitted, use len(s). If i is greater than or equal to j, the slice is empty.
- (5) The slice of s from i to j with step k is defined as the sequence of items with index x = i + n * k such that $0 \le n < \frac{j-i}{k}$. In other words, the indices are i, i+k, i+2*k, i+3*k and so on, stopping when j is reached (but never including j). If i or j is greater than len(s), use len(s). If i or j are omitted then they become "end" values (which end depends on the sign of k). Note, k cannot be zero.
- (6) If *s* and *t* are both strings, some Python implementations such as CPython can usually perform an in-place optimization for assignments of the form *s*=*s*+*t* or *s*+=*t*. When applicable, this optimization makes quadratic run-time much less likely. This optimization is both version and implementation dependent. For performance sensitive code, it is preferable to use the str.join() method which assures consistent linear concatenation performance across versions and implementations. Changed in version 2.4: Formerly, string concatenation never occurred in-place.

String Methods

These are the string methods which both 8-bit strings and Unicode objects support:

capitalize()

Return a copy of the string with only its first character capitalized.

For 8-bit strings, this method is locale-dependent.

```
center(width[, fillchar])
```

Return centered in a string of length *width*. Padding is done using the specified *fillchar* (default is a space). Changed in version 2.4: Support for the *fillchar* argument.

```
count (sub[, start[, end]])
```

Return the number of occurrences of substring *sub* in string S[*start*: *end*]. Optional arguments *start* and *end* are interpreted as in slice notation.

```
decode ( encoding , errors )
```

Decodes the string using the codec registered for *encoding*. *encoding* defaults to the default string encoding. *errors* may be given to set a different error handling scheme. The default is 'strict', meaning that encoding errors raise UnicodeError. Other possible values are 'ignore', 'replace' and any other name registered via codecs.register_error. New in version 2.2. Changed in version 2.3: Support for other error handling schemes added.

```
encode([encoding[,errors]])
```

Return an encoded version of the string. Default encoding is the current default string encoding. *errors* may be given to set a different error handling scheme. The default for *errors* is 'strict', meaning that encoding errors raise a UnicodeError. Other possible values are 'ignore', 'replace', 'xmlcharrefreplace', 'backslashreplace' and any other name registered via codecs.register_error. For a list of possible encodings, see section 4.9.2. New in version 2.0. Changed in version 2.3: Support for 'xmlcharrefreplace' and 'backslashreplace' and other error handling schemes added.

endswith(suffix[, start[, end]])

Return True if the string ends with the specified *suffix*, otherwise return False. With optional *start*, test beginning at that position. With optional *end*, stop comparing at that position.

expandtabs([tabsize])

Return a copy of the string where all tab characters are expanded using spaces. If *tabsize* is not given, a tab size of 8 characters is assumed.

find(sub[, start[, end]])

Return the lowest index in the string where substring *sub* is found, such that *sub* is contained in the range [*start*, *end*). Optional arguments *start* and *end* are interpreted as in slice notation. Return -1 if *sub* is not found.

index(sub[, start[, end]])

Like find(), but raise ValueError when the substring is not found.

isalnum()

Return true if all characters in the string are alphanumeric and there is at least one character, false otherwise.

For 8-bit strings, this method is locale-dependent.

isalpha()

Return true if all characters in the string are alphabetic and there is at least one character, false otherwise.

For 8-bit strings, this method is locale-dependent.

isdigit()

Return true if all characters in the string are digits and there is at least one character, false otherwise.

For 8-bit strings, this method is locale-dependent.

islower()

Return true if all cased characters in the string are lowercase and there is at least one cased character, false otherwise.

For 8-bit strings, this method is locale-dependent.

isspace()

Return true if there are only whitespace characters in the string and there is at least one character, false otherwise

For 8-bit strings, this method is locale-dependent.

istitle()

Return true if the string is a titlecased string and there is at least one character, for example uppercase characters may only follow uncased characters and lowercase characters only cased ones. Return false otherwise.

For 8-bit strings, this method is locale-dependent.

isupper()

Return true if all cased characters in the string are uppercase and there is at least one cased character, false otherwise.

For 8-bit strings, this method is locale-dependent.

join(seq)

Return a string which is the concatenation of the strings in the sequence *seq*. The separator between elements is the string providing this method.

ljust(width, fillchar)

Return the string left justified in a string of length width. Padding is done using the specified fillchar (default is a space). The original string is returned if width is less than len(s). Changed in version 2.4: Support for the fillchar argument.

lower()

Return a copy of the string converted to lowercase.

For 8-bit strings, this method is locale-dependent.

2.3. Built-in Types 21

lstrip([chars])

Return a copy of the string with leading characters removed. The *chars* argument is a string specifying the set of characters to be removed. If omitted or None, the *chars* argument defaults to removing whitespace. The *chars* argument is not a prefix; rather, all combinations of its values are stripped:

```
>>> ' spacious '.lstrip()
'spacious '
>>> 'www.example.com'.lstrip('cmowz.')
'example.com'
```

Changed in version 2.2.2: Support for the *chars* argument.

replace(old, new[, count])

Return a copy of the string with all occurrences of substring *old* replaced by *new*. If the optional argument *count* is given, only the first *count* occurrences are replaced.

rfind(sub[,start[,end]])

Return the highest index in the string where substring sub is found, such that sub is contained within s[start,end]. Optional arguments start and end are interpreted as in slice notation. Return -1 on failure.

rindex(sub[, start[, end]])

Like rfind() but raises ValueError when the substring *sub* is not found.

```
rjust(width[, fillchar])
```

Return the string right justified in a string of length width. Padding is done using the specified fillchar (default is a space). The original string is returned if width is less than len(s). Changed in version 2.4: Support for the fillchar argument.

```
rsplit([sep[,maxsplit]])
```

Return a list of the words in the string, using *sep* as the delimiter string. If *maxsplit* is given, at most *maxsplit* splits are done, the *rightmost* ones. If *sep* is not specified or None, any whitespace string is a separator. Except for splitting from the right, rsplit() behaves like split() which is described in detail below. New in version 2.4.

rstrip([chars])

Return a copy of the string with trailing characters removed. The *chars* argument is a string specifying the set of characters to be removed. If omitted or None, the *chars* argument defaults to removing whitespace. The *chars* argument is not a suffix; rather, all combinations of its values are stripped:

```
>>> ' spacious '.rstrip()
' spacious'
>>> 'mississippi'.rstrip('ipz')
'mississ'
```

Changed in version 2.2.2: Support for the *chars* argument.

split([sep [,maxsplit]])

Return a list of the words in the string, using *sep* as the delimiter string. If *maxsplit* is given, at most *maxsplit* splits are done. (thus, the list will have at most *maxsplit*+1 elements). If *maxsplit* is not specified, then there is no limit on the number of splits (all possible splits are made). Consecutive delimiters are not grouped together and are deemed to delimit empty strings (for example, '1, 2'.split(',')' returns '['1', '', '2']'). The *sep* argument may consist of multiple characters (for example, '1, 2, 3'.split(',')' returns '['1', '2', '3']'). Splitting an empty string with a specified separator returns '['']'.

If sep is not specified or is None, a different splitting algorithm is applied. First, whitespace characters (spaces, tabs, newlines, returns, and formfeeds) are stripped from both ends. Then, words are separated by arbitrary length strings of whitespace characters. Consecutive whitespace delimiters are treated as a single delimiter (''1 2 3'.split()' returns '['1', '2', '3']'). Splitting an empty string or a string consisting of just whitespace returns an empty list.

splitlines([keepends])

Return a list of the lines in the string, breaking at line boundaries. Line breaks are not included in the resulting list unless *keepends* is given and true.

startswith(prefix[, start[, end]])

Return True if string starts with the *prefix*, otherwise return False. With optional *start*, test string beginning at that position. With optional *end*, stop comparing string at that position.

strip([chars])

Return a copy of the string with the leading and trailing characters removed. The *chars* argument is a string specifying the set of characters to be removed. If omitted or None, the *chars* argument defaults to removing whitespace. The *chars* argument is not a prefix or suffix; rather, all combinations of its values are stripped:

```
>>> ' spacious '.strip()
'spacious'
>>> 'www.example.com'.strip('cmowz.')
'example'
```

Changed in version 2.2.2: Support for the *chars* argument.

swapcase()

Return a copy of the string with uppercase characters converted to lowercase and vice versa.

For 8-bit strings, this method is locale-dependent.

title()

Return a titlecased version of the string: words start with uppercase characters, all remaining cased characters are lowercase.

For 8-bit strings, this method is locale-dependent.

translate(table[, deletechars])

Return a copy of the string where all characters occurring in the optional argument *deletechars* are removed, and the remaining characters have been mapped through the given translation table, which must be a string of length 256.

For Unicode objects, the translate() method does not accept the optional *deletechars* argument. Instead, it returns a copy of the *s* where all characters have been mapped through the given translation table which must be a mapping of Unicode ordinals to Unicode ordinals, Unicode strings or None. Unmapped characters are left untouched. Characters mapped to None are deleted. Note, a more flexible approach is to create a custom character mapping codec using the codecs module (see encodings.cp1251 for an example).

upper()

Return a copy of the string converted to uppercase.

For 8-bit strings, this method is locale-dependent.

zfill(width)

Return the numeric string left filled with zeros in a string of length width. The original string is returned if width is less than len(s). New in version 2.2.2.

String Formatting Operations

String and Unicode objects have one unique built-in operation: the % operator (modulo). This is also known as the string formatting or interpolation operator. Given format %values (where format is a string or Unicode object), % conversion specifications in format are replaced with zero or more elements of values. The effect is similar to the using sprintf() in the C language. If format is a Unicode object, or if any of the objects being converted using the %s conversion are Unicode objects, the result will also be a Unicode object.

If *format* requires a single argument, *values* may be a single non-tuple object. Otherwise, *values* must be a tuple with exactly the number of items specified by the format string, or a single mapping object (for example, a dictionary).

A conversion specifier contains two or more characters and has the following components, which must occur in this order:

1. The '%' character, which marks the start of the specifier.

2.3. Built-in Types 23

⁸To format only a tuple you should therefore provide a singleton tuple whose only element is the tuple to be formatted.

- 2. Mapping key (optional), consisting of a parenthesised sequence of characters (for example, (somename)).
- 3. Conversion flags (optional), which affect the result of some conversion types.
- 4. Minimum field width (optional). If specified as an '*' (asterisk), the actual width is read from the next element of the tuple in *values*, and the object to convert comes after the minimum field width and optional precision.
- 5. Precision (optional), given as a '.' (dot) followed by the precision. If specified as '*' (an asterisk), the actual width is read from the next element of the tuple in *values*, and the value to convert comes after the precision.
- 6. Length modifier (optional).
- 7. Conversion type.

When the right argument is a dictionary (or other mapping type), then the formats in the string *must* include a parenthesised mapping key into that dictionary inserted immediately after the '%' character. The mapping key selects the value to be formatted from the mapping. For example:

```
>>> print '%(language)s has %(\#)03d quote types.' % \ {'language': "Python", "\#": 2} Python has 002 quote types.
```

In this case no * specifiers may occur in a format (since they require a sequential parameter list).

The conversion flag characters are:

Flag	Meaning
·#'	The value conversion will use the "alternate form" (where defined below).
'0'	The conversion will be zero padded for numeric values.
' -'	The converted value is left adjusted (overrides the '0' conversion if both are given).
٠,	(a space) A blank should be left before a positive number (or empty string) produced by a signed conversion.
·+'	A sign character ('+' or '-') will precede the conversion (overrides a "space" flag).

The length modifier may be h, 1, and L may be present, but are ignored as they are not necessary for Python.

The conversion types are:

Conversion	Meaning	Notes
'd'	Signed integer decimal.	
'i'	Signed integer decimal.	
o'	Unsigned octal.	(1)
ʻu'	Unsigned decimal.	
ʻx'	Unsigned hexadecimal (lowercase).	(2)
'х'	Unsigned hexadecimal (uppercase).	(2)
'e'	Floating point exponential format (lowercase).	
E'	Floating point exponential format (uppercase).	
'f'	Floating point decimal format.	
F'	Floating point decimal format.	
ʻg'	Same as 'e' if exponent is greater than -4 or less than precision, 'f' otherwise.	
'G'	Same as 'E' if exponent is greater than -4 or less than precision, 'F' otherwise.	
'c'	Single character (accepts integer or single character string).	
r'	String (converts any python object using repr()).	(3)
ʻs'	String (converts any python object using str()).	(4)
·%'	No argument is converted, results in a '%' character in the result.	

Notes:

- (1) The alternate form causes a leading zero ('0') to be inserted between left-hand padding and the formatting of the number if the leading character of the result is not already a zero.
- (2) The alternate form causes a leading '0x' or '0X' (depending on whether the 'x' or 'X' format was used) to be inserted between left-hand padding and the formatting of the number if the leading character of the result is not already a zero.
- (3) The %r conversion was added in Python 2.0.
- (4) If the object or format provided is a unicode string, the resulting string will also be unicode.

Since Python strings have an explicit length, \$s conversions do not assume that '\0' is the end of the string.

For safety reasons, floating point precisions are clipped to 50; %f conversions for numbers whose absolute value is over 1e25 are replaced by %g conversions. All other errors raise exceptions.

Additional string operations are defined in standard modules string and re.

XRange Type

The xrange type is an immutable sequence which is commonly used for looping. The advantage of the xrange type is that an xrange object will always take the same amount of memory, no matter the size of the range it represents. There are no consistent performance advantages.

XRange objects have very little behavior: they only support indexing, iteration, and the len() function.

Mutable Sequence Types

List objects support additional operations that allow in-place modification of the object. Other mutable sequence types (when added to the language) should also support these operations. Strings and tuples are immutable sequence types: such objects cannot be modified once created. The following operations are defined on mutable sequence types (where *x* is an arbitrary object):

Operation	Result	Notes
s[i] = x	item i of s is replaced by x	
s[i:j] = t	slice of s from i to j is replaced by t	
del s[i:j]	same as $s[i:j] = []$	
s[i:j:k] = t	the elements of $s[i:j:k]$ are replaced by those of t	(1)
del s[i:j:k]	removes the elements of $s[i:j:k]$ from the list	
s.append(x)	same as $s[len(s):len(s)] = [x]$	(2)
s.extend(x)	same as $s[len(s):len(s)] = x$	(3)
$s.\mathtt{count}(x)$	return number of i's for which $s[i] == x$	
s.index(x[, i[, j]])	return smallest k such that $s[k] == x$ and $i <= k < j$	(4)
s.insert(i, x)	same as $s[i:i] = [x]$	(5)
s.pop([i])	same as $x = s[i]$; del $s[i]$; return x	(6)
s.remove(x)	same as del $s[s.index(x)]$	(4)
$s.\mathtt{reverse}()$	reverses the items of s in place	(7)
s.sort([cmp[, key[, reverse]]])	sort the items of s in place	(7), (8), (9), (10)

Notes:

- (1) t must have the same length as the slice it is replacing.
- (2) The C implementation of Python has historically accepted multiple parameters and implicitly joined them into a tuple; this no longer works in Python 2.0. Use of this misfeature has been deprecated since Python 1.4.

2.3. Built-in Types 25

⁹These numbers are fairly arbitrary. They are intended to avoid printing endless strings of meaningless digits without hampering correct use and without having to know the exact precision of floating point values on a particular machine.

- (3) x can be any iterable object.
- (4) Raises ValueError when x is not found in s. When a negative index is passed as the second or third parameter to the index() method, the list length is added, as for slice indices. If it is still negative, it is truncated to zero, as for slice indices. Changed in version 2.3: Previously, index() didn't have arguments for specifying start and stop positions.
- (5) When a negative index is passed as the first parameter to the insert() method, the list length is added, as for slice indices. If it is still negative, it is truncated to zero, as for slice indices. Changed in version 2.3: Previously, all negative indices were truncated to zero.
- (6) The pop() method is only supported by the list and array types. The optional argument i defaults to -1, so that by default the last item is removed and returned.
- (7) The sort() and reverse() methods modify the list in place for economy of space when sorting or reversing a large list. To remind you that they operate by side effect, they don't return the sorted or reversed list.
- (8) The sort () method takes optional arguments for controlling the comparisons.

cmp specifies a custom comparison function of two arguments (list items) which should return a negative, zero or positive number depending on whether the first argument is considered smaller than, equal to, or larger than the second argument: 'cmp=lambda x,y: cmp(x.lower(), y.lower())'

key specifies a function of one argument that is used to extract a comparison key from each list element: '*key*=str.lower'

reverse is a boolean value. If set to True, then the list elements are sorted as if each comparison were reversed.

In general, the *key* and *reverse* conversion processes are much faster than specifying an equivalent *cmp* function. This is because *cmp* is called multiple times for each list element while *key* and *reverse* touch each element only once.

Changed in version 2.3: Support for None as an equivalent to omitting *cmp* was added.

Changed in version 2.4: Support for key and reverse was added.

- (9) Starting with Python 2.3, the sort () method is guaranteed to be stable. A sort is stable if it guarantees not to change the relative order of elements that compare equal this is helpful for sorting in multiple passes (for example, sort by department, then by salary grade).
- (10) While a list is being sorted, the effect of attempting to mutate, or even inspect, the list is undefined. The C implementation of Python 2.3 and newer makes the list appear empty for the duration, and raises ValueError if it can detect that the list has been mutated during a sort.

2.3.7 Set Types — set, frozenset

A *set* object is an unordered collection of immutable values. Common uses include membership testing, removing duplicates from a sequence, and computing mathematical operations such as intersection, union, difference, and symmetric difference. New in version 2.4.

Like other collections, sets support x in set, len(set), and for x in set. Being an unordered collection, sets do not record element position or order of insertion. Accordingly, sets do not support indexing, slicing, or other sequence-like behavior.

There are currently two builtin set types, set and frozenset. The set type is mutable — the contents can be changed using methods like add() and remove(). Since it is mutable, it has no hash value and cannot be used as either a dictionary key or as an element of another set. The frozenset type is immutable and hashable — its contents cannot be altered after is created; however, it can be used as a dictionary key or as an element of another set.

Instances of set and frozenset provide the following operations:

Operation	Equivalent	Result
len(s)		cardinality of set s
x in s		test x for membership in s
x not in s		test x for non-membership in s
s.issubset(t)	$s \ll t$	test whether every element in s is in t
s.issuperset (t)	s >= t	test whether every element in t is in s
s.union(t)	s — t	new set with elements from both s and t
s.intersection(t)	s & t	new set with elements common to s and t
s.difference(t)	s - t	new set with elements in <i>s</i> but not in <i>t</i>
$s.symmetric_difference(t)$	$s \hat{t}$	new set with elements in either <i>s</i> or <i>t</i> but not both
$s.\mathtt{copy}($ $)$		new set with a shallow copy of s

Note, the non-operator versions of union(), intersection(), difference(), and symmetric_difference(), issubset(), and issuperset() methods will accept any iterable as an argument. In contrast, their operator based counterparts require their arguments to be sets. This precludes error-prone constructions like set('abc') & 'cbs' in favor of the more readable set('abc').intersection('cbs').

Both set and frozenset support set to set comparisons. Two sets are equal if and only if every element of each set is contained in the other (each is a subset of the other). A set is less than another set if and only if the first set is a proper subset of the second set (is a subset, but is not equal). A set is greater than another set if and only if the first set is a proper superset of the second set (is a superset, but is not equal).

Instances of set are compared to instances of frozenset based on their members. For example, 'set('abc') == frozenset('abc')' returns True.

The subset and equality comparisons do not generalize to a complete ordering function. For example, any two disjoint sets are not equal and are not subsets of each other, so *all* of the following return False: a < b, a == b, or a > b. Accordingly, sets do not implement the __cmp__ method.

Since sets only define partial ordering (subset relationships), the output of the list.sort() method is undefined for lists of sets.

Set elements are like dictionary keys; they need to define both __hash__ and __eq__ methods.

Binary operations that mix set instances with frozenset return the type of the first operand. For example: 'frozenset('ab') | set('bc')' returns an instance of frozenset.

The following table lists operations available for set that do not apply to immutable instances of frozenset:

Operation	Equivalent	Result
s.update(t)	s —= t	return set s with elements added from t
$s.intersection_update(t)$	s &= t	return set s keeping only elements also found in t
$s.difference_update(t)$	s = t	return set s after removing elements found in t
$s. {\tt symmetric_difference_update}(t)$	s = t	return set s with elements from s or t but not both
s.add(x)		add element x to set s
s.remove(x)		remove x from set s; raises KeyError if not present
s.discard(x)		removes x from set s if present
$s.\mathtt{pop}()$		remove and return an arbitrary element from s ; raises KeyError
$s.\mathtt{clear}()$		remove all elements from set s

Note, the non-operator versions of the update(), intersection_update(), difference_update(), and symmetric_difference_update() methods will accept any iterable as an argument.

The design of the set types was based on lessons learned from the sets module.

See Also:

Module sets (section ??):

Differences between the sets module and the built-in set types.

2.3. Built-in Types 27

2.3.8 Mapping Types — classdict

A *mapping* object maps immutable values to arbitrary objects. Mappings are mutable objects. There is currently only one standard mapping type, the *dictionary*. A dictionary's keys are almost arbitrary values. Only values containing lists, dictionaries or other mutable types (that are compared by value rather than by object identity) may not be used as keys. Numeric types used for keys obey the normal rules for numeric comparison: if two numbers compare equal (such as 1 and 1.0) then they can be used interchangeably to index the same dictionary entry.

Dictionaries are created by placing a comma-separated list of *key*: *value* pairs within braces, for example: {'jack': 4098, 'sjoerd': 4127} or {4098: 'jack', 4127: 'sjoerd'}.

The following operations are defined on mappings (where a and b are mappings, k is a key, and v and x are arbitrary objects):

Operation	Result	Notes
len(a)	the number of items in a	
a[k]	the item of a with key k	(1)
a[k] = v	set $a[k]$ to v	
del a[k]	remove $a[k]$ from a	(1)
$a.\mathtt{clear}()$	remove all items from a	
$a.\mathtt{copy}()$	a (shallow) copy of a	
$a.\mathtt{has}_\mathtt{key}(k)$	True if a has a key k , else False	
k in a	Equivalent to a .has_key(k)	(2)
k not in a	Equivalent to not a .has_key(k)	(2)
$a.\mathtt{items}()$	a copy of a's list of (key, value) pairs	(3)
$a.\mathtt{keys}$ ()	a copy of a's list of keys	(3)
$a.\mathtt{update}(egin{bmatrix} b \end{bmatrix})$	updates (and overwrites) key/value pairs from b	(9)
a.fromkeys(seq[, value])	Creates a new dictionary with keys from seq and values set to value	(7)
<pre>a.values()</pre>	a copy of a's list of values	(3)
$a.\mathtt{get}(k[, x])$	a[k] if k in a , else x	(4)
$a.\mathtt{setdefault}(k[x])$	a[k] if k in a , else x (also setting it)	(5)
a.pop(k[, x])	a[k] if k in a , else x (and remove k)	(8)
$a.\mathtt{popitem()}$	remove and return an arbitrary (key, value) pair	(6)
$a.\mathtt{iteritems}()$	return an iterator over (key, value) pairs	(2), (3)
a.iterkeys()	return an iterator over the mapping's keys	(2), (3)
a.itervalues()	return an iterator over the mapping's values	(2), (3)

Notes:

- (1) Raises a KeyError exception if k is not in the map.
- (2) New in version 2.2.
- (3) Keys and values are listed in an arbitrary order which is non-random, varies across Python implementations, and depends on the dictionary's history of insertions and deletions. If items(), keys(), values(), iteritems(), iterkeys(), and itervalues() are called with no intervening modifications to the dictionary, the lists will directly correspond. This allows the creation of (value, key) pairs using zip(): 'pairs = zip(a.values(), a.keys())'. The same relationship holds for the iterkeys() and itervalues() methods: 'pairs = zip(a.itervalues(), a.iterkeys())' provides the same value for pairs. Another way to create the same list is 'pairs = [(v, k) for (k, v) in a.iteritems()]'.
- (4) Never raises an exception if *k* is not in the map, instead it returns *x*. *x* is optional; when *x* is not provided and *k* is not in the map, None is returned.
- (5) setdefault() is like get(), except that if k is missing, x is both returned and inserted into the dictionary as the value of k. x defaults to None.

- (6) popitem() is useful to destructively iterate over a dictionary, as often used in set algorithms. If the dictionary is empty, calling popitem() raises a KeyError.
- (7) fromkeys () is a class method that returns a new dictionary. value defaults to None. New in version 2.3.
- (8) pop() raises a KeyError when no default value is given and the key is not found. New in version 2.3.
- (9) update() accepts either another mapping object or an iterable of key/value pairs (as a tuple or other iterable of length two). If keyword arguments are specified, the mapping is then is updated with those key/value pairs: 'd.update(red=1, blue=2)'. Changed in version 2.4: Allowed the argument to be an iterable of key/value pairs and allowed keyword arguments.

2.3.9 File Objects

File objects are implemented using C's stdio package and can be created with the built-in constructor file() described in section 2.1, "Built-in Functions." File objects are also returned by some other built-in functions and methods, such as os.popen() and os.fdopen() and the makefile() method of socket objects.

When a file operation fails for an I/O-related reason, the exception IOError is raised. This includes situations where the operation is not defined for some reason, like seek() on a tty device or writing a file opened for reading.

Files have the following methods:

close()

Close the file. A closed file cannot be read or written any more. Any operation which requires that the file be open will raise a ValueError after the file has been closed. Calling close() more than once is allowed.

flush()

Flush the internal buffer, like stdio's fflush(). This may be a no-op on some file-like objects.

fileno()

Return the integer "file descriptor" that is used by the underlying implementation to request I/O operations from the operating system. This can be useful for other, lower level interfaces that use file descriptors, such as the fcntl module or os.read() and friends. **Note:** File-like objects which do not have a real file descriptor should *not* provide this method!

isatty()

Return True if the file is connected to a tty(-like) device, else False. **Note:** If a file-like object is not associated with a real file, this method should *not* be implemented.

next()

A file object is its own iterator, for example iter(f) returns f (unless f is closed). When a file is used as an iterator, typically in a for loop (for example, for line in f: print line), the next() method is called repeatedly. This method returns the next input line, or raises StopIteration when EOF is hit. In order to make a for loop the most efficient way of looping over the lines of a file (a very common operation), the next() method uses a hidden read-ahead buffer. As a consequence of using a read-ahead buffer, combining next() with other file methods (like readline()) does not work right. However, using seek() to reposition the file to an absolute position will flush the read-ahead buffer. New in version 2.3.

read([size])

Read at most *size* bytes from the file (less if the read hits EOF before obtaining *size* bytes). If the *size* argument is negative or omitted, read all data until EOF is reached. The bytes are returned as a string object. An empty string is returned when EOF is encountered immediately. (For certain files, like ttys, it makes sense to continue reading after an EOF is hit.) Note that this method may call the underlying C function fread() more than once in an effort to acquire as close to *size* bytes as possible. Also note that when in non-blocking mode, less data than what was requested may be returned, even if no *size* parameter was given.

2.3. Built-in Types 29

¹⁰file() is new in Python 2.2. The older built-in open() is an alias for file().

readline([size])

Read one entire line from the file. A trailing newline character is kept in the string (but may be absent when a file ends with an incomplete line). If the size argument is present and non-negative, it is a maximum byte count (including the trailing newline) and an incomplete line may be returned. An empty string is returned *only* when EOF is encountered immediately. **Note:** Unlike stdio's fgets(), the returned string contains null characters ('\0') if they occurred in the input.

readlines([sizehint])

Read until EOF using readline() and return a list containing the lines thus read. If the optional *sizehint* argument is present, instead of reading up to EOF, whole lines totalling approximately *sizehint* bytes (possibly after rounding up to an internal buffer size) are read. Objects implementing a file-like interface may choose to ignore *sizehint* if it cannot be implemented, or cannot be implemented efficiently.

xreadlines()

This method returns the same thing as iter(f). New in version 2.1. **Deprecated since release 2.3.** Use 'for *line* in *file*' instead.

seek(offset[, whence])

Set the file's current position, like stdio's fseek(). The whence argument is optional and defaults to 0 (absolute file positioning); other values are 1 (seek relative to the current position) and 2 (seek relative to the file's end). There is no return value. Note that if the file is opened for appending (mode 'a' or 'a+'), any seek() operations will be undone at the next write. If the file is only opened for writing in append mode (mode 'a'), this method is essentially a no-op, but it remains useful for files opened in append mode with reading enabled (mode 'a+'). If the file is opened in text mode (mode 't'), only offsets returned by tell() are legal. Use of other offsets causes undefined behavior.

Note that not all file objects are seekable.

tell()

Return the file's current position, like stdio's ftell().

truncate([size])

Truncate the file's size. If the optional *size* argument is present, the file is truncated to (at most) that size. The size defaults to the current position. The current file position is not changed. Note that if a specified size exceeds the file's current size, the result is platform-dependent: possibilities include that file may remain unchanged, increase to the specified size as if zero-filled, or increase to the specified size with undefined new content. Availability: Windows, many UNIX variants.

write(str)

Write a string to the file. There is no return value. Due to buffering, the string may not actually show up in the file until the flush() or close() method is called.

writelines(sequence)

Write a sequence of strings to the file. The sequence can be any iterable object producing strings, typically a list of strings. There is no return value. (The name is intended to match readlines(); writelines() does not add line separators.)

Files support the iterator protocol. Each iteration returns the same result as *file*.readline(), and iteration ends when the readline() method returns an empty string.

File objects also offer a number of other interesting attributes. These are not required for file-like objects, but should be implemented if they make sense for the particular object.

closed

bool indicating the current state of the file object. This is a read-only attribute; the close() method changes the value. It may not be available on all file-like objects.

encoding

The encoding that this file uses. When Unicode strings are written to a file, they will be converted to byte strings using this encoding. In addition, when the file is connected to a terminal, the attribute gives the encoding that the terminal is likely to use (that information might be incorrect if the user has misconfigured the terminal). The attribute is read-only and may not be present on all file-like objects. It may also be None,

¹¹The advantage of leaving the newline on is that returning an empty string is then an unambiguous EOF indication. It is also possible (in cases where it might matter, for example, if you want to make an exact copy of a file while scanning its lines) to tell whether the last line of a file ended in a newline or not (yes this happens!).

in which case the file uses the system default encoding for converting Unicode strings.

New in version 2.3.

mode

The I/O mode for the file. If the file was created using the open() built-in function, this will be the value of the *mode* parameter. This is a read-only attribute and may not be present on all file-like objects.

name

If the file object was created using open(), the name of the file. Otherwise, some string that indicates the source of the file object, of the form '<...>'. This is a read-only attribute and may not be present on all file-like objects.

newlines

If Python was built with the **--with-universal-newlines** option to **configure** (the default) this read-only attribute exists, and for files opened in universal newline read mode it keeps track of the types of newlines encountered while reading the file. The values it can take are '\r', '\n', '\r\n', None (unknown, no newlines read yet) or a tuple containing all the newline types seen, to indicate that multiple newline conventions were encountered. For files not opened in universal newline read mode the value of this attribute will be None.

softspace

Boolean that indicates whether a space character needs to be printed before another value when using the print statement. Classes that are trying to simulate a file object should also have a writable softspace attribute, which should be initialized to zero. This will be automatic for most classes implemented in Python (care may be needed for objects that override attribute access); types implemented in C will have to provide a writable softspace attribute. **Note:** This attribute is not used to control the print statement, but to allow the implementation of print to keep track of its internal state.

2.3.10 Other Built-in Types

The interpreter supports several other kinds of objects. Most of these support only one or two operations.

Modules

The only special operation on a module is attribute access: m.name, where m is a module and name accesses a name defined in m's symbol table. Module attributes can be assigned to. (Note that the import statement is not, strictly speaking, an operation on a module object; import foo does not require a module object named foo to exist, rather it requires an (external) definition for a module named foo somewhere.)

A special member of every module is $__dict__$. This is the dictionary containing the module's symbol table. Modifying this dictionary will actually change the module's symbol table, but direct assignment to the $__dict__$ attribute is not possible (you can write $m.__dict__['a'] = 1$, which defines m.a to be 1, but you can't write $m.__dict__ = \{\}$). Modifying $__dict__$ directly is not recommended.

Modules built into the interpreter are written like this: <module 'sys' (built-in)>. If loaded from a file, they are written as <module 'os' from '/usr/local/lib/python2.4/os.pyc'>.

Classes and Class Instances

See chapters 3 and 7 of the *Python Reference Manual* for these.

Functions

Function objects are created by function definitions. The only operation on a function object is to call it: func (argument-list).

There are really two flavors of function objects: built-in functions and user-defined functions. Both support the same operation (to call the function), but the implementation is different, hence the different object types.

2.3. Built-in Types 31

See the *Python Reference Manual* for more information.

Methods

Methods are functions that are called using the attribute notation. There are two flavors: built-in methods (such as append () on lists) and class instance methods. Built-in methods are described with the types that support them.

The implementation adds two special read-only attributes to class instance methods: $m.im_self$ is the object on which the method operates, and $m.im_func$ is the function implementing the method. Calling m(arg-1, arg-2, ..., arg-n) is completely equivalent to calling $m.im_func(m.im_self, arg-1, arg-2, ..., arg-n)$.

Class instance methods are either bound or unbound, referring to whether the method was accessed through an instance or a class, respectively. When a method is unbound, its im_self attribute will be None ach (for)H2daarclla that cla[(,or)-rultods.4+2451(40)]TFIbut71618(methods)-3ncde6dsixcancethfunktril(e)]TO 60cde785/ushTy520167160

TheNuwillO(

The Ellipsis Object

This object is used by extended slice notation (see the *Python Reference Manual*). It supports no special operations. There is exactly one ellipsis object, named Ellipsis (a built-in name).

It is written as Ellipsis.

Boolean Values

Boolean values are the two constant objects False and True. They are used to represent truth values (although other values can also be considered false or true). In numeric contexts (for example when used as the argument to an arithmetic operator), they behave like the integers 0 and 1, respectively. The built-in function bool() can be used to cast any value to a Boolean, if the value can be interpreted as a truth value (see section Truth Value Testing above).

They are written as False and True, respectively.

Internal Objects

See the *Python Reference Manual* for this information. It describes stack frame objects, traceback objects, and slice objects.

2.3.11 Special Attributes

The implementation adds a few special read-only attributes to several object types, where they are relevant. Some of these are not reported by the dir() built-in function.

__dict__

A dictionary or other mapping object used to store an object's (writable) attributes.

__methods_

Deprecated since release 2.2. Use the built-in function dir() to get a list of an object's attributes. This attribute is no longer available.

__members__

Deprecated since release 2.2. Use the built-in function dir() to get a list of an object's attributes. This attribute is no longer available.

__class__

The class to which a class instance belongs.

__bases__

The tuple of base classes of a class object. If there are no base classes, this will be an empty tuple.

__name__

The name of the class or type.

2.4 Built-in Exceptions

Exceptions should be class objects. The exceptions are defined in the module exceptions. This module never needs to be imported explicitly: the exceptions are provided in the built-in namespace as well as the exceptions module.

Note: In past versions of Python string exceptions were supported. In Python 1.5 and newer versions, all standard exceptions have been converted to class objects and users are encouraged to do the same. String exceptions will raise a PendingDeprecationWarning. In future versions, support for string exceptions will be removed.

Two distinct string objects with the same value are considered different exceptions. This is done to force programmers to use exception names rather than their string value when specifying exception handlers. The string value of

all built-in exceptions is their name, but this is not a requirement for user-defined exceptions or exceptions defined by library modules.

For class exceptions, in a try statement with an except clause that mentions a particular class, that clause also handles any exception classes derived from that class (but not exception classes from which *it* is derived). Two exception classes that are not related via subclassing are never equivalent, even if they have the same name.

The built-in exceptions listed below can be generated by the interpreter or built-in functions. Except where mentioned, they have an "associated value" indicating the detailed cause of the error. This may be a string or a tuple containing several items of information (e.g., an error code and a string explaining the code). The associated value is the second argument to the raise statement. For string exceptions, the associated value itself will be stored in the variable named as the second argument of the except clause (if any). For class exceptions, that variable receives the exception instance. If the exception class is derived from the standard root class Exception, the associated value is present as the exception instance's args attribute, and possibly on other attributes as well.

User code can raise built-in exceptions. This can be used to test an exception handler or to report an error condition "just like" the situation in which the interpreter raises the same exception; but beware that there is nothing to prevent user code from raising an inappropriate error.

The built-in exception classes can be sub-classed to define new exceptions; programmers are encouraged to at least derive new exceptions from the Exception base class. More information on defining exceptions is available in the *Python Tutorial* under the heading "User-defined Exceptions."

The following exceptions are only used as base classes for other exceptions.

exception Exception

The root class for exceptions. All built-in exceptions are derived from this class. All user-defined exceptions should also be derived from this class, but this is not (yet) enforced. The str() function, when applied to an instance of this class (or most derived classes) returns the string value of the argument or arguments, or an empty string if no arguments were given to the constructor. When used as a sequence, this accesses the arguments given to the constructor (handy for backward compatibility with old code). The arguments are also available on the instance's args attribute, as a tuple.

$exception \ {\tt StandardError}$

The base class for all built-in exceptions except StopIteration and SystemExit. StandardError itself is derived from the root class Exception.

exception ArithmeticError

The base class for those built-in exceptions that are raised for various arithmetic errors: OverflowError, ZeroDivisionError, FloatingPointError.

exception LookupError

The base class for the exceptions that are raised when a key or index used on a mapping or sequence is invalid: IndexError, KeyError. This can be raised directly by sys.setdefaultencoding().

exception EnvironmentError

The base class for exceptions that can occur outside the Python system: IOError, OSError. When exceptions of this type are created with a 2-tuple, the first item is available on the instance's errno attribute (it is assumed to be an error number), and the second item is available on the strerror attribute (it is usually the associated error message). The tuple itself is also available on the args attribute. New in version 1.5.2.

When an EnvironmentError exception is instantiated with a 3-tuple, the first two items are available as above, while the third item is available on the filename attribute. However, for backwards compatibility, the args attribute contains only a 2-tuple of the first two constructor arguments.

The filename attribute is None when this exception is created with other than 3 arguments. The errno and strerror attributes are also None when the instance was created with other than 2 or 3 arguments. In this last case, args contains the verbatim constructor arguments as a tuple.

The following exceptions are the exceptions that are actually raised.

exception AssertionError

Raised when an assert statement fails.

exception AttributeError

Raised when an attribute reference or assignment fails. (When an object does not support attribute references or attribute assignments at all, TypeError is raised.)

exception EOFError

Raised when one of the built-in functions (input() or raw_input()) hits an end-of-file condition (EOF) without reading any data. (N.B.: the read() and readline() methods of file objects return an empty string when they hit EOF.)

exception FloatingPointError

Raised when a floating point operation fails. This exception is always defined, but can only be raised when Python is configured with the **--with-fpectl** option, or the WANT_SIGFPE_HANDLER symbol is defined in the 'pyconfig.h' file.

exception IOError

Raised when an I/O operation (such as a print statement, the built-in open() function or a method of a file object) fails for an I/O-related reason, e.g., "file not found" or "disk full".

This class is derived from EnvironmentError. See the discussion above for more information on exception instance attributes.

exception ImportError

Raised when an import statement fails to find the module definition or when a from ... import fails to find a name that is to be imported.

exception IndexError

Raised when a sequence subscript is out of range. (Slice indices are silently truncated to fall in the allowed range; if an index is not a plain integer, TypeError is raised.)

exception KeyError

Raised when a mapping (dictionary) key is not found in the set of existing keys.

exception KeyboardInterrupt

Raised when the user hits the interrupt key (normally Control-C or Delete). During execution, a check for interrupts is made regularly. Interrupts typed when a built-in function input () or raw_input() is waiting for input also raise this exception.

exception MemoryError

Raised when an operation runs out of memory but the situation may still be rescued (by deleting some objects). The associated value is a string indicating what kind of (internal) operation ran out of memory. Note that because of the underlying memory management architecture (C's malloc() function), the interpreter may not always be able to completely recover from this situation; it nevertheless raises an exception so that a stack traceback can be printed, in case a run-away program was the cause.

exception NameError

Raised when a local or global name is not found. This applies only to unqualified names. The associated value is an error message that includes the name that could not be found.

exception NotImplementedError

This exception is derived from RuntimeError. In user defined base classes, abstract methods should raise this exception when they require derived classes to override the method. New in version 1.5.2.

exception OSError

This class is derived from EnvironmentError and is used primarily as the os module's os.error exception. See EnvironmentError above for a description of the possible associated values. New in version 1.5.2.

exception OverflowError

Raised when the result of an arithmetic operation is too large to be represented. This cannot occur for long integers (which would rather raise MemoryError than give up). Because of the lack of standardization of floating point exception handling in C, most floating point operations also aren't checked. For plain integers, all operations that can overflow are checked except left shift, where typical applications prefer to drop bits than raise an exception.

exception ReferenceError

This exception is raised when a weak reference proxy, created by the weakref.proxy() function, is used to access an attribute of the referent after it has been garbage collected. For more informa-

tion on weak references, see the weakref module. New in version 2.2: Previously known as the weakref.ReferenceError exception.

exception RuntimeError

Raised when an error is detected that doesn't fall in any of the other categories. The associated value is a string indicating what precisely went wrong. (This exception is mostly a relic from a previous version of the interpreter; it is not used very much any more.)

exception StopIteration

Raised by an iterator's next() method to signal that there are no further values. This is derived from Exception rather than StandardError, since this is not considered an error in its normal application. New in version 2.2.

exception SyntaxError

Raised when the parser encounters a syntax error. This may occur in an import statement, in an exec statement, in a call to the built-in function eval() or input(), or when reading the initial script or standard input (also interactively).

Instances of this class have attributes filename, lineno, offset and text for easier access to the details. str() of the exception instance returns only the message.

exception SystemError

Raised when the interpreter finds an internal error, but the situation does not look so serious to cause it to abandon all hope. The associated value is a string indicating what went wrong (in low-level terms).

You should report this to the author or maintainer of your Python interpreter. Be sure to report the version of the Python interpreter (sys.version; it is also printed at the start of an interactive Python session), the exact error message (the exception's associated value) and if possible the source of the program that triggered the error.

exception SystemExit

This exception is raised by the sys.exit() function. When it is not handled, the Python interpreter exits; no stack traceback is printed. If the associated value is a plain integer, it specifies the system exit status (passed to C's exit() function); if it is None, the exit status is zero; if it has another type (such as a string), the object's value is printed and the exit status is one.

Instances have an attribute code which is set to the proposed exit status or error message (defaulting to None). Also, this exception derives directly from Exception and not StandardError, since it is not technically an error.

A call to sys.exit() is translated into an exception so that clean-up handlers (finally clauses of try statements) can be executed, and so that a debugger can execute a script without running the risk of losing control. The os._exit() function can be used if it is absolutely positively necessary to exit immediately (for example, in the child process after a call to fork()).

exception TypeError

Raised when an operation or function is applied to an object of inappropriate type. The associated value is a string giving details about the type mismatch.

exception UnboundLocalError

Raised when a reference is made to a local variable in a function or method, but no value has been bound to that variable. This is a subclass of NameError. New in version 2.0.

exception UnicodeError

Raised when a Unicode-related encoding or decoding error occurs. It is a subclass of ValueError. New in version 2.0.

exception UnicodeEncodeError

Raised when a Unicode-related error occurs during encoding. It is a subclass of UnicodeError. New in version 2.3.

exception UnicodeDecodeError

Raised when a Unicode-related error occurs during decoding. It is a subclass of UnicodeError. New in version 2.3.

exception UnicodeTranslateError

Raised when a Unicode-related error occurs during translating. It is a subclass of UnicodeError. New

in version 2.3.

exception ValueError

Raised when a built-in operation or function receives an argument that has the right type but an inappropriate value, and the situation is not described by a more precise exception such as IndexError.

exception WindowsError

Raised when a Windows-specific error occurs or when the error number does not correspond to an errno value. The errno and strerror values are created from the return values of the GetLastError() and FormatMessage() functions from the Windows Platform API. This is a subclass of OSError. New in version 2.0.

exception ZeroDivisionError

Raised when the second argument of a division or modulo operation is zero. The associated value is a string indicating the type of the operands and the operation.

The following exceptions are used as warning categories; see the warnings module for more information.

exception Warning

Base class for warning categories.

exception UserWarning

Base class for warnings generated by user code.

exception DeprecationWarning

Base class for warnings about deprecated features.

exception PendingDeprecationWarning

Base class for warnings about features which will be deprecated in the future.

exception SyntaxWarning

Base class for warnings about dubious syntax

exception RuntimeWarning

Base class for warnings about dubious runtime behavior.

exception FutureWarning

Base class for warnings about constructs that will change semantically in the future.

The class hierarchy for built-in exceptions is:

```
Exception
   +-- SystemExit
   +-- StopIteration
   +-- StandardError
        +-- KeyboardInterrupt
        +-- ImportError
        +-- EnvironmentError
            +-- IOError
            +-- OSError
                 +-- WindowsError
        +-- EOFError
        +-- RuntimeError
            +-- NotImplementedError
        +-- NameError
            +-- UnboundLocalError
        +-- AttributeError
        +-- SyntaxError
            +-- IndentationError
                 +-- TabError
        +-- TypeError
        +-- AssertionError
        +-- LookupError
            +-- IndexError
            +-- KeyError
        +-- ArithmeticError
             +-- OverflowError
             +-- ZeroDivisionError
            +-- FloatingPointError
        +-- ValueError
            +-- UnicodeError
                 +-- UnicodeEncodeError
                 +-- UnicodeDecodeError
                 +-- UnicodeTranslateError
        +-- ReferenceError
        +-- SystemError
       +-- MemoryError
   +---Warning
+-- UserWarning
+-- DeprecationWarning
+-- PendingDeprecationWarning
+-- SyntaxWarning
+-- OverflowWarning (not generated in 2.4; won't exist in 2.5)
+-- RuntimeWarning
+-- FutureWarning
```

2.5 Built-in Constants

A small number of constants live in the built-in namespace. They are:

False

The false value of the bool type. New in version 2.3.

True

The true value of the bool type. New in version 2.3.

None

The sole value of types. None Type. None is frequently used to represent the absence of a value, as when default arguments are not passed to a function.

NotImplemented

Special value which can be returned by the "rich comparison" special methods ($_eq_-()$, $_lt_-()$, and friends), to indicate that the comparison is not implemented with respect to the other type.

Ellipsis

Special value used in conjunction with extended slicing syntax.

2.5. Built-in Constants 39

Python Runtime Services

The modules described in this chapter provide a wide range of services related to the Python interpreter and its interaction with its environment. Here's an overview:

sys Access system-specific parameters and functions.

gc Interface to the cycle-detecting garbage collector.

weakref Support for weak references and weak dictionaries.

fpect1 Provide control for floating point exception handling.

atexit Register and execute cleanup functions.

types Names for built-in types.

UserList Class wrapper for dictionary objects.
UserString Class wrapper for list objects.
Class wrapper for string objects.

operator All Python's standard operators as built-in functions.

Extract information and source code from live objects.

traceback Print or retrieve a stack traceback.

linecache This module provides random access to individual lines from text files.

pickle Convert Python objects to streams of bytes and back. **cPickle** Faster version of **pickle**, but not subclassable.

copy_reg Register pickle support functions.

shelve Python object persistence.

COPY Shallow and deep copy operations.

marshal Convert Python objects to streams of bytes and back (with different constraints).

warningsimpAccess the implementation of the import statement.zipimportsupport for importing Python modules from ZIP archives.

pkgutil Utilities to support extension of packages.

modulefinder Find modules used by a script.

codeBase classes for interactive Python interpreters. **codeop**Compile (possibly incomplete) Python code.

pprint Data pretty printer.

repr Alternate repr() implementation with size limits.

new Interface to the creation of runtime implementation objects.

A standard way to reference site-specific modules.

A standard way to reference user-specific modules.

The module that provides the built-in namespace.

The environment where the top-level script is run.

__future__ Future statement definitions

3.1 sys — System-specific parameters and functions

This module provides access to some variables used or maintained by the interpreter and to functions that interact strongly with the interpreter. It is always available.

argv

The list of command line arguments passed to a Python script. argv[0] is the script name (it is operating system dependent whether this is a full pathname or not). If the command was executed using the -c command line option to the interpreter, argv[0] is set to the string '-c'. If no script name was passed to the Python interpreter, argv has zero length.

byteorder

An indicator of the native byte order. This will have the value 'big' on big-endian (most-signigicant byte first) platforms, and 'little' on little-endian (least-significant byte first) platforms. New in version 2.0.

builtin_module_names

A tuple of strings giving the names of all modules that are compiled into this Python interpreter. (This information is not available in any other way — modules.)

copyright

A string containing the copyright pertaining to the Python interpreter.

dllhandle

Integer specifying the handle of the Python DLL. Availability: Windows.

displayhook(value)

If value is not None, this function prints it to sys.stdout, and saves it in __builtin__._.

sys.displayhook is called on the result of evaluating an expression entered in an interactive Python session. The display of these values can be customized by assigning another one-argument function to sys.displayhook.

excepthook(type, value, traceback)

This function prints out a given traceback and exception to sys.stderr.

When an exception is raised and uncaught, the interpreter calls sys.excepthook with three arguments, the exception class, exception instance, and a traceback object. In an interactive session this happens just before control is returned to the prompt; in a Python program this happens just before the program exits. The handling of such top-level exceptions can be customized by assigning another three-argument function to sys.excepthook.

__displayhook__

__excepthook__

These objects contain the original values of displayhook and excepthook at the start of the program. They are saved so that displayhook and excepthook can be restored in case they happen to get replaced with broken objects.

exc_info()

This function returns a tuple of three values that give information about the exception that is currently being handled. The information returned is specific both to the current thread and to the current stack frame. If the current stack frame is not handling an exception, the information is taken from the calling stack frame, or its caller, and so on until a stack frame is found that is handling an exception. Here, "handling an exception" is defined as "executing or having executed an except clause." For any stack frame, only information about the most recently handled exception is accessible.

If no exception is being handled anywhere on the stack, a tuple containing three None values is returned. Otherwise, the values returned are (type, value, traceback). Their meaning is: type gets the exception type of the exception being handled (a class object); value gets the exception parameter (its associated value or the second argument to raise, which is always a class instance if the exception type is a class object); traceback gets a traceback object (see the Reference Manual) which encapsulates the call stack at the point where the exception originally occurred.

If exc_clear() is called, this function will return three None values until either another exception is raised in the current thread or the execution stack returns to a frame where another exception is being handled.

Warning: Assigning the *traceback* return value to a local variable in a function that is handling an exception will cause a circular reference. This will prevent anything referenced by a local variable in the same function or by the traceback from being garbage collected. Since most functions don't need access to the traceback, the best solution is to use something like exctype, value = sys.exc_info()[:2] to extract only the exception type and value. If you do need the traceback, make sure to delete it after use (best done with a try ... finally

an exception. **Note:** Beginning with Python 2.2, such cycles are automatically reclaimed when garbage collection is enabled and they become unreachable, but it remains more efficient to avoid creating cycles.

exc_clear()

This function clears all information relating to the current or last exception that occurred in the current thread. After calling this function, <code>exc_info()</code> will return three None values until another exception is raised in the current thread or the execution stack returns to a frame where another exception is being handled.

This function is only needed in only a few obscure situations. These include logging and error handling systems that report information on the last or current exception. This function can also be used to try to free resources and trigger object finalization, though no guarantee is made as to what objects will be freed, if any. New in version 2.3.

exc_type

exc_value

exc_traceback

Deprecated since release 1.5. Use exc_info() instead.

Since they are global variables, they are not specific to the current thread, so their use is not safe in a multithreaded program. When no exception is being handled, exc_type is set to None and the other two are undefined.

exec_prefix

A string giving the site-specific directory prefix where the platform-dependent Python files are installed; by default, this is also '/usr/local'. This can be set at build time with the --exec-prefix argument to the configure script. Specifically, all configuration files (e.g. the 'pyconfig.h' header file) are installed in the directory exec_prefix + '/lib/pythonversion/config', and shared library modules are installed in exec_prefix + '/lib/pythonversion/lib-dynload', where version is equal to version[:3].

executable

A string giving the name of the executable binary for the Python interpreter, on systems where this makes sense

exit([arg])

Exit from Python. This is implemented by raising the SystemExit exception, so cleanup actions specified by finally clauses of try statements are honored, and it is possible to intercept the exit attempt at an outer level. The optional argument arg can be an integer giving the exit status (defaulting to zero), or another type of object. If it is an integer, zero is considered "successful termination" and any nonzero value is considered "abnormal termination" by shells and the like. Most systems require it to be in the range 0-127, and produce undefined results otherwise. Some systems have a convention for assigning specific meanings to specific exit codes, but these are generally underdeveloped; UNIX programs generally use 2 for command line syntax errors and 1 for all other kind of errors. If another type of object is passed, None is equivalent to passing zero, and any other object is printed to sys.stderr and results in an exit code of 1. In particular, sys.exit("some error message") is a quick way to exit a program when an error occurs.

exitfunc

This value is not actually defined by the module, but can be set by the user (or by a program) to specify a clean-up action at program exit. When set, it should be a parameterless function. This function will be called when the interpreter exits. Only one function may be installed in this way; to allow multiple functions which will be called at termination, use the atexit module. Note: The exit function is not called when the program is killed by a signal, when a Python fatal internal error is detected, or when os._exit() is called. Deprecated since release 2.4. Use atexit instead.

getcheckinterval()

Return the interpreter's "check interval"; see setcheckinterval(). New in version 2.3.

getdefaultencoding()

Return the name of the current default string encoding used by the Unicode implementation. New in version 2.0.

getdlopenflags()

Return the current value of the flags that are used for dlopen() calls. The flag constants are defined in

the dl and DLFCN modules. Availability: UNIX. New in version 2.2.

getfilesystemencoding()

Return the name of the encoding used to convert Unicode filenames into system file names, or None if the system default encoding is used. The result value depends on the operating system:

- •On Windows 9x, the encoding is "mbcs".
- •On Mac OS X, the encoding is "utf-8".
- •On Unix, the encoding is the user's preference according to the result of nl_langinfo(CODESET), or None if the nl_langinfo(CODESET) failed.
- •On Windows NT+, file names are Unicode natively, so no conversion is performed. getfilesystemencoding still returns "mbcs", as this is the encoding that applications should use when they explicitly want to convert Unicode strings to byte strings that are equivalent when used as file names.

New in version 2.3.

getrefcount(object)

Return the reference count of the *object*. The count returned is generally one higher than you might expect, because it includes the (temporary) reference as an argument to getrefcount().

getrecursionlimit()

Return the current value of the recursion limit, the maximum depth of the Python interpreter stack. This limit prevents infinite recursion from causing an overflow of the C stack and crashing Python. It can be set by setrecursionlimit().

_getframe([depth])

Return a frame object from the call stack. If optional integer *depth* is given, return the frame object that many calls below the top of the stack. If that is deeper than the call stack, ValueError is raised. The default for *depth* is zero, returning the frame at the top of the call stack.

This function should be used for internal and specialized purposes only.

getwindowsversion()

Return a tuple containing five components, describing the Windows version currently running. The elements are *major*, *minor*, *build*, *platform*, and *text*. *text* contains a string while all other values are integers.

platform may be one of the following values:

Constant	Platform
VER_PLATFORM_WIN32s	Win32s on Windows 3.1
VER_PLATFORM_WIN32_WINDOWS	Windows 95/98/ME
VER_PLATFORM_WIN32_NT	Windows NT/2000/XP
VER_PLATFORM_WIN32_CE	Windows CE

This function wraps the Win32 GetVersionEx() function; see the Microsoft documentation for more information about these fields.

Availability: Windows. New in version 2.3.

hexversion

The version number encoded as a single integer. This is guaranteed to increase with each version, including proper support for non-production releases. For example, to test that the Python interpreter is at least version 1.5.2, use:

```
if sys.hexversion >= 0x010502F0:
    # use some advanced feature
    ...
else:
    # use an alternative implementation or warn the user
    ...
```

This is called 'hexversion' since it only really looks meaningful when viewed as the result of passing it to the built-in hex() function. The version_info value may be used for a more human-friendly encoding of the same information. New in version 1.5.2.

last_type

last_value

last_traceback

These three variables are not always defined; they are set when an exception is not handled and the interpreter prints an error message and a stack traceback. Their intended use is to allow an interactive user to import a debugger module and engage in post-mortem debugging without having to re-execute the command that caused the error. (Typical use is 'import pdb; pdb.pm()' to enter the post-mortem debugger; see chapter 9, "The Python Debugger," for more information.)

The meaning of the variables is the same as that of the return values from exc_info() above. (Since there is only one interactive thread, thread-safety is not a concern for these variables, unlike for exc_type etc.)

maxint

The largest positive integer supported by Python's regular integer type. This is at least 2**31-1. The largest negative integer is -maxint-1 — the asymmetry results from the use of 2's complement binary arithmetic.

maxunicode

An integer giving the largest supported code point for a Unicode character. The value of this depends on the configuration option that specifies whether Unicode characters are stored as UCS-2 or UCS-4.

modules

This is a dictionary that maps module names to modules which have already been loaded. This can be manipulated to force reloading of modules and other tricks. Note that removing a module from this dictionary is *not* the same as calling reload() on the corresponding module object.

path

A list of strings that specifies the search path for modules. Initialized from the environment variable PYTHONPATH, plus an installation-dependent default.

As initialized upon program startup, the first item of this list, path[0], is the directory containing the script that was used to invoke the Python interpreter. If the script directory is not available (e.g. if the interpreter is invoked interactively or if the script is read from standard input), path[0] is the empty string, which directs Python to search modules in the current directory first. Notice that the script directory is inserted before the entries inserted as a result of PYTHONPATH.

A program is free to modify this list for its own purposes.

Changed in version 2.3: Unicode strings are no longer ignored.

platform

This string contains a platform identifier, e.g. 'sunos5' or 'linux1'. This can be used to append platform-specific components to path, for instance.

prefix

A string giving the site-specific directory prefix where the platform independent Python files are installed; by default, this is the string '/usr/local'. This can be set at build time with the --prefix argument to the configure script. The main collection of Python library modules is installed in the directory prefix + '/lib/pythonversion' while the platform independent header files (all except 'pyconfig.h') are stored in prefix + '/include/pythonversion', where version is equal to version[:3].

ps1 ps2

Strings specifying the primary and secondary prompt of the interpreter. These are only defined if the interpreter is in interactive mode. Their initial values in this case are '>>> ' and '... '. If a non-string object is assigned to either variable, its str() is re-evaluated each time the interpreter prepares to read a new interactive command; this can be used to implement a dynamic prompt.

setcheckinterval(interval)

Set the interpreter's "check interval". This integer value determines how often the interpreter checks for periodic things such as thread switches and signal handlers. The default is 100, meaning the check is performed every 100 Python virtual instructions. Setting it to a larger value may increase performance for programs using threads. Setting it to a value <= 0 checks every virtual instruction, maximizing responsiveness as well as overhead.

setdefaultencoding(name)

Set the current default string encoding used by the Unicode implementation. If *name* does not match any available encoding, LookupError is raised. This function is only intended to be used by the site module implementation and, where needed, by sitecustomize. Once used by the site module, it is removed from the sys module's namespace. New in version 2.0.

setdlopenflags(n)

Set the flags used by the interpreter for dlopen() calls, such as when the interpreter loads extension modules. Among other things, this will enable a lazy resolving of symbols when importing a module, if called as sys.setdlopenflags(0). To share symbols across extension modules, call as sys.setdlopenflags(dl.RTLD_NOW | dl.RTLD_GLOBAL). Symbolic names for the flag modules can be either found in the dl module, or in the DLFCN module. If DLFCN is not available, it can be generated from '/usr/include/dlfcn.h' using the h2py script. Availability: UNIX. New in version 2.2.

setprofile(profilefunc)

Set the system's profile function, which allows you to implement a Python source code profiler in Python. See chapter 10 for more information on the Python profiler. The system's profile function is called similarly to the system's trace function (see settrace()), but it isn't called for each executed line of code (only on call and return, but the return event is reported even when an exception has been set). The function is thread-specific, but there is no way for the profiler to know about context switches between threads, so it does not make sense to use this in the presence of multiple threads. Also, its return value is not used, so it can simply return None.

setrecursionlimit(limit)

Set the maximum depth of the Python interpreter stack to *limit*. This limit prevents infinite recursion from causing an overflow of the C stack and crashing Python.

The highest possible limit is platform-dependent. A user may need to set the limit higher when she has a program that requires deep recursion and a platform that supports a higher limit. This should be done with care, because a too-high limit can lead to a crash.

settrace(tracefunc)

Set the system's trace function, which allows you to implement a Python source code debugger in Python. See section 9.2, "How It Works," in the chapter on the Python debugger. The function is thread-specific; for a debugger to support multiple threads, it must be registered using settrace() for each thread being debugged. **Note:** The settrace() function is intended only for implementing debuggers, profilers, coverage tools and the like. Its behavior is part of the implementation platform, rather than part of the language definition, and thus may not be available in all Python implementations.

settscdump(on_flag)

Activate dumping of VM measurements using the Pentium timestamp counter, if on_flag is true. Deactivate these dumps if on_flag is off. The function is available only if Python was compiled with --with-tsc. To understand the output of this dump, read 'Python/ceval.c' in the Python sources. New in version 2.4.

stdin stdout stderr

File objects corresponding to the interpreter's standard input, output and error streams. stdin is used for all interpreter input except for scripts but including calls to input() and raw_input(). stdout is used for the output of print and expression statements and for the prompts of input() and raw_input(). The interpreter's own prompts and (almost all of) its error messages go to stderr. stdout and stderr needn't be built-in file objects: any object is acceptable as long as it has a write() method that takes a string argument. (Changing these objects doesn't affect the standard I/O streams of processes executed by os.popen(), os.system() or the exec*() family of functions in the os module.)

__stdin__ __stdout__ __stderr__

These objects contain the original values of stdin, stderr and stdout at the start of the program. They are used during finalization, and could be useful to restore the actual files to known working file objects in case they have been overwritten with a broken object.

tracebacklimit

When this variable is set to an integer value, it determines the maximum number of levels of traceback

information printed when an unhandled exception occurs. The default is 1000. When set to 0 or less, all traceback information is suppressed and only the exception type and value are printed.

version

A string containing the version number of the Python interpreter plus additional information on the build number and compiler used. It has a value of the form 'version (#build_number, build_date, build_time) [compiler]'. The first three characters are used to identify the version in the installation directories (where appropriate on each platform). An example:

```
>>> import sys
>>> sys.version
'1.5.2 (#0 Apr 13 1999, 10:51:12) [MSC 32 bit (Intel)]'
```

api_version

The C API version for this interpreter. Programmers may find this useful when debugging version conflicts between Python and extension modules. New in version 2.3.

version_info

A tuple containing the five components of the version number: *major*, *minor*, *micro*, *releaselevel*, and *serial*. All values except *releaselevel* are integers; the release level is 'alpha', 'beta', 'candidate', or 'final'. The version_info value corresponding to the Python version 2.0 is (2, 0, 0, 'final', 0). New in version 2.0.

warnoptions

This is an implementation detail of the warnings framework; do not modify this value. Refer to the warnings module for more information on the warnings framework.

winver

The version number used to form registry keys on Windows platforms. This is stored as string resource 1000 in the Python DLL. The value is normally the first three characters of version. It is provided in the sys module for informational purposes; modifying this value has no effect on the registry keys used by Python. Availability: Windows.

See Also:

Module site (section 3.30):

This describes how to use .pth files to extend sys.path.

3.2 gc — Garbage Collector interface

This module provides an interface to the optional garbage collector. It provides the ability to disable the collector, tune the collection frequency, and set debugging options. It also provides access to unreachable objects that the collector found but cannot free. Since the collector supplements the reference counting already used in Python, you can disable the collector if you are sure your program does not create reference cycles. Automatic collection can be disabled by calling gc.disable(). To debug a leaking program call gc.set_debug(gc.DEBUG_LEAK). Notice that this includes gc.DEBUG_SAVEALL, causing garbage-collected objects to be saved in gc.garbage for inspection.

The gc module provides the following functions:

enable()

Enable automatic garbage collection.

disable()

Disable automatic garbage collection.

isenabled()

Returns true if automatic collection is enabled.

collect()

Run a full collection. All generations are examined and the number of unreachable objects found is returned.

set_debug(flags)

Set the garbage collection debugging flags. Debugging information will be written to sys.stderr. See

below for a list of debugging flags which can be combined using bit operations to control debugging.

get_debug()

Return the debugging flags currently set.

get_objects()

Returns a list of all objects tracked by the collector, excluding the list returned. New in version 2.2.

set_threshold(threshold0[, threshold1[, threshold2]])

Set the garbage collection thresholds (the collection frequency). Setting threshold0 to zero disables collection

The GC classifies objects into three generations depending on how many collection sweeps they have survived. New objects are placed in the youngest generation (generation 0). If an object survives a collection it is moved into the next older generation. Since generation 2 is the oldest generation, objects in that generation remain there after a collection. In order to decide when to run, the collector keeps track of the number object allocations and deallocations since the last collection. When the number of allocations minus the number of deallocations exceeds *threshold0*, collection starts. Initially only generation 0 is examined. If generation 0 has been examined more than *threshold1* times since generation 1 has been examined, then generation 1 is examined as well. Similarly, *threshold2* controls the number of collections of generation 1 before collecting generation 2.

get_threshold()

Return the current collection thresholds as a tuple of (threshold0, threshold1, threshold1).

get_referrers(*objs)

Return the list of objects that directly refer to any of objs. This function will only locate those containers which support garbage collection; extension types which do refer to other objects but do not support garbage collection will not be found.

Note that objects which have already been dereferenced, but which live in cycles and have not yet been collected by the garbage collector can be listed among the resulting referrers. To get only currently live objects, call collect() before calling get_referrers().

Care must be taken when using objects returned by get_referrers() because some of them could still be under construction and hence in a temporarily invalid state. Avoid using get_referrers() for any purpose other than debugging.

New in version 2.2.

get_referents(*objs)

Return a list of objects directly referred to by any of the arguments. The referents returned are those objects visited by the arguments' C-level tp_traverse methods (if any), and may not be all objects actually directly reachable. tp_traverse methods are supported only by objects that support garbage collection, and are only required to visit objects that may be involved in a cycle. So, for example, if an integer is directly reachable from an argument, that integer object may or may not appear in the result list.

New in version 2.3.

The following variable is provided for read-only access (you can mutate its value but should not rebind it):

garbage

A list of objects which the collector found to be unreachable but could not be freed (uncollectable objects). By default, this list contains only objects with <code>__del__()</code> methods.\(^1\) Objects that have <code>__del__()</code> methods and are part of a reference cycle cause the entire reference cycle to be uncollectable, including objects not necessarily in the cycle but reachable only from it. Python doesn't collect such cycles automatically because, in general, it isn't possible for Python to guess a safe order in which to run the <code>__del__()</code> methods. If you know a safe order, you can force the issue by examining the <code>garbage</code> list, and explicitly breaking cycles due to your objects within the list. Note that these objects are kept alive even so by virtue of being in the <code>garbage</code> list, so they should be removed from <code>garbage</code> too. For example, after breaking cycles, do <code>del gc.garbage[:]</code> to empty the list. It's generally better to avoid the issue by not creating cycles containing objects with <code>__del__()</code> methods, and <code>garbage</code> can be examined in that case to verify that no such cycles are being created.

If DEBUG_SAVEALL is set, then all unreachable objects will be added to this list rather than freed.

¹Prior to Python 2.2, the list contained all instance objects in unreachable cycles, not only those with __del__() methods.

The following constants are provided for use with set_debug():

DEBUG_STATS

Print statistics during collection. This information can be useful when tuning the collection frequency.

DEBUG_COLLECTABLE

Print information on collectable objects found.

DEBUG_UNCOLLECTABLE

Print information of uncollectable objects found (objects which are not reachable but cannot be freed by the collector). These objects will be added to the garbage list.

DEBUG_INSTANCES

When DEBUG_COLLECTABLE or DEBUG_UNCOLLECTABLE is set, print information about instance objects found.

DEBUG_OBJECTS

When DEBUG_COLLECTABLE or DEBUG_UNCOLLECTABLE is set, print information about objects other than instance objects found.

DEBUG_SAVEALL

When set, all unreachable objects found will be appended to *garbage* rather than being freed. This can be useful for debugging a leaking program.

DEBUG_LEAK

The debugging flags necessary for the collector to print information about a leaking program (equal to DEBUG_COLLECTABLE | DEBUG_UNCOLLECTABLE | DEBUG_INSTANCES | DEBUG_OBJECTS | DEBUG_SAVEALL).

3.3 weakref — Weak references

New in version 2.1.

The weakref module allows the Python programmer to create weak references to objects.

In the following, the term referent means the object which is referred to by a weak reference.

A weak reference to an object is not enough to keep the object alive: when the only remaining references to a referent are weak references, garbage collection is free to destroy the referent and reuse its memory for something else. A primary use for weak references is to implement caches or mappings holding large objects, where it's desired that a large object not be kept alive solely because it appears in a cache or mapping. For example, if you have a number of large binary image objects, you may wish to associate a name with each. If you used a Python dictionary to map names to images, or images to names, the image objects would remain alive just because they appeared as values or keys in the dictionaries. The WeakKeyDictionary and WeakValueDictionary classes supplied by the weakref module are an alternative, using weak references to construct mappings that don't keep objects alive solely because they appear in the mapping objects. If, for example, an image object is a value in a WeakValueDictionary, then when the last remaining references to that image object are the weak references held by weak mappings, garbage collection can reclaim the object, and its corresponding entries in weak mappings are simply deleted.

WeakKeyDictionary and WeakValueDictionary use weak references in their implementation, setting up callback functions on the weak references that notify the weak dictionaries when a key or value has been reclaimed by garbage collection. Most programs should find that using one of these weak dictionary types is all they need — it's not usually necessary to create your own weak references directly. The low-level machinery used by the weak dictionary implementations is exposed by the weakref module for the benefit of advanced uses.

Not all objects can be weakly referenced; those objects which can include class instances, functions written in Python (but not in C), methods (both bound and unbound), sets, frozensets, file objects, generators, type objects, DBcursor objects from the baddb module, sockets, arrays, deques, and regular expression pattern objects. Changed in version 2.4: Added support for files, sockets, arrays, and patterns.

Several builtin types such as list and dict do not directly support weak references but can add support through subclassing:

```
class Dict(dict):
    pass

obj = Dict(red=1, green=2, blue=3) # this object is weak referencable
```

Extension types can easily be made to support weak references; see section 3.3.3, "Weak References in Extension Types," for more information.

```
class ref(object[, callback])
```

Return a weak reference to *object*. The original object can be retrieved by calling the reference object if the referent is still alive; if the referent is no longer alive, calling the reference object will cause None to be returned. If *callback* is provided and not None, it will be called when the object is about to be finalized; the weak reference object will be passed as the only parameter to the callback; the referent will no longer be available.

It is allowable for many weak references to be constructed for the same object. Callbacks registered for each weak reference will be called from the most recently registered callback to the oldest registered callback.

Exceptions raised by the callback will be noted on the standard error output, but cannot be propagated; they are handled in exactly the same way as exceptions raised from an object's __del__() method.

Weak references are hashable if the *object* is hashable. They will maintain their hash value even after the *object* was deleted. If hash() is called the first time only after the *object* was deleted, the call will raise TypeError.

Weak references support tests for equality, but not ordering. If the referents are still alive, two references have the same equality relationship as their referents (regardless of the *callback*). If either referent has been deleted, the references are equal only if the reference objects are the same object.

Changed in version 2.4: This is now a subclassable type rather than a factory function; it derives from object

ReferenceType

The type object for weak references objects.

ProxyType

The type object for proxies of objects which are not callable.

CallableProxyType

The type object for proxies of callable objects.

ProxyTypes

Sequence containing all the type objects for proxies. This can make it simpler to test if an object is a proxy without being dependent on naming both proxy types.

exception ReferenceError

Exception raised when a proxy object is used but the underlying object has been collected. This is the same as the standard ReferenceError exception.

See Also:

```
PEP 0205, "Weak References"
```

The proposal and rationale for this feature, including links to earlier implementations and information about similar features in other languages.

3.3.1 Weak Reference Objects

Weak reference objects have no attributes or methods, but do allow the referent to be obtained, if it still exists, by calling it:

```
>>> import weakref
>>> class Object:
... pass
...
>>> o = Object()
>>> r = weakref.ref(o)
>>> o2 = r()
>>> o is o2
True
```

If the referent no longer exists, calling the reference object returns None:

```
>>> del o, o2
>>> print r()
None
```

Testing that a weak reference object is still live should be done using the expression ref() is not None. Normally, application code that needs to use a reference object should follow this pattern:

```
# r is a weak reference object
o = r()
if o is None:
    # referent has been garbage collected
    print "Object has been deallocated; can't frobnicate."
else:
    print "Object is still live!"
    o.do_something_useful()
```

Using a separate test for "liveness" creates race conditions in threaded applications; another thread can cause a weak reference to become invalidated before the weak reference is called; the idiom shown above is safe in threaded applications as well as single-threaded applications.

Specialized versions of ref objects can be created through subclassing. This is used in the implementation of the WeakValueDictionary to reduce the memory overhead for each entry in the mapping. This may be most useful to associate additional information with a reference, but could also be used to insert additional processing on calls to retrieve the referent.

This example shows how a subclass of ref can be used to store additional information about an object and affect the value that's returned when the referent is accessed:

```
import weakref

class ExtendedRef(weakref.ref):
    def __init__(self, ob, callback=None, **annotations):
        super(ExtendedRef, self).__init__(ob, callback)
        self.__counter = 0
        for k, v in annotations.iteritems():
            setattr(self, k, v)

def __call__(self):
    """Return a pair containing the referent and the number of times the reference has been called.
    """
    ob = super(ExtendedRef, self).__call__()
    if ob is not None:
        self.__counter += 1
        ob = (ob, self.__counter)
    return ob
```

3.3.2 Example

This simple example shows how an application can use objects IDs to retrieve objects that it has seen before. The IDs of the objects can then be used in other data structures without forcing the objects to remain alive, but the objects can still be retrieved by ID if they do.

```
import weakref
_id2obj_dict = weakref.WeakValueDictionary()

def remember(obj):
    oid = id(obj)
    _id2obj_dict[oid] = obj
    return oid

def id2obj(oid):
    return _id2obj_dict[oid]
```

3.3.3 Weak References in Extension Types

One of the goals of the implementation is to allow any type to participate in the weak reference mechanism without incurring the overhead on those objects which do not benefit by weak referencing (such as numbers).

For an object to be weakly referencable, the extension must include a PyObject* field in the instance structure for the use of the weak reference mechanism; it must be initialized to NULL by the object's constructor. It must also set the tp_weaklistoffset field of the corresponding type object to the offset of the field. Also, it needs to add Py_TPFLAGS_HAVE_WEAKREFS to the tp_flags slot. For example, the instance type is defined with the following structure:

The statically-declared type object for instances is defined this way:

```
PyTypeObject PyInstance_Type = {
    PyObject_HEAD_INIT(&PyType_Type)
    0,
    "module.instance",
    /* Lots of stuff omitted for brevity... */
    Py_TPFLAGS_DEFAULT | Py_TPFLAGS_HAVE_WEAKREFS
                                                   /* tp_flags */
                                                 /* tp_doc */
    Ο,
                                                 /* tp_traverse */
    0,
                                                 /* tp_clear */
    0,
                                                 /* tp_richcompare */
    0,
    offsetof(PyInstanceObject, in_weakreflist), /* tp_weaklistoffset */
};
```

The type constructor is responsible for initializing the weak reference list to NULL:

```
static PyObject *
instance_new() {
    /* Other initialization stuff omitted for brevity */
    self->in_weakreflist = NULL;
    return (PyObject *) self;
}
```

The only further addition is that the destructor needs to call the weak reference manager to clear any weak references. This should be done before any other parts of the destruction have occurred, but is only required if the weak reference list is non-NULL:

```
static void
instance_dealloc(PyInstanceObject *inst)
{
    /* Allocate temporaries if needed, but do not begin
        destruction just yet.
    */
    if (inst->in_weakreflist != NULL)
        PyObject_ClearWeakRefs((PyObject *) inst);
    /* Proceed with object destruction normally. */
}
```

3.4 fpect1 — Floating point exception control

Most computers carry out floating point operations in conformance with the so-called IEEE-754 standard. On any real computer, some floating point operations produce results that cannot be expressed as a normal floating point value. For example, try

```
>>> import math
>>> math.exp(1000)
inf
>>> math.exp(1000) / math.exp(1000)
nan
```

(The example above will work on many platforms. DEC Alpha may be one exception.) "Inf" is a special, non-numeric value in IEEE-754 that stands for "infinity", and "nan" means "not a number." Note that, other than the non-numeric results, nothing special happened when you asked Python to carry out those calculations. That is in fact the default behaviour prescribed in the IEEE-754 standard, and if it works for you, stop reading now.

In some circumstances, it would be better to raise an exception and stop processing at the point where the faulty operation was attempted. The fpectl module is for use in that situation. It provides control over floating point units from several hardware manufacturers, allowing the user to turn on the generation of SIGFPE whenever any of the IEEE-754 exceptions Division by Zero, Overflow, or Invalid Operation occurs. In tandem with a pair of wrapper macros that are inserted into the C code comprising your python system, SIGFPE is trapped and converted into the Python FloatingPointError exception.

The fpectl module defines the following functions and may raise the given exception:

turnon_sigfpe()

Turn on the generation of SIGFPE, and set up an appropriate signal handler.

turnoff_sigfpe()

Reset default handling of floating point exceptions.

exception FloatingPointError

After turnon_sigfpe() has been executed, a floating point operation that raises one of the IEEE-754 exceptions Division by Zero, Overflow, or Invalid operation will in turn raise this standard Python exception.

3.4.1 Example

The following example demonstrates how to start up and test operation of the fpect1 module.

```
>>> import fpectl
>>> import fpetest
>>> fpectl.turnon_sigfpe()
>>> fpetest.test()
overflow
                PASS
FloatingPointError: Overflow
div by 0
                PASS
FloatingPointError: Division by zero
  [ more output from test elided ]
>>> import math
>>> math.exp(1000)
Traceback (most recent call last):
  File "<stdin>", line 1, in ?
FloatingPointError: in math_1
```

3.4.2 Limitations and other considerations

Setting up a given processor to trap IEEE-754 floating point errors currently requires custom code on a perarchitecture basis. You may have to modify fpect1 to control your particular hardware.

Conversion of an IEEE-754 exception to a Python exception requires that the wrapper macros Pyfpe_START_PROTECT and Pyfpe_END_PROTECT be inserted into your code in an appropriate fashion. Python itself has been modified to support the fpectl module, but many other codes of interest to numerical analysts have not.

The fpect1 module is not thread-safe.

See Also:

Some files in the source distribution may be interesting in learning more about how this module operates. The include file 'Include/pyfpe.h' discusses the implementation of this module at some length. 'Modules/fpetestmodule.c' gives several examples of use. Many additional examples can be found in 'Objects/floatobject.c'.

3.5 atexit — Exit handlers

New in version 2.0.

The atexit module defines a single function to register cleanup functions. Functions thus registered are automatically executed upon normal interpreter termination.

Note: the functions registered via this module are not called when the program is killed by a signal, when a Python fatal internal error is detected, or when os._exit() is called.

This is an alternate interface to the functionality provided by the sys.exitfunc variable.

Note: This module is unlikely to work correctly when used with other code that sets sys.exitfunc. In particular, other core Python modules are free to use atexit without the programmer's knowledge. Authors who use sys.exitfunc should convert their code to use atexit instead. The simplest way to convert code that sets sys.exitfunc is to import atexit and register the function that had been bound to sys.exitfunc.

```
register(func[, *args[, **kargs]])
```

Register *func* as a function to be executed at termination. Any optional arguments that are to be passed to *func* must be passed as arguments to register().

At normal program termination (for instance, if sys.exit() is called or the main module's execution completes), all functions registered are called in last in, first out order. The assumption is that lower level modules will normally be imported before higher level modules and thus must be cleaned up later.

If an exception is raised during execution of the exit handlers, a traceback is printed (unless SystemExit is raised) and the exception information is saved. After all exit handlers have had a chance to run the last exception to be raised is re-raised.

See Also:

Module readline (section 7.20):

Useful example of atexit to read and write readline history files.

3.5.1 atexit Example

The following simple example demonstrates how a module can initialize a counter from a file when it is imported and save the counter's updated value automatically when the program terminates without relying on the application making an explicit call into this module at termination.

```
try:
    _count = int(open("/tmp/counter").read())
except IOError:
    _count = 0

def incrcounter(n):
    global _count
    _count = _count + n

def savecounter():
    open("/tmp/counter", "w").write("%d" % _count)

import atexit
atexit.register(savecounter)
```

Positional and keyword arguments may also be passed to register() to be passed along to the registered function when it is called:

```
def goodbye(name, adjective):
    print 'Goodbye, %s, it was %s to meet you.' % (name, adjective)
import atexit
atexit.register(goodbye, 'Donny', 'nice')
# or:
atexit.register(goodbye, adjective='nice', name='Donny')
```

3.6 types — Names for built-in types

This module defines names for some object types that are used by the standard Python interpreter, but not for the types defined by various extension modules. Also, it does not include some of the types that arise during processing such the listiterator type. It is safe to use 'from types import *'— the module does not export any names besides the ones listed here. New names exported by future versions of this module will all end in 'Type'.

Typical use is for functions that do different things depending on their argument types, like the following:

```
from types import *
def delete(mylist, item):
    if type(item) is IntType:
        del mylist[item]
    else:
        mylist.remove(item)
```

Starting in Python 2.2, built-in factory functions such as int() and str() are also names for the corresponding types. This is now the preferred way to access the type instead of using the types module. Accordingly, the example above should be written as follows:

```
def delete(mylist, item):
    if isinstance(item, int):
        del mylist[item]
    else:
        mylist.remove(item)
```

The module defines the following names:

NoneType

The type of None.

TypeType

The type of type objects (such as returned by type ()).

BooleanType

The type of the bool values True and False; this is an alias of the built-in bool () function. New in version 2.3.

IntType

The type of integers (e.g. 1).

LongType

The type of long integers (e.g. 1L).

FloatType

The type of floating point numbers (e.g. 1.0).

ComplexType

The type of complex numbers (e.g. 1.0j). This is not defined if Python was built without complex number support.

StringType

The type of character strings (e.g. 'Spam').

UnicodeType

The type of Unicode character strings (e.g. u'Spam'). This is not defined if Python was built without Unicode support.

TupleType

The type of tuples (e.g. (1, 2, 3, 'Spam')).

ListType

The type of lists (e.g. [0, 1, 2, 3]).

DictType

The type of dictionaries (e.g. { 'Bacon': 1, 'Ham': 0}).

DictionaryType

An alternate name for DictType.

FunctionType

The type of user-defined functions and lambdas.

LambdaType

An alternate name for FunctionType.

GeneratorType

The type of generator-iterator objects, produced by calling a generator function. New in version 2.2.

CodeType

The type for code objects such as returned by compile().

ClassType

The type of user-defined classes.

InstanceType

The type of instances of user-defined classes.

MethodType

The type of methods of user-defined class instances.

UnboundMethodType

An alternate name for MethodType.

BuiltinFunctionType

The type of built-in functions like len() or sys.exit().

BuiltinMethodType

An alternate name for BuiltinFunction.

ModuleType

The type of modules.

FileType

The type of open file objects such as sys.stdout.

XRangeType

The type of range objects returned by xrange().

SliceType

The type of objects returned by slice().

EllipsisType

The type of Ellipsis.

TracebackType

The type of traceback objects such as found in sys.exc_traceback.

FrameType

The type of frame objects such as found in tb.tb_frame if tb is a traceback object.

BufferType

The type of buffer objects created by the buffer () function.

StringTypes

A sequence containing StringType and UnicodeType used to facilitate easier checking for any string object. Using this is more portable than using a sequence of the two string types constructed elsewhere since it only contains UnicodeType if it has been built in the running version of Python. For example: isinstance(s, types.StringTypes). New in version 2.2.

3.7 UserDict — Class wrapper for dictionary objects

The module defines a mixin, DictMixin, defining all dictionary methods for classes that already have a minimum mapping interface. This greatly simplifies writing classes that need to be substitutable for dictionaries (such as the shelve module).

This also module defines a class, UserDict, that acts as a wrapper around dictionary objects. The need for this class has been largely supplanted by the ability to subclass directly from dict (a feature that became available starting with Python version 2.2). Prior to the introduction of dict, the UserDict class was used to create dictionary-like sub-classes that obtained new behaviors by overriding existing methods or adding new ones.

The UserDict module defines the UserDict class and DictMixin:

class UserDict([initialdata])

Class that simulates a dictionary. The instance's contents are kept in a regular dictionary, which is accessible via the data attribute of UserDict instances. If *initialdata* is provided, data is initialized with its contents; note that a reference to *initialdata* will not be kept, allowing it be used for other purposes. **Note:** For backward compatibility, instances of UserDict are not iterable.

class IterableUserDict([initialdata])

Subclass of UserDict that supports direct iteration (e.g. for key in myDict).

In addition to supporting the methods and operations of mappings (see section 2.3.8), UserDict and IterableUserDict instances provide the following attribute:

data

A real dictionary used to store the contents of the UserDict class.

class DictMixin()

Mixin defining all dictionary methods for classes that already have a minimum dictionary interface including $__getitem__(), __setitem__(), __delitem__(), and keys().$

This mixin should be used as a superclass. Adding each of the above methods adds progressively more

functionality. For instance, defining all but __delitem__ will preclude only pop and popitem from the full interface.

In addition to the four base methods, progressively more efficiency comes with defining $_$ contains $_$ (), $_$ iter $_$ (), and iteritems().

Since the mixin has no knowledge of the subclass constructor, it does not define __init__() or copy().

3.8 UserList — Class wrapper for list objects

Note: This module is available for backward compatibility only. If you are writing code that does not need to work with versions of Python earlier than Python 2.2, please consider subclassing directly from the built-in list type.

This module defines a class that acts as a wrapper around list objects. It is a useful base class for your own list-like classes, which can inherit from them and override existing methods or add new ones. In this way one can add new behaviors to lists.

The UserList module defines the UserList class:

class UserList([list])

Class that simulates a list. The instance's contents are kept in a regular list, which is accessible via the data attribute of UserList instances. The instance's contents are initially set to a copy of *list*, defaulting to the empty list []. *list* can be either a regular Python list, or an instance of UserList (or a subclass).

In addition to supporting the methods and operations of mutable sequences (see section 2.3.6), UserList instances provide the following attribute:

data

A real Python list object used to store the contents of the UserList class.

Subclassing requirements: Subclasses of UserList are expect to offer a constructor which can be called with either no arguments or one argument. List operations which return a new sequence attempt to create an instance of the actual implementation class. To do so, it assumes that the constructor can be called with a single parameter, which is a sequence object used as a data source.

If a derived class does not wish to comply with this requirement, all of the special methods supported by this class will need to be overridden; please consult the sources for information about the methods which need to be provided in that case.

Changed in version 2.0: Python versions 1.5.2 and 1.6 also required that the constructor be callable with no parameters, and offer a mutable data attribute. Earlier versions of Python did not attempt to create instances of the derived class.

3.9 UserString — Class wrapper for string objects

Note: This UserString class from this module is available for backward compatibility only. If you are writing code that does not need to work with versions of Python earlier than Python 2.2, please consider subclassing directly from the built-in str type instead of using UserString (there is no built-in equivalent to MutableString).

This module defines a class that acts as a wrapper around string objects. It is a useful base class for your own string-like classes, which can inherit from them and override existing methods or add new ones. In this way one can add new behaviors to strings.

It should be noted that these classes are highly inefficient compared to real string or Unicode objects; this is especially the case for MutableString.

The UserString module defines the following classes:

class UserString([sequence])

Class that simulates a string or a Unicode string object. The instance's content is kept in a regular string or Unicode string object, which is accessible via the data attribute of UserString instances. The instance's

contents are initially set to a copy of *sequence*. *sequence* can be either a regular Python string or Unicode string, an instance of UserString (or a subclass) or an arbitrary sequence which can be converted into a string using the built-in str() function.

class MutableString([sequence])

This class is derived from the UserString above and redefines strings to be *mutable*. Mutable strings can't be used as dictionary keys, because dictionaries require *immutable* objects as keys. The main intention of this class is to serve as an educational example for inheritance and necessity to remove (override) the __hash__() method in order to trap attempts to use a mutable object as dictionary key, which would be otherwise very error prone and hard to track down.

In addition to supporting the methods and operations of string and Unicode objects (see section 2.3.6, "String Methods"), UserString instances provide the following attribute:

data

A real Python string or Unicode object used to store the content of the UserString class.

3.10 operator — Standard operators as functions.

The operator module exports a set of functions implemented in C corresponding to the intrinsic operators of Python. For example, operator.add(x, y) is equivalent to the expression x+y. The function names are those used for special class methods; variants without leading and trailing '__' are also provided for convenience.

The functions fall into categories that perform object comparisons, logical operations, mathematical operations, sequence operations, and abstract type tests.

The object comparison functions are useful for all objects, and are named after the rich comparison operators they support:

```
lt(a, b)
le(a, b)
eq(a, b)
ne(a, b)
ge(a, b)
gt(a, b)
__lt___(a, b)
__le___(a, b)
__ne___(a, b)
__ge___(a, b)
__gt___(a, b)
```

Perform "rich comparisons" between a and b. Specifically, lt(a, b) is equivalent to a < b, le(a, b) is equivalent to a <= b, eq(a, b) is equivalent to a == b, ne(a, b) is equivalent to a != b, gt(a, b) is equivalent to a >= b. Note that unlike the built-in cmp(), these functions can return any value, which may or may not be interpretable as a Boolean value. See the *Python Reference Manual* for more information about rich comparisons. New in version 2.2.

The logical operations are also generally applicable to all objects, and support truth tests, identity tests, and boolean operations:

```
not_(o)
__not__(o)
    Return the outcome of not o. (Note that there is no __not__() method for object instances; only the interpreter core defines this operation. The result is affected by the __nonzero__() and __len__() methods.)

truth(o)
    Return True if o is true, and False otherwise. This is equivalent to using the bool constructor.

is_(a, b)
    Return a is b. Tests object identity. New in version 2.3.
```

```
Return a is not b. Tests object identity. New in version 2.3.
The mathematical and bitwise operations are the most numerous:
__abs__(o)
     Return the absolute value of o.
add(a, b)
__add__(a, b)
     Return a + b, for a and b numbers.
and_{a}(a, b)
__and__(a, b)
     Return the bitwise and of a and b.
div(a, b)
__div__(a, b)
     Return a / b when __future__.division is not in effect. This is also known as "classic" division.
floordiv(a, b)
__floordiv__(a, b)
     Return a / / b. New in version 2.2.
inv(o)
invert(o)
__inv__(o)
__invert__(o)
     Return the bitwise inverse of the number o. This is equivalent to \tilde{o}. The names invert() and
     __invert__() were added in Python 2.0.
lshift(a, b)
__lshift__(a, b)
     Return a shifted left by b.
mod(a, b)
__mod__(a, b)
     Return a \% b.
mul(a, b)
__mul__(a, b)
     Return a * b, for a and b numbers.
neg(o)
__neg__(o)
     Return o negated.
or_{-}(a, b)
__or__(a, b)
     Return the bitwise or of a and b.
pos(o)
__pos__(o)
     Return o positive.
pow(a, b)
__pow__(a, b)
     Return a * * b, for a and b numbers. New in version 2.3.
rshift(a, b)
__rshift__(a, b)
     Return a shifted right by b.
sub(a, b)
__sub__(a, b)
```

is_not(a, b)

```
Return a - b.
truediv(a, b)
__truediv__(a, b)
     Return a / b when __future__.division is in effect. This is also known as division. New in version
xor(a, b)
__xor__(a, b)
     Return the bitwise exclusive or of a and b.
Operations which work with sequences include:
concat(a, b)
__concat__(a, b)
     Return a + b for a and b sequences.
contains(a, b)
\_contains\_(a, b)
     Return the outcome of the test b in a. Note the reversed operands. The name __contains__() was
     added in Python 2.0.
countOf(a, b)
     Return the number of occurrences of b in a.
delitem(a, b)
__delitem__(a, b)
     Remove the value of a at index b.
delslice(a, b, c)
__delslice__(a, b, c)
     Delete the slice of a from index b to index c-1.
getitem(a, b)
\_getitem\_(a, b)
     Return the value of a at index b.
getslice(a, b, c)
__getslice__(a, b, c)
     Return the slice of a from index b to index c-1.
indexOf(a, b)
     Return the index of the first of occurrence of b in a.
repeat(a, b)
__repeat__(a, b)
     Return a * b where a is a sequence and b is an integer.
sequenceIncludes(...)
     Deprecated since release 2.0. Use contains () instead.
     Alias for contains().
setitem(a, b, c)
__setitem__(a, b, c)
     Set the value of a at index b to c.
setslice(a, b, c, v)
__setslice__(a, b, c, v)
     Set the slice of a from index b to index c-1 to the sequence v.
```

The operator module also defines a few predicates to test the type of objects. **Note:** Be careful not to misinterpret the results of these functions; only isCallable() has any measure of reliability with instance objects. For example:

```
>>> class C:
... pass
...
>>> import operator
>>> o = C()
>>> operator.isMappingType(o)
```

isCallable(o)

Deprecated since release 2.0. Use the callable() built-in function instead.

Returns true if the object o can be called like a function, otherwise it returns false. True is returned for functions, bound and unbound methods, class objects, and instance objects which support the $__call__()$ method.

isMappingType(o)

Returns true if the object o supports the mapping interface. This is true for dictionaries and all instance objects defining __getitem__. Warning: There is no reliable way to test if an instance supports the complete mapping protocol since the interface itself is ill-defined. This makes this test less useful than it otherwise might be.

isNumberType(o)

Returns true if the object *o* represents a number. This is true for all numeric types implemented in C. **Warning:** There is no reliable way to test if an instance supports the complete numeric interface since the interface itself is ill-defined. This makes this test less useful than it otherwise might be.

isSequenceType(o)

Returns true if the object o supports the sequence protocol. This returns true for all objects which define sequence methods in C, and for all instance objects defining __getitem__. Warning: There is no reliable way to test if an instance supports the complete sequence interface since the interface itself is ill-defined. This makes this test less useful than it otherwise might be.

Example: Build a dictionary that maps the ordinals from 0 to 255 to their character equivalents.

```
>>> import operator
>>> d = {}
>>> keys = range(256)
>>> vals = map(chr, keys)
>>> map(operator.setitem, [d]*len(keys), keys, vals)
```

The operator module also defines tools for generalized attribute and item lookups. These are useful for making fast field extractors as arguments for map(), sorted(), itertools.groupby(), or other functions that expect a function argument.

attrgetter(attr)

Return a callable object that fetches *attr* from its operand. After, 'f=attrgetter('name')', the call 'f(b)' returns 'b.name'. New in version 2.4.

$\verb|itemgetter|(item|)$

Return a callable object that fetches *item* from its operand. After, 'f=itemgetter(2)', the call 'f(b)' returns 'b[2]'. New in version 2.4.

Examples:

```
>>> from operator import *
>>> inventory = [('apple', 3), ('banana', 2), ('pear', 5), ('orange', 1)]
>>> getcount = itemgetter(1)
>>> map(getcount, inventory)
[3, 2, 5, 1]
>>> sorted(inventory, key=getcount)
[('orange', 1), ('banana', 2), ('apple', 3), ('pear', 5)]
```

3.10.1 Mapping Operators to Functions

This table shows how abstract operations correspond to operator symbols in the Python syntax and the functions in the operator module.

Operation	Syntax	Function
Addition	a + b	add(a, b)
Concatenation	seq1 + seq2	concat(seq1, seq2)
Containment Test	o in seq	contains(seq, o)
Division	a / b	div(a, b) # withoutfuturedivision
Division	a / b	truediv(a, b) # withfuturedivision
Division	a // b	floordiv(a, b)
Bitwise And	a & b	$and_a(a, b)$
Bitwise Exclusive Or	a ^ b	xor(a, b)
Bitwise Inversion	~ a	invert(a)
Bitwise Or	$a \mid b$	$or_{a}(a, b)$
Exponentiation	a ** b	pow(a, b)
Identity	a is b	$is_{-}(a, b)$
Identity	a is not b	$is_not(a, b)$
Indexed Assignment	o[k] = v	setitem(o, k, v)
Indexed Deletion	del o[k]	delitem(o, k)
Indexing	o[k]	getitem(o, k)
Left Shift	$a \ll b$	lshift(a, b)
Modulo	a % b	mod(a, b)
Multiplication	a * b	mul(a, b)
Negation (Arithmetic)	- a	neg(a)
Negation (Logical)	not a	$not_{-}(a)$
Right Shift	$a \gg b$	rshift(a, b)
Sequence Repitition	seq * i	repeat(seq, i)
Slice Assignment	seq[i:j] = values	setslice(seq, i, j, values)
Slice Deletion	del seq[i:j]	delslice(seq, i, j)
Slicing	seq[i:j]	getslice(seq, i, j)
String Formatting	s % o	mod(s, o)
Subtraction	a - b	sub(a, b)
Truth Test	o	truth(o)
Ordering	a < b	lt(a, b)
Ordering	$a \le b$	le(a, b)
Equality	a == b	eq(a, b)
Difference	a != b	ne(a, b)
Ordering	a >= b	ge(a, b)
Ordering	a > b	gt(a, b)

3.11 inspect — Inspect live objects

New in version 2.1.

The inspect module provides several useful functions to help get information about live objects such as modules, classes, methods, functions, tracebacks, frame objects, and code objects. For example, it can help you examine the contents of a class, retrieve the source code of a method, extract and format the argument list for a function, or get all the information you need to display a detailed traceback.

There are four main kinds of services provided by this module: type checking, getting source code, inspecting classes and functions, and examining the interpreter stack.

3.11.1 Types and members

The <code>getmembers()</code> function retrieves the members of an object such as a class or module. The eleven functions whose names begin with "is" are mainly provided as convenient choices for the second argument to <code>getmembers()</code>. They also help you determine when you can expect to find the following special attributes:

Type	Attribute	Description	Notes
module	doc	documentation string	
	file	filename (missing for built-in modules)	
class	doc	documentation string	
	module	name of module in which this class was defined	
method	doc	documentation string	
	name	name with which this method was defined	
	im_class	class object that asked for this method	(1)
	im_func	function object containing implementation of method	
	im_self	instance to which this method is bound, or None	
function	doc	documentation string	
1011011011	name	name with which this function was defined	
	func_code	code object containing compiled function bytecode	
	func_defaults	tuple of any default values for arguments	
	func_doc	(same asdoc)	
	func_globals	global namespace in which this function was defined	
	func_name	(same asname)	
traceback	tb_frame	frame object at this level	
пассыск	tb_lasti	index of last attempted instruction in bytecode	
	tb_lineno	current line number in Python source code	
	tb_next	next inner traceback object (called by this level)	
frame	f_back	next outer frame object (this frame's caller)	
Irame	f_builtins	built-in namespace seen by this frame	
	f code	code object being executed in this frame	
	f_exc_traceback	traceback if raised in this frame, or None	
		·	
	f_exc_type f_exc_value	exception type if raised in this frame, or None	
		exception value if raised in this frame, or None	
	f_globals f_lasti	global namespace seen by this frame	
		index of last attempted instruction in bytecode	
	f_lineno f_locals	current line number in Python source code	
	1	local namespace seen by this frame	
	f_restricted	0 or 1 if frame is in restricted execution mode	
1.	f_trace	tracing function for this frame, or None	
code	co_argcount	number of arguments (not including * or ** args)	
	co_code	string of raw compiled bytecode	
	co_consts	tuple of constants used in the bytecode	
	co_filename	name of file in which this code object was created	
	co_firstlineno	number of first line in Python source code	
	co_flags	bitmap: 1=optimized 2=newlocals 4=*arg 8=**arg	
	co_lnotab	encoded mapping of line numbers to bytecode indices	
	co_name	name with which this code object was defined	
	co_names	tuple of names of local variables	
	co_nlocals	number of local variables	
	co_stacksize	virtual machine stack space required	
	co_varnames	tuple of names of arguments and local variables	
builtin	doc	documentation string	
	name	original name of this function or method	
	self	instance to which a method is bound, or None	

Note:

(1) Changed in version 2.2: im_class used to refer to the class that defined the method.

getmembers(object[, predicate])

Return all the members of an object in a list of (name, value) pairs sorted by name. If the optional *predicate* argument is supplied, only members for which the predicate returns a true value are included.

getmoduleinfo(path)

Return a tuple of values that describe how Python will interpret the file identified by path if it is a module,

or None if it would not be identified as a module. The return tuple is (name, suffix, mode, mtype), where name is the name of the module without the name of any enclosing package, suffix is the trailing part of the file name (which may not be a dot-delimited extension), mode is the open() mode that would be used ('r' or 'rb'), and mtype is an integer giving the type of the module. mtype will have a value which can be compared to the constants defined in the imp module; see the documentation for that module for more information on module types.

getmodulename(path)

Return the name of the module named by the file *path*, without including the names of enclosing packages. This uses the same algorithm as the interpreter uses when searching for modules. If the name cannot be matched according to the interpreter's rules, None is returned.

ismodule(object)

Return true if the object is a module.

isclass(object)

Return true if the object is a class.

ismethod(object)

Return true if the object is a method.

isfunction(object)

Return true if the object is a Python function or unnamed (lambda) function.

istraceback(object)

Return true if the object is a traceback.

isframe(object)

Return true if the object is a frame.

iscode(object)

Return true if the object is a code.

isbuiltin(object)

Return true if the object is a built-in function.

isroutine(object)

Return true if the object is a user-defined or built-in function or method.

ismethoddescriptor(object)

Return true if the object is a method descriptor, but not if ismethod() or isclass() or isfunction() are true.

This is new as of Python 2.2, and, for example, is true of int.__add__. An object passing this test has a __get__ attribute but not a __set__ attribute, but beyond that the set of attributes varies. __name__ is usually sensible, and __doc__ often is.

Methods implemented via descriptors that also pass one of the other tests return false from the ismethod-descriptor() test, simply because the other tests promise more – you can, e.g., count on having the im_func attribute (etc) when an object passes ismethod().

isdatadescriptor(object)

Return true if the object is a data descriptor.

Data descriptors have both a __get__ and a __set__ attribute. Examples are properties (defined in Python) and getsets and members (defined in C). Typically, data descriptors will also have __name__ and __doc__ attributes (properties, getsets, and members have both of these attributes), but this is not guaranteed. New in version 2.3.

3.11.2 Retrieving source code

getdoc(object)

Get the documentation string for an object. All tabs are expanded to spaces. To clean up docstrings that are indented to line up with blocks of code, any whitespace than can be uniformly removed from the second line onwards is removed.

getcomments(object)

Return in a single string any lines of comments immediately preceding the object's source code (for a class, function, or method), or at the top of the Python source file (if the object is a module).

getfile(object)

Return the name of the (text or binary) file in which an object was defined. This will fail with a TypeError if the object is a built-in module, class, or function.

getmodule(object)

Try to guess which module an object was defined in.

getsourcefile(object)

Return the name of the Python source file in which an object was defined. This will fail with a TypeError if the object is a built-in module, class, or function.

getsourcelines(object)

Return a list of source lines and starting line number for an object. The argument may be a module, class, method, function, traceback, frame, or code object. The source code is returned as a list of the lines corresponding to the object and the line number indicates where in the original source file the first line of code was found. An IOError is raised if the source code cannot be retrieved.

getsource(object)

Return the text of the source code for an object. The argument may be a module, class, method, function, traceback, frame, or code object. The source code is returned as a single string. An IOError is raised if the source code cannot be retrieved.

3.11.3 Classes and functions

getclasstree(classes[, unique])

Arrange the given list of classes into a hierarchy of nested lists. Where a nested list appears, it contains classes derived from the class whose entry immediately precedes the list. Each entry is a 2-tuple containing a class and a tuple of its base classes. If the *unique* argument is true, exactly one entry appears in the returned structure for each class in the given list. Otherwise, classes using multiple inheritance and their descendants will appear multiple times.

getargspec(func)

Get the names and default values of a function's arguments. A tuple of four things is returned: (args, varargs, varkw, defaults). args is a list of the argument names (it may contain nested lists). varargs and varkw are the names of the * and ** arguments or None. defaults is a tuple of default argument values or None if there are no default arguments; if this tuple has n elements, they correspond to the last n elements listed in args.

getargvalues(frame)

Get information about arguments passed into a particular frame. A tuple of four things is returned: (args, varargs, varkw, locals). args is a list of the argument names (it may contain nested lists). varargs and varkw are the names of the * and * * arguments or None. locals is the locals dictionary of the given frame.

- **formatargspec** (args[, varargs, varkw, defaults, argformat, varargsformat, varkwformat, defaultformat])

 Format a pretty argument spec from the four values returned by getargspec(). The other four arguments are the corresponding optional formatting functions that are called to turn names and values into strings.
- **formatargvalues** (args[, varargs, varkw, locals, argformat, varargsformat, varkwformat, valueformat])

 Format a pretty argument spec from the four values returned by getargvalues(). The other four arguments are the corresponding optional formatting functions that are called to turn names and values into strings.

getmro(cls)

Return a tuple of class cls's base classes, including cls, in method resolution order. No class appears more than once in this tuple. Note that the method resolution order depends on cls's type. Unless a very peculiar user-defined metatype is in use, cls will be the first element of the tuple.

3.11.4 The interpreter stack

When the following functions return "frame records," each record is a tuple of six items: the frame object, the filename, the line number of the current line, the function name, a list of lines of context from the source code, and the index of the current line within that list.

Warning: Keeping references to frame objects, as found in the first element of the frame records these functions return, can cause your program to create reference cycles. Once a reference cycle has been created, the lifespan of all objects which can be accessed from the objects which form the cycle can become much longer even if Python's optional cycle detector is enabled. If such cycles must be created, it is important to ensure they are explicitly broken to avoid the delayed destruction of objects and increased memory consumption which occurs.

Though the cycle detector will catch these, destruction of the frames (and local variables) can be made deterministic by removing the cycle in a finally clause. This is also important if the cycle detector was disabled when Python was compiled or using gc.disable(). For example:

```
def handle_stackframe_without_leak():
    frame = inspect.currentframe()
    try:
        # do something with the frame
    finally:
        del frame
```

The optional *context* argument supported by most of these functions specifies the number of lines of context to return, which are centered around the current line.

getframeinfo(frame[, context])

Get information about a frame or traceback object. A 5-tuple is returned, the last five elements of the frame's frame record.

getouterframes(frame[, context])

Get a list of frame records for a frame and all outer frames. These frames represent the calls that lead to the creation of *frame*. The first entry in the returned list represents *frame*; the last entry represents the outermost call on *frame*'s stack.

getinnerframes(traceback[, context])

Get a list of frame records for a traceback's frame and all inner frames. These frames represent calls made as a consequence of *frame*. The first entry in the list represents *traceback*; the last entry represents where the exception was raised.

currentframe()

Return the frame object for the caller's stack frame.

```
stack([context])
```

Return a list of frame records for the caller's stack. The first entry in the returned list represents the caller; the last entry represents the outermost call on the stack.

```
trace([context])
```

Return a list of frame records for the stack between the current frame and the frame in which an exception currently being handled was raised in. The first entry in the list represents the caller; the last entry represents where the exception was raised.

3.12 traceback — Print or retrieve a stack traceback

This module provides a standard interface to extract, format and print stack traces of Python programs. It exactly mimics the behavior of the Python interpreter when it prints a stack trace. This is useful when you want to print stack traces under program control, such as in a "wrapper" around the interpreter.

The module uses traceback objects — this is the object type that is stored in the variables sys.exc_traceback (deprecated) and sys.last_traceback and returned as the third item from sys.exc_info().

The module defines the following functions:

print_tb(traceback[, limit[, file]])

Print up to *limit* stack trace entries from *traceback*. If *limit* is omitted or None, all entries are printed. If *file* is omitted or None, the output goes to sys.stderr; otherwise it should be an open file or file-like object to receive the output.

print_exception(type, value, traceback[, limit[, file]])

Print exception information and up to *limit* stack trace entries from *traceback* to *file*. This differs from print_tb() in the following ways: (1) if *traceback* is not None, it prints a header 'Traceback (most recent call last):'; (2) it prints the exception *type* and *value* after the stack trace; (3) if *type* is SyntaxError and *value* has the appropriate format, it prints the line where the syntax error occurred with a caret indicating the approximate position of the error.

print_exc([limit[, file]])

This is a shorthand for print_exception(sys.exc_type, sys.exc_value, sys.exc_traceback, *limit*, *file*). (In fact, it uses sys.exc_info() to retrieve the same information in a thread-safe way instead of using the deprecated variables.)

format_exc([limit[, file]])

This is like print_exc(limit) but returns a string instead of printing to a file. New in version 2.4.

print_last([limit[, file]])

This is a shorthand for print_exception(sys.last_type, sys.last_value, sys.last_traceback, limit, file).

$print_stack([f[, limit[, file]]])$

This function prints a stack trace from its invocation point. The optional f argument can be used to specify an alternate stack frame to start. The optional *limit* and *file* arguments have the same meaning as for print_exception().

extract_tb(traceback[, limit])

Return a list of up to *limit* "pre-processed" stack trace entries extracted from the traceback object *traceback*. It is useful for alternate formatting of stack traces. If *limit* is omitted or None, all entries are extracted. A "pre-processed" stack trace entry is a quadruple (*filename*, *line number*, *function name*, *text*) representing the information that is usually printed for a stack trace. The *text* is a string with leading and trailing whitespace stripped; if the source is not available it is None.

$extract_stack([f[, limit]])$

Extract the raw traceback from the current stack frame. The return value has the same format as for extract_tb(). The optional f and limit arguments have the same meaning as for print_stack().

format_list(list)

Given a list of tuples as returned by extract_tb() or extract_stack(), return a list of strings ready for printing. Each string in the resulting list corresponds to the item with the same index in the argument list. Each string ends in a newline; the strings may contain internal newlines as well, for those items whose source text line is not None.

format_exception_only(type, value)

Format the exception part of a traceback. The arguments are the exception type and value such as given by sys.last_type and sys.last_value. The return value is a list of strings, each ending in a newline. Normally, the list contains a single string; however, for SyntaxError exceptions, it contains several lines that (when printed) display detailed information about where the syntax error occurred. The message indicating which exception occurred is the always last string in the list.

format_exception(type, value, tb[, limit])

Format a stack trace and the exception information. The arguments have the same meaning as the corresponding arguments to print_exception(). The return value is a list of strings, each ending in a newline and some containing internal newlines. When these lines are concatenated and printed, exactly the same text is printed as does print_exception().

format_tb(tb[, limit])

A shorthand for format_list(extract_tb(tb, limit)).

$format_stack([f[, limit]])$

A shorthand for format_list(extract_stack(f, limit)).

tb_lineno(tb)

This function returns the current line number set in the traceback object. This function was necessary because in versions of Python prior to 2.3 when the **-O** flag was passed to Python the *tb*.tb_lineno was not updated correctly. This function has no use in versions past 2.3.

3.12.1 Traceback Example

This simple example implements a basic read-eval-print loop, similar to (but less useful than) the standard Python interactive interpreter loop. For a more complete implementation of the interpreter loop, refer to the code module.

```
import sys, traceback

def run_user_code(envdir):
    source = raw_input(">>> ")
    try:
        exec source in envdir
    except:
        print "Exception in user code:"
        print '-'*60
        traceback.print_exc(file=sys.stdout)
        print '-'*60

envdir = {}
while 1:
    run_user_code(envdir)
```

3.13 linecache — Random access to text lines

The linecache module allows one to get any line from any file, while attempting to optimize internally, using a cache, the common case where many lines are read from a single file. This is used by the traceback module to retrieve source lines for inclusion in the formatted traceback.

The linecache module defines the following functions:

```
getline(filename, lineno)
```

Get line *lineno* from file named *filename*. This function will never throw an exception — it will return '' on errors (the terminating newline character will be included for lines that are found).

If a file named filename is not found, the function will look for it in the module search path, sys.path.

clearcache()

Clear the cache. Use this function if you no longer need lines from files previously read using getline().

```
checkcache([filename])
```

Check the cache for validity. Use this function if files in the cache may have changed on disk, and you require the updated version. If *filename* is omitted, it will check the whole cache entries.

Example:

```
>>> import linecache
>>> linecache.getline('/etc/passwd', 4)
'sys:x:3:3:sys:/dev:/bin/sh\n'
```

3.14 pickle — Python object serialization

The pickle module implements a fundamental, but powerful algorithm for serializing and de-serializing a Python object structure. "Pickling" is the process whereby a Python object hierarchy is converted into a byte stream, and "unpickling" is the inverse operation, whereby a byte stream is converted back into an object hierarchy. Pickling (and unpickling) is alternatively known as "serialization", "marshalling," or "flattening", however, to avoid confusion, the terms used here are "pickling" and "unpickling".

This documentation describes both the pickle module and the cPickle module.

3.14.1 Relationship to other Python modules

The pickle module has an optimized cousin called the cPickle module. As its name implies, cPickle is written in C, so it can be up to 1000 times faster than pickle. However it does not support subclassing of the Pickler() and Unpickler() classes, because in cPickle these are functions, not classes. Most applications have no need for this functionality, and can benefit from the improved performance of cPickle. Other than that, the interfaces of the two modules are nearly identical; the common interface is described in this manual and differences are pointed out where necessary. In the following discussions, we use the term "pickle" to collectively describe the pickle and cPickle modules.

The data streams the two modules produce are guaranteed to be interchangeable.

Python has a more primitive serialization module called marshal, but in general pickle should always be the preferred way to serialize Python objects. marshal exists primarily to support Python's '.pyc' files.

The pickle module differs from marshal several significant ways:

- The pickle module keeps track of the objects it has already serialized, so that later references to the same object won't be serialized again. marshal doesn't do this.
 - This has implications both for recursive objects and object sharing. Recursive objects are objects that contain references to themselves. These are not handled by marshal, and in fact, attempting to marshal recursive objects will crash your Python interpreter. Object sharing happens when there are multiple references to the same object in different places in the object hierarchy being serialized. pickle stores such objects only once, and ensures that all other references point to the master copy. Shared objects remain shared, which can be very important for mutable objects.
- marshal cannot be used to serialize user-defined classes and their instances. pickle can save and restore class instances transparently, however the class definition must be importable and live in the same module as when the object was stored.
- The marshal serialization format is not guaranteed to be portable across Python versions. Because its primary job in life is to support '.pyc' files, the Python implementers reserve the right to change the serialization format in non-backwards compatible ways should the need arise. The pickle serialization format is guaranteed to be backwards compatible across Python releases.

Warning: The pickle module is not intended to be secure against erroneous or maliciously constructed data. Never unpickle data received from an untrusted or unauthenticated source.

Note that serialization is a more primitive notion than persistence; although pickle reads and writes file objects, it does not handle the issue of naming persistent objects, nor the (even more complicated) issue of concurrent access to persistent objects. The pickle module can transform a complex object into a byte stream and it can transform the byte stream into an object with the same internal structure. Perhaps the most obvious thing to do with these byte streams is to write them onto a file, but it is also conceivable to send them across a network or store them in a database. The module shelve provides a simple interface to pickle and unpickle objects on DBM-style database files.

²Don't confuse this with the marshal module

3.14.2 Data stream format

The data format used by pickle is Python-specific. This has the advantage that there are no restrictions imposed by external standards such as XDR (which can't represent pointer sharing); however it means that non-Python programs may not be able to reconstruct pickled Python objects.

By default, the pickle data format uses a printable ASCII representation. This is slightly more voluminous than a binary representation. The big advantage of using printable ASCII (and of some other characteristics of pickle's representation) is that for debugging or recovery purposes it is possible for a human to read the pickled file with a standard text editor.

There are currently 3 different protocols which can be used for pickling.

- Protocol version 0 is the original ASCII protocol and is backwards compatible with earlier versions of Python.
- Protocol version 1 is the old binary format which is also compatible with earlier versions of Python.
- Protocol version 2 was introduced in Python 2.3. It provides much more efficient pickling of new-style classes.

Refer to PEP 307 for more information.

If a *protocol* is not specified, protocol 0 is used. If *protocol* is specified as a negative value or HIGHEST_PROTOCOL, the highest protocol version available will be used.

Changed in version 2.3: The *bin* parameter is deprecated and only provided for backwards compatibility. You should use the *protocol* parameter instead.

A binary format, which is slightly more efficient, can be chosen by specifying a true value for the bin argument to the Pickler constructor or the dump() and dumps() functions. A protocol version i = 1 implies use of a binary format.

3.14.3 Usage

To serialize an object hierarchy, you first create a pickler, then you call the pickler's dump() method. To deserialize a data stream, you first create an unpickler, then you call the unpickler's load() method. The pickle module provides the following constant:

HIGHEST_PROTOCOL

The highest protocol version available. This value can be passed as a *protocol* value. New in version 2.3.

The pickle module provides the following functions to make this process more convenient:

dump(obj, file[, protocol[, bin]])

Write a pickled representation of obj to the open file object file. This is equivalent to Pickler (file, protocol, bin). dump (obj).

If the *protocol* parameter is omitted, protocol 0 is used. If *protocol* is specified as a negative value or HIGHEST_PROTOCOL, the highest protocol version will be used.

Changed in version 2.3: The *protocol* parameter was added. The *bin* parameter is deprecated and only provided for backwards compatibility. You should use the *protocol* parameter instead.

If the optional *bin* argument is true, the binary pickle format is used; otherwise the (less efficient) text pickle format is used (for backwards compatibility, this is the default).

file must have a write() method that accepts a single string argument. It can thus be a file object opened for writing, a StringIO object, or any other custom object that meets this interface.

load(file)

Read a string from the open file object *file* and interpret it as a pickle data stream, reconstructing and returning the original object hierarchy. This is equivalent to Unpickler(*file*).load().

file must have two methods, a read() method that takes an integer argument, and a readline() method that requires no arguments. Both methods should return a string. Thus file can be a file object opened for reading, a StringIO object, or any other custom object that meets this interface.

This function automatically determines whether the data stream was written in binary mode or not.

$\mathtt{dumps}(obj[,protocol[,bin]])$

Return the pickled representation of the object as a string, instead of writing it to a file.

If the *protocol* parameter is omitted, protocol 0 is used. If *protocol* is specified as a negative value or HIGHEST_PROTOCOL, the highest protocol version will be used.

Changed in version 2.3: The *protocol* parameter was added. The *bin* parameter is deprecated and only provided for backwards compatibility. You should use the *protocol* parameter instead.

If the optional *bin* argument is true, the binary pickle format is used; otherwise the (less efficient) text pickle format is used (this is the default).

loads(string)

Read a pickled object hierarchy from a string. Characters in the string past the pickled object's representation are ignored.

The pickle module also defines three exceptions:

exception PickleError

A common base class for the other exceptions defined below. This inherits from Exception.

exception PicklingError

This exception is raised when an unpicklable object is passed to the dump () method.

exception UnpicklingError

This exception is raised when there is a problem unpickling an object. Note that other exceptions may also be raised during unpickling, including (but not necessarily limited to) AttributeError, EOFError, ImportError, and IndexError.

The pickle module also exports two callables³, Pickler and Unpickler:

class Pickler(file[, protocol[, bin]])

This takes a file-like object to which it will write a pickle data stream.

If the *protocol* parameter is omitted, protocol 0 is used. If *protocol* is specified as a negative value, the highest protocol version will be used.

Changed in version 2.3: The *bin* parameter is deprecated and only provided for backwards compatibility. You should use the *protocol* parameter instead.

Optional *bin* if true, tells the pickler to use the more efficient binary pickle format, otherwise the ASCII format is used (this is the default).

file must have a write() method that accepts a single string argument. It can thus be an open file object, a StringIO object, or any other custom object that meets this interface.

Pickler objects define one (or two) public methods:

dump(obi)

Write a pickled representation of *obj* to the open file object given in the constructor. Either the binary or ASCII format will be used, depending on the value of the *bin* flag passed to the constructor.

clear_memo()

Clears the pickler's "memo". The memo is the data structure that remembers which objects the pickler has already seen, so that shared or recursive objects pickled by reference and not by value. This method is useful when re-using picklers.

Note: Prior to Python 2.3, clear_memo() was only available on the picklers created by cPickle. In the pickle module, picklers have an instance variable called memo which is a Python dictionary. So to clear the memo for a pickle module pickler, you could do the following:

```
mypickler.memo.clear()
```

Code that does not need to support older versions of Python should simply use clear_memo().

³In the pickle module these callables are classes, which you could subclass to customize the behavior. However, in the cPickle module these callables are factory functions and so cannot be subclassed. One common reason to subclass is to control what objects can actually be unpickled. See section 3.14.6 for more details.

It is possible to make multiple calls to the dump() method of the same Pickler instance. These must then be matched to the same number of calls to the load() method of the corresponding Unpickler instance. If the same object is pickled by multiple dump() calls, the load() will all yield references to the same object.⁴

Unpickler objects are defined as:

class Unpickler(file)

This takes a file-like object from which it will read a pickle data stream. This class automatically determines whether the data stream was written in binary mode or not, so it does not need a flag as in the Pickler factory.

file must have two methods, a read() method that takes an integer argument, and a readline() method that requires no arguments. Both methods should return a string. Thus file can be a file object opened for reading, a StringIO object, or any other custom object that meets this interface.

Unpickler objects have one (or two) public methods:

load()

Read a pickled object representation from the open file object given in the constructor, and return the reconstituted object hierarchy specified therein.

noload()

This is just like load() except that it doesn't actually create any objects. This is useful primarily for finding what's called "persistent ids" that may be referenced in a pickle data stream. See section 3.14.5 below for more details.

Note: the noload() method is currently only available on Unpickler objects created with the cPickle module. pickle module Unpicklers do not have the noload() method.

3.14.4 What can be pickled and unpickled?

The following types can be pickled:

- None, True, and False
- integers, long integers, floating point numbers, complex numbers
- normal and Unicode strings
- tuples, lists, sets, and dictionaries containing only picklable objects
- functions defined at the top level of a module
- built-in functions defined at the top level of a module
- classes that are defined at the top level of a module
- instances of such classes whose __dict__ or __setstate__() is picklable (see section 3.14.5 for details)

Attempts to pickle unpicklable objects will raise the PicklingError exception; when this happens, an unspecified number of bytes may have already been written to the underlying file.

Note that functions (built-in and user-defined) are pickled by "fully qualified" name reference, not by value. This means that only the function name is pickled, along with the name of module the function is defined in. Neither the function's code, nor any of its function attributes are pickled. Thus the defining module must be importable in the unpickling environment, and the module must contain the named object, otherwise an exception will be raised.⁵

⁴Warning: this is intended for pickling multiple objects without intervening modifications to the objects or their parts. If you modify an object and then pickle it again using the same Pickler instance, the object is not pickled again — a reference to it is pickled and the Unpickler will return the old value, not the modified one. There are two problems here: (1) detecting changes, and (2) marshalling a minimal set of changes. Garbage Collection may also become a problem here.

⁵The exception raised will likely be an ImportError or an AttributeError but it could be something else.

Similarly, classes are pickled by named reference, so the same restrictions in the unpickling environment apply. Note that none of the class's code or data is pickled, so in the following example the class attribute attr is not restored in the unpickling environment:

```
class Foo:
    attr = 'a class attr'
picklestring = pickle.dumps(Foo)
```

These restrictions are why picklable functions and classes must be defined in the top level of a module.

Similarly, when class instances are pickled, their class's code and data are not pickled along with them. Only the instance data are pickled. This is done on purpose, so you can fix bugs in a class or add methods to the class and still load objects that were created with an earlier version of the class. If you plan to have long-lived objects that will see many versions of a class, it may be worthwhile to put a version number in the objects so that suitable conversions can be made by the class's __setstate__() method.

3.14.5 The pickle protocol

This section describes the "pickling protocol" that defines the interface between the pickler/unpickler and the objects that are being serialized. This protocol provides a standard way for you to define, customize, and control how your objects are serialized and de-serialized. The description in this section doesn't cover specific customizations that you can employ to make the unpickling environment slightly safer from untrusted pickle data streams; see section 3.14.6 for more details.

Pickling and unpickling normal class instances

When a pickled class instance is unpickled, its __init__() method is normally *not* invoked. If it is desirable that the __init__() method be called on unpickling, an old-style class can define a method __getinitargs__(), which should return a *tuple* containing the arguments to be passed to the class constructor (i.e. __init__()). The __getinitargs__() method is called at pickle time; the tuple it returns is incorporated in the pickle for the instance.

New-style types can provide a __getnewargs__() method that is used for protocol 2. Implementing this method is needed if the type establishes some internal invariants when the instance is created, or if the memory allocation is affected by the values passed to the __new__() method for the type (as it is for tuples and strings). Instances of a new-style type C are created using

```
obj = C._new_(C, *args)
```

where *args* is the result of calling __getnewargs__() on the original object; if there is no __getnewargs__(), an empty tuple is assumed.

Classes can further influence how their instances are pickled; if the class defines the method __getstate__(), it is called and the return state is pickled as the contents for the instance, instead of the contents of the instance's dictionary. If there is no __getstate__() method, the instance's __dict__ is pickled.

Upon unpickling, if the class also defines the method __setstate__(), it is called with the unpickled state. If there is no __setstate__() method, the pickled state must be a dictionary and its items are assigned to the new instance's dictionary. If a class defines both __getstate__() and __setstate__(), the state object needn't be a dictionary and these methods can do what they want.

Warning: For new-style classes, if __getstate__() returns a false value, the __setstate__() method will not be called.

⁶These methods can also be used to implement copying class instances.

⁷This protocol is also used by the shallow and deep copying operations defined in the copy module.

Pickling and unpickling extension types

When the Pickler encounters an object of a type it knows nothing about — such as an extension type — it looks in two places for a hint of how to pickle it. One alternative is for the object to implement a <code>__reduce__()</code> method. If provided, at pickling time <code>__reduce__()</code> will be called with no arguments, and it must return either a string or a tuple.

If a string is returned, it names a global variable whose contents are pickled as normal. The string returned by __reduce__ should be the object's local name relative to its module; the pickle module searches the module namespace to determine the object's module.

When a tuple is returned, it must be between two and five elements long. Optional elements can either be omitted, or None can be provided as their value. The semantics of each element are:

- A callable object that will be called to create the initial version of the object. The next element of the tuple will provide arguments for this callable, and later elements provide additional state information that will subsequently be used to fully reconstruct the pickled date.
 - In the unpickling environment this object must be either a class, a callable registered as a "safe constructor" (see below), or it must have an attribute <code>__safe_for_unpickling_</code> with a true value. Otherwise, an <code>UnpicklingError</code> will be raised in the unpickling environment. Note that as usual, the callable itself is pickled by name.
- A tuple of arguments for the callable object, or None. **Deprecated since release 2.3.** If this item is None, then instead of calling the callable directly, its __basicnew__() method is called without arguments; this method should also return the unpickled object. Providing None is deprecated, however; return a tuple of arguments instead.
- Optionally, the object's state, which will be passed to the object's __setstate__() method as described in section 3.14.5. If the object has no __setstate__() method, then, as above, the value must be a dictionary and it will be added to the object's __dict__.
- Optionally, an iterator (and not a sequence) yielding successive list items. These list items will be pickled, and appended to the object using either obj.append(item) or obj.extend(list_of_items). This is primarily used for list subclasses, but may be used by other classes as long as they have append() and extend() methods with the appropriate signature. (Whether append() or extend() is used depends on which pickle protocol version is used as well as the number of items to append, so both must be supported.)
- Optionally, an iterator (not a sequenc7(ob)-268(s2.092050not)-270(successi)25(v)15otdictiona67 y2 whiotshouot 6A shouot

Pickling and unpickling external objects

For the benefit of object persistence, the pickle module supports the notion of a reference to an object outside the pickled data stream. Such objects are referenced by a "persistent id", which is just an arbitrary string of printable ASCII characters. The resolution of such names is not defined by the pickle module; it will delegate this resolution to user defined functions on the pickler and unpickler.⁸

To define external persistent id resolution, you need to set the persistent_id attribute of the pickler object and the persistent_load attribute of the unpickler object.

To pickle objects that have an external persistent id, the pickler must have a custom persistent_id() method that takes an object as an argument and returns either None or the persistent id for that object. When None is returned, the pickler simply pickles the object as normal. When a persistent id string is returned, the pickler will pickle that string, along with a marker so that the unpickler will recognize the string as a persistent id.

To unpickle external objects, the unpickler must have a custom persistent_load() function that takes a persistent id string and returns the referenced object.

Here's a silly example that *might* shed more light:

⁸The actual mechanism for associating these user defined functions is slightly different for pickle and cPickle. The description given here works the same for both implementations. Users of the pickle module could also use subclassing to effect the same results, overriding the persistent_id() and persistent_load() methods in the derived classes.

```
import pickle
from cStringIO import StringIO
src = StringIO()
p = pickle.Pickler(src)
def persistent_id(obj):
    if hasattr(obj, 'x'):
        return 'the value %d' % obj.x
    else:
        return None
p.persistent_id = persistent_id
class Integer:
    def __init__(self, x):
        self.x = x
    def __str__(self):
        return 'My name is integer %d' % self.x
i = Integer(7)
print i
p.dump(i)
datastream = src.getvalue()
print repr(datastream)
dst = StringIO(datastream)
up = pickle.Unpickler(dst)
class FancyInteger(Integer):
    def __str__(self):
        return 'I am the integer %d' % self.x
def persistent_load(persid):
    if persid.startswith('the value '):
        value = int(persid.split()[2])
        return FancyInteger(value)
    else:
        raise pickle.UnpicklingError, 'Invalid persistent id'
up.persistent_load = persistent_load
j = up.load()
print j
```

In the cPickle module, the unpickler's persistent_load attribute can also be set to a Python list, in which case, when the unpickler reaches a persistent id, the persistent id string will simply be appended to this list. This functionality exists so that a pickle data stream can be "sniffed" for object references without actually instantiating all the objects in a pickle. Setting persistent_load to a list is usually used in conjunction with the noload() method on the Unpickler.

3.14.6 Subclassing Unpicklers

By default, unpickling will import any class that it finds in the pickle data. You can control exactly what gets unpickled and what gets called by customizing your unpickler. Unfortunately, exactly how you do this is different

⁹We'll leave you with the image of Guido and Jim sitting around sniffing pickles in their living rooms.

depending on whether you're using pickle or cPickle. 10

In the pickle module, you need to derive a subclass from Unpickler, overriding the load_global() method. load_global() should read two lines from the pickle data stream where the first line will the name of the module containing the class and the second line will be the name of the instance's class. It then looks up the class, possibly importing the module and digging out the attribute, then it appends what it finds to the unpickler's stack. Later on, this class will be assigned to the __class__ attribute of an empty class, as a way of magically creating an instance without calling its class's __init__(). Your job (should you choose to accept it), would be to have load_global() push onto the unpickler's stack, a known safe version of any class you deem safe to unpickle. It is up to you to produce such a class. Or you could raise an error if you want to disallow all unpickling of instances. If this sounds like a hack, you're right. Refer to the source code to make this work.

Things are a little cleaner with cPickle, but not by much. To control what gets unpickled, you can set the unpickler's find_global attribute to a function or None. If it is None then any attempts to unpickle instances will raise an UnpicklingError. If it is a function, then it should accept a module name and a class name, and return the corresponding class object. It is responsible for looking up the class and performing any necessary imports, and it may raise an error to prevent instances of the class from being unpickled.

The moral of the story is that you should be really careful about the source of the strings your application unpickles.

3.14.7 Example

Here's a simple example of how to modify pickling behavior for a class. The TextReader class opens a text file, and returns the line number and line contents each time its readline() method is called. If a TextReader instance is pickled, all attributes *except* the file object member are saved. When the instance is unpickled, the file is reopened, and reading resumes from the last location. The __setstate__() and __getstate__() methods are used to implement this behavior.

```
class TextReader:
    """Print and number lines in a text file."""
   def __init__(self, file):
        self.file = file
        self.fh = open(file)
        self.lineno = 0
   def readline(self):
        self.lineno = self.lineno + 1
        line = self.fh.readline()
        if not line:
           return None
        if line.endswith("\n"):
            line = line[:-1]
        return "%d: %s" % (self.lineno, line)
   def __getstate__(self):
        odict = self.__dict__.copy() # copy the dict since we change it
        del odict['fh']
                                     # remove filehandle entry
        return odict
   def __setstate__(self,dict):
        fh = open(dict['file'])
                                     # reopen file
        count = dict['lineno']
                                     # read from file...
        while count:
                                     # until line count is restored
            fh.readline()
            count = count - 1
        self.__dict__.update(dict)
                                     # update attributes
        self.fh = fh
                                     # save the file object
```

¹⁰A word of caution: the mechanisms described here use internal attributes and methods, which are subject to change in future versions of Python. We intend to someday provide a common interface for controlling this behavior, which will work in either pickle or cPickle.

A sample usage might be something like this:

```
>>> import TextReader
>>> obj = TextReader.TextReader("TextReader.py")
>>> obj.readline()
'1: #!/usr/local/bin/python'
>>> # (more invocations of obj.readline() here)
... obj.readline()
'7: class TextReader:'
>>> import pickle
>>> pickle.dump(obj,open('save.p','w'))
```

If you want to see that pickle works across Python processes, start another Python session, before continuing. What follows can happen from either the same process or a new process.

See Also:

Module copy_reg (section 3.16):

Pickle interface constructor registration for extension types.

Module shelve (section 3.17):

Indexed databases of objects; uses pickle.

Module copy (section 3.18):

Shallow and deep object copying.

Module marshal (section 3.19):

High-performance serialization of built-in types.

3.15 cPickle — A faster pickle

The cPickle module supports serialization and de-serialization of Python objects, providing an interface and functionality nearly identical to the pickle module. There are several differences, the most important being performance and subclassability.

First, cPickle can be up to 1000 times faster than pickle because the former is implemented in C. Second, in the cPickle module the callables Pickler() and Unpickler() are functions, not classes. This means that you cannot use them to derive custom pickling and unpickling subclasses. Most applications have no need for this functionality and should benefit from the greatly improved performance of the cPickle module.

The pickle data stream produced by pickle and cPickle are identical, so it is possible to use pickle and cPickle interchangeably with existing pickles. 11

There are additional minor differences in API between cPickle and pickle, however for most applications, they are interchangeable. More documentation is provided in the pickle module documentation, which includes a list of the documented differences.

3.16 copy_reg — Register pickle support functions

¹¹Since the pickle data format is actually a tiny stack-oriented programming language, and some freedom is taken in the encodings of certain objects, it is possible that the two modules produce different data streams for the same input objects. However it is guaranteed that they will always be able to read each other's data streams.

The copy_reg module provides support for the pickle and cPickle modules. The copy module is likely to use this in the future as well. It provides configuration information about object constructors which are not classes. Such constructors may be factory functions or class instances.

constructor(object)

Declares *object* to be a valid constructor. If *object* is not callable (and hence not valid as a constructor), raises TypeError.

pickle(type, function[, constructor])

Declares that *function* should be used as a "reduction" function for objects of type *type*; *type* must not be a "classic" class object. (Classic classes are handled differently; see the documentation for the pickle module for details.) *function* should return either a string or a tuple containing two or three elements.

The optional *constructor* parameter, if provided, is a callable object which can be used to reconstruct the object when called with the tuple of arguments returned by *function* at pickling time. TypeError will be raised if *object* is a class or *constructor* is not callable.

See the pickle module for more details on the interface expected of function and constructor.

3.17 shelve — Python object persistence

A "shelf" is a persistent, dictionary-like object. The difference with "dbm" databases is that the values (not the keys!) in a shelf can be essentially arbitrary Python objects — anything that the pickle module can handle. This includes most class instances, recursive data types, and objects containing lots of shared sub-objects. The keys are ordinary strings.

```
open(filename[,flag='c'[,protocol=None[,writeback=False[,binary=None]]]]))
```

Open a persistent dictionary. The filename specified is the base filename for the underlying database. As a side-effect, an extension may be added to the filename and more than one file may be created. By default, the underlying database file is opened for reading and writing. The optional *flag* parameter has the same interpretation as the *flag* parameter of anydom.open.

By default, version 0 pickles are used to serialize values. The version of the pickle protocol can be specified with the *protocol* parameter. Changed in version 2.3: The *protocol* parameter was added. The *binary* parameter is deprecated and provided for backwards compatibility only.

By default, mutations to persistent-dictionary mutable entries are not automatically written back. If the optional *writeback* parameter is set to *True*, all entries accessed are cached in memory, and written back at close time; this can make it handier to mutate mutable entries in the persistent dictionary, but, if many entries are accessed, it can consume vast amounts of memory for the cache, and it can make the close operation very slow since all accessed entries are written back (there is no way to determine which accessed entries are mutable, nor which ones were actually mutated).

Shelve objects support all methods supported by dictionaries. This eases the transition from dictionary based scripts to those requiring persistent storage.

One additional method is supported:

sync()

Write back all entries in the cache if the shelf was opened with *writeback* set to *True*. Also empty the cache and synchronize the persistent dictionary on disk, if feasible. This is called automatically when the shelf is closed with close().

3.17.1 Restrictions

- The choice of which database package will be used (such as dbm, gdbm or bsddb) depends on which interface is available. Therefore it is not safe to open the database directly using dbm. The database is also (unfortunately) subject to the limitations of dbm, if it is used this means that (the pickled representation of) the objects stored in the database should be fairly small, and in rare cases key collisions may cause the database to refuse updates.
- Depending on the implementation, closing a persistent dictionary may or may not be necessary to flush changes to disk. The __del__ method of the Shelf class calls the close method, so the programmer

generally need not do this explicitly.

• The shelve module does not support *concurrent* read/write access to shelved objects. (Multiple simultaneous read accesses are safe.) When a program has a shelf open for writing, no other program should have it open for reading or writing. UNIX file locking can be used to solve this, but this differs across UNIX versions and requires knowledge about the database implementation used.

```
class Shelf(dict[, protocol=None[, writeback=False[, binary=None]]])
```

A subclass of UserDict. DictMixin which stores pickled values in the dict object.

By default, version 0 pickles are used to serialize values. The version of the pickle protocol can be specified with the *protocol* parameter. See the pickle documentation for a discussion of the pickle protocols. Changed in version 2.3: The protocol parameter was added. The binary parameter is deprecated and provided for backwards compatibility only.

If the writeback parameter is True, the object will hold a cache of all entries accessed and write them back to the dict at sync and close times. This allows natural operations on mutable entries, but can consume much more memory and make sync and close take a long time.

class BsdDbShelf(dict[, protocol=None[, writeback=False[, binary=None]]])

A subclass of Shelf which exposes first, next, previous, last and set_location which are available in the baddb module but not in other database modules. The dict object passed to the constructor must support those methods. This is generally accomplished by calling one of bsddb.hashopen, bsddb.btopen or bsddb.rnopen. The optional protocol, writeback, and binary parameters have the same interpretation as for the Shelf class.

class DbfilenameShelf(filename[, flag='c'[, protocol=None[, writeback=False[, binary=None]]]])) A subclass of Shelf which accepts a filename instead of a dict-like object. The underlying file will be opened using anydom.open. By default, the file will be created and opened for both read and write. The optional flag parameter has the same interpretation as for the open function. The optional protocol, writeback, and binary parameters have the same interpretation as for the Shelf class.

3.17.2 Example

To summarize the interface (key is a string, data is an arbitrary object):

```
import shelve
d = shelve.open(filename) # open -- file may get suffix added by low-level
                          # library
d[key] = data
               # store data at key (overwrites old data if
                # using an existing key)
data = d[key]
                # retrieve a COPY of data at key (raise KeyError if no
                # such key)
del d[key]
                # delete data stored at key (raises KeyError
                # if no such key)
flag = d.has_key(key) # true if the key exists
list = d.keys() # a list of all existing keys (slow!)
# as d was opened WITHOUT writeback=True, beware:
d['xx'] = range(4) # this works as expected, but...
d['xx'].append(5)
                   # *this doesn't!* -- d['xx'] is STILL range(4)!!!
# having opened d without writeback=True, you need to code carefully:
temp = d['xx']
                   # extracts the copy
temp.append(5)
                   # mutates the copy
                   # stores the copy right back, to persist it
d['xx'] = temp
# or, d=shelve.open(filename,writeback=True) would let you just code
# d['xx'].append(5) and have it work as expected, BUT it would also
# consume more memory and make the d.close() operation slower.
d.close()
                # close it
```

See Also:

Module anydbm (section 7.10):

Generic interface to dbm-style databases.

Module bsddb (section 7.13):

BSD db database interface.

Module dbhash (section 7.11):

Thin layer around the bsddb which provides an open function like the other database modules.

Module dbm (section 8.6):

Standard UNIX database interface.

Module dumbdbm (section 7.14):

Portable implementation of the dbm interface.

Module gdbm (section 8.7):

GNU database interface, based on the dbm interface.

Module pickle (section 3.14):

Object serialization used by shelve.

Module cPickle (section 3.15):

High-performance version of pickle.

3.18 copy — Shallow and deep copy operations

This module provides generic (shallow and deep) copying operations.

Interface summary:

```
import copy
x = copy.copy(y)  # make a shallow copy of y
x = copy.deepcopy(y)  # make a deep copy of y
```

For module specific errors, copy.error is raised.

The difference between shallow and deep copying is only relevant for compound objects (objects that contain other objects, like lists or class instances):

- A *shallow copy* constructs a new compound object and then (to the extent possible) inserts *references* into it to the objects found in the original.
- A *deep copy* constructs a new compound object and then, recursively, inserts *copies* into it of the objects found in the original.

Two problems often exist with deep copy operations that don't exist with shallow copy operations:

- Recursive objects (compound objects that, directly or indirectly, contain a reference to themselves) may cause a recursive loop.
- Because deep copy copies *everything* it may copy too much, e.g., administrative data structures that should be shared even between copies.

The deepcopy () function avoids these problems by:

- keeping a "memo" dictionary of objects already copied during the current copying pass; and
- letting user-defined classes override the copying operation or the set of components copied.

This version does not copy types like module, class, function, method, stack trace, stack frame, file, socket, window, array, or any similar types.

Classes can use the same interfaces to control copying that they use to control pickling. See the description of module pickle for information on these methods. The copy module does not use the copy_reg registration module.

In order for a class to define its own copy implementation, it can define special methods __copy__() and __deepcopy__(). The former is called to implement the shallow copy operation; no additional arguments are passed. The latter is called to implement the deep copy operation; it is passed one argument, the memo dictionary. If the __deepcopy__() implementation needs to make a deep copy of a component, it should call the deepcopy() function with the component as first argument and the memo dictionary as second argument.

See Also:

Module pickle (section 3.14):

Discussion of the special methods used to support object state retrieval and restoration.

3.19 marshal — Internal Python object serialization

This module contains functions that can read and write Python values in a binary format. The format is specific to Python, but independent of machine architecture issues (e.g., you can write a Python value to a file on a PC, transport the file to a Sun, and read it back there). Details of the format are undocumented on purpose; it may change between Python versions (although it rarely does).¹²

¹²The name of this module stems from a bit of terminology used by the designers of Modula-3 (amongst others), who use the term "marshalling" for shipping of data around in a self-contained form. Strictly speaking, "to marshal" means to convert some data from internal to external form (in an RPC buffer for instance) and "unmarshalling" for the reverse process.

This is not a general "persistence" module. For general persistence and transfer of Python objects through RPC calls, see the modules pickle and shelve. The marshal module exists mainly to support reading and writing the "pseudo-compiled" code for Python modules of '.pyc' files. Therefore, the Python maintainers reserve the right to modify the marshal format in backward incompatible ways should the need arise. If you're serializing and de-serializing Python objects, use the pickle module instead.

Warning: The marshal module is not intended to be secure against erroneous or maliciously constructed data. Never unmarshal data received from an untrusted or unauthenticated source.

Not all Python object types are supported; in general, only objects whose value is independent from a particular invocation of Python can be written and read by this module. The following types are supported: None, integers, long integers, floating point numbers, strings, Unicode objects, tuples, lists, dictionaries, and code objects, where it should be understood that tuples, lists and dictionaries are only supported as long as the values contained therein are themselves supported; and recursive lists and dictionaries should not be written (they will cause infinite loops).

Caveat: On machines where C's long int type has more than 32 bits (such as the DEC Alpha), it is possible to create plain Python integers that are longer than 32 bits. If such an integer is marshaled and read back in on a machine where C's long int type has only 32 bits, a Python long integer object is returned instead. While of a different type, the numeric value is the same. (This behavior is new in Python 2.2. In earlier versions, all but the least-significant 32 bits of the value were lost, and a warning message was printed.)

There are functions that read/write files as well as functions operating on strings.

The module defines these functions:

dump(value, file[, version])

Write the value on the open file. The value must be a supported type. The file must be an open file object such as sys.stdout or returned by open() or posix.popen(). It must be opened in binary mode ('wb' or 'w+b').

If the value has (or contains an object that has) an unsupported type, a ValueError exception is raised — but garbage data will also be written to the file. The object will not be properly read back by load().

New in version 2.4: The *version* argument indicates the data format that dump should use (see below).

load(file)

Read one value from the open file and return it. If no valid value is read, raise EOFError, ValueError or TypeError. The file must be an open file object opened in binary mode ('rb' or 'r+b').

Warning: If an object containing an unsupported type was marshalled with dump(), load() will substitute None for the unmarshallable type.

dumps (value , version)

Return the string that would be written to a file by dump(value, file). The value must be a supported type. Raise a ValueError exception if value has (or contains an object that has) an unsupported type.

New in version 2.4: The version argument indicates the data format that dumps should use (see below).

loads(string)

Convert the string to a value. If no valid value is found, raise EOFError, ValueError or TypeError. Extra characters in the string are ignored.

In addition, the following constants are defined:

version

Indicates the format that the module uses. Version 0 is the historical format, version 1 (added in Python 2.4) shares interned strings. The current version is 1.

New in version 2.4.

3.20 warnings — Warning control

New in version 2.1.

Warning messages are typically issued in situations where it is useful to alert the user of some condition in a

program, where that condition (normally) doesn't warrant raising an exception and terminating the program. For example, one might want to issue a warning when a program uses an obsolete module.

Python programmers issue warnings by calling the warn() function defined in this module. (C programmers use PyErr_Warn(); see the *Python/C API Reference Manual* for details).

Warning messages are normally written to sys.stderr, but their disposition can be changed flexibly, from ignoring all warnings to turning them into exceptions. The disposition of warnings can vary based on the warning category (see below), the text of the warning message, and the source location where it is issued. Repetitions of a particular warning for the same source location are typically suppressed.

There are two stages in warning control: first, each time a warning is issued, a determination is made whether a message should be issued or not; next, if a message is to be issued, it is formatted and printed using a user-settable book

The determination whether to issue a warning message is controlled by the warning filter, which is a sequence of matching rules and actions. Rules can be added to the filter by calling filterwarnings() and reset to its default state by calling resetwarnings().

The printing of warning messages is done by calling showwarning(), which may be overridden; the default implementation of this function formats the message by calling formatwarning(), which is also available for use by custom implementations.

3.20.1 Warning Categories

There are a number of built-in exceptions that represent warning categories. This categorization is useful to be able to filter out groups of warnings. The following warnings category classes are currently defined:

Class	Description	
Warning	This is the base class of all warning category classes. It is a subclass of Exception.	
UserWarning	The default category for warn().	
DeprecationWarning	Base category for warnings about deprecated features.	
SyntaxWarning	Base category for warnings about dubious syntactic features.	
RuntimeWarning	Base category for warnings about dubious runtime features.	
FutureWarning	Base category for warnings about constructs that will change semantically in the future.	

While these are technically built-in exceptions, they are documented here, because conceptually they belong to the warnings mechanism.

User code can define additional warning categories by subclassing one of the standard warning categories. A warning category must always be a subclass of the Warning class.

3.20.2 The Warnings Filter

The warnings filter controls whether warnings are ignored, displayed, or turned into errors (raising an exception).

Conceptually, the warnings filter maintains an ordered list of filter specifications; any specific warning is matched against each filter specification in the list in turn until a match is found; the match determines the disposition of the match. Each entry is a tuple of the form (action, message, category, module, lineno), where:

• *action* is one of the following strings:

Value	Disposition
"error"	turn matching warnings into exceptions
"ignore"	never print matching warnings
"always"	always print matching warnings
"default"	print the first occurrence of matching warnings for each location where the warning is issued
"module"	print the first occurrence of matching warnings for each module where the warning is issued
"once"	print only the first occurrence of matching warnings, regardless of location

- *message* is a string containing a regular expression that the warning message must match (the match is compiled to always be case-insensitive)
- category is a class (a subclass of Warning) of which the warning category must be a subclass in order to match
- *module* is a string containing a regular expression that the module name must match (the match is compiled to be case-sensitive)
- *lineno* is an integer that the line number where the warning occurred must match, or 0 to match all line numbers

Since the Warning class is derived from the built-in Exception class, to turn a warning into an error we simply raise category (message).

The warnings filter is initialized by **-W** options passed to the Python interpreter command line. The interpreter saves the arguments for all **-W** options without interpretation in sys.warnoptions; the warnings module parses these when it is first imported (invalid options are ignored, after printing a message to sys.stderr).

3.20.3 Available Functions

warn(message[, category[, stacklevel]])

Issue a warning, or maybe ignore it or raise an exception. The *category* argument, if given, must be a warning category class (see above); it defaults to UserWarning. Alternatively *message* can be a Warning instance, in which case *category* will be ignored and message.__class__ will be used. In this case the message text will be str(message). This function raises an exception if the particular warning issued is changed into an error by the warnings filter see above. The *stacklevel* argument can be used by wrapper functions written in Python, like this:

```
def deprecation(message):
    warnings.warn(message, DeprecationWarning, stacklevel=2)
```

This makes the warning refer to deprecation()'s caller, rather than to the source of deprecation() itself (since the latter would defeat the purpose of the warning message).

```
warn_explicit(message, category, filename, lineno[, module[, registry]])
```

This is a low-level interface to the functionality of warn(), passing in explicitly the message, category, filename and line number, and optionally the module name and the registry (which should be the __warningregistry__ dictionary of the module). The module name defaults to the filename with .py stripped; if no registry is passed, the warning is never suppressed. message must be a string and category a subclass of Warning or message may be a Warning instance, in which case category will be ignored.

```
showwarning (message, category, filename, lineno[, file])
```

Write a warning to a file. The default implementation calls formatwarning (message, category, filename, lineno) and writes the resulting string to file, which defaults to sys.stderr. You may replace this function with an alternative implementation by assigning to warnings.showwarning.

formatwarning (*message*, *category*, *filename*, *lineno*)

Format a warning the standard way. This returns a string which may contain embedded newlines and ends in a newline.

```
filterwarnings(action[, message[, category[, module[, lineno[, append]]]]]))
```

Insert an entry into the list of warnings filters. The entry is inserted at the front by default; if *append* is true, it is inserted at the end. This checks the types of the arguments, compiles the message and module regular expressions, and inserts them as a tuple in front of the warnings filter. Entries inserted later override entries inserted earlier, if both match a particular warning. Omitted arguments default to a value that matches everything.

resetwarnings()

Reset the warnings filter. This discards the effect of all previous calls to filterwarnings(), including that of the -W command line options.

3.21 imp — Access the import internals

This module provides an interface to the mechanisms used to implement the import statement. It defines the following constants and functions:

get_magic()

Return the magic string value used to recognize byte-compiled code files ('.pyc' files). (This value may be different for each Python version.)

get_suffixes()

Return a list of triples, each describing a particular type of module. Each triple has the form (*suffix* , *mode* , *type*), where *suffix* is a string to be appended to the module name to form the filename to search for, *mode* is the mode string to pass to the built-in open() function to open the file (this can be 'r' for text files or 'rb' for binary files), and *type* is the file type, which has one of the values PY_SOURCE, PY_COMPILED, or C_EXTENSION, described below.

find_module(name[, path])

Try to find the module *name* on the search path *path*. If *path* is a list of directory names, each directory is searched for files with any of the suffixes returned by <code>get_suffixes()</code> above. Invalid names in the list are silently ignored (but all list items must be strings). If *path* is omitted or None, the list of directory names given by <code>sys.path</code> is searched, but first it searches a few special places: it tries to find a built-in module with the given name (<code>C_BUILTIN</code>), then a frozen module (<code>PY_FROZEN</code>), and on some systems some other places are looked in as well (on the Mac, it looks for a resource (<code>PY_RESOURCE</code>); on Windows, it looks in the registry which may point to a specific file).

If search is successful, the return value is a triple (file, pathname, description) where file is an open file object positioned at the beginning, pathname is the pathname of the file found, and description is a triple as contained in the list returned by get_suffixes() describing the kind of module found. If the module does not live in a file, the returned file is None, filename is the empty string, and the description tuple contains empty strings for its suffix and mode; the module type is as indicate in parentheses above. If the search is unsuccessful, ImportError is raised. Other exceptions indicate problems with the arguments or environment.

This function does not handle hierarchical module names (names containing dots). In order to find P.M, that is, submodule M of package P, use find_module() and load_module() to find and load package P, and then use find_module() with the P argument set to P.__path___. When P itself has a dotted name, apply this recipe recursively.

load_module(name, file, filename, description)

Load a module that was previously found by find_module() (or by an otherwise conducted search yielding compatible results). This function does more than importing the module: if the module was already imported, it is equivalent to a reload()! The *name* argument indicates the full module name (including the package name, if this is a submodule of a package). The *file* argument is an open file, and *filename* is the corresponding file name; these can be None and '', respectively, when the module is not being loaded from a file. The *description* argument is a tuple, as would be returned by get_suffixes(), describing what kind of module must be loaded.

If the load is successful, the return value is the module object; otherwise, an exception (usually ImportError) is raised.

Important: the caller is responsible for closing the *file* argument, if it was not None, even when an exception is raised. This is best done using a try ... finally statement.

new_module(name)

Return a new empty module object called *name*. This object is *not* inserted in sys.modules.

lock held()

Return True if the import lock is currently held, else False. On platforms without threads, always return False.

On platforms with threads, a thread executing an import holds an internal lock until the import is complete. This lock blocks other threads from doing an import until the original import completes, which in turn prevents other threads from seeing incomplete module objects constructed by the original thread while in the process of completing its import (and the imports, if any, triggered by that).

acquire_lock()

Acquires the interpreter's import lock for the current thread. This lock should be used by import hooks to ensure thread-safety when importing modules. On platforms without threads, this function does nothing. New in version 2.3.

release_lock()

Release the interpreter's import lock. On platforms without threads, this function does nothing. New in version 2.3.

The following constants with integer values, defined in this module, are used to indicate the search result of find_module().

PY_SOURCE

The module was found as a source file.

PY_COMPILED

The module was found as a compiled code object file.

C_EXTENSION

The module was found as dynamically loadable shared library.

PY_RESOURCE

The module was found as a Mac OS 9 resource. This value can only be returned on a Mac OS 9 or earlier Macintosh.

PKG_DIRECTORY

The module was found as a package directory.

C_BUILTIN

The module was found as a built-in module.

PY_FROZEN

The module was found as a frozen module (see init_frozen()).

The following constant and functions are obsolete; their functionality is available through find_module() or load_module(). They are kept around for backward compatibility:

SEARCH_ERROR

Unused.

init_builtin(name)

Initialize the built-in module called *name* and return its module object. If the module was already initialized, it will be initialized *again*. A f0(as)-250Tf iinagain

load_dynamic(name, pathname[, file])

Load and initialize a module implemented as a dynamically loadable shared library and return its module object. If the module was already initialized, it will be initialized *again*. Some modules don't like that and may raise an exception. The *pathname* argument must point to the shared library. The *name* argument is used to construct the name of the initialization function: an external C function called 'initname()' in the shared library is called. The optional *file* argument is ignored. (Note: using shared libraries is highly system dependent, and not all systems support it.)

load_source(name, pathname[, file])

Load and initialize a module implemented as a Python source file and return its module object. If the module was already initialized, it will be initialized *again*. The *name* argument is used to create or access a module object. The *pathname* argument points to the source file. The *file* argument is the source file, open for reading as text, from the beginning. It must currently be a real file object, not a user-defined class emulating a file. Note that if a properly matching byte-compiled file (with suffix '.pyc' or '.pyo') exists, it will be used instead of parsing the given source file.

3.21.1 Examples

The following function emulates what was the standard import statement up to Python 1.4 (no hierarchical module names). (This *implementation* wouldn't work in that version, since find_module() has been extended and load_module() has been added in 1.4.)

```
import imp
import sys

def __import__(name, globals=None, locals=None, fromlist=None):
    # Fast path: see if the module has already been imported.
    try:
        return sys.modules[name]
    except KeyError:
        pass

# If any of the following calls raises an exception,
    # there's a problem we can't handle -- let the caller handle it.

fp, pathname, description = imp.find_module(name)

try:
    return imp.load_module(name, fp, pathname, description)
finally:
    # Since we may exit via an exception, close fp explicitly.
    if fp:
        fp.close()
```

A more complete example that implements hierarchical module names and includes a reload() function can be found in the module knee. The knee module can be found in 'Demo/imputil/' in the Python source distribution.

3.22 zipimport — Import modules from Zip archives

New in version 2.3.

This module adds the ability to import Python modules ('*.py', '*.py[co]') and packages from ZIP-format archives. It is usually not needed to use the zipimport module explicitly; it is automatically used by the builtin import mechanism for sys.path items that are paths to ZIP archives.

Typically, sys.path is a list of directory names as strings. This module also allows an item of sys.path to be a string naming a ZIP file archive. The ZIP archive can contain a subdirectory structure to support package

imports, and a path within the archive can be specified to only import from a subdirectory. For example, the path '/tmp/example.zip/lib/' would only import from the 'lib/' subdirectory within the archive.

Any files may be present in the ZIP archive, but only files '.py' and '.py[co]' are available for import. ZIP import of dynamic modules ('.pyd', '.so') is disallowed. Note that if an archive only contains '.py' files, Python will not attempt to modify the archive by adding the corresponding '.pyc' or '.pyo' file, meaning that if a ZIP archive doesn't contain '.pyc' files, importing may be rather slow.

Using the built-in reload() function will fail if called on a module loaded from a ZIP archive; it is unlikely that reload() would be needed, since this would imply that the ZIP has been altered during runtime.

The available attributes of this module are:

exception ZipImporterError

Exception raised by zipimporter objects. It's a subclass of ImportError, so it can be caught as ImportError, too.

class zipimporter

The class for importing ZIP files. See "zipimporter Objects" (section 3.22.1) for constructor details.

See Also:

PKZIP Application Note

(http://www.pkware.com/appnote.html)

Documentation on the ZIP file format by Phil Katz, the creator of the format and algorithms used.

PEP 0273, "Import Modules from Zip Archives"

Written by James C. Ahlstrom, who also provided an implementation. Python 2.3 follows the specification in PEP 273, but uses an implementation written by Just van Rossum that uses the import hooks described in PEP 302.

PEP 0302, "New Import Hooks"

The PEP to add the import hooks that help this module work.

3.22.1 zipimporter Objects

class zipimporter(archivepath)

Create a new zipimporter instance. *archivepath* must be a path to a zipfile. ZipImportError is raised if *archivepath* doesn't point to a valid ZIP archive.

find_module(fullname[, path])

Search for a module specified by *fullname*. *fullname* must be the fully qualified (dotted) module name. It returns the zipimporter instance itself if the module was found, or None if it wasn't. The optional *path* argument is ignored—it's there for compatibility with the importer protocol.

get_code(fullname)

Return the code object for the specified module. Raise ZipImportError if the module couldn't be found.

get_data(pathname)

Return the data associated with *pathname*. Raise IOError if the file wasn't found.

get_source(fullname)

Return the source code for the specified module. Raise ZipImportError if the module couldn't be found, return None if the archive does contain the module, but has no source for it.

is_package(fullname)

Return True if the module specified by *fullname* is a package. Raise ZipImportError if the module couldn't be found.

load_module(fullname)

Load the module specified by *fullname*. *fullname* must be the fully qualified (dotted) module name. It returns the imported module, or raises ZipImportError if it wasn't found.

3.22.2 Examples

Here is an example that imports a module from a ZIP archive - note that the zipimport module is not explicitly used.

```
$ unzip -l /tmp/example.zip
Archive: /tmp/example.zip
 Length
           Date Time
                           Name
    8467 11-26-02 22:30
                           jwzthreading.py
 _____
    8467
                           1 file
$ ./python
Python 2.3 (#1, Aug 1 2003, 19:54:32)
>>> import sys
>>> sys.path.insert(0, '/tmp/example.zip')  # Add .zip file to front of path
>>> import jwzthreading
>>> jwzthreading.__file_
'/tmp/example.zip/jwzthreading.py'
```

3.23 pkgutil — Package extension utility

New in version 2.3.

This module provides a single function:

```
extend_path(path, name)
```

Extend the search path for the modules which comprise a package. Intended use is to place the following code in a package's '__init__.py':

```
from pkgutil import extend_path
__path__ = extend_path(__path__, __name__)
```

This will add to the package's __path__ all subdirectories of directories on sys.path named after the package. This is useful if one wants to distribute different parts of a single logical package as multiple directories.

It also looks for '*.pkg' files beginning where * matches the *name* argument. This feature is similar to '*.pth' files (see the site module for more information), except that it doesn't special-case lines starting with import. A '*.pkg' file is trusted at face value: apart from checking for duplicates, all entries found in a '*.pkg' file are added to the path, regardless of whether they exist the filesystem. (This is a feature.)

If the input path is not a list (as is the case for frozen packages) it is returned unchanged. The input path is not modified; an extended copy is returned. Items are only appended to the copy at the end.

It is assumed that sys.path is a sequence. Items of sys.path that are not (Unicode or 8-bit) strings referring to existing directories are ignored. Unicode items on sys.path that cause errors when used as filenames may cause this function to raise an exception (in line with os.path.isdir() behavior).

3.24 modulefinder — Find modules used by a script

This module provides a ModuleFinder class that can be used to determine the set of modules imported by a script. modulefinder.py can also be run as a script, giving the filename of a Python script as its argument, after which a report of the imported modules will be printed.

```
{\tt AddPackagePath}\,(\,pkg\_name,\,path\,)
```

Record that the package named *pkg_name* can be found in the specified *path*.

ReplacePackage (oldname, newname)

Allows specifying that the module named *oldname* is in fact the package named *newname*. The most common usage would be to handle how the _xmlplus package replaces the xml package.

class ModuleFinder([path=None, debug=0, excludes=[], replace_paths=[]])

This class provides run_script() and report() methods to determine the set of modules imported by a script. path can be a list of directories to search for modules; if not specified, sys.path is used. debug sets the debugging level; higher values make the class print debugging messages about what it's doing. excludes is a list of module names to exclude from the analysis. replace_paths is a list of (oldpath, newpath) tuples that will be replaced in module paths.

report()

Print a report to standard output that lists the modules imported by the script and their paths, as well as modules that are missing or seem to be missing.

run_script(pathname)

Analyze the contents of the *pathname* file, which must contain Python code.

3.25 code — Interpreter base classes

The code module provides facilities to implement read-eval-print loops in Python. Two classes and convenience functions are included which can be used to build applications which provide an interactive interpreter prompt.

class InteractiveInterpreter([locals])

This class deals with parsing and interpreter state (the user's namespace); it does not deal with input buffering or prompting or input file naming (the filename is always passed in explicitly). The optional *locals* argument specifies the dictionary in which code will be executed; it defaults to a newly created dictionary with key '__name__' set to '__console__' and key '__doc__' set to None.

class InteractiveConsole([locals[, filename]])

Closely emulate the behavior of the interactive Python interpreter. This class builds on InteractiveInterpreter and adds prompting using the familiar sys.ps1 and sys.ps2, and input buffering.

interact([banner[, readfunc[, local]]])

Convenience function to run a read-eval-print loop. This creates a new instance of InteractiveConsole and sets *readfunc* to be used as the raw_input() method, if provided. If *local* is provided, it is passed to the InteractiveConsole constructor for use as the default namespace for the interpreter loop. The interact() method of the instance is then run with *banner* passed as the banner to use, if provided. The console object is discarded after use.

compile_command(source[, filename[, symbol]])

This function is useful for programs that want to emulate Python's interpreter main loop (a.k.a. the read-eval-print loop). The tricky part is to determine when the user has entered an incomplete command that can be completed by entering more text (as opposed to a complete command or a syntax error). This function *almost* always makes the same decision as the real interpreter main loop.

source is the source string; *filename* is the optional filename from which source was read, defaulting to '<input>'; and *symbol* is the optional grammar start symbol, which should be either 'single' (the default) or 'eval'.

Returns a code object (the same as compile(source, filename, symbol)) if the command is complete and valid; None if the command is incomplete; raises SyntaxError if the command is complete and contains a syntax error, or raises OverflowError or ValueError if the command contains an invalid literal.

3.25.1 Interactive Interpreter Objects

runsource(source[, filename[, symbol]])

Compile and run some source in the interpreter. Arguments are the same as for compile_command(); the default for *filename* is '<input>', and for *symbol* is 'single'. One several things can happen:

- •The input is incorrect; compile_command() raised an exception (SyntaxError or OverflowError). A syntax traceback will be printed by calling the showsyntaxerror() method.runsource() returns False.
- •The input is incomplete, and more input is required; compile_command() returned None. runsource() returns True.
- •The input is complete; compile_command() returned a code object. The code is executed by calling the runcode() (which also handles run-time exceptions, except for SystemExit). runsource() returns False.

The return value can be used to decide whether to use sys.ps1 or sys.ps2 to prompt the next line.

runcode (code)

Execute a code object. When an exception occurs, showtraceback() is called to display a traceback. All exceptions are caught except SystemExit, which is allowed to propagate.

A note about KeyboardInterrupt: this exception may occur elsewhere in this code, and may not always be caught. The caller should be prepared to deal with it.

showsyntaxerror([filename])

Display the syntax error that just occurred. This does not display a stack trace because there isn't one for syntax errors. If *filename* is given, it is stuffed into the exception instead of the default filename provided by Python's parser, because it always uses '<string>' when reading from a string. The output is written by the write() method.

showtraceback()

Display the exception that just occurred. We remove the first stack item because it is within the interpreter object implementation. The output is written by the write() method.

write(data)

Write a string to the standard error stream (sys.stderr). Derived classes should override this to provide the appropriate output handling as needed.

3.25.2 Interactive Console Objects

The InteractiveConsole class is a subclass of InteractiveInterpreter, and so offers all the methods of the interpreter objects as well as the following additions.

interact([banner])

Closely emulate the interactive Python console. The optional banner argument specify the banner to print before the first interaction; by default it prints a banner similar to the one printed by the standard Python interpreter, followed by the class name of the console object in parentheses (so as not to confuse this with the real interpreter – since it's so close!).

push(line)

Push a line of source text to the interpreter. The line should not have a trailing newline; it may have internal newlines. The line is appended to a buffer and the interpreter's runsource() method is called with the concatenated contents of the buffer as source. If this indicates that the command was executed or invalid, the buffer is reset; otherwise, the command is incomplete, and the buffer is left as it was after the line was appended. The return value is True if more input is required, False if the line was dealt with in some way (this is the same as runsource()).

resetbuffer()

Remove any unhandled source text from the input buffer.

raw_input([prompt])

Write a prompt and read a line. The returned line does not include the trailing newline. When the user enters the EOF key sequence, EOFError is raised. The base implementation uses the built-in function raw_input(); a subclass may replace this with a different implementation.

3.26 codeop — Compile Python code

The codeop module provides utilities upon which the Python read-eval-print loop can be emulated, as is done in the code module. As a result, you probably don't want to use the module directly; if you want to include such a loop in your program you probably want to use the code module instead.

There are two parts to this job:

- 1. Being able to tell if a line of input completes a Python statement: in short, telling whether to print '>>> ' or '... ' next.
- 2. Remembering which future statements the user has entered, so subsequent input can be compiled with these in effect.

The codeop module provides a way of doing each of these things, and a way of doing them both.

To do just the former:

```
compile_command(source[, filename[, symbol]])
```

Tries to compile *source*, which should be a string of Python code and return a code object if *source* is valid Python code. In that case, the filename attribute of the code object will be *filename*, which defaults to '<input>'. Returns None if *source* is *not* valid Python code, but is a prefix of valid Python code.

If there is a problem with *source*, an exception will be raised. SyntaxError is raised if there is invalid Python syntax, and OverflowError or ValueError if there is an invalid literal.

The *symbol* argument determines whether *source* is compiled as a statement ('single', the default) or as an expression ('eval'). Any other value will cause ValueError to be raised.

Caveat: It is possible (but not likely) that the parser stops parsing with a successful outcome before reaching the end of the source; in this case, trailing symbols may be ignored instead of causing an error. For example, a backslash followed by two newlines may be followed by arbitrary garbage. This will be fixed once the API for the parser is better.

class Compile()

Instances of this class have __call__() methods identical in signature to the built-in function compile(), but with the difference that if the instance compiles program text containing a __future__ statement, the instance 'remembers' and compiles all subsequent program texts with the statement in force.

class CommandCompiler()

Instances of this class have __call__() methods identical in signature to compile_command(); the difference is that if the instance compiles program text containing a __future__ statement, the instance 'remembers' and compiles all subsequent program texts with the statement in force.

A note on version compatibility: the Compile and CommandCompiler are new in Python 2.2. If you want to enable the future-tracking features of 2.2 but also retain compatibility with 2.1 and earlier versions of Python you can either write

```
try:
    from codeop import CommandCompiler
    compile_command = CommandCompiler()
    del CommandCompiler
except ImportError:
    from codeop import compile_command
```

which is a low-impact change, but introduces possibly unwanted global state into your program, or you can write:

```
try:
    from codeop import CommandCompiler
except ImportError:
    def CommandCompiler():
        from codeop import compile_command
        return compile_command
```

and then call CommandCompiler every time you need a fresh compiler object.

3.27 pprint — Data pretty printer

The pprint module provides a capability to "pretty-print" arbitrary Python data structures in a form which can be used as input to the interpreter. If the formatted structures include objects which are not fundamental Python types, the representation may not be loadable. This may be the case if objects such as files, sockets, classes, or instances are included, as well as many other builtin objects which are not representable as Python constants.

The formatted representation keeps objects on a single line if it can, and breaks them onto multiple lines if they don't fit within the allowed width. Construct PrettyPrinter objects explicitly if you need to adjust the width constraint.

The pprint module defines one class:

class PrettyPrinter(...)

Construct a PrettyPrinter instance. This constructor understands several keyword parameters. An output stream may be set using the *stream* keyword; the only method used on the stream object is the file protocol's write() method. If not specified, the PrettyPrinter adopts sys.stdout. Three additional parameters may be used to control the formatted representation. The keywords are *indent*, *depth*, and *width*. The amount of indentation added for each recursive level is specified by *indent*; the default is one. Other values can cause output to look a little odd, but can make nesting easier to spot. The number of levels which may be printed is controlled by *depth*; if the data structure being printed is too deep, the next contained level is replaced by '...'. By default, there is no constraint on the depth of the objects being formatted. The desired output width is constrained using the *width* parameter; the default is eighty characters. If a structure cannot be formatted within the constrained width, a best effort will be made.

```
>>> import pprint, sys
>>> stuff = sys.path[:]
>>> stuff.insert(0, stuff[:])
>>> pp = pprint.PrettyPrinter(indent=4)
>>> pp.pprint(stuff)
       '',
        '/usr/local/lib/python1.5',
        '/usr/local/lib/python1.5/test',
        '/usr/local/lib/python1.5/sunos5',
        '/usr/local/lib/python1.5/sharedmodules',
        '/usr/local/lib/python1.5/tkinter'],
    '/usr/local/lib/python1.5',
    '/usr/local/lib/python1.5/test',
    '/usr/local/lib/python1.5/sunos5',
    '/usr/local/lib/python1.5/sharedmodules',
    '/usr/local/lib/python1.5/tkinter']
>>> import parser
>>> tup = parser.ast2tuple(
       parser.suite(open('pprint.py').read()))[1][1][1]
>>> pp = pprint.PrettyPrinter(depth=6)
>>> pp.pprint(tup)
(266, (267, (307, (287, (288, (...))))))
```

The PrettyPrinter class supports several derivative functions:

```
pformat(object[, indent[, width[, depth]]])
```

Return the formatted representation of *object* as a string. *indent*, *width* and *depth* will be passed to the PrettyPrinter constructor as formatting parameters. Changed in version 2.4: The parameters *indent*, *width* and *depth* were added.

```
pprint(object[, stream[, indent[, width[, depth]]]])
```

Prints the formatted representation of object on stream, followed by a newline. If stream is omitted,

sys.stdout is used. This may be used in the interactive interpreter instead of a print statement for inspecting values. *indent*, *width* and *depth* will be passed to the PrettyPrinter constructor as formatting parameters.

Changed in version 2.4: The parameters *indent*, *width* and *depth* were added.

isreadable(object)

Determine if the formatted representation of *object* is "readable," or can be used to reconstruct the value using eval(). This always returns false for recursive objects.

```
>>> pprint.isreadable(stuff)
False
```

isrecursive(object)

Determine if *object* requires a recursive representation.

One more support function is also defined:

saferepr(object)

Return a string representation of *object*, protected against recursive data structures. If the representation of *object* exposes a recursive entry, the recursive reference will be represented as '<Recursion on *type-name* with id=number>'. The representation is not otherwise formatted.

```
>>> pprint.saferepr(stuff)
"[<Recursion on list with id=682968>, '', '/usr/local/lib/python1.5', '/usr/local
l/lib/python1.5/test', '/usr/local/lib/python1.5/sunos5', '/usr/local/lib/python
1.5/sharedmodules', '/usr/local/lib/python1.5/tkinter']"
```

3.27.1 PrettyPrinter Objects

PrettyPrinter instances have the following methods:

```
pformat(object)
```

Return the formatted representation of *object*. This takes into Account the options passed to the PrettyPrinter constructor.

pprint(object)

Print the formatted representation of *object* on the configured stream, followed by a newline.

The following methods provide the implementations for the corresponding functions of the same names. Using these methods on an instance is slightly more efficient since new PrettyPrinter objects don't need to be created.

isreadable(object)

Determine if the formatted representation of the object is "readable," or can be used to reconstruct the value using eval(). Note that this returns false for recursive objects. If the *depth* parameter of the PrettyPrinter is set and the object is deeper than allowed, this returns false.

isrecursive(object)

Determine if the object requires a recursive representation.

This method is provided as a hook to allow subclasses to modify the way objects are converted to strings. The default implementation uses the internals of the saferepr() implementation.

format(object, context, maxlevels, level)

Returns three values: the formatted version of *object* as a string, a flag indicating whether the result is readable, and a flag indicating whether recursion was detected. The first argument is the object to be presented. The second is a dictionary which contains the id() of objects that are part of the current presentation context (direct and indirect containers for *object* that are affecting the presentation) as the keys; if an object needs to be presented which is already represented in *context*, the third return value should be true. Recursive calls to the format() method should add additional entries for containers to this dictionary. The fourth argument, *maxlevels*, gives the requested limit to recursion; this will be 0 if there is no requested limit. This argument should be passed unmodified to recursive calls. The fourth argument, *level* gives the current level; recursive calls should be passed a value less than that of the current call. New in version 2.3.

3.28 repr — Alternate repr() implementation

The repr module provides a means for producing object representations with limits on the size of the resulting strings. This is used in the Python debugger and may be useful in other contexts as well.

This module provides a class, an instance, and a function:

class Repr()

Class which provides formatting services useful in implementing functions similar to the built-in repr(); size limits for different object types are added to avoid the generation of representations which are excessively long.

aRepr

This is an instance of Repr which is used to provide the repr() function described below. Changing the attributes of this object will affect the size limits used by repr() and the Python debugger.

repr(obj)

This is the repr() method of aRepr. It returns a string similar to that returned by the built-in function of the same name, but with limits on most sizes.

3.28.1 Repr Objects

Repr instances provide several members which can be used to provide size limits for the representations of different object types, and methods which format specific object types.

maxlevel

Depth limit on the creation of recursive representations. The default is 6.

maxdict

maxlist

maxtuple

maxset

maxfrozenset

maxdeque

maxarray

Limits on the number of entries represented for the named object type. The default is 4 for maxdict, 5 for maxarray, and 6 for the others. New in version 2.4: maxset, maxfrozenset, and set...

maxlong

Maximum number of characters in the representation for a long integer. Digits are dropped from the middle. The default is 40.

maxstring

Limit on the number of characters in the representation of the string. Note that the "normal" representation of the string is used as the character source: if escape sequences are needed in the representation, these may

be mangled when the representation is shortened. The default is 30.

maxother

This limit is used to control the size of object types for which no specific formatting method is available on the Repr object. It is applied in a similar manner as maxstring. The default is 20.

repr(obj)

The equivalent to the built-in repr() that uses the formatting imposed by the instance.

```
repr1(obj, level)
```

Recursive implementation used by repr(). This uses the type of *obj* to determine which formatting method to call, passing it *obj* and *level*. The type-specific methods should call repr1() to perform recursive formatting, with *level* - 1 for the value of *level* in the recursive call.

```
repr_type (obj, level)
```

Formatting methods for specific types are implemented as methods with a name based on the type name. In the method name, *type* is replaced by string.join(string.split(type(obj).__name__, '_')). Dispatch to these methods is handled by repr1(). Type-specific methods which need to recursively format a value should call 'self.repr1(subobj, level - 1)'.

3.28.2 Subclassing Repr Objects

The use of dynamic dispatching by Repr.repr1() allows subclasses of Repr to add support for additional built-in object types or to modify the handling of types already supported. This example shows how special support for file objects could be added:

```
import repr
import sys

class MyRepr(repr.Repr):
    def repr_file(self, obj, level):
        if obj.name in ['<stdin>', '<stdout>', '<stderr>']:
            return obj.name
        else:
            return 'obj'

aRepr = MyRepr()
print aRepr.repr(sys.stdin)  # prints '<stdin>'
```

3.29 new

If it is a string, the function will have the given name, otherwise the function name will be taken from *code*.co_name. If *argdefs* is given, it must be a tuple and will be used to determine the default values of parameters.

code (argcount, nlocals, stacksize, flags, codestring, constants, names, varnames, filename, name, firstlineno, lnotab)

This function is an interface to the PyCode_New() C function.

module(name)

This function returns a new module object with name name. name must be a string.

```
classobj(name, baseclasses, dict)
```

This function returns a new class object, with name *name*, derived from *baseclasses* (which should be a tuple of classes) and with namespace *dict*.

3.30 site — Site-specific configuration hook

This module is automatically imported during initialization. The automatic import can be suppressed using the interpreter's **-S** option.

Importing this module will append site-specific paths to the module search path.

It starts by constructing up to four directories from a head and a tail part. For the head part, it uses sys.prefix and sys.exec_prefix; empty heads are skipped. For the tail part, it uses the empty string (on Windows) or 'lib/python2.4/site-packages' (on UNIX and Macintosh) and then 'lib/site-python'. For each of the distinct head-tail combinations, it sees if it refers to an existing directory, and if so, adds it to sys.path and also inspects the newly added path for configuration files.

A path configuration file is a file whose name has the form 'package.pth' and exists in one of the four directories mentioned above; its contents are additional items (one per line) to be added to sys.path. Non-existing items are never added to sys.path, but no check is made that the item refers to a directory (rather than a file). No item is added to sys.path more than once. Blank lines and lines beginning with # are skipped. Lines starting with import are executed.

For example, suppose sys.prefix and sys.exec_prefix are set to '/usr/local'. The Python 2.4.2 library is then installed in '/usr/local/lib/python2.4' (where only the first three characters of sys.version are used to form the installation path name). Suppose this has a subdirectory '/usr/local/lib/python2.4/site-packages' with three subsubdirectories, 'foo', 'bar' and 'spam', and two path configuration files, 'foo.pth' and 'bar.pth'. Assume 'foo.pth' contains the following:

```
# foo package configuration
foo
bar
bletch
```

and 'bar.pth' contains:

```
# bar package configuration
bar
```

Then the following directories are added to sys.path, in this order:

```
/usr/local/lib/python2.3/site-packages/bar
/usr/local/lib/python2.3/site-packages/foo
```

Note that 'bletch' is omitted because it doesn't exist; the 'bar' directory precedes the 'foo' directory because

'bar.pth' comes alphabetically before 'foo.pth'; and 'spam' is omitted because it is not mentioned in either path configuration file.

After these path manipulations, an attempt is made to import a module named sitecustomize, which can perform arbitrary site-specific customizations. If this import fails with an ImportError exception, it is silently ignored.

Note that for some non-UNIX systems, sys.prefix and sys.exec_prefix are empty, and the path manipulations are skipped; however the import of sitecustomize is still attempted.

3.31 user — User-specific configuration hook

As a policy, Python doesn't run user-specified code on startup of Python programs. (Only interactive sessions execute the script specified in the PYTHONSTARTUP environment variable if it exists).

However, some programs or sites may find it convenient to allow users to have a standard customization file, which gets run when a program requests it. This module implements such a mechanism. A program that wishes to use the mechanism must execute the statement

```
import user
```

The user module looks for a file '.pythonrc.py' in the user's home directory and if it can be opened, executes it (using execfile()) in its own (the module user's) global namespace. Errors during this phase are not caught; that's up to the program that imports the user module, if it wishes. The home directory is assumed to be named by the HOME environment variable; if this is not set, the current directory is used.

The user's '.pythonrc.py' could conceivably test for sys.version if it wishes to do different things depending on the Python version.

A warning to users: be very conservative in what you place in your '.pythonrc.py' file. Since you don't know which programs will use it, changing the behavior of standard modules or functions is generally not a good idea.

A suggestion for programmers who wish to use this mechanism: a simple way to let users specify options for your package is to have them define variables in their '.pythonrc.py' file that you test in your module. For example, a module spam that has a verbosity level can look for a variable user.spam_verbose, as follows:

```
import user
verbose = bool(getattr(user, "spam_verbose", 0))
```

(The three-argument form of getattr() is used in case the user has not defined spam_verbose in their '.pythonrc.py' file.)

Programs with extensive customization needs are better off reading a program-specific customization file.

Programs with security or privacy concerns should *not* import this module; a user can easily break into a program by placing arbitrary code in the '.pythonrc.py' file.

Modules for general use should *not* import this module; it may interfere with the operation of the importing program.

See Also:

```
Module site (section 3.30):
```

Site-wide customization mechanism.

3.32 __builtin__ — Built-in objects

This module provides direct access to all 'built-in' identifiers of Python; for example, __builtin__.open is the full name for the built-in function open(). See chapter 2, "Built-in Objects."

This module is not normally accessed explicitly by most applications, but can be useful in modules that provide objects with the same name as a built-in value, but in which the built-in of that name is also needed. For example, in a module that wants to implement an open() function that wraps the built-in open(), this module can be used directly:

```
import __builtin__
def open(path):
    f = __builtin__.open(path, 'r')
    return UpperCaser(f)

class UpperCaser:
    '''Wrapper around a file that converts output to upper-case.'''

    def __init__(self, f):
        self._f = f

    def read(self, count=-1):
        return self._f.read(count).upper()

# ...
```

As an implementation detail, most modules have the name __builtins__ (note the 's') made available as part of their globals. The value of __builtins__ is normally either this module or the value of this modules's __dict__ attribute. Since this is an implementation detail, it may not be used by alternate implementations of Python.

3.33 __main__ — Top-level script environment

This module represents the (otherwise anonymous) scope in which the interpreter's main program executes — commands read either from standard input, from a script file, or from an interactive prompt. It is this environment in which the idiomatic "conditional script" stanza causes a script to run:

```
if __name__ == "__main__":
    main()
```

3.34 __future__ — Future statement definitions

__future__ is a real module, and serves three purposes:

- To avoid confusing existing tools that analyze import statements and expect to find the modules they're importing.
- To ensure that future_statements run under releases prior to 2.1 at least yield runtime exceptions (the import of __future__ will fail, because there was no module of that name prior to 2.1).
- To document when incompatible changes were introduced, and when they will be or were made mandatory. This is a form of executable documentation, and can be inspected programatically via importing __future__ and examining its contents.

Each statement in '__future__.py' is of the form:

```
FeatureName = "_Feature(" OptionalRelease "," MandatoryRelease "," CompilerFlag ")"
```

where, normally, *OptionalRelease* is less than *MandatoryRelease*, and both are 5-tuples of the same form as sys.version_info:

```
(PY_MAJOR_VERSION, # the 2 in 2.1.0a3; an int
PY_MINOR_VERSION, # the 1; an int
PY_MICRO_VERSION, # the 0; an int
PY_RELEASE_LEVEL, # "alpha", "beta", "candidate" or "final"; string
PY_RELEASE_SERIAL # the 3; an int
)
```

OptionalRelease records the first release in which the feature was accepted.

In the case of a *MandatoryRelease* that has not yet occurred, *MandatoryRelease* predicts the release in which the feature will become part of the language.

Else *MandatoryRelease* records when the feature became part of the language; in releases at or after that, modules no longer need a future statement to use the feature in question, but may continue to use such imports.

MandatoryRelease may also be None, meaning that a planned feature got dropped.

Instances of class _Feature have two corresponding methods, getOptionalRelease() and getMandatoryRelease().

CompilerFlag is the (bitfield) flag that should be passed in the fourth argument to the builtin function <code>compile()</code> to enable the feature in dynamically compiled code. This flag is stored in the <code>compiler_flag</code> attribute on <code>_Future</code> instances.

No feature description will ever be deleted from __future__.

String Services

The modules described in this chapter provide a wide range of string manipulation operations. Here's an overview:

string Common string operations.

re Regular expression search and match operations with a Perl-style expression syntax.

struct Interpret strings as packed binary data.

difflib Helpers for computing differences between objects.

fpformat General floating point formatting functions. **StringIO** Read and write strings as if they were files.

cStringIO Faster version of StringIO, but not subclassable.

textwrap Text wrapping and filling

encodings.idna Internationalized Domain Names implementation

unicodedata Access the Unicode Database.

stringprep String preparation, as per RFC 3453

Information on the methods of string objects can be found in section 2.3.6, "String Methods."

4.1 string — Common string operations

The string module contains a number of useful constants and classes, as well as some deprecated legacy functions that are also available as methods on strings. See the module re for string functions based on regular expressions.

4.1.1 String constants

The constants defined in this module are:

ascii_letters

The concatenation of the ascii_lowercase and ascii_uppercase constants described below. This value is not locale-dependent.

$ascii_lowercase$

The lowercase letters 'abcdefghijklmnopqrstuvwxyz'. This value is not locale-dependent and will not change.

ascii_uppercase

The uppercase letters 'ABCDEFGHIJKLMNOPQRSTUVWXYZ'. This value is not locale-dependent and will not change.

digits

The string '0123456789'.

hexdigits

The string '0123456789abcdefABCDEF'.

letters

The concatenation of the strings lowercase and uppercase described below. The specific value is

locale-dependent, and will be updated when locale.setlocale() is called.

lowercase

A string containing all the characters that are considered lowercase letters. On most systems this is the string 'abcdefghijklmnopqrstuvwxyz'. Do not change its definition — the effect on the routines upper() and swapcase() is undefined. The specific value is locale-dependent, and will be updated when locale.setlocale() is called.

octdigits

The string '01234567'.

punctuation

String of ASCII characters which are considered punctuation characters in the 'C' locale.

printable

String of characters which are considered printable. This is a combination of digits, letters, punctuation, and whitespace.

uppercase

A string containing all the characters that are considered uppercase letters. On most systems this is the string 'ABCDEFGHIJKLMNOPQRSTUVWXYZ'. Do not change its definition — the effect on the routines lower() and swapcase() is undefined. The specific value is locale-dependent, and will be updated when locale.setlocale() is called.

whitespace

A string containing all characters that are considered whitespace. On most systems this includes the characters space, tab, linefeed, return, formfeed, and vertical tab. Do not change its definition — the effect on the routines strip() and split() is undefined.

4.1.2 Template strings

Templates provide simpler string substitutions as described in PEP 292. Instead of the normal '%'-based substitutions, Templates support '\$'-based substitutions, using the following rules:

- '\$\$' is an escape; it is replaced with a single '\$'.
- '\$identifier' names a substitution placeholder matching a mapping key of "identifier". By default, "identifier" must spell a Python identifier. The first non-identifier character after the '\$' character terminates this placeholder specification.
- '\${identifier}' is equivalent to '\$identifier'. It is required when valid identifier characters follow the placeholder but are not part of the placeholder, such as "\${noun}ification".

Any other appearance of '\$' in the string will result in a ValueError being raised.

New in version 2.4.

The string module provides a Template class that implements these rules. The methods of Template are:

class Template (template)

The constructor takes a single argument which is the template string.

substitute(mapping[, **kws])

Performs the template substitution, returning a new string. *mapping* is any dictionary-like object with keys that match the placeholders in the template. Alternatively, you can provide keyword arguments, where the keywords are the placeholders. When both *mapping* and *kws* are given and there are duplicates, the placeholders from *kws* take precedence.

safe_substitute(mapping[, **kws])

Like substitute(), except that if placeholders are missing from *mapping* and *kws*, instead of raising a KeyError exception, the original placeholder will appear in the resulting string intact. Also, unlike with substitute(), any other appearances of the '\$' will simply return '\$' instead of raising ValueError.

While other exceptions may still occur, this method is called "safe" because substitutions always tries to return a usable string instead of raising an exception. In another sense, safe_substitute() may be

anything other than safe, since it will silently ignore malformed templates containing dangling delimiters, unmatched braces, or placeholders that are not valid Python identifiers.

Template instances also provide one public data attribute:

template

This is the object passed to the constructor's *template* argument. In general, you shouldn't change it, but read-only access is not enforced.

Here is an example of how to use a Template:

```
>>> from string import Template
>>> s = Template('$who likes $what')
>>> s.substitute(who='tim', what='kung pao')
'tim likes kung pao'
>>> d = dict(who='tim')
>>> Template('Give $who $100').substitute(d)
Traceback (most recent call last):
[...]
ValueError: Invalid placeholder in string: line 1, col 10
>>> Template('$who likes $what').substitute(d)
Traceback (most recent call last):
[...]
KeyError: 'what'
>>> Template('$who likes $what').safe_substitute(d)
'tim likes $what'
```

Advanced usage: you can derive subclasses of Template to customize the placeholder syntax, delimiter character, or the entire regular expression used to parse template strings. To do this, you can override these class attributes:

- *delimiter* This is the literal string describing a placeholder introducing delimiter. The default value '\$'. Note that this should *not* be a regular expression, as the implementation will call re.escape() on this string as needed.
- *idpattern* This is the regular expression describing the pattern for non-braced placeholders (the braces will be added automatically as appropriate). The default value is the regular expression '[_a-z][_a-z0-9]*'.

Alternatively, you can provide the entire regular expression pattern by overriding the class attribute *pattern*. If you do this, the value must be a regular expression object with four named capturing groups. The capturing groups correspond to the rules given above, along with the invalid placeholder rule:

- escaped This group matches the escape sequence, e.g. '\$\$', in the default pattern.
- *named* This group matches the unbraced placeholder name; it should not include the delimiter in capturing group.
- *braced* This group matches the brace enclosed placeholder name; it should not include either the delimiter or braces in the capturing group.
- *invalid* This group matches any other delimiter pattern (usually a single delimiter), and it should appear last in the regular expression.

4.1.3 String functions

The following functions are available to operate on string and Unicode objects. They are not available as string methods.

capwords(s)

Split the argument into words using split(), capitalize each word using capitalize(), and join the capitalized words using join(). Note that this replaces runs of whitespace characters by a single space, and removes leading and trailing whitespace.

maketrans(from, to)

Return a translation table suitable for passing to translate() or regex.compile(), that will map each character in *from* into the character at the same position in *to*; *from* and *to* must have the same length.

Warning: Don't use strings derived from lowercase and uppercase as arguments; in some locales, these don't have the same length. For case conversions, always use lower() and upper().

4.1.4 Deprecated string functions

The following list of functions are also defined as methods of string and Unicode objects; see "String Methods" (section 2.3.6) for more information on those. You should consider these functions as deprecated, although they will not be removed until Python 3.0. The functions defined in this module are:

atof(s)

Deprecated since release 2.0. Use the float() built-in function.

Convert a string to a floating point number. The string must have the standard syntax for a floating point literal in Python, optionally preceded by a sign ('+' or '-'). Note that this behaves identical to the built-in function float() when passed a string.

Note: When passing in a string, values for NaN and Infinity may be returned, depending on the underlying C library. The specific set of strings accepted which cause these values to be returned depends entirely on the C library and is known to vary.

atoi(s[, base])

Deprecated since release 2.0. Use the int() built-in function.

Convert string s to an integer in the given *base*. The string must consist of one or more digits, optionally preceded by a sign ('+' or '-'). The *base* defaults to 10. If it is 0, a default base is chosen depending on the leading characters of the string (after stripping the sign): '0x' or '0x' means 16, '0' means 8, anything else means 10. If *base* is 16, a leading '0x' or '0x' is always accepted, though not required. This behaves identically to the built-in function int() when passed a string. (Also note: for a more flexible interpretation of numeric literals, use the built-in function eval().)

```
atol(s[,base])
```

Deprecated since release 2.0. Use the long() built-in function.

Convert string s to a long integer in the given base. The string must consist of one or more digits, optionally preceded by a sign ('+' or '-'). The base argument has the same meaning as for atoi(). A trailing 'l' or 'L' is not allowed, except if the base is 0. Note that when invoked without base or with base set to 10, this behaves identical to the built-in function long() when passed a string.

capitalize(word)

Return a copy of word with only its first character capitalized.

```
expandtabs(s, tabsize)
```

Expand tabs in a string replacing them by one or more spaces, depending on the current column and the given tab size. The column number is reset to zero after each newline occurring in the string. This doesn't understand other non-printing characters or escape sequences. The tab size defaults to 8.

```
find(s, sub[, start[,end]])
```

Return the lowest index in s where the substring sub is found such that sub is wholly contained in s[start:end]. Return -1 on failure. Defaults for start and end and interpretation of negative values is the same as for slices.

```
rfind(s, sub[, start[, end]])
```

Like find() but find the highest index.

```
index(s, sub[, start[, end]])
```

Like find() but raise ValueError when the substring is not found.

rindex(s, sub[, start[, end]])

Like rfind() but raise ValueError when the substring is not found.

count(s, sub[, start[, end]])

Return the number of (non-overlapping) occurrences of substring sub in string s[start:end]. Defaults for start and end and interpretation of negative values are the same as for slices.

lower(s)

Return a copy of s, but with upper case letters converted to lower case.

split(s[, sep[, maxsplit]])

Return a list of the words of the string s. If the optional second argument sep is absent or None, the words are separated by arbitrary strings of whitespace characters (space, tab, newline, return, formfeed). If the second argument sep is present and not None, it specifies a string to be used as the word separator. The returned list will then have one more item than the number of non-overlapping occurrences of the separator in the string. The optional third argument maxsplit defaults to 0. If it is nonzero, at most maxsplit number of splits occur, and the remainder of the string is returned as the final element of the list (thus, the list will have at most maxsplit+1 elements).

The behavior of split on an empty string depends on the value of *sep*. If *sep* is not specified, or specified as None, the result will be an empty list. If *sep* is specified as any string, the result will be a list containing one element which is an empty string.

rsplit(s[, sep[, maxsplit]])

Return a list of the words of the string s, scanning s from the end. To all intents and purposes, the resulting list of words is the same as returned by $\mathtt{split}()$, except when the optional third argument maxsplit is explicitly specified and nonzero. When maxsplit is nonzero, at most maxsplit number of splits – the rightmost ones – occur, and the remainder of the string is returned as the first element of the list (thus, the list will have at most maxsplit+1 elements). New in version 2.4.

splitfields(s[, sep[, maxsplit]])

This function behaves identically to split(). (In the past, split() was only used with one argument, while splitfields() was only used with two arguments.)

join(words[, sep])

Concatenate a list or tuple of words with intervening occurrences of *sep*. The default value for *sep* is a single space character. It is always true that 'string.join(string.split(s, sep), sep)' equals s.

joinfields(words[, sep])

This function behaves identically to join(). (In the past, join() was only used with one argument, while joinfields() was only used with two arguments.) Note that there is no joinfields() method on string objects; use the join() method instead.

lstrip(s[, chars])

Return a copy of the string with leading characters removed. If *chars* is omitted or None, whitespace characters are removed. If given and not None, *chars* must be a string; the characters in the string will be stripped from the beginning of the string this method is called on. Changed in version 2.2.3: The *chars* parameter was added. The *chars* parameter cannot be passed in earlier 2.2 versions.

rstrip(s[, chars])

Return a copy of the string with trailing characters removed. If *chars* is omitted or None, whitespace characters are removed. If given and not None, *chars* must be a string; the characters in the string will be stripped from the end of the string this method is called on. Changed in version 2.2.3: The *chars* parameter was added. The *chars* parameter cannot be passed in earlier 2.2 versions.

strip(s[, chars])

Return a copy of the string with leading and trailing characters removed. If *chars* is omitted or None, whitespace characters are removed. If given and not None, *chars* must be a string; the characters in the string will be stripped from the both ends of the string this method is called on. Changed in version 2.2.3: The *chars* parameter was added. The *chars* parameter cannot be passed in earlier 2.2 versions.

swapcase(s)

Return a copy of s, but with lower case letters converted to upper case and vice versa.

```
translate(s, table[, deletechars])
```

Delete all characters from s that are in *deletechars* (if present), and then translate the characters using *table*, which must be a 256-character string giving the translation for each character value, indexed by its ordinal.

upper(s)

Return a copy of s, but with lower case letters converted to upper case.

```
ljust(s, width)
rjust(s, width)
center(s, width)
```

These functions respectively left-justify, right-justify and center a string in a field of given width. They return a string that is at least *width* characters wide, created by padding the string s with spaces until the given width on the right, left or both sides. The string is never truncated.

```
zfill(s, width)
```

Pad a numeric string on the left with zero digits until the given width is reached. Strings starting with a sign are handled correctly.

```
replace(str, old, new[, maxreplace])
```

Return a copy of string *str* with all occurrences of substring *old* replaced by *new*. If the optional argument *maxreplace* is given, the first *maxreplace* occurrences are replaced.

4.2 re — Regular expression operations

This module provides regular expression matching operations similar to those found in Perl. Regular expression pattern strings may not contain null bytes, but can specify the null byte using the \number notation. Both patterns and strings to be searched can be Unicode strings as well as 8-bit strings. The re module is always available.

Regular expressions use the backslash character ('\') to indicate special forms or to allow special characters to be used without invoking their special meaning. This collides with Python's usage of the same character for the same purpose in string literals; for example, to match a literal backslash, one might have to write '\\\' as the pattern string, because the regular expression must be '\\', and each backslash must be expressed as '\\' inside a regular Python string literal.

The solution is to use Python's raw string notation for regular expression patterns; backslashes are not handled in any special way in a string literal prefixed with 'r'. So $r"\n"$ is a two-character string containing '\' and 'n', while "\n" is a one-character string containing a newline. Usually patterns will be expressed in Python code using this raw string notation.

See Also:

Mastering Regular Expressions

Book on regular expressions by Jeffrey Friedl, published by O'Reilly. The second edition of the book no longer covers Python at all, but the first edition covered writing good regular expression patterns in great detail.

4.2.1 Regular Expression Syntax

A regular expression (or RE) specifies a set of strings that matches it; the functions in this module let you check if a particular string matches a given regular expression (or if a given regular expression matches a particular string, which comes down to the same thing).

Regular expressions can be concatenated to form new regular expressions; if A and B are both regular expressions, then AB is also a regular expression. In general, if a string p matches A and another string q matches B, the string pq will match AB. This holds unless A or B contain low precedence operations; boundary conditions between A and B; or have numbered group references. Thus, complex expressions can easily be constructed from simpler primitive expressions like the ones described here. For details of the theory and implementation of regular expressions, consult the Friedl book referenced above, or almost any textbook about compiler construction.

A brief explanation of the format of regular expressions follows. For further information and a gentler presentation, consult the Regular Expression HOWTO, accessible from http://www.python.org/doc/howto/.

Regular expressions can contain both special and ordinary characters. Most ordinary characters, like 'A', 'a', or '0', are the simplest regular expressions; they simply match themselves. You can concatenate ordinary characters, so <code>last</code> matches the string 'last'. (In the rest of this section, we'll write RE's in <code>this special style</code>, usually without quotes, and strings to be matched 'in single quotes'.)

Some characters, like '|' or '(', are special. Special characters either stand for classes of ordinary characters, or affect how the regular expressions around them are interpreted.

The special characters are:

- **'.'** (Dot.) In the default mode, this matches any character except a newline. If the DOTALL flag has been specified, this matches any character including a newline.
- '^' (Caret.) Matches the start of the string, and in MULTILINE mode also matches immediately after each newline.
- '\$' Matches the end of the string or just before the newline at the end of the string, and in MULTILINE mode also matches before a newline.

 [foo] matches both 'foo' and 'foobar', while the regular expression

 [foo\$] matches only 'foo'. More interestingly, searching for

 [foo.\$] in 'foo1\nfoo2\n' matches 'foo2' normally, but 'foo1' in MULTILINE mode.
- '*' Causes the resulting RE to match 0 or more repetitions of the preceding RE, as many repetitions as are possible. [ab*] will match 'a', 'ab', or 'a' followed by any number of 'b's.
- '+' Causes the resulting RE to match 1 or more repetitions of the preceding RE. [ab+] will match 'a' followed by any non-zero number of 'b's; it will not match just 'a'.
- '?' Causes the resulting RE to match 0 or 1 repetitions of the preceding RE. [ab?] will match either 'a' or 'ab'.
- *?, +?, ?? The '*', '+', and '?' qualifiers are all *greedy*; they match as much text as possible. Sometimes this behaviour isn't desired; if the RE [<.*>] is matched against '<H1>title</H1>', it will match the entire string, and not just '<H1>'. Adding '?' after the qualifier makes it perform the match in *non-greedy* or *minimal* fashion; as *few* characters as possible will be matched. Using [.*?] in the previous expression will match only '<H1>'.
- $\{m\}$ Specifies that exactly m copies of the previous RE should be matched; fewer matches cause the entire RE not to match. For example, $[a\{6\}]$ will match exactly six 'a' characters, but not five.
- $\{m,n\}$ Causes the resulting RE to match from m to n repetitions of the preceding RE, attempting to match as many repetitions as possible. For example, $[a\{3,5\}]$ will match from 3 to 5 'a' characters. Omitting m specifies a lower bound of zero, and omitting n specifies an infinite upper bound. As an example, $[a\{4,\}b]$ will match aaaab or a thousand 'a' characters followed by a b, but not aaab. The comma may not be omitted or the modifier would be confused with the previously described form.
- $\{m,n\}$? Causes the resulting RE to match from m to n repetitions of the preceding RE, attempting to match as few repetitions as possible. This is the non-greedy version of the previous qualifier. For example, on the 6-character string 'aaaaaa', $[a\{3,5\}]$ will match 5 'a' characters, while $[a\{3,5\}]$ will only match 3 characters.
- '\' Either escapes special characters (permitting you to match characters like '*', '?', and so forth), or signals a special sequence; special sequences are discussed below.
 - If you're not using a raw string to express the pattern, remember that Python also uses the backslash as an escape sequence in string literals; if the escape sequence isn't recognized by Python's parser, the backslash and subsequent character are included in the resulting string. However, if Python would recognize the resulting sequence, the backslash should be repeated twice. This is complicated and hard to understand, so it's highly recommended that you use raw strings for all but the simplest expressions.
- [] Used to indicate a set of characters. Characters can be listed individually, or a range of characters can be indicated by giving two characters and separating them by a '-'. Special characters are not active inside sets. For example, <code>[akm\$]_j</code> will match any of the characters 'a', 'k', 'm', or '\$'; <code>[a-z]_j</code> will match any lowercase letter, and <code>[a-zA-Z0-9]</code> matches any letter or digit. Character classes such as <code>\w</code> or <code>\S</code> (defined below) are also acceptable inside a range. If you want to include a ']' or a '-' inside a set, precede it with a backslash, or place it as the first character. The pattern <code>[]]_j</code> will match ']', for example.

You can match the characters not within a range by *complementing* the set. This is indicated by including a ' $^{^{\circ}}$ ' as the first character of the set; ' $^{^{\circ}}$ ' elsewhere will simply match the ' $^{^{\circ}}$ ' character. For example, $\lceil \lceil ^{\circ} \rceil \rfloor$ will match any character except ' $^{\circ}$ ', and $\lceil \lceil ^{\circ} \rceil \rfloor$ will match any character except ' $^{\circ}$ '.

- '|' A|B, where A and B can be arbitrary REs, creates a regular expression that will match either A or B. An arbitrary number of REs can be separated by the '|' in this way. This can be used inside groups (see below) as well. As the target string is scanned, REs separated by '|' are tried from left to right. When one pattern completely matches, that branch is accepted. This means that once A matches, B will not be tested further, even if it would produce a longer overall match. In other words, the '|' operator is never greedy. To match a literal '|', use [\], or enclose it inside a character class, as in [[]].
- (...) Matches whatever regular expression is inside the parentheses, and indicates the start and end of a group;

```
>>> import re
>>> m = re.search('(?<=abc)def', 'abcdef')
>>> m.group(0)
'def'
```

This example looks for a word following a hyphen:

```
>>> m = re.search('(?<=-)\w+', 'spam-egg')
>>> m.group(0)
'egg'
```

- (?<!...) Matches if the current position in the string is not preceded by a match for [...]. This is called a *negative lookbehind assertion*. Similar to positive lookbehind assertions, the contained pattern must only match strings of some fixed length. Patterns which start with negative lookbehind assertions may match at the beginning of the string being searched.
- (?(id/name)yes-pattern|no-pattern) Will try to match with <code>[yes-pattern]</code> if the group with given id or name exists, and with <code>[no-pattern]</code> if it doesn't. <code>[|no-pattern]</code> is optional and can be omitted. For example, <code>[(<)?(\w+@\w+(?:\.\w+)+)(?(1)>)]</code> is a poor email matching pattern, which will match with '<user@host.com', but not with '<user@host.com'. New in version 2.4.

The special sequences consist of '\' and a character from the list below. If the ordinary character is not on the list, then the resulting RE will match the second character. For example, $\lceil \ \ \ \ \rceil$ matches the character '\$'.

- **\A** Matches only at the start of the string.
- \b Matches the empty string, but only at the beginning or end of a word. A word is defined as a sequence of alphanumeric or underscore characters, so the end of a word is indicated by whitespace or a non-alphanumeric, non-underscore character. Note that \b is defined as the boundary between \w and \W, so the precise set of characters deemed to be alphanumeric depends on the values of the UNICODE and LOCALE flags. Inside a character range, \b represents the backspace character, for compatibility with Python's string literals.
- \B Matches the empty string, but only when it is *not* at the beginning or end of a word. This is just the opposite of \b, so is also subject to the settings of LOCALE and UNICODE.
- \d When the UNICODE flag is not specified, matches any decimal digit; this is equivalent to the set [0-9]. With UNICODE, it will match whatever is classified as a digit in the Unicode character properties database.
- **\D** When the UNICODE flag is not specified, matches any non-digit character; this is equivalent to the set <code>[^0-9]</code>. With UNICODE, it will match anything other than character marked as digits in the Unicode character properties database.
- \s When the LOCALE and UNICODE flags are not specified, matches any whitespace character; this is equivalent to the set \[\t\n\r\f\v]_\]. With LOCALE, it will match this set plus whatever characters are defined as space for the current locale. If UNICODE is set, this will match the characters \[\t\n\r\f\v]_\] plus whatever is classified as space in the Unicode character properties database.
- \\$ When the LOCALE and UNICODE flags are not specified, matches any non-whitespace character; this is equivalent to the set $\lceil \lceil \frac{t \cdot r \cdot r \cdot r}{v} \rfloor$ With LOCALE, it will match any character not in this set, and not defined as space in the current locale. If UNICODE is set, this will match anything other than $\lceil \lfloor \frac{t \cdot r}{v} \rfloor$ and characters marked as space in the Unicode character properties database.

- \w When the LOCALE and UNICODE flags are not specified, matches any alphanumeric character and the underscore; this is equivalent to the set \[[a-zA-Z0-9_] \]. With LOCALE, it will match the set \[[0-9_] \] plus whatever characters are defined as alphanumeric for the current locale. If UNICODE is set, this will match the characters \[[0-9_] \] plus whatever is classified as alphanumeric in the Unicode character properties database.
- When the LOCALE and UNICODE flags are not specified, matches any non-alphanumeric character; this is equivalent to the set [[a-zA-Z0-9_]]. With LOCALE, it will match any character not in the set [0-9_]], and not defined as alphanumeric for the current locale. If UNICODE is set, this will match anything other than [0-9_]] and characters marked as alphanumeric in the Unicode character properties database.
- **\Z** Matches only at the end of the string.

Most of the standard escapes supported by Python string literals are also accepted by the regular expression parser:

Octal escapes are included in a limited form: If the first digit is a 0, or if there are three octal digits, it is considered an octal escape. Otherwise, it is a group reference. As for string literals, octal escapes are always at most three digits in length.

4.2.2 Matching vs Searching

Python offers two different primitive operations based on regular expressions: match and search. If you are accustomed to Perl's semantics, the search operation is what you're looking for. See the search() function and corresponding method of compiled regular expression objects.

Note that match may differ from search using a regular expression beginning with '^': '^' matches only at the start of the string, or in MULTILINE mode also immediately following a newline. The "match" operation succeeds only if the pattern matches at the start of the string regardless of mode, or at the starting position given by the optional *pos* argument regardless of whether a newline precedes it.

4.2.3 Module Contents

The module defines several functions, constants, and an exception. Some of the functions are simplified versions of the full featured methods for compiled regular expressions. Most non-trivial applications always use the compiled form

```
compile(pattern[, flags])
```

Compile a regular expression pattern into a regular expression object, which can be used for matching using its match() and search() methods, described below.

The expression's behaviour can be modified by specifying a *flags* value. Values can be any of the following variables, combined using bitwise OR (the | operator).

The sequence

```
prog = re.compile(pat)
result = prog.match(str)
```

is equivalent to

```
result = re.match(pat, str)
```

but the version using compile() is more efficient when the expression will be used several times in a single program.

т

IGNORECASE

Perform case-insensitive matching; expressions like $\lceil [A-Z] \rfloor$ will match lowercase letters, too. This is not affected by the current locale.

L

LOCALE

Make $\wbegin{align*}[t]{ll} \end{align*} \end{align*} \begin{align*}[t]{ll} \end{ali$

М

MULTILINE

When specified, the pattern character '^' matches at the beginning of the string and at the beginning of each line (immediately following each newline); and the pattern character '\$' matches at the end of the string and at the end of each line (immediately preceding each newline). By default, '^' matches only at the beginning of the string, and '\$' only at the end of the string and immediately before the newline (if any) at the end of the string.

S

DOTALL

Make the '.' special character match any character at all, including a newline; without this flag, '.' will match anything *except* a newline.

TT

UNICODE

Make $\[\] w_j, \] \[\] w_j, \] \[\] w_j, \] \[\] w_j, \]$

Х

VERBOSE

This flag allows you to write regular expressions that look nicer. Whitespace within the pattern is ignored, except when in a character class or preceded by an unescaped backslash, and, when a line contains a '#' neither in a character class or preceded by an unescaped backslash, all characters from the leftmost such '#' through the end of the line are ignored.

search(pattern, string[, flags])

Scan through *string* looking for a location where the regular expression *pattern* produces a match, and return a corresponding MatchObject instance. Return None if no position in the string matches the pattern; note that this is different from finding a zero-length match at some point in the string.

match(pattern, string[, flags])

If zero or more characters at the beginning of *string* match the regular expression *pattern*, return a corresponding MatchObject instance. Return None if the string does not match the pattern; note that this is different from a zero-length match.

Note: If you want to locate a match anywhere in *string*, use search() instead.

split(pattern, string[, maxsplit = 0])

Split *string* by the occurrences of *pattern*. If capturing parentheses are used in *pattern*, then the text of all groups in the pattern are also returned as part of the resulting list. If *maxsplit* is nonzero, at most *maxsplit* splits occur, and the remainder of the string is returned as the final element of the list. (Incompatibility note: in the original Python 1.5 release, *maxsplit* was ignored. This has been fixed in later releases.)

```
>>> re.split('\W+', 'Words, words, words.')
['Words', 'words', 'v]
>>> re.split('(\W+)', 'Words, words, words.')
['Words', ', ', 'words', ', ', 'words', '.', '']
>>> re.split('\W+', 'Words, words, words.', 1)
['Words', 'words, words.']
```

This function combines and extends the functionality of the old regsub.split() and regsub.splitx().

findall(pattern, string[, flags])

Return a list of all non-overlapping matches of *pattern* in *string*. If one or more groups are present in the pattern, return a list of groups; this will be a list of tuples if the pattern has more than one group. Empty matches are included in the result unless they touch the beginning of another match. New in version 1.5.2. Changed in version 2.4: Added the optional flags argument.

finditer(pattern, string[, flags])

Return an iterator over all non-overlapping matches for the RE *pattern* in *string*. For each match, the iterator returns a match object. Empty matches are included in the result unless they touch the beginning of another match. New in version 2.2. Changed in version 2.4: Added the optional flags argument.

```
sub(pattern, repl, string[, count])
```

Return the string obtained by replacing the leftmost non-overlapping occurrences of *pattern* in *string* by the replacement *repl*. If the pattern isn't found, *string* is returned unchanged. *repl* can be a string or a function; if it is a string, any backslash escapes in it are processed. That is, '\n' is converted to a single newline character, '\r' is converted to a linefeed, and so forth. Unknown escapes such as '\j' are left alone. Backreferences, such as '\6', are replaced with the substring matched by group 6 in the pattern. For example:

If *repl* is a function, it is called for every non-overlapping occurrence of *pattern*. The function takes a single match object argument, and returns the replacement string. For example:

```
>>> def dashrepl(matchobj):
...    if matchobj.group(0) == '-': return ' '
...    else: return '-'
>>> re.sub('-{1,2}', dashrepl, 'pro---gram-files')
'pro--gram files'
```

The pattern may be a string or an RE object; if you need to specify regular expression flags, you must use a RE object, or use embedded modifiers in a pattern; for example, 'sub("(?i)b+", "x", "bbbb BBBB")' returns 'x x'.

The optional argument *count* is the maximum number of pattern occurrences to be replaced; *count* must be a non-negative integer. If omitted or zero, all occurrences will be replaced. Empty matches for the pattern are replaced only when not adjacent to a previous match, so 'sub('x*'', '-', 'abc')' returns '-a-b-c-'.

In addition to character escapes and backreferences as described above, '\g<name>' will use the substring matched by the group named 'name', as defined by the $\lceil (?P<name>...) \rfloor$ syntax. '\g<number>' uses the corresponding group number; '\g<2>' is therefore equivalent to '\2', but isn't ambiguous in a replacement such as '\g<2>0'. '\20' would be interpreted as a reference to group 20, not a reference to group 2 followed by the literal character '0'. The backreference '\g<0>' substitutes in the entire substring matched by the RE.

```
subn(pattern, repl, string[, count])
```

Perform the same operation as sub(), but return a tuple (new_string, number_of_subs_made).

escape(string)

Return *string* with all non-alphanumerics backslashed; this is useful if you want to match an arbitrary literal string that may have regular expression metacharacters in it.

exception error

Exception raised when a string passed to one of the functions here is not a valid regular expression (for example, it might contain unmatched parentheses) or when some other error occurs during compilation or matching. It is never an error if a string contains no match for a pattern.

4.2.4 Regular Expression Objects

Compiled regular expression objects support the following methods and attributes:

```
match(string[, pos[, endpos]])
```

If zero or more characters at the beginning of *string* match this regular expression, return a corresponding MatchObject instance. Return None if the string does not match the pattern; note that this is different from a zero-length match.

Note: If you want to locate a match anywhere in *string*, use search() instead.

The optional second parameter *pos* gives an index in the string where the search is to start; it defaults to 0. This is not completely equivalent to slicing the string; the '^' pattern character matches at the real beginning of the string and at positions just after a newline, but not necessarily at the index where the search is to start.

The optional parameter *endpos* limits how far the string will be searched; it will be as if the string is *endpos* characters long, so only the characters from *pos* to *endpos* – 1 will be searched for a match. If *endpos* is less than *pos*, no match will be found, otherwise, if rx is a compiled regular expression object, rx.match(string, 0, 50) is equivalent to rx.match(string[:50], 0).

```
search(string[, pos[, endpos]])
```

Scan through *string* looking for a location where this regular expression produces a match, and return a corresponding MatchObject instance. Return None if no position in the string matches the pattern; note that this is different from finding a zero-length match at some point in the string.

The optional pos and endpos parameters have the same meaning as for the match () method.

```
split(string[, maxsplit = 0])
```

Identical to the split() function, using the compiled pattern.

```
findall(string[, pos[, endpos]])
```

Identical to the findall() function, using the compiled pattern.

```
finditer(string[, pos[, endpos]])
```

Identical to the finditer() function, using the compiled pattern.

```
sub(repl, string[, count = 0])
```

Identical to the sub() function, using the compiled pattern.

```
subn(repl, string[, count = 0])
```

Identical to the subn () function, using the compiled pattern.

flags

The flags argument used when the RE object was compiled, or 0 if no flags were provided.

groupindex

A dictionary mapping any symbolic group names defined by $\lceil (?P < id >) \rfloor$ to group numbers. The dictionary is empty if no symbolic groups were used in the pattern.

pattern

The pattern string from which the RE object was compiled.

4.2.5 Match Objects

MatchObject instances support the following methods and attributes:

expand(template)

Return the string obtained by doing backslash substitution on the template string *template*, as done by the sub() method. Escapes such as '\n' are converted to the appropriate characters, and numeric backreferences ('\1', '\2') and named backreferences ('\g<1>', '\g<name>') are replaced by the contents of the corresponding group.

group([group1, ...])

Returns one or more subgroups of the match. If there is a single argument, the result is a single string; if there are multiple arguments, the result is a tuple with one item per argument. Without arguments, group1 defaults to zero (the whole match is returned). If a groupN argument is zero, the corresponding return value is the entire matching string; if it is in the inclusive range [1..99], it is the string matching the corresponding parenthesized group. If a group number is negative or larger than the number of groups defined in the pattern, an Indexerror exception is raised. If a group is contained in a part of the pattern that did not match, the corresponding result is None. If a group is contained in a part of the pattern that matched multiple times, the last match is returned.

If the regular expression uses the $\lceil (?P < name > ...) \rceil$ syntax, the *groupN* arguments may also be strings identifying groups by their group name. If a string argument is not used as a group name in the pattern, an IndexError exception is raised.

A moderately complicated example:

```
m = re.match(r"(?P<int>\d+)\.(\d*)", '3.14')
```

After performing this match, m.group(1) is '3', as is m.group('int'), and m.group(2) is '14'.

groups([default])

Return a tuple containing all the subgroups of the match, from 1 up to however many groups are in the pattern. The *default* argument is used for groups that did not participate in the match; it defaults to None. (Incompatibility note: in the original Python 1.5 release, if the tuple was one element long, a string would be returned instead. In later versions (from 1.5.1 on), a singleton tuple is returned in such cases.)

groupdict([default])

Return a dictionary containing all the *named* subgroups of the match, keyed by the subgroup name. The *default* argument is used for groups that did not participate in the match; it defaults to None.

```
start([group])
end([group])
```

Return the indices of the start and end of the substring matched by group; group defaults to zero (meaning the whole matched substring). Return -1 if group exists but did not contribute to the match. For a match object m, and a group g that did contribute to the match, the substring matched by group g (equivalent to m. group (g)) is

```
m.string[m.start(g):m.end(g)]
```

Note that m.start(group) will equal m.end(group) if group matched a null string. For example, after m = re.search('b(c?)', 'cba'), m.start(0) is 1, m.end(0) is 2, m.start(1) and m.end(1) are both 2, and m.start(2) raises an IndexError exception.

span([group])

For MatchObject m, return the 2-tuple (m.start(group), m.end(group)). Note that if group did not contribute to the match, this is (-1, -1). Again, group defaults to zero.

pos

The value of *pos* which was passed to the search() or match() method of the RegexObject. This is the index into the string at which the RE engine started looking for a match.

endpos

The value of *endpos* which was passed to the search() or match() method of the RegexObject. This is the index into the string beyond which the RE engine will not go.

lastindex

The integer index of the last matched capturing group, or None if no group was matched at all. For example,

the expressions $\lceil (a)b_j, \lceil ((a)(b))_j, \text{ and } \lceil ((ab))_j \text{ will have lastindex} == 1 if applied to the string 'ab', while the expression <math>\lceil (a)(b)_j \text{ will have lastindex} == 2$, if applied to the same string.

lastgroup

The name of the last matched capturing group, or None if the group didn't have a name, or if no group was matched at all.

re

The regular expression object whose match() or search() method produced this MatchObject instance.

string

The string passed to match() or search().

4.2.6 Examples

Simulating scanf()

Python does not currently have an equivalent to scanf(). Regular expressions are generally more powerful, though also more verbose, than scanf() format strings. The table below offers some more-or-less equivalent mappings between scanf() format tokens and regular expressions.

scanf() Token	Regular Expression
%C	[.]
%5c	[.{5}]
%d	[[-+]?\d+]
%e, %E, %f, %g	[[-+]?(\d+(\.\d*)? \d*\.\d+)([eE][-+]?\d+)?
%i	[[-+]?(0[xX][\dA-Fa-f]+ 0[0-7]* \d+)
%0	[0[0-7]*]
%s	\S+j
%u	\\d+j
%x, %X	[0[xX][\dA-Fa-f]+j

To extract the filename and numbers from a string like

```
/usr/sbin/sendmail - 0 errors, 4 warnings
```

you would use a scanf() format like

```
%s - %d errors, %d warnings
```

The equivalent regular expression would be

```
(\S+) - (\d+) \text{ errors}, (\d+) \text{ warnings}
```

Avoiding recursion

If you create regular expressions that require the engine to perform a lot of recursion, you may encounter a RuntimeError exception with the message maximum recursion limit exceeded. For example,

```
>>> import re
>>> s = 'Begin ' + 1000*'a very long string ' + 'end'
>>> re.match('Begin (\w| )*? end', s).end()
Traceback (most recent call last):
  File "<stdin>", line 1, in ?
  File "/usr/local/lib/python2.3/sre.py", line 132, in match
    return _compile(pattern, flags).match(string)
RuntimeError: maximum recursion limit exceeded
```

You can often restructure your regular expression to avoid recursion.

Starting with Python 2.3, simple uses of the <code>f*?j</code> pattern are special-cased to avoid recursion. Thus, the above regular expression can avoid recursion by being recast as <code>Begin [a-zA-Z0-9_]*?endj</code>. As a further benefit, such regular expressions will run faster than their recursive equivalents.

4.3 struct — Interpret strings as packed binary data

This module performs conversions between Python values and C structs represented as Python strings. It uses *format strings* (explained below) as compact descriptions of the lay-out of the C structs and the intended conversion to/from Python values. This can be used in handling binary data stored in files or from network connections, among other sources.

The module defines the following exception and functions:

exception error

Exception raised on various occasions; argument is a string describing what is wrong.

```
pack(fmt, v1, v2, ...)
```

Return a string containing the values v1, v2, ... packed according to the given format. The arguments must match the values required by the format exactly.

unpack(fmt, string)

Unpack the string (presumably packed by pack(fmt, ...)) according to the given format. The result is a tuple even if it contains exactly one item. The string must contain exactly the amount of data required by the format (len(string) must equal calcsize(fmt)).

calcsize(fmt)

Return the size of the struct (and hence of the string) corresponding to the given format.

Format characters have the following meaning; the conversion between C and Python values should be obvious given their types:

Format	C Type	Python	Notes
'x'	pad byte	no value	
'c'	char	string of length 1	
'b'	signed char	integer	
'В'	unsigned char	integer	
'h'	short	integer	
'H'	unsigned short	integer	
ʻi'	int	integer	
'I'	unsigned int	long	
' 1'	long	integer	
'L'	unsigned long	long	
ʻq'	long long	long	(1)
'Q'	unsigned long long	long	(1)
'f'	float	float	
'd'	double	float	
's'	char[]	string	
ʻp'	char[]	string	
'P'	void *	integer	

Notes:

(1) The 'q' and 'Q' conversion codes are available in native mode only if the platform C compiler supports C long long, or, on Windows, __int64. They are always available in standard modes. New in version 2.2.

A format character may be preceded by an integral repeat count. For example, the format string '4h' means exactly the same as 'hhhh'.

Whitespace characters between formats are ignored; a count and its format must not contain whitespace though.

For the 's' format character, the count is interpreted as the size of the string, not a repeat count like for the other format characters; for example, '10s' means a single 10-byte string, while '10c' means 10 characters. For packing, the string is truncated or padded with null bytes as appropriate to make it fit. For unpacking, the resulting string always has exactly the specified number of bytes. As a special case, '0s' means a single, empty string (while '0c' means 0 characters).

The 'p' format character encodes a "Pascal string", meaning a short variable-length string stored in a fixed number of bytes. The count is the total number of bytes stored. The first byte stored is the length of the string, or 255, whichever is smaller. The bytes of the string follow. If the string passed in to pack() is too long (longer than the count minus 1), only the leading count-1 bytes of the string are stored. If the string is shorter than count-1, it is padded with null bytes so that exactly count bytes in all are used. Note that for unpack(), the 'p' format character consumes count bytes, but that the string returned can never contain more than 255 characters.

For the 'I', 'L', 'q' and 'Q' format characters, the return value is a Python long integer.

For the 'P' format character, the return value is a Python integer or long integer, depending on the size needed to hold a pointer when it has been cast to an integer type. A NULL pointer will always be returned as the Python integer 0. When packing pointer-sized values, Python integer or long integer objects may be used. For example, the Alpha and Merced processors use 64-bit pointer values, meaning a Python long integer will be used to hold the pointer; other platforms use 32-bit pointers and will use a Python integer.

By default, C numbers are represented in the machine's native format and byte order, and properly aligned by skipping pad bytes if necessary (according to the rules used by the C compiler).

Alternatively, the first character of the format string can be used to indicate the byte order, size and alignment of the packed data, according to the following table:

Character	Byte order	Size and alignment
' @'	native	native
'='	native	standard
'<'	little-endian	standard
'>'	big-endian	standard
'!'	network (= big-endian)	standard

If the first character is not one of these, '@' is assumed.

Native byte order is big-endian or little-endian, depending on the host system. For example, Motorola and Sun processors are big-endian; Intel and DEC processors are little-endian.

Native size and alignment are determined using the C compiler's sizeof expression. This is always combined with native byte order.

Standard size and alignment are as follows: no alignment is required for any type (so you have to use pad bytes); short is 2 bytes; int and long are 4 bytes; long long (__int64 on Windows) is 8 bytes; float and double are 32-bit and 64-bit IEEE floating point numbers, respectively.

Note the difference between '@' and '=': both use native byte order, but the size and alignment of the latter is standardized.

The form '!' is available for those poor souls who claim they can't remember whether network byte order is big-endian or little-endian.

There is no way to indicate non-native byte order (force byte-swapping); use the appropriate choice of '<' or '>'.

The 'P' format character is only available for the native byte ordering (selected as the default or with the '@' byte order character). The byte order character '=' chooses to use little- or big-endian ordering based on the host system. The struct module does not interpret this as native ordering, so the 'P' format is not available.

Examples (all using native byte order, size and alignment, on a big-endian machine):

```
>>> from struct import *
>>> pack('hhl', 1, 2, 3)
'\x00\x01\x00\x02\x00\x00\x00\x03'
>>> unpack('hhl', '\x00\x01\x00\x02\x00\x00\x00\x03')
(1, 2, 3)
>>> calcsize('hhl')
8
```

Hint: to align the end of a structure to the alignment requirement of a particular type, end the format with the code for that type with a repeat count of zero. For example, the format 'llh0l' specifies two pad bytes at the end, assuming longs are aligned on 4-byte boundaries. This only works when native size and alignment are in effect; standard size and alignment does not enforce any alignment.

See Also:

```
Module array (section 5.14):
```

Packed binary storage of homogeneous data.

Module xdrlib (section 12.17):

Packing and unpacking of XDR data.

4.4 difflib — Helpers for computing deltas

New in version 2.1.

class SequenceMatcher

This is a flexible class for comparing pairs of sequences of any type, so long as the sequence elements are hashable. The basic algorithm predates, and is a little fancier than, an algorithm published in the late 1980's by Ratcliff and Obershelp under the hyperbolic name "gestalt pattern matching." The idea is to find

the longest contiguous matching subsequence that contains no "junk" elements (the Ratcliff and Obershelp algorithm doesn't address junk). The same idea is then applied recursively to the pieces of the sequences to the left and to the right of the matching subsequence. This does not yield minimal edit sequences, but does tend to yield matches that "look right" to people.

Timing: The basic Ratcliff-Obershelp algorithm is cubic time in the worst case and quadratic time in the expected case. SequenceMatcher is quadratic time for the worst case and has expected-case behavior dependent in a complicated way on how many elements the sequences have in common; best case time is linear.

class Differ

This is a class for comparing sequences of lines of text, and producing human-readable differences or deltas. Differ uses SequenceMatcher both to compare sequences of lines, and to compare sequences of characters within similar (near-matching) lines.

Each line of a Differ delta begins with a two-letter code:

Code	Meaning
′ – ′	line unique to sequence 1
' + '	line unique to sequence 2
, ,	line common to both sequences
'?'	line not present in either input sequence

Lines beginning with '?' attempt to guide the eye to intraline differences, and were not present in either input sequence. These lines can be confusing if the sequences contain tab characters.

class HtmlDiff

This class can be used to create an HTML table (or a complete HTML file containing the table) showing a side by side, line by line comparison of text with inter-line and intra-line change highlights. The table can be generated in either full or contextual difference mode.

The constructor for this class is:

```
__init__([tabsize][, wrapcolumn][, linejunk][, charjunk])
Initializes instance of HtmlDiff.
```

tabsize is an optional keyword argument to specify tab stop spacing and defaults to 8.

wrapcolumn is an optional keyword to specify column number where lines are broken and wrapped, defaults to None where lines are not wrapped.

linejunk and *charjunk* are optional keyword arguments passed into ndiff() (used by HtmlDiff to generate the side by side HTML differences). See ndiff() documentation for argument default values and descriptions.

The following methods are public:

```
make\_file(from lines, to lines[, from desc][, to desc][, context][, numlines])
```

Compares *fromlines* and *tolines* (lists of strings) and returns a string which is a complete HTML file containing a table showing line by line differences with inter-line and intra-line changes highlighted.

fromdesc and todesc are optional keyword arguments to specify from/to file column header strings (both default to an empty string).

context and numlines are both optional keyword arguments. Set context to True when contextual differences are to be shown, else the default is False to show the full files. numlines defaults to 5. When context is True numlines controls the number of context lines which surround the difference highlights. When context is False numlines controls the number of lines which are shown before a difference highlight when using the "next" hyperlinks (setting to zero would cause the "next" hyperlinks to place the next difference highlight at the top of the browser without any leading context).

```
{\tt make\_table}(\textit{from lines}, \textit{to lines} \ \big[, \textit{from desc} \ \big] \big[, \textit{to desc} \ \big] \big[, \textit{context} \ \big] \big[, \textit{num lines} \ \big])
```

Compares *fromlines* and *tolines* (lists of strings) and returns a string which is a complete HTML table showing line by line differences with inter-line and intra-line changes highlighted.

The arguments for this method are the same as those for the make_file() method.

'Tools/scripts/diff.py' is a command-line front-end to this class and contains a good example of its use.

New in version 2.4.

```
context\_diff(a, b[, fromfile][, tofile][, fromfiledate][, tofiledate][, n][, lineterm])
```

Compare a and b (lists of strings); return a delta (a generator generating the delta lines) in context diff format.

Context diffs are a compact way of showing just the lines that have changed plus a few lines of context. The changes are shown in a before/after style. The number of context lines is set by n which defaults to three.

By default, the diff control lines (those with *** or ---) are created with a trailing newline. This is helpful so that inputs created from file.readlines() result in diffs that are suitable for use with file.writelines() since both the inputs and outputs have trailing newlines.

For inputs that do not have trailing newlines, set the *lineterm* argument to " " so that the output will be uniformly newline free.

The context diff format normally has a header for filenames and modification times. Any or all of these may be specified using strings for *fromfile*, *tofile*, *fromfiledate*, and *tofiledate*. The modification times are normally expressed in the format returned by time.ctime(). If not specified, the strings default to blanks.

'Tools/scripts/diff.py' is a command-line front-end for this function.

New in version 2.3.

```
get_close_matches(word, possibilities[, n][, cutoff])
```

Return a list of the best "good enough" matches. word is a sequence for which close matches are desired (typically a string), and possibilities is a list of sequences against which to match word (typically a list of strings).

Optional argument n (default 3) is the maximum number of close matches to return; n must be greater than 0.

Optional argument cutoff (default 0.6) is a float in the range [0, 1]. Possibilities that don't score at least that similar to word are ignored.

The best (no more than n) matches among the possibilities are returned in a list, sorted by similarity score, most similar first.

```
>>> get_close_matches('appel', ['ape', 'apple', 'peach', 'puppy'])
['apple', 'ape']
>>> import keyword
>>> get_close_matches('wheel', keyword.kwlist)
['while']
>>> get_close_matches('apple', keyword.kwlist)
[]
>>> get_close_matches('accept', keyword.kwlist)
['except']
```

ndiff(a, b[, linejunk][, charjunk])

Compare a and b (lists of strings); return a Differ-style delta (a generator generating the delta lines).

Optional keyword parameters *linejunk* and *charjunk* are for filter functions (or None):

linejunk: A function that accepts a single string argument, and returns true if the string is junk, or false if not. The default is (None), starting with Python 2.3. Before then, the default was the module-level function IS_LINE_JUNK(), which filters out lines without visible characters, except for at most one pound character ('#'). As of Python 2.3, the underlying SequenceMatcher class does a dynamic analysis of which lines are so frequent as to constitute noise, and this usually works better than the pre-2.3 default.

charjunk: A function that accepts a character (a string of length 1), and returns if the character is junk, or false if not. The default is module-level function IS_CHARACTER_JUNK(), which filters out whitespace characters (a blank or tab; note: bad idea to include newline in this!).

'Tools/scripts/ndiff.py' is a command-line front-end to this function.

restore(sequence, which)

Return one of the two sequences that generated a delta.

Given a *sequence* produced by Differ.compare() or ndiff(), extract lines originating from file 1 or 2 (parameter *which*), stripping off line prefixes.

Example:

$unified_diff(a, b[, fromfile][, tofile][, fromfiledate][, tofiledate][, n][, lineterm])$

Compare a and b (lists of strings); return a delta (a generator generating the delta lines) in unified diff format.

Unified diffs are a compact way of showing just the lines that have changed plus a few lines of context. The changes are shown in a inline style (instead of separate before/after blocks). The number of context lines is set by n which defaults to three.

By default, the diff control lines (those with ---, +++, or @@) are created with a trailing newline. This is helpful so that inputs created from file.readlines() result in diffs that are suitable for use with file.writelines() since both the inputs and outputs have trailing newlines.

For inputs that do not have trailing newlines, set the *lineterm* argument to " " so that the output will be uniformly newline free.

The context diff format normally has a header for filenames and modification times. Any or all of these may be specified using strings for *fromfile*, *tofile*, *fromfiledate*, and *tofiledate*. The modification times are normally expressed in the format returned by time.ctime(). If not specified, the strings default to blanks.

'Tools/scripts/diff.py' is a command-line front-end for this function.

New in version 2.3.

IS_LINE_JUNK(line)

Return true for ignorable lines. The line *line* is ignorable if *line* is blank or contains a single '#', otherwise it is not ignorable. Used as a default for parameter *linejunk* in ndiff() before Python 2.3.

$IS_CHARACTER_JUNK(ch)$

Return true for ignorable characters. The character ch is ignorable if ch is a space or tab, otherwise it is not ignorable. Used as a default for parameter charjunk in ndiff().

See Also:

Pattern Matching: The Gestalt Approach

(http://www.ddj.com/documents/s=1103/ddj8807c/)

Discussion of a similar algorithm by John W. Ratcliff and D. E. Metzener. This was published in *Dr. Dobb's Journal* in July, 1988.

4.4.1 SequenceMatcher Objects

The SequenceMatcher class has this constructor:

```
class SequenceMatcher ([isjunk[, a[, b]]])
```

Optional argument *isjunk* must be None (the default) or a one-argument function that takes a sequence element and returns true if and only if the element is "junk" and should be ignored. Passing None for *isjunk* is equivalent to passing lambda x: 0; in other words, no elements are ignored. For example, pass:

```
lambda x: x in " \t"
```

if you're comparing lines as sequences of characters, and don't want to synch up on blanks or hard tabs.

The optional arguments a and b are sequences to be compared; both default to empty strings. The elements of both sequences must be hashable.

SequenceMatcher objects have the following methods:

```
set\_seqs(a, b)
```

Set the two sequences to be compared.

SequenceMatcher computes and caches detailed information about the second sequence, so if you want to compare one sequence against many sequences, use set_seq2() to set the commonly used sequence once and call set_seq1() repeatedly, once for each of the other sequences.

```
set_seq1(a)
```

Set the first sequence to be compared. The second sequence to be compared is not changed.

$set_seq2(b)$

Set the second sequence to be compared. The first sequence to be compared is not changed.

find_longest_match(alo, ahi, blo, bhi)

Find longest matching block in a[alo:ahi] and b[blo:bhi].

If isjunk was omitted or None, $get_longest_match()$ returns (i, j, k) such that a[i:i+k] is equal to b[j:j+k], where alo <= i <= i+k <= ahi and blo <= j <= j+k <= bhi. For all (i', j', k') meeting those conditions, the additional conditions k >= k', i <= i', and if i == i', j <= j' are also met. In other words, of all maximal matching blocks, return one that starts earliest in a, and of all those maximal matching blocks that start earliest in a, return the one that starts earliest in b.

```
>>> s = SequenceMatcher(None, " abcd", "abcd abcd")
>>> s.find_longest_match(0, 5, 0, 9)
(0. 4. 5)
```

If *isjunk* was provided, first the longest matching block is determined as above, but with the additional restriction that no junk element appears in the block. Then that block is extended as far as possible by matching (only) junk elements on both sides. So the resulting block never matches on junk except as identical junk happens to be adjacent to an interesting match.

Here's the same example as before, but considering blanks to be junk. That prevents 'abcd' from matching the 'abcd' at the tail end of the second sequence directly. Instead only the 'abcd' can match, and matches the leftmost 'abcd' in the second sequence:

```
>>> s = SequenceMatcher(lambda x: x==" ", " abcd", "abcd abcd") >>> s.find_longest_match(0, 5, 0, 9)  
(1, 0, 4)
```

If no blocks match, this returns (alo, blo, 0).

get_matching_blocks()

Return list of triples describing matching subsequences. Each triple is of the form (i, j, n), and means that a[i:i+n] == b[j:j+n]. The triples are monotonically increasing in i and j.

The last triple is a dummy, and has the value (len(a), len(b), 0). It is the only triple with n = 0.

```
>>> s = SequenceMatcher(None, "abxcd", "abcd")
>>> s.get_matching_blocks()
[(0, 0, 2), (3, 2, 2), (5, 4, 0)]
```

get_opcodes()

Return list of 5-tuples describing how to turn a into b. Each tuple is of the form (tag, i1, i2, j1, j2). The first tuple has i1 == j1 == 0, and remaining tuples have i1 equal to the i2 from the preceding tuple, and, likewise, i1 equal to the previous i2.

The *tag* values are strings, with these meanings:

Value	Meaning
'replace'	a[i1:i2] should be replaced by $b[j1:j2]$.
'delete'	a[i1:i2] should be deleted. Note that $j1 == j2$ in this case.
'insert'	b[j1:j2] should be inserted at $a[i1:i1]$. Note that $i1 == i2$ in this case.
'equal'	a[i1:i2] == b[j1:j2] (the sub-sequences are equal).

For example:

$get_grouped_opcodes([n])$

Return a generator of groups with up to n lines of context.

Starting with the groups returned by get_opcodes(), this method splits out smaller change clusters and eliminates intervening ranges which have no changes.

The groups are returned in the same format as get_opcodes (). New in version 2.3.

ratio()

Return a measure of the sequences' similarity as a float in the range [0, 1].

Where T is the total number of elements in both sequences, and M is the number of matches, this is 2.0*M / T. Note that this is 1.0 if the sequences are identical, and 0.0 if they have nothing in common.

This is expensive to compute if get_matching_blocks() or get_opcodes() hasn't already been called, in which case you may want to try quick_ratio() or real_quick_ratio() first to get an upper bound.

quick_ratio()

Return an upper bound on ratio() relatively quickly.

This isn't defined beyond that it is an upper bound on ratio(), and is faster to compute.

real_quick_ratio()

Return an upper bound on ${\tt ratio()}$ very quickly.

This isn't defined beyond that it is an upper bound on ratio(), and is faster to compute than either ratio() or quick_ratio().

The three methods that return the ratio of matching to total characters can give different results due to differing levels of approximation, although quick_ratio() and real_quick_ratio() are always at least as large as ratio():

```
>>> s = SequenceMatcher(None, "abcd", "bcde")
>>> s.ratio()
0.75
>>> s.quick_ratio()
0.75
>>> s.real_quick_ratio()
1.0
```

4.4.2 SequenceMatcher Examples

This example compares two strings, considering blanks to be "junk:"

ratio() returns a float in [0, 1], measuring the similarity of the sequences. As a rule of thumb, a ratio() value over 0.6 means the sequences are close matches:

```
>>> print round(s.ratio(), 3)
0.866
```

If you're only interested in where the sequences match, get_matching_blocks() is handy:

```
>>> for block in s.get_matching_blocks():
... print "a[%d] and b[%d] match for %d elements" % block
a[0] and b[0] match for 8 elements
a[8] and b[17] match for 6 elements
a[14] and b[23] match for 15 elements
a[29] and b[38] match for 0 elements
```

Note that the last tuple returned by $get_matching_blocks()$ is always a dummy, (len(a), len(b), 0), and this is the only case in which the last tuple element (number of elements matched) is 0.

If you want to know how to change the first sequence into the second, use get_opcodes():

```
>>> for opcode in s.get_opcodes():
...    print "%6s a[%d:%d] b[%d:%d]" % opcode
    equal a[0:8] b[0:8]
insert a[8:8] b[8:17]
    equal a[8:14] b[17:23]
    equal a[14:29] b[23:38]
```

See also the function get_close_matches() in this module, which shows how simple code building on SequenceMatcher can be used to do useful work.

4.4.3 Differ Objects

Note that Differ-generated deltas make no claim to be **minimal** diffs. To the contrary, minimal diffs are often counter-intuitive, because they synch up anywhere possible, sometimes accidental matches 100 pages apart. Restricting synch points to contiguous matches preserves some notion of locality, at the occasional cost of producing a longer diff.

The Differ class has this constructor:

```
class Differ([linejunk[, charjunk]])
```

Optional keyword parameters *linejunk* and *charjunk* are for filter functions (or None):

linejunk: A function that accepts a single string argument, and returns true if the string is junk. The default is None, meaning that no line is considered junk.

charjunk: A function that accepts a single character argument (a string of length 1), and returns true if the character is junk. The default is None, meaning that no character is considered junk.

Differ objects are used (deltas generated) via a single method:

```
compare(a, b)
```

Compare two sequences of lines, and generate the delta (a sequence of lines).

Each sequence must contain individual single-line strings ending with newlines. Such sequences can be obtained from the readlines() method of file-like objects. The delta generated also consists of newline-terminated strings, ready to be printed as-is via the writelines() method of a file-like object.

4.4.4 Differ Example

This example compares two texts. First we set up the texts, sequences of individual single-line strings ending with newlines (such sequences can also be obtained from the readlines () method of file-like objects):

```
>>> text1 = ''' 1. Beautiful is better than ugly.
... 2. Explicit is better than implicit.
... 3. Simple is better than complex.
... 4. Complex is better than complicated.
... '''.splitlines(1)
>>> len(text1)
4
>>> text1[0][-1]
'\n'
>>> text2 = ''' 1. Beautiful is better than ugly.
... 3. Simple is better than complex.
... 4. Complicated is better than complex.
... 5. Flat is better than nested.
... '''.splitlines(1)
```

Next we instantiate a Differ object:

```
>>> d = Differ()
```

Note that when instantiating a Differ object we may pass functions to filter out line and character "junk." See the Differ() constructor for details.

Finally, we compare the two:

```
>>> result = list(d.compare(text1, text2))
```

result is a list of strings, so let's pretty-print it:

As a single multi-line string it looks like this:

4.5 fpformat — Floating point conversions

The fpformat module defines functions for dealing with floating point numbers representations in 100% pure Python. **Note:** This module is unneeded: everything here could be done via the % string interpolation operator.

The fpformat module defines the following functions and an exception:

fix(x, digs)

Format x as [-]ddd .ddd with digs digits after the point and at least one digit before. If digs <= 0, the decimal point is suppressed.

x can be either a number or a string that looks like one. digs is an integer.

Return value is a string.

```
sci(x, digs)
```

Format x as [-]d.ddE[+-]ddd with digs digits after the point and exactly one digit before. If digs <= 0, one digit is kept and the point is suppressed.

x can be either a real number, or a string that looks like one. digs is an integer.

Return value is a string.

exception NotANumber

Exception raised when a string passed to fix() or sci() as the x parameter does not look like a number. This is a subclass of ValueError when the standard exceptions are strings. The exception value is the improperly formatted string that caused the exception to be raised.

Example:

```
>>> import fpformat
>>> fpformat.fix(1.23, 1)
'1.2'
```

4.6 StringIO — Read and write strings as files

This module implements a file-like class, StringIO, that reads and writes a string buffer (also known as *memory files*). See the description of file objects for operations (section 2.3.9).

class StringIO([buffer])

When a StringIO object is created, it can be initialized to an existing string by passing the string to the constructor. If no string is given, the StringIO will start empty. In both cases, the initial file position starts at zero.

The StringIO object can accept either Unicode or 8-bit strings, but mixing the two may take some care. If both are used, 8-bit strings that cannot be interpreted as 7-bit ASCII (that use the 8th bit) will cause a UnicodeError to be raised when getvalue() is called.

The following methods of StringIO objects require special mention:

getvalue()

Retrieve the entire contents of the "file" at any time before the StringIO object's close() method is called. See the note above for information about mixing Unicode and 8-bit strings; such mixing can cause this method to raise UnicodeError.

close()

Free the memory buffer.

4.7 cStringIO — Faster version of StringIO

The module cStringIO provides an interface similar to that of the StringIO module. Heavy use of StringIO.StringIO objects can be made more efficient by using the function StringIO() from this module instead.

Since this module provides a factory function which returns objects of built-in types, there's no way to build your own version using subclassing. Use the original StringIO module in that case.

Unlike the memory files implemented by the StringIO module, those provided by this module are not able to accept Unicode strings that cannot be encoded as plain ASCII strings.

Another difference from the StringIO module is that calling StringIO() with a string parameter creates a read-only object. Unlike an object created without a string parameter, it does not have write methods. These objects are not generally visible. They turn up in tracebacks as StringI and StringO.

The following data objects are provided as well:

InputType

The type object of the objects created by calling ${\tt StringIO}$ with a string parameter.

OutputType

The type object of the objects returned by calling ${\tt StringIO}$ with no parameters.

There is a C API to the module as well; refer to the module source for more information.

4.8 textwrap — Text wrapping and filling

New in version 2.3.

The textwrap module provides two convenience functions, wrap() and fill(), as well as TextWrapper, the class that does all the work, and a utility function dedent(). If you're just wrapping or filling one or two text strings, the convenience functions should be good enough; otherwise, you should use an instance of TextWrapper for efficiency.

```
wrap(text[, width[, ...]])
```

Wraps the single paragraph in *text* (a string) so every line is at most *width* characters long. Returns a list of output lines, without final newlines.

Optional keyword arguments correspond to the instance attributes of TextWrapper, documented below. *width* defaults to 70.

```
fill(text[, width[, ...]])
```

Wraps the single paragraph in *text*, and returns a single string containing the wrapped paragraph. fill() is shorthand for

```
"\n".join(wrap(text, ...))
```

In particular, fill() accepts exactly the same keyword arguments as wrap().

Both wrap() and fill() work by creating a TextWrapper instance and calling a single method on it. That instance is not reused, so for applications that wrap/fill many text strings, it will be more efficient for you to create your own TextWrapper object.

An additional utility function, dedent(), is provided to remove indentation from strings that have unwanted whitespace to the left of the text.

dedent(text)

Remove any whitespace that can be uniformly removed from the left of every line in text.

This is typically used to make triple-quoted strings line up with the left edge of screen/whatever, while still presenting it in the source code in indented form.

For example:

```
def test():
    # end first line with \ to avoid the empty line!
    s = '''\
    hello
        world
    '''
    print repr(s)  # prints ' hello\n world\n
    print repr(dedent(s))  # prints 'hello\n world\n'
```

${\bf class}\; {\tt TextWrapper}\,(\,\dots\,)$

The TextWrapper constructor accepts a number of optional keyword arguments. Each argument corresponds to one instance attribute, so for example

```
wrapper = TextWrapper(initial_indent="* ")
is the same as

wrapper = TextWrapper()
 wrapper.initial_indent = "* "
```

You can re-use the same TextWrapper object many times, and you can change any of its options through direct assignment to instance attributes between uses.

The TextWrapper instance attributes (and keyword arguments to the constructor) are as follows:

width

(default: 70) The maximum length of wrapped lines. As long as there are no individual words in the input text longer than width, TextWrapper guarantees that no output line will be longer than width characters.

expand_tabs

(default: True) If true, then all tab characters in *text* will be expanded to spaces using the expandtabs () method of *text*.

replace_whitespace

(default: True) If true, each whitespace character (as defined by string.whitespace) remaining after tab expansion will be replaced by a single space. **Note:** If expand_tabs is false and replace_whitespace is true, each tab character will be replaced by a single space, which is *not* the same as tab expansion.

initial_indent

(default: '') String that will be prepended to the first line of wrapped output. Counts towards the length of the first line.

subsequent_indent

(default: '') String that will be prepended to all lines of wrapped output except the first. Counts towards the length of each line except the first.

fix_sentence_endings

(default: False) If true, TextWrapper attempts to detect sentence endings and ensure that sentences are always separated by exactly two spaces. This is generally desired for text in a monospaced font. However, the sentence detection algorithm is imperfect: it assumes that a sentence ending consists of a lowercase letter followed by one of '.', '!', or '?', possibly followed by one of '"' or ''', followed by a space. One problem with this is algorithm is that it is unable to detect the difference between "Dr." in

```
[...] Dr. Frankenstein's monster [...] and "Spot." in
[...] See Spot. See Spot run [...]
```

fix_sentence_endings is false by default.

Since the sentence detection algorithm relies on string.lowercase for the definition of "lowercase letter," and a convention of using two spaces after a period to separate sentences on the same line, it is specific to English-language texts.

break_long_words

(default: True) If true, then words longer than width will be broken in order to ensure that no lines are longer than width. If it is false, long words will not be broken, and some lines may be longer than width. (Long words will be put on a line by themselves, in order to minimize the amount by which width is exceeded.)

TextWrapper also provides two public methods, analogous to the module-level convenience functions:

wrap(text)

Wraps the single paragraph in *text* (a string) so every line is at most width characters long. All wrapping options are taken from instance attributes of the TextWrapper instance. Returns a list of output lines, without final newlines.

fill(text)

Wraps the single paragraph in text, and returns a single string containing the wrapped paragraph.

4.9 codecs — Codec registry and base classes

This module defines base classes for standard Python codecs (encoders and decoders) and provides access to the internal Python codec registry which manages the codec and error handling lookup process.

It defines the following functions:

$\verb"register" (search_function)$

Register a codec search function. Search functions are expected to take one argument, the encoding

name in all lower case letters, and return a tuple of functions (encoder, decoder, stream_reader, stream_writer) taking the following arguments:

encoder and decoder: These must be functions or methods which have the same interface as the encode()/decode() methods of Codec instances (see Codec Interface). The functions/methods are expected to work in a stateless mode.

stream_reader and stream_writer: These have to be factory functions providing the following interface:

```
factory(stream, errors='strict')
```

The factory functions must return objects providing the interfaces defined by the base classes StreamWriter and StreamReader, respectively. Stream codecs can maintain state.

Possible values for errors are 'strict' (raise an exception in case of an encoding error), 'replace' (replace malformed data with a suitable replacement marker, such as '?'), 'ignore' (ignore malformed data and continue without further notice), 'xmlcharrefreplace' (replace with the appropriate XML character reference (for encoding only)) and 'backslashreplace' (replace with backslashed escape sequences (for encoding only)) as well as any other error handling name defined via register_error().

In case a search function cannot find a given encoding, it should return None.

lookup(encoding)

Looks up a codec tuple in the Python codec registry and returns the function tuple as defined above.

Encodings are first looked up in the registry's cache. If not found, the list of registered search functions is scanned. If no codecs tuple is found, a LookupError is raised. Otherwise, the codecs tuple is stored in the cache and returned to the caller.

To simplify access to the various codecs, the module provides these additional functions which use lookup() for the codec lookup:

getencoder(encoding)

Lookup up the codec for the given encoding and return its encoder function.

Raises a LookupError in case the encoding cannot be found.

getdecoder(encoding)

Lookup up the codec for the given encoding and return its decoder function.

Raises a LookupError in case the encoding cannot be found.

getreader(encoding)

Lookup up the codec for the given encoding and return its StreamReader class or factory function.

Raises a LookupError in case the encoding cannot be found.

getwriter(encoding)

Lookup up the codec for the given encoding and return its StreamWriter class or factory function.

Raises a LookupError in case the encoding cannot be found.

register_error(name, error_handler)

Register the error handling function *error_handler* under the name *name*. *error_handler* will be called during encoding and decoding in case of an error, when *name* is specified as the errors parameter.

For encoding <code>error_handler</code> will be called with a <code>UnicodeEncodeError</code> instance, which contains information about the location of the error. The error handler must either raise this or a different exception or return a tuple with a replacement for the unencodable part of the input and a position where encoding should continue. The encoder will encode the replacement and continue encoding the original input at the specified position. Negative position values will be treated as being relative to the end of the input string. If the resulting position is out of bound an IndexError will be raised.

Decoding and translating works similar, except UnicodeDecodeError or UnicodeTranslateError will be passed to the handler and that the replacement from the error handler will be put into the output directly.

lookup_error(name)

Return the error handler previously register under the name *name*.

Raises a LookupError in case the handler cannot be found.

```
strict_errors(exception)
```

Implements the strict error handling.

```
replace_errors(exception)
```

Implements the replace error handling.

```
ignore_errors(exception)
```

Implements the ignore error handling.

xmlcharrefreplace_errors_errors(exception)

Implements the xmlcharrefreplace error handling.

backslashreplace_errors(exception)

Implements the backslashreplace error handling.

To simplify working with encoded files or stream, the module also defines these utility functions:

```
open (filename, mode[, encoding[, errors[, buffering]]])
```

Open an encoded file using the given *mode* and return a wrapped version providing transparent encoding/decoding.

Note: The wrapped version will only accept the object format defined by the codecs, i.e. Unicode objects for most built-in codecs. Output is also codec-dependent and will usually be Unicode as well.

encoding specifies the encoding which is to be used for the file.

errors may be given to define the error handling. It defaults to 'strict' which causes a ValueError to be raised in case an encoding error occurs.

buffering has the same meaning as for the built-in open () function. It defaults to line buffered.

```
EncodedFile(file, input[, output[, errors]])
```

Return a wrapped version of file which provides transparent encoding translation.

Strings written to the wrapped file are interpreted according to the given *input* encoding and then written to the original file as strings using the *output* encoding. The intermediate encoding will usually be Unicode but depends on the specified codecs.

If *output* is not given, it defaults to *input*.

errors may be given to define the error handling. It defaults to 'strict', which causes ValueError to be raised in case an encoding error occurs.

The module also provides the following constants which are useful for reading and writing to platform dependent files:

BOM

BOM_BE

BOM_LE

BOM_UTF8

BOM_UTF16

BOM_UTF16_BE

BOM_UTF16_LE

BOM_UTF32

BOM_UTF32_BE

BOM_UTF32_LE

These constants define various encodings of the Unicode byte order mark (BOM) used in UTF-16 and UTF-32 data streams to indicate the byte order used in the stream or file and in UTF-8 as a Unicode signature. BOM_UTF16 is either BOM_UTF16_BE or BOM_UTF16_LE depending on the platform's native byte order, BOM is an alias for BOM_UTF16, BOM_LE for BOM_UTF16_LE and BOM_BE for BOM_UTF16_BE. The others represent the BOM in UTF-8 and UTF-32 encodings.

4.9.1 Codec Base Classes

The codecs defines a set of base classes which define the interface and can also be used to easily write you own codecs for use in Python.

Each codec has to define four interfaces to make it usable as codec in Python: stateless encoder, stateless decoder, stream reader and stream writer. The stream reader and writers typically reuse the stateless encoder/decoder to implement the file protocols.

The Codec class defines the interface for stateless encoders/decoders.

To simplify and standardize error handling, the <code>encode()</code> and <code>decode()</code> methods may implement different error handling schemes by providing the *errors* string argument. The following string values are defined and implemented by all standard Python codecs:

Value	Meaning
'strict'	Raise UnicodeError (or a subclass); this is the default.
'ignore'	Ignore the character and continue with the next.
'replace'	Replace with a suitable replacement character; Python will use the official U+FFFD REPLACEM
'xmlcharrefreplace'	Replace with the appropriate XML character reference (only for encoding).
'backslashreplace'	Replace with backslashed escape sequences (only for encoding).

The set of allowed values can be extended via register_error.

Codec Objects

The Codec class defines these methods which also define the function interfaces of the stateless encoder and decoder:

encode(input[, errors])

Encodes the object *input* and returns a tuple (output object, length consumed). While codecs are not restricted to use with Unicode, in a Unicode context, encoding converts a Unicode object to a plain string using a particular character set encoding (e.g., cp1252 or iso-8859-1).

errors defines the error handling to apply. It defaults to 'strict' handling.

The method may not store state in the Codec instance. Use StreamCodec for codecs which have to keep state in order to make encoding/decoding efficient.

The encoder must be able to handle zero length input and return an empty object of the output object type in this situation.

decode(input[, errors])

Decodes the object *input* and returns a tuple (output object, length consumed). In a Unicode context, decoding converts a plain string encoded using a particular character set encoding to a Unicode object.

input must be an object which provides the bf_getreadbuf buffer slot. Python strings, buffer objects and memory mapped files are examples of objects providing this slot.

errors defines the error handling to apply. It defaults to 'strict' handling.

The method may not store state in the Codec instance. Use StreamCodec for codecs which have to keep state in order to make encoding/decoding efficient.

The decoder must be able to handle zero length input and return an empty object of the output object type in this situation.

The StreamWriter and StreamReader classes provide generic working interfaces which can be used to implement new encodings submodules very easily. See encodings.utf_8 for an example on how this is done.

StreamWriter Objects

The StreamWriter class is a subclass of Codec and defines the following methods which every stream writer must define in order to be compatible to the Python codec registry.

class StreamWriter(stream[, errors])

Constructor for a StreamWriter instance.

All stream writers must provide this constructor interface. They are free to add additional keyword arguments, but only the ones defined here are used by the Python codec registry.

stream must be a file-like object open for writing (binary) data.

The StreamWriter may implement different error handling schemes by providing the *errors* keyword argument. These parameters are predefined:

- 'strict' Raise ValueError (or a subclass); this is the default.
- 'ignore' Ignore the character and continue with the next.
- 'replace' Replace with a suitable replacement character
- 'xmlcharrefreplace' Replace with the appropriate XML character reference
- 'backslashreplace' Replace with backslashed escape sequences.

The *errors* argument will be assigned to an attribute of the same name. Assigning to this attribute makes it possible to switch between different error handling strategies during the lifetime of the StreamWriter object.

The set of allowed values for the *errors* argument can be extended with register_error().

write(object)

Writes the object's contents encoded to the stream.

writelines(list)

Writes the concatenated list of strings to the stream (possibly by reusing the write() method).

reset()

Flushes and resets the codec buffers used for keeping state.

Calling this method should ensure that the data on the output is put into a clean state, that allows appending of new fresh data without having to rescan the whole stream to recover state.

In addition to the above methods, the StreamWriter must also inherit all other methods and attribute from the underlying stream.

StreamReader Objects

The StreamReader class is a subclass of Codec and defines the following methods which every stream reader must define in order to be compatible to the Python codec registry.

class StreamReader(stream[, errors])

Constructor for a StreamReader instance.

All stream readers must provide this constructor interface. They are free to add additional keyword arguments, but only the ones defined here are used by the Python codec registry.

stream must be a file-like object open for reading (binary) data.

The StreamReader may implement different error handling schemes by providing the *errors* keyword argument. These parameters are defined:

- 'strict' Raise ValueError (or a subclass); this is the default.
- 'ignore' Ignore the character and continue with the next.
- 'replace' Replace with a suitable replacement character.

The *errors* argument will be assigned to an attribute of the same name. Assigning to this attribute makes it possible to switch between different error handling strategies during the lifetime of the StreamReader object.

The set of allowed values for the *errors* argument can be extended with register_error().

read([size[, chars, [firstline]]])

Decodes data from the stream and returns the resulting object.

chars indicates the number of characters to read from the stream. read() will never return more than *chars* characters, but it might return less, if there are not enough characters available.

size indicates the approximate maximum number of bytes to read from the stream for decoding purposes. The decoder can modify this setting as appropriate. The default value -1 indicates to read and decode as much as possible. *size* is intended to prevent having to decode huge files in one step.

firstline indicates that it would be sufficient to only return the first line, if there are decoding errors on later lines.

The method should use a greedy read strategy meaning that it should read as much data as is allowed within

class StreamRecoder (stream, encode, decode, Reader, Writer, errors)

Creates a StreamRecoder instance which implements a two-way conversion: *encode* and *decode* work on the frontend (the input to read() and output of write()) while *Reader* and *Writer* work on the backend (reading and writing to the stream).

You can use these objects to do transparent direct recodings from e.g. Latin-1 to UTF-8 and back.

stream must be a file-like object.

encode, decode must adhere to the Codec interface, Reader, Writer must be factory functions or classes providing objects of the StreamReader and StreamWriter interface respectively.

encode and *decode* are needed for the frontend translation, *Reader* and *Writer* for the backend translation. The intermediate format used is determined by the two sets of codecs, e.g. the Unicode codecs will use Unicode as intermediate encoding.

Error handling is done in the same way as defined for the stream readers and writers.

StreamRecoder instances define the combined interfaces of StreamReader and StreamWriter classes. They inherit all other methods and attribute from the underlying stream.

4.9.2 Standard Encodings

Python comes with a number of codecs builtin, either implemented as C functions, or with dictionaries as mapping tables. The following table lists the codecs by name, together with a few common aliases, and the languages for which the encoding is likely used. Neither the list of aliases nor the list of languages is meant to be exhaustive. Notice that spelling alternatives that only differ in case or use a hyphen instead of an underscore are also valid aliases.

Many of the character sets support the same languages. They vary in individual characters (e.g. whether the EURO SIGN is supported or not), and in the assignment of characters to code positions. For the European languages in particular, the following variants typically exist:

- an ISO 8859 codeset
- a Microsoft Windows code page, which is typically derived from a 8859 codeset, but replaces control characters with additional graphic characters
- an IBM EBCDIC code page
- an IBM PC code page, which is ASCII compatible

Codec	Aliases	Languages
ascii	646, us-ascii	English
big5	big5-tw, csbig5	Traditional C
big5hkscs	big5-hkscs, hkscs	Traditional C
cp037	IBM037, IBM039	English
cp424	EBCDIC-CP-HE, IBM424	Hebrew
cp437	437, IBM437	English
cp500	EBCDIC-CP-BE, EBCDIC-CP-CH, IBM500	Western Euro
cp737		Greek
cp775	IBM775	Baltic langua
cp850	850, IBM850	Western Euro
cp852	852, IBM852	Central and I
cp855	855, IBM855	Bulgarian, B
cp856		Hebrew
cp857	857, IBM857	Turkish
cp860	860, IBM860	Portuguese
cp861	861, CP-IS, IBM861	Icelandic
cp862	862, IBM862	Hebrew
cp863	863, IBM863	Canadian
cp864	IBM864	Arabic

cp866 866, CP-GR, IBM869 Greek cp874 869, CP-GR, IBM869 Greek cp875 932, ms932, mskanji, m-kanji Japanes cp949 949, ms494), uhe Korean cp1006 17 Traditio Urd cp1107 ibm1026 Traditio cp1140 ibm1026 Turkish cp1251 windows-1251 Western cp1252 windows-1252 Western cp1253 windows-1253 Greek cp1254 windows-1253 Greek cp1255 windows-1254 Turkish cp1256 windows-1258 Turkish cp1258 windows-1258 Victuam cp1258 windows-1258 Western cp1257 windows-1258 Weight cuc_ip weight Japanes uc_ip weight Japanes gb31 weight Weight Japanes gb212 dwindows-1258 Weight Japanes weight weight </th <th>Codec</th> <th>Aliases</th> <th>Languages</th>	Codec	Aliases	Languages
cp866 866, IBM866 Russian cp874 869, CP-GR, IBM869 Russian cp875 969, CP-GR, IBM869 Thi cp9787 992 mskanji, ms-kanji Thi cp990 949, ms494, uhe Korean Traditio cp1006 ibm1026 Turkish cp1140 ibm1026 Turkish cp1251 windows-1250 Western cp1252 windows-1251 Bulgari cp1253 windows-1253 Western cp1254 windows-1254 Turkish cp1255 windows-1254 Turkish cp1256 windows-125 Turkish cp1257 windows-125 Turkish cp1258 windows-125 Turkish cp1259 windows-125 Turkish p1250 windows-125 Turkish p1251 dec. p125 windows-125 Turkish p1252 windows-125 Turkish p1253 windows-125 Turkish p1254	cp865	865, IBM865	Danish, Nor
cp869 869, CP-GR, IBM869 Greek cp875 cp875 Thi cp875 cp932 932, ms932, mskanji, ms-kanji Greek cp999 949, ms949, uhe Korean cp9100 50, ms950 Urdu cp1026 ibm1026 Urdu cp11270 windows-1250 Central cp1251 windows-1251 Ballgari cp1252 windows-1253 Western cp1253 windows-1254 Turkish cp1254 windows-1254 Turkish cp1255 windows-1254 Turkish cp1257 windows-1256 Arabic cp1258 windows-1257 Baltical cp1257 windows-1257 Baltical cp1258 windows-1258 Victnam cuc_ja_204 cuc_ja_204 Japanes sp2312 chinsex, csiso58gb231280, cuc-cn, cucen, cucgb2312-cn, gb2312-90, gb2312-80, iso-ir-8 Simplifi gb18030 3b18030-200 br2 Japanes isco2022_jp_1 iso-2022_jp_1,	-	866, IBM866	Russian
cp874 Cp875 Greek cp932 932, ms932, mskanji, ms-kanji Japanes cp949 949, ms949, uhe Korean cp1006 ibm1026 Traditio cp1140 ibm1140 Western cp1251 windows-1251 Bulgarii cp1252 windows-1253 Greek cp1253 windows-1254 Western cp1254 windows-1254 Western cp1255 windows-1254 Turkish cp1256 windows-1256 Turkish cp1257 windows-1257 Baltic la cp1258 windows-1258 Vienar cuc_lj ucij, ujis, u-jis Japanes cuc_lj ucij, ujis, u-jis Japanes cuc_k windows-1258 Ucik, korean, ksc5601, ks_c-5601, ks_c-5601-1987, ksx1001, ks_x-1001 Japanes gb2312 pl80802 gb gb 18030-2000 Japanes jsc02022_ip1 iso2022_ip2 iso2022_ip2 Japanes jsc02022_ip2 iso2022_ip2 Japanes	-		Greek
cp875 cp892 932, ms932, mskanji, ms-kanji Japanes cp949 949, ms949, uhe Tradition cp1026 ibm1026 Trakito cp11250 windows-1250 Central cp1251 windows-1251 Western cp1252 windows-1251 Western cp1253 windows-1254 Western cp1254 windows-1255 Western cp1255 windows-1254 Hebrew cp1257 windows-1258 Hebrew cp1257 windows-1258 Windows-1258 cp1257 windows-1258 Windows-1258 cwc.jp1258 windows-1258 Windows-1258 cwc.jp2259 windows-1258 Windows-1258 cwc.jp1259 windows-1258 Windows-1258 cwc.jp1259 windows-1258 Windows-1258 cwc.jp1259 windows-1258 Baltic le cwc.jp1259 windows-1258 Baltic le cwc.jp1259 windows-1251 Baltic le gb1 jp201 Lip2 </td <td>-</td> <td></td> <td></td>	-		
cp932 932, ms932, ms930, ms-kanji Japanese cp950 950, ms950 Traditio cp1066 ibm1026 Traditio cp1140 ibm1140 Western cp1251 windows-1250 Central cp1253 windows-1254 Western cp1254 windows-1254 Western cp1255 windows-1254 Trakish cp1255 windows-1254 Trakish cp1255 windows-1254 Trakish cp1256 windows-1258 Verann cp1257 windows-1258 Verann cp1258 windows-1258 Verann cwc_jis.2004 eucj.jis. u.jis Japanes cwc_jis.2013 eucj.jis. u.jis Japanes gb212 chinese, csiso58pb231280, euc-en. eucen, eucgb2312-en, gb2312-1980, gb2312-80, iso-ir-88 Japanes gb318030 gh 8030-2000 Lzgh, tzg-gb, tz-gb-2312 Japanes iso20222_pp_1 iso2022_pp_2, iso-2022_pp_1 Japanes iso20222_pp_2 iso2022_pp_2, iso-2022_pp_2 Japanes	•		
cp949 y49, ms949, uhc Korean cp1026 jbm1026 Truditio cp1026 ibm1026 Truditio cp1140 ibm1140 tbm1141 Western cp1250 windows-1250 Central cp1252 windows-1251 Western cp1253 windows-1254 Western cp1255 windows-1255 Hebrew cp1255 windows-1255 Hebrew cp1257 windows-1257 Baltic le cp1258 windows-1257 Baltic le cp1257 windows-1258 Lec'pt. cuc_jis-2014 windows-1258 Japanes cuc_jis-2024 leucjkx0213 Japanes gb18030 206 cp36, cp936, ms936 gb18030-2000 b180 296, cp936, ms936 gb18030-2000 Lugikx peb, bz-gb-2312 Simplifi isc02022_jp_ 1sic02022_jp_ isc02022_jp, isc02022_jp. Japanes isc02022_jp_ isc02022_jp_ jsc02022_jp- Japanes isc02022_jp_ isc02022_j	-	932. ms932. mskanii. ms-kanii	
cp950 p950 mp950 Traditio cp1026 ibm1026 ibm1026 Tradito cp1140 ibm1140 Western cp1251 windows-1251 Bulgari cp1252 windows-1253 Greek cp1253 windows-1255 Greek cp1254 windows-1255 Tradito cp1255 windows-1256 Arabic cp1257 windows-1258 Vietnam cp1258 windows-1258 Vietnam cp1257 windows-1258 Vietnam cp1258 windows-1258 Vietnam cp1259 windows-1258 Vietnam cp1251 windows-1258 Vietnam cp1252 windows-1258 Vietnam cp1258 windows-1258 Vietnam cp1259 windows-1258 Vietnam cp1251 windows-1258 Vietnam cp1252 windows-1258 Vietnam cp1252 windows-1250 Vietnam cp1252 windows-1250 </td <td>•</td> <td></td> <td></td>	•		
CP1006	-		Traditional (
cp1026 ibm1040 Turkish cp1250 ibm140 Western cp1251 windows-1250 Central cp1252 windows-1252 Western cp1253 windows-1253 Western cp1254 windows-1253 Greek cp1255 windows-1255 Hebrew cp1256 windows-1256 Arabic cp1257 windows-1258 Vienar cuc., ip cucja, jis. u-jis Japanes cuc., jis. 2004 ucijsx0213 Japanes cuc., kr cuck. r cuck. r gb212 chinese, csiso58gb231280, euc-cn, euccn, eucgb2312-cn, gb2312-1980, gb2312-80, iso-ir-58 Simplifi gb18030 gb18030-2000 gb18030-2000 Japanes siso2022_jp csiso2022_jp, so-2022-jp-3 Japanes siso2022_jp. 2 siso2022_jp-3 Japanes siso2022_jp. 2.st siso2022_jp-3, iso-2022-jp-3 Japanes siso2022_jp. ext siso2022_jp-3, iso-2022-jp-2 Japanes siso8859_3 siso-8859_4, iso-8859_4, iso-3022-jp-ext	•	750, III5750	
Description	•	ibm1026	
cp1250 windows-1250 Central cp1251 windows-1251 Windows-1252 cp1253 windows-1253 Western cp1254 windows-1253 Greek cp1255 windows-1255 Hebrew cp1256 windows-1257 Baltie la cp1257 windows-1257 Baltie la cp1258 windows-1258 Vietnam cuc_jisx.2004 eucj.jis.0213 Japanes cuc_jisx.2013 eucjisx0213 Japanes cuc_jisx.20213 eucjisx0213 japanes cuc_jisx.20213 eucjisx.20213 japanes gb31 chinesc, csiso5886231280, cuc-cn, cucen, cucepb2312-cn, gb2312-1980, gb2312-80, iso-ir-58 Simplifi gb18030 pls 18030-2000 lurified Unified lx brz. brz. brz. brz. iso2022_jp iso2022_jp-1, iso-2022-jp-1 japanes iso2022_jp iso2022_jp-2, iso-2022-jp-2 japanes iso2022_jp iso2022_jp-2, iso-2022-jp-2 japanes iso2022_jp iso2	-		Western Eur
cp1251 windows-1251 Bulgariz cp1252 windows-1253 Greek cp1254 windows-1253 Greek cp1255 windows-1255 Hebree cp1256 windows-1256 Hebree cp1257 windows-1258 Vietnam euc. jp eucip, juis, u-jis Japanes gbc-2123 cuck, korean, ksc5601, ks_c-5601, ks_c-5601-1987, ksx1001, ks_x-1001 Japanes cuc. kr cuckr, korean, ksc5601, ks_c-5601, ks_c-5601-1987, ksx1001, ks_x-1001 Korean gbb gbc-2312 chiese, csiso58gb231280, euc-cn, euccn, eucgb2312-cn, gb2312-1980, gb2312-80, iso-ir-58 Japanes gbb gbc-2022 gbc-36, m936 gbl 8030-2000 Japanes Japanes sico2022_jp iso2022_jp-1 iso2022_jp-1 jiso2022_jp-1 Japanes sico2022_jp iso2022_jp-2 jiso2022_jp-2 Japanes sico2022_jp-2 iso2022_jp-2 jiso2022_jp-2 Japanes sico2022_jp-2 iso2022_jp-2 jiso2022_jp-2 Korean sico8859_1 iso8859_1 jiso8859_1 <td< td=""><td>-</td><td></td><td></td></td<>	-		
cp1252 windows-1253 Western Greek cp1253 windows-1253 Turkish cp1255 windows-1254 Turkish cp1257 windows-1257 Baltic le Windows-1257 Arabic cp1258 windows-1258 Victnam cuc_ jp eucj, jis, e-jis Japanes cuc_ jis. 2004 eucjis.0213 eucjis.0213 eucjis.02013 euc_ kr eucjis.0213 eucjis.02014 eucjis.02013 eucjis.02014 jis.0213, eucjis.2004 gb2312 chinese, csiso.58gb231280, euc-cn, euccn, eucgb2312-cn, gb2312-1980, gb2312-80, iso-ir-58 japanes gb18030 gb18030-2000 bj8030-2000 js0618030-2002 js02022jp. iso-2022jp japanes iso2022_jp iso2022_jp. iso-2022jp, iso-2022-jp japanes japanes iso2022_jp iso2022_jp-204, iso-2022-jp-2 iso2022_jp-204, iso-2022-jp-2 japanes iso2022_jp iso2022_jp-204, iso-2022-jp-2 japanes japanes iso2022_jp iso-8859-1 js0859-1 js0859-1 iso8859 jso-8859-1 js022jp-1 js0	-		
cp1253 windows-1254 Greek cp1254 windows-1254 Turkish cp1255 windows-1255 Hebrew cp1256 windows-1257 Baltic le cp1257 windows-1258 Vietnam cucjis _ 2004 windows-1258 Vietnam cucjis _ 2004 jisx0213 jisx0213 cucjis _ 2004 eucjisx0213 jisx0213 jisx0213 guckr euck, k orean, ksc5601, ks_c-5601, ks_c-5601-1987, ksx1001, ks_x-1001 Korean gb18030 gb18030-2000 Unified Unified bz 2022_j lz _ 258, hz-gb. 2312 Simplifi Japanes sico2022_j jsco2022_jp. iso2022jp, iso2022jp; iso2022jp- iso2022jp- iso2022jp- iso2022jp- iso2022jp- iso2022jp- iso2022jp- iso2022jp- jp- 2004 Japanes sico2022_jp 2004 iso2022_jp- 204 iso2022jp- 204, iso-2022-jp- 204 Japanes sico2022_jp 201 iso2022_jp- 204, iso-2022-jp- 204 Japanes sico2022_jp 201 iso2022_jp- 204, iso-2022-jp- 204 Japanes sico2022_jp 201 iso2022_jp- 204, iso-2022-jp- 204 Japanes	-		
cp1254 windows-1255 Turkish cp1255 windows-1256 Hebrew cp1257 windows-1258 Vietnam cuc_jp uijs, u-jis Japanes cuc_jp uijs, u-jis Japanes cuc_jis.2004 ucijis.2004 Japanes cuc_jis.2013 euckr, korean, ksc5601, ks_c-5601, ks_c-5601-1987, ksx1001, ks_x-1001 Japanes gb2312 chinese, cis.so8gb231280, cuc-cn, cuccn, cucgb2312-cn, gb2312-1980, gb2312-80, iso-ir-58 Simplifi gb18030 936, cp936, ms936 Japanes gb21022_jp kosc02022jp, iso-2022-jp Simplifi iso2022_jp iso2022_jp, iso-2022-jp Japanes iso2022_jp iso2022_jp, iso-2022-jp-1 Japanes iso2022_jp iso2022_jp-2, iso-2022-jp-2 Japanes iso2022_jp iso2022_jp-3, iso-2022-jp-3 Japanes iso2022_jp iso2022_jp-3, iso-2022-jp-3 Japanes iso2022_jp iso2022_jp-3, iso-2022-jp-3 Japanes iso2022_jp iso-8859-1 iso-8859-1 Japanes iso2022_jp iso-8859-1 <t< td=""><td>•</td><td></td><td></td></t<>	•		
cp1255 windows1255 Hebrew cp1257 windows1256 Arabic cp1258 windows-1257 Baltic la cwc_jp ewc_jp ewcjp, ujis, u-jis Japanes ewc_jsx0213 ewcjisx0213, ewcjisx0014 Japanes ewc_kr ewckr, korean, ksc5601, ks_c-5601, ks_c-5601-1987, ksx1001, ks_x-1001 Korean gb2312 chinese, csiso58gb231280, ewc-en, ewcen, ewcgb2312-en, gb2312-1980, gb2312-80, iso-ir-58 Simplifi gb18030 gb18030-2000 Unified br brzgb, hz-gb, hz-gb-2312 Siso2022_jp iso2022_jp iso2022_jp, iso-2022-jp Japanes iso2022_jp iso2022_jp, iso-2022-jp-2 Japanes iso2022_jp iso2022_jp-1, iso-2022-jp-2 Japanes iso2022_jp iso2022_jp-2, iso-2022-jp-2 Japanes iso2022_jp iso2022_jp-3, iso-2022-jp-3 Japanes iso2022_jp iso2022_jp-3, iso-2022-jp-3 Japanes iso2022_jp iso2022_jp-3, iso-2022-jp-3 Japanes iso2022_jp iso22jp-8, iso-8859-1, 8859, q8819 Jatin, latin, L1 West En	•		
cp1256 windows1256 Arabic cp1257 windows1257 Baltic la cuc_jp eucjp, ujis, u-jis Japanes euc_jisx0213 eucjisx0213 eucjisx0213 euc_jisx0213 eucjisx0213 eucjisx0213 euc.kr euckr, korean, ksc5601, ks_c-5601, ks_c-5601-1987, ksx1001, ks_x-1001 Korean gbk 936, cp936, ms936 Unified gb18030 pg18030-2000 Unified lx lx_gb, hz-gb, hz-gb-2312 siso2022_jp iso2022_jp iso2022_jp, iso2022jp, iso2022jp, iso2022jp, iso2022jp, iso2022jp, iso2022jp-1 Japanes iso2022_jp_2 iso2022jp-1, iso2022jp-1 Japanes iso2022_jp_3 iso2022jp-2, iso2022jp-2, iso2022jp-2 Japanes iso2022_jp_3 iso2022jp-3, iso2022jp-204 Japanes iso2022_jp_3 iso2022jp-204, iso2022jp-204 Japanes iso2022_jp iso2022jp-204, iso2022jp-204 Japanes iso2022_jp iso2022jp-3, iso2022jp-3 Japanes iso2022_jp iso22jp-3, iso2022jp-3 Japanes iso2022_jp iso22jp-3 <	•		
cp1257 windows-1257 Baltic la vindows-1258 Vietnam venuc-jis 2004 Vietnam venuc-jis 2004 Vietnam venuc-jis 2004 Vietnam venuc-jis 2004 Japanes venuc-jis 2001 Japanes venuc-jis 2002 Japanes v	•		
cp1258 windows-1258 Vietnam euc_jp euc_jp, ujis, u-jis Japanes euc_jisx0213 eucjisx0213 eujisx0213 euc_jisx0213 eucjisx0213 eucjisx0213 euc_kr euckr, korean, ksc5601, ks_c-5601, ks_c-5601-1987, ksx1001, ks_x-1001 Simplifi gb18030 p36, cp936, ms936 Unified blz p36, cp936, ms936 Unified blz ciso2022_jp ciso2022_jp, iso-2022;p iso2022_jp ciso2022_jp, iso-2022;p Japanes iso2022_jp_2 iso2022_jp-1 japanes iso2022_jp_2 iso2022_jp-2, iso-2022;p-2 Japanes iso2022_jp_a iso2022_jp-2 japanes iso2022_jp_a iso2022_jp-2 japanes iso2022_jp_axt iso222jp-2, iso-2022;p-2 Japanes iso2022_jp_axt iso222jp-axt japanes iso2022_jp_axt iso2022_jp-axt japanes iso2022_jp_axt iso2022_jp-axt japanes iso2022_jp_axt iso222_jp-axt japanes iso8859_3 iso8859_4	•		
euc_jip_ 2004 jisx0213, eucjis:2004 japanese euc_jis:x0213 eucjis:2013 eucjis:2013 eucjis:2013 eucjis:x0213 eucj	-		Baltic langua
euc_jis_2004 jisx0213 Japanes euc_jisx0213 eucjisx0213 Japanes euc_kr euck. korean, ksc5601, ks_c-5601, ks_c-5601, ks_c-5601, ks_c-5601, ks_c-101 Korean gb2312 chinese, csiso58gb231280, euc-cn, euccn, eucgb2312-cn, gb2312-1980, gb2312-80, iso-ir-58 Simplifi gb18030 gb18030-2000 Unified hz kizgb, hz-gb, hz-gb-2312 Simplifi iso2022_jp_1 csico2022_jp_1 iso20222jp, iso-2022-jp Japanes iso2022_jp_2 iso2022_jp_2, iso-2022-jp-2 Japanes iso2022_jp_2 iso2022_jp_2, iso-2022-jp-204 Japanes iso2022_jp_2 iso2022_jp_2, iso-2022-jp-204 Japanes iso2022_jp_2 iso2022_jp_2, iso-2022-jp-204 Japanes iso2022_jp_2 iso2022_jp-ax Japanes iso2022_jp_x iso2859	-		Vietnamese
euc_jisx0213 eucjisx0213 japanese euc_kr euckr, korean, ksc5601, ks_c-5601, ks_c-5601, ks_c-5601, ks_x-1001 Korean gb2312 chinese, csiso58gb231280, euc-cn, euccn, eucgb2312-cn, gb2312-1980, gb2312-80, iso-ir-58 Simplifi gb18030 gb18030-2000 Unified hz hzgb, hz-gb, hz-gb-2312 Simplifi iso2022_jp_1 iso2022jp, iso-2022jp. Japanese iso2022_jp_2 iso2022jp-1, iso-2022-jp-1 jac2022jp-2 iso2022_jp_2 iso2022jp-2, iso-2022-jp-2 Japanese iso2022_jp_2 iso2022jp-2, iso-2022-jp-20 Japanese iso2022_jp_3 iso2022jp-3, iso-2022-jp-20 Japanese iso2022_jp_a iso2022jp-3, iso-2022-jp-20 Japanese iso2022_jp_a iso2022jp-3, iso-2022-jp-3 Japanese iso2022_jp_a iso2022jp-3, iso-2022-jp-3 Japanese iso8859_1 iso8859-1, iso8859-1, iso859-1, iso-2022-jp-a Japanese iso8859_1 iso8859-1, iso8859-1, iso-2022-jp-a Japanese iso8859_3 jatin3, L3 Esperan iso8859_4 jatin4, L4 Baltic la <	• •		_
euc.kr euckr, korean, ksc5601, ks_c-5601, ks_c-5601-1987, ksx1001, ks_x-1001 Korean gb2312 chinese, cisiso58gb231280, euc-cn, euccn, eucgb2312-cn, gb2312-1980, gb2312-80, iso-ir-58 Simplifi gbk 936, cp936, mp936 Unified gb18030 lp 18030-2000 Mrgb, hz-gb, hz-gb, hz-gb-2312 Simplifi iso2022_jp cisic2022jp, iso2022jp, iso2022jp, iso2022jp. Japanes iso2022_jp_2 iso2022jp-1, iso2022jp-1 Japanes iso2022_jp_2 iso2022jp-2, iso-2022-jp-2 Japanes iso2022_jp_3 iso2022jp-2, iso-2022-jp-204 Japanes iso2022_jp_act iso2022jp-3, iso-2022-jp-204 Japanes iso2022_jp_act iso2022jp-3, iso-2022-jp-2 Japanes iso2022_jp_act iso2022jp-3, iso-2022-jp-204 Japanes iso2022_jp_act iso2022jp-3, iso-2022-jp-2 Japanes iso2022_jp_act iso2022jp-3, iso-2022-jp-2 Japanes iso2022_jp_act iso2022jp-3, iso-2022-jp-2 Japanes iso2022_jp_act iso2022jp-3, iso-2022-jp-2 Japanes iso2022_jp_act iso2022_jp-3 Japanes iso88	•		_
gb2312 chinese, csiso58gb231280, euc-cn, euccn, eucgb2312-cn, gb2312-1980, gb2312-80, iso-ir-58 Simplifi gbk 936, cp936, ms936 gb18030-2000 Unified hz hzgb, hz-gb, hz-gb-2312 Simplifi iso2022_jp_1 csiso2022jp, iso2022jp, iso-2022-jp Japanes iso2022_jp_2 iso2022jp-1, iso-2022-jp-1 Japanes iso2022_jp_3 iso2022jp-2, iso-2022-jp-2 Japanes iso2022_jp_3 iso2022jp-2004, iso-2022-jp-2004 Japanes iso2022_jp_a iso2022jp-ext, iso-2022-jp-2004 Japanes iso2022_jp_ext iso2022jp-ext, iso-2022-jp-ext Japanes iso2022_jp_ext iso-2022_jp-ext, iso-2022-jp-ext Japanes iso8859_2 iso-8859_2, latin3, L3 Esperan iso-8859_3 jatin3, L3 Esperan iso8859_3 iso-8859_4, latin4, L4 Baltic latic	•		_
gbk 936, cp936, ms936 Unified gb18030_2000 Unified gb18030_2000 Unified lz lz hzgb.nz-gb, hz-gb-2312 Simplifi iso2022_jp csiso2022jp, iso-2022jp iso-2022jp iso-2022jp iso-2022jp iso-2022jp iso-2022jp iso-2022jp iso2022jp.1 Japanes iso2022_jp_2 iso2022jp-1, iso-2022-jp-1 Japanes iso2022_jp_2 iso2022jp-2004 Japanes iso2022_jp_3 iso2022jp-2004 Japanes iso2022_jp_ast iso2022jp-2004, iso-2022-jp-3 Japanes iso2022_jp_ext iso-2022-jp-3 Japanes iso2022_jp_ext iso-2022-jp-3 Japanes iso2022_jp_ext iso-2022-jp-8t iso2022jp-204, iso-2022-jp-8t Iso-2022-jp-8t iso2022jp-3, iso-2022-jp-8t iso-2022-jp-3 Japanes iso-2022-jp-204 Japanes iso-2022-jp-2			
gb18030 gb18030-2000 Unified hz hzgb, hz-gb, hz-gb, hz-gb-2312 Simplifi iso2022_jp csiso2022_jp, iso-2022_jp Japanes iso2022_jp_2 iso2022_jp-1 Japanes iso2022_jp_2 iso2022_jp-2 Japanes iso2022_jp_a iso2022_jp-3 Japanes iso2022_jp_a iso2022_jp-3 Japanes iso2022_jp_a iso2022_jp-3 Japanes iso2022_jp_a iso2022_jp-3 Japanes iso2022_kr iso2022jp-3 Japanes iso2022_kr iso2022jp-st Korean usiso2022_kr iso2022jp-st Korean usiso859_1 iso-8859-1, iso8859-1, 8859, cp819, latin, latin1, L1 West Eu iso8859_3 iso-8859-3, latin3, L3 Esperan iso8859_4 iso-8859-4, latin4, L4 Baltic la iso8859_5 iso-8859-5, cyrillic Baltic la iso8859_1 iso-8859-1, greek, greek8 Greek iso8859_1 iso-8859-1, latin5, L5 Turkish iso8859_1 iso-8859-1, latin5, L5 <td< td=""><td>_</td><td></td><td>Simplified C</td></td<>	_		Simplified C
hz hzgb, hz-gb, hz-gb-2312 Simplifi iso2022_jp csiso2022jp, iso2022jp, iso-2022-jp Japanes iso2022_jp_1 iso2022_jp_1, iso-2022-jp-1 Japanes iso2022_jp_2 iso2022jp-2, iso-2022-jp-2 Japanes iso2022_jp_2 iso2022jp-2, iso-2022-jp-2004 Japanes iso2022_jp_3 iso2022jp-2, 2004 Japanes iso2022_jp_ext iso2022jp-ext Japanes iso2022_jp_ext iso2022jp-ext Japanes iso2022_kr csiso2022kr, iso-2022-jp-ext Japanes iso2022_kr csiso2022kr, iso-2022-jp-ext Japanes iso2022_kr csiso2022kr, iso-2022-jp-ext Japanes iso2022_kr iso-8859-1, iso8859-1, iso859-1, 8859, cp819, latin, latin1, L1 West Eu iso8859_2 iso-8859-1, iso859-1, 1859, cp819, latin, latin1, L1 West Eu iso8859_3 iso-8859-3, latin3, L3 Esperan iso8859_4 iso-8859-4, latin4, L4 Baltic la iso8859_5 iso-8859-7, greek, greek8 Greek iso8859_8 iso-8859-7, greek, greek8 Greek iso8859_1	_	•	Unified Chir
iso2022_jp	•		Unified Chin
iso2022_jp_1 iso2022_jp_1 iso2022_jp_1 iso2022_jp_2 iso2022_jp_3 iso2022_jp_3 iso2022_jp_3 iso2022_jp_3 iso2022_jp_2 iso2			Simplified C
iso2022_jp_2 iso2022_jp_2004 jso2022_jp_2004 japaness iso2022_jp_a iso2022_jp_2004, iso-2022-jp-2004 japaness iso2022_jp_ext iso2022_jp_ext jso2022_jp_ext japaness iso2022_jp_ext iso2022_jp_ext, iso-2022-jp_ext Korean iso2022_jp_ext csiso2022kr, iso-2022-kr Korean latin_1 iso-8859-1, iso8859-1, 8859, cp819, latin, latin1, L1 West Eucliso8859_2 iso-8859-2, latin2, L2 Central iso8859_3 iso-8859-3, latin3, L3 Esperan iso8859_4 iso-8859-4, latin4, L4 Baltic la iso8859_5 iso-8859-6, cyrillic Bulgaria iso8859_6 iso-8859-6, arabic Arabic iso8859_7 iso-8859-1, greek, greek8 Greek iso8859_8 iso-8859-10, latin5, L5 Turkish iso8859_10 iso-8859-10, latin6, L6 Nordic latio8, latin5,	• •	V1 V1 V1	_
iso2022_jp_2004 iso2022_jp_2004, iso-2022_jp_2004 iso2022_jp_3 iso2022_jp_3 iso2022_jp_8 iso2022_kr i	• • •	V1	
iso2022_jp_3 iso2022_jpax, iso-2022-jp-ax Japaness iso2022_ip_ext iso2022_jp_ext, iso-2022-jp_ext Japaness iso2022_kr csiso2022_kr, iso-2022-kr Korean latin_1 iso-8859-1, iso8859-1, 8859-c, p819, latin, latin1, L1 West Eu iso8859_2 iso-8859-1, latin3, L3 Esperan iso8859_3 iso-8859-3, latin3, L3 Esperan iso8859_4 iso-8859-4, latin4, L4 Baltic latin4 iso8859_5 iso-8859-6, cyrillic Bulgaria iso8859_6 iso-8859-6, arabic Arabic iso8859_8 iso-8859-7, greek, greek8 Greek iso8859_8 iso-8859-9, latin5, L5 Turkish iso8859_10 iso-8859-10, latin6, L6 Nordic latio8 iso8859_13 iso-8859-13 Baltic latic latio8 iso8859_14 iso-8859-14, latin8, L8 Celtic latio8 iso8859_15 iso-8859-15 Western johab cpl361, msl361 Korean koi8_r maccyrillic macgreek Greek mac_iceland maclatin2, maccentraleurope	• •	V1	Japanese, Ko
iso2022_jp_ext iso2022_jp_ext, iso-2022-jp_ext Japaness iso2022_kr csiso2022kr, iso-2022-kr Korean latin_1 iso-8859-1, iso8859-1, 8859, cp819, latin, latin1, L1 West Eu iso8859_2 iso-8859-2, latin2, L2 Central iso8859_3 iso-8859-3, latin3, L3 Esperan iso8859_4 iso-8859-4, latin4, L4 Baltic la iso8859_5 iso-8859-5, cyrillic Bulgaria iso8859_6 iso-8859-6, arabic Arabic iso8859_7 iso-8859-7, greek, greek8 Greek iso8859_8 iso-8859-8, hebrew Hebrew iso8859_10 iso-8859-10, latin6, L6 Nordic latios iso8859_13 iso-8859-13 Baltic la iso8859_14 iso-8859-15 Western johab cp1361, ms1361 Korean koi8_r koi8_r Koi8_r iso-8859-15 iso-8859-16 Bulgaria iso-8859-16 greek Greek hoib cp1361, ms1361 Korean koi8_r mac-greek macgreek	• • •		Japanese
iso2022_kr csiso2022kr, iso2022kr, iso-2022-kr Korean latin_1 iso-8859-1, iso8859-1, 8859, cp819, latin, latin1, L1 West Eu iso8859_2 iso-8859-2, latin2, L2 Central iso8859_3 iso-8859-3, latin3, L3 Esperan iso8859_4 iso-8859-4, latin4, L4 Baltic la iso8859_5 iso-8859-5, cyrillic Bulgaria iso8859_6 iso-8859-6, arabic Arabic iso8859_7 iso-8859-7, greek, greek8 Greek iso8859_8 iso-8859-9, latin5, L5 Turkish iso8859_10 iso-8859-10, latin6, L6 Nordic la iso8859_11 iso-8859-13 Baltic la iso8859_14 iso-8859-15 Western johab cp1361, ms1361 Korean koi8_r koi8_r Russian koi8_r mac_greek macgreek mac_greek macgreek Greek mac_iceland maciceland Icelandi mac_latin2 maclatin2, maccentraleurope Central Western	• •	01	Japanese
latin_1 iso-8859-1, iso8859-1, 8859, cp819, latin, latin1, L1 West Eurose859-2 iso8859_2 iso-8859-2, latin2, L2 Central iso8859_3 iso-8859-3, latin3, L3 Esperan iso8859_4 iso-8859-4, latin4, L4 Baltic la iso8859_5 iso-8859-5, cyrillic Bulgaria iso8859_6 iso-8859-6, arabic Arabic iso8859_7 iso-8859-7, greek, greek8 Greek iso8859_8 iso-8859-8, hebrew Iso-8859-9, latin5, L5 iso8859_10 iso-8859-10, latin6, L6 Nordic latios iso8859_11 iso-8859-13 Baltic latios iso8859_14 iso-8859-14, latin8, L8 Celtic latios iso8859_15 iso-8859-15 Western johab cp1361, ms1361 Korean koi8_u mac_cyrillic Bulgaria mac_greek macgreek Greek mac_iceland macieland Icelandi mac_latin2 maclatin2, maccentraleurope Central mac_roman Western	• •	V1.	Japanese
iso8859_2 iso-8859-2, latin2, L2 Central iso8859_3 iso-8859-3, latin3, L3 Esperan iso8859_4 iso-8859-4, latin4, L4 Baltic la iso8859_5 iso-8859-5, cyrillic Bulgaria iso8859_7 iso-8859-6, arabic Arabic iso8859_8 iso-8859-7, greek, greek8 Greek iso8859_8 iso-8859-9, latin5, L5 Turkish iso8859_10 iso-8859-10, latin6, L6 Nordic lation iso8859_11 iso-8859-13 Baltic lation iso8859_14 iso-8859-14, latin8, L8 Celtic lation iso8859_15 iso-8859-15 Western johab cp1361, ms1361 Korean koi8_u mac_cyrillic macgreek mac_greek macgreek macgreek mac_iceland maciceland Icelandi mac_latin2 maclatin2, maccentraleurope Central mac_roman Western	iso2022_kr		
iso8859_3 iso-8859-3, latin3, L3 Esperan iso8859_4 iso-8859-4, latin4, L4 Baltic la iso8859_5 iso-8859-5, cyrillic Bulgaria iso8859_6 iso-8859-6, arabic Arabic iso8859_7 iso-8859-7, greek, greek8 Greek iso8859_8 iso-8859-8, hebrew Hebrew iso8859_9 iso-8859-9, latin5, L5 Turkish iso8859_10 iso-8859-10, latin6, L6 Nordic la iso8859_13 iso-8859-13 Baltic la iso8859_14 iso-8859-14, latin8, L8 Celtic la iso8859_15 iso-8859-15 Western johab cp1361, ms1361 Korean koi8_r koi8_r Ukrainia koi8_r mac_greek macgreek mac_jerek macjerek Greek mac_iceland maclatin2 maclatin2, maccentraleurope Central mac_roman Western	latin_1		West Europe
iso8859_4 iso-8859-4, latin4, L4 Baltic lation iso8859_5 iso-8859-5, cyrillic Bulgaria iso8859_6 iso-8859-6, arabic Arabic iso8859_7 iso-8859-7, greek, greek8 Greek iso8859_8 iso-8859-8, hebrew Hebrew iso8859_10 iso-8859-10, latin6, L6 Nordic lation iso8859_13 iso-8859-13 Baltic lation iso8859_14 iso-8859-14, latin8, L8 Celtic lation iso8859_15 iso-8859-15 Western johab cp1361, ms1361 Korean koi8_r Russian koi8_r Greek mac_greek macgreek mac_greek macgreek mac_iceland Icelandi mac_latin2 maclatin2, maccentraleurope Central mac_roman Western	iso8859_2		Central and l
iso8859_5 iso-8859-5, cyrillic Bulgaria iso8859_6 iso-8859-6, arabic Arabic iso8859_7 iso-8859-7, greek, greek8 Greek iso8859_8 iso-8859-8, hebrew Hebrew iso8859_9 iso-8859-9, latin5, L5 Turkish iso8859_10 iso-8859-10, latin6, L6 Nordic lation iso8859_13 iso-8859-13 Baltic lation iso8859_14 iso-8859-14, latin8, L8 Celtic lation iso8859_15 iso-8859-15 Western johab cp1361, ms1361 Korean koi8_r Rois Russian koi8_u mac_greek Greek mac_jereek macgreek Greek mac_iceland macitalin2 maclatin2, maccentraleurope Central mac_roman Western	iso8859_3	iso-8859-3, latin3, L3	Esperanto, M
iso8859_6 iso-8859-6, arabic Arabic iso8859_7 iso-8859-7, greek, greek8 Greek iso8859_8 iso-8859-8, hebrew Hebrew iso8859_9 iso-8859-9, latin5, L5 Turkish iso8859_10 iso-8859-10, latin6, L6 Nordic I iso8859_13 iso-8859-13 Baltic la iso8859_14 iso-8859-14, latin8, L8 Celtic la iso8859_15 iso-8859-15 Western johab cp1361, ms1361 Korean koi8_r Russian koi8_u mac_cyrillic macyrillic mac_greek macgreek Greek mac_iceland maciceland Icelandi mac_latin2 maclatin2, maccentraleurope Central mac_roman Western	iso8859_4	iso-8859-4, latin4, L4	Baltic langua
iso8859_7 iso-8859-7, greek, greek8 iso-8859_8 iso-8859-8, hebrew iso8859_9 iso-8859-9, latin5, L5 Turkish iso8859_10 iso-8859-10, latin6, L6 Nordic Iso8859_13 iso-8859-14 iso-8859-14, latin8, L8 Celtic latiso8859_15 iso-8859-15 cp1361, ms1361 Korean Russian koi8_r koi8_r koi8_u mac_cyrillic mac_greek mac_jreek mac_jreek mac_iceland mac_latin2 mac_latin2 mac_man mac_orman mac_orman mac_orman week mac_iceland mac_orman mac_orman week Hebrew	iso8859_5	iso-8859-5, cyrillic	Bulgarian, B
iso8859_8iso-8859-8, hebrewHebrewiso8859_9iso-8859-9, latin5, L5Turkishiso8859_10iso-8859-10, latin6, L6Nordic latio8859_13iso8859_13iso-8859-13Baltic latio8859_14iso8859_14iso-8859-14, latin8, L8Celtic latio8859_15johabcp1361, ms1361Koreankoi8_rRussianUkrainiakoi8_umac_cyrillicmacyrillicBulgariamac_greekmacgreekGreekmac_icelandmacicelandIcelandimac_latin2maclatin2, maccentraleuropeCentralmac_romanWestern	iso8859_6	iso-8859-6, arabic	Arabic
iso8859_9 iso-8859-9, latin5, L5 iso8859_10 iso-8859-10, latin6, L6 iso8859_13 iso-8859-13 iso-8859-14, latin8, L8 iso8859_14 iso-8859-15 iso-8859-15 johab cp1361, ms1361 Korean koi8_r koi8_r koi8_u Rac_cyrillic mac_cyrillic mac_greek mac_iceland mac_iceland mac_iceland mac_latin2 mac_aroman macroman iso-8859-10, latin5, L5 Nordic I	iso8859_7	iso-8859-7, greek, greek8	Greek
iso8859_10 iso-8859-10, latin6, L6 iso8859_13 iso-8859-14 iso-8859-14, latin8, L8 Celtic latiso8859_15 iso-8859-15 cp1361, ms1361 Korean koi8_r koi8_u mac_cyrillic mac_cyrillic mac_greek mac_iceland mac_iceland mac_latin2 mac_roman macroman macroman macroman macroman Nordic latin2 Nordic latin2, maccentraleurope macgreek mac_iceland mac_ordic latin2 macroman macroman Western Nordic latin2 Nordic latin6, L6 Nordic latin2 Nordic latin8, L8 Celtic latin6 Nordic latin2 Nordic latin8, L8 Celtic latin6 Nordic latin2 Nordic latin8, L8 Celtic latin6, L6 Nordic latin2 Nordic latin8, L8 Celtic latin6, L6 Nordic latin8 Baltic latin6, L6 Nordic latin8, L8 Celtic lat	iso8859_8	iso-8859-8, hebrew	Hebrew
iso8859_13 iso-8859-13 Celtic latio8859_14 iso-8859-14, latin8, L8 Celtic latio8859_15 iso-8859-15 Western johab cp1361, ms1361 Korean koi8_r koi8_u Ukrainia mac_cyrillic maccyrillic maccyrillic maccjeek mac_iceland maciceland maciceland mac_latin2 maccontraleurope maccoman macroman western western western western celtic lation and latin2 maccontraleurope maccoman western	iso8859_9	iso-8859-9, latin5, L5	Turkish
iso8859_14 iso-8859-14, latin8, L8 Celtic latin8 iso-8859_15 iso-8859-15 Western johab cp1361, ms1361 Korean koi8_r Russian koi8_u Ukrainia mac_cyrillic maccyrillic maccyrillic macgreek macjiceland maciceland maciceland maciceland maciceland macjiceland macj	iso8859_10	iso-8859-10, latin6, L6	Nordic langu
iso8859_15 iso-8859-15 Western johab cp1361, ms1361 Korean koi8_r koi8_u Russian mac_cyrillic maccyrillic macgreek macjreek macjreek maciceland maciceland maciceland maciceland macjelatin2 maccentraleurope macjelatin2 macroman macroman Western	iso8859_13	iso-8859-13	Baltic langua
iso8859_15 iso-8859-15 Western johab cp1361, ms1361 Korean koi8_r koi8_u Ukrainia mac_cyrillic maccyrillic macgreek macgreek mac_iceland maciceland maciceland maclatin2 maclatin2, maccentraleurope macgreek macgroman macroman Western	iso8859_14	iso-8859-14, latin8, L8	Celtic langua
koi8_rRussiankoi8_uUkrainiamac_cyrillicmaccyrillicmac_greekmacgreekmac_icelandmacicelandmac_latin2maclatin2, maccentraleuropeCentralmac_romanmacroman	iso8859_15	iso-8859-15	Western Eur
koi8_rRussiankoi8_uUkrainiamac_cyrillicmaccyrillicmac_greekmacgreekmac_icelandmacicelandmac_latin2maclatin2, maccentraleuropeCentralmac_romanmacroman	johab	cp1361, ms1361	Korean
koi8_uUkrainiamac_cyrillicmaccyrillicmac_greekmacgreekmac_icelandmacicelandmac_latin2maclatin2, maccentraleuropemac_romanmacromanWestern	•	-	Russian
mac_cyrillicmaccyrillicBulgariamac_greekmacgreekGreekmac_icelandmacicelandIcelandimac_latin2maclatin2, maccentraleuropeCentralmac_romanmacromanWestern			Ukrainian
mac_greekmacgreekGreekmac_icelandmacicelandIcelandimac_latin2maclatin2, maccentraleuropeCentralmac_romanmacromanWestern		maccyrillic	Bulgarian, B
mac_icelandmacicelandIcelandimac_latin2maclatin2, maccentraleuropeCentralmac_romanmacromanWestern	•	·	_
mac_latin2maclatin2, maccentraleuropeCentralmac_romanmacromanWestern	•		Icelandic
mac_roman macroman Western			Central and l
		•	Western Eur
Turkish hacterian			
	mac_tarRish	IIIW-twi Middle	Turkisii

Codec	Aliases	Languages
ptcp154	csptcp154, pt154, cp154, cyrillic-asian	Kazakh
shift_jis	csshiftjis, shiftjis, sjis, s_jis	Japanese
shift_jis_2004	shiftjis2004, sjis_2004, sjis2004	Japanese
shift_jisx0213	shiftjisx0213, sjisx0213, s_jisx0213	Japanese
utf_16	U16, utf16	all languages
utf_16_be	UTF-16BE	all languages
utf_16_le	UTF-16LE	all languages
utf_7	U7	all languages
utf_8	U8, UTF, utf8	all languages

A number of codecs are specific to Python, so their codec names have no meaning outside Python. Some of them don't convert from Unicode strings to byte strings, but instead use the property of the Python codecs machinery that any bijective function with one argument can be considered as an encoding.

For the codecs listed below, the result in the "encoding" direction is always a byte string. The result of the "decoding" direction is listed as operand type in the table.

Codec	Aliases	Operand type	Purpose
base64_codec	base64, base-64	byte string	Convert operand to MIME base64
bz2_codec	bz2	byte string	Compress the operand using bz2
hex_codec	hex	byte string	Convert operand to hexadecimal representation
idna		Unicode string	Implements RFC 3490. New in version 2.3
mbcs	dbcs	Unicode string	Windows only: Encode operand according
palmos		Unicode string	Encoding of PalmOS 3.5
punycode		Unicode string	Implements RFC 3492. New in version 2.3
quopri_codec	quopri, quoted-printable, quotedprintable	byte string	Convert operand to MIME quoted printable
raw_unicode_escape		Unicode string	Produce a string that is suitable as raw Unic
rot_13	rot13	byte string	Returns the Caesar-cypher encryption of the
string_escape		byte string	Produce a string that is suitable as string lite
undefined		any	Raise an exception for all conversion. Can l
unicode_escape		Unicode string	Produce a string that is suitable as Unicode
unicode_internal		Unicode string	Return the internal representation of the ope
uu_codec	uu	byte string	Convert the operand using uuencode
zlib_codec	zip, zlib	byte string	Compress the operand using gzip

4.9.3 encodings.idna — Internationalized Domain Names in Applications

New in version 2.3.

This module implements RFC 3490 (Internationalized Domain Names in Applications) and RFC 3492 (Nameprep: A Stringprep Profile for Internationalized Domain Names (IDN)). It builds upon the punycode encoding and stringprep.

These RFCs together define a protocol to support non-ASCII characters in domain names. A domain name containing non-ASCII characters (such as "www.Alliancefrançaise.nu") is converted into an ASCII-compatible encoding (ACE, such as "www.xn-alliancefranaise-npb.nu"). The ACE form of the domain name is then used in all places where arbitrary characters are not allowed by the protocol, such as DNS queries, HTTP Host: fields, and so on. This conversion is carried out in the application; if possible invisible to the user: The application should transparently convert Unicode domain labels to IDNA on the wire, and convert back ACE labels to Unicode before presenting them to the user.

Python supports this conversion in several ways: The idna codec allows to convert between Unicode and the ACE. Furthermore, the socket module transparently converts Unicode host names to ACE, so that applications need not be concerned about converting host names themselves when they pass them to the socket module. On top of that, modules that have host names as function parameters, such as httplib and ftplib, accept Unicode

host names (httplib then also transparently sends an IDNA hostname in the Host: field if it sends that field at all).

When receiving host names from the wire (such as in reverse name lookup), no automatic conversion to Unicode is performed: Applications wishing to present such host names to the user should decode them to Unicode.

The module encodings.idna also implements the nameprep procedure, which performs certain normalizations on host names, to achieve case-insensitivity of international domain names, and to unify similar characters. The nameprep functions can be used directly if desired.

nameprep(label)

Return the name prepped version of label. The implementation currently assumes query strings, so Allow Unassigned is true.

ToASCII(label)

Convert a label to ASCII, as specified in RFC 3490. UseSTD3ASCIIRules is assumed to be false.

ToUnicode(label)

Convert a label to Unicode, as specified in RFC 3490.

4.10 unicodedata — Unicode Database

This module provides access to the Unicode Character Database which defines character properties for all Unicode characters. The data in this database is based on the 'UnicodeData.txt' file version 3.2.0 which is publically available from ftp://ftp.unicode.org/.

The module uses the same names and symbols as defined by the UnicodeData File Format 3.2.0 (see http://www.unicode.org/Public/UNIDATA/UnicodeData.html). It defines the following functions:

lookup(name)

Look up character by name. If a character with the given name is found, return the corresponding Unicode character. If not found, KeyError is raised.

name (unichr, default)

Returns the name assigned to the Unicode character *unichr* as a string. If no name is defined, *default* is returned, or, if not given, ValueError is raised.

decimal(unichr , default)

Returns the decimal value assigned to the Unicode character *unichr* as integer. If no such value is defined, *default* is returned, or, if not given, ValueError is raised.

digit(unichr[, default])

Returns the digit value assigned to the Unicode character *unichr* as integer. If no such value is defined, *default* is returned, or, if not given, ValueError is raised.

numeric(unichr[, default])

Returns the numeric value assigned to the Unicode character *unichr* as float. If no such value is defined, *default* is returned, or, if not given, ValueError is raised.

category(unichr)

Returns the general category assigned to the Unicode character unichr as string.

bidirectional(unichr)

Returns the bidirectional category assigned to the Unicode character *unichr* as string. If no such value is defined, an empty string is returned.

combining(unichr)

Returns the canonical combining class assigned to the Unicode character *unichr* as integer. Returns 0 if no combining class is defined.

$\verb"east_asian_width" (\textit{unichr}")$

Returns the east asian width assigned to the Unicode character unichr as string. New in version 2.4.

mirrored(unichr)

Returns the mirrored property assigned to the Unicode character unichr as integer. Returns 1 if the character

has been identified as a "mirrored" character in bidirectional text, 0 otherwise.

decomposition(unichr)

Returns the character decomposition mapping assigned to the Unicode character *unichr* as string. An empty string is returned in case no such mapping is defined.

normalize(form, unistr)

Return the normal form for the Unicode string *unistr*. Valid values for form are 'NFC', 'NFKC', 'NFD', and 'NFKD'.

The Unicode standard defines various normalization forms of a Unicode string, based on the definition of canonical equivalence and compatibility equivalence. In Unicode, several characters can be expressed in various way. For example, the character U+00C7 (LATIN CAPITAL LETTER C WITH CEDILLA) can also be expressed as the sequence U+0043 (LATIN CAPITAL LETTER C) U+0327 (COMBINING CEDILLA).

For each character, there are two normal forms: normal form C and normal form D. Normal form D (NFD) is also known as canonical decomposition, and translates each character into its decomposed form. Normal form C (NFC) first applies a canonical decomposition, then composes pre-combined characters again.

In addition to these two forms, there two additional normal forms based on compatibility equivalence. In Unicode, certain characters are supported which normally would be unified with other characters. For example, U+2160 (ROMAN NUMERAL ONE) is really the same thing as U+0049 (LATIN CAPITAL LETTER I). However, it is supported in Unicode for compatibility with existing character sets (e.g. gb2312).

The normal form KD (NFKD) will apply the compatibility decomposition, i.e. replace all compatibility characters with their equivalents. The normal form KC (NFKC) first applies the compatibility decomposition, followed by the canonical composition.

New in version 2.3.

In addition, the module exposes the following constant:

unidata_version

The version of the Unicode database used in this module.

New in version 2.3.

4.11 stringprep — Internet String Preparation

When identifying things (such as host names) in the internet, it is often necessary to compare such identifications for "equality". Exactly how this comparison is executed may depend on the application domain, e.g. whether it should be case-insensitive or not. It may be also necessary to restrict the possible identifications, to allow only identifications consisting of "printable" characters.

RFC 3454 defines a procedure for "preparing" Unicode strings in internet protocols. Before passing strings onto the wire, they are processed with the preparation procedure, after which they have a certain normalized form. The RFC defines a set of tables, which can be combined into profiles. Each profile must define which tables it uses, and what other optional parts of the stringprep procedure are part of the profile. One example of a stringprep profile is nameprep, which is used for internationalized domain names.

The module stringprep only exposes the tables from RFC 3454. As these tables would be very large to represent them as dictionaries or lists, the module uses the Unicode character database internally. The module source code itself was generated using the mkstringprep.py utility.

As a result, these tables are exposed as functions, not as data structures. There are two kinds of tables in the RFC: sets and mappings. For a set, stringprep provides the "characteristic function", i.e. a function that returns true if the parameter is part of the set. For mappings, it provides the mapping function: given the key, it returns the associated value. Below is a list of all functions available in the module.

in_table_a1(code)

Determine whether *code* is in table A.1 (Unassigned code points in Unicode 3.2).

in_table_b1(code)

Determine whether *code* is in tableB.1 (Commonly mapped to nothing).

map_table_b2(code)

Return the mapped value for code according to table B.2 (Mapping for case-folding used with NFKC).

map_table_b3(code)

Return the mapped value for *code* according to table B.3 (Mapping for case-folding used with no normalization).

in_table_c11(code)

Determine whether *code* is in tableC.1.1 (ASCII space characters).

in_table_c12(code)

Determine whether *code* is in tableC.1.2 (Non-ASCII space characters).

in_table_c11_c12(code)

Determine whether *code* is in table C.1 (Space characters, union of C.1.1 and C.1.2).

in_table_c21(code)

Determine whether *code* is in tableC.2.1 (ASCII control characters).

in_table_c22(code)

Determine whether *code* is in tableC.2.2 (Non-ASCII control characters).

in_table_c21_c22(code)

Determine whether *code* is in table C.2 (Control characters, union of C.2.1 and C.2.2).

in_table_c3(code)

Determine whether *code* is in tableC.3 (Private use).

in_table_c4(code)

Determine whether *code* is in tableC.4 (Non-character code points).

in_table_c5(code)

Determine whether *code* is in tableC.5 (Surrogate codes).

in_table_c6(code)

Determine whether *code* is in tableC.6 (Inappropriate for plain text).

in_table_c7(code)

Determine whether *code* is in tableC.7 (Inappropriate for canonical representation).

$\verb"in_table_c8" (code")$

Determine whether *code* is in tableC.8 (Change display properties or are deprecated).

in_table_c9(code)

Determine whether *code* is in tableC.9 (Tagging characters).

in_table_d1(code)

Determine whether *code* is in tableD.1 (Characters with bidirectional property "R" or "AL").

in_table_d2(code)

Determine whether *code* is in table D.2 (Characters with bidirectional property "L").

Miscellaneous Services

The modules described in this chapter provide miscellaneous services that are available in all Python versions. Here's an overview:

Documentation generator and online help system. **doctest**A framework for verifying interactive Python examples.

unittest Unit testing framework for Python.

Regression tests package containing the testing suite for Python.

test.test_support Support for Python regression tests.

decimal Implementation of the General Decimal Arithmetic Specification.

math Mathematical functions (sin() etc.).

cmath Mathematical functions for complex numbers.

random Generate pseudo-random numbers with various common distributions.

whrandomFloating point pseudo-random number generator.bisectArray bisection algorithms for binary searching.

collections High-performance datatypes

heapq Heap queue algorithm (a.k.a. priority queue).

array Efficient arrays of uniformly typed numeric values.

sets Implementation of sets of unique elements.itertools Functions creating iterators for efficient looping.

Configuration file parser.

fileinput Perl-like iteration over lines from multiple input streams, with "save in place" capability. **calendar** Functions for working with calendars, including some emulation of the UNIX **cal** program.

cmd Build line-oriented command interpreters.

shlex Simple lexical analysis for UNIX shell-like languages.

5.1 pydoc — Documentation generator and online help system

New in version 2.1.

The pydoc module automatically generates documentation from Python modules. The documentation can be presented as pages of text on the console, served to a Web browser, or saved to HTML files.

The built-in function help() invokes the online help system in the interactive interpreter, which uses pydoc to generate its documentation as text on the console. The same text documentation can also be viewed from outside the Python interpreter by running **pydoc** as a script at the operating system's command prompt. For example, running

pydoc sys

at a shell prompt will display documentation on the sys module, in a style similar to the manual pages shown by the UNIX **man** command. The argument to **pydoc** can be the name of a function, module, or package, or a dotted reference to a class, method, or function within a module or module in a package. If the argument to **pydoc** looks like a path (that is, it contains the path separator for your operating system, such as a slash in UNIX), and refers to

an existing Python source file, then documentation is produced for that file.

Specifying a -w flag before the argument will cause HTML documentation to be written out to a file in the current directory, instead of displaying text on the console.

Specifying a -k flag before the argument will search the synopsis lines of all available modules for the keyword given as the argument, again in a manner similar to the UNIX man command. The synopsis line of a module is the first line of its documentation string.

You can also use **pydoc** to start an HTTP server on the local machine that will serve documentation to visiting Web browsers. **pydoc -p 1234** will start a HTTP server on port 1234, allowing you to browse the documentation at http://localhost:1234/ in your preferred Web browser. **pydoc -g** will start the server and additionally bring up a small Tkinter-based graphical interface to help you search for documentation pages.

When **pydoc** generates documentation, it uses the current environment and path to locate modules. Thus, invoking **pydoc spam** documents precisely the version of the module you would get if you started the Python interpreter and typed 'import spam'.

Module docs for core modules are assumed to reside in http://www.python.org/doc/current/lib/. This can be overridden by setting the PYTHONDOCS environment variable to a different URL or to a local directory containing the Library Reference Manual pages.

5.2 doctest — Test interactive Python examples

The doctest module searches for pieces of text that look like interactive Python sessions, and then executes those sessions to verify that they work exactly as shown. There are several common ways to use doctest:

- To check that a module's docstrings are up-to-date by verifying that all interactive examples still work as documented.
- To perform regression testing by verifying that interactive examples from a test file or a test object work as expected.
- To write tutorial documentation for a package, liberally illustrated with input-output examples. Depending on whether the examples or the expository text are emphasized, this has the flavor of "literate testing" or "executable documentation".

Here's a complete but small example module:

```
This is the "example" module.
The example module supplies one function, factorial(). For example,
>>> factorial(5)
120
def factorial(n):
    """Return the factorial of n, an exact integer >= 0.
    If the result is small enough to fit in an int, return an int.
    Else return a long.
    >>> [factorial(n) for n in range(6)]
    [1, 1, 2, 6, 24, 120]
    >>> [factorial(long(n)) for n in range(6)]
    [1, 1, 2, 6, 24, 120]
    >>> factorial(30)
    265252859812191058636308480000000L
    >>> factorial(30L)
    265252859812191058636308480000000L
    >>> factorial(-1)
    Traceback (most recent call last):
    ValueError: n must be >= 0
    Factorials of floats are OK, but the float must be an exact integer:
    >>> factorial(30.1)
    Traceback (most recent call last):
    ValueError: n must be exact integer
    >>> factorial(30.0)
    265252859812191058636308480000000L
    It must also not be ridiculously large:
    >>> factorial(1e100)
    Traceback (most recent call last):
    OverflowError: n too large
```

```
import math
    if not n \ge 0:
       raise ValueError("n must be >= 0")
    if math.floor(n) != n:
       raise ValueError("n must be exact integer")
    if n+1 == n: # catch a value like 1e300
       raise OverflowError("n too large")
    result = 1
    factor = 2
    while factor <= n:
       result *= factor
        factor += 1
    return result
def _test():
    import doctest
    doctest.testmod()
if __name__ == "__main__":
    _test()
```

If you run 'example.py' directly from the command line, doctest works its magic:

```
$ python example.py$
```

There's no output! That's normal, and it means all the examples worked. Pass -v to the script, and doctest prints a detailed log of what it's trying, and prints a summary at the end:

```
$ python example.py -v
Trying:
    factorial(5)
Expecting:
    120
ok
Trying:
    [factorial(n) for n in range(6)]
Expecting:
    [1, 1, 2, 6, 24, 120]
ok
Trying:
    [factorial(long(n)) for n in range(6)]
Expecting:
    [1, 1, 2, 6, 24, 120]
ok
```

And so on, eventually ending with:

That's all you need to know to start making productive use of doctest! Jump in. The following sections provide full details. Note that there are many examples of doctests in the standard Python test suite and libraries. Especially useful examples can be found in the standard test file 'Lib/test/test_doctest.py'.

5.2.1 Simple Usage: Checking Examples in Docstrings

The simplest way to start using doctest (but not necessarily the way you'll continue to do it) is to end each module M with:

```
def _test():
    import doctest
    doctest.testmod()

if __name__ == "__main__":
    _test()
```

doctest then examines docstrings in module M.

Running the module as a script causes the examples in the docstrings to get executed and verified:

```
python M.py
```

This won't display anything unless an example fails, in which case the failing example(s) and the cause(s) of the failure(s) are printed to stdout, and the final line of output is '***Test Failed*** N failures.', where N is the number of examples that failed.

Run it with the -v switch instead:

```
python M.py -v
```

and a detailed report of all examples tried is printed to standard output, along with assorted summaries at the end.

You can force verbose mode by passing verbose=True to testmod(), or prohibit it by passing verbose=False. In either of those cases, sys.argv is not examined by testmod() (so passing -v or not has no effect).

For more information on testmod(), see section 5.2.4.

5.2.2 Simple Usage: Checking Examples in a Text File

Another simple application of doctest is testing interactive examples in a text file. This can be done with the testfile() function:

```
import doctest
doctest.testfile("example.txt")
```

That short script executes and verifies any interactive Python examples contained in the file 'example.txt'. The file content is treated as if it were a single giant docstring; the file doesn't need to contain a Python program! For example, perhaps 'example.txt' contains this:

Running doctest.testfile("example.txt") then finds the error in this documentation:

```
File "./example.txt", line 14, in example.txt
Failed example:
    factorial(6)
Expected:
    120
Got:
    720
```

As with testmod(), testfile() won't display anything unless an example fails. If an example does fail, then the failing example(s) and the cause(s) of the failure(s) are printed to stdout, using the same format as testmod().

By default, testfile() looks for files in the calling module's directory. See section 5.2.4 for a description of the optional arguments that can be used to tell it to look for files in other locations.

Like testmod(), testfile()'s verbosity can be set with the **-v** command-line switch or with the optional keyword argument *verbose*.

For more information on testfile(), see section 5.2.4.

5.2.3 How It Works

This section examines in detail how doctest works: which docstrings it looks at, how it finds interactive examples, what execution context it uses, how it handles exceptions, and how option flags can be used to control its behavior. This is the information that you need to know to write doctest examples; for information about actually running doctest on these examples, see the following sections.

Which Docstrings Are Examined?

The module docstring, and all function, class and method docstrings are searched. Objects imported into the module are not searched.

In addition, if M.__test__ exists and "is true", it must be a dict, and each entry maps a (string) name to a function object, class object, or string. Function and class object docstrings found from M.__test__ are searched, and strings are treated as if they were docstrings. In output, a key K in M.__test__ appears with name

```
<name of M>.__test__.K
```

Any classes found are recursively searched similarly, to test docstrings in their contained methods and nested classes.

Changed in version 2.4: A "private name" concept is deprecated and no longer documented.

How are Docstring Examples Recognized?

In most cases a copy-and-paste of an interactive console session works fine, but doctest isn't trying to do an exact emulation of any specific Python shell. All hard tab characters are expanded to spaces, using 8-column tab stops. If you don't believe tabs should mean that, too bad: don't use hard tabs, or write your own DocTestParser class.

Changed in version 2.4: Expanding tabs to spaces is new; previous versions tried to preserve hard tabs, with confusing results.

```
>>> # comments are ignored
>>> x = 12
>>> x
12
>>> if x == 13:
        print "yes"
. . .
... else:
        print "no"
. . .
        print "NO"
. . .
        print "NO!!!"
. . .
. . .
no
NO
NO!!!
>>>
```

Any expected output must immediately follow the final '>>> ' or '... ' line containing the code, and the expected output (if any) extends to the next '>>> ' or all-whitespace line.

The fine print:

- Expected output cannot contain an all-whitespace line, since such a line is taken to signal the end of expected output. If expected output does contain a blank line, put <BLANKLINE> in your doctest example each place a blank line is expected. Changed in version 2.4: <BLANKLINE> was added; there was no way to use expected output containing empty lines in previous versions.
- Output to stdout is captured, but not output to stderr (exception tracebacks are captured via a different means).
- If you continue a line via backslashing in an interactive session, or for any other reason use a backslash, you should use a raw docstring, which will preserve your backslashes exactly as you type them:

```
>>> def f(x):
... r'''Backslashes in a raw docstring: m\n'''
>>> print f.__doc__
Backslashes in a raw docstring: m\n
```

Otherwise, the backslash will be interpreted as part of the string. For example, the "\" above would be interpreted as a newline character. Alternatively, you can double each backslash in the doctest version (and not use a raw string):

```
>>> def f(x):
... '''Backslashes in a raw docstring: m\\n'''
>>> print f.__doc__
Backslashes in a raw docstring: m\n
```

• The starting column doesn't matter:

and as many leading whitespace characters are stripped from the expected output as appeared in the initial '>>> ' line that started the example.

What's the Execution Context?

By default, each time doctest finds a docstring to test, it uses a *shallow copy* of M's globals, so that running tests doesn't change the module's real globals, and so that one test in M can't leave behind crumbs that accidentally allow another test to work. This means examples can freely use any names defined at top-level in M, and names defined earlier in the docstring being run. Examples cannot see names defined in other docstrings.

You can force use of your own dict as the execution context by passing globs=your_dict to testmod() or testfile() instead.

What About Exceptions?

No problem, provided that the traceback is the only output produced by the example: just paste in the traceback. Since tracebacks contain details that are likely to change rapidly (for example, exact file paths and line numbers), this is one case where doctest works hard to be flexible in what it accepts.

Simple example:

```
>>> [1, 2, 3].remove(42)
Traceback (most recent call last):
  File "<stdin>", line 1, in ?
ValueError: list.remove(x): x not in list
```

That doctest succeeds if ValueError is raised, with the 'list.remove(x): x not in list' detail as shown.

The expected output for an exception must start with a traceback header, which may be either of the following two lines, indented the same as the first line of the example:

```
Traceback (most recent call last):
Traceback (innermost last):
```

The traceback header is followed by an optional traceback stack, whose contents are ignored by doctest. The traceback stack is typically omitted, or copied verbatim from an interactive session.

The traceback stack is followed by the most interesting part: the line(s) containing the exception type and detail. This is usually the last line of a traceback, but can extend across multiple lines if the exception has a multi-line detail:

```
>>> raise ValueError('multi\n line\ndetail')
Traceback (most recent call last):
   File "<stdin>", line 1, in ?
ValueError: multi
    line
detail
```

The last three lines (starting with ValueError) are compared against the exception's type and detail, and the rest are ignored.

Best practice is to omit the traceback stack, unless it adds significant documentation value to the example. So the last example is probably better as:

```
>>> raise ValueError('multi\n line\ndetail')
Traceback (most recent call last):
    ...
ValueError: multi
    line
detail
```

Note that tracebacks are treated very specially. In particular, in the rewritten example, the use of '...' is independent of doctest's ELLIPSIS option. The ellipsis in that example could be left out, or could just as well be three (or three hundred) commas or digits, or an indented transcript of a Monty Python skit.

Some details you should read once, but won't need to remember:

- Doctest can't guess whether your expected output came from an exception traceback or from ordinary printing. So, e.g., an example that expects 'ValueError: 42 is prime' will pass whether ValueError is actually raised or if the example merely prints that traceback text. In practice, ordinary output rarely begins with a traceback header line, so this doesn't create real problems.
- Each line of the traceback stack (if present) must be indented further than the first line of the example, or start with a non-alphanumeric character. The first line following the traceback header indented the same and starting with an alphanumeric is taken to be the start of the exception detail. Of course this does the right thing for genuine tracebacks.
- When the IGNORE_EXCEPTION_DETAIL doctest option is is specified, everything following the leftmost colon is ignored.
- The interactive shell omits the traceback header line for some SyntaxErrors. But doctest uses the traceback header line to distinguish exceptions from non-exceptions. So in the rare case where you need to test a SyntaxError that omits the traceback header, you will need to manually add the traceback header line to your test example.
- For some SyntaxErrors, Python displays the character position of the syntax error, using a ^ marker:

Since the lines showing the position of the error come before the exception type and detail, they are not checked by doctest. For example, the following test would pass, even though it puts the ^ marker in the wrong location:

Changed in version 2.4: The ability to handle a multi-line exception detail, and the IGNORE_EXCEPTION_DETAIL doctest option, were added.

Option Flags and Directives

A number of option flags control various aspects of doctest's behavior. Symbolic names for the flags are supplied as module constants, which can be or'ed together and passed to various functions. The names can also be used in doctest directives (see below).

The first group of options define test semantics, controlling aspects of how doctest decides whether actual output matches an example's expected output:

DONT_ACCEPT_TRUE_FOR_1

By default, if an expected output block contains just 1, an actual output block containing just 1 or just True is considered to be a match, and similarly for 0 versus False. When DONT_ACCEPT_TRUE_FOR_1 is specified, neither substitution is allowed. The default behavior caters to that Python changed the return type of many functions from integer to boolean; doctests expecting "little integer" output still work in these cases. This option will probably go away, but not for several years.

DONT_ACCEPT_BLANKLINE

By default, if an expected output block contains a line containing only the string <BLANKLINE>, then that line will match a blank line in the actual output. Because a genuinely blank line delimits the expected output, this is the only way to communicate that a blank line is expected. When DONT_ACCEPT_BLANKLINE is specified, this substitution is not allowed.

NORMALIZE_WHITESPACE

When specified, all sequences of whitespace (blanks and newlines) are treated as equal. Any sequence of whitespace within the expected output will match any sequence of whitespace within the actual output. By default, whitespace must match exactly. NORMALIZE_WHITESPACE is especially useful when a line of expected output is very long, and you want to wrap it across multiple lines in your source.

ELLIPSIS

When specified, an ellipsis marker (...) in the expected output can match any substring in the actual output. This includes substrings that span line boundaries, and empty substrings, so it's best to keep usage of this simple. Complicated uses can lead to the same kinds of "oops, it matched too much!" surprises that $[\cdot, \star]$ is prone to in regular expressions.

IGNORE_EXCEPTION_DETAIL

When specified, an example that expects an exception passes if an exception of the expected type is raised, even if the exception detail does not match. For example, an example expecting 'ValueError: 42'

will pass if the actual exception raised is 'ValueError: 3*14', but will fail, e.g., if TypeError is raised.

Note that a similar effect can be obtained using ELLIPSIS, and IGNORE_EXCEPTION_DETAIL may go away when Python releases prior to 2.4 become uninteresting. Until then, IGNORE_EXCEPTION_DETAIL is the only clear way to write a doctest that doesn't care about the exception detail yet continues to pass under Python releases prior to 2.4 (doctest directives appear to be comments to them). For example,

```
>>> (1, 2)[3] = 'moo' #doctest: +IGNORE_EXCEPTION_DETAIL
Traceback (most recent call last):
  File "<stdin>", line 1, in ?
TypeError: object doesn't support item assignment
```

passes under Python 2.4 and Python 2.3. The detail changed in 2.4, to say "does not" instead of "doesn't".

COMPARISON_FLAGS

A bitmask or'ing together all the comparison flags above.

The second group of options controls how test failures are reported:

REPORT_UDIFF

When specified, failures that involve multi-line expected and actual outputs are displayed using a unified diff.

REPORT_CDIFF

When specified, failures that involve multi-line expected and actual outputs will be displayed using a context diff

REPORT_NDIFF

When specified, differences are computed by difflib.Differ, using the same algorithm as the popular 'ndiff.py' utility. This is the only method that marks differences within lines as well as across lines. For example, if a line of expected output contains digit 1 where actual output contains letter 1, a line is inserted with a caret marking the mismatching column positions.

REPORT_ONLY_FIRST_FAILURE

When specified, display the first failing example in each doctest, but suppress output for all remaining examples. This will prevent doctest from reporting correct examples that break because of earlier failures; but it might also hide incorrect examples that fail independently of the first failure. When REPORT_ONLY_FIRST_FAILURE is specified, the remaining examples are still run, and still count towards the total number of failures reported; only the output is suppressed.

REPORTING_FLAGS

A bitmask or'ing together all the reporting flags above.

"Doctest directives" may be used to modify the option flags for individual examples. Doctest directives are expressed as a special Python comment following an example's source code:

```
directive
directive_options
directive_options
directive_option ::= directive_option ("," directive_option)*
directive_option ::= on_or_off directive_option_name
on_or_off ::= "+" | "-"
directive_option_name ::= "DONT_ACCEPT_BLANKLINE" | "NORMALIZE_WHITESPACE" | ...
```

Whitespace is not allowed between the + or - and the directive option name. The directive option name can be any of the option flag names explained above.

An example's doctest directives modify doctest's behavior for that single example. Use + to enable the named behavior, or - to disable it.

For example, this test passes:

```
>>> print range(20) #doctest: +NORMALIZE_WHITESPACE
[0, 1, 2, 3, 4, 5, 6, 7, 8, 9,
10, 11, 12, 13, 14, 15, 16, 17, 18, 19]
```

Without the directive it would fail, both because the actual output doesn't have two blanks before the single-digit list elements, and because the actual output is on a single line. This test also passes, and also requires a directive to do so:

```
>>> print range(20) # doctest:+ELLIPSIS
[0, 1, ..., 18, 19]
```

Multiple directives can be used on a single physical line, separated by commas:

```
>>> print range(20) # doctest: +ELLIPSIS, +NORMALIZE_WHITESPACE
[0, 1, ..., 18, 19]
```

If multiple directive comments are used for a single example, then they are combined:

```
>>> print range(20) # doctest: +ELLIPSIS
... # doctest: +NORMALIZE_WHITESPACE
[0, 1, ..., 18, 19]
```

As the previous example shows, you can add '...' lines to your example containing only directives. This can be useful when an example is too long for a directive to comfortably fit on the same line:

```
>>> print range(5) + range(10,20) + range(30,40) + range(50,60)
... # doctest: +ELLIPSIS
[0, ..., 4, 10, ..., 19, 30, ..., 39, 50, ..., 59]
```

Note that since all options are disabled by default, and directives apply only to the example they appear in, enabling options (via + in a directive) is usually the only meaningful choice. However, option flags can also be passed to functions that run doctests, establishing different defaults. In such cases, disabling an option via – in a directive can be useful.

Changed in version 2.4: Constants DONT_ACCEPT_BLANKLINE, NORMALIZE_WHITESPACE, ELLIPSIS, IGNORE_EXCEPTION_DETAIL, REPORT_UDIFF, REPORT_CDIFF, REPORT_NDIFF, REPORT_ONLY_FIRST_FAILURE, COMPARISON_FLAGS and REPORTING_FLAGS were added; by default <BLANKLINE> in expected output matches an empty line in actual output; and doctest directives were added.

There's also a way to register new option flag names, although this isn't useful unless you intend to extend doctest internals via subclassing:

register_optionflag(name)

Create a new option flag with a given name, and return the new flag's integer value. register_optionflag() can be used when subclassing OutputChecker or DocTestRunner to create new options that are supported by your subclasses. register_optionflag should always be called using the following idiom:

```
MY_FLAG = register_optionflag('MY_FLAG')
```

New in version 2.4.

Warnings

doctest is serious about requiring exact matches in expected output. If even a single character doesn't match, the test fails. This will probably surprise you a few times, as you learn exactly what Python does and doesn't guarantee about output. For example, when printing a dict, Python doesn't guarantee that the key-value pairs will be printed in any particular order, so a test like

```
>>> foo()
{"Hermione": "hippogryph", "Harry": "broomstick"}
```

is vulnerable! One workaround is to do

```
>>> foo() == {"Hermione": "hippogryph", "Harry": "broomstick"}
True
```

instead. Another is to do

```
>>> d = foo().items()
>>> d.sort()
>>> d
[('Harry', 'broomstick'), ('Hermione', 'hippogryph')]
```

There are others, but you get the idea.

Another bad idea is to print things that embed an object address, like

```
>>> id(1.0) # certain to fail some of the time
7948648
>>> class C: pass
>>> C() # the default repr() for instances embeds an address
<__main__.C instance at 0x00AC18F0>
```

The ELLIPSIS directive gives a nice approach for the last example:

```
>>> C() #doctest: +ELLIPSIS
<__main__.C instance at 0x...>
```

Floating-point numbers are also subject to small output variations across platforms, because Python defers to the platform C library for float formatting, and C libraries vary widely in quality here.

```
>>> 1./7  # risky
0.14285714285714285
>>> print 1./7  # safer
0.142857142857
>>> print round(1./7, 6)  # much safer
0.142857
```

Numbers of the form I/2.**J are safe across all platforms, and I often contrive doctest examples to produce numbers of that form:

```
>>> 3./4 # utterly safe 0.75
```

Simple fractions are also easier for people to understand, and that makes for better documentation.

5.2.4 Basic API

The functions testmod() and testfile() provide a simple interface to doctest that should be sufficient for most basic uses. For a less formal introduction to these two functions, see sections 5.2.1 and 5.2.2.

```
testfile(filename[, module_relative][, name][, package][, globs][, verbose][, report][, optionflags][, extraglobs][, raise_on_error][, parser])
```

All arguments except *filename* are optional, and should be specified in keyword form.

Test examples in the file named filename. Return '(failure_count, test_count)'.

Optional argument *module_relative* specifies how the filename should be interpreted:

- •If module_relative is True (the default), then filename specifies an OS-independent module-relative path. By default, this path is relative to the calling module's directory; but if the package argument is specified, then it is relative to that package. To ensure OS-independence, filename should use / characters to separate path segments, and may not be an absolute path (i.e., it may not begin with /).
- •If *module_relative* is False, then *filename* specifies an OS-specific path. The path may be absolute or relative; relative paths are resolved with respect to the current working directory.

Optional argument *name* gives the name of the test; by default, or if None, os.path.basename(*filename*) is used.

Optional argument *package* is a Python package or the name of a Python package whose directory should be used as the base directory for a module-relative filename. If no package is specified, then the calling module's directory is used as the base directory for module-relative filenames. It is an error to specify *package* if *module_relative* is False.

Optional argument *globs* gives a dict to be used as the globals when executing examples. A new shallow copy of this dict is created for the doctest, so its examples start with a clean slate. By default, or if None, a new empty dict is used.

Optional argument <code>extraglobs</code> gives a dict merged into the globals used to execute examples. This works like <code>dict.update()</code>: if <code>globs</code> and <code>extraglobs</code> have a common key, the associated value in <code>extraglobs</code> appears in the combined dict. By default, or if <code>None</code>, no extra globals are used. This is an advanced feature that allows parameterization of doctests. For example, a doctest can be written for a base class, using a generic name for the class, then reused to test any number of subclasses by passing an <code>extraglobs</code> dict mapping the generic name to the subclass to be tested.

Optional argument *verbose* prints lots of stuff if true, and prints only failures if false; by default, or if None, it's true if and only if '-v' is in sys.argv.

Optional argument *report* prints a summary at the end when true, else prints nothing at the end. In verbose mode, the summary is detailed, else the summary is very brief (in fact, empty if all tests passed).

Optional argument optionflags or's together option flags. See section 5.2.3.

Optional argument *raise_on_error* defaults to false. If true, an exception is raised upon the first failure or unexpected exception in an example. This allows failures to be post-mortem debugged. Default behavior is to continue running examples.

Optional argument *parser* specifies a DocTestParser (or subclass) that should be used to extract tests from the files. It defaults to a normal parser (i.e., DocTestParser ()).

New in version 2.4.

```
testmod([m][, name][, globs][, verbose][, isprivate][, report][, optionflags][, extraglobs][, raise_on_error][, exclude_empty])
All arguments are optional, and all except for m should be specified in keyword form.
```

Test examples in docstrings in functions and classes reachable from module m (or module $__main__$ if m is not supplied or is None), starting with $m.__doc__$.

Also test examples reachable from dict m. __test__, if it exists and is not None. m. __test__ maps names (strings) to functions, classes and strings; function and class docstrings are searched for examples; strings are searched directly, as if they were docstrings.

Only docstrings attached to objects belonging to module *m* are searched.

Return '(failure_count, test_count)'.

Optional argument *name* gives the name of the module; by default, or if None, m. __name__ is used.

Optional argument <code>exclude_empty</code> defaults to false. If true, objects for which no doctests are found are excluded from consideration. The default is a backward compatibility hack, so that code still using <code>doctest.master.summarize()</code> in conjunction with <code>testmod()</code> continues to get output for objects with no tests. The <code>exclude_empty</code> argument to the newer <code>DocTestFinder</code> constructor defaults to true.

Optional arguments extraglobs, verbose, report, optionflags, $raise_on_error$, and globs are the same as for function testfile() above, except that globs defaults to m. $__dict__$.

Optional argument *isprivate* specifies a function used to determine whether a name is private. The default function treats all names as public. *isprivate* can be set to doctest.is_private to skip over names that are private according to Python's underscore naming convention. **Deprecated since release 2.4.** *isprivate* was a stupid idea – don't use it. If you need to skip tests based on name, filter the list returned by DocTestFinder.find() instead.

Changed in version 2.3: The parameter optionflags was added.

Changed in version 2.4: The parameters extraglobs, raise_on_error and exclude_empty were added.

There's also a function to run the doctests associated with a single object. This function is provided for backward compatibility. There are no plans to deprecate it, but it's rarely useful:

```
run_docstring_examples(f, globs[, verbose][, name][, compileflags][, optionflags])
```

Test examples associated with object f; for example, f may be a module, function, or class object.

A shallow copy of dictionary argument *globs* is used for the execution context.

Optional argument name is used in failure messages, and defaults to "NoName".

If optional argument *verbose* is true, output is generated even if there are no failures. By default, output is generated only in case of an example failure.

Optional argument *compileflags* gives the set of flags that should be used by the Python compiler when running the examples. By default, or if None, flags are deduced corresponding to the set of future features found in *globs*.

Optional argument *optionflags* works as for function testfile() above.

5.2.5 Unittest API

As your collection of doctest'ed modules grows, you'll want a way to run all their doctests systematically. Prior to Python 2.4, doctest had a barely documented Tester class that supplied a rudimentary way to combine doctests from multiple modules. Tester was feeble, and in practice most serious Python testing frameworks build on the unittest module, which supplies many flexible ways to combine tests from multiple sources. So, in Python 2.4, doctest's Tester class is deprecated, and doctest provides two functions that can be used to create unittest test suites from modules and text files containing doctests. These test suites can then be run using unittest test runners:

```
import unittest
import doctest
import my_module_with_doctests, and_another

suite = unittest.TestSuite()
for mod in my_module_with_doctests, and_another:
    suite.addTest(doctest.DocTestSuite(mod))
runner = unittest.TextTestRunner()
runner.run(suite)
```

There are two main functions for creating unittest. TestSuite instances from text files and modules with doctests:

```
DocFileSuite(*paths, **kw)
```

Convert doctest tests from one or more text files to a unittest. TestSuite.

The returned unittest.TestSuite is to be run by the unittest framework and runs the interactive examples in each file. If an example in any file fails, then the synthesized unit test fails, and a failureException exception is raised showing the name of the file containing the test and a (sometimes approximate) line number.

Pass one or more paths (as strings) to text files to be examined.

Options may be provided as keyword arguments:

Optional argument *module_relative* specifies how the filenames in *paths* should be interpreted:

- •If module_relative is True (the default), then each filename specifies an OS-independent module-relative path. By default, this path is relative to the calling module's directory; but if the package argument is specified, then it is relative to that package. To ensure OS-independence, each filename should use / characters to separate path segments, and may not be an absolute path (i.e., it may not begin with /).
- •If *module_relative* is False, then each filename specifies an OS-specific path. The path may be absolute or relative; relative paths are resolved with respect to the current working directory.

Optional argument *package* is a Python package or the name of a Python package whose directory should be used as the base directory for module-relative filenames. If no package is specified, then the calling module's directory is used as the base directory for module-relative filenames. It is an error to specify *package* if *module_relative* is False.

Optional argument setUp specifies a set-up function for the test suite. This is called before running the tests in each file. The setUp function will be passed a DocTest object. The setUp function can access the test globals as the globs attribute of the test passed.

Optional argument *tearDown* specifies a tear-down function for the test suite. This is called after running the tests in each file. The *tearDown* function will be passed a DocTest object. The setUp function can access the test globals as the *globs* attribute of the test passed.

Optional argument *globs* is a dictionary containing the initial global variables for the tests. A new copy of this dictionary is created for each test. By default, *globs* is a new empty dictionary.

Optional argument *optionflags* specifies the default doctest options for the tests, created by or-ing together individual option flags. See section 5.2.3. See function set_unittest_reportflags() below for a better way to set reporting options.

Optional argument *parser* specifies a DocTestParser (or subclass) that should be used to extract tests from the files. It defaults to a normal parser (i.e., DocTestParser ()).

New in version 2.4

```
DocTestSuite([module][, globs][, extraglobs][, test_finder][, setUp][, tearDown][, checker])
Convert doctest tests for a module to a unittest. TestSuite.
```

The returned unittest. TestSuite is to be run by the unittest framework and runs each doctest in the module. If any of the doctests fail, then the synthesized unit test fails, and a failureException

exception is raised showing the name of the file containing the test and a (sometimes approximate) line number.

Optional argument *module* provides the module to be tested. It can be a module object or a (possibly dotted) module name. If not specified, the module calling this function is used.

Optional argument *globs* is a dictionary containing the initial global variables for the tests. A new copy of this dictionary is created for each test. By default, *globs* is a new empty dictionary.

Optional argument *extraglobs* specifies an extra set of global variables, which is merged into *globs*. By default, no extra globals are used.

Optional argument *test_finder* is the DocTestFinder object (or a drop-in replacement) that is used to extract doctests from the module.

Optional arguments setUp, tearDown, and optionflags are the same as for function DocFileSuite() above.

New in version 2.3.

Changed in version 2.4: The parameters *globs*, *extraglobs*, *test_finder*, *setUp*, *tearDown*, and *optionflags* were added; this function now uses the same search technique as testmod().

Under the covers, DocTestSuite() creates a unittest.TestSuite out of doctest.DocTestCase instances, and DocTestCase is a subclass of unittest.TestCase. DocTestCase isn't documented here (it's an internal detail), but studying its code can answer questions about the exact details of unittest integration.

Similarly, DocFileSuite() creates a unittest. TestSuite out of doctest. DocFileCase instances, and DocFileCase is a subclass of DocTestCase.

So both ways of creating a unittest. TestSuite run instances of DocTestCase. This is important for a subtle reason: when you run doctest functions yourself, you can control the doctest options in use directly, by passing option flags to doctest functions. However, if you're writing a unittest framework, unittest ultimately controls when and how tests get run. The framework author typically wants to control doctest reporting options (perhaps, e.g., specified by command line options), but there's no way to pass options through unittest to doctest test runners.

For this reason, doctest also supports a notion of doctest reporting flags specific to unittest support, via this function:

set_unittest_reportflags(flags)

Set the doctest reporting flags to use.

Argument *flags* or's together option flags. See section 5.2.3. Only "reporting flags" can be used.

This is a module-global setting, and affects all future doctests run by module unittest: the runTest() method of DocTestCase looks at the option flags specified for the test case when the DocTestCase instance was constructed. If no reporting flags were specified (which is the typical and expected case), doctest's unittest reporting flags are or'ed into the option flags, and the option flags so augmented are passed to the DocTestRunner instance created to run the doctest. If any reporting flags were specified when the DocTestCase instance was constructed, doctest's unittest reporting flags are ignored.

The value of the unittest reporting flags in effect before the function was called is returned by the function.

New in version 2.4.

5.2.6 Advanced API

The basic API is a simple wrapper that's intended to make doctest easy to use. It is fairly flexible, and should meet most users' needs; however, if you require more fine-grained control over testing, or wish to extend doctest's capabilities, then you should use the advanced API.

The advanced API revolves around two container classes, which are used to store the interactive examples extracted from doctest cases:

• Example: A single python statement, paired with its expected output.

• DocTest: A collection of Examples, typically extracted from a single docstring or text file.

Additional processing classes are defined to find, parse, and run, and check doctest examples:

- DocTestFinder: Finds all docstrings in a given module, and uses a DocTestParser to create a DocTest from every docstring that contains interactive examples.
- DocTestParser: Creates a DocTest object from a string (such as an object's docstring).
- DocTestRunner: Executes the examples in a DocTest, and uses an OutputChecker to verify their output.
- OutputChecker: Compares the actual output from a doctest example with the expected output, and decides whether they match.

The relationships among these processing classes are summarized in the following diagram:



DocTest Objects

class DocTest (examples, globs, name, filename, lineno, docstring)

A collection of doctest examples that should be run in a single namespace. The constructor arguments are used to initialize the member variables of the same names. New in version 2.4.

DocTest defines the following member variables. They are initialized by the constructor, and should not be modified directly.

examples

A list of Example objects encoding the individual interactive Python examples that should be run by this test.

globs

The namespace (aka globals) that the examples should be run in. This is a dictionary mapping names to values. Any changes to the namespace made by the examples (such as binding new variables) will be reflected in globs after the test is run.

name

A string name identifying the DocTest. Typically, this is the name of the object or file that the test was extracted from.

filename

The name of the file that this DocTest was extracted from; or None if the filename is unknown, or if the DocTest was not extracted from a file.

lineno

The line number within filename where this DocTest begins, or None if the line number is unavailable. This line number is zero-based with respect to the beginning of the file.

docstring

The string that the test was extracted from, or 'None' if the string is unavailable, or if the test was not extracted from a string.

Example Objects

class Example (source, want[, exc_msg][, lineno][, indent][, options])

A single interactive example, consisting of a Python statement and its expected output. The constructor arguments are used to initialize the member variables of the same names. New in version 2.4.

Example defines the following member variables. They are initialized by the constructor, and should not be modified directly.

source

A string containing the example's source code. This source code consists of a single Python statement, and always ends with a newline; the constructor adds a newline when necessary.

want

The expected output from running the example's source code (either from stdout, or a traceback in case of exception). want ends with a newline unless no output is expected, in which case it's an empty string. The constructor adds a newline when necessary.

exc_msg

The exception message generated by the example, if the example is expected to generate an exception; or None if it is not expected to generate an exception. This exception message is compared against the return value of traceback.format_exception_only(). exc_msg ends with a newline unless it's None. The constructor adds a newline if needed.

lineno

The line number within the string containing this example where the example begins. This line number is zero-based with respect to the beginning of the containing string.

indent

The example's indentation in the containing string, i.e., the number of space characters that precede the example's first prompt.

options

A dictionary mapping from option flags to True or False, which is used to override default options for this example. Any option flags not contained in this dictionary are left at their default value (as specified by the DocTestRunner's optionflags). By default, no options are set.

DocTestFinder objects

class DocTestFinder([verbose][, parser][, recurse][, exclude_empty])

A processing class used to extract the DocTests that are relevant to a given object, from its docstring and the docstrings of its contained objects. DocTests can currently be extracted from the following object types: modules, functions, classes, methods, staticmethods, classmethods, and properties.

The optional argument *verbose* can be used to display the objects searched by the finder. It defaults to False (no output).

The optional argument *parser* specifies the DocTestParser object (or a drop-in replacement) that is used to extract doctests from docstrings.

If the optional argument *recurse* is false, then DocTestFinder.find() will only examine the given object, and not any contained objects.

If the optional argument *exclude_empty* is false, then DocTestFinder.find() will include tests for objects with empty docstrings.

New in version 2.4.

DocTestFinder defines the following method:

find(obj[, name][, module][, globs][, extraglobs])

Return a list of the DocTests that are defined by *obj*'s docstring, or by any of its contained objects' docstrings.

The optional argument *name* specifies the object's name; this name will be used to construct names for the returned DocTests. If *name* is not specified, then *obj*.__name__ is used.

The optional parameter *module* is the module that contains the given object. If the module is not specified or is None, then the test finder will attempt to automatically determine the correct module. The object's module is used:

- •As a default namespace, if *globs* is not specified.
- •To prevent the DocTestFinder from extracting DocTests from objects that are imported from other modules. (Contained objects with modules other than *module* are ignored.)
- •To find the name of the file containing the object.
- •To help find the line number of the object within its file.

If *module* is False, no attempt to find the module will be made. This is obscure, of use mostly in testing doctest itself: if *module* is False, or is None but cannot be found automatically, then all objects are considered to belong to the (non-existent) module, so all contained objects will (recursively) be searched for doctests.

The globals for each DocTest is formed by combining *globs* and *extraglobs* (bindings in *extraglobs* override bindings in *globs*). A new shallow copy of the globals dictionary is created for each DocTest. If *globs* is not specified, then it defaults to the module's __dict__, if specified, or {} otherwise. If *extraglobs* is not specified, then it defaults to {}.

DocTestParser objects

class DocTestParser()

A processing class used to extract interactive examples from a string, and use them to create a DocTest object. New in version 2.4.

DocTestParser defines the following methods:

get_doctest(string, globs, name, filename, lineno)

Extract all doctest examples from the given string, and collect them into a DocTest object.

globs, name, filename, and lineno are attributes for the new DocTest object. See the documentation for DocTest for more information.

get_examples(string[, name])

Extract all doctest examples from the given string, and return them as a list of Example objects. Line numbers are 0-based. The optional argument *name* is a name identifying this string, and is only used for error messages.

parse(string[, name])

Divide the given string into examples and intervening text, and return them as a list of alternating Examples and strings. Line numbers for the Examples are 0-based. The optional argument *name* is a name identifying this string, and is only used for error messages.

DocTestRunner objects

class DocTestRunner([checker][, verbose][, optionflags])

A processing class used to execute and verify the interactive examples in a DocTest.

The comparison between expected outputs and actual outputs is done by an OutputChecker. This comparison may be customized with a number of option flags; see section 5.2.3 for more information. If the option flags are insufficient, then the comparison may also be customized by passing a subclass of OutputChecker to the constructor.

The test runner's display output can be controlled in two ways. First, an output function can be passed to TestRunner.run(); this function will be called with strings that should be displayed. It defaults to sys.stdout.write. If capturing the output is not sufficient, then the display output can be also customized by subclassing DocTestRunner, and overriding the methods report_start, report_success, report_unexpected_exception, and report_failure.

The optional keyword argument *checker* specifies the OutputChecker object (or drop-in replacement) that should be used to compare the expected outputs to the actual outputs of doctest examples.

The optional keyword argument *verbose* controls the DocTestRunner's verbosity. If *verbose* is True, then information is printed about each example, as it is run. If *verbose* is False, then only failures are printed. If *verbose* is unspecified, or None, then verbose output is used iff the command-line switch **-v** is used.

The optional keyword argument *optionflags* can be used to control how the test runner compares expected output to actual output, and how it displays failures. For more information, see section 5.2.3.

New in version 2.4.

DocTestParser defines the following methods:

report_start(out, test, example)

Report that the test runner is about to process the given example. This method is provided to allow subclasses of DocTestRunner to customize their output; it should not be called directly.

example is the example about to be processed. *test* is the test containing *example*. *out* is the output function that was passed to DocTestRunner.run().

report_success(out, test, example, got)

Report that the given example ran successfully. This method is provided to allow subclasses of DocTestRunner to customize their output; it should not be called directly.

example is the example about to be processed. *got* is the actual output from the example. *test* is the test containing *example*. *out* is the output function that was passed to DocTestRunner.run().

report_failure(out, test, example, got)

Report that the given example failed. This method is provided to allow subclasses of DocTestRunner to customize their output; it should not be called directly.

example is the example about to be processed. got is the actual output from the example. test is the test containing example. out is the output function that was passed to DocTestRunner.run().

report_unexpected_exception(out, test, example, exc_info)

Report that the given example raised an unexpected exception. This method is provided to allow subclasses of DocTestRunner to customize their output; it should not be called directly.

example is the example about to be processed. exc_info is a tuple containing information about the unexpected exception (as returned by sys.exc_info()). test is the test containing example. out is the output function that was passed to DocTestRunner.run().

run(test[, compileflags][, out][, clear_globs])

Run the examples in test (a DocTest object), and display the results using the writer function out.

The examples are run in the namespace test.globs. If *clear_globs* is true (the default), then this namespace will be cleared after the test runs, to help with garbage collection. If you would like to examine the namespace after the test completes, then use *clear_globs=False*.

compileflags gives the set of flags that should be used by the Python compiler when running the examples. If not specified, then it will default to the set of future-import flags that apply to *globs*.

The output of each example is checked using the DocTestRunner's output checker, and the results are formatted by the DocTestRunner.report_* methods.

summarize([verbose])

Print a summary of all the test cases that have been run by this DocTestRunner, and return a tuple '(failure_count, test_count)'.

The optional *verbose* argument controls how detailed the summary is. If the verbosity is not specified, then the DocTestRunner's verbosity is used.

OutputChecker objects

class OutputChecker()

A class used to check the whether the actual output from a doctest example matches the expected output. OutputChecker defines two methods: check_output, which compares a given pair of outputs, and returns true if they match; and output_difference, which returns a string describing the differences between two outputs. New in version 2.4.

OutputChecker defines the following methods:

check_output(want, got, optionflags)

Return True iff the actual output from an example (*got*) matches the expected output (*want*). These strings are always considered to match if they are identical; but depending on what option flags the test runner is using, several non-exact match types are also possible. See section 5.2.3 for more information about option flags.

output_difference(example, got, optionflags)

Return a string describing the differences between the expected output for a given example (*example*) and the actual output (*got*). *optionflags* is the set of option flags used to compare *want* and *got*.

5.2.7 Debugging

Doctest provides several mechanisms for debugging doctest examples:

- Several functions convert doctests to executable Python programs, which can be run under the Python debugger, pdb.
- The DebugRunner class is a subclass of DocTestRunner that raises an exception for the first failing example, containing information about that example. This information can be used to perform post-mortem debugging on the example.
- The unittest cases generated by DocTestSuite() support the debug() method defined by unittest. TestCase.
- You can add a call to pdb.set_trace() in a doctest example, and you'll drop into the Python debugger when that line is executed. Then you can inspect current values of variables, and so on. For example, suppose 'a.py' contains just this module docstring:

```
"""
>>> def f(x):
...     g(x*2)
>>> def g(x):
...     print x+3
...     import pdb; pdb.set_trace()
>>> f(3)
9
"""
```

Then an interactive Python session may look like this:

```
>>> import a, doctest
>>> doctest.testmod(a)
> <doctest a[1]>(3)g()->None
-> import pdb; pdb.set_trace()
(Pdb) list
 1
      def g(x):
         print x+3
 2
 3 ->
           import pdb; pdb.set_trace()
[EOF]
(Pdb) print x
(Pdb) step
--Return--
> <doctest a[0]>(2)f()->None
-> g(x*2)
(Pdb) list
 1 def f(x):
 2 ->
        g(x*2)
[EOF]
(Pdb) print x
3
(Pdb) step
--Return--
> <doctest a[2]>(1)?()->None
-> f(3)
(Pdb) cont
(0, 3)
>>>
```

Changed in version 2.4: The ability to use pdb.set_trace() usefully inside doctests was added.

Functions that convert doctests to Python code, and possibly run the synthesized code under the debugger:

script_from_examples(s)

Convert text with examples to a script.

Argument s is a string containing doctest examples. The string is converted to a Python script, where doctest examples in s are converted to regular code, and everything else is converted to Python comments. The generated script is returned as a string. For example,

```
import doctest
print doctest.script_from_examples(r"""
    Set x and y to 1 and 2.
    >>> x, y = 1, 2

    Print their sum:
    >>> print x+y
    3
"""")
```

displays:

```
# Set x and y to 1 and 2.
x, y = 1, 2
#
# Print their sum:
print x+y
# Expected:
## 3
```

This function is used internally by other functions (see below), but can also be useful when you want to transform an interactive Python session into a Python script.

New in version 2.4.

testsource(module, name)

Convert the doctest for an object to a script.

Argument *module* is a module object, or dotted name of a module, containing the object whose doctests are of interest. Argument *name* is the name (within the module) of the object with the doctests of interest. The result is a string, containing the object's docstring converted to a Python script, as described for script_from_examples() above. For example, if module 'a.py' contains a top-level function f(), then

```
import a, doctest
print doctest.testsource(a, "a.f")
```

prints a script version of function £ ()'s docstring, with doctests converted to code, and the rest placed in comments.

New in version 2.3.

debug(module, name[, pm])

Debug the doctests for an object.

The *module* and *name* arguments are the same as for function testsource() above. The synthesized Python script for the named object's docstring is written to a temporary file, and then that file is run under the control of the Python debugger, pdb.

A shallow copy of *module* . __dict__ is used for both local and global execution context.

Optional argument *pm* controls whether post-mortem debugging is used. If *pm* has a true value, the script file is run directly, and the debugger gets involved only if the script terminates via raising an unhandled exception. If it does, then post-mortem debugging is invoked, via pdb.post_mortem(), passing the traceback object from the unhandled exception. If *pm* is not specified, or is false, the script is run under the debugger from the start, via passing an appropriate execfile() call to pdb.run().

New in version 2.3.

Changed in version 2.4: The pm argument was added.

```
debug\_src(src[,pm][,globs])
```

Debug the doctests in a string.

This is like function debug () above, except that a string containing doctest examples is specified directly, via the *src* argument.

Optional argument pm has the same meaning as in function debug () above.

Optional argument *globs* gives a dictionary to use as both local and global execution context. If not specified, or None, an empty dictionary is used. If specified, a shallow copy of the dictionary is used.

New in version 2.4.

The DebugRunner class, and the special exceptions it may raise, are of most interest to testing framework authors, and will only be sketched here. See the source code, and especially DebugRunner's docstring (which is a doctest!) for more details:

```
class DebugRunner([checker][, verbose][, optionflags])
```

A subclass of DocTestRunner that raises an exception as soon as a failure is encountered. If an unexpected exception occurs, an UnexpectedException exception is raised, containing the test, the exam-

ple, and the original exception. If the output doesn't match, then a DocTestFailure exception is raised, containing the test, the example, and the actual output.

For information about the constructor parameters and methods, see the documentation for DocTestRunner in section 5.2.6.

There are two exceptions that may be raised by DebugRunner instances:

exception DocTestFailure(test, example, got)

An exception thrown by DocTestRunner to signal that a doctest example's actual output did not match its expected output. The constructor arguments are used to initialize the member variables of the same names.

DocTestFailure defines the following member variables:

test

The DocTest object that was being run when the example failed.

example

The Example that failed.

got

The example's actual output.

exception UnexpectedException(test, example, exc_info)

An exception thrown by DocTestRunner to signal that a doctest example raised an unexpected exception. The constructor arguments are used to initialize the member variables of the same names.

UnexpectedException defines the following member variables:

test

The DocTest object that was being run when the example failed.

example

The Example that failed.

exc_info

A tuple containing information about the unexpected exception, as returned by sys.exc_info().

5.2.8 Soapbox

As mentioned in the introduction, doctest has grown to have three primary uses:

- 1. Checking examples in docstrings.
- 2. Regression testing.
- 3. Executable documentation / literate testing.

These uses have different requirements, and it is important to distinguish them. In particular, filling your docstrings with obscure test cases makes for bad documentation.

When writing a docstring, choose docstring examples with care. There's an art to this that needs to be learned—it may not be natural at first. Examples should add genuine value to the documentation. A good example can often be worth many words. If done with care, the examples will be invaluable for your users, and will pay back the time it takes to collect them many times over as the years go by and things change. I'm still amazed at how often one of my doctest examples stops working after a "harmless" change.

Doctest also makes an excellent tool for regression testing, especially if you don't skimp on explanatory text. By interleaving prose and examples, it becomes much easier to keep track of what's actually being tested, and why. When a test fails, good prose can make it much easier to figure out what the problem is, and how it should be fixed. It's true that you could write extensive comments in code-based testing, but few programmers do. Many have found that using doctest approaches instead leads to much clearer tests. Perhaps this is simply because doctest makes writing prose a little easier than writing code, while writing comments in code is a little harder. I think it goes deeper than just that: the natural attitude when writing a doctest-based test is that you want to explain the fine points of your software, and illustrate them with examples. This in turn naturally leads to test files that

start with the simplest features, and logically progress to complications and edge cases. A coherent narrative is the result, instead of a collection of isolated functions that test isolated bits of functionality seemingly at random. It's a different attitude, and produces different results, blurring the distinction between testing and explaining.

Regression testing is best confined to dedicated objects or files. There are several options for organizing tests:

- Write text files containing test cases as interactive examples, and test the files using testfile() or DocFileSuite(). This is recommended, although is easiest to do for new projects, designed from the start to use doctest.
- Define functions named <u>_regrtest_topic</u> that consist of single docstrings, containing test cases for the named topics. These functions can be included in the same file as the module, or separated out into a separate test file.
- Define a __test__ dictionary mapping from regression test topics to docstrings containing test cases.

5.3 unittest — Unit testing framework

New in version 2.1.

The Python unit testing framework, often referred to as "PyUnit," is a Python language version of JUnit, by Kent Beck and Erich Gamma. JUnit is, in turn, a Java version of Kent's Smalltalk testing framework. Each is the de facto standard unit testing framework for its respective language.

PyUnit supports test automation, sharing of setup and shutdown code for tests, aggregation of tests into collections, and independence of the tests from the reporting framework. The unittest module provides classes that make it easy to support these qualities for a set of tests.

To achieve this, PyUnit supports some important concepts:

test fixture

A *test fixture* represents the preparation needed to perform one or more tests, and any associate cleanup actions. This may involve, for example, creating temporary or proxy databases, directories, or starting a server process.

test case

A *test case* is the smallest unit of testing. It checks for a specific response to a particular set of inputs. PyUnit provides a base class, TestCase, which may be used to create new test cases. You may provide your own implementation that does not subclass from TestCase, of course.

test suite

A *test suite* is a collection of test cases, test suites, or both. It is used to aggregate tests that should be executed together.

test runner

A *test runner* is a component which orchestrates the execution of tests and provides the outcome to the user. The runner may use a graphical interface, a textual interface, or return a special value to indicate the results of executing the tests.

The test case and test fixture concepts are supported through the TestCase and FunctionTestCase classes; the former should be used when creating new tests, and the latter can be used when integrating existing test code with a PyUnit-driven framework. When building test fixtures using TestCase, the setUp() and tearDown() methods can be overridden to provide initialization and cleanup for the fixture. With FunctionTestCase, existing functions can be passed to the constructor for these purposes. When the test is run, the fixture initialization is run first; if it succeeds, the cleanup method is run after the test has been executed, regardless of the outcome of the test. Each instance of the TestCase will only be used to run a single test method, so a new fixture is created for each test.

Test suites are implemented by the TestSuite class. This class allows individual tests and test suites to be aggregated; when the suite is executed, all tests added directly to the suite and in "child" test suites are run.

A test runner is an object that provides a single method, run(), which accepts a TestCase or TestSuite object as a parameter, and returns a result object. The class TestResult is provided for use as the result object. PyUnit provide the TextTestRunner as an example test runner which reports test results on the standard error stream by default. Alternate runners can be implemented for other environments (such as graphical environments) without any need to derive from a specific class.

See Also:

```
Module doctest (section 5.2):
```

Another test-support module with a very different flavor.

PyUnit Web Site

(http://pyunit.sourceforge.net/)

The source for further information on PyUnit.

Simple Smalltalk Testing: With Patterns (http://www.XProgramming.com/testfram.htm)

Kent Beck's original paper on testing frameworks using the pattern shared by unittest.

5.3.1 Basic example

The unittest module provides a rich set of tools for constructing and running tests. This section demonstrates that a small subset of the tools suffice to meet the needs of most users.

Here is a short script to test three functions from the random module:

```
import random
import unittest
class TestSequenceFunctions(unittest.TestCase):
   def setUp(self):
        self.seq = range(10)
   def testshuffle(self):
        # make sure the shuffled sequence does not lose any elements
        random.shuffle(self.seq)
        self.seq.sort()
        self.assertEqual(self.seq, range(10))
   def testchoice(self):
        element = random.choice(self.seq)
        self.assert_(element in self.seq)
   def testsample(self):
        self.assertRaises(ValueError, random.sample, self.seq, 20)
        for element in random.sample(self.seq, 5):
            self.assert_(element in self.seq)
if __name__ == '__main__':
    unittest.main()
```

A testcase is created by subclassing unittest. TestCase. The three individual tests are defined with methods whose names start with the letters 'test'. This naming convention informs the test runner about which methods represent tests.

The crux of each test is a call to assertEqual() to check for an expected result; assert_() to verify a condition; or assertRaises() to verify that an expected exception gets raised. These methods are used instead of the assert statement so the test runner can accumulate all test results and produce a report.

When a setUp() method is defined, the test runner will run that method prior to each test. Likewise, if a tearDown() method is defined, the test runner will invoke that method after each test. In the example,

setUp() was used to create a fresh sequence for each test.

The final block shows a simple way to run the tests. unittest.main() provides a command line interface to the test script. When run from the command line, the above script produces an output that looks like this:

```
Ran 3 tests in 0.000s
```

Instead of unittest.main(), there are other ways to run the tests with a finer level of control, less terse output, and no requirement to be run from the command line. For example, the last two lines may be replaced with:

```
suite = unittest.makeSuite(TestSequenceFunctions)
unittest.TextTestRunner(verbosity=2).run(suite)
```

Running the revised script from the interpreter or another script produces the following output:

The above examples show the most commonly used unittest features which are sufficient to meet many everyday testing needs. The remainder of the documentation explores the full feature set from first principles.

5.3.2 Organizing test code

The basic building blocks of unit testing are *test cases* — single scenarios that must be set up and checked for correctness. In PyUnit, test cases are represented by instances of the TestCase class in the unittest module. To make your own test cases you must write subclasses of TestCase, or use FunctionTestCase.

An instance of a TestCase-derived class is an object that can completely run a single test method, together with optional set-up and tidy-up code.

The testing code of a TestCase instance should be entirely self contained, such that it can be run either in isolation or in arbitrary combination with any number of other test cases.

The simplest test case subclass will simply override the runTest() method in order to perform specific testing code:

```
import unittest

class DefaultWidgetSizeTestCase(unittest.TestCase):
    def runTest(self):
        widget = Widget("The widget")
        self.failUnless(widget.size() == (50,50), 'incorrect default size')
```

Note that in order to test something, we use the one of the assert*() or fail*() methods provided by the TestCase base class. If the test fails when the test case runs, an exception will be raised, and the testing framework will identify the test case as a *failure*. Other exceptions that do not arise from checks made through the assert*() and fail*() methods are identified by the testing framework as dfnerrors.

The way to run a test case will be described later. For now, note that to construct an instance of such a test case, we call its constructor without arguments:

```
testCase = DefaultWidgetSizeTestCase()
```

Now, such test cases can be numerous, and their set-up can be repetitive. In the above case, constructing a "Widget" in each of 100 Widget test case subclasses would mean unsightly duplication.

Luckily, we can factor out such set-up code by implementing a method called setUp(), which the testing framework will automatically call for us when we run the test:

If the setUp() method raises an exception while the test is running, the framework will consider the test to have suffered an error, and the runTest() method will not be executed.

Similarly, we can provide a tearDown() method that tidies up after the runTest() method has been run:

```
import unittest

class SimpleWidgetTestCase(unittest.TestCase):
    def setUp(self):
        self.widget = Widget("The widget")

    def tearDown(self):
        self.widget.dispose()
        self.widget = None
```

If setUp() succeeded, the tearDown() method will be run regardless of whether or not runTest() succeeded.

Such a working environment for the testing code is called a *fixture*.

Often, many small test cases will use the same fixture. In this case, we would end up subclassing SimpleWidgetTestCase into many small one-method classes such as DefaultWidgetSizeTestCase. This is time-consuming and discouraging, so in the same vein as JUnit, PyUnit provides a simpler mechanism:

Here we have not provided a runTest() method, but have instead provided two different test methods. Class instances will now each run one of the test*() methods, with self.widget created and destroyed separately for each instance. When creating an instance we must specify the test method it is to run. We do this by passing the method name in the constructor:

```
defaultSizeTestCase = WidgetTestCase("testDefaultSize")
resizeTestCase = WidgetTestCase("testResize")
```

Test case instances are grouped together according to the features they test. PyUnit provides a mechanism for this: the test suite, represented by the class TestSuite in the unittest module:

```
widgetTestSuite = unittest.TestSuite()
widgetTestSuite.addTest(WidgetTestCase("testDefaultSize"))
widgetTestSuite.addTest(WidgetTestCase("testResize"))
```

For the ease of running tests, as we will see later, it is a good idea to provide in each test module a callable object that returns a pre-built test suite:

(The latter is admittedly not for the faint-hearted!)

Since it is a common pattern to create a TestCase subclass with many similarly named test functions, there is a convenience function called makeSuite() that constructs a test suite that comprises all of the test cases in a

test case class:

```
suite = unittest.makeSuite(WidgetTestCase)
```

Note that when using the makeSuite() function, the order in which the various test cases will be run by the test suite is the order determined by sorting the test function names using the cmp() built-in function.

Often it is desirable to group suites of test cases together, so as to run tests for the whole system at once. This is easy, since TestSuite instances can be added to a TestSuite just as TestCase instances can be added to a TestSuite:

```
suite1 = module1.TheTestSuite()
suite2 = module2.TheTestSuite()
alltests = unittest.TestSuite((suite1, suite2))
```

You can place the definitions of test cases and test suites in the same modules as the code they are to test (such as 'widget.py'), but there are several advantages to placing the test code in a separate module, such as 'widgettests.py':

- The test module can be run standalone from the command line.
- The test code can more easily be separated from shipped code.
- There is less temptation to change test code to fit the code it tests without a good reason.
- Test code should be modified much less frequently than the code it tests.
- Tested code can be refactored more easily.
- Tests for modules written in C must be in separate modules anyway, so why not be consistent?
- If the testing strategy changes, there is no need to change the source code.

5.3.3 Re-using old test code

Some users will find that they have existing test code that they would like to run from PyUnit, without converting every old test function to a TestCase subclass.

For this reason, PyUnit provides a FunctionTestCase class. This subclass of TestCase can be used to wrap an existing test function. Set-up and tear-down functions can also optionally be wrapped.

Given the following test function:

```
def testSomething():
    something = makeSomething()
    assert something.name is not None
# ...
```

one can create an equivalent test case instance as follows:

```
testcase = unittest.FunctionTestCase(testSomething)
```

If there are additional set-up and tear-down methods that should be called as part of the test case's operation, they can also be provided:

Note: PyUnit supports the use of AssertionError as an indicator of test failure, but does not recommend it. Future versions may treat AssertionError differently.

5.3.4 Classes and functions

class TestCase()

Instances of the TestCase class represent the smallest testable units in a set of tests. This class is intended to be used as a base class, with specific tests being implemented by concrete subclasses. This class implements the interface needed by the test runner to allow it to drive the test, and methods that the test code can use to check for and report various kinds of failures.

class FunctionTestCase(testFunc[, setUp[, tearDown[, description]]])

This class implements the portion of the TestCase interface which allows the test runner to drive the test, but does not provide the methods which test code can use to check and report errors. This is used to create test cases using legacy test code, allowing it to be integrated into a unittest-based test framework.

```
class TestSuite([tests])
```

This class represents an aggregation of individual tests cases and test suites. The class presents the interface needed by the test runner to allow it to be run as any other test case, but all the contained tests and test suites are executed. Additional methods are provided to add test cases and suites to the aggregation. If *tests* is given, it must be a sequence of individual tests that will be added to the suite.

class TestLoader()

This class is responsible for loading tests according to various criteria and returning them wrapped in a TestSuite. It can load all tests within a given module or TestCase class. When loading from a module, it considers all TestCase-derived classes. For each such class, it creates an instance for each method with a name beginning with the string 'test'.

defaultTestLoader

Instance of the TestLoader class which can be shared. If no customization of the TestLoader is needed, this instance can always be used instead of creating new instances.

```
class TextTestRunner([stream[, descriptions[, verbosity]]])
```

A basic test runner implementation which prints results on standard output. It has a few configurable parameters, but is essentially very simple. Graphical applications which run test suites should provide alternate implementations.

```
main([module[, defaultTest[, argv[, testRunner[, testRunner]]]]]))
```

A command-line program that runs a set of tests; this is primarily for making test modules conveniently executable. The simplest use for this function is:

```
if __name__ == '__main__':
    unittest.main()
```

In some cases, the existing tests may have be written using the doctest module. If so, that module provides a DocTestSuite class that can automatically build unittest. TestSuite instances from the existing test code. New in version 2.3.

5.3.5 TestCase Objects

Each TestCase instance represents a single test, but each concrete subclass may be used to define multiple tests — the concrete class represents a single test fixture. The fixture is created and cleaned up for each test case.

TestCase instances provide three groups of methods: one group used to run the test, another used by the test

implementation to check conditions and report failures, and some inquiry methods allowing information about the test itself to be gathered.

Methods in the first group are:

setUp()

Method called to prepare the test fixture. This is called immediately before calling the test method; any exception raised by this method will be considered an error rather than a test failure. The default implementation does nothing.

tearDown()

Method called immediately after the test method has been called and the result recorded. This is called even if the test method raised an exception, so the implementation in subclasses may need to be particularly careful about checking internal state. Any exception raised by this method will be considered an error rather than a test failure. This method will only be called if the setUp() succeeds, regardless of the outcome of the test method. The default implementation does nothing.

run([result])

Run the test, collecting the result into the test result object passed as *result*. If *result* is omitted or None, a temporary result object is created and used, but is not made available to the caller. This is equivalent to simply calling the TestCase instance.

debug()

Run the test without collecting the result. This allows exceptions raised by the test to be propagated to the caller, and can be used to support running tests under a debugger.

The test code can use any of the following methods to check for and report failures.

```
assert_(expr[, msg])
failUnless(expr[, msg])
```

Signal a test failure if *expr* is false; the explanation for the error will be *msg* if given, otherwise it will be None.

```
assertEqual(first, second[, msg])
failUnlessEqual(first, second[, msg])
```

Test that *first* and *second* are equal. If the values do not compare equal, the test will fail with the explanation given by *msg*, or None. Note that using failUnlessEqual() improves upon doing the comparison as the first parameter to failUnless(): the default value for *msg* can be computed to include representations of both *first* and *second*.

```
assertNotEqual(first, second[, msg])
failIfEqual(first, second[, msg])
```

Test that *first* and *second* are not equal. If the values do compare equal, the test will fail with the explanation given by *msg*, or None. Note that using failIfEqual() improves upon doing the comparison as the first parameter to failUnless() is that the default value for *msg* can be computed to include representations of both *first* and *second*.

```
assertAlmostEqual(first, second[, places[, msg]])
failUnlessAlmostEqual(first, second[, places[, msg]])
```

Test that *first* and *second* are approximately equal by computing the difference, rounding to the given number of *places*, and comparing to zero. Note that comparing a given number of decimal places is not the same as comparing a given number of significant digits. If the values do not compare equal, the test will fail with the explanation given by *msg*, or None.

```
assertNotAlmostEqual(first, second[, places[, msg]])
failIfAlmostEqual(first, second[, places[, msg]])
```

Test that *first* and *second* are not approximately equal by computing the difference, rounding to the given number of *places*, and comparing to zero. Note that comparing a given number of decimal places is not the same as comparing a given number of significant digits. If the values do not compare equal, the test will fail with the explanation given by *msg*, or None.

```
\begin{tabular}{ll} {\bf assertRaises} (\it{exception}, \it{callable}, \dots) \\ {\bf failUnlessRaises} (\it{exception}, \it{callable}, \dots) \\ \end{tabular}
```

Test that an exception is raised when *callable* is called with any positional or keyword arguments that are

also passed to assertRaises(). The test passes if *exception* is raised, is an error if another exception is raised, or fails if no exception is raised. To catch any of a group of exceptions, a tuple containing the exception classes may be passed as *exception*.

failIf(expr[, msg])

The inverse of the failUnless() method is the failIf() method. This signals a test failure if *expr* is true, with *msg* or None for the error message.

fail([msg])

Signals a test failure unconditionally, with msg or None for the error message.

failureException

This class attribute gives the exception raised by the test() method. If a test framework needs to use a specialized exception, possibly to carry additional information, it must subclass this exception in order to "play fair" with the framework. The initial value of this attribute is AssertionError.

Testing frameworks can use the following methods to collect information on the test:

countTestCases()

Return the number of tests represented by the this test object. For TestCase instances, this will always be 1, but this method is also implemented by the TestSuite class, which can return larger values.

defaultTestResult()

Return the default type of test result object to be used to run this test.

id()

Return a string identifying the specific test case. This is usually the full name of the test method, including the module and class names.

shortDescription()

Returns a one-line description of the test, or None if no description has been provided. The default implementation of this method returns the first line of the test method's docstring, if available, or None.

5.3.6 TestSuite Objects

TestSuite objects behave much like TestCase objects, except they do not actually implement a test. Instead, they are used to aggregate tests into groups that should be run together. Some additional methods are available to add tests to TestSuite instances:

addTest(test)

Add a TestCase or TestSuite to the set of tests that make up the suite.

addTests(tests)

Add all the tests from a sequence of TestCase and TestSuite instances to this test suite.

The run() method is also slightly different:

run (result)

Run the tests associated with this suite, collecting the result into the test result object passed as *result*. Note that unlike TestCase.run(), TestSuite.run() requires the result object to be passed in.

In the typical usage of a TestSuite object, the run() method is invoked by a TestRunner rather than by the end-user test harness.

5.3.7 TestResult Objects

A TestResult object stores the results of a set of tests. The TestCase and TestSuite classes ensure that results are properly stored; test authors do not need to worry about recording the outcome of tests.

Testing frameworks built on top of unittest may want access to the TestResult object generated by running a set of tests for reporting purposes; a TestResult instance is returned by the TestRunner.run() method for this purpose.

Each instance holds the total number of tests run, and collections of failures and errors that occurred among

those test runs. The collections contain tuples of (*testcase*, *traceback*), where *traceback* is a string containing a formatted version of the traceback for the exception.

TestResult instances have the following attributes that will be of interest when inspecting the results of running a set of tests:

errors

A list containing pairs of TestCase instances and the formatted tracebacks for tests which raised an exception but did not signal a test failure. Changed in version 2.2: Contains formatted tracebacks instead of sys.exc_info() results.

failures

A list containing pairs of TestCase instances and the formatted tracebacks for tests which signalled a failure in the code under test. Changed in version 2.2: Contains formatted tracebacks instead of sys.exc_info() results.

testsRun

The number of tests which have been started.

wasSuccessful()

Returns true if all tests run so far have passed, otherwise returns false.

The following methods of the TestResult class are used to maintain the internal data structures, and may be extended in subclasses to support additional reporting requirements. This is particularly useful in building tools which support interactive reporting while tests are being run.

startTest(test)

Called when the test case *test* is about to be run.

stopTest(test)

Called when the test case *test* has been executed, regardless of the outcome.

addError(test, err)

Called when the test case *test* raises an exception without signalling a test failure. *err* is a tuple of the form returned by sys.exc_info(): (*type*, *value*, *traceback*).

addFailure(test, err)

Called when the test case *test* signals a failure. *err* is a tuple of the form returned by sys.exc_info(): (type, value, traceback).

addSuccess(test)

This method is called for a test that does not fail; test is the test case object.

One additional method is available for TestResult objects:

stop()

This method can be called to signal that the set of tests being run should be aborted. Once this has been called, the TestRunner object return to its caller without running any additional tests. This is used by the TextTestRunner class to stop the test framework when the user signals an interrupt from the keyboard. Interactive tools which provide runners can use this in a similar manner.

5.3.8 TestLoader Objects

The TestLoader class is used to create test suites from classes and modules. Normally, there is no need to create an instance of this class; the unittest module provides an instance that can be shared as the defaultTestLoader module attribute. Using a subclass or instance would allow customization of some configurable properties.

TestLoader objects have the following methods:

loadTestsFromTestCase(testCaseClass)

Return a suite of all tests cases contained in the TestCase-derived class testCaseClass.

loadTestsFromModule(module)

Return a suite of all tests cases contained in the given module. This method searches *module* for classes derived from TestCase and creates an instance of the class for each test method defined for the class.

Warning: While using a hierarchy of Testcase-derived classes can be convenient in sharing fixtures and helper functions, defining test methods on base classes that are not intended to be instantiated directly does not play well with this method. Doing so, however, can be useful when the fixtures are different and defined in subclasses.

loadTestsFromName(name[, module])

Return a suite of all tests cases given a string specifier.

The specifier name is a "dotted name" that may resolve either to a module, a test case class, a test method within a test case class, or a callable object which returns a TestCase or TestSuite instance. For example, if you have a module SampleTests containing a TestCase-derived class SampleTestCase with three test methods (test_one(), test_two(), and test_three()), the specifier 'SampleTestS.SampleTestCase' would cause this method to return a suite which will run all three test methods. Using the specifier 'SampleTestS.SampleTestCase.test_two' would cause it to return a test suite which will run only the test_two() test method. The specifier can refer to modules and packages which have not been imported; they will be imported as a side-effect.

The method optionally resolves *name* relative to a given module.

loadTestsFromNames(names[, module])

Similar to loadTestsFromName(), but takes a sequence of names rather than a single name. The return value is a test suite which supports all the tests defined for each name.

getTestCaseNames(testCaseClass)

Return a sorted sequence of method names found within testCaseClass.

The following attributes of a TestLoader can be configured either by subclassing or assignment on an instance:

testMethodPrefix

String giving the prefix of method names which will be interpreted as test methods. The default value is 'test'.

sortTestMethodsUsing

Function to be used to compare method names when sorting them in getTestCaseNames(). The default value is the built-in cmp() function; it can be set to None to disable the sort.

suiteClass

Callable object that constructs a test suite from a list of tests. No methods on the resulting object are needed. The default value is the TestSuite class.

5.4 test — Regression tests package for Python

The test package contains all regression tests for Python as well as the modules test.test_support and test.regrtest.test_support is used to enhance your tests while test.regrtest drives the testing suite.

Each module in the test package whose name starts with 'test_' is a testing suite for a specific module or feature. All new tests should be written using the unittest module; using unittest is not required but makes the tests more flexible and maintenance of the tests easier. Some older tests are written to use doctest and a "traditional" testing style; these styles of tests will not be covered.

See Also:

Module unittest (section 5.3):

Writing PyUnit regression tests.

Module doctest (section 5.2):

Tests embedded in documentation strings.

5.4.1 Writing Unit Tests for the test package

It is preferred that tests for the test package use the unittest module and follow a few guidelines. One is to have the name of all the test methods start with 'test_' as well as the module's name. This is needed so that the

methods are recognized by the test driver as test methods. Also, no documentation string for the method should be included. A comment (such as '#Tests function returns only True or False') should be used to provide documentation for test methods. This is done because documentation strings get printed out if they exist and thus what test is being run is not stated.

A basic boilerplate is often used:

```
import unittest
from test import test_support
class MyTestCase1(unittest.TestCase):
    # Only use setUp() and tearDown() if necessary
    def setUp(self):
        ... code to execute in preparation for tests ...
    def tearDown(self):
        ... code to execute to clean up after tests ...
    def test_feature_one(self):
        # Test feature one.
        ... testing code ...
    def test_feature_two(self):
        # Test feature two.
        ... testing code ...
    ... more test methods ...
class MyTestCase2(unittest.TestCase):
    ... same structure as MyTestCase1 ...
... more test classes ...
def test_main():
    test_support.run_unittest(MyTestCase1,
                              MyTestCase2,
                              ... list other tests ...
if __name__ == '__main__':
    test main()
```

This boilerplate code allows the testing suite to be run by test.regrtest as well as on its own as a script.

The goal for regression testing is to try to break code. This leads to a few guidelines to be followed:

- The testing suite should exercise all classes, functions, and constants. This includes not just the external API that is to be presented to the outside world but also "private" code.
- Whitebox testing (examining the code being tested when the tests are being written) is preferred. Blackbox testing (testing only the published user interface) is not complete enough to make sure all boundary and edge cases are tested.
- Make sure all possible values are tested including invalid ones. This makes sure that not only all valid values are acceptable but also that improper values are handled correctly.
- Exhaust as many code paths as possible. Test where branching occurs and thus tailor input to make sure as many different paths through the code are taken.
- Add an explicit test for any bugs discovered for the tested code. This will make sure that the error does not crop up again if the code is changed in the future.

- Make sure to clean up after your tests (such as close and remove all temporary files).
- Import as few modules as possible and do it as soon as possible. This minimizes external dependencies of tests and also minimizes possible anomalous behavior from side-effects of importing a module.
- Try to maximize code reuse. On occasion, tests will vary by something as small as what type of input is used. Minimize code duplication by subclassing a basic test class with a class that specifies the input:

```
class TestFuncAcceptsSequences(unittest.TestCase):
    func = mySuperWhammyFunction
    def test_func(self):
        self.func(self.arg)

class AcceptLists(TestFuncAcceptsSequences):
    arg = [1,2,3]

class AcceptStrings(TestFuncAcceptsSequences):
    arg = 'abc'

class AcceptTuples(TestFuncAcceptsSequences):
    arg = (1,2,3)
```

See Also:

Test Driven Development

A book by Kent Beck on writing tests before code.

5.4.2 Running tests using test.regrtest

test.regreest can be used as a script to drive Python's regression test suite. Running the script by itself automatically starts running all regression tests in the test package. It does this by finding all modules in the package whose name starts with 'test_', importing them, and executing the function test_main() if present. The names of tests to execute may also be passed to the script. Specifying a single regression test (python regress.py test_spam.py) will minimize output and only print whether the test passed or failed and thus minimize output.

Running test.regrtest directly allows what resources are available for tests to use to be set. You do this by using the **-u** command-line option. Run **python regrtest.py -uall** to turn on all resources; specifying **all** as an option for **-u** enables all possible resources. If all but one resource is desired (a more common case), a comma-separated list of resources that are not desired may be listed after **all**. The command **python regrtest.py -uall,-audio,-largefile** will run test.regrtest with all resources except the **audio** and **largefile** resources. For a list of all resources and more command-line options, run **python regrtest.py -h**.

Some other ways to execute the regression tests depend on what platform the tests are being executed on. On UNIX, you can run **make test** at the top-level directory where Python was built. On Windows, executing **rt.bat** from your 'PCBuild' directory will run all regression tests.

5.5 test.test_support — Utility functions for tests

The test.test_support module provides support for Python's regression tests.

This module defines the following exceptions:

exception TestFailed

Exception to be raised when a test fails.

exception TestSkipped

Subclass of TestFailed. Raised when a test is skipped. This occurs when a needed resource (such as a network connection) is not available at the time of testing.

exception ResourceDenied

Subclass of TestSkipped. Raised when a resource (such as a network connection) is not available. Raised by the requires () function.

The test.test_support module defines the following constants:

verbose

True when verbose output is enabled. Should be checked when more detailed information is desired about a running test. *verbose* is set by test.regrtest.

have_unicode

True when Unicode support is available.

is_jython

True if the running interpreter is Jython.

TESTFN

Set to the path that a temporary file may be created at. Any temporary that is created should be closed and unlinked (removed).

The test.test_support module defines the following functions:

forget(module_name)

Removes the module named *module_name* from sys.modules and deletes any byte-compiled files of the module.

is_resource_enabled(resource)

Returns True if *resource* is enabled and available. The list of available resources is only set when test.regreest is executing the tests.

requires(resource[, msg])

Raises ResourceDenied if *resource* is not available. *msg* is the argument to ResourceDenied if it is raised. Always returns true if called by a function whose __name__ is '__main__'. Used when tests are executed by test.regrtest.

${\tt findfile}(\mathit{filename}\,)$

Return the path to the file named *filename*. If no match is found *filename* is returned. This does not equal a failure since it could be the path to the file.

run_unittest(*classes)

Execute unittest.TestCase subclasses passed to the function. The function scans the classes for methods starting with the prefix 'test_' and executes the tests individually. This is the preferred way to execute tests.

run_suite(suite[, testclass])

Execute the unittest. TestSuite instance *suite*. The optional argument *testclass* accepts one of the test classes in the suite so as to print out more detailed information on where the testing suite originated from.

5.6 decimal — Decimal floating point arithmetic

New in version 2.4.

The decimal module provides support for decimal floating point arithmetic. It offers several advantages over the float() datatype:

• Decimal numbers can be represented exactly. In contrast, numbers like 1.1 do not have an exact representation in binary floating point. End users typically would not expect 1.1 to display as 1.100000000000001 as it does with binary floating point.

- The exactness carries over into arithmetic. In decimal floating point, '0.1 + 0.1 + 0.1 0.3' is exactly equal to zero. In binary floating point, result is 5.5511151231257827e-017. While near to zero, the differences prevent reliable equality testing and differences can accumulate. For this reason, decimal would be preferred in accounting applications which have strict equality invariants.
- The decimal module incorporates a notion of significant places so that '1.30 + 1.20' is 2.50. The trailing zero is kept to indicate significance. This is the customary presentation for monetary applications. For multiplication, the "schoolbook" approach uses all the figures in the multiplicands. For instance, '1.3 * 1.2' gives 1.56 while '1.30 * 1.20' gives 1.5600.
- Unlike hardware based binary floating point, the decimal module has a user settable precision (defaulting to 28 places) which can be as large as needed for a given problem:

```
>>> getcontext().prec = 6
>>> Decimal(1) / Decimal(7)
Decimal("0.142857")
>>> getcontext().prec = 28
>>> Decimal(1) / Decimal(7)
Decimal("0.1428571428571428571428571429")
```

• Both binary and decimal floating point are implemented in terms of published standards. While the built-in float type exposes only a modest portion of its capabilities, the decimal module exposes all required parts of the standard. When needed, the programmer has full control over rounding and signal handling.

The module design is centered around three concepts: the decimal number, the context for arithmetic, and signals.

A decimal number is immutable. It has a sign, coefficient digits, and an exponent. To preserve significance, the coefficient digits do not truncate trailing zeroes. Decimals also include special values such as Infinity, -Infinity, and NaN. The standard also differentiates -0 from +0.

The context for arithmetic is an environment specifying precision, rounding rules, limits on exponents, flags indicating the results of operations, and trap enablers which determine whether signals are treated as exceptions. Rounding options include ROUND_CEILING, ROUND_DOWN, ROUND_FLOOR, ROUND_HALF_DOWN, ROUND_HALF_EVEN, ROUND_HALF_UP, and ROUND_UP.

Signals are groups of exceptional conditions arising during the course of computation. Depending on the needs of the application, signals may be ignored, considered as informational, or treated as exceptions. The signals in the decimal module are: Clamped, InvalidOperation, DivisionByZero, Inexact, Rounded, Subnormal, Overflow, and Underflow.

For each signal there is a flag and a trap enabler. When a signal is encountered, its flag incremented from zero and, then, if the trap enabler is set to one, an exception is raised. Flags are sticky, so the user needs to reset them before monitoring a calculation.

See Also:

IBM's General Decimal Arithmetic Specification, *The General Decimal Arithmetic Specification*.

IEEE standard 854-1987, Unofficial IEEE 854 Text.

5.6.1 Quick-start Tutorial

The usual start to using decimals is importing the module, viewing the current context with getcontext() and, if necessary, setting new values for precision, rounding, or enabled traps:

Decimal instances can be constructed from integers, strings or tuples. To create a Decimal from a float, first convert it to a string. This serves as an explicit reminder of the details of the conversion (including representation error). Decimal numbers include special values such as NaN which stands for "Not a number", positive and negative Infinity, and -0.

```
>>> Decimal(10)
Decimal("10")
>>> Decimal("3.14")
Decimal("3.14")
>>> Decimal((0, (3, 1, 4), -2))
Decimal("3.14")
>>> Decimal(str(2.0 ** 0.5))
Decimal("1.41421356237")
>>> Decimal("NaN")
Decimal("NaN")
>>> Decimal("-Infinity")
```

The significance of a new Decimal is determined solely by the number of digits input. Context precision and rounding only come into play during arithmetic operations.

```
>>> getcontext().prec = 6
>>> Decimal('3.0')
Decimal("3.0")
>>> Decimal('3.1415926535')
Decimal("3.1415926535")
>>> Decimal('3.1415926535') + Decimal('2.7182818285')
Decimal("5.85987")
>>> getcontext().rounding = ROUND_UP
>>> Decimal('3.1415926535') + Decimal('2.7182818285')
Decimal("5.85988")
```

Decimals interact well with much of the rest of python. Here is a small decimal floating point flying circus:

```
>>> data = map(Decimal, '1.34 1.87 3.45 2.35 1.00 0.03 9.25'.split())
>>> max(data)
Decimal("9.25")
>>> min(data)
Decimal("0.03")
>>> sorted(data)
[Decimal("0.03"), Decimal("1.00"), Decimal("1.34"), Decimal("1.87"), Dec
   Decimal("2.35"), Decimal("3.45"), Decimal("9.25")]
>>> sum(data)
Decimal("19.29")
>>> a,b,c = data[:3]
>>> str(a)
11.34
>>> float(a)
1.3400000000000001
>>> round(a, 1)
                                                                                                 # round() first converts to binary floating point
1.3
>>> int(a)
1
>>> a * 5
Decimal("6.70")
>>> a * b
Decimal("2.5058")
>>> c % a
Decimal("0.77")
```

The quantize() method rounds a number to a fixed exponent. This method is useful for monetary applications that often round results to a fixed number of places:

```
>>> Decimal('7.325').quantize(Decimal('.01'), rounding=ROUND_DOWN)
Decimal("7.32")
>>> Decimal('7.325').quantize(Decimal('1.'), rounding=ROUND_UP)
Decimal("8")
```

As shown above, the getcontext() function accesses the current context and allows the settings to be changed. This approach meets the needs of most applications.

For more advanced work, it may be useful to create alternate contexts using the Context() constructor. To make an alternate active, use the setcontext() function.

In accordance with the standard, the Decimal module provides two ready to use standard contexts, BasicContext and ExtendedContext. The former is especially useful for debugging because many of the traps are enabled:

```
>>> myothercontext = Context(prec=60, rounding=ROUND_HALF_DOWN)
>>> setcontext(myothercontext)
>>> Decimal(1) / Decimal(7)
Decimal("0.1428571428571428571428571428571428571428571428571428571428571428571
>>> ExtendedContext
Context(prec=9, rounding=ROUND_HALF_EVEN, Emin=-999999999, Emax=999999999,
        capitals=1, flags=[], traps=[])
>>> setcontext(ExtendedContext)
>>> Decimal(1) / Decimal(7)
Decimal("0.142857143")
>>> Decimal(42) / Decimal(0)
Decimal("Infinity")
>>> setcontext(BasicContext)
>>> Decimal(42) / Decimal(0)
Traceback (most recent call last):
 File "<pyshell#143>", line 1, in -toplevel-
   Decimal(42) / Decimal(0)
DivisionByZero: x / 0
```

Contexts also have signal flags for monitoring exceptional conditions encountered during computations. The flags remain set until explicitly cleared, so it is best to clear the flags before each set of monitored c959 428c003agy(flags)]TJ 0 -11.x

If value is a tuple, it should have three components, a sign (0 for positive or 1 for negative), a tuple of digits, and an integer exponent. For example, 'Decimal((0, (1, 4, 1, 4), -3))' returns Decimal("1.414").

The *context* precision does not affect how many digits are stored. That is determined exclusively by the number of digits in *value*. For example, 'Decimal("3.00000")' records all five zeroes even if the context precision is only three.

The purpose of the *context* argument is determining what to do if *value* is a malformed string. If the context traps InvalidOperation, an exception is raised; otherwise, the constructor returns a new Decimal with the value of NaN.

Once constructed, Decimal objects are immutable.

Decimal floating point objects share many properties with the other builtin numeric types such as float and int. All of the usual math operations and special methods apply. Likewise, decimal objects can be copied, pickled, printed, used as dictionary keys, used as set elements, compared, sorted, and coerced to another type (such as float or long).

In addition to the standard numeric properties, decimal floating point objects also have a number of specialized methods:

adjusted()

Return the adjusted exponent after shifting out the coefficient's rightmost digits until only the lead digit remains: Decimal("32le+5"). adjusted() returns seven. Used for determining the position of the most significant digit with respect to the decimal point.

as_tuple()

Returns a tuple representation of the number: '(sign, digittuple, exponent)'.

compare(other[, context])

Compares like __cmp__() but returns a decimal instance:

```
max(other[, context])
```

Like 'max(self, other)' except that the context rounding rule is applied before returning and that NaN values are either signalled or ignored (depending on the context and whether they are signaling or quiet).

```
min(other, context)
```

Like 'min(self, other)' except that the context rounding rule is applied before returning and that NaN values are either signalled or ignored (depending on the context and whether they are signaling or quiet).

```
normalize([context])
```

Normalize the number by stripping the rightmost trailing zeroes and converting any result equal to Decimal("0") to Decimal("0e0"). Used for producing canonical values for members of an equiv-

alence class. For example, Decimal("32.100") and Decimal("0.321000e+2") both normalize to the equivalent value Decimal("32.1").

quantize(exp [, rounding[, context[, watchexp]]])

Quantize makes the exponent the same as *exp*. Searches for a rounding method in *rounding*, then in *context*, and then in the current context.

If *watchexp* is set (default), then an error is returned whenever the resulting exponent is greater than Emax or less than Etiny.

remainder_near(other[, context])

Computes the modulo as either a positive or negative value depending on which is closest to zero. For instance, 'Decimal(10).remainder_near(6)' returns Decimal("-2") which is closer to zero than Decimal("4").

If both are equally close, the one chosen will have the same sign as *self*.

same_quantum(other[, context])

Test whether self and other have the same exponent or whether both are NaN.

sqrt([context])

Return the square root to full precision.

to_eng_string([context])

Convert to an engineering-type string.

Engineering notation has an exponent which is a multiple of 3, so there are up to 3 digits left of the decimal place. For example, converts Decimal ('123E+1') to Decimal ("1.23E+3")

to_integral([rounding[, context]])

Rounds to the nearest integer without signaling Inexact or Rounded. If given, applies *rounding*; otherwise, uses the rounding method in either the supplied *context* or the current context.

5.6.3 Context objects

Contexts are environments for arithmetic operations. They govern precision, set rules for rounding, determine which signals are treated as exceptions, and limit the range for exponents.

Each thread has its own current context which is accessed or changed using the getcontext() and setcontext() functions:

getcontext()

Return the current context for the active thread.

setcontext(c)

Set the current context for the active thread to c.

New contexts can formed using the Context constructor described below. In addition, the module provides three pre-made contexts:

class BasicContext

This is a standard context defined by the General Decimal Arithmetic Specification. Precision is set to nine. Rounding is set to ROUND_HALF_UP. All flags are cleared. All traps are enabled (treated as exceptions) except Inexact, Rounded, and Subnormal.

Because many of the traps are enabled, this context is useful for debugging.

class ExtendedContext

This is a standard context defined by the General Decimal Arithmetic Specification. Precision is set to nine. Rounding is set to ROUND_HALF_EVEN. All flags are cleared. No traps are enabled (so that exceptions are not raised during computations).

Because the trapped are disabled, this context is useful for applications that prefer to have result value of NaN or Infinity instead of raising exceptions. This allows an application to complete a run in the presence of conditions that would otherwise halt the program.

class DefaultContext

This context is used by the Context constructor as a prototype for new contexts. Changing a field (such a

precision) has the effect of changing the default for new contexts creating by the Context constructor.

This context is most useful in multi-threaded environments. Changing one of the fields before threads are started has the effect of setting system-wide defaults. Changing the fields after threads have started is not recommended as it would require thread synchronization to prevent race conditions.

In single threaded environments, it is preferable to not use this context at all. Instead, simply create contexts explicitly as described below.

The default values are precision=28, rounding=ROUND_HALF_EVEN, and enabled traps for Overflow, InvalidOperation, and DivisionByZero.

In addition to the three supplied contexts, new contexts can be created with the Context constructor.

class Context(prec=None, rounding=None, traps=None, flags=None, Emin=None, Emax=None, capitals=1)
Creates a new context. If a field is not specified or is None, the default values are copied from the DefaultContext. If the flags field is not specified or is None, all flags are cleared.

The prec field is a positive integer that sets the precision for arithmetic operations in the context.

The *rounding* option is one of:

- •ROUND_CEILING (towards Infinity),
- •ROUND_DOWN (towards zero),
- •ROUND_FLOOR (towards -Infinity),
- •ROUND_HALF_DOWN (to nearest with ties going towards zero),
- •ROUND_HALF_EVEN (to nearest with ties going to nearest even integer),
- •ROUND_HALF_UP (to nearest with ties going away from zero), or
- •ROUND_UP (away from zero).

The *traps* and *flags* fields list any signals to be set. Generally, new contexts should only set traps and leave the flags clear.

The *Emin* and *Emax* fields are integers specifying the outer limits allowable for exponents.

The *capitals* field is either 0 or 1 (the default). If set to 1, exponents are printed with a capital E; otherwise, a lowercase e is used: Decimal('6.02e+23').

The Context class defines several general purpose methods as well as a large number of methods for doing arithmetic directly in a given context.

clear_flags()

Resets all of the flags to 0.

copy()

Return a duplicate of the context.

create_decimal(num)

Creates a new Decimal instance from *num* but using *self* as context. Unlike the Decimal constructor, the context precision, rounding method, flags, and traps are applied to the conversion.

This is useful because constants are often given to a greater precision than is needed by the application. Another benefit is that rounding immediately eliminates unintended effects from digits beyond the current precision. In the following example, using unrounded inputs means that adding zero to a sum can change the result:

```
>>> getcontext().prec = 3
>>> Decimal("3.4445") + Decimal("1.0023")
Decimal("4.45")
>>> Decimal("3.4445") + Decimal(0) + Decimal("1.0023")
Decimal("4.44")
```

Etiny()

Returns a value equal to 'Emin - prec + 1' which is the minimum exponent value for subnormal results. When underflow occurs, the exponent is set to Etiny.

```
Etop()
```

```
Returns a value equal to 'Emax - prec + 1'.
```

The usual approach to working with decimals is to create Decimal instances and then apply arithmetic operations which take place within the current context for the active thread. An alternate approach is to use context methods for calculating within a specific context. The methods are similar to those for the Decimal class and are only briefly recounted here.

abs(x)

Returns the absolute value of x.

add(x, y)

Return the sum of x and y.

compare(x, y)

Compares values numerically.

Like __cmp__() but returns a decimal instance:

divide(x, y)

Return x divided by y.

divmod(x, y)

Divides two numbers and returns the integer part of the result.

max(x, y)

Compare two values numerically and return the maximum.

If they are numerically equal then the left-hand operand is chosen as the result.

min(x, y)

Compare two values numerically and return the minimum.

If they are numerically equal then the left-hand operand is chosen as the result.

minus(x)

Minus corresponds to the unary prefix minus operator in Python.

multiply(x, y)

Return the product of x and y.

normalize(x)

Normalize reduces an operand to its simplest form.

Essentially a plus operation with all trailing zeros removed from the result.

plus(x

Plus corresponds to the unary prefix plus operator in Python. This operation applies the context precision and rounding, so it is *not* an identity operation.

```
power(x, y[, modulo])
```

Return 'x ** y' to the modulo if given.

The right-hand operand must be a whole number whose integer part (after any exponent has been applied) has no more than 9 digits and whose fractional part (if any) is all zeros before any rounding. The operand may be positive, negative, or zero; if negative, the absolute value of the power is used, and the left-hand operand is inverted (divided into 1) before use.

If the increased precision needed for the intermediate calculations exceeds the capabilities of the implementation then an InvalidOperation condition is signaled.

If, when raising to a negative power, an underflow occurs during the division into 1, the operation is not halted at that point but continues.

quantize(x, y)

Returns a value equal to x after rounding and having the exponent of y.

Unlike other operations, if the length of the coefficient after the quantize operation would be greater than precision, then an InvalidOperation is signaled. This guarantees that, unless there is an error condition, the quantized exponent is always equal to that of the right-hand operand.

Also unlike other operations, quantize never signals Underflow, even if the result is subnormal and inexact.

remainder(x, y)

Returns the remainder from integer division.

The sign of the result, if non-zero, is the same as that of the original dividend.

remainder_near(x, y)

class Inexact

Indicates that rounding occurred and the result is not exact.

Signals when non-zero digits were discarded during rounding. The rounded result is returned. The signal flag or trap is used to detect when results are inexact.

class InvalidOperation

An invalid operation was performed.

Indicates that an operation was requested that does not make sense. If not trapped, returns NaN. Possible causes include:

```
Infinity - Infinity
0 * Infinity
Infinity / Infinity
x % 0
Infinity % x
x._rescale( non-integer )
sqrt(-x) and x > 0
0 ** 0
x ** (non-integer)
x ** Infinity
```

class Overflow

Numerical overflow.

Indicates the exponent is larger than Emax after rounding has occurred. If not trapped, the result depends on the rounding mode, either pulling inward to the largest representable finite number or rounding outward to Infinity. In either case, Inexact and Rounded are also signaled.

class Rounded

Rounding occurred though possibly no information was lost.

Signaled whenever rounding discards digits; even if those digits are zero (such as rounding 5.00 to 5.0). If not trapped, returns the result unchanged. This signal is used to detect loss of significant digits.

class Subnormal

Exponent was lower than Emin prior to rounding.

Occurs when an operation result is subnormal (the exponent is too small). If not trapped, returns the result unchanged.

class Underflow

Numerical underflow with result rounded to zero.

Occurs when a subnormal result is pushed to zero by rounding. Inexact and Subnormal are also signaled.

The following table summarizes the hierarchy of signals:

```
exceptions.ArithmeticError(exceptions.StandardError)

DecimalException

Clamped

DivisionByZero(DecimalException, exceptions.ZeroDivisionError)

Inexact

Overflow(Inexact, Rounded)

Underflow(Inexact, Rounded, Subnormal)

InvalidOperation

Rounded

Subnormal
```

5.6.5 Floating Point Notes

Mitigating round-off error with increased precision

The use of decimal floating point eliminates decimal representation error (making it possible to represent 0.1 exactly); however, some operations can still incur round-off error when non-zero digits exceed the fixed precision.

The effects of round-off error can be amplified by the addition or subtraction of nearly offsetting quantities resulting in loss of significance. Knuth provides two instructive examples where rounded floating point arithmetic with insufficient precision causes the breakdown of the associative and distributive properties of addition:

```
# Examples from Seminumerical Algorithms, Section 4.2.2.
>>> from decimal import *
>>> getcontext().prec = 8

>>> u, v, w = Decimal(11111113), Decimal(-11111111), Decimal('7.51111111')
>>> (u + v) + w
Decimal("9.5111111")
>>> u + (v + w)
Decimal("10")

>>> u, v, w = Decimal(20000), Decimal(-6), Decimal('6.0000003')
>>> (u*v) + (u*w)
Decimal("0.01")
>>> u * (v+w)
Decimal("0.0060000")
```

The decimal module makes it possible to restore the identities by expanding the precision sufficiently to avoid loss of significance:

```
>>> getcontext().prec = 20
>>> u, v, w = Decimal(11111113), Decimal(-11111111), Decimal('7.51111111')
>>> (u + v) + w
Decimal("9.51111111")
>>> u + (v + w)
Decimal("9.51111111")
>>>
>>> u, v, w = Decimal(20000), Decimal(-6), Decimal('6.0000003')
>>> (u*v) + (u*w)
Decimal("0.0060000")
>>> u * (v+w)
Decimal("0.0060000")
```

Special values

The number system for the decimal module provides special values including NaN, sNaN, -Infinity, Infinity, and two zeroes, +0 and -0.

Infinities can be constructed directly with: Decimal ('Infinity'). Also, they can arise from dividing by zero when the DivisionByZero signal is not trapped. Likewise, when the Overflow signal is not trapped, infinity can result from rounding beyond the limits of the largest representable number.

The infinities are signed (affine) and can be used in arithmetic operations where they get treated as very large, indeterminate numbers. For instance, adding a constant to infinity gives another infinite result.

Some operations are indeterminate and return NaN, or if the InvalidOperation signal is trapped, raise an exception. For example, 0/0 returns NaN which means "not a number". This variety of NaN is quiet and, once created, will flow through other computations always resulting in another NaN. This behavior can be useful for a

series of computations that occasionally have missing inputs — it allows the calculation to proceed while flagging specific results as invalid.

A variant is sNaN which signals rather than remaining quiet after every operation. This is a useful return value when an invalid result needs to interrupt a calculation for special handling.

The signed zeros can result from calculations that underflow. They keep the sign that would have resulted if the calculation had been carried out to greater precision. Since their magnitude is zero, both positive and negative zeros are treated as equal and their sign is informational.

In addition to the two signed zeros which are distinct yet equal, there are various representations of zero with differing precisions yet equivalent in value. This takes a bit of getting used to. For an eye accustomed to normalized floating point representations, it is not immediately obvious that the following calculation returns a value equal to zero:

```
>>> 1 / Decimal('Infinity')
Decimal("0E-1000000026")
```

5.6.6 Working with threads

The getcontext() function accesses a different Context object for each thread. Having separate thread contexts means that threads may make changes (such as getcontext.prec=10) without interfering with other threads.

Likewise, the setcontext() function automatically assigns its target to the current thread.

If setcontext() has not been called before getcontext(), then getcontext() will automatically create a new context for use in the current thread.

The new context is copied from a prototype context called *DefaultContext*. To control the defaults so that each thread will use the same values throughout the application, directly modify the *DefaultContext* object. This should be done *before* any threads are started so that there won't be a race condition between threads calling <code>getcontext()</code>. For example:

```
# Set applicationwide defaults for all threads about to be launched
DefaultContext.prec = 12
DefaultContext.rounding = ROUND_DOWN
DefaultContext.traps = ExtendedContext.traps.copy()
DefaultContext.traps[InvalidOperation] = 1
setcontext(DefaultContext)

# Afterwards, the threads can be started
t1.start()
t2.start()
t3.start()
```

5.6.7 Recipes

Here are a few recipes that serve as utility functions and that demonstrate ways to work with the Decimal class:

```
def moneyfmt(value, places=2, curr='', sep=',', dp='.',
            pos='', neg='-', trailneg=''):
    """Convert Decimal to a money formatted string.
    places: required number of places after the decimal point
             optional currency symbol before the sign (may be blank)
    sep:
             optional grouping separator (comma, period, space, or blank)
    dp:
             decimal point indicator (comma or period)
             only specify as blank when places is zero
             optional sign for positive numbers: '+', space or blank
    pos:
            optional sign for negative numbers: '-', '(', space or blank
    neq:
    trailneg:optional trailing minus indicator: '-', ')', space or blank
    >>> d = Decimal('-1234567.8901')
    >>> moneyfmt(d, curr='$')
    '-$1,234,567.89'
    >>> moneyfmt(d, places=0, sep='.', dp='', neg='', trailneg='-')
    11.234.568-1
    >>> moneyfmt(d, curr='$', neg='(', trailneg=')')
    '($1,234,567.89)'
    >>> moneyfmt(Decimal(123456789), sep=' ')
    '123 456 789.00'
    >>> moneyfmt(Decimal('-0.02'), neg='<', trailneg='>')
    '<.02>'
    . . .
    q = Decimal((0, (1,), -places))
                                      # 2 places --> '0.01'
    sign, digits, exp = value.quantize(q).as_tuple()
    assert exp == -places
    result = []
    digits = map(str, digits)
    build, next = result.append, digits.pop
    if sign:
       build(trailneg)
    for i in range(places):
        if digits:
           build(next())
        else:
           build('0')
    build(dp)
    i = 0
    while digits:
       build(next())
        i += 1
        if i == 3 and digits:
            i = 0
            build(sep)
    build(curr)
    if sign:
       build(neg)
    else:
       build(pos)
    result.reverse()
    return ''.join(result)
    """Compute Pi to the current precision.
    >>> print pi()
    3.141592653589793238462643383
    getcontext().prec += 2 # extra digits for intermediate steps
    three = Decimal(3)
                           # substitute "three=3.0" for regular floats
    lasts, t, s, n, na, d, da = 0, three, 3, 1, 0 Chapter 5. Miscellaneous Services
    while s != lasts:
        lasts = s
        n, na = n+na, na+8
```

196

d, da = d+da, da+32

5.6.8 Decimal FAQ

- Q. It is cumbersome to type decimal.Decimal('1234.5'). Is there a way to minimize typing when using the interactive interpreter?
- A. Some users abbreviate the constructor to just a single letter:

```
>>> D = decimal.Decimal
>>> D('1.23') + D('3.45')
Decimal("4.68")
```

- Q. In a fixed-point application with two decimal places, some inputs have many places and need to be rounded. Others are not supposed to have excess digits and need to be validated. What methods should be used?
- A. The quantize() method rounds to a fixed number of decimal places. If the Inexact trap is set, it is also useful for validation:

```
>>> TWOPLACES = Decimal(10) ** -2  # same as Decimal('0.01')
>>> # Round to two places
>>> Decimal("3.214").quantize(TWOPLACES)
Decimal("3.21")
>>> # Validate that a number does not exceed two places
>>> Decimal("3.21").quantize(TWOPLACES, context=Context(traps=[Inexact]))
Decimal("3.21")
>>> Decimal("3.21")

Traceback (most recent call last):
...
Inexact: Changed in rounding
```

- Q. Once I have valid two place inputs, how do I maintain that invariant throughout an application?
- A. Some operations like addition and subtraction automatically preserve fixed point. Others, like multiplication and division, change the number of decimal places and need to be followed-up with a quantize() step.
- Q. There are many ways to express the same value. The numbers 200, 200.000, 2E2, and .02E+4 all have the same value at various precisions. Is there a way to transform them to a single recognizable canonical value?
- A. The normalize() method maps all equivalent values to a single representive:

```
>>> values = map(Decimal, '200 200.000 2E2 .02E+4'.split())
>>> [v.normalize() for v in values]
[Decimal("2E+2"), Decimal("2E+2"), Decimal("2E+2")]
```

- Q. Some decimal values always print with exponential notation. Is there a way to get a non-exponential representation?
- A. For some values, exponential notation is the only way to express the number of significant places in the coefficient. For example, expressing 5.0E+3 as 5000 keeps the value constant but cannot show the original's two-place significance.
- Q. Is there a way to convert a regular float to a Decimal?
- A. Yes, all binary floating point numbers can be exactly expressed as a Decimal. An exact conversion may take more precision than intuition would suggest, so trapping Inexact will signal a need for more precision:

```
def floatToDecimal(f):
    "Convert a floating point number to a Decimal with no loss of information"
    \# Transform (exactly) a float to a mantissa (0.5 <= abs(m) < 1.0) and an
    # exponent. Double the mantissa until it is an integer. Use the integer
    # mantissa and exponent to compute an equivalent Decimal. If this cannot
    # be done exactly, then retry with more precision.
    mantissa, exponent = math.frexp(f)
    while mantissa != int(mantissa):
        mantissa *= 2.0
        exponent -= 1
    mantissa = int(mantissa)
    oldcontext = getcontext()
    setcontext(Context(traps=[Inexact]))
    try:
        while True:
           try:
               return mantissa * Decimal(2) ** exponent
            except Inexact:
                getcontext().prec += 1
    finally:
        setcontext(oldcontext)
```

- Q. Why isn't the floatToDecimal() routine included in the module?
- A. There is some question about whether it is advisable to mix binary and decimal floating point. Also, its use requires some care to avoid the representation issues associated with binary floating point:

```
>>> floatToDecimal(1.1)
Decimal("1.100000000000000088817841970012523233890533447265625")
```

- Q. Within a complex calculation, how can I make sure that I haven't gotten a spurious result because of insufficient precision or rounding anomalies.
- A. The decimal module makes it easy to test results. A best practice is to re-run calculations using greater precision and with various rounding modes. Widely differing results indicate insufficient precision, rounding mode issues, ill-conditioned inputs, or a numerically unstable algorithm.
- Q. I noticed that context precision is applied to the results of operations but not to the inputs. Is there anything to watch out for when mixing values of different precisions?
- A. Yes. The principle is that all values are considered to be exact and so is the arithmetic on those values. Only the results are rounded. The advantage for inputs is that "what you type is what you get". A disadvantage is that the results can look odd if you forget that the inputs haven't been rounded:

```
>>> getcontext().prec = 3
>>> Decimal('3.104') + D('2.104')
Decimal("5.21")
>>> Decimal('3.104') + D('0.000') + D('2.104')
Decimal("5.20")
```

The solution is either to increase precision or to force rounding of inputs using the unary plus operation:

```
>>> getcontext().prec = 3
>>> +Decimal('1.23456789')  # unary plus triggers rounding
Decimal("1.23")
```

Alternatively, inputs can be rounded upon creation using the Context.create_decimal() method:

```
>>> Context(prec=5, rounding=ROUND_DOWN).create_decimal('1.2345678')
Decimal("1.2345")
```

5.7 math — Mathematical functions

This module is always available. It provides access to the mathematical functions defined by the C standard.

These functions cannot be used with complex numbers; use the functions of the same name from the cmath module if you require support for complex numbers. The distinction between functions which support complex numbers and those which don't is made since most users do not want to learn quite as much mathematics as required to understand complex numbers. Receiving an exception instead of a complex result allows earlier detection of the unexpected complex number used as a parameter, so that the programmer can determine how and why it was generated in the first place.

The following functions are provided by this module. Except when explicitly noted otherwise, all return values are floats.

Number-theoretic and representation functions:

ceil(x)

Return the ceiling of x as a float, the smallest integer value greater than or equal to x.

fabs(x)

Return the absolute value of x.

floor(x)

Return the floor of x as a float, the largest integer value less than or equal to x.

fmod(x, y)

frexp(x)

Return the mantissa and exponent of x as the pair (m, e). m is a float and e is an integer such that x = m * 2**e exactly. If x is zero, returns (0.0, 0), otherwise 0.5 <= abs(m) < 1. This is used to "pick apart" the internal representation of a float in a portable way.

ldexp(x, i)

Return x * (2**i). This is essentially the inverse of function frexp().

modf(x)

Return the fractional and integer parts of x. Both results carry the sign of x, and both are floats.

Note that frexp() and modf() have a different call/return pattern than their C equivalents: they take a single argument and return a pair of values, rather than returning their second return value through an 'output parameter' (there is no such thing in Python).

For the ceil(), floor(), and modf() functions, note that *all* floating-point numbers of sufficiently large magnitude are exact integers. Python floats typically carry no more than 53 bits of precision (the same as the platform C double type), in which case any float x with abs (x) >= 2**52 necessarily has no fractional bits.

Power and logarithmic functions:

```
exp(x)
```

```
Return e^*x.
log(x[,base])
     Return the logarithm of x to the given base. If the base is not specified, return the natural logarithm of x
     (that is, the logarithm to base e). Changed in version 2.3: base argument added.
log10(x)
     Return the base-10 logarithm of x.
pow(x, y)
     Return x * * y.
sqrt(x)
     Return the square root of x.
Trigonometric functions:
acos(x)
     Return the arc cosine of x, in radians.
asin(x)
     Return the arc sine of x, in radians.
atan(x)
     Return the arc tangent of x, in radians.
atan2(y, x)
     Return atan(y / x), in radians. The result is between -pi and pi. The vector in the plane from the
     origin to point (x, y) makes this angle with the positive X axis. The point of atan2() is that the signs
     of both inputs are known to it, so it can compute the correct quadrant for the angle. For example, atan (1)
     and atan2(1, 1) are both pi/4, but atan2(-1, -1) is -3*pi/4.
\cos(x)
     Return the cosine of x radians.
hypot(x, y)
     Return the Euclidean norm, sqrt(x*x + y*y). This is the length of the vector from the origin to point
      (x, y).
sin(x)
     Return the sine of x radians.
tan(x)
     Return the tangent of x radians.
Angular conversion:
degrees(x)
     Converts angle x from radians to degrees.
radians(x)
     Converts angle x from degrees to radians.
Hyperbolic functions:
cosh(x)
     Return the hyperbolic cosine of x.
sinh(x)
     Return the hyperbolic sine of x.
tanh(x)
     Return the hyperbolic tangent of x.
The module also defines two mathematical constants:
```

рi

The mathematical constant pi.

The mathematical constant e.

Note: The math module consists mostly of thin wrappers around the platform C math library functions. Behavior in exceptional cases is loosely specified by the C standards, and Python inherits much of its mathfunction error-reporting behavior from the platform C implementation. As a result, the specific exceptions raised in error cases (and even whether some arguments are considered to be exceptional at all) are not defined in any useful cross-platform or cross-release way. For example, whether math.log(0) returns -Inf or raises ValueError or OverflowError isn't defined, and in cases where math.log(0) raises OverflowError, math.log(0L) may raise ValueError instead.

See Also:

Module cmath (section 5.8):

Complex number versions of many of these functions.

5.8 cmath — Mathematical functions for complex numbers

This module is always available. It provides access to mathematical functions for complex numbers. The functions are:

acos(x)

Return the arc cosine of x. There are two branch cuts: One extends right from 1 along the real axis to ∞ , continuous from below. The other extends left from -1 along the real axis to $-\infty$, continuous from above.

acosh(x)

Return the hyperbolic arc cosine of x. There is one branch cut, extending left from 1 along the real axis to $-\infty$, continuous from above.

asin(x)

Return the arc sine of x. This has the same branch cuts as acos().

asinh(x)

Return the hyperbolic arc sine of x. There are two branch cuts, extending left from $\pm 1 j$ to $\pm -\infty j$, both continuous from above. These branch cuts should be considered a bug to be corrected in a future release. The correct branch cuts should extend along the imaginary axis, one from 1j up to ∞j and continuous from the right, and one from -1j down to $-\infty j$ and continuous from the left.

atan(x)

Return the arc tangent of x. There are two branch cuts: One extends from 1j along the imaginary axis to ∞j , continuous from the left. The other extends from -1j along the imaginary axis to $-\infty j$, continuous from the left. (This should probably be changed so the upper cut becomes continuous from the other side.)

atanh(x)

Return the hyperbolic arc tangent of x. There are two branch cuts: One extends from 1 along the real axis to ∞ , continuous from above. The other extends from -1 along the real axis to $-\infty$, continuous from above. (This should probably be changed so the right cut becomes continuous from the other side.)

$\cos(x)$

Return the cosine of x.

cosh(x)

Return the hyperbolic cosine of x.

exp(x)

Return the exponential value e^*x .

$\log(x[,base])$

Returns the logarithm of x to the given *base*. If the *base* is not specified, returns the natural logarithm of x. There is one branch cut, from 0 along the negative real axis to $-\infty$, continuous from above. Changed in version 2.4: *base* argument added.

log10(x)

Return the base-10 logarithm of x. This has the same branch cut as log().

```
sin(x)
    Return the sine of x.

sinh(x)
    Return the hyperbolic sine of x.

sqrt(x)
    Return the square root of x. This has the same branch cut as log().

tan(x)
    Return the tangent of x.

tanh(x)
    Return the hyperbolic tangent of x.

The module also defines two mathematical constants:

pi
    The mathematical constant pi, as a real.
```

The mathematical constant e, as a real.

Note that the selection of functions is similar, but not identical, to that in module math. The reason for having two modules is that some users aren't interested in complex numbers, and perhaps don't even know what they are. They would rather have math.sqrt(-1) raise an exception than return a complex number. Also note that the functions defined in cmath always return a complex number, even if the answer can be expressed as a real number (in which case the complex number has an imaginary part of zero).

A note on branch cuts: They are curves along which the given function fails to be continuous. They are a necessary feature of many complex functions. It is assumed that if you need to compute with complex functions, you will understand about branch cuts. Consult almost any (not too elementary) book on complex variables for enlightenment. For information of the proper choice of branch cuts for numerical purposes, a good reference should be the following:

See Also:

Kahan, W: Branch cuts for complex elementary functions; or, Much ado about nothing's sign bit. In Iserles, A., and Powell, M. (eds.), *The state of the art in numerical analysis*. Clarendon Press (1987) pp165-211.

5.9 random — Generate pseudo-random numbers

This module implements pseudo-random number generators for various distributions.

For integers, uniform selection from a range. For sequences, uniform selection of a random element, a function to generate a random permutation of a list in-place, and a function for random sampling without replacement.

On the real line, there are functions to compute uniform, normal (Gaussian), lognormal, negative exponential, gamma, and beta distributions. For generating distributions of angles, the von Mises distribution is available.

Almost all module functions depend on the basic function random(), which generates a random float uniformly in the semi-open range [0.0, 1.0). Python uses the Mersenne Twister as the core generator. It produces 53-bit precision floats and has a period of $2^{**}19937-1$. The underlying implementation in C is both fast and threadsafe. The Mersenne Twister is one of the most extensively tested random number generators in existence. However, being completely deterministic, it is not suitable for all purposes, and is completely unsuitable for cryptographic purposes.

The functions supplied by this module are actually bound methods of a hidden instance of the random.Random class. You can instantiate your own instances of Random to get generators that don't share state. This is especially useful for multi-threaded programs, creating a different instance of Random for each thread, and using the jumpahead() method to ensure that the generated sequences seen by each thread don't overlap.

Class Random can also be subclassed if you want to use a different basic generator of your own devising: in that case, override the random(), seed(), getstate(), setstate() and jumpahead() methods. Optionally, a new generator can supply a getrandombits() method — this allows randrange() to produce

selections over an arbitrarily large range. New in version 2.4: the getrandombits() method.

As an example of subclassing, the random module provides the WichmannHill class which implements an alternative generator in pure Python. The class provides a backward compatible way to reproduce results from earlier versions of Python which used the Wichmann-Hill algorithm as the core generator. Changed in version 2.3: Substituted Mersenne Twister for Wichmann-Hill.

Bookkeeping functions:

seed([x])

Initialize the basic random number generator. Optional argument x can be any hashable object. If x is omitted or None, current system time is used; current system time is also used to initialize the generator when the module is first imported. If randomness sources are provided by the operating system, they are used instead of the system time (see the os.urandom() function for details on availability). Changed in version 2.4: formerly, operating system resources were not used. If x is not None or an int or long, hash(x) is used instead. If x is an int or long, x is used directly.

getstate()

Return an object capturing the current internal state of the generator. This object can be passed to setstate() to restore the state. New in version 2.1.

setstate(state)

state should have been obtained from a previous call to getstate(), and setstate() restores the internal state of the generator to what it was at the time setstate() was called. New in version 2.1.

jumpahead(n)

Change the internal state to one different from and likely far away from the current state. n is a non-negative integer which is used to scramble the current state vector. This is most useful in multi-threaded programs, in conjuction with multiple instances of the Random class: setstate() or seed() can be used to force all instances into the same internal state, and then jumpahead() can be used to force the instances' states far apart. New in version 2.1. Changed in version 2.3: Instead of jumping to a specific state, n steps ahead, jumpahead(n) jumps to another state likely to be separated by many steps.

getrandbits(k)

Returns a python long int with k random bits. This method is supplied with the MersenneTwister generator and some other generators may also provide it as an optional part of the API. When available, getrandbits() enables randrange() to handle arbitrarily large ranges. New in version 2.4.

Functions for integers:

randrange ([start,] stop[, step])

Return a randomly selected element from range(start, stop, step). This is equivalent to choice(range(start, stop, step)), but doesn't actually build a range object. New in version 1.5.2.

randint(a, b)

Return a random integer N such that $a \ll N \ll b$.

Functions for sequences:

choice(seq)

Return a random element from the non-empty sequence *seq*. If *seq* is empty, raises IndexError.

shuffle(x[, random])

Shuffle the sequence x in place. The optional argument random is a 0-argument function returning a random float in [0.0, 1.0); by default, this is the function random().

Note that for even rather small len(x), the total number of permutations of x is larger than the period of most random number generators; this implies that most permutations of a long sequence can never be generated.

sample(population, k)

Return a k length list of unique elements chosen from the population sequence. Used for random sampling without replacement. New in version 2.3.

Returns a new list containing elements from the population while leaving the original population unchanged. The resulting list is in selection order so that all sub-slices will also be valid random samples. This allows raffle winners (the sample) to be partitioned into grand prize and second place winners (the subslices).

Members of the population need not be hashable or unique. If the population contains repeats, then each occurrence is a possible selection in the sample.

To choose a sample from a range of integers, use xrange as an argument. This is especially fast and space efficient for sampling from a large population: sample(xrange(10000000), 60).

The following functions generate specific real-valued distributions. Function parameters are named after the corresponding variables in the distribution's equation, as used in common mathematical practice; most of these equations can be found in any statistics text.

random()

Return the next random floating point number in the range [0.0, 1.0).

uniform(a, b)

Return a random real number N such that a <= N < b.

betavariate(alpha, beta)

Beta distribution. Conditions on the parameters are alpha > -1 and beta > -1. Returned values range between 0 and 1.

expovariate(lambd)

Exponential distribution. *lambd* is 1.0 divided by the desired mean. (The parameter would be called "lambda", but that is a reserved word in Python.) Returned values range from 0 to positive infinity.

gammavariate(alpha, beta)

Gamma distribution. (*Not* the gamma function!) Conditions on the parameters are alpha > 0 and beta > 0.

gauss (mu, sigma)

Gaussian distribution. mu is the mean, and sigma is the standard deviation. This is slightly faster than the normalvariate() function defined below.

lognormvariate(mu, sigma)

Log normal distribution. If you take the natural logarithm of this distribution, you'll get a normal distribution with mean *mu* and standard deviation *sigma*. *mu* can have any value, and *sigma* must be greater than zero.

normalvariate(mu, sigma)

Normal distribution. mu is the mean, and sigma is the standard deviation.

vonmisesvariate(mu, kappa)

mu is the mean angle, expressed in radians between 0 and 2*pi, and kappa is the concentration parameter, which must be greater than or equal to zero. If kappa is equal to zero, this distribution reduces to a uniform random angle over the range 0 to 2*pi.

paretovariate(alpha)

Pareto distribution. alpha is the shape parameter.

weibullvariate(alpha, beta)

Weibull distribution. *alpha* is the scale parameter and *beta* is the shape parameter.

Alternative Generators

class WichmannHill([seed])

Class that implements the Wichmann-Hill algorithm as the core generator. Has all of the same methods as Random plus the whseed method described below. Because this class is implemented in pure Python, it is not threadsafe and may require locks between calls. The period of the generator is 6,953,607,871,644 which is small enough to require care that two independent random sequences do not overlap.

whseed([x])

This is obsolete, supplied for bit-level compatibility with versions of Python prior to 2.1. See seed for details. whseed does not guarantee that distinct integer arguments yield distinct internal states, and can yield no more than about 2**24 distinct internal states in all.

class SystemRandom([seed])

Class that uses the os.urandom() function for generating random numbers from sources provided by the operating system. Not available on all systems. Does not rely on software state and sequences are not reproducible. Accordingly, the seed() and jumpahead() methods have no effect and are ignored. The

getstate() and setstate() methods raise NotImplementedError if called. New in version 2.4.

See Also:

M. Matsumoto and T. Nishimura, "Mersenne Twister: A 623-dimensionally equidistributed uniform pseudorandom number generator", *ACM Transactions on Modeling and Computer Simulation* Vol. 8, No. 1, January pp.3-30 1998

Wichmann, B. A. & Hill, I. D., "Algorithm AS 183: An efficient and portable pseudo-random number generator", *Applied Statistics* 31 (1982) 188-190.

5.10 whrandom — Pseudo-random number generator

Deprecated since release 2.1. Use random instead.

Note: This module was an implementation detail of the <u>random</u> module in releases of Python prior to 2.1. It is no longer used. Please do not use this module directly; use <u>random</u> instead.

This module implements a Wichmann-Hill pseudo-random number generator class that is also named whrandom. Instances of the whrandom class conform to the Random Number Generator interface described in the docs for the random module. They also offer the following method, specific to the Wichmann-Hill algorithm:

```
seed([x, y, z])
```

Initializes the random number generator from the integers x, y and z. When the module is first imported, the random number is initialized using values derived from the current time. If x, y, and z are either omitted or 0, the seed will be computed from the current system time. If one or two of the parameters are 0, but not all three, the zero values are replaced by ones. This causes some apparently different seeds to be equal, with the corresponding result on the pseudo-random series produced by the generator.

Other supported methods include:

choice(seq)

Chooses a random element from the non-empty sequence seq and returns it.

randint(a, b)

Returns a random integer N such that a <= N <= b.

random()

Returns the next random floating point number in the range [0.0 ... 1.0).

```
seed(x, y, z)
```

Initializes the random number generator from the integers *x*, *y* and *z*. When the module is first imported, the random number is initialized using values derived from the current time.

uniform(a, b)

Returns a random real number N such that a <= N < b.

When imported, the whrandom module also creates an instance of the whrandom class, and makes the methods of that instance available at the module level. Therefore one can write either N = whrandom.random() or:

```
generator = whrandom.whrandom()
N = generator.random()
```

Note that using separate instances of the generator leads to independent sequences of pseudo-random numbers.

See Also:

Module random (section 5.9):

Generators for various random distributions and documentation for the Random Number Generator interface

Wichmann, B. A. & Hill, I. D., "Algorithm AS 183: An efficient and portable pseudo-random number generator", *Applied Statistics* 31 (1982) 188-190.

5.11 bisect — Array bisection algorithm

This module provides support for maintaining a list in sorted order without having to sort the list after each insertion. For long lists of items with expensive comparison operations, this can be an improvement over the more common approach. The module is called bisect because it uses a basic bisection algorithm to do its work. The source code may be most useful as a working example of the algorithm (the boundary conditions are already right!).

The following functions are provided:

```
bisect_left(list, item[, lo[, hi]])
```

Locate the proper insertion point for *item* in *list* to maintain sorted order. The parameters *lo* and *hi* may be used to specify a subset of the list which should be considered; by default the entire list is used. If *item* is already present in *list*, the insertion point will be before (to the left of) any existing entries. The return value is suitable for use as the first parameter to *list*.insert(). This assumes that *list* is already sorted. New in version 2.1.

```
bisect_right(list, item[, lo[, hi]])
```

Similar to bisect_left(), but returns an insertion point which comes after (to the right of) any existing entries of *item* in *list*. New in version 2.1.

```
bisect(...)
```

Alias for bisect_right().

```
insort\_left(list, item[, lo[, hi]])
```

Insert *item* in *list* in sorted order. This is equivalent to *list*.insert(bisect.bisect_left(*list*, *item*, *lo*, *hi*), *item*). This assumes that *list* is already sorted. New in version 2.1.

```
insort\_right(list, item[, lo[, hi]])
```

Similar to insort_left(), but inserting *item* in *list* after any existing entries of *item*. New in version 2.1.

```
insort(...)
```

Alias for insort_right().

5.11.1 Examples

The bisect() function is generally useful for categorizing numeric data. This example uses bisect() to look up a letter grade for an exam total (say) based on a set of ordered numeric breakpoints: 85 and up is an 'A', 75..84 is a 'B', etc.

```
>>> grades = "FEDCBA"
>>> breakpoints = [30, 44, 66, 75, 85]
>>> from bisect import bisect
>>> def grade(total):
... return grades[bisect(breakpoints, total)]
...
>>> grade(66)
'C'
>>> map(grade, [33, 99, 77, 44, 12, 88])
['E', 'A', 'B', 'D', 'F', 'A']
```

5.12 collections — High-performance container datatypes

New in version 2.4.

This module implements high-performance container datatypes. Currently, the only datatype is a deque. Future

additions may include B-trees and Fibonacci heaps.

deque([iterable])

Returns a new deque objected initialized left-to-right (using append()) with data from *iterable*. If *iterable* is not specified, the new deque is empty.

Deques are a generalization of stacks and queues (the name is pronounced "deck" and is short for "double-ended queue"). Deques support thread-safe, memory efficient appends and pops from either side of the deque with approximately the same O(1) performance in either direction.

Though list objects support similar operations, they are optimized for fast fixed-length operations and incur O(n) memory movement costs for 'pop(0)' and 'insert(0, v)' operations which change both the size and position of the underlying data representation. New in version 2.4.

Deque objects support the following methods:

append(x)

Add *x* to the right side of the deque.

appendleft(x)

Add *x* to the left side of the deque.

clear()

Remove all elements from the deque leaving it with length 0.

extend(iterable)

Extend the right side of the deque by appending elements from the iterable argument.

extendleft(iterable)

Extend the left side of the deque by appending elements from *iterable*. Note, the series of left appends results in reversing the order of elements in the iterable argument.

() gog

Remove and return an element from the right side of the deque. If no elements are present, raises a IndexError.

popleft()

Remove and return an element from the left side of the deque. If no elements are present, raises a IndexError.

rotate(n)

Rotate the deque n steps to the right. If n is negative, rotate to the left. Rotating one step to the right is equivalent to: 'd.appendleft(d.pop())'.

In addition to the above, deques support iteration, pickling, 'len(d)', 'reversed(d)', 'copy.copy(d)', 'copy.deepcopy(d)', membership testing with the in operator, and subscript references such as 'd[-1]'.

Example:

```
>>> from collections import deque
>>> d = deque('ghi')
                                      # make a new deque with three items
>>> for elem in d:
                                      # iterate over the deque's elements
       print elem.upper()
G
Η
Ι
>>> d.append('j')
                                      # add a new entry to the right side
                                      # add a new entry to the left side
>>> d.appendleft('f')
                                      # show the representation of the deque
deque(['f', 'g', 'h', 'i', 'j'])
>>> d.pop()
                                      # return and remove the rightmost item
′j′
>>> d.popleft()
                                      # return and remove the leftmost item
'f'
>>> list(d)
                                     # list the contents of the deque
['g', 'h', 'i']
>>> d[0]
                                      # peek at leftmost item
′g′
>>> d[-1]
                                      # peek at rightmost item
'i'
>>> list(reversed(d))
                                     # list the contents of a deque in reverse
['i', 'h', 'g']
>>> 'h' in d
                                     # search the deque
True
>>> d.extend('jkl')
                                     # add multiple elements at once
deque(['g', 'h', 'i', 'j', 'k', 'l'])
>>> d.rotate(1)
                                     # right rotation
deque(['l', 'g', 'h', 'i', 'j', 'k'])
>>> d.rotate(-1)
                                      # left rotation
deque(['g', 'h', 'i', 'j', 'k', 'l'])
>>> deque(reversed(d))
                                      # make a new deque in reverse order
deque(['l', 'k', 'j', 'i', 'h', 'g'])
>>> d.clear()
                                      # empty the deque
>>> d.pop()
                                      # cannot pop from an empty deque
Traceback (most recent call last):
 File "<pyshell#6>", line 1, in -toplevel-
    d.pop()
IndexError: pop from an empty deque
>>> d.extendleft('abc')
                                     # extendleft() reverses the input order
>>> d
deque(['c', 'b', 'a'])
```

5.12.1 Recipes

This section shows various approaches to working with deques.

The rotate() method provides a way to implement deque slicing and deletion. For example, a pure python implementation of del d[n] relies on the rotate() method to position elements to be popped:

```
def delete_nth(d, n):
    d.rotate(-n)
    d.popleft()
    d.rotate(n)
```

To implement deque slicing, use a similar approach applying rotate() to bring a target element to the left side of the deque. Remove old entries with popleft(), add new entries with extend(), and then reverse the rotation.

With minor variations on that approach, it is easy to implement Forth style stack manipulations such as dup, drop, swap, over, pick, rot, and roll.

A roundrobin task server can be built from a deque using popleft() to select the current task and append() to add it back to the tasklist if the input stream is not exhausted:

```
def roundrobin(*iterables):
    pending = deque(iter(i) for i in iterables)
    while pending:
        task = pending.popleft()
        try:
            yield task.next()
        except StopIteration:
            continue
        pending.append(task)
>>> for value in roundrobin('abc', 'd', 'efgh'):
        print value
d
6
b
f
С
q
h
```

Multi-pass data reduction algorithms can be succinctly expressed and efficiently coded by extracting elements with multiple calls to popleft(), applying the reduction function, and calling append() to add the result back to the queue.

For example, building a balanced binary tree of nested lists entails reducing two adjacent nodes into one by grouping them in a list:

```
def maketree(iterable):
    d = deque(iterable)
    while len(d) > 1:
        pair = [d.popleft(), d.popleft()]
        d.append(pair)
    return list(d)

>>> print maketree('abcdefgh')
[[[['a', 'b'], ['c', 'd']], [['e', 'f'], ['g', 'h']]]]
```

5.13 heapq — Heap queue algorithm

New in version 2.3.

This module provides an implementation of the heap queue algorithm, also known as the priority queue algorithm.

Heaps are arrays for which heap[k] <= heap[2*k+1] and heap[k] <= heap[2*k+2] for all k, counting elements from zero. For the sake of comparison, non-existing elements are considered to be infinite. The interesting property of a heap is that heap[0] is always its smallest element.

The API below differs from textbook heap algorithms in two aspects: (a) We use zero-based indexing. This makes the relationship between the index for a node and the indexes for its children slightly less obvious, but is more suitable since Python uses zero-based indexing. (b) Our pop method returns the smallest item, not the largest (called a "min heap" in textbooks; a "max heap" is more common in texts because of its suitability for in-place sorting).

These two make it possible to view the heap as a regular Python list without surprises: *heap*[0] is the smallest item, and *heap*.sort() maintains the heap invariant!

To create a heap, use a list initialized to [], or you can transform a populated list into a heap via function heapify().

The following functions are provided:

heappush(heap, item)

Push the value *item* onto the *heap*, maintaining the heap invariant.

heappop(heap)

Pop and return the smallest item from the *heap*, maintaining the heap invariant. If the heap is empty, IndexError is raised.

heapify(x)

Transform list *x* into a heap, in-place, in linear time.

heapreplace (heap, item)

Pop and return the smallest item from the *heap*, and also push the new *item*. The heap size doesn't change. If the heap is empty, IndexError is raised. This is more efficient than heappop() followed by heappush(), and can be more appropriate when using a fixed-size heap. Note that the value returned may be larger than *item*! That constrains reasonable uses of this routine unless written as part of a conditional replacement:

```
if item > heap[0]:
    item = heapreplace(heap, item)
```

Example of use:

```
>>> from heapq import heappush, heappop
>>> heap = []
>>> data = [1, 3, 5, 7, 9, 2, 4, 6, 8, 0]
>>> for item in data:
... heappush(heap, item)
...
>>> sorted = []
>>> while heap:
... sorted.append(heappop(heap))
...
>>> print sorted
[0, 1, 2, 3, 4, 5, 6, 7, 8, 9]
>>> data.sort()
>>> print data == sorted
True
>>>
```

The module also offers two general purpose functions based on heaps.

nlargest(n, iterable)

Return a list with the n largest elements from the dataset defined by *iterable*. Equivalent to: sorted(iterable, reverse=True)[:n] New in version 2.4.

nsmallest(n, iterable)

Return a list with the n smallest elements from the dataset defined by *iterable*. Equivalent to: sorted(iterable)[:n] New in version 2.4.


Both functions perform best for smaller values of n. For larger values, it is more efficient to use the sorted() function. Also, when n=1, it is more efficient to use the builtin min() and max() functions.

5.13.1 Theory

(This explanation is due to Franois Pinard. The Python code for this module was contributed by Kevin O'Connor.)

Heaps are arrays for which $a[k] \le a[2*k+1]$ and $a[k] \le a[2*k+2]$ for all k, counting elements from 0. For the sake of comparison, non-existing elements are considered to be infinite. The interesting property of a heap is that a[0] is always its smallest element.

The strange invariant above is meant to be an efficient memory representation for a tournament. The numbers below are k, not a [k]:



In the tree above, each cell k is topping 2*k+1 and 2*k+2. In an usual binary tournament we see in sports, each cell is the winner over the two cells it tops, and we can trace the winner down the tree to see all opponents s/he had. However, in many computer applications of such tournaments, we do not need to trace the history of a winner. To be more memory efficient, when a winner is promoted, we try to replace it by something else at a lower level, and the rule becomes that a cell and the two cells it tops contain three different items, but the top cell "wins" over the two topped cells.

If this heap invariant is protected at all time, index 0 is clearly the overall winner. The simplest algorithmic way to remove it and find the "next" winner is to move some loser (let's say cell 30 in the diagram above) into the 0 position, and then percolate this new 0 down the tree, exchanging values, until the invariant is re-established. This is clearly logarithmic on the total number of items in the tree. By iterating over all items, you get an O(n log n) sort

A nice feature of this sort is that you can efficiently insert new items while the sort is going on, provided that the inserted items are not "better" than the last 0'th element you extracted. This is especially useful in simulation contexts, where the tree holds all incoming events, and the "win" condition means the smallest scheduled time. When an event schedule other events for execution, they are scheduled into the future, so they can easily go into the heap. So, a heap is a good structure for implementing schedulers (this is what I used for my MIDI sequencer:-).

Various structures for implementing schedulers have been extensively studied, and heaps are good for this, as they are reasonably speedy, the speed is almost constant, and the worst case is not much different than the average case. However, there are other representations which are more efficient overall, yet the worst cases might be terrible.

Heaps are also very useful in big disk sorts. You most probably all know that a big sort implies producing "runs" (which are pre-sorted sequences, which size is usually related to the amount of CPU memory), followed by a merging passes for these runs, which merging is often very cleverly organised¹. It is very important that the initial sort produces the longest runs possible. Tournaments are a good way to that. If, using all the memory available to

¹The disk balancing algorithms which are current, nowadays, are more annoying than clever, and this is a consequence of the seeking

hold a tournament, you replace and percolate items that happen to fit the current run, you'll produce runs which are twice the size of the memory for random input, and much better for input fuzzily ordered.

Moreover, if you output the 0'th item on disk and get an input which may not fit in the current tournament (because the value "wins" over the last output value), it cannot fit in the heap, so the size of the heap decreases. The freed memory could be cleverly reused immediately for progressively building a second heap, which grows at exactly the same rate the first heap is melting. When the first heap completely vanishes, you switch heaps and start a new run. Clever and quite effective!

In a word, heaps are useful memory structures to know. I use them in a few applications, and I think it is good to keep a 'heap' module around. :-)

5.14 array — Efficient arrays of numeric values

This module defines an object type which can efficiently represent an array of basic values: characters, integers, floating point numbers. Arrays are sequence types and behave very much like lists, except that the type of objects stored in them is constrained. The type is specified at object creation time by using a *type code*, which is a single character. The following type codes are defined:

Type code	C Type	Python Type	Minimum size in bytes
′ C ′	char	character	1
'b'	signed char	int	1
'B'	unsigned char	int	1
'u'	Py_UNICODE	Unicode character	2
'h'	signed short	int	2
'H'	unsigned short	int	2
'i'	signed int	int	2
'I'	unsigned int	long	2
11'	signed long	int	4
'L'	unsigned long	long	4
'f'	float	float	4
'd'	double	float	8

The actual representation of values is determined by the machine architecture (strictly speaking, by the C implementation). The actual size can be accessed through the itemsize attribute. The values stored for 'L' and 'I' items will be represented as Python long integers when retrieved, because Python's plain integer type cannot represent the full range of C's unsigned (long) integers.

The module defines the following type:

array(typecode[, initializer])

Return a new array whose items are restricted by *typecode*, and initialized from the optional *initializer* value, which must be a list, string, or iterable over elements of the appropriate type. Changed in version 2.4: Formerly, only lists or strings were accepted. If given a list or string, the initializer is passed to the new array's fromlist(), fromstring(), or fromunicode() method (see below) to add initial items to the array. Otherwise, the iterable initializer is passed to the extend() method.

ArrayType

Obsolete alias for array.

Array objects support the ordinary sequence operations of indexing, slicing, concatenation, and multiplication. When using slice assignment, the assigned value must be an array object with the same type code; in all other cases, TypeError is raised. Array objects also implement the buffer interface, and may be used wherever buffer objects are supported.

The following data items and methods are also supported:

capabilities of the disks. On devices which cannot seek, like big tape drives, the story was quite different, and one had to be very clever to ensure (far in advance) that each tape movement will be the most effective possible (that is, will best participate at "progressing" the merge). Some tapes were even able to read backwards, and this was also used to avoid the rewinding time. Believe me, real good tape sorts were quite spectacular to watch! From all times, sorting has always been a Great Art!:-)

typecode

The typecode character used to create the array.

itemsize

The length in bytes of one array item in the internal representation.

append(x)

Append a new item with value x to the end of the array.

buffer_info()

Return a tuple (address, length) giving the current memory address and the length in elements of the buffer used to hold array's contents. The size of the memory buffer in bytes can be computed as array.buffer_info()[1] * array.itemsize. This is occasionally useful when working with low-level (and inherently unsafe) I/O interfaces that require memory addresses, such as certain ioctl() operations. The returned numbers are valid as long as the array exists and no length-changing operations are applied to it.

Note: When using array objects from code written in C or C++ (the only way to effectively make use of this information), it makes more sense to use the buffer interface supported by array objects. This method is maintained for backward compatibility and should be avoided in new code. The buffer interface is documented in the *Python/C API Reference Manual*.

byteswap()

"Byteswap" all items of the array. This is only supported for values which are 1, 2, 4, or 8 bytes in size; for other types of values, RuntimeError is raised. It is useful when reading data from a file written on a machine with a different byte order.

count(x)

Return the number of occurrences of x in the array.

extend(iterable)

Append items from *iterable* to the end of the array. If *iterable* is another array, it must have *exactly* the same type code; if not, TypeError will be raised. If *iterable* is not an array, it must be iterable and its elements must be the right type to be appended to the array. Changed in version 2.4: Formerly, the argument could only be another array.

fromfile(f, n)

Read n items (as machine values) from the file object f and append them to the end of the array. If less than n items are available, EOFError is raised, but the items that were available are still inserted into the array. f must be a real built-in file object; something else with a read () method won't do.

fromlist(list)

Append items from the list. This is equivalent to 'for x in list: a.append(x)' except that if there is a type error, the array is unchanged.

fromstring(s)

Appends items from the string, interpreting the string as an array of machine values (as if it had been read from a file using the fromfile() method).

fromunicode(s)

Extends this array with data from the given unicode string. The array must be a type 'u' array; otherwise a ValueError is raised. Use 'array.fromstring(ustr.decode(enc))' to append Unicode data to an array of some other type.

index(x)

Return the smallest i such that i is the index of the first occurrence of x in the array.

insert(i, x)

Insert a new item with value x in the array before position i. Negative values are treated as being relative to the end of the array.

pop([i])

Removes the item with the index i from the array and returns it. The optional argument defaults to -1, so that by default the last item is removed and returned.

read(f, n)

Deprecated since release 1.5.1. Use the fromfile() method.

Read n items (as machine values) from the file object f and append them to the end of the array. If less than n items are available, EOFError is raised, but the items that were available are still inserted into the array. f must be a real built-in file object; something else with a read () method won't do.

remove(x)

Remove the first occurrence of *x* from the array.

reverse()

Reverse the order of the items in the array.

tofile(f)

Write all items (as machine values) to the file object f.

tolist(

Convert the array to an ordinary list with the same items.

tostring()

Convert the array to an array of machine values and return the string representation (the same sequence of bytes that would be written to a file by the tofile() method.)

tounicode(

Convert the array to a unicode string. The array must be a type 'u' array; otherwise a ValueError is raised. Use array.tostring().decode(enc) to obtain a unicode string from an array of some other type.

write(f)

Deprecated since release 1.5.1. Use the tofile() method.

Write all items (as machine values) to the file object f.

When an array object is printed or converted to a string, it is represented as <code>array(typecode, initializer)</code>. The <code>initializer</code> is omitted if the array is empty, otherwise it is a string if the <code>typecode</code> is 'c', otherwise it is a list of numbers. The string is guaranteed to be able to be converted back to an array with the same type and value using reverse quotes (''), so long as the <code>array()</code> function has been imported using from <code>array import array</code>. Examples:

```
array('l')
array('c', 'hello world')
array('u', u'hello \textbackslash u2641')
array('l', [1, 2, 3, 4, 5])
array('d', [1.0, 2.0, 3.14])
```

See Also:

Module struct (section 4.3):

Packing and unpacking of heterogeneous binary data.

```
Module xdrlib (section 12.17):
```

Packing and unpacking of External Data Representation (XDR) data as used in some remote procedure call systems.

The Numerical Python Manual

(http://numpy.sourceforge.net/numdoc/HTML/numdoc.htm)

The Numeric Python extension (NumPy) defines another array type; see http://numpy.sourceforge.net/ for further information about Numerical Python. (A PDF version of the NumPy manual is available at http://numpy.sourceforge.net/numdoc/numdoc.pdf).

5.15 sets — Unordered collections of unique elements

New in version 2.3.

The sets module provides classes for constructing and manipulating unordered collections of unique elements.

Common uses include membership testing, removing duplicates from a sequence, and computing standard math operations on sets such as intersection, union, difference, and symmetric difference.

Like other collections, sets support x in set, len(set), and for x in set. Being an unordered collection, sets do not record element position or order of insertion. Accordingly, sets do not support indexing, slicing, or other sequence-like behavior.

Most set applications use the Set class which provides every set method except for __hash__(). For advanced applications requiring a hash method, the ImmutableSet class adds a __hash__() method but omits methods which alter the contents of the set. Both Set and ImmutableSet derive from BaseSet, an abstract class useful for determining whether something is a set: isinstance(obj, BaseSet).

The set classes are implemented using dictionaries. Accordingly, the requirements for set elements are the same as those for dictionary keys; namely, that the element defines both __eq__ and __hash__. As a result, sets cannot contain mutable elements such as lists or dictionaries. However, they can contain immutable collections such as tuples or instances of ImmutableSet. For convenience in implementing sets of sets, inner sets are automatically converted to immutable form, for example, Set([Set(['dog'])]) is transformed to Set([ImmutableSet(['dog'])]).

class Set([iterable])

Constructs a new empty Set object. If the optional *iterable* parameter is supplied, updates the set with elements obtained from iteration. All of the elements in *iterable* should be immutable or be transformable to an immutable using the protocol described in section 5.15.3.

class ImmutableSet([iterable])

Constructs a new empty ImmutableSet object. If the optional *iterable* parameter is supplied, updates the set with elements obtained from iteration. All of the elements in *iterable* should be immutable or be transformable to an immutable using the protocol described in section 5.15.3.

Because ImmutableSet objects provide a __hash__() method, they can be used as set elements or as dictionary keys. ImmutableSet objects do not have methods for adding or removing elements, so all of the elements must be known when the constructor is called.

5.15.1 Set Objects

Instances of Set and ImmutableSet both provide the following operations:

Operation	Equivalent	Result
len(s)		cardinality of set s
x in s		test x for membership in s
x not in s		test x for non-membership in s
s.issubset(t)	$s \ll t$	test whether every element in s is in t
s.issuperset (t)	s >= t	test whether every element in t is in s
s.union(t)	s t	new set with elements from both s and t
s.intersection(t)	s & t	new set with elements common to s and t
s.difference(t)	s - t	new set with elements in s but not in t
$s.\mathtt{symmetric_difference}(t)$	s ^ t	new set with elements in either <i>s</i> or <i>t</i> but not both
$s.\mathtt{copy}(\)$		new set with a shallow copy of s

Note, the non-operator versions of union(), intersection(), difference(), and symmetric_difference() will accept any iterable as an argument. In contrast, their operator based counterparts require their arguments to be sets. This precludes error-prone constructions like Set('abc') & 'cbs' in favor of the more readable Set('abc').intersection('cbs'). Changed in version 2.3.1: Formerly all arguments were required to be sets.

In addition, both Set and ImmutableSet support set to set comparisons. Two sets are equal if and only if every element of each set is contained in the other (each is a subset of the other). A set is less than another set if and only if the first set is a proper subset of the second set (is a subset, but is not equal). A set is greater than another set if and only if the first set is a proper superset of the second set (is a superset, but is not equal).

The subset and equality comparisons do not generalize to a complete ordering function. For example, any two disjoint sets are not equal and are not subsets of each other, so *all* of the following return False: a < b, a == b, or

a>b. Accordingly, sets do not implement the __cmp__ method.

Since sets only define partial ordering (subset relationships), the output of the list.sort() method is undefined for lists of sets.

The following table lists operations available in ImmutableSet but not found in Set:

Operation	Result	
hash(s)	returns a hash value for s	

The following table lists operations available in Set but not found in ImmutableSet:

	Operation	Equivalent	Result
	s.update(t)	$s \mid = t$	return set s with elements added from t
	<pre>s.intersection_update(t)</pre>	s &= t	return set s keeping only elements also found in t
	$s.difference_update(t)$	s = t	return set s after removing elements found in t
	<pre>s.symmetric_difference_update(t)</pre>	s = t	return set s with elements from s or t but not both
	s.add(x)		add element x to set s
s.remove(x)			remove x from set s; raises KeyError if not present
s.discard(x)			removes x from set s if present
	s.pop()		remove and return an arbitrary element from s; raises KeyError if
	$s.\mathtt{clear}()$		remove all elements from set s

Note, the non-operator versions of update(), intersection_update(), difference_update(), and symmetric_difference_update() will accept any iterable as an argument. Changed in version 2.3.1: Formerly all arguments were required to be sets.

Also note, the module also includes a union_update() method which is an alias for update(). The method is included for backwards compatibility. Programmers should prefer the update() method because it the one supported by the builtin set() and frozenset() types.

5.15.2 Example

```
>>> from sets import Set
>>> engineers = Set(['John', 'Jane', 'Jack', 'Janice'])
>>> programmers = Set(['Jack', 'Sam', 'Susan', 'Janice'])
>>> managers = Set(['Jane', 'Jack', 'Susan', 'Zack'])
>>> employees = engineers | programmers | managers
                                                            # union
>>> engineering_management = engineers & managers
                                                            # intersection
>>> fulltime_management = managers - engineers - programmers # difference
>>> engineers.add('Marvin')
                                                            # add element
>>> print engineers
Set(['Jane', 'Marvin', 'Janice', 'John', 'Jack'])
>>> employees.issuperset(engineers)
                                            # superset test
>>> employees.union_update(engineers)
                                             # update from another set
>>> employees.issuperset(engineers)
>>> for group in [engineers, programmers, managers, employees]:
... group.discard('Susan')
                                         # unconditionally remove element
       print group
Set(['Jane', 'Marvin', 'Janice', 'John', 'Jack'])
Set(['Janice', 'Jack', 'Sam'])
Set(['Jane', 'Zack', 'Jack'])
Set(['Jack', 'Sam', 'Jane', 'Marvin', 'Janice', 'John', 'Zack'])
```

5.15.3 Protocol for automatic conversion to immutable

Sets can only contain immutable elements. For convenience, mutable Set objects are automatically copied to an ImmutableSet before being added as a set element.

The mechanism is to always add a hashable element, or if it is not hashable, the element is checked to see if it has an __as_immutable__() method which returns an immutable equivalent.

Since Set objects have a __as_immutable__() method returning an instance of ImmutableSet, it is possible to construct sets of sets.

A similar mechanism is needed by the __contains__() and remove() methods which need to hash an element to check for membership in a set. Those methods check an element for hashability and, if not, check for a __as_temporarily_immutable__() method which returns the element wrapped by a class that provides temporary methods for __hash__(), __eq__(), and __ne__().

The alternate mechanism spares the need to build a separate copy of the original mutable object.

Set objects implement the __as_temporarily_immutable__() method which returns the Set object wrapped by a new class _TemporarilyImmutableSet.

The two mechanisms for adding hashability are normally invisible to the user; however, a conflict can arise in a multi-threaded environment where one thread is updating a set while another has temporarily wrapped it in _TemporarilyImmutableSet. In other words, sets of mutable sets are not thread-safe.

5.15.4 Comparison to the built-in set types

The built-in set and frozenset types were designed based on lessons learned from the sets module. The key differences are:

- Set and ImmutableSet were renamed to set and frozenset.
- There is no equivalent to BaseSet. Instead, use isinstance(x, (set, frozenset)).
- The hash algorithm for the built-ins performs significantly better (fewer collisions) for most datasets.
- The built-in versions have more space efficient pickles.
- The built-in versions do not have a union_update() method. Instead, use the update() method which is equivalent.
- The built-in versions do not have a _repr(sort=True) method. Instead, use the built-in repr() and sorted() functions: repr(sorted(s)).
- The built-in version does not have a protocol for automatic conversion to immutable. Many found this feature to be confusing and no one in the community reported having found real uses for it.

5.16 itertools — Functions creating iterators for efficient looping

New in version 2.3.

This module implements a number of iterator building blocks inspired by constructs from the Haskell and SML programming languages. Each has been recast in a form suitable for Python.

The module standardizes a core set of fast, memory efficient tools that are useful by themselves or in combination. Standardization helps avoid the readability and reliability problems which arise when many different individuals create their own slightly varying implementations, each with their own quirks and naming conventions.

The tools are designed to combine readily with one another. This makes it easy to construct more specialized tools succinctly and efficiently in pure Python.

For instance, SML provides a tabulation tool: tabulate(f) which produces a sequence f(0), f(1), This toolbox provides imap() and count() which can be combined to form imap(f, count()) and produce an equivalent result.

Likewise, the functional tools are designed to work well with the high-speed functions provided by the operator module.

The module author welcomes suggestions for other basic building blocks to be added to future versions of the module.

Whether cast in pure python form or compiled code, tools that use iterators are more memory efficient (and faster) than their list based counterparts. Adopting the principles of just-in-time manufacturing, they create data when and where needed instead of consuming memory with the computer equivalent of "inventory".

The performance advantage of iterators becomes more acute as the number of elements increases – at some point, lists grow large enough to severely impact memory cache performance and start running slowly.

See Also:

The Standard ML Basis Library, The Standard ML Basis Library.

Haskell, A Purely Functional Language, Definition of Haskell and the Standard Libraries.

5.16.1 Itertool functions

The following module functions all construct and return iterators. Some provide streams of infinite length, so they should only be accessed by functions or loops that truncate the stream.

```
chain(*iterables)
```

Make an iterator that returns elements from the first iterable until it is exhausted, then proceeds to the next iterable, until all of the iterables are exhausted. Used for treating consecutive sequences as a single sequence. Equivalent to:

```
def chain(*iterables):
    for it in iterables:
        for element in it:
        yield element
```

count([n])

Make an iterator that returns consecutive integers starting with n. If not specified n defaults to zero. Does not currently support python long integers. Often used as an argument to imap() to generate consecutive data points. Also, used with izip() to add sequence numbers. Equivalent to:

```
def count(n=0):
    while True:
        yield n
        n += 1
```

Note, count() does not check for overflow and will return negative numbers after exceeding sys.maxint. This behavior may change in the future.

cycle(iterable)

Make an iterator returning elements from the iterable and saving a copy of each. When the iterable is exhausted, return elements from the saved copy. Repeats indefinitely. Equivalent to:

```
def cycle(iterable):
    saved = []
    for element in iterable:
        yield element
        saved.append(element)
    while saved:
        for element in saved:
            yield element
```

Note, this member of the toolkit may require significant auxiliary storage (depending on the length of the iterable).

dropwhile(predicate, iterable)

Make an iterator that drops elements from the iterable as long as the predicate is true; afterwards, returns every element. Note, the iterator does not produce *any* output until the predicate is true, so it may have a lengthy start-up time. Equivalent to:

```
def dropwhile(predicate, iterable):
   iterable = iter(iterable)
   for x in iterable:
       if not predicate(x):
            yield x
            break
   for x in iterable:
            yield x
```

groupby(iterable[, key])

Make an iterator that returns consecutive keys and groups from the *iterable*. The *key* is a function computing a key value for each element. If not specified or is None, *key* defaults to an identity function and returns the element unchanged. Generally, the iterable needs to already be sorted on the same key function.

The returned group is itself an iterator that shares the underlying iterable with <code>groupby()</code>. Because the source is shared, when the <code>groupby</code> object is advanced, the previous group is no longer visible. So, if that data is needed later, it should be stored as a list:

```
groups = []
uniquekeys = []
for k, g in groupby(data, keyfunc):
    groups.append(list(g))  # Store group iterator as a list
    uniquekeys.append(k)
```

groupby() is equivalent to:

```
class groupby(object):
   def __init__(self, iterable, key=None):
        if key is None:
           key = lambda x: x
        self.keyfunc = key
        self.it = iter(iterable)
        self.tgtkey = self.currkey = self.currvalue = xrange(0)
   def __iter__(self):
       return self
   def next(self):
       while self.currkey == self.tgtkey:
            self.currvalue = self.it.next() # Exit on StopIteration
            self.currkey = self.keyfunc(self.currvalue)
        self.tgtkey = self.currkey
       return (self.currkey, self._grouper(self.tgtkey))
   def _grouper(self, tgtkey):
        while self.currkey == tgtkey:
            yield self.currvalue
            self.currvalue = self.it.next() # Exit on StopIteration
            self.currkey = self.keyfunc(self.currvalue)
```

New in version 2.4.

ifilter(predicate, iterable)

Make an iterator that filters elements from iterable returning only those for which the predicate is True. If *predicate* is None, return the items that are true. Equivalent to:

```
def ifilter(predicate, iterable):
    if predicate is None:
        predicate = bool
    for x in iterable:
        if predicate(x):
            yield x
```

$\verb|ifilterfalse|| (\textit{predicate, iterable}|)$

Make an iterator that filters elements from iterable returning only those for which the predicate is False. If *predicate* is None, return the items that are false. Equivalent to:

```
def ifilterfalse(predicate, iterable):
    if predicate is None:
        predicate = bool
    for x in iterable:
        if not predicate(x):
            yield x
```

imap(function, *iterables)

Make an iterator that computes the function using arguments from each of the iterables. If *function* is set to None, then imap() returns the arguments as a tuple. Like map() but stops when the shortest iterable is exhausted instead of filling in None for shorter iterables. The reason for the difference is that infinite iterator arguments are typically an error for map() (because the output is fully evaluated) but represent a common and useful way of supplying arguments to imap(). Equivalent to:

```
def imap(function, *iterables):
   iterables = map(iter, iterables)
   while True:
       args = [i.next() for i in iterables]
       if function is None:
           yield tuple(args)
       else:
           yield function(*args)
```

islice(iterable, [start,] stop [, step])

Make an iterator that returns selected elements from the iterable. If *start* is non-zero, then elements from the iterable are skipped until start is reached. Afterward, elements are returned consecutively unless *step* is set higher than one which results in items being skipped. If *stop* is None, then iteration continues until the iterator is exhausted, if at all; otherwise, it stops at the specified position. Unlike regular slicing, <code>islice()</code> does not support negative values for *start*, *stop*, or *step*. Can be used to extract related fields from data where the internal structure has been flattened (for example, a multi-line report may list a name field on every third line). Equivalent to:

```
def islice(iterable, *args):
    s = slice(*args)
    it = iter(xrange(s.start or 0, s.stop or sys.maxint, s.step or 1))
    nexti = it.next()
    for i, element in enumerate(iterable):
        if i == nexti:
            yield element
            nexti = it.next()
```

izip(*iterables)

Make an iterator that aggregates elements from each of the iterables. Like zip() except that it returns an iterator instead of a list. Used for lock-step iteration over several iterables at a time. Equivalent to:

```
def izip(*iterables):
    iterables = map(iter, iterables)
    while iterables:
        result = [i.next() for i in iterables]
        yield tuple(result)
```

Changed in version 2.4: When no iterables are specified, returns a zero length iterator instead of raising a TypeError exception.

repeat(object[, times])

Make an iterator that returns *object* over and over again. Runs indefinitely unless the *times* argument is specified. Used as argument to imap() for invariant parameters to the called function. Also used with izip() to create an invariant part of a tuple record. Equivalent to:

```
def repeat(object, times=None):
    if times is None:
        while True:
            yield object
    else:
        for i in xrange(times):
            yield object
```

starmap(function, iterable)

Make an iterator that computes the function using arguments tuples obtained from the iterable. Used instead of imap() when argument parameters are already grouped in tuples from a single iterable (the data has

been "pre-zipped"). The difference between imap() and starmap() parallels the distinction between function(a,b) and function(*c). Equivalent to:

```
def starmap(function, iterable):
   iterable = iter(iterable)
   while True:
        yield function(*iterable.next())
```

takewhile(predicate, iterable)

Make an iterator that returns elements from the iterable as long as the predicate is true. Equivalent to:

```
def takewhile(predicate, iterable):
    for x in iterable:
        if predicate(x):
            yield x
        else:
            break
```

tee(iterable[, n=2])

Return n independent iterators from a single iterable. The case where n==2 is equivalent to:

```
def tee(iterable):
    def gen(next, data={}, cnt=[0]):
        for i in count():
        if i == cnt[0]:
            item = data[i] = next()
            cnt[0] += 1
        else:
            item = data.pop(i)
            yield item
    it = iter(iterable)
    return (gen(it.next), gen(it.next))
```

Note, once tee() has made a split, the original *iterable* should not be used anywhere else; otherwise, the *iterable* could get advanced without the tee objects being informed.

Note, this member of the toolkit may require significant auxiliary storage (depending on how much temporary data needs to be stored). In general, if one iterator is going to use most or all of the data before the other iterator, it is faster to use list() instead of tee(). New in version 2.4.

5.16.2 Examples

The following examples show common uses for each tool and demonstrate ways they can be combined.

```
>>> amounts = [120.15, 764.05, 823.14]
>>> for checknum, amount in izip(count(1200), amounts):
        print 'Check %d is for $%.2f' % (checknum, amount)
Check 1200 is for $120.15
Check 1201 is for $764.05
Check 1202 is for $823.14
>>> import operator
>>> for cube in imap(operator.pow, xrange(1,5), repeat(3)):
       print cube
. . .
1
8
2.7
64
>>> reportlines = ['EuroPython', 'Roster', '', 'alex', '', 'laura', '', 'martin', '', 'walter', '', 'mark']
>>> for name in islice(reportlines, 3, None, 2):
      print name.title()
. . .
. . .
Alex
Laura
Martin
Walter
Mark
# Show a dictionary sorted and grouped by value
>>> from operator import itemgetter
>>> d = dict(a=1, b=2, c=1, d=2, e=1, f=2, g=3)
>>> di = sorted(d.iteritems(), key=itemgetter(1))
>>> for k, g in groupby(di, key=itemgetter(1)):
        print k, map(itemgetter(0), g)
1 ['a', 'c', 'e']
2 ['b', 'd', 'f']
3 ['g']
# Find runs of consecutive numbers using groupby. The key to the solution
# is differencing with a range so that consecutive numbers all appear in
# same group.
>>> data = [ 1, 4,5,6, 10, 15,16,17,18, 22, 25,26,27,28]
>>> for k, g in groupby(enumerate(data), lambda (i,x):i-x):
        print map(operator.itemgetter(1), g)
. . .
[1]
[4, 5, 6]
[10]
[15, 16, 17, 18]
[22]
[25, 26, 27, 28]
```

5.16.3 Recipes

This section shows recipes for creating an extended toolset using the existing itertools as building blocks.

The extended tools offer the same high performance as the underlying toolset. The superior memory performance

is kept by processing elements one at a time rather than bringing the whole iterable into memory all at once. Code volume is kept small by linking the tools together in a functional style which helps eliminate temporary variables. High speed is retained by preferring "vectorized" building blocks over the use of for-loops and generators which incur interpreter overhead.

```
def take(n, seq):
    return list(islice(seq, n))
def enumerate(iterable):
    return izip(count(), iterable)
def tabulate(function):
    "Return function(0), function(1), ..."
    return imap(function, count())
def iteritems(mapping):
    return izip(mapping.iterkeys(), mapping.itervalues())
def nth(iterable, n):
    "Returns the nth item"
    return list(islice(iterable, n, n+1))
def all(seq, pred=bool):
    "Returns True if pred(x) is True for every element in the iterable"
    for elem in ifilterfalse(pred, seq):
        return False
    return True
def any(seq, pred=bool):
    "Returns True if pred(x) is True for at least one element in the iterable"
    for elem in ifilter(pred, seq):
        return True
    return False
def no(seq, pred=bool):
    "Returns True if pred(x) is False for every element in the iterable"
    for elem in ifilter(pred, seq):
       return False
    return True
def quantify(seq, pred=bool):
    "Count how many times the predicate is True in the sequence"
    return sum(imap(pred, seq))
def padnone(seq):
    """Returns the sequence elements and then returns None indefinitely.
    Useful for emulating the behavior of the built-in map() function.
    return chain(seq, repeat(None))
def ncycles(seq, n):
    "Returns the sequence elements n times"
    return chain(*repeat(seq, n))
def dotproduct(vec1, vec2):
    return sum(imap(operator.mul, vec1, vec2))
def flatten(listOfLists):
    return list(chain(*listOfLists))
def repeatfunc(func, times=None, *args):
    """Repeat calls to func with specified arguments.
    Example: repeatfunc(random.random)
    if times is None:
       return starmap(func, repeat(args))
```

5.17 ConfigParser — Configuration file parser

This module defines the class ConfigParser. The ConfigParser class implements a basic configuration file parser language which provides a structure similar to what you would find on Microsoft Windows INI files. You can use this to write Python programs which can be customized by end users easily.

Warning: This library does *not* interpret or write the value-type prefixes used in the Windows Registry extended version of INI syntax.

The configuration file consists of sections, led by a '[section]' header and followed by 'name: value' entries, with continuations in the style of RFC 822; 'name=value' is also accepted. Note that leading whitespace is removed from values. The optional values can contain format strings which refer to other values in the same section, or values in a special DEFAULT section. Additional defaults can be provided on initialization and retrieval. Lines beginning with '#' or ';' are ignored and may be used to provide comments.

For example:

```
[My Section]
foodir: %(dir)s/whatever
dir=frob
```

would resolve the '%(dir)s' to the value of 'dir' ('frob' in this case). All reference expansions are done on demand.

Default values can be specified by passing them into the ConfigParser constructor as a dictionary. Additional defaults may be passed into the get () method which will override all others.

class RawConfigParser([defaults])

The basic configuration object. When *defaults* is given, it is initialized into the dictionary of intrinsic defaults. This class does not support the magical interpolation behavior. New in version 2.3.

class ConfigParser([defaults])

Derived class of RawConfigParser that implements the magical interpolation feature and adds optional arguments to the get() and items() methods. The values in *defaults* must be appropriate for the '%()s' string interpolation. Note that __name__ is an intrinsic default; its value is the section name, and will override any value provided in *defaults*.

All option names used in interpolation will be passed through the optionxform() method just like any other option name reference. For example, using the default implementation of optionxform() (which converts option names to lower case), the values 'foo %(bar)s' and 'foo %(BAR)s' are equivalent.

class SafeConfigParser([defaults])

Derived class of ConfigParser that implements a more-sane variant of the magical interpolation feature. This implementation is more predictable as well. New applications should prefer this version if they don't need to be compatible with older versions of Python. New in version 2.3.

exception NoSectionError

Exception raised when a specified section is not found.

exception DuplicateSectionError

Exception raised if add_section() is called with the name of a section that is already present.

exception NoOptionError

Exception raised when a specified option is not found in the specified section.

exception InterpolationError

Base class for exceptions raised when problems occur performing string interpolation.

exception InterpolationDepthError

Exception raised when string interpolation cannot be completed because the number of iterations exceeds MAX_INTERPOLATION_DEPTH. Subclass of InterpolationError.

exception InterpolationMissingOptionError

Exception raised when an option referenced from a value does not exist. Subclass of InterpolationError. New in version 2.3.

exception InterpolationSyntaxError

Exception raised when the source text into which substitutions are made does not conform to the required syntax. Subclass of InterpolationError. New in version 2.3.

exception MissingSectionHeaderError

Exception raised when attempting to parse a file which has no section headers.

exception ParsingError

Exception raised when errors occur attempting to parse a file.

MAX_INTERPOLATION_DEPTH

The maximum depth for recursive interpolation for get () when the *raw* parameter is false. This is relevant only for the ConfigParser class.

See Also:

Module shlex (section 5.21):

Support for a creating UNIX shell-like mini-languages which can be used as an alternate format for application configuration files.

5.17.1 RawConfigParser Objects

RawConfigParser instances have the following methods:

defaults()

Return a dictionary containing the instance-wide defaults.

sections()

Return a list of the sections available; DEFAULT is not included in the list.

add_section(section)

Add a section named *section* to the instance. If a section by the given name already exists, DuplicateSectionError is raised.

has_section(section)

Indicates whether the named section is present in the configuration. The DEFAULT section is not acknowledged.

options(section)

Returns a list of options available in the specified section.

has_option(section, option)

If the given section exists, and contains the given option, return True; otherwise return False. New in version 1.6.

read(filenames)

Attempt to read and parse a list of filenames, returning a list of filenames which were successfully parsed. If *filenames* is a string or Unicode string, it is treated as a single filename. If a file named in *filenames* cannot be opened, that file will be ignored. This is designed so that you can specify a list of potential configuration file locations (for example, the current directory, the user's home directory, and some system-wide directory), and all existing configuration files in the list will be read. If none of the named files exist, the ConfigParser instance will contain an empty dataset. An application which requires initial values to be loaded from a file should load the required file or files using readfp() before calling read() for any optional files:

```
import ConfigParser, os

config = ConfigParser.ConfigParser()
config.readfp(open('defaults.cfg'))
config.read(['site.cfg', os.path.expanduser('~/.myapp.cfg')])
```

Changed in version 2.4: Returns list of successfully parsed filenames.

readfp(fp[, filename])

Read and parse configuration data from the file or file-like object in *fp* (only the readline() method is used). If *filename* is omitted and *fp* has a name attribute, that is used for *filename*; the default is '<???>'.

get(section, option)

Get an option value for the named section.

getint(section, option)

A convenience method which coerces the option in the specified section to an integer.

getfloat(section, option)

A convenience method which coerces the option in the specified section to a floating point number.

getboolean(section, option)

A convenience method which coerces the *option* in the specified *section* to a Boolean value. Note that the accepted values for the option are "1", "yes", "true", and "on", which cause this method to return True, and "0", "no", "false", and "off", which cause it to return False. These string values are checked in a case-insensitive manner. Any other value will cause it to raise ValueError.

items(section)

Return a list of (name, value) pairs for each option in the given section.

set(section, option, value)

If the given section exists, set the given option to the specified value; otherwise raise NoSectionError. While it is possible to use RawConfigParser (or ConfigParser with *raw* parameters set to true) for *internal* storage of non-string values, full functionality (including interpolation and output to files) can only be achieved using string values. New in version 1.6.

write(fileobject)

Write a representation of the configuration to the specified file object. This representation can be parsed by a future read() call. New in version 1.6.

remove_option(section, option)

Remove the specified *option* from the specified *section*. If the section does not exist, raise NoSectionError. If the option existed to be removed, return True; otherwise return False. New in version 1.6.

remove_section(section)

Remove the specified *section* from the configuration. If the section in fact existed, return True. Otherwise return False.

optionxform(option)

Transforms the option name *option* as found in an input file or as passed in by client code to the form that should be used in the internal structures. The default implementation returns a lower-case version of *option*; subclasses may override this or client code can set an attribute of this name on instances to affect this behavior. Setting this to str(), for example, would make option names case sensitive.

5.17.2 ConfigParser Objects

The ConfigParser class extends some methods of the RawConfigParser interface, adding some optional arguments.

```
get(section, option[, raw[, vars]])
```

Get an *option* value for the named *section*. All the '%' interpolations are expanded in the return values, based on the defaults passed into the constructor, as well as the options *vars* provided, unless the *raw* argument is

true.

```
items(section[, raw[, vars]])
```

Return a list of (*name*, *value*) pairs for each option in the given *section*. Optional arguments have the same meaning as for the get () method. New in version 2.3.

5.17.3 SafeConfigParser Objects

The SafeConfigParser class implements the same extended interface as ConfigParser, with the following addition:

```
set(section, option, value)
```

If the given section exists, set the given option to the specified value; otherwise raise NoSectionError. *value* must be a string (str or unicode); if not, TypeError is raised. New in version 2.4.

5.18 fileinput — Iterate over lines from multiple input streams

This module implements a helper class and functions to quickly write a loop over standard input or a list of files.

The typical use is:

```
import fileinput
for line in fileinput.input():
    process(line)
```

This iterates over the lines of all files listed in sys.argv[1:], defaulting to sys.stdin if the list is empty. If a filename is '-', it is also replaced by sys.stdin. To specify an alternative list of filenames, pass it as the first argument to input(). A single file name is also allowed.

All files are opened in text mode. If an I/O error occurs during opening or reading a file, IOError is raised.

If sys.stdin is used more than once, the second and further use will return no lines, except perhaps for interactive use, or if it has been explicitly reset (e.g. using sys.stdin.seek(0)).

Empty files are opened and immediately closed; the only time their presence in the list of filenames is noticeable at all is when the last file opened is empty.

It is possible that the last line of a file does not end in a newline character; lines are returned including the trailing newline when it is present.

The following function is the primary interface of this module:

```
input([files[, inplace[, backup]]])
```

Create an instance of the FileInput class. The instance will be used as global state for the functions of this module, and is also returned to use during iteration. The parameters to this function will be passed along to the constructor of the FileInput class.

The following functions use the global state created by input(); if there is no active state, RuntimeError is raised.

filename()

Return the name of the file currently being read. Before the first line has been read, returns None.

lineno(

Return the cumulative line number of the line that has just been read. Before the first line has been read, returns 0. After the last line of the last file has been read, returns the line number of that line.

filelineno()

Return the line number in the current file. Before the first line has been read, returns 0. After the last line of the last file has been read, returns the line number of that line within the file.

isfirstline()

Returns true if the line just read is the first line of its file, otherwise returns false.

isstdin()

Returns true if the last line was read from sys.stdin, otherwise returns false.

nextfile()

Close the current file so that the next iteration will read the first line from the next file (if any); lines not read from the file will not count towards the cumulative line count. The filename is not changed until after the first line of the next file has been read. Before the first line has been read, this function has no effect; it cannot be used to skip the first file. After the last line of the last file has been read, this function has no effect.

close()

Close the sequence.

The class which implements the sequence behavior provided by the module is available for subclassing as well:

class FileInput([files[, inplace[, backup]]])

Class FileInput is the implementation; its methods filename(), lineno(), fileline(), isfirstline(), isstdin(), nextfile() and close() correspond to the functions of the same name in the module. In addition it has a readline() method which returns the next input line, and a __getitem__() method which implements the sequence behavior. The sequence must be accessed in strictly sequential order; random access and readline() cannot be mixed.

Optional in-place filtering: if the keyword argument *inplace*=1 is passed to input() or to the FileInput constructor, the file is moved to a backup file and standard output is directed to the input file (if a file of the same name as the backup file already exists, it will be replaced silently). This makes it possible to write a filter that rewrites its input file in place. If the keyword argument backup='. <some extension>' is also given, it specifies the extension for the backup file, and the backup file remains around; by default, the extension is '.bak' and it is deleted when the output file is closed. In-place filtering is disabled when standard input is read.

Caveat: The current implementation does not work for MS-DOS 8+3 filesystems.

5.19 calendar — General calendar-related functions

This module allows you to output calendars like the UNIX **cal** program, and provides additional useful functions related to the calendar. By default, these calendars have Monday as the first day of the week, and Sunday as the last (the European convention). Use setfirstweekday() to set the first day of the week to Sunday (6) or to any other weekday. Parameters that specify dates are given as integers.

Most of these functions rely on the datetime module which uses an idealized calendar, the current Gregorian calendar indefinitely extended in both directions. This matches the definition of the "proleptic Gregorian" calendar in Dershowitz and Reingold's book "Calendrical Calculations", where it's the base calendar for all computations.

setfirstweekday(weekday)

Sets the weekday (0 is Monday, 6 is Sunday) to start each week. The values MONDAY, TUESDAY, WEDNESDAY, THURSDAY, FRIDAY, SATURDAY, and SUNDAY are provided for convenience. For example, to set the first weekday to Sunday:

```
import calendar
calendar.setfirstweekday(calendar.SUNDAY)
```

New in version 2.0.

firstweekday()

Returns the current setting for the weekday to start each week. New in version 2.0.

isleap(year)

Returns True if year is a leap year, otherwise False.

leapdays(y1, y2)

Returns the number of leap years in the range [y1...y2), where y1 and y2 are years. Changed in version 2.0: This function didn't work for ranges spanning a century change in Python 1.5.2.

weekday (year, month, day)

Returns the day of the week (0 is Monday) for year (1970-...), month (1-12), day (1-31).

weekheader(n)

Return a header containing abbreviated weekday names. n specifies the width in characters for one weekday.

monthrange(year, month)

Returns weekday of first day of the month and number of days in month, for the specified year and month.

monthcalendar(year, month)

Returns a matrix representing a month's calendar. Each row represents a week; days outside of the month a represented by zeros. Each week begins with Monday unless set by setfirstweekday().

prmonth(theyear, themonth[, w[, l]])

Prints a month's calendar as returned by month().

```
month(theyear, themonth[, w[, l]])
```

Returns a month's calendar in a multi-line string. If w is provided, it specifies the width of the date columns, which are centered. If l is given, it specifies the number of lines that each week will use. Depends on the first weekday as set by setfirstweekday(). New in version 2.0.

prcal(year[, w[, l[c]]))

Prints the calendar for an entire year as returned by calendar ().

calendar(year[, w[, l[c]]))

Returns a 3-column calendar for an entire year as a multi-line string. Optional parameters w, l, and c are for date column width, lines per week, and number of spaces between month columns, respectively. Depends on the first weekday as set by setfirstweekday(). The earliest year for which a calendar can be generated is platform-dependent. New in version 2.0.

timegm(tuple)

An unrelated but handy function that takes a time tuple such as returned by the gmtime() function in the time module, and returns the corresponding UNIX timestamp value, assuming an epoch of 1970, and the POSIX encoding. In fact, time.gmtime() and timegm() are each others' inverse. New in version 2.0.

See Also:

Module datetime (section 6.10):

Object-oriented interface to dates and times with similar functionality to the time module.

Module time (section 6.11):

Low-level time related functions.

5.20 cmd — Support for line-oriented command interpreters

The Cmd class provides a simple framework for writing line-oriented command interpreters. These are often useful for test harnesses, administrative tools, and prototypes that will later be wrapped in a more sophisticated interface.

```
class Cmd ([completekey[, stdin[, stdout]]])
```

A Cmd instance or subclass instance is a line-oriented interpreter framework. There is no good reason to instantiate Cmd itself; rather, it's useful as a superclass of an interpreter class you define yourself in order to inherit Cmd's methods and encapsulate action methods.

The optional argument *completekey* is the readline name of a completion key; it defaults to Tab. If *completekey* is not None and readline is available, command completion is done automatically.

The optional arguments *stdin* and *stdout* specify the input and output file objects that the Cmd instance or subclass instance will use for input and output. If not specified, they will default to *sys.stdin* and *sys.stdout*.

Changed in version 2.3: The stdin and stdout parameters were added...

5.20.1 Cmd Objects

A Cmd instance has the following methods:

cmdloop([intro])

Repeatedly issue a prompt, accept input, parse an initial prefix off the received input, and dispatch to action methods, passing them the remainder of the line as argument.

The optional argument is a banner or intro string to be issued before the first prompt (this overrides the intro class member).

If the readline module is loaded, input will automatically inherit bash-like history-list editing (e.g. Control-P scrolls back to the last command, Control-N forward to the next one, Control-F moves the cursor to the right non-destructively, Control-B moves the cursor to the left non-destructively, etc.).

An end-of-file on input is passed back as the string 'EOF'.

An interpreter instance will recognize a command name 'foo' if and only if it has a method do_foo(). As a special case, a line beginning with the character '?' is dispatched to the method do_help(). As another special case, a line beginning with the character '!' is dispatched to the method do_shell() (if such a method is defined).

This method will return when the postcmd() method returns a true value. The *stop* argument to postcmd() is the return value from the command's corresponding do_*() method.

If completion is enabled, completing commands will be done automatically, and completing of commands args is done by calling <code>complete_foo()</code> with arguments <code>text</code>, <code>line</code>, <code>begidx</code>, and <code>endidx</code>. <code>text</code> is the string prefix we are attempting to match: all returned matches must begin with it. <code>line</code> is the current input line with leading whitespace removed, <code>begidx</code> and <code>endidx</code> are the beginning and ending indexes of the prefix text, which could be used to provide different completion depending upon which position the argument is in.

All subclasses of Cmd inherit a predefined do_help(). This method, called with an argument 'bar', invokes the corresponding method help_bar(). With no argument, do_help() lists all available help topics (that is, all commands with corresponding help_*() methods), and also lists any undocumented commands.

onecmd(str)

Interpret the argument as though it had been typed in response to the prompt. This may be overridden, but should not normally need to be; see the precmd() and postcmd() methods for useful execution hooks. The return value is a flag indicating whether interpretation of commands by the interpreter should stop. If there is a do_*() method for the command *str*, the return value of that method is returned, otherwise the return value from the default() method is returned.

emptyline()

Method called when an empty line is entered in response to the prompt. If this method is not overridden, it repeats the last nonempty command entered.

default(line)

Method called on an input line when the command prefix is not recognized. If this method is not overridden, it prints an error message and returns.

completedefault(text, line, begidx, endidx)

Method called to complete an input line when no command-specific complete_*() method is available. By default, it returns an empty list.

precmd(line)

Hook method executed just before the command line *line* is interpreted, but after the input prompt is generated and issued. This method is a stub in Cmd; it exists to be overridden by subclasses. The return value is used as the command which will be executed by the onecmd() method; the precmd() implementation may re-write the command or simply return *line* unchanged.

postcmd(stop, line)

Hook method executed just after a command dispatch is finished. This method is a stub in Cmd; it exists to be overridden by subclasses. *line* is the command line which was executed, and *stop* is a flag which indicates whether execution will be terminated after the call to postcmd(); this will be the return value of the onecmd() method. The return value of this method will be used as the new value for the internal flag which corresponds to *stop*; returning false will cause interpretation to continue.

preloop()

Hook method executed once when cmdloop() is called. This method is a stub in Cmd; it exists to be overridden by subclasses.

postloop()

Hook method executed once when cmdloop() is about to return. This method is a stub in Cmd; it exists to be overridden by subclasses.

Instances of Cmd subclasses have some public instance variables:

prompt

The prompt issued to solicit input.

identchars

The string of characters accepted for the command prefix.

lastcmd

The last nonempty command prefix seen.

intro

A string to issue as an intro or banner. May be overridden by giving the cmdloop() method an argument.

doc_header

The header to issue if the help output has a section for documented commands.

misc_header

The header to issue if the help output has a section for miscellaneous help topics (that is, there are $help_*()$) methods without corresponding $do_*()$) methods).

undoc_header

The header to issue if the help output has a section for undocumented commands (that is, there are do_* () methods without corresponding $help_*$ () methods).

ruler

The character used to draw separator lines under the help-message headers. If empty, no ruler line is drawn. It defaults to '='.

use_rawinput

A flag, defaulting to true. If true, cmdloop() uses raw_input() to display a prompt and read the next command; if false, sys.stdout.write() and sys.stdin.readline() are used. (This means that by importing readline, on systems that support it, the interpreter will automatically support Emacs-like line editing and command-history keystrokes.)

5.21 shlex — Simple lexical analysis

New in version 1.5.2.

The shlex class makes it easy to write lexical analyzers for simple syntaxes resembling that of the UNIX shell. This will often be useful for writing minilanguages, (for example, in run control files for Python applications) or for parsing quoted strings.

The shlex module defines the following functions:

split(s[, comments])

Split the string s using shell-like syntax. If *comments* is False (the default), the parsing of comments in the given string will be disabled (setting the commenters member of the shlex instance to the empty string). This function operates in POSIX mode. New in version 2.3.

The shlex module defines the following class:

class shlex([instream[, infile[, posix]]])

A shlex instance or subclass instance is a lexical analyzer object. The initialization argument, if present, specifies where to read characters from. It must be a file-/stream-like object with read() and readline() methods, or a string (strings are accepted since Python 2.3). If no argument is given, input will be taken from sys.stdin. The second optional argument is a filename string, which sets the initial value of the infile member. If the *instream* argument is omitted or equal to sys.stdin, this second

argument defaults to "stdin". The *posix* argument was introduced in Python 2.3, and defines the operational mode. When *posix* is not true (default), the shlex instance will operate in compatibility mode. When operating in POSIX mode, shlex will try to be as close as possible to the POSIX shell parsing rules. See section 5.21.1.

See Also:

Module ConfigParser (section 5.17):

Parser for configuration files similar to the Windows '.ini' files.

5.21.1 shlex Objects

A shlex instance has the following methods:

get_token()

Return a token. If tokens have been stacked using push_token(), pop a token off the stack. Otherwise, read one from the input stream. If reading encounters an immediate end-of-file, self.eof is returned (the empty string ('') in non-POSIX mode, and None in POSIX mode).

push_token(str)

Push the argument onto the token stack.

read_token()

Read a raw token. Ignore the pushback stack, and do not interpret source requests. (This is not ordinarily a useful entry point, and is documented here only for the sake of completeness.)

sourcehook(filename)

When shlex detects a source request (see source below) this method is given the following token as argument, and expected to return a tuple consisting of a filename and an open file-like object.

Normally, this method first strips any quotes off the argument. If the result is an absolute pathname, or there was no previous source request in effect, or the previous source was a stream (such as sys.stdin), the result is left alone. Otherwise, if the result is a relative pathname, the directory part of the name of the file immediately before it on the source inclusion stack is prepended (this behavior is like the way the C preprocessor handles #include "file.h").

The result of the manipulations is treated as a filename, and returned as the first component of the tuple, with open() called on it to yield the second component. (Note: this is the reverse of the order of arguments in instance initialization!)

This hook is exposed so that you can use it to implement directory search paths, addition of file extensions, and other namespace hacks. There is no corresponding 'close' hook, but a shlex instance will call the close() method of the sourced input stream when it returns EOF.

For more explicit control of source stacking, use the push_source() and pop_source() methods.

push_source(stream[, filename])

Push an input source stream onto the input stack. If the filename argument is specified it will later be available for use in error messages. This is the same method used internally by the sourcehook method. New in version 2.1.

pop_source()

Pop the last-pushed input source from the input stack. This is the same method used internally when the lexer reaches EOF on a stacked input stream. New in version 2.1.

error_leader([file[, line]])

This method generates an error message leader in the format of a UNIX C compiler error label; the format is '"%s", line %d: ', where the '%s' is replaced with the name of the current source file and the '%d' with the current input line number (the optional arguments can be used to override these).

This convenience is provided to encourage shlex users to generate error messages in the standard, parseable format understood by Emacs and other UNIX tools.

Instances of shlex subclasses have some public instance variables which either control lexical analysis or can be used for debugging:

commenters

The string of characters that are recognized as comment beginners. All characters from the comment beginner to end of line are ignored. Includes just '#' by default.

wordchars

The string of characters that will accumulate into multi-character tokens. By default, includes all ASCII alphanumerics and underscore.

whitespace

Characters that will be considered whitespace and skipped. Whitespace bounds tokens. By default, includes space, tab, linefeed and carriage-return.

escape

Characters that will be considered as escape. This will be only used in POSIX mode, and includes just '\' by default. New in version 2.3.

quotes

Characters that will be considered string quotes. The token accumulates until the same quote is encountered again (thus, different quote types protect each other as in the shell.) By default, includes ASCII single and double quotes.

escapedquotes

Characters in quotes that will interpret escape characters defined in escape. This is only used in POSIX mode, and includes just '"' by default. New in version 2.3.

whitespace_split

If True, tokens will only be split in whitespaces. This is useful, for example, for parsing command lines with shlex, getting tokens in a similar way to shell arguments. New in version 2.3.

infile

The name of the current input file, as initially set at class instantiation time or stacked by later source requests. It may be useful to examine this when constructing error messages.

instream

The input stream from which this shlex instance is reading characters.

source

This member is None by default. If you assign a string to it, that string will be recognized as a lexical-level inclusion request similar to the 'source' keyword in various shells. That is, the immediately following token will opened as a filename and input taken from that stream until EOF, at which point the close() method of that stream will be called and the input source will again become the original input stream. Source requests may be stacked any number of levels deep.

debug

If this member is numeric and 1 or more, a shlex instance will print verbose progress output on its behavior. If you need to use this, you can read the module source code to learn the details.

lineno

Source line number (count of newlines seen so far plus one).

token

The token buffer. It may be useful to examine this when catching exceptions.

eof

Token used to determine end of file. This will be set to the empty string (''), in non-POSIX mode, and to None in POSIX mode. New in version 2.3.

5.21.2 Parsing Rules

When operating in non-POSIX mode, shlex will try to obey to the following rules.

- Quote characters are not recognized within words (Do"Not"Separate is parsed as the single word Do"Not"Separate);
- Escape characters are not recognized;

- Enclosing characters in quotes preserve the literal value of all characters within the quotes;
- Closing quotes separate words ("Do" Separate is parsed as "Do" and Separate);
- If whitespace_split is False, any character not declared to be a word character, whitespace, or a quote will be returned as a single-character token. If it is True, shlex will only split words in whitespaces;
- EOF is signaled with an empty string ('');
- It's not possible to parse empty strings, even if quoted.

When operating in POSIX mode, shlex will try to obey to the following parsing rules.

- Quotes are stripped out, and do not separate words ("Do"Not"Separate" is parsed as the single word DoNotSeparate);
- Non-quoted escape characters (e.g. '\') preserve the literal value of the next character that follows;
- Enclosing characters in quotes which are not part of escapedquotes (e.g. ''') preserve the literal value of all characters within the quotes;
- Enclosing characters in quotes which are part of escapedquotes (e.g. '"') preserves the literal value of all characters within the quotes, with the exception of the characters mentioned in escape. The escape characters retain its special meaning only when followed by the quote in use, or the escape character itself. Otherwise the escape character will be considered a normal character.
- EOF is signaled with a None value;
- Quoted empty strings ('') are allowed;

Generic Operating System Services

The modules described in this chapter provide interfaces to operating system features that are available on (almost) all operating systems, such as files and a clock. The interfaces are generally modeled after the UNIX or C interfaces, but they are available on most other systems as well. Here's an overview:

os Miscellaneous operating system interfaces.

os.path Common pathname manipulations.

direache Return directory listing, with cache mechanism.

stat
Utilities for interpreting the results of os.stat(), os.lstat() and os.fstat().

statcache Stat files, and remember results.

statvfs Constants for interpreting the result of os.statvfs().

filecmp Compare files efficiently. **subprocess** Subprocess management.

popen2 Subprocesses with accessible standard I/O streams.

datetimeBasic date and time types.timeTime access and conversions.schedGeneral purpose event scheduler.mutexLock and queue for mutual exclusion.

getpass Portable reading of passwords and retrieval of the userid.

curses An interface to the curses library, providing portable terminal handling.

curses.textpad Emacs-like input editing in a curses window.

curses.wrapper Terminal configuration wrapper for curses programs.

curses.ascii Constants and set-membership functions for ASCII characters. A panel stack extension that adds depth to curses windows.

getopt Portable parser for command line options; support both short and long option names.

optparse More convenient, flexible, and powerful command-line parsing library.

tempfile Generate temporary files and directories.

errno Standard errno system symbols.

glob UNIX shell style pathname pattern expansion.

fnmatch UNIX shell style filename pattern matching.

shutil High-level file operations, including copying.

locale Internationalization services.

gettext Multilingual internationalization services.

Logging module for Python based on PEP 282.

platform Retrieves as much platform identifying data as possible.

6.1 os — Miscellaneous operating system interfaces

This module provides a more portable way of using operating system dependent functionality than importing a operating system dependent built-in module like posix or nt.

This module searches for an operating system dependent built-in module like mac or posix and exports the same functions and data as found there. The design of all Python's built-in operating system dependent modules is such that as long as the same functionality is available, it uses the same interface; for example, the function

os.stat(path) returns stat information about path in the same format (which happens to have originated with the POSIX interface).

Extensions peculiar to a particular operating system are also available through the os module, but using them is of course a threat to portability!

Note that after the first time os is imported, there is *no* performance penalty in using functions from os instead of directly from the operating system dependent built-in module, so there should be *no* reason not to use os!

exception error

This exception is raised when a function returns a system-related error (not for illegal argument types or other incidental errors). This is also known as the built-in exception OSError. The accompanying value is a pair containing the numeric error code from errno and the corresponding string, as would be printed by the C function perror (). See the module errno, which contains names for the error codes defined by the underlying operating system.

When exceptions are classes, this exception carries two attributes, errno and strerror. The first holds the value of the C errno variable, and the latter holds the corresponding error message from strerror(). For exceptions that involve a file system path (such as chdir() or unlink()), the exception instance will contain a third attribute, filename, which is the file name passed to the function.

name

The name of the operating system dependent module imported. The following names have currently been registered: 'posix', 'nt', 'mac', 'os2', 'ce', 'java', 'riscos'.

path

The corresponding operating system dependent standard module for pathname operations, such as posixpath or macpath. Thus, given the proper imports, os.path.split(file) is equivalent to but more portable than posixpath.split(file). Note that this is also an importable module: it may be imported directly as os.path.

6.1.1 Process Parameters

These functions and data items provide information and operate on the current process and user.

environ

A mapping object representing the string environment. For example, environ['HOME'] is the pathname of your home directory (on some platforms), and is equivalent to getenv("HOME") in C.

This mapping is captured the first time the os module is imported, typically during Python startup as part of processing 'site.py'. Changes to the environment made after this time are not reflected in os.environ, except for changes made by modifying os.environ directly.

If the platform supports the putenv() function, this mapping may be used to modify the environment as well as query the environment. putenv() will be called automatically when the mapping is modified. **Note:** Calling putenv() directly does not change os.environ, so it's better to modify os.environ. **Note:** On some platforms, including FreeBSD and Mac OS X, setting environ may cause memory leaks. Refer to the system documentation for putenv().

If putenv() is not provided, a modified copy of this mapping may be passed to the appropriate process-creation functions to cause child processes to use a modified environment.

If the platform supports the unsetenv() function, you can delete items in this mapping to unset environment variables. unsetenv() will be called automatically when an item is deleted from os.environ.

```
chdir(path)
fchdir(fd)
getcwd()
```

These functions are described in "Files and Directories" (section 6.1.4).

ctermid()

Return the filename corresponding to the controlling terminal of the process. Availability: UNIX.

getegid()

Return the effective group id of the current process. This corresponds to the 'set id' bit on the file being executed in the current process. Availability: UNIX.

geteuid()

Return the current process' effective user id. Availability: UNIX.

getgid(

Return the real group id of the current process. Availability: UNIX.

getgroups()

Return list of supplemental group ids associated with the current process. Availability: UNIX.

getlogin()

Return the name of the user logged in on the controlling terminal of the process. For most purposes, it is more useful to use the environment variable LOGNAME to find out who the user is, or pwd.getpwuid(os.getuid())[0] to get the login name of the currently effective user ID. Availability: UNIX.

getpgid(pid)

Return the process group id of the process with process id *pid*. If *pid* is 0, the process group id of the current process is returned. Availability: UNIX. New in version 2.3.

getpgrp()

Return the id of the current process group. Availability: UNIX.

getpid()

Return the current process id. Availability: UNIX, Windows.

getppid()

Return the parent's process id. Availability: UNIX.

getuid()

Return the current process' user id. Availability: UNIX.

getenv(varname[, value])

Return the value of the environment variable *varname* if it exists, or *value* if it doesn't. *value* defaults to None. Availability: most flavors of UNIX, Windows.

putenv(varname, value)

Set the environment variable named *varname* to the string *value*. Such changes to the environment affect subprocesses started with os.system(), popen() or fork() and execv(). Availability: most flavors of UNIX, Windows.

Note: On some platforms, including FreeBSD and Mac OS X, setting environ may cause memory leaks. Refer to the system documentation for putenv.

When putenv() is supported, assignments to items in os.environ are automatically translated into corresponding calls to putenv(); however, calls to putenv() don't update os.environ, so it is actually preferable to assign to items of os.environ.

setegid(egid)

Set the current process's effective group id. Availability: UNIX.

seteuid(euid)

Set the current process's effective user id. Availability: UNIX.

setgid(gid)

Set the current process' group id. Availability: UNIX.

setgroups(groups)

Set the list of supplemental group ids associated with the current process to *groups*. *groups* must be a sequence, and each element must be an integer identifying a group. This operation is typical available only to the superuser. Availability: UNIX. New in version 2.2.

setpgrp()

Calls the system call setpgrp() or setpgrp(0, 0) depending on which version is implemented (if any). See the UNIX manual for the semantics. Availability: UNIX.

setpgid(pid, pgrp)

Calls the system call setpgid() to set the process group id of the process with id *pid* to the process group with id *pgrp*. See the UNIX manual for the semantics. Availability: UNIX.

setreuid(ruid, euid)

Set the current process's real and effective user ids. Availability: UNIX.

setregid(rgid, egid)

Set the current process's real and effective group ids. Availability: UNIX.

getsid(pid)

Calls the system call getsid(). See the UNIX manual for the semantics. Availability: UNIX. New in version 2.4.

setsid()

Calls the system call setsid(). See the UNIX manual for the semantics. Availability: UNIX.

setuid(uid)

Set the current process' user id. Availability: UNIX.

strerror(code)

Return the error message corresponding to the error code in code. Availability: UNIX, Windows.

umask (mask)

Set the current numeric umask and returns the previous umask. Availability: UNIX, Windows.

uname()

Return a 5-tuple containing information identifying the current operating system. The tuple contains 5 strings: (sysname, nodename, release, version, machine). Some systems truncate the nodename to 8 characters or to the leading component; a better way to get the hostname is socket.gethostname() or even socket.gethostbyaddr(socket.gethostname()). Availability: recent flavors of UNIX.

unsetenv(varname)

Unset (delete) the environment variable named *varname*. Such changes to the environment affect subprocesses started with os.system(), popen() or fork() and execv(). Availability: most flavors of UNIX, Windows.

When unsetenv() is supported, deletion of items in os.environ is automatically translated into a corresponding call to unsetenv(); however, calls to unsetenv() don't update os.environ, so it is actually preferable to delete items of os.environ.

6.1.2 File Object Creation

These functions create new file objects.

fdopen (fd[, mode[, bufsize]])

Return an open file object connected to the file descriptor *fd*. The *mode* and *bufsize* arguments have the same meaning as the corresponding arguments to the built-in open() function. Availability: Macintosh, UNIX, Windows.

Changed in version 2.3: When specified, the *mode* argument must now start with one of the letters 'r', 'w', or 'a', otherwise a ValueError is raised.

popen(command[, mode[, bufsize]])

Open a pipe to or from *command*. The return value is an open file object connected to the pipe, which can be read or written depending on whether *mode* is 'r' (default) or 'w'. The *bufsize* argument has the same meaning as the corresponding argument to the built-in open() function. The exit status of the command (encoded in the format specified for wait()) is available as the return value of the close() method of the file object, except that when the exit status is zero (termination without errors), None is returned. Availability: Macintosh, UNIX, Windows.

Changed in version 2.0: This function worked unreliably under Windows in earlier versions of Python. This was due to the use of the _popen() function from the libraries provided with Windows. Newer versions of Python do not use the broken implementation from the Windows libraries.

tmpfile()

Return a new file object opened in update mode ('w+b'). The file has no directory entries associated with it and will be automatically deleted once there are no file descriptors for the file. Availability: Macintosh,

UNIX, Windows.

For each of the following popen() variants, if *bufsize* is specified, it specifies the buffer size for the I/O pipes. *mode*, if provided, should be the string 'b' or 't'; on Windows this is needed to determine whether the file objects should be opened in binary or text mode. The default value for *mode* is 't'.

Also, for each of these variants, on UNIX, *cmd* may be a sequence, in which case arguments will be passed directly to the program without shell intervention (as with os.spawnv()). If *cmd* is a string it will be passed to the shell (as with os.system()).

These methods do not make it possible to retrieve the exit status from the child processes. The only way to control the input and output streams and also retrieve the return codes is to use the Popen3 and Popen4 classes from the popen2 module; these are only available on UNIX.

For a discussion of possible deadlock conditions related to the use of these functions, see "Flow Control Issues" (section 6.9.2).

```
popen2(cmd[, mode[, bufsize]])
```

Executes *cmd* as a sub-process. Returns the file objects (*child_stdin*, *child_stdout*). Availability: Macintosh, UNIX, Windows. New in version 2.0.

```
popen3(cmd[, mode[, bufsize]])
```

Executes *cmd* as a sub-process. Returns the file objects (*child_stdin*, *child_stdout*, *child_stderr*). Availability: Macintosh, UNIX, Windows. New in version 2.0.

```
popen4(cmd[, mode[, bufsize]])
```

Executes *cmd* as a sub-process. Returns the file objects (*child_stdin*, *child_stdout_and_stderr*). Availability: Macintosh, UNIX, Windows. New in version 2.0.

(Note that *child_stdin*, *child_stdout*, and *child_stderr* are named from the point of view of the child process, i.e. *child_stdin* is the child's standard input.)

This functionality is also available in the popen2 module using functions of the same names, but the return values of those functions have a different order.

6.1.3 File Descriptor Operations

These functions operate on I/O streams referred to using file descriptors.

${\tt close}({\it fd})$

Close file descriptor fd. Availability: Macintosh, UNIX, Windows.

Note: This function is intended for low-level I/O and must be applied to a file descriptor as returned by open() or pipe(). To close a "file object" returned by the built-in function open() or by popen() or fdopen(), use its close() method.

dup(fd)

Return a duplicate of file descriptor fd. Availability: Macintosh, UNIX, Windows.

dup2 (fd, fd2)

Duplicate file descriptor fd to fd2, closing the latter first if necessary. Availability: Macintosh, UNIX, Windows.

fdatasync(fd)

Force write of file with filedescriptor fd to disk. Does not force update of metadata. Availability: UNIX.

fpathconf(fd, name)

Return system configuration information relevant to an open file. *name* specifies the configuration value to retrieve; it may be a string which is the name of a defined system value; these names are specified in a number of standards (POSIX.1, UNIX 95, UNIX 98, and others). Some platforms define additional names as well. The names known to the host operating system are given in the pathconf_names dictionary. For configuration variables not included in that mapping, passing an integer for *name* is also accepted. Availability: Macintosh, UNIX.

If *name* is a string and is not known, ValueError is raised. If a specific value for *name* is not supported by the host system, even if it is included in pathconf_names, an OSError is raised with errno. EINVAL

for the error number.

fstat(fd)

Return status for file descriptor fd, like stat(). Availability: Macintosh, UNIX, Windows.

fstatvfs(fd)

Return information about the filesystem containing the file associated with file descriptor fd, like statvfs(). Availability: UNIX.

fsync(fd)

Force write of file with filedescriptor fd to disk. On UNIX, this calls the native fsync() function; on Windows, the MS $_$ commit() function.

If you're starting with a Python file object f, first do f.flush(), and then do os.fsync(f.fileno()), to ensure that all internal buffers associated with f are written to disk. Availability: Macintosh, UNIX, and Windows starting in 2.2.3.

ftruncate(fd, length)

Truncate the file corresponding to file descriptor fd, so that it is at most length bytes in size. Availability: Macintosh, UNIX.

isatty(fd)

Return True if the file descriptor fd is open and connected to a tty(-like) device, else False. Availability: Macintosh, UNIX.

lseek(fd, pos, how)

Set the current position of file descriptor fd to position pos, modified by how: 0 to set the position relative to the beginning of the file; 1 to set it relative to the current position; 2 to set it relative to the end of the file. Availability: Macintosh, UNIX, Windows.

open (file, flags[, mode])

Open the file *file* and set various flags according to *flags* and possibly its mode according to *mode*. The default *mode* is 0777 (octal), and the current umask value is first masked out. Return the file descriptor for the newly opened file. Availability: Macintosh, UNIX, Windows.

For a description of the flag and mode values, see the C run-time documentation; flag constants (like O_RDONLY and O_WRONLY) are defined in this module too (see below).

Note: This function is intended for low-level I/O. For normal usage, use the built-in function open(), which returns a "file object" with read() and write() methods (and many more).

openpty()

Open a new pseudo-terminal pair. Return a pair of file descriptors (*master*, *slave*) for the pty and the tty, respectively. For a (slightly) more portable approach, use the pty module. Availability: Macintosh, Some flavors of UNIX.

pipe()

Create a pipe. Return a pair of file descriptors (r, w) usable for reading and writing, respectively. Availability: Macintosh, UNIX, Windows.

read(*fd*, *n*)

Read at most n bytes from file descriptor fd. Return a string containing the bytes read. If the end of the file referred to by fd has been reached, an empty string is returned. Availability: Macintosh, UNIX, Windows.

Note: This function is intended for low-level I/O and must be applied to a file descriptor as returned by open() or pipe(). To read a "file object" returned by the built-in function open() or by popen() or fdopen(), or sys.stdin, use its read() or readline() methods.

tcgetpgrp(fd)

Return the process group associated with the terminal given by fd (an open file descriptor as returned by open()). Availability: Macintosh, UNIX.

tcsetpgrp(fd, pg)

Set the process group associated with the terminal given by fd (an open file descriptor as returned by open()) to pg. Availability: Macintosh, UNIX.

ttyname(fd)

Return a string which specifies the terminal device associated with file-descriptor fd. If fd is not associated

with a terminal device, an exception is raised. Availability:Macintosh, UNIX.

write(fd, str)

Write the string *str* to file descriptor *fd*. Return the number of bytes actually written. Availability: Macintosh, UNIX, Windows.

Note: This function is intended for low-level I/O and must be applied to a file descriptor as returned by open() or pipe(). To write a "file object" returned by the built-in function open() or by popen() or fdopen(), or sys.stdout or sys.stderr, use its write() method.

The following data items are available for use in constructing the *flags* parameter to the open () function.

- O RDONLY
- O_WRONLY
- O_RDWR
- O APPEND
- O_CREAT
- O_EXCL
- O_TRUNC

Options for the *flag* argument to the open() function. These can be bit-wise OR'd together. Availability: Macintosh, UNIX, Windows.

- O_DSYNC
- O_RSYNC
- O_SYNC
- O_NDELAY
- O_NONBLOCK
- O_NOCTTY

More options for the *flag* argument to the open () function. Availability: Macintosh, UNIX.

O_BINARY

Option for the *flag* argument to the open() function. This can be bit-wise OR'd together with those listed above. Availability: Windows.

- O_NOINHERIT
- O_SHORT_LIVED
- O_TEMPORARY
- O_RANDOM
- O_SEQUENTIAL
- O_TEXT

Options for the *flag* argument to the open() function. These can be bit-wise OR'd together. Availability: Windows.

6.1.4 Files and Directories

access (path, mode)

Use the real uid/gid to test for access to *path*. Note that most operations will use the effective uid/gid, therefore this routine can be used in a suid/sgid environment to test if the invoking user has the specified access to *path*. *mode* should be F_OK to test the existence of *path*, or it can be the inclusive OR of one or more of R_OK, W_OK, and X_OK to test permissions. Return True if access is allowed, False if not. See the UNIX man page *access*(2) for more information. Availability: Macintosh, UNIX, Windows.

Note: Using access() to check if a user is authorized to e.g. open a file before actually doing so using open() creates a security hole, because the user might exploit the short time interval between checking and opening the file to manipulate it.

F_OK

Value to pass as the *mode* parameter of access () to test the existence of *path*.

R_OK

Value to include in the *mode* parameter of access () to test the readability of *path*.

W_OK

Value to include in the *mode* parameter of access () to test the writability of path.

X_OK

Value to include in the *mode* parameter of access() to determine if *path* can be executed.

chdir(path)

Change the current working directory to path. Availability: Macintosh, UNIX, Windows.

fchdir(fd)

Change the current working directory to the directory represented by the file descriptor *fd*. The descriptor must refer to an opened directory, not an open file. Availability: UNIX. New in version 2.3.

getcwd()

Return a string representing the current working directory. Availability: Macintosh, UNIX, Windows.

getcwdu()

Return a Unicode object representing the current working directory. Availability: Macintosh, UNIX, Windows. New in version 2.3.

chroot(path)

Change the root directory of the current process to *path*. Availability: Macintosh, UNIX. New in version 2.2.

chmod(path, mode)

Change the mode of *path* to the numeric *mode*. *mode* may take one of the following values (as defined in the stat module):

- •S_ISUID
- •S_ISGID
- •S_ENFMT
- •S_ISVTX
- •S_IREAD
- •S_IWRITE
- •S_IEXEC
- •S_IRWXU
- •S_IRUSR
- •S_IWUSR
- \bullet S_IXUSR
- •S_IRWXG •S_IRGRP
- •S_IWGRP
- •b_IWGRI
- •S_IXGRP
- •S_IRWXO
- •S_IROTH
- •S_IWOTH
- •S_IXOTH

Availability: Macintosh, UNIX, Windows.

Note: Although Windows supports chmod(), you can only set the file's read-only flag with it (via the S_IWRITE and S_IREAD constants or a corresponding integer value). All other bits are ignored.

chown (path, uid, gid)

Change the owner and group id of *path* to the numeric *uid* and *gid*. To leave one of the ids unchanged, set it to -1. Availability: Macintosh, UNIX.

lchown(path, uid, gid)

Change the owner and group id of *path* to the numeric *uid* and gid. This function will not follow symbolic links. Availability: Macintosh, UNIX. New in version 2.3.

link(src, dst)

Create a hard link pointing to src named dst. Availability: Macintosh, UNIX.

listdir(path)

Return a list containing the names of the entries in the directory. The list is in arbitrary order. It does not include the special entries '.' and '..' even if they are present in the directory. Availability: Macintosh, UNIX, Windows.

Changed in version 2.3: On Windows NT/2k/XP and Unix, if *path* is a Unicode object, the result will be a list of Unicode objects..

lstat(path)

Like stat(), but do not follow symbolic links. Availability: Macintosh, UNIX.

mkfifo(path[, mode])

Create a FIFO (a named pipe) named *path* with numeric mode *mode*. The default *mode* is 0666 (octal). The current umask value is first masked out from the mode. Availability: Macintosh, UNIX.

FIFOs are pipes that can be accessed like regular files. FIFOs exist until they are deleted (for example with os.unlink()). Generally, FIFOs are used as rendezvous between "client" and "server" type processes: the server opens the FIFO for reading, and the client opens it for writing. Note that mkfifo() doesn't open the FIFO — it just creates the rendezvous point.

mknod(path[, mode=0600, device])

Create a filesystem node (file, device special file or named pipe) named filename. *mode* specifies both the permissions to use and the type of node to be created, being combined (bitwise OR) with one of S_IFREG, S_IFCHR, S_IFBLK, and S_IFIFO (those constants are available in stat). For S_IFCHR and S_IFBLK, *device* defines the newly created device special file (probably using os.makedev()), otherwise it is ignored. New in version 2.3.

major(device)

Extracts a device major number from a raw device number. New in version 2.3.

minor(device)

Extracts a device minor number from a raw device number. New in version 2.3.

makedev(major, minor)

Composes a raw device number from the major and minor device numbers. New in version 2.3.

mkdir(path[, mode])

Create a directory named *path* with numeric mode *mode*. The default *mode* is 0777 (octal). On some systems, *mode* is ignored. Where it is used, the current umask value is first masked out. Availability: Macintosh, UNIX, Windows.

makedirs(path[, mode])

Recursive directory creation function. Like mkdir(), but makes all intermediate-level directories needed to contain the leaf directory. Throws an error exception if the leaf directory already exists or cannot be created. The default *mode* is 0777 (octal). This function does not properly handle UNC paths (only relevant on Windows systems; Universal Naming Convention paths are those that use the '\host\path' syntax). New in version 1.5.2.

pathconf(path, name)

Return system configuration information relevant to a named file. *name* specifies the configuration value to retrieve; it may be a string which is the name of a defined system value; these names are specified in a number of standards (POSIX.1, UNIX 95, UNIX 98, and others). Some platforms define additional names as well. The names known to the host operating system are given in the pathconf_names dictionary. For configuration variables not included in that mapping, passing an integer for *name* is also accepted. Availability: Macintosh, UNIX.

If *name* is a string and is not known, ValueError is raised. If a specific value for *name* is not supported by the host system, even if it is included in pathconf_names, an OSError is raised with errno.EINVAL for the error number.

pathconf_names

Dictionary mapping names accepted by pathconf() and fpathconf() to the integer values defined for those names by the host operating system. This can be used to determine the set of names known to the

system. Availability: Macintosh, UNIX.

readlink(path)

Return a string representing the path to which the symbolic link points. The result may be either an absolute or relative pathname; if it is relative, it may be converted to an absolute pathname using os.path.join(os.path.dirname(path), result). Availability: Macintosh, UNIX.

remove(path)

Remove the file *path*. If *path* is a directory, OSError is raised; see rmdir() below to remove a directory. This is identical to the unlink() function documented below. On Windows, attempting to remove a file that is in use causes an exception to be raised; on UNIX, the directory entry is removed but the storage allocated to the file is not made available until the original file is no longer in use. Availability: Macintosh, UNIX, Windows.

removedirs(path)

Removes directories recursively. Works like rmdir() except that, if the leaf directory is successfully removed, directories corresponding to rightmost path segments will be pruned way until either the whole path is consumed or an error is raised (which is ignored, because it generally means that a parent directory is not empty). Throws an error exception if the leaf directory could not be successfully removed. New in version 1.5.2.

rename (src, dst)

Rename the file or directory *src* to *dst*. If *dst* is a directory, OSError will be raised. On UNIX, if *dst* exists and is a file, it will be removed silently if the user has permission. The operation may fail on some UNIX flavors if *src* and *dst* are on different filesystems. If successful, the renaming will be an atomic operation (this is a POSIX requirement). On Windows, if *dst* already exists, OSError will be raised even if it is a file; there may be no way to implement an atomic rename when *dst* names an existing file. Availability: Macintosh, UNIX, Windows.

renames(old, new)

Recursive directory or file renaming function. Works like rename(), except creation of any intermediate directories needed to make the new pathname good is attempted first. After the rename, directories corresponding to rightmost path segments of the old name will be pruned away using removedirs(). New in version 1.5.2.

Note: This function can fail with the new directory structure made if you lack permissions needed to remove the leaf directory or file.

rmdir(path)

Remove the directory path. Availability: Macintosh, UNIX, Windows.

stat(path)

Perform a stat() system call on the given path. The return value is an object whose attributes correspond to the members of the stat structure, namely: st_mode (protection bits), st_ino (inode number), st_dev (device), st_nlink (number of hard links), st_uid (user ID of owner), st_gid (group ID of owner), st_size (size of file, in bytes), st_atime (time of most recent access), st_mtime (time of most recent content modification), st_ctime (platform dependent; time of most recent metadata change on UNIX, or the time of creation on Windows).

Changed in version 2.3: If stat_float_times returns true, the time values are floats, measuring seconds. Fractions of a second may be reported if the system supports that. On Mac OS, the times are always floats. See stat_float_times for further discussion.

On some Unix systems (such as Linux), the following attributes may also be available: st_blocks (number of blocks allocated for file), st_blksize (filesystem blocksize), st_rdev (type of device if an inode device).

On Mac OS systems, the following attributes may also be available: st_rsize, st_creator, st_type.

On RISCOS systems, the following attributes are also available: st_ftype (file type), st_attrs (attributes), st_obtype (object type).

For backward compatibility, the return value of stat() is also accessible as a tuple of at least 10 integers giving the most important (and portable) members of the stat structure, in the order st_mode, st_ino, st_dev, st_nlink, st_uid, st_gid, st_size, st_atime, st_mtime, st_ctime. More items

may be added at the end by some implementations. The standard module stat defines functions and constants that are useful for extracting information from a stat structure. (On Windows, some items are filled with dummy values.)

Note: The exact meaning and resolution of the st_atime, st_mtime, and st_ctime members depends on the operating system and the file system. For example, on Windows systems using the FAT or FAT32 file systems, st_mtime has 2-second resolution, and st_atime has only 1-day resolution. See your operating system documentation for details.

Availability: Macintosh, UNIX, Windows.

Changed in version 2.2: Added access to values as attributes of the returned object.

stat_float_times([newvalue])

Determine whether stat_result represents time stamps as float objects. If newval is True, future calls to stat() return floats, if it is False, future calls return ints. If newval is omitted, return the current setting.

For compatibility with older Python versions, accessing stat_result as a tuple always returns integers. For compatibility with Python 2.2, accessing the time stamps by field name also returns integers. Applications that want to determine the fractions of a second in a time stamp can use this function to have time stamps represented as floats. Whether they will actually observe non-zero fractions depends on the system.

Future Python releases will change the default of this setting; applications that cannot deal with floating point time stamps can then use this function to turn the feature off.

It is recommended that this setting is only changed at program startup time in the __main__ module; libraries should never change this setting. If an application uses a library that works incorrectly if floating point time stamps are processed, this application should turn the feature off until the library has been corrected.

statvfs(path)

Perform a statvfs() system call on the given path. The return value is an object whose attributes describe the filesystem on the given path, and correspond to the members of the statvfs structure, namely: f_frsize, f_blocks, f_bfree, f_bavail, f_files, f_ffree, f_favail, f_flag, f_namemax. Availability: UNIX.

For backward compatibility, the return value is also accessible as a tuple whose values correspond to the attributes, in the order given above. The standard module <code>statvfs</code> defines constants that are useful for extracting information from a <code>statvfs</code> structure when accessing it as a sequence; this remains useful when writing code that needs to work with versions of Python that don't support accessing the fields as attributes.

Changed in version 2.2: Added access to values as attributes of the returned object.

symlink(src, dst)

Create a symbolic link pointing to src named dst. Availability: UNIX.

tempnam([dir[, prefix]])

Return a unique path name that is reasonable for creating a temporary file. This will be an absolute path that names a potential directory entry in the directory *dir* or a common location for temporary files if *dir* is omitted or None. If given and not None, *prefix* is used to provide a short prefix to the filename. Applications are responsible for properly creating and managing files created using paths returned by tempnam(); no automatic cleanup is provided. On UNIX, the environment variable TMPDIR overrides *dir*, while on Windows the TMP is used. The specific behavior of this function depends on the C library implementation; some aspects are underspecified in system documentation. **Warning:** Use of tempnam() is vulnerable to symlink attacks; consider using tmpfile() (section 6.1.2) instead. Availability: Macintosh, UNIX, Windows.

tmpnam()

Return a unique path name that is reasonable for creating a temporary file. This will be an absolute path that names a potential directory entry in a common location for temporary files. Applications are responsible for properly creating and managing files created using paths returned by tmpnam(); no automatic cleanup is provided. Warning: Use of tmpnam() is vulnerable to symlink attacks; consider using tmpfile() (section 6.1.2) instead. Availability: UNIX, Windows. This function probably shouldn't be used on Windows, though: Microsoft's implementation of tmpnam() always creates a name in the root directory of the current drive, and that's generally a poor location for a temp file (depending on privileges, you may not even be able to open a file using this name).

TMP_MAX

The maximum number of unique names that tmpnam() will generate before reusing names.

unlink(path)

Remove the file *path*. This is the same function as remove(); the unlink() name is its traditional UNIX name. Availability: Macintosh, UNIX, Windows.

utime(path, times)

Set the access and modified times of the file specified by *path*. If *times* is None, then the file's access and modified times are set to the current time. Otherwise, *times* must be a 2-tuple of numbers, of the form (*atime*, *mtime*) which is used to set the access and modified times, respectively. Whether a directory can be given for *path* depends on whether the operating system implements directories as files (for example, Windows does not). Note that the exact times you set here may not be returned by a subsequent stat() call, depending on the resolution with which your operating system records access and modification times; see stat(). Changed in version 2.0: Added support for None for *times*. Availability: Macintosh, UNIX, Windows.

walk(top[, topdown=True [, onerror=None]])

walk() generates the file names in a directory tree, by walking the tree either top down or bottom up. For each directory in the tree rooted at directory *top* (including *top* itself), it yields a 3-tuple (*dirpath*, *dirnames*, *filenames*).

dirpath is a string, the path to the directory. dirnames is a list of the names of the subdirectories in dirpath (excluding '.' and '..'). filenames is a list of the names of the non-directory files in dirpath. Note that the names in the lists contain no path components. To get a full path (which begins with top) to a file or directory in dirpath, do os.path.join(dirpath, name).

If optional argument *topdown* is true or not specified, the triple for a directory is generated before the triples for any of its subdirectories (directories are generated top down). If *topdown* is false, the triple for a directory is generated after the triples for all of its subdirectories (directories are generated bottom up).

When *topdown* is true, the caller can modify the *dirnames* list in-place (perhaps using del or slice assignment), and walk() will only recurse into the subdirectories whose names remain in *dirnames*; this can be used to prune the search, impose a specific order of visiting, or even to inform walk() about directories the caller creates or renames before it resumes walk() again. Modifying *dirnames* when *topdown* is false is ineffective, because in bottom-up mode the directories in *dirnames* are generated before *dirnames* itself is generated.

By default errors from the os.listdir() call are ignored. If optional argument *onerror* is specified, it should be a function; it will be called with one argument, an os.error instance. It can report the error to continue with the walk, or raise the exception to abort the walk. Note that the filename is available as the filename attribute of the exception object.

Note: If you pass a relative pathname, don't change the current working directory between resumptions of walk(). walk() never changes the current directory, and assumes that its caller doesn't either.

Note: On systems that support symbolic links, links to subdirectories appear in *dirnames* lists, but walk() will not visit them (infinite loops are hard to avoid when following symbolic links). To visit linked directories, you can identify them with os.path.islink(path), and invoke walk(path) on each directly.

This example displays the number of bytes taken by non-directory files in each directory under the starting directory, except that it doesn't look under any CVS subdirectory:

```
import os
from os.path import join, getsize
for root, dirs, files in os.walk('python/Lib/email'):
    print root, "consumes",
    print sum(getsize(join(root, name)) for name in files),
    print "bytes in", len(files), "non-directory files"
    if 'CVS' in dirs:
        dirs.remove('CVS') # don't visit CVS directories
```

In the next example, walking the tree bottom up is essential: rmdir() doesn't allow deleting a directory before the directory is empty:

```
# Delete everything reachable from the directory named in 'top',
# assuming there are no symbolic links.
# CAUTION: This is dangerous! For example, if top == '/', it
# could delete all your disk files.
import os
for root, dirs, files in os.walk(top, topdown=False):
    for name in files:
        os.remove(os.path.join(root, name))
    for name in dirs:
        os.rmdir(os.path.join(root, name))
```

New in version 2.3.

6.1.5 Process Management

These functions may be used to create and manage processes.

The various <code>exec*()</code> functions take a list of arguments for the new program loaded into the process. In each case, the first of these arguments is passed to the new program as its own name rather than as an argument a user may have typed on a command line. For the C programmer, this is the <code>argv[0]</code> passed to a program's <code>main()</code>. For example, 'os.execv('/bin/echo', ['foo', 'bar'])' will only print 'bar' on standard output; 'foo' will seem to be ignored.

abort()

Generate a SIGABRT signal to the current process. On UNIX, the default behavior is to produce a core dump; on Windows, the process immediately returns an exit code of 3. Be aware that programs which use signal.signal() to register a handler for SIGABRT will behave differently. Availability: Macintosh, UNIX, Windows.

```
execl(path, arg0, arg1, ...)
execle(path, arg0, arg1, ..., env)
execlp(file, arg0, arg1, ...)
execlpe(file, arg0, arg1, ..., env)
execv(path, args)
execve(path, args, env)
execvp(file, args)
execvpe(file, args, env)
```

These functions all execute a new program, replacing the current process; they do not return. On UNIX, the new executable is loaded into the current process, and will have the same process ID as the caller. Errors will be reported as OSError exceptions.

The '1' and 'v' variants of the exec*() functions differ in how command-line arguments are passed. The '1' variants are perhaps the easiest to work with if the number of parameters is fixed when the code is written; the individual parameters simply become additional parameters to the execl*() functions. The 'v' variants are good when the number of parameters is variable, with the arguments being passed in a list or tuple as the *args* parameter. In either case, the arguments to the child process should start with the name of the command being run, but this is not enforced.

The variants which include a 'p' near the end (execlp(), execlpe(), execvp(), and execvpe()) will use the PATH environment variable to locate the program *file*. When the environment is being replaced (using one of the exec*e() variants, discussed in the next paragraph), the new environment is used as the source of the PATH variable. The other variants, execl(), execle(), execv(), and execve(), will not use the PATH variable to locate the executable; *path* must contain an appropriate absolute or relative path.

For execle(), execlpe(), execve(), and execvpe() (note that these all end in 'e'), the *env* parameter must be a mapping which is used to define the environment variables for the new process; the execl(), execv(), execv(), and execvp() all cause the new process to inherit the environment of the current process. Availability: Macintosh, UNIX, Windows.

```
_{-}\mathtt{exit}(n)
```

Exit to the system with status *n*, without calling cleanup handlers, flushing stdio buffers, etc. Availability: Macintosh, UNIX, Windows.

Note: The standard way to exit is sys.exit(n). $_exit()$ should normally only be used in the child process after a fork().

The following exit codes are a defined, and can be used with <code>_exit()</code>, although they are not required. These are typically used for system programs written in Python, such as a mail server's external command delivery program. **Note:** Some of these may not be available on all UNIX platforms, since there is some variation. These constants are defined where they are defined by the underlying platform.

EX_OK

Exit code that means no error occurred. Availability: Macintosh, UNIX. New in version 2.3.

EX USAGE

Exit code that means the command was used incorrectly, such as when the wrong number of arguments are given. Availability: Macintosh, UNIX. New in version 2.3.

EX_DATAERR

Exit code that means the input data was incorrect. Availability: Macintosh, UNIX. New in version 2.3.

EX_NOINPUT

Exit code that means an input file did not exist or was not readable. Availability: Macintosh, UNIX. New in version 2.3.

EX_NOUSER

Exit code that means a specified user did not exist. Availability: Macintosh, UNIX. New in version 2.3.

EX_NOHOST

Exit code that means a specified host did not exist. Availability: Macintosh, UNIX. New in version 2.3.

EX_UNAVAILABLE

Exit code that means that a required service is unavailable. Availability: Macintosh, UNIX. New in version 2.3.

EX_SOFTWARE

Exit code that means an internal software error was detected. Availability: Macintosh, UNIX. New in version 2.3.

EX_OSERR

Exit code that means an operating system error was detected, such as the inability to fork or create a pipe. Availability: Macintosh, UNIX. New in version 2.3.

EX_OSFILE

Exit code that means some system file did not exist, could not be opened, or had some other kind of error. Availability: Macintosh, UNIX. New in version 2.3.

EX_CANTCREAT

Exit code that means a user specified output file could not be created. Availability: Macintosh, UNIX. New in version 2.3.

EX_IOERR

Exit code that means that an error occurred while doing I/O on some file. Availability: Macintosh, UNIX. New in version 2.3.

EX_TEMPFAIL

Exit code that means a temporary failure occurred. This indicates something that may not really be an error, such as a network connection that couldn't be made during a retryable operation. Availability: Macintosh, UNIX. New in version 2.3.

EX DROTOCOL

Exit code that means that a protocol exchange was illegal, invalid, or not understood. Availability: Macintosh, UNIX. New in version 2.3.

EX_NOPERM

Exit code that means that there were insufficient permissions to perform the operation (but not intended for file system problems). Availability: Macintosh, UNIX. New in version 2.3.

EX_CONFIG

Exit code that means that some kind of configuration error occurred. Availability: Macintosh, UNIX. New in version 2.3.

EX_NOTFOUND

Exit code that means something like "an entry was not found". Availability: Macintosh, UNIX. New in version 2.3

fork()

Fork a child process. Return 0 in the child, the child's process id in the parent. Availability: Macintosh,

forkpty()

Fork a child process, using a new pseudo-terminal as the child's controlling terminal. Return a pair of (pid, fd), where pid is 0 in the child, the new child's process id in the parent, and fd is the file descriptor of the master end of the pseudo-terminal. For a more portable approach, use the pty module. Availability: Macintosh, Some flavors of UNIX.

kill(pid, sig)

Kill the process *pid* with signal *sig*. Constants for the specific signals available on the host platform are defined in the signal module. Availability: Macintosh, UNIX.

killpg(pgid, sig)

Kill the process group pgid with the signal sig. Availability: Macintosh, UNIX. New in version 2.3.

nice(increment)

Add increment to the process's "niceness". Return the new niceness. Availability: Macintosh, UNIX.

plock(op)

Lock program segments into memory. The value of *op* (defined in <sys/lock.h>) determines which segments are locked. Availability: Macintosh, UNIX.

```
popen(...)
popen2(...)
popen3(...)
popen4(...)
```

Run child processes, returning opened pipes for communications. These functions are described in section 6.1.2.

```
spawnl (mode, path, ...)
spawnle (mode, path, ..., env)
spawnlp (mode, file, ...)
spawnlpe (mode, file, ..., env)
spawnv (mode, path, args)
spawnve (mode, path, args, env)
spawnvp (mode, file, args)
spawnvpe (mode, file, args, env)
```

Execute the program *path* in a new process. If *mode* is P_NOWAIT, this function returns the process ID of the new process; if *mode* is P_WAIT, returns the process's exit code if it exits normally, or *-signal*, where *signal* is the signal that killed the process. On Windows, the process ID will actually be the process handle, so can be used with the waitpid() function.

The '1' and 'v' variants of the spawn*() functions differ in how command-line arguments are passed. The '1' variants are perhaps the easiest to work with if the number of parameters is fixed when the code is written; the individual parameters simply become additional parameters to the spawn1*() functions. The 'v' variants are good when the number of parameters is variable, with the arguments being passed in a list or tuple as the *args* parameter. In either case, the arguments to the child process must start with the name of the command being run.

The variants which include a second 'p' near the end (spawnlp(), spawnlpe(), spawnvp(), and spawnvpe()) will use the PATH environment variable to locate the program file. When the environment is being replaced (using one of the spawn*e() variants, discussed in the next paragraph), the new environment is used as the source of the PATH variable. The other variants, spawnl(), spawnle(), spawnve(), and spawnve(), will not use the PATH variable to locate the executable; path must contain

an appropriate absolute or relative path.

For spawnle(), spawnlpe(), spawnve(), and spawnvpe() (note that these all end in 'e'), the *env* parameter must be a mapping which is used to define the environment variables for the new process; the spawnl(), spawnlp(), spawnv(), and spawnvp() all cause the new process to inherit the environment of the current process.

As an example, the following calls to spawnlp() and spawnvpe() are equivalent:

```
import os
os.spawnlp(os.P_WAIT, 'cp', 'cp', 'index.html', '/dev/null')
L = ['cp', 'index.html', '/dev/null']
os.spawnvpe(os.P_WAIT, 'cp', L, os.environ)
```

Availability: UNIX, Windows. spawnlp(), spawnlpe(), spawnvp() and spawnvpe() are not available on Windows. New in version 1.6.

P_NOWAIT

P NOWAITO

Possible values for the *mode* parameter to the spawn*() family of functions. If either of these values is given, the spawn*() functions will return as soon as the new process has been created, with the process ID as the return value. Availability: Macintosh, UNIX, Windows. New in version 1.6.

P_WAIT

Possible value for the *mode* parameter to the spawn*() family of functions. If this is given as *mode*, the spawn*() functions will not return until the new process has run to completion and will return the exit code of the process the run is successful, or *-signal* if a signal kills the process. Availability: Macintosh, UNIX, Windows. New in version 1.6.

P_DETACH

P_OVERLAY

Possible values for the *mode* parameter to the <code>spawn*()</code> family of functions. These are less portable than those listed above. P_DETACH is similar to P_NOWAIT, but the new process is detached from the console of the calling process. If P_OVERLAY is used, the current process will be replaced; the <code>spawn*()</code> function will not return. Availability: Windows. New in version 1.6.

startfile(path)

Start a file with its associated application. This acts like double-clicking the file in Windows Explorer, or giving the file name as an argument to the **start** command from the interactive command shell: the file is opened with whatever application (if any) its extension is associated.

startfile() returns as soon as the associated application is launched. There is no option to wait for the application to close, and no way to retrieve the application's exit status. The *path* parameter is relative to the current directory. If you want to use an absolute path, make sure the first character is not a slash ('/'); the underlying Win32 ShellExecute() function doesn't work if it is. Use the os.path.normpath() function to ensure that the path is properly encoded for Win32. Availability: Windows. New in version 2.0.

${\tt system} (command)$

Execute the command (a string) in a subshell. This is implemented by calling the Standard C function system(), and has the same limitations. Changes to posix.environ, sys.stdin, etc. are not reflected in the environment of the executed command.

On UNIX, the return value is the exit status of the process encoded in the format specified for wait(). Note that POSIX does not specify the meaning of the return value of the C system() function, so the return value of the Python function is system-dependent.

On Windows, the return value is that returned by the system shell after running *command*, given by the Windows environment variable COMSPEC: on **command.com** systems (Windows 95, 98 and ME) this is always 0; on **cmd.exe** systems (Windows NT, 2000 and XP) this is the exit status of the command run; on systems using a non-native shell, consult your shell documentation.

Availability: Macintosh, UNIX, Windows.

times()

Return a 5-tuple of floating point numbers indicating accumulated (processor or other) times, in seconds. The items are: user time, system time, children's user time, children's system time, and elapsed real time since a fixed point in the past, in that order. See the UNIX manual page *times*(2) or the corresponding Windows Platform API documentation. Availability: Macintosh, UNIX, Windows.

wait()

Wait for completion of a child process, and return a tuple containing its pid and exit status indication: a 16-bit number, whose low byte is the signal number that killed the process, and whose high byte is the exit status (if the signal number is zero); the high bit of the low byte is set if a core file was produced. Availability: Macintosh, UNIX.

waitpid(pid, options)

The details of this function differ on UNIX and Windows.

On UNIX: Wait for completion of a child process given by process id *pid*, and return a tuple containing its process id and exit status indication (encoded as for wait()). The semantics of the call are affected by the value of the integer *options*, which should be 0 for normal operation.

If pid is greater than 0, waitpid() requests status information for that specific process. If pid is 0, the request is for the status of any child in the process group of the current process. If pid is -1, the request pertains to any child of the current process. If pid is less than -1, status is requested for any process in the process group -pid (the absolute value of pid).

On Windows: Wait for completion of a process given by process handle pid, and return a tuple containing pid, and its exit status shifted left by 8 bits (shifting makes cross-platform use of the function easier). A pid less than or equal to 0 has no special meaning on Windows, and raises an exception. The value of integer options has no effect. pid can refer to any process whose id is known, not necessarily a child process. The spawn () functions called with P_NOWAIT return suitable process handles.

WNOHANG

The option for waitpid() to return immediately if no child process status is available immediately. The function returns (0, 0) in this case. Availability: Macintosh, UNIX.

WCONTINUED

This option causes child processes to be reported if they have been continued from a job control stop since their status was last reported. Availability: Some UNIX systems. New in version 2.3.

WUNTRACED

This option causes child processes to be reported if they have been stopped but their current state has not been reported since they were stopped. Availability: Macintosh, UNIX. New in version 2.3.

The following functions take a process status code as returned by system(), wait(), or waitpid() as a parameter. They may be used to determine the disposition of a process.

WCOREDUMP (status)

Returns True if a core dump was generated for the process, otherwise it returns False. Availability: Macintosh, UNIX. New in version 2.3.

WIFCONTINUED (status)

Returns True if the process has been continued from a job control stop, otherwise it returns False. Availability: UNIX. New in version 2.3.

WIFSTOPPED (status)

Returns True if the process has been stopped, otherwise it returns False. Availability: UNIX.

WIFSIGNALED (*status*)

Returns True if the process exited due to a signal, otherwise it returns False. Availability: Macintosh, UNIX.

WIFEXITED(status)

Returns True if the process exited using the exit(2) system call, otherwise it returns False. Availability: Macintosh, UNIX.

WEXITSTATUS (status)

If WIFEXITED (*status*) is true, return the integer parameter to the *exit*(2) system call. Otherwise, the return value is meaningless. Availability: Macintosh, UNIX.

WSTOPSIG(status)

Return the signal which caused the process to stop. Availability: Macintosh, UNIX.

WTERMSIG (status)

Return the signal which caused the process to exit. Availability: Macintosh, UNIX.

6.1.6 Miscellaneous System Information

confstr(name)

Return string-valued system configuration values. *name* specifies the configuration value to retrieve; it may be a string which is the name of a defined system value; these names are specified in a number of standards (POSIX, UNIX 95, UNIX 98, and others). Some platforms define additional names as well. The names known to the host operating system are given in the confstr_names dictionary. For configuration variables not included in that mapping, passing an integer for *name* is also accepted. Availability: Macintosh, UNIX.

If the configuration value specified by *name* isn't defined, the empty string is returned.

If *name* is a string and is not known, ValueError is raised. If a specific value for *name* is not supported by the host system, even if it is included in confstr_names, an OSError is raised with errno.EINVAL for the error number.

confstr_names

Dictionary mapping names accepted by confstr() to the integer values defined for those names by the host operating system. This can be used to determine the set of names known to the system. Availability: Macintosh, UNIX.

getloadavg()

Return the number of processes in the system run queue averaged over the last 1, 5, and 15 minutes or raises OSError if the load average was unobtainable.

New in version 2.3.

sysconf(name)

Return integer-valued system configuration values. If the configuration value specified by *name* isn't defined, -1 is returned. The comments regarding the *name* parameter for confstr() apply here as well; the dictionary that provides information on the known names is given by sysconf_names. Availability: Macintosh, UNIX.

sysconf_names

Dictionary mapping names accepted by sysconf() to the integer values defined for those names by the host operating system. This can be used to determine the set of names known to the system. Availability: Macintosh, UNIX.

The follow data values are used to support path manipulation operations. These are defined for all platforms.

Higher-level operations on pathnames are defined in the os.path module.

curdir

The constant string used by the operating system to refer to the current directory. For example: '.' for POSIX or ':' for Mac OS 9. Also available via os.path.

pardir

The constant string used by the operating system to refer to the parent directory. For example: '..' for POSIX or '::' for Mac OS 9. Also available via os.path.

sep

The character used by the operating system to separate pathname components, for example, '/' for POSIX or ':' for Mac OS 9. Note that knowing this is not sufficient to be able to parse or concatenate pathnames — use os.path.split() and os.path.join() — but it is occasionally useful. Also available via os.path.

altsep

An alternative character used by the operating system to separate pathname components, or None if only one separator character exists. This is set to '/' on Windows systems where sep is a backslash. Also

available via os.path.

extsep

The character which separates the base filename from the extension; for example, the '.' in 'os.py'. Also available via os.path. New in version 2.2.

pathsep

The character conventionally used by the operating system to separate search path components (as in PATH), such as ':' for POSIX or ';' for Windows. Also available via os.path.

defpath

The default search path used by exec*p*() and spawn*p*() if the environment doesn't have a 'PATH' key. Also available via os.path.

linesep

The string used to separate (or, rather, terminate) lines on the current platform. This may be a single character, such as ' \n' for POSIX or ' \n' for Mac OS, or multiple characters, for example, ' \n' for Windows

devnull

The file path of the null device. For example: '/dev/null' for POSIX or 'Dev:Nul' for Mac OS 9. Also available via os.path. New in version 2.4.

6.1.7 Miscellaneous Functions

urandom(n)

Return a string of *n* random bytes suitable for cryptographic use.

This function returns random bytes from an OS-specific randomness source. The returned data should be unpredictable enough for cryptographic applications, though its exact quality depends on the OS implementation. On a UNIX-like system this will query /dev/urandom, and on Windows it will use CryptGenRandom. If a randomness source is not found, NotImplementedError will be raised. New in version 2.4.

6.2 os.path — Common pathname manipulations

This module implements some useful functions on pathnames.

Warning: On Windows, many of these functions do not properly support UNC pathnames. splitunc() and ismount() do handle them correctly.

abspath(path)

Return a normalized absolutized version of the pathname path. On most platforms, this is equivalent to normpath(join(os.getcwd(), path)). New in version 1.5.2.

basename(path)

Return the base name of pathname *path*. This is the second half of the pair returned by split(*path*). Note that the result of this function is different from the UNIX **basename** program; where **basename** for '/foo/bar/' returns 'bar', the basename() function returns an empty string('').

commonprefix(list)

Return the longest path prefix (taken character-by-character) that is a prefix of all paths in *list*. If *list* is empty, return the empty string (''). Note that this may return invalid paths because it works a character at a time.

dirname(path)

Return the directory name of pathname *path*. This is the first half of the pair returned by split (*path*).

exists(path)

Return True if path refers to an existing path. Returns False for broken symbolic links.

lexists(path)

Return True if *path* refers to an existing path. Returns True for broken symbolic links. Equivalent to exists() on platforms lacking os.lstat(). New in version 2.4.

expanduser(path)

On UNIX, return the argument with an initial component of "" or "" user" replaced by that user's home directory. An initial "" is replaced by the environment variable HOME if it is set; otherwise the current user's home directory is looked up in the password directory through the built-in module pwd. An initial "user" is looked up directly in the password directory.

On Windows, only "~" is supported; it is replaced by the environment variable HOME or by a combination of HOMEDRIVE and HOMEPATH.

If the expansion fails or if the path does not begin with a tilde, the path is returned unchanged.

expandvars(path)

Return the argument with environment variables expanded. Substrings of the form '\$name' or '\${name}' are replaced by the value of environment variable name. Malformed variable names and references to non-existing variables are left unchanged.

getatime(path)

Return the time of last access of *path*. The return value is a number giving the number of seconds since the epoch (see the time module). Raise os.error if the file does not exist or is inaccessible. New in version 1.5.2. Changed in version 2.3: If os.stat_float_times() returns True, the result is a floating point number.

getmtime(path)

Return the time of last modification of *path*. The return value is a number giving the number of seconds since the epoch (see the time module). Raise os.error if the file does not exist or is inaccessible. New in version 1.5.2. Changed in version 2.3: If os.stat_float_times() returns True, the result is a floating point number.

getctime(path)

Return the system's ctime which, on some systems (like UNIX) is the time of the last change, and, on others (like Windows), is the creation time for *path*. The return value is a number giving the number of seconds since the epoch (see the time module). Raise os.error if the file does not exist or is inaccessible. New in version 2.3.

getsize(path)

Return the size, in bytes, of *path*. Raise os.error if the file does not exist or is inaccessible. New in version 1.5.2.

isabs(path)

Return True if *path* is an absolute pathname (begins with a slash).

isfile(path)

Return True if *path* is an existing regular file. This follows symbolic links, so both islink() and isfile() can be true for the same path.

isdir(path)

Return True if *path* is an existing directory. This follows symbolic links, so both islink() and isdir() can be true for the same path.

islink(path)

Return True if *path* refers to a directory entry that is a symbolic link. Always False if symbolic links are not supported.

ismount(path)

Return True if pathname *path* is a *mount point*: a point in a file system where a different file system has been mounted. The function checks whether *path*'s parent, '*path*|...', is on a different device than *path*, or whether '*path*|...' and *path* point to the same i-node on the same device — this should detect mount points for all UNIX and POSIX variants.

join(path1[, path2[, ...]))

Joins one or more path components intelligently. If any component is an absolute path, all previous components are thrown away, and joining continues. The return value is the concatenation of path1, and optionally path2, etc., with exactly one directory separator (os.sep) inserted between components, unless path2 is empty. Note that on Windows, since there is a current directory for each drive, os.path.join("c:", "foo") represents a path relative to the current directory on drive 'C:' ('c:foo'), not 'c:\\foo'.

normcase(path)

Normalize the case of a pathname. On UNIX, this returns the path unchanged; on case-insensitive filesystems, it converts the path to lowercase. On Windows, it also converts forward slashes to backward slashes.

normpath(path)

Normalize a pathname. This collapses redundant separators and up-level references so that A/B, A/./B and A/foo/../B all become A/B. It does not normalize the case (use normase()) for that). On Windows, it converts forward slashes to backward slashes. It should be understood that this may change the meaning of the path if it contains symbolic links!

realpath(path)

Return the canonical path of the specified filename, eliminating any symbolic links encountered in the path. Availability: UNIX. New in version 2.2.

samefile(path1, path2)

Return True if both pathname arguments refer to the same file or directory (as indicated by device number and i-node number). Raise an exception if a os.stat() call on either pathname fails. Availability: Macintosh, UNIX.

sameopenfile(fp1, fp2)

Return True if the file objects fp1 and fp2 refer to the same file. The two file objects may represent different file descriptors. Availability: Macintosh, UNIX.

samestat(stat1, stat2)

Return True if the stat tuples *stat1* and *stat2* refer to the same file. These structures may have been returned by fstat(), lstat(), or stat(). This function implements the underlying comparison used by samefile() and sameopenfile(). Availability: Macintosh, UNIX.

split(path)

Split the pathname *path* into a pair, (*head*, *tail*) where *tail* is the last pathname component and *head* is everything leading up to that. The *tail* part will never contain a slash; if *path* ends in a slash, *tail* will be empty. If there is no slash in *path*, *head* will be empty. If *path* is empty, both *head* and *tail* are empty. Trailing slashes are stripped from *head* unless it is the root (one or more slashes only). In nearly all cases, <code>join(head, tail)</code> equals *path* (the only exception being when there were multiple slashes separating *head* from *tail*).

splitdrive(path)

Split the pathname *path* into a pair (*drive*, *tail*) where *drive* is either a drive specification or the empty string. On systems which do not use drive specifications, *drive* will always be the empty string. In all cases, *drive* + *tail* will be the same as *path*. New in version 1.3.

splitext(path)

Split the pathname path into a pair (root, ext) such that root + ext == path, and ext is empty or begins with a period and contains at most one period.

splitunc(path)

Split the pathname path into a pair (unc, rest) so that unc is the UNC mount point (such as $r' \neq mount'$), if present, and rest the rest of the path (such as $r' \neq mount'$). For paths containing drive letters, unc will always be the empty string. Availability: Windows.

walk(path, visit, arg)

Calls the function *visit* with arguments (*arg*, *dirname*, *names*) for each directory in the directory tree rooted at *path* (including *path* itself, if it is a directory). The argument *dirname* specifies the visited directory, the argument *names* lists the files in the directory (gotten from os.listdir(*dirname*)). The *visit* function may modify *names* to influence the set of directories visited below *dirname*, e.g. to avoid visiting certain parts of the tree. (The object referred to by *names* must be modified in place, using del or slice assignment.)

Note: Symbolic links to directories are not treated as subdirectories, and that walk() therefore will not visit them. To visit linked directories you must identify them with os.path.islink(*file*) and os.path.isdir(*file*), and invoke walk() as necessary.

Note: The newer os . walk () generator supplies similar functionality and can be easier to use.

supports_unicode_filenames

True if arbitrary Unicode strings can be used as file names (within limitations imposed by the file system), and if os.listdir() returns Unicode strings for a Unicode argument. New in version 2.3.

6.3 direache — Cached directory listings

The direache module defines a function for reading directory listing using a cache, and cache invalidation using the *mtime* of the directory. Additionally, it defines a function to annotate directories by appending a slash.

The direache module defines the following functions:

listdir(path)

Return a directory listing of *path*, as gotten from os.listdir(). Note that unless *path* changes, further call to listdir() will not re-read the directory structure.

Note that the list returned should be regarded as read-only. (Perhaps a future version should change it to return a tuple?)

opendir(path)

Same as listdir(). Defined for backwards compatibility.

annotate(head, list)

Assume *list* is a list of paths relative to *head*, and append, in place, a '/' to each path which points to a directory.

```
>>> import dircache
>>> a = dircache.listdir('/')
>>> a = a[:] # Copy the return value so we can change 'a'
>>> a
['bin', 'boot', 'cdrom', 'dev', 'etc', 'floppy', 'home', 'initrd', 'lib', 'lost+
found', 'mnt', 'proc', 'root', 'sbin', 'tmp', 'usr', 'var', 'vmlinuz']
>>> dircache.annotate('/', a)
>>> a
['bin/', 'boot/', 'cdrom/', 'dev/', 'etc/', 'floppy/', 'home/', 'initrd/', 'lib/
', 'lost+found/', 'mnt/', 'proc/', 'root/', 'sbin/', 'tmp/', 'usr/', 'var/', 'vm
linuz']
```

6.4 stat — Interpreting stat() results

The stat module defines constants and functions for interpreting the results of os.stat(), os.fstat() and os.lstat() (if they exist). For complete details about the stat(), fstat() and lstat() calls, consult the documentation for your system.

The stat module defines the following functions to test for specific file types:

S_ISDIR(*mode*)

Return non-zero if the mode is from a directory.

$S_{ISCHR}(mode)$

Return non-zero if the mode is from a character special device file.

$S_ISBLK(mode)$

Return non-zero if the mode is from a block special device file.

S_ISREG(mode)

Return non-zero if the mode is from a regular file.

$S_{ISFIFO}(mode)$

Return non-zero if the mode is from a FIFO (named pipe).

$S_{ISLNK}(mode)$

Return non-zero if the mode is from a symbolic link.

S_ISSOCK(mode)

Return non-zero if the mode is from a socket.

Two additional functions are defined for more general manipulation of the file's mode:

S_IMODE(mode)

Return the portion of the file's mode that can be set by os.chmod()—that is, the file's permission bits, plus the sticky bit, set-group-id, and set-user-id bits (on systems that support them).

S_IFMT (mode)

Return the portion of the file's mode that describes the file type (used by the S_IS*() functions above).

Normally, you would use the os.path.is*() functions for testing the type of a file; the functions here are useful when you are doing multiple tests of the same file and wish to avoid the overhead of the stat() system call for each test. These are also useful when checking for information about a file that isn't handled by os.path, like the tests for block and character devices.

All the variables below are simply symbolic indexes into the 10-tuple returned by os.stat(), os.fstat() or os.lstat().

ST_MODE

Inode protection mode.

ST_INO

Inode number.

ST_DEV

Device inode resides on.

ST_NLINK

Number of links to the inode.

ST_UID

User id of the owner.

ST_GID

Group id of the owner.

ST SIZE

Size in bytes of a plain file; amount of data waiting on some special files.

ST ATIME

Time of last access.

ST MTIME

Time of last modification.

ST_CTIME

The "ctime" as reported by the operating system. On some systems (like UNIX) is the time of the last metadata change, and, on others (like Windows), is the creation time (see platform documentation for details).

The interpretation of "file size" changes according to the file type. For plain files this is the size of the file in bytes. For FIFOs and sockets under most flavors of UNIX (including Linux in particular), the "size" is the number of bytes waiting to be read at the time of the call to os.stat(), os.fstat(), or os.lstat(); this can sometimes be useful, especially for polling one of these special files after a non-blocking open. The meaning of the size field for other character and block devices varies more, depending on the implementation of the underlying system call.

Example:

```
import os, sys
from stat import *
def walktree(top, callback):
    '''recursively descend the directory tree rooted at top,
       calling the callback function for each regular file ^{\prime\prime\prime}
    for f in os.listdir(top):
        pathname = os.path.join(top, f)
        mode = os.stat(pathname)[ST_MODE]
        if S_ISDIR(mode):
            # It's a directory, recurse into it
            walktree(pathname, callback)
        elif S_ISREG(mode):
            # It's a file, call the callback function
            callback(pathname)
        else:
            # Unknown file type, print a message
            print 'Skipping %s' % pathname
def visitfile(file):
    print 'visiting', file
if __name__ == '__main__':
    walktree(sys.argv[1], visitfile)
```

6.5 statcache — An optimization of os.stat()

Deprecated since release 2.2. Use os.stat() directly instead of using the cache; the cache introduces a very high level of fragility in applications using it and complicates application code with the addition of cache management support.

The statcache module provides a simple optimization to os.stat(): remembering the values of previous invocations.

The statcache module defines the following functions:

```
stat(path)
```

This is the main module entry-point. Identical for os.stat(), except for remembering the result for future invocations of the function.

The rest of the functions are used to clear the cache, or parts of it.

```
reset()
```

Clear the cache: forget all results of previous stat() calls.

```
forget(path)
```

Forget the result of stat (path), if any.

forget_prefix(prefix)

Forget all results of stat (path) for path starting with prefix.

forget_dir(prefix)

Forget all results of stat (path) for path a file in the directory prefix, including stat (prefix).

forget_except_prefix(prefix)

Similar to forget_prefix(), but for all *path* values *not* starting with *prefix*.

Example:

```
>>> import os, statcache
>>> statcache.stat('.')
(16893, 2049, 772, 18, 1000, 1000, 2048, 929609777, 929609777, 929609777)
>>> os.stat('.')
(16893, 2049, 772, 18, 1000, 1000, 2048, 929609777, 929609777, 929609777)
```

6.6 statvfs — Constants used with os.statvfs()

The statvfs module defines constants so interpreting the result if os.statvfs(), which returns a tuple, can be made without remembering "magic numbers." Each of the constants defined in this module is the *index* of the entry in the tuple returned by os.statvfs() that contains the specified information.

F BSIZE

Preferred file system block size.

F_FRSIZE

Fundamental file system block size.

F_BLOCKS

Total number of blocks in the filesystem.

F_BFREE

Total number of free blocks.

F_BAVAIL

Free blocks available to non-super user.

F_FILES

Total number of file nodes.

F_FFREE

Total number of free file nodes.

F_FAVAIL

Free nodes available to non-super user.

F_FLAG

Flags. System dependent: see ${\tt statvfs}($) man page.

$F_NAMEMAX$

Maximum file name length.

6.7 filecmp — File and Directory Comparisons

The filecmp module defines functions to compare files and directories, with various optional time/correctness trade-offs.

The filecmp module defines the following functions:

```
cmp(f1, f2[, shallow[, use\_statcache]])
```

Compare the files named fI and f2, returning True if they seem equal, False otherwise.

Unless *shallow* is given and is false, files with identical os.stat() signatures are taken to be equal. Changed in version 2.3: *use_statcache* is obsolete and ignored..

Files that were compared using this function will not be compared again unless their os.stat() signature changes.

Note that no external programs are called from this function, giving it portability and efficiency.

```
cmpfiles(dir1, dir2, common[, shallow[, use_statcache]])
```

Returns three lists of file names: match, mismatch, errors. match contains the list of files match in both

directories, *mismatch* includes the names of those that don't, and *errros* lists the names of files which could not be compared. Files may be listed in *errors* because the user may lack permission to read them or many other reasons, but always that the comparison could not be done for some reason.

The *common* parameter is a list of file names found in both directories. The *shallow* and *use_statcache* parameters have the same meanings and default values as for filecmp.cmp().

Example:

```
>>> import filecmp
>>> filecmp.cmp('libundoc.tex', 'libundoc.tex')
True
>>> filecmp.cmp('libundoc.tex', 'lib.tex')
False
```

6.7.1 The dircmp class

dircmp instances are built using this constructor:

```
class dircmp (a, b[, ignore[, hide]])
```

Construct a new directory comparison object, to compare the directories *a* and *b*. *ignore* is a list of names to ignore, and defaults to ['RCS', 'CVS', 'tags']. *hide* is a list of names to hide, and defaults to [os.curdir, os.pardir].

The dircmp class provides the following methods:

report()

Print (to sys.stdout) a comparison between a and b.

report_partial_closure()

Print a comparison between a and b and common immediate subdirectories.

report_full_closure()

Print a comparison between a and b and common subdirectories (recursively).

The dircmp offers a number of interesting attributes that may be used to get various bits of information about the directory trees being compared.

Note that via $__getattr__($) hooks, all attributes are computed lazily, so there is no speed penalty if only those attributes which are lightweight to compute are used.

left_list

Files and subdirectories in a, filtered by hide and ignore.

right_list

Files and subdirectories in b, filtered by hide and ignore.

common

Files and subdirectories in both a and b.

left_only

Files and subdirectories only in a.

right_only

Files and subdirectories only in b.

common_dirs

Subdirectories in both a and b.

common_files

Files in both a and b

common_funny

Names in both a and b, such that the type differs between the directories, or names for which os.stat() reports an error.

same_files

Files which are identical in both a and b.

diff_files

Files which are in both a and b, whose contents differ.

funny_files

Files which are in both a and b, but could not be compared.

subdirs

A dictionary mapping names in common_dirs to dircmp objects.

6.8 subprocess — Subprocess management

New in version 2.4.

The subprocess module allows you to spawn new processes, connect to their input/output/error pipes, and obtain their return codes. This module intends to replace several other, older modules and functions, such as:

```
os.system
os.spawn*
os.popen*
popen2.*
commands.*
```

Information about how the subprocess module can be used to replace these modules and functions can be found in the following sections.

6.8.1 Using the subprocess Module

This module defines one class called Popen:

Arguments are:

args should be a string, or a sequence of program arguments. The program to execute is normally the first item in the args sequence or string, but can be explicitly set by using the executable argument.

On UNIX, with *shell=False* (default): In this case, the Popen class uses os.execvp() to execute the child program. *args* should normally be a sequence. A string will be treated as a sequence with the string as the only item (the program to execute).

On UNIX, with *shell=True*: If args is a string, it specifies the command string to execute through the shell. If *args* is a sequence, the first item specifies the command string, and any additional items will be treated as additional shell arguments.

On Windows: the Popen class uses CreateProcess() to execute the child program, which operates on strings. If args is a sequence, it will be converted to a string using the <code>list2cmdline</code> method. Please note that not all MS Windows applications interpret the command line the same way: <code>list2cmdline</code> is designed for applications using the same rules as the MS C runtime.

bufsize, if given, has the same meaning as the corresponding argument to the built-in open() function: 0 means unbuffered, 1 means line buffered, any other positive value means use a buffer of (approximately) that size. A negative bufsize means to use the system default, which usually means fully buffered. The default value for bufsize is 0 (unbuffered).

The *executable* argument specifies the program to execute. It is very seldom needed: Usually, the program to execute is defined by the *args* argument. If *shell=True*, the *executable* argument specifies which shell to use. On UNIX, the default shell is /bin/sh. On Windows, the default shell is specified by the COMSPEC environment variable.

stdin, stdout and stderr specify the executed programs' standard input, standard output and standard error file handles, respectively. Valid values are PIPE, an existing file descriptor (a positive integer), an existing file object, and None. PIPE indicates that a new pipe to the child should be created. With None, no redirection will occur; the child's file handles will be inherited from the parent. Additionally, stderr can be STDOUT, which indicates that the stderr data from the applications should be captured into the same file handle as for stdout.

If *preexec_fn* is set to a callable object, this object will be called in the child process just before the child is executed.

If close_fds is true, all file descriptors except 0, 1 and 2 will be closed before the child process is executed.

If shell is True, the specified command will be executed through the shell.

If cwd is not None, the current directory will be changed to cwd before the child is executed.

If env is not None, it defines the environment variables for the new process.

If $universal_newlines$ is True, the file objects stdout and stderr are opened as a text files, but lines may be terminated by any of '\n', the Unix end-of-line convention, '\r', the Macintosh convention or '\r\n', the Windows convention. All of these external representations are seen as '\n' by the Python program. **Note:** This feature is only available if Python is built with universal newline support (the default). Also, the newlines attribute of the file objects stdout, stdin and stderr are not updated by the communicate() method.

The *startupinfo* and *creationflags*, if given, will be passed to the underlying CreateProcess() function. They can specify things such as appearance of the main window and priority for the new process. (Windows only)

Convenience Functions

This module also defines one shortcut function:

```
call(*args, **kwargs)
```

Run command with arguments. Wait for command to complete, then return the returncode attribute.

The arguments are the same as for the Popen constructor. Example:

```
retcode = call(["ls", "-l"])
```

Exceptions

Exceptions raised in the child process, before the new program has started to execute, will be re-raised in the parent. Additionally, the exception object will have one extra attribute called child_traceback, which is a string containing traceback information from the childs point of view.

The most common exception raised is OSError. This occurs, for example, when trying to execute a non-existent file. Applications should prepare for OSError exceptions.

A ValueError will be raised if Popen is called with invalid arguments.

Security

Unlike some other popen functions, this implementation will never call /bin/sh implicitly. This means that all characters, including shell metacharacters, can safely be passed to child processes.

6.8.2 Popen Objects

Instances of the Popen class have the following methods:

```
poll()
```

Check if child process has terminated. Returns returncode attribute.

wait()

Wait for child process to terminate. Returns returncode attribute.

communicate(input=None)

Interact with process: Send data to stdin. Read data from stdout and stderr, until end-of-file is reached. Wait for process to terminate. The optional *input* argument should be a string to be sent to the child process, or None, if no data should be sent to the child.

communicate() returns a tuple (stdout, stderr).

Note: The data read is buffered in memory, so do not use this method if the data size is large or unlimited.

The following attributes are also available:

stdin

If the *stdin* argument is PIPE, this attribute is a file object that provides input to the child process. Otherwise, it is None.

stdout

If the *stdout* argument is PIPE, this attribute is a file object that provides output from the child process. Otherwise, it is None.

stderr

If the *stderr* argument is PIPE, this attribute is file object that provides error output from the child process. Otherwise, it is None.

pid

The process ID of the child process.

returncode

The child return code. A None value indicates that the process hasn't terminated yet. A negative value -N indicates that the child was terminated by signal N (UNIX only).

6.8.3 Replacing Older Functions with the subprocess Module

In this section, "a == i, b" means that b can be used as a replacement for a.

Note: All functions in this section fail (more or less) silently if the executed program cannot be found; this module raises an OSError exception.

In the following examples, we assume that the subprocess module is imported with "from subprocess import *".

Replacing /bin/sh shell backquote

```
output='mycmd myarg'
==>
output = Popen(["mycmd", "myarg"], stdout=PIPE).communicate()[0]
```

Replacing shell pipe line

```
output='dmesg | grep hda'
==>
p1 = Popen(["dmesg"], stdout=PIPE)
p2 = Popen(["grep", "hda"], stdin=p1.stdout, stdout=PIPE)
output = p2.communicate()[0]
```

Replacing os.system()

```
sts = os.system("mycmd" + " myarg")
==>
p = Popen("mycmd" + " myarg", shell=True)
sts = os.waitpid(p.pid, 0)
```

Notes:

- Calling the program through the shell is usually not required.
- It's easier to look at the returncode attribute than the exit status.

A more realistic example would look like this:

```
try:
    retcode = call("mycmd" + " myarg", shell=True)
    if retcode < 0:
        print >>sys.stderr, "Child was terminated by signal", -retcode
    else:
        print >>sys.stderr, "Child returned", retcode
except OSError, e:
    print >>sys.stderr, "Execution failed:", e
```

Replacing os.spawn*

P_NOWAIT example:

```
pid = os.spawnlp(os.P_NOWAIT, "/bin/mycmd", "mycmd", "myarg")
==>
pid = Popen(["/bin/mycmd", "myarg"]).pid
```

P_WAIT example:

```
retcode = os.spawnlp(os.P_WAIT, "/bin/mycmd", "mycmd", "myarg")
==>
retcode = call(["/bin/mycmd", "myarg"])
```

Vector example:

```
os.spawnvp(os.P_NOWAIT, path, args)
==>
Popen([path] + args[1:])
```

Environment example:

```
os.spawnlpe(os.P_NOWAIT, "/bin/mycmd", "mycmd", "myarg", env)
==>
Popen(["/bin/mycmd", "myarg"], env={"PATH": "/usr/bin"})
```

Replacing os.popen*

```
pipe = os.popen(cmd, mode='r', bufsize)
==>
pipe = Popen(cmd, shell=True, bufsize=bufsize, stdout=PIPE).stdout
     pipe = os.popen(cmd, mode='w', bufsize)
     ==>
     pipe = Popen(cmd, shell=True, bufsize=bufsize, stdin=PIPE).stdin
     (child_stdin, child_stdout) = os.popen2(cmd, mode, bufsize)
     p = Popen(cmd, shell=True, bufsize=bufsize,
               stdin=PIPE, stdout=PIPE, close_fds=True)
     (child_stdin, child_stdout) = (p.stdin, p.stdout)
     (child_stdin,
      child_stdout,
      child_stderr) = os.popen3(cmd, mode, bufsize)
     p = Popen(cmd, shell=True, bufsize=bufsize,
               stdin=PIPE, stdout=PIPE, stderr=PIPE, close_fds=True)
     (child_stdin,
      child_stdout,
      child_stderr) = (p.stdin, p.stdout, p.stderr)
     (child_stdin, child_stdout_and_stderr) = os.popen4(cmd, mode, bufsize)
     p = Popen(cmd, shell=True, bufsize=bufsize,
               stdin=PIPE, stdout=PIPE, stderr=STDOUT, close_fds=True)
     (child_stdin, child_stdout_and_stderr) = (p.stdin, p.stdout)
```

Replacing popen2.*

Note: If the cmd argument to popen2 functions is a string, the command is executed through /bin/sh. If it is a list, the command is directly executed.

The popen2.Popen3 and popen3.Popen4 basically works as subprocess.Popen, except that:

- subprocess. Popen raises an exception if the execution fails
- the *capturestderr* argument is replaced with the *stderr* argument.
- stdin=PIPE and stdout=PIPE must be specified.
- popen2 closes all file descriptors by default, but you have to specify close_fds=True with subprocess.Popen.

6.9 popen2 — Subprocesses with accessible I/O streams

This module allows you to spawn processes and connect to their input/output/error pipes and obtain their return codes under UNIX and Windows.

Note that starting with Python 2.0, this functionality is available using functions from the os module which have the same names as the factory functions here, but the order of the return values is more intuitive in the os module variants.

The primary interface offered by this module is a trio of factory functions. For each of these, if *bufsize* is specified, it specifies the buffer size for the I/O pipes. *mode*, if provided, should be the string 'b' or 't'; on Windows this is needed to determine whether the file objects should be opened in binary or text mode. The default value for *mode* is 't'.

On UNIX, *cmd* may be a sequence, in which case arguments will be passed directly to the program without shell intervention (as with os.spawnv()). If *cmd* is a string it will be passed to the shell (as with os.system()).

The only way to retrieve the return codes for the child processes is by using the poll() or wait() methods on the Popen3 and Popen4 classes; these are only available on UNIX. This information is not available when using the popen2(), popen3(), and popen4() functions, or the equivalent functions in the os module. (Note that the tuples returned by the os module's functions are in a different order from the ones returned by the popen2 module.)

```
popen2(cmd[, bufsize[, mode]])
```

Executes *cmd* as a sub-process. Returns the file objects (*child_stdout*, *child_stdin*).

```
popen3 (cmd, bufsize, mode))
```

Executes cmd as a sub-process. Returns the file objects (child_stdout, child_stdin, child_stderr).

```
popen4 (cmd, bufsize, mode))
```

Executes *cmd* as a sub-process. Returns the file objects (*child_stdout_and_stderr*, *child_stdin*). New in version 2.0.

On UNIX, a class defining the objects returned by the factory functions is also available. These are not used for the Windows implementation, and are not available on that platform.

```
class Popen3 (cmd , capturestderr , bufsize )
```

This class represents a child process. Normally, Popen3 instances are created using the popen2() and popen3() factory functions described above.

If not using one of the helper functions to create Popen3 objects, the parameter *cmd* is the shell command to execute in a sub-process. The *capturestderr* flag, if true, specifies that the object should capture standard error output of the child process. The default is false. If the *bufsize* parameter is specified, it specifies the size of the I/O buffers to/from the child process.

```
class Popen4 (cmd[, bufsize])
```

Similar to Popen3, but always captures standard error into the same file object as standard output. These are typically created using popen4 (). New in version 2.0.

6.9.1 Popen3 and Popen4 Objects

Instances of the Popen3 and Popen4 classes have the following methods:

```
( ) 110q
```

Returns -1 if child process hasn't completed yet, or its return code otherwise.

wait()

Waits for and returns the status code of the child process. The status code encodes both the return code of the process and information about whether it exited using the exit() system call or died due to a signal. Functions to help interpret the status code are defined in the os module; see section 6.1.5 for the $W^*()$ family of functions.

The following attributes are also available:

fromchild.

A file object that provides output from the child process. For Popen4 instances, this will provide both the standard output and standard error streams.

tochild

A file object that provides input to the child process.

childerr

A file object that provides error output from the child process, if *capturestderr* was true for the constructor, otherwise None. This will always be None for Popen4 instances.

pid

The process ID of the child process.

6.9.2 Flow Control Issues

Any time you are working with any form of inter-process communication, control flow needs to be carefully thought out. This remains the case with the file objects provided by this module (or the os module equivalents).

When reading output from a child process that writes a lot of data to standard error while the parent is reading from the child's standard output, a deadlock can occur. A similar situation can occur with other combinations of reads and writes. The essential factors are that more than <code>_PC_PIPE_BUF</code> bytes are being written by one process in a blocking fashion, while the other process is reading from the other process, also in a blocking fashion.

There are several ways to deal with this situation.

The simplest application change, in many cases, will be to follow this model in the parent process:

```
import popen2
r, w, e = popen2.popen3('python slave.py')
e.readlines()
r.readlines()
r.close()
e.close()
w.close()
```

with code like this in the child:

```
import os
import sys

# note that each of these print statements
# writes a single long string

print >>sys.stderr, 400 * 'this is a test\n'
os.close(sys.stderr.fileno())
print >>sys.stdout, 400 * 'this is another test\n'
```

In particular, note that sys.stderr must be closed after writing all data, or readlines() won't return. Also note that os.close() must be used, as sys.stderr.close() won't close stderr (otherwise assigning to sys.stderr will silently close it, so no further errors can be printed).

Applications which need to support a more general approach should integrate I/O over pipes with their select() loops, or use separate threads to read each of the individual files provided by whichever popen*() function or Popen* class was used.

6.10 datetime — Basic date and time types

New in version 2.3.

The datetime module supplies classes for manipulating dates and times in both simple and complex ways. While date and time arithmetic is supported, the focus of the implementation is on efficient member extraction for output formatting and manipulation.

There are two kinds of date and time objects: "naive" and "aware". This distinction refers to whether the object has any notion of time zone, daylight saving time, or other kind of algorithmic or political time adjustment. Whether a naive datetime object represents Coordinated Universal Time (UTC), local time, or time in some other timezone is purely up to the program, just like it's up to the program whether a particular number represents metres, miles, or mass. Naive datetime objects are easy to understand and to work with, at the cost of ignoring some aspects of reality.

For applications requiring more, datetime and time objects have an optional time zone information member, tzinfo, that can contain an instance of a subclass of the abstract tzinfo class. These tzinfo objects capture information about the offset from UTC time, the time zone name, and whether Daylight Saving Time is in effect. Note that no concrete tzinfo classes are supplied by the datetime module. Supporting timezones at whatever level of detail is required is up to the application. The rules for time adjustment across the world are more political than rational, and there is no standard suitable for every application.

The datetime module exports the following constants:

MINYEAR

The smallest year number allowed in a date or datetime object. MINYEAR is 1.

MAXYEAR

The largest year number allowed in a date or datetime object. MAXYEAR is 9999.

See Also:

Module calendar (section 5.19):

General calendar related functions.

Module time (section 6.11):

Time access and conversions.

6.10.1 Available Types

class date

An idealized naive date, assuming the current Gregorian calendar always was, and always will be, in effect. Attributes: year, month, and day.

class time

An idealized time, independent of any particular day, assuming that every day has exactly 24*60*60 seconds (there is no notion of "leap seconds" here). Attributes: hour, minute, second, microsecond, and tzinfo.

class datetime

A combination of a date and a time. Attributes: year, month, day, hour, minute, second, microsecond, and tzinfo.

class timedelta

A duration expressing the difference between two date, time, or datetime instances to microsecond resolution.

class tzinfo

An abstract base class for time zone information objects. These are used by the datetime and time

classes to provide a customizable notion of time adjustment (for example, to account for time zone and/or daylight saving time).

Objects of these types are immutable.

Objects of the date type are always naive.

An object d of type time or datetime may be naive or aware. d is aware if d.tzinfo is not None and d.tzinfo.utcoffset(d) does not return None. If d.tzinfo is None, or if d.tzinfo is not None but d.tzinfo.utcoffset(d) returns None, d is naive.

The distinction between naive and aware doesn't apply to timedelta objects.

Subclass relationships:

```
object
    timedelta
    tzinfo
    time
    date
    datetime
```

6.10.2 timedelta Objects

A timedelta object represents a duration, the difference between two dates or times.

```
class timedelta ([days[, seconds[, microseconds[, milliseconds[, minutes[, hours[, weeks]]]]]]]]) All arguments are optional and default to 0. Arguments may be ints, longs, or floats, and may be positive or negative.
```

Only days, seconds and microseconds are stored internally. Arguments are converted to those units:

- •A millisecond is converted to 1000 microseconds.
- •A minute is converted to 60 seconds.
- •An hour is converted to 3600 seconds.
- •A week is converted to 7 days.

and days, seconds and microseconds are then normalized so that the representation is unique, with

```
    •0 <= microseconds < 1000000</li>
    •0 <= seconds < 3600*24 (the number of seconds in one day)</li>
    •-999999999 <= days <= 999999999</li>
```

If any argument is a float and there are fractional microseconds, the fractional microseconds left over from all arguments are combined and their sum is rounded to the nearest microsecond. If no argument is a float, the conversion and normalization processes are exact (no information is lost).

If the normalized value of days lies outside the indicated range, OverflowError is raised.

Note that normalization of negative values may be surprising at first. For example,

```
>>> d = timedelta(microseconds=-1)
>>> (d.days, d.seconds, d.microseconds)
(-1, 86399, 999999)
```

Class attributes are:

min

The most negative timedelta object, timedelta (-99999999).

max

The most positive timedelta object, timedelta(days=9999999999999, hours=23, minutes=59, seconds=59, microseconds=999999).

resolution

The smallest possible difference between non-equal timedelta objects, timedelta(microseconds=1).

Note that, because of normalization, timedelta.max >-timedelta.min. -timedelta.max is not representable as a timedelta object.

Instance attributes (read-only):

Attribute	Value
days	Between -999999999 and 999999999 inclusive
seconds	Between 0 and 86399 inclusive
microseconds	Between 0 and 999999 inclusive

Supported operations:

Operation	Result
t1 = t2 + t3	Sum of $t2$ and $t3$. Afterwards $t1-t2 == t3$ and $t1-t3 == t2$ are true. (1)
t1 = t2 - t3	Difference of $t2$ and $t3$. Afterwards $t1 == t2 - t3$ and $t2 == t1 + t3$ are true. (1)
t1 = t2 * i or t1 = i * t2	Delta multiplied by an integer or long. Afterwards $t1 // i == t2$ is true, provided i $! = 0$.
	In general, $tl * i == tl * (i-1) + tl$ is true. (1)
t1 = t2 // i	The floor is computed and the remainder (if any) is thrown away. (3)
+t1	Returns a timedelta object with the same value. (2)
-t1	equivalent to timedelta(- $t1.days$, - $t1.seconds$, - $t1.microseconds$), and to $t1*$ -1. (1)(4)
abs(<i>t</i>)	equivalent to $+t$ when t.days $>= 0$, and to $-t$ when t.days $< 0. (2)$

Notes:

- (1) This is exact, but may overflow.
- (2) This is exact, and cannot overflow.
- (3) Division by 0 raises ZeroDivisionError.
- (4) -timedelta.max is not representable as a timedelta object.

In addition to the operations listed above timedelta objects support certain additions and subtractions with date and datetime objects (see below).

Comparisons of timedelta objects are supported with the timedelta object representing the smaller duration considered to be the smaller timedelta. In order to stop mixed-type comparisons from falling back to the default comparison by object address, when a timedelta object is compared to an object of a different type, TypeError is raised unless the comparison is == or !=. The latter cases return False or True, respectively.

 $\label{timedelta} \begin{tabular}{l}{timedelta objects are hashable (usable as dictionary keys), support efficient pickling, and in Boolean contexts, a timedelta object is considered to be true if and only if it isn't equal to timedelta(0).} \end{timedelta}$

6.10.3 date Objects

A date object represents a date (year, month and day) in an idealized calendar, the current Gregorian calendar indefinitely extended in both directions. January 1 of year 1 is called day number 1, January 2 of year 1 is called day number 2, and so on. This matches the definition of the "proleptic Gregorian" calendar in Dershowitz and Reingold's book *Calendrical Calculations*, where it's the base calendar for all computations. See the book for algorithms for converting between proleptic Gregorian ordinals and many other calendar systems.

class date(year, month, day)

All arguments are required. Arguments may be ints or longs, in the following ranges:

```
●MINYEAR <= year <= MAXYEAR
```

- ●1 <= *month* <= 12
- •1 <= day <= number of days in the given month and year

If an argument outside those ranges is given, ValueError is raised.

Other constructors, all class methods:

today()

Return the current local date. This is equivalent to date.fromtimestamp(time.time()).

fromtimestamp(timestamp)

Return the local date corresponding to the POSIX timestamp, such as is returned by time.time(). This may raise ValueError, if the timestamp is out of the range of values supported by the platform C localtime() function. It's common for this to be restricted to years from 1970 through 2038. Note that on non-POSIX systems that include leap seconds in their notion of a timestamp, leap seconds are ignored by fromtimestamp().

fromordinal(ordinal)

Return the date corresponding to the proleptic Gregorian ordinal, where January 1 of year 1 has ordinal 1. ValueError is raised unless 1 <= ordinal <= date.max.toordinal(). For any date d, date.fromordinal(d.toordinal()) == d.

Class attributes:

min

The earliest representable date, date(MINYEAR, 1, 1).

max

The latest representable date, date (MAXYEAR, 12, 31).

resolution

The smallest possible difference between non-equal date objects, timedelta(days=1).

Instance attributes (read-only):

year

Between MINYEAR and MAXYEAR inclusive.

month

Between 1 and 12 inclusive.

day

Between 1 and the number of days in the given month of the given year.

Supported operations:

Operation	Result
date2 = date1 + timedelta	date2 is timedelta.days days removed from date1. (1)
date2 = date1 - timedelta	Computes $date2$ such that $date2 + timedelta == date1$. (2)
timedelta = date1 - date2	(3)
date1 < date2	date1 is considered less than date2 when date1 precedes date2 in time. (4)

Notes:

- (1) date2 is moved forward in time if timedelta.days > 0, or backward if timedelta.days < 0. Afterward date2 date1 == timedelta.days. timedelta.seconds and timedelta.microseconds are ignored.

 OverflowError is raised if date2.year would be smaller than MINYEAR or larger than MAXYEAR.
- (2) This isn't quite equivalent to date1 + (-timedelta), because -timedelta in isolation can overflow in cases where date1 timedelta does not. *timedelta*.seconds and *timedelta*.microseconds are ignored.

- (3) This is exact, and cannot overflow. timedelta.seconds and timedelta.microseconds are 0, and date2 + timedelta == date1 after.
- (4) In other words, date1 < date2 if and only if date1.toordinal() < date2.toordinal(). In order to stop comparison from falling back to the default scheme of comparing object addresses, date comparison normally raises TypeError if the other comparand isn't also a date object. However, NotImplemented is returned instead if the other comparand has a timetuple attribute. This hook gives other kinds of date objects a chance at implementing mixed-type comparison. If not, when a date object is compared to an object of a different type, TypeError is raised unless the comparison is == or !=. The latter cases return False or True, respectively.</p>

Dates can be used as dictionary keys. In Boolean contexts, all date objects are considered to be true.

Instance methods:

replace(year, month, day)

Return a date with the same value, except for those members given new values by whichever keyword arguments are specified. For example, if d == date(2002, 12, 31), then d.replace(day=26) == date(2002, 12, 26).

timetuple()

Return a time.struct_time such as returned by time.localtime(). The hours, minutes and seconds are 0, and the DST flag is -1. d.timetuple() is equivalent to time.struct_time((d.year, d.month, d.day, 0, 0, 0, d.weekday(), d.toordinal() - date(d.year, 1, 1).toordinal() + 1, -1))

toordinal()

Return the proleptic Gregorian ordinal of the date, where January 1 of year 1 has ordinal 1. For any date object d, date.fromordinal(d.toordinal()) == d.

weekday()

Return the day of the week as an integer, where Monday is 0 and Sunday is 6. For example, date(2002, 12, 4).weekday() == 2, a Wednesday. See also isoweekday().

isoweekday()

Return the day of the week as an integer, where Monday is 1 and Sunday is 7. For example, date(2002, 12, 4).isoweekday() == 3, a Wednesday. See also weekday(), isocalendar().

isocalendar()

Return a 3-tuple, (ISO year, ISO week number, ISO weekday).

The ISO calendar is a widely used variant of the Gregorian calendar. See http://www.phys.uu.nl/ vgent/calendar/isocalendar.htm for a good explanation.

The ISO year consists of 52 or 53 full weeks, and where a week starts on a Monday and ends on a Sunday. The first week of an ISO year is the first (Gregorian) calendar week of a year containing a Thursday. This is called week number 1, and the ISO year of that Thursday is the same as its Gregorian year.

For example, 2004 begins on a Thursday, so the first week of ISO year 2004 begins on Monday, 29 Dec 2003 and ends on Sunday, 4 Jan 2004, so that date(2003, 12, 29).isocalendar() == (2004, 1, 1) and date(2004, 1, 4).isocalendar() == (2004, 1, 7).

isoformat()

Return a string representing the date in ISO 8601 format, 'YYYY-MM-DD'. For example, date(2002, 12, 4).isoformat() == '2002-12-04'.

__str__()

For a date d, str(d) is equivalent to d. isoformat().

ctime()

Return a string representing the date, for example date(2002, 12, 4).ctime() == 'Wed Dec 4 00:00:00 2002'. d.ctime() is equivalent to time.ctime(time.mktime(d.timetuple())) on platforms where the native C ctime() function (which time.ctime() invokes, but which date.ctime() does not invoke) conforms to the C standard.

strftime(format)

Return a string representing the date, controlled by an explicit format string. Format codes referring to hours, minutes or seconds will see 0 values. See the section on strftime() behavior.

6.10.4 datetime Objects

A datetime object is a single object containing all the information from a date object and a time object. Like a date object, datetime assumes the current Gregorian calendar extended in both directions; like a time object, datetime assumes there are exactly 3600*24 seconds in every day.

Constructor:

class datetime (year, month, day[, hour[, minute[, second[, microsecond[, tzinfo]]]]]) The year, month and day arguments are required. tzinfo

utcfromtimestamp(timestamp)

Return the UTC datetime corresponding to the POSIX timestamp, with tzinfo None. This may raise ValueError, if the timestamp is out of the range of values supported by the platform C gmtime() function. It's common for this to be restricted to years in 1970 through 2038. See also fromtimestamp().

fromordinal(ordinal)

Return the datetime corresponding to the proleptic Gregorian ordinal, where January 1 of year 1 has ordinal 1. ValueError is raised unless 1 <= ordinal <= datetime.max.toordinal(). The hour, minute, second and microsecond of the result are all 0, and tzinfo is None.

combine(date, time)

Return a new datetime object whose date members are equal to the given date object's, and whose time and tzinfo members are equal to the given time object's. For any datetime object d, d == datetime.combine(d.date(), d.timetz()). If date is a datetime object, its time and tzinfo members are ignored.

Class attributes:

min

The earliest representable datetime, datetime (MINYEAR, 1, 1, tzinfo=None).

max

The latest representable datetime, datetime(MAXYEAR, 12, 31, 23, 59, 59, 999999, tzinfo=None).

resolution

The smallest possible difference between non-equal datetime objects, timedelta(microseconds=1).

Instance attributes (read-only):

year

Between MINYEAR and MAXYEAR inclusive.

month

Between 1 and 12 inclusive.

day

Between 1 and the number of days in the given month of the given year.

hour

In range (24).

minute

In range(60).

second

In range (60).

microsecond

In range(1000000).

tzinfo

The object passed as the tzinfo argument to the datetime constructor, or None if none was passed.

Supported operations:

Operation	Result
datetime2 = datetime1 + timedelta	(1)
datetime2 = datetime1 - timedelta	(2)
timedelta = datetime1 - datetime2	(3)
datetime1 < datetime2	Compares datetime to datetime. (4)

(1) datetime2 is a duration of timedelta removed from datetime1, moving forward in time if *timedelta*.days; 0, or backward if *timedelta*.days; 0. The result has the same tzinfo member as the input datetime, and datetime2 - datetime1 == timedelta after. OverflowError is raised if datetime2.year would be smaller

than MINYEAR or larger than MAXYEAR. Note that no time zone adjustments are done even if the input is an aware object.

- (2) Computes the datetime2 such that datetime2 + timedelta == datetime1. As for addition, the result has the same tzinfo member as the input datetime, and no time zone adjustments are done even if the input is aware. This isn't quite equivalent to datetime1 + (-timedelta), because -timedelta in isolation can overflow in cases where datetime1 timedelta does not.
- (3) Subtraction of a datetime from a datetime is defined only if both operands are naive, or if both are aware. If one is aware and the other is naive, TypeError is raised.

If both are naive, or both are aware and have the same tzinfo member, the tzinfo members are ignored, and the result is a timedelta object t such that datetime2 + t == datetime1. No time zone adjustments are done in this case.

If both are aware and have different tzinfo members, a-b acts as if a and b were first converted to naive UTC datetimes first. The result is (a.replace(tzinfo=None) - a.utcoffset()) - (b.replace(tzinfo=None) - b.utcoffset()) except that the implementation never overflows.

(4) datetime1 is considered less than datetime2 when datetime1 precedes datetime2 in time.

If one comparand is naive and the other is aware, TypeError is raised. If both comparands are aware, and have the same tzinfo member, the common tzinfo member is ignored and the base datetimes are compared. If both comparands are aware and have different tzinfo members, the comparands are first adjusted by subtracting their UTC offsets (obtained from self.utcoffset()). Note: In order to stop comparison from falling back to the default scheme of comparing object addresses, datetime comparison normally raises TypeError if the other comparand isn't also a datetime object. However, NotImplemented is returned instead if the other comparand has a timetuple attribute. This hook gives other kinds of date objects a chance at implementing mixed-type comparison. If not, when a datetime object is compared to an object of a different type, TypeError is raised unless the comparison is == or !=. The latter cases return False or True, respectively.

datetime objects can be used as dictionary keys. In Boolean contexts, all datetime objects are considered to be true.

Instance methods:

date()

Return date object with same year, month and day.

time()

Return time object with same hour, minute, second and microsecond. tzinfo is None. See also method timetz().

timetz()

Return time object with same hour, minute, second, microsecond, and tzinfo members. See also method time()

replace ([year[, month[, day[, hour[, minute[, second[, microsecond[, tzinfo]]]]]]]])

Return a datetime with the same members, except for those members given new values by whichever keyword arguments are specified. Note that tzinfo=None can be specified to create a naive datetime from an aware datetime with no conversion of date and time members.

astimezone(tz)

Return a datetime object with new tzinfo member tz, adjusting the date and time members so the result is the same UTC time as self, but in tz's local time.

tz must be an instance of a tzinfo subclass, and its utcoffset() and dst() methods must not return None. self must be aware (self.tzinfo must not be None, and self.utcoffset() must not return None).

If self.tzinfo is tz, self.astimezone(tz) is equal to self: no adjustment of date or time members is performed. Else the result is local time in time zone tz, representing the same UTC time as self: after astz = dt.astimezone(tz), astz - astz.utcoffset() will usually have the same date and time members as dt - dt.utcoffset(). The discussion of class tzinfo explains the cases at Daylight Saving Time

transition boundaries where this cannot be achieved (an issue only if tz models both standard and daylight time).

If you merely want to attach a time zone object tz to a datetime dt without adjustment of date and time members, use dt.replace(tzinfo=tz). If you merely want to remove the time zone object from an aware datetime dt without conversion of date and time members, use dt.replace(tzinfo=None).

Note that the default tzinfo.fromutc() method can be overridden in a tzinfo subclass to affect the result returned by astimezone(). Ignoring error cases, astimezone() acts like:

```
def astimezone(self, tz):
    if self.tzinfo is tz:
        return self
# Convert self to UTC, and attach the new time zone object.
    utc = (self - self.utcoffset()).replace(tzinfo=tz)
# Convert from UTC to tz's local time.
    return tz.fromutc(utc)
```

utcoffset()

If tzinfo is None, returns None, else returns self. tzinfo.utcoffset(self), and raises an exception if the latter doesn't return None, or a timedelta object representing a whole number of minutes with magnitude less than one day.

dst()

If tzinfo is None, returns None, else returns self.tzinfo.dst(self), and raises an exception if the latter doesn't return None, or a timedelta object representing a whole number of minutes with magnitude less than one day.

tzname()

If tzinfo is None, returns None, else returns self. tzinfo. tzname (self), raises an exception if the latter doesn't return None or a string object,

timetuple()

Return a time.struct_time such as returned by time.localtime(). d.timetuple() is equivalent to time.struct_time((d.year, d.month, d.day, d.hour, d.minute, d.second, d.weekday(), d.toordinal() - date(d.year, 1, 1).toordinal() + 1, dst)) The tm_isdst flag of the result is set according to the dst() method: tzinfo is None or dst() returns None, tm_isdst is set to -1; else if dst() returns a non-zero value, tm_isdst is set to 1; else tm_isdst is set to 0.

utctimetuple()

If datetime instance d is naive, this is the same as d. timetuple() except that tm_isdst is forced to 0 regardless of what d.dst() returns. DST is never in effect for a UTC time.

If d is aware, d is normalized to UTC time, by subtracting d. utcoffset (), and a time.struct_time for the normalized time is returned. tm_isdst is forced to 0. Note that the result's tm_year member may be MINYEAR-1 or MAXYEAR+1, if d.year was MINYEAR or MAXYEAR and UTC adjustment spills over a year boundary.

toordinal()

Return the proleptic Gregorian ordinal of the date. The same as self.date().toordinal().

weekday()

Return the day of the week as an integer, where Monday is 0 and Sunday is 6. The same as self.date().weekday(). See also isoweekday().

isoweekday()

Return the day of the week as an integer, where Monday is 1 and Sunday is 7. The same as self.date().isoweekday().See also weekday(), isocalendar().

isocalendar()

Return a 3-tuple, (ISO year, ISO week number, ISO weekday). The same as self.date().isocalendar().

```
isoformat([sep])
```

Return a string representing the date and time in ISO 8601 format, YYYY-MM-DDTHH:MM:SS.mmmmmm or, if microsecond is 0, YYYY-MM-DDTHH:MM:SS

If utcoffset() does not return None, a 6-character string is appended, giving the UTC offset in (signed) hours and minutes: YYYY-MM-DDTHH:MM:SS.mmmmmm+HH:MM or, if microsecond is 0 YYYY-MM-DDTHH:MM:SS+HH:MM

The optional argument sep (default 'T') is a one-character separator, placed between the date and time portions of the result. For example,

```
>>> from datetime import tzinfo, timedelta, datetime
>>> class TZ(tzinfo):
...    def utcoffset(self, dt): return timedelta(minutes=-399)
...
>>> datetime(2002, 12, 25, tzinfo=TZ()).isoformat(' ')
'2002-12-25 00:00:00-06:39'
```

__str__()

For a datetime instance d, str(d) is equivalent to d. isoformat('').

ctime(

Return a string representing the date and time, for example datetime(2002, 12, 4, 20, 30, 40).ctime() == 'Wed Dec 4 20:30:40 2002'. d.ctime() is equivalent to time.ctime(time.mktime(d.timetuple())) on platforms where the native <math>C ctime() function (which time.ctime() invokes, but which datetime.ctime() does not invoke) conforms to the C standard.

strftime(format)

Return a string representing the date and time, controlled by an explicit format string. See the section on strftime() behavior.

6.10.5 time Objects

A time object represents a (local) time of day, independent of any particular day, and subject to adjustment via a tzinfo object.

```
class time(hour[, minute[, second[, microsecond[, tzinfo]]]])
```

All arguments are optional. *tzinfo* may be None, or an instance of a tzinfo subclass. The remaining arguments may be ints or longs, in the following ranges:

```
•0 <= hour < 24</li>
•0 <= minute < 60</li>
•0 <= second < 60</li>
•0 <= microsecond < 1000000.</li>
```

If an argument outside those ranges is given, ValueError is raised. All default to 0 except *tzinfo*, which defaults to None.

Class attributes:

min

The earliest representable time, time (0, 0, 0, 0).

max

The latest representable time, time(23, 59, 59, 999999).

resolution

The smallest possible difference between non-equal time objects, timedelta(microseconds=1), although note that arithmetic on time objects is not supported.

Instance attributes (read-only):

hour

In range (24).

minute

In range (60).

second

In range (60).

microsecond

In range(1000000).

tzinfo

The object passed as the tzinfo argument to the time constructor, or None if none was passed.

Supported operations:

- comparison of time to time, where a is considered less than b when a precedes b in time. If one comparand is naive and the other is aware, TypeError is raised. If both comparands are aware, and have the same tzinfo member, the common tzinfo member is ignored and the base times are compared. If both comparands are aware and have different tzinfo members, the comparands are first adjusted by subtracting their UTC offsets (obtained from self.utcoffset()). In order to stop mixed-type comparisons from falling back to the default comparison by object address, when a time object is compared to an object of a different type, TypeError is raised unless the comparison is == or !=. The latter cases return False or True, respectively.
- hash, use as dict key
- · efficient pickling
- in Boolean contexts, a time object is considered to be true if and only if, after converting it to minutes and subtracting utcoffset() (or 0 if that's None), the result is non-zero.

Instance methods:

replace([hour[, minute[, second[, microsecond[, tzinfo]]]]]))

Return a time with the same value, except for those members given new values by whichever keyword arguments are specified. Note that tzinfo=None can be specified to create a naive time from an aware time, without conversion of the time members.

isoformat()

Return a string representing the time in ISO 8601 format, HH:MM:SS.mmmmmm or, if self.microsecond is 0, HH:MM:SS If utcoffset() does not return None, a 6-character string is appended, giving the UTC offset in (signed) hours and minutes: HH:MM:SS.mmmmmm+HH:MM or, if self.microsecond is 0, HH:MM:SS+HH:MM

__str__()

For a time t, str(t) is equivalent to t. isoformat().

strftime(format)

Return a string representing the time, controlled by an explicit format string. See the section on strftime() behavior.

utcoffset()

If tzinfo is None, returns None, else returns self.tzinfo.utcoffset(None), and raises an exception if the latter doesn't return None or a timedelta object representing a whole number of minutes with magnitude less than one day.

dst()

If tzinfo is None, returns None, else returns *self*.tzinfo.dst(None), and raises an exception if the latter doesn't return None, or a timedelta object representing a whole number of minutes with magnitude less than one day.

tzname()

If tzinfo is None, returns None, else returns self. tzinfo. tzname (None), or raises an exception if the latter doesn't return None or a string object.

6.10.6 tzinfo Objects

tzinfo is an abstract base clase, meaning that this class should not be instantiated directly. You need to derive a concrete subclass, and (at least) supply implementations of the standard tzinfo methods needed by the datetime methods you use. The datetime module does not supply any concrete subclasses of tzinfo.

An instance of (a concrete subclass of) tzinfo can be passed to the constructors for datetime and time objects. The latter objects view their members as being in local time, and the tzinfo object supports methods revealing offset of local time from UTC, the name of the time zone, and DST offset, all relative to a date or time object passed to them.

Special requirement for pickling: A tzinfo subclass must have an __init__ method that can be called with no arguments, else it can be pickled but possibly not unpickled again. This is a technical requirement that may be relaxed in the future.

A concrete subclass of tzinfo may need to implement the following methods. Exactly which methods are needed depends on the uses made of aware datetime objects. If in doubt, simply implement all of them.

utcoffset(self, dt)

Return offset of local time from UTC, in minutes east of UTC. If local time is west of UTC, this should be negative. Note that this is intended to be the total offset from UTC; for example, if a tzinfo object represents both time zone and DST adjustments, utcoffset() should return their sum. If the UTC offset isn't known, return None. Else the value returned must be a timedelta object specifying a whole number of minutes in the range -1439 to 1439 inclusive (1440 = 24*60; the magnitude of the offset must be less than one day). Most implementations of utcoffset() will probably look like one of these two:

If utcoffset() does not return None, dst() should not return None either.

The default implementation of utcoffset() raises NotImplementedError.

dst(self, dt)

Return the daylight saving time (DST) adjustment, in minutes east of UTC, or None if DST information isn't known. Return timedelta(0) if DST is not in effect. If DST is in effect, return the offset as a timedelta object (see utcoffset() for details). Note that DST offset, if applicable, has already been added to the UTC offset returned by utcoffset(), so there's no need to consult dst() unless you're interested in obtaining DST info separately. For example, datetime.timetuple() calls its tzinfo member's dst() method to determine how the tm_isdst flag should be set, and tzinfo.fromutc() calls dst() to account for DST changes when crossing time zones.

An instance tz of a tzinfo subclass that models both standard and daylight times must be consistent in this sense:

```
tz.utcoffset(dt) - tz.dst(dt)
```

must return the same result for every datetime dt with dt.tzinfo == tz For sane tzinfo subclasses, this expression yields the time zone's "standard offset", which should not depend on the date or the time, but only on geographic location. The implementation of datetime.astimezone() relies on this, but cannot detect violations; it's the programmer's responsibility to ensure it. If a tzinfo subclass cannot guarantee this, it may be able to override the default implementation of tzinfo.fromutc() to work correctly with astimezone() regardless.

Most implementations of dst() will probably look like one of these two:

```
def dst(self):
    # a fixed-offset class: doesn't account for DST
    return timedelta(0)
```

or

```
def dst(self):
    # Code to set dston and dstoff to the time zone's DST
    # transition times based on the input dt.year, and expressed
    # in standard local time. Then

if dston <= dt.replace(tzinfo=None) < dstoff:
    return timedelta(hours=1)
else:
    return timedelta(0)</pre>
```

The default implementation of dst() raises NotImplementedError.

tzname(self, dt)

Return the time zone name corresponding to the datetime object dt, as a string. Nothing about string names is defined by the datetime module, and there's no requirement that it mean anything in particular. For example, "GMT", "UTC", "-500", "-5:00", "EDT", "US/Eastern", "America/New York" are all valid replies. Return None if a string name isn't known. Note that this is a method rather than a fixed string primarily because some tzinfo subclasses will wish to return different names depending on the specific value of dt passed, especially if the tzinfo class is accounting for daylight time.

The default implementation of tzname() raises NotImplementedError.

These methods are called by a datetime or time object, in response to their methods of the same names. A datetime object passes itself as the argument, and a time object passes None as the argument. A tzinfo subclass's methods should therefore be prepared to accept a dt argument of None, or of class datetime.

When None is passed, it's up to the class designer to decide the best response. For example, returning None is appropriate if the class wishes to say that time objects don't participate in the tzinfo protocols. It may be more useful for utcoffset (None) to return the standard UTC offset, as there is no other convention for discovering the standard offset.

When a datetime object is passed in response to a datetime method, dt.tzinfo is the same object as self. tzinfo methods can rely on this, unless user code calls tzinfo methods directly. The intent is that the tzinfo methods interpret dt as being in local time, and not need worry about objects in other timezones.

There is one more tzinfo method that a subclass may wish to override:

fromutc(self, dt)

This is called from the default datetime.astimezone() implementation. When called from that, dt.tzinfo is self, and dt's date and time members are to be viewed as expressing a UTC time. The purpose of fromutc() is to adjust the date and time members, returning an equivalent datetime in self's local time.

Most tzinfo subclasses should be able to inherit the default fromuto() implementation without problems. It's strong enough to handle fixed-offset time zones, and time zones accounting for both standard and daylight time, and the latter even if the DST transition times differ in different years. An example of a time zone the default fromuto() implementation may not handle correctly in all cases is one where the standard offset (from UTC) depends on the specific date and time passed, which can happen for political reasons. The default implementations of astimezone() and fromuto() may not produce the result you want if the result is one of the hours straddling the moment the standard offset changes.

Skipping code for error cases, the default fromute() implementation acts like:

```
def fromutc(self, dt):
    # raise ValueError error if dt.tzinfo is not self
    dtoff = dt.utcoffset()
    dtdst = dt.dst()
    # raise ValueError if dtoff is None or dtdst is None
    delta = dtoff - dtdst # this is self's standard offset
    if delta:
        dt += delta # convert to standard local time
        dtdst = dt.dst()
        # raise ValueError if dtdst is None
    if dtdst:
        return dt + dtdst
    else:
        return dt
```

Example tzinfo classes:

```
from datetime import tzinfo, timedelta, datetime
ZERO = timedelta(0)
HOUR = timedelta(hours=1)
# A UTC class.
class UTC(tzinfo):
    """UTC"""
    def utcoffset(self, dt):
        return ZERO
    def tzname(self, dt):
        return "UTC"
    def dst(self, dt):
        return ZERO
utc = UTC()
# A class building tzinfo objects for fixed-offset time zones.
# Note that FixedOffset(0, "UTC") is a different way to build a
# UTC tzinfo object.
class FixedOffset(tzinfo):
    """Fixed offset in minutes east from UTC."""
    def __init__(self, offset, name):
        self.__offset = timedelta(minutes = offset)
        self.__name = name
    def utcoffset(self, dt):
        return self.__offset
    def tzname(self, dt):
        return self.__name
    def dst(self, dt):
        return ZERO
# A class capturing the platform's idea of local time.
import time as _time
```

```
STDOFFSET = timedelta(seconds = -_time.timezone)
if _time.daylight:
    DSTOFFSET = timedelta(seconds = -_time.altzone)
else:
    DSTOFFSET = STDOFFSET
DSTDIFF = DSTOFFSET - STDOFFSET
class LocalTimezone(tzinfo):
    def utcoffset(self, dt):
        if self._isdst(dt):
           return DSTOFFSET
        else:
            return STDOFFSET
    def dst(self, dt):
        if self._isdst(dt):
            return DSTDIFF
        else:
           return ZERO
    def tzname(self, dt):
        return _time.tzname[self._isdst(dt)]
    def _isdst(self, dt):
        tt = (dt.year, dt.month, dt.day,
              dt.hour, dt.minute, dt.second,
              dt.weekday(), 0, -1)
        stamp = _time.mktime(tt)
        tt = _time.localtime(stamp)
        return tt.tm_isdst > 0
Local = LocalTimezone()
# A complete implementation of current DST rules for major US time zones.
def first_sunday_on_or_after(dt):
    days_to_go = 6 - dt.weekday()
    if days_to_go:
       dt += timedelta(days_to_go)
    return dt
# In the US, DST starts at 2am (standard time) on the first Sunday in April.
DSTSTART = datetime(1, 4, 1, 2)
# and ends at 2am (DST time; 1am standard time) on the last Sunday of Oct.
# which is the first Sunday on or after Oct 25.
DSTEND = datetime(1, 10, 25, 1)
class USTimeZone(tzinfo):
    def __init__(self, hours, reprname, stdname, dstname):
        self.stdoffset = timedelta(hours=hours)
        self.reprname = reprname
        self.stdname = stdname
        self.dstname = dstname
    def __repr__(self):
        return self.reprname
    def tzname(self, dt):
```

```
if self.dst(dt):
            return self.dstname
        else:
            return self.stdname
    def utcoffset(self, dt):
        return self.stdoffset + self.dst(dt)
    def dst(self, dt):
        if dt is None or dt.tzinfo is None:
            # An exception may be sensible here, in one or both cases.
            # It depends on how you want to treat them. The default
            # fromutc() implementation (called by the default astimezone()
            # implementation) passes a datetime with dt.tzinfo is self.
            return ZERO
        assert dt.tzinfo is self
        # Find first Sunday in April & the last in October.
        start = first_sunday_on_or_after(DSTSTART.replace(year=dt.year))
        end = first_sunday_on_or_after(DSTEND.replace(year=dt.year))
        # Can't compare naive to aware objects, so strip the timezone from
        # dt first.
        if start <= dt.replace(tzinfo=None) < end:</pre>
            return HOUR
            return ZERO
Eastern = USTimeZone(-5, "Eastern",
                                      "EST", "EDT")
Central = USTimeZone(-6, "Central",
                                      "CST", "CDT")
Mountain = USTimeZone(-7, "Mountain", "MST", "MDT")
Pacific = USTimeZone(-8, "Pacific", "PST", "PDT")
```

Note that there are unavoidable subtleties twice per year in a tzinfo subclass accounting for both standard and daylight time, at the DST transition points. For concreteness, consider US Eastern (UTC -0500), where EDT begins the minute after 1:59 (EST) on the first Sunday in April, and ends the minute after 1:59 (EDT) on the last Sunday in October:

```
UTC 3:MM 4:MM 5:MM 6:MM 7:MM 8:MM
EST 22:MM 23:MM 0:MM 1:MM 2:MM 3:MM
EDT 23:MM 0:MM 1:MM 2:MM 3:MM 4:MM

start 22:MM 23:MM 0:MM 1:MM 3:MM 4:MM
end 23:MM 0:MM 1:MM 1:MM 2:MM 3:MM
```

When DST starts (the "start" line), the local wall clock leaps from 1:59 to 3:00. A wall time of the form 2:MM doesn't really make sense on that day, so astimezone (Eastern) won't deliver a result with hour == 2 on the day DST begins. In order for astimezone() to make this guarantee, the rzinfo.dst() method must consider times in the "missing hour" (2:MM for Eastern) to be in daylight time.

When DST ends (the "end" line), there's a potentially worse problem: there's an hour that can't be spelled unambiguously in local wall time: the last hour of daylight time. In Eastern, that's times of the form 5:MM UTC on the day daylight time ends. The local wall clock leaps from 1:59 (daylight time) back to 1:00 (standard time) again. Local times of the form 1:MM are ambiguous. astimezone() mimics the local clock's behavior by mapping two adjacent UTC hours into the same local hour then. In the Eastern example, UTC times of the form 5:MM and 6:MM both map to 1:MM when converted to Eastern. In order for astimezone() to make this guarantee, the tzinfo.dst() method must consider times in the "repeated hour" to be in standard time. This is easily arranged, as in the example, by expressing DST switch times in the time zone's standard local time.

Applications that can't bear such ambiguities should avoid using hybrid tzinfo subclasses; there are no ambi-

guities when using UTC, or any other fixed-offset tzinfo subclass (such as a class representing only EST (fixed offset -5 hours), or only EDT (fixed offset -4 hours)).

6.10.7 strftime() Behavior

date, datetime, and time objects all support a strftime(format) method, to create a string representing the time under the control of an explicit format string. Broadly speaking, d.strftime(fmt) acts like the time module's time.strftime(fmt, d.timetuple()) although not all objects support a timetuple() method.

For time objects, the format codes for year, month, and day should not be used, as time objects have no such values. If they're used anyway, 1900 is substituted for the year, and 0 for the month and day.

For date objects, the format codes for hours, minutes, and seconds should not be used, as date objects have no such values. If they're used anyway, 0 is substituted for them.

For a naive object, the $\$ z and $\$ Z format codes are replaced by empty strings.

For an aware object:

- %z utcoffset() is transformed into a 5-character string of the form +HHMM or -HHMM, where HH is a
 2-digit string giving the number of UTC offset hours, and MM is a 2-digit string giving the number of UTC
 offset minutes. For example, if utcoffset() returns timedelta(hours=-3, minutes=-30),
 %z is replaced with the string '-0330'.
- %Z If tzname() returns None, %Z is replaced by an empty string. Otherwise %Z is replaced by the returned value, which must be a string.

The full set of format codes supported varies across platforms, because Python calls the platform C library's strftime() function, and platform variations are common. The documentation for Python's time module lists the format codes that the C standard (1989 version) requires, and those work on all platforms with a standard C implementation. Note that the 1999 version of the C standard added additional format codes.

The exact range of years for which strftime() works also varies across platforms. Regardless of platform, years before 1900 cannot be used.

6.11 time — Time access and conversions

This module provides various time-related functions. It is always available, but not all functions are available on all platforms. Most of the functions defined in this module call platform C library functions with the same name. It may sometimes be helpful to consult the platform documentation, because the semantics of these functions varies among platforms.

An explanation of some terminology and conventions is in order.

- The *epoch* is the point where the time starts. On January 1st of that year, at 0 hours, the "time since the epoch" is zero. For UNIX, the epoch is 1970. To find out what the epoch is, look at gmtime (0).
- The functions in this module do not handle dates and times before the epoch or far in the future. The cut-off point in the future is determined by the C library; for UNIX, it is typically in 2038.
- Year 2000 (Y2K) issues: Python depends on the platform's C library, which generally doesn't have year 2000 issues, since all dates and times are represented internally as seconds since the epoch. Functions accepting a struct_time (see below) generally require a 4-digit year. For backward compatibility, 2-digit years are supported if the module variable accept2dyear is a non-zero integer; this variable is initialized to 1 unless the environment variable PYTHONY2K is set to a non-empty string, in which case it is initialized to 0. Thus, you can set PYTHONY2K to a non-empty string in the environment to require 4-digit years for all year input. When 2-digit years are accepted, they are converted according to the POSIX or X/Open standard: values 69-99 are mapped to 1969-1999, and values 0-68 are mapped to 2000-2068.

Values 100–1899 are always illegal. Note that this is new as of Python 1.5.2(a2); earlier versions, up to Python 1.5.1 and 1.5.2a1, would add 1900 to year values below 1900.

- UTC is Coordinated Universal Time (formerly known as Greenwich Mean Time, or GMT). The acronym UTC is not a mistake but a compromise between English and French.
- DST is Daylight Saving Time, an adjustment of the timezone by (usually) one hour during part of the year.
 DST rules are magic (determined by local law) and can change from year to year. The C library has a table containing the local rules (often it is read from a system file for flexibility) and is the only source of True Wisdom in this respect.
- The precision of the various real-time functions may be less than suggested by the units in which their value or argument is expressed. E.g. on most UNIX systems, the clock "ticks" only 50 or 100 times a second, and on the Mac, times are only accurate to whole seconds.
- On the other hand, the precision of time() and sleep() is better than their UNIX equivalents: times are expressed as floating point numbers, time() returns the most accurate time available (using UNIX gettimeofday() where available), and sleep() will accept a time with a nonzero fraction (UNIX select() is used to implement this, where available).
- The time value as returned by gmtime(), localtime(), and strptime(), and accepted by asctime(), mktime() and strftime(), is a sequence of 9 integers. The return values of gmtime(), localtime(), and strptime() also offer attribute names for individual fields.

Index	Attribute	Values
0	tm_year	(for example, 1993)
1	tm_mon	range [1,12]
2	tm_mday	range [1,31]
3	tm_hour	range [0,23]
4	tm_min	range [0,59]
5	tm_sec	range [0,61]; see (1) in strftime() description
6	tm_wday	range [0,6], Monday is 0
7	tm_yday	range [1,366]
8	tm_isdst	0, 1 or -1; see below

Note that unlike the C structure, the month value is a range of 1-12, not 0-11. A year value will be handled as described under "Year 2000 (Y2K) issues" above. A -1 argument as the daylight savings flag, passed to mktime() will usually result in the correct daylight savings state to be filled in.

When a tuple with an incorrect length is passed to a function expecting a struct_time, or having elements of the wrong type, a TypeError is raised.

Changed in version 2.2: The time value sequence was changed from a tuple to a struct_time, with the addition of attribute names for the fields.

The module defines the following functions and data items:

accept2dyear

Boolean value indicating whether two-digit year values will be accepted. This is true by default, but will be set to false if the environment variable PYTHONY2K has been set to a non-empty string. It may also be modified at run time.

altzone

The offset of the local DST timezone, in seconds west of UTC, if one is defined. This is negative if the local DST timezone is east of UTC (as in Western Europe, including the UK). Only use this if daylight is nonzero.

asctime([t])

Convert a tuple or struct_time representing a time as returned by gmtime() or localtime() to a 24-character string of the following form: 'Sun Jun 20 23:21:05 1993'. If t is not provided, the current time as returned by localtime() is used. Locale information is not used by asctime(). **Note:** Unlike the C function of the same name, there is no trailing newline. Changed in version 2.1: Allowed t to be omitted.

clock()

On UNIX, return the current processor time as a floating point number expressed in seconds. The precision, and in fact the very definition of the meaning of "processor time", depends on that of the C function of the same name, but in any case, this is the function to use for benchmarking Python or timing algorithms.

On Windows, this function returns wall-clock seconds elapsed since the first call to this function, as a floating point number, based on the Win32 function QueryPerformanceCounter(). The resolution is typically better than one microsecond.

ctime([secs])

Convert a time expressed in seconds since the epoch to a string representing local time. If *secs* is not provided or None, the current time as returned by time() is used. ctime(*secs*) is equivalent to asctime(localtime(*secs*)). Locale information is not used by ctime(). Changed in version 2.1: Allowed *secs* to be omitted. Changed in version 2.4: If *secs* is None, the current time is used.

daylight

Nonzero if a DST timezone is defined.

gmtime([secs])

Convert a time expressed in seconds since the epoch to a struct_time in UTC in which the dst flag is always zero. If *secs* is not provided or None, the current time as returned by time() is used. Fractions of a second are ignored. See above for a description of the struct_time object. See calendar.timegm() for the inverse of this function. Changed in version 2.1: Allowed *secs* to be omitted. Changed in version 2.4: If *secs* is None, the current time is used.

localtime([secs])

Like gmtime() but converts to local time. If *secs* is not provided or None, the current time as returned by time() is used. The dst flag is set to 1 when DST applies to the given time. Changed in version 2.1: Allowed *secs* to be omitted. Changed in version 2.4: If *secs* is None, the current time is used.

mktime(t)

This is the inverse function of localtime(). Its argument is the struct_time or full 9-tuple (since the dst flag is needed; use -1 as the dst flag if it is unknown) which expresses the time in *local* time, not UTC. It returns a floating point number, for compatibility with time(). If the input value cannot be represented as a valid time, either OverflowError or ValueError will be raised (which depends on whether the invalid value is caught by Python or the underlying C libraries). The earliest date for which it can generate a time is platform-dependent.

sleep(secs)

Suspend execution for the given number of seconds. The argument may be a floating point number to indicate a more precise sleep time. The actual suspension time may be less than that requested because any caught signal will terminate the <code>sleep()</code> following execution of that signal's catching routine. Also, the suspension time may be longer than requested by an arbitrary amount because of the scheduling of other activity in the system.

strftime(format[,t])

Convert a tuple or $struct_time$ representing a time as returned by gmtime() or localtime() to a string as specified by the *format* argument. If t is not provided, the current time as returned by localtime() is used. *format* must be a string. ValueError is raised if any field in t is outside of the allowed range. Changed in version 2.1: Allowed t to be omitted. Changed in version 2.4: ValueError raised if a field in t is out of range.

The following directives can be embedded in the *format* string. They are shown without the optional field width and precision specification, and are replaced by the indicated characters in the strftime() result:

Directive	Meaning	Notes
%a	Locale's abbreviated weekday name.	
%A	Locale's full weekday name.	
%b	Locale's abbreviated month name.	
%B	Locale's full month name.	
%C	Locale's appropriate date and time representation.	
%d	Day of the month as a decimal number [01,31].	
%H	Hour (24-hour clock) as a decimal number [00,23].	
%I	Hour (12-hour clock) as a decimal number [01,12].	
%j	Day of the year as a decimal number [001,366].	
%m	Month as a decimal number [01,12].	
%M	Minute as a decimal number [00,59].	
%p	Locale's equivalent of either AM or PM.	(1)
%S	Second as a decimal number [00,61].	(2)
%U	Week number of the year (Sunday as the first day of the	(3)
	week) as a decimal number [00,53]. All days in a new year	
	preceding the first Sunday are considered to be in week 0.	
%w	Weekday as a decimal number [0(Sunday),6].	
%₩	Week number of the year (Monday as the first day of the	(3)
	week) as a decimal number [00,53]. All days in a new year	
	preceding the first Monday are considered to be in week 0.	
%x	Locale's appropriate date representation.	
%X	Locale's appropriate time representation.	
%Y	Year without century as a decimal number [00,99].	
%Y	Year with century as a decimal number.	
%Z	Time zone name (no characters if no time zone exists).	
%%	A literal '%' character.	

Notes:

- (1) When used with the strptime() function, the %p directive only affects the output hour field if the %I directive is used to parse the hour.
- (2) The range really is 0 to 61; this accounts for leap seconds and the (very rare) double leap seconds.
- (3)When used with the strptime() function, %U and %W are only used in calculations when the day of the week and the year are specified.

Here is an example, a format for dates compatible with that specified in the RFC 2822 Internet email standard. ¹

```
>>> from time import gmtime, strftime
>>> strftime("%a, %d %b %Y %H:%M:%S +0000", gmtime())
'Thu, 28 Jun 2001 14:17:15 +0000'
```

Additional directives may be supported on certain platforms, but only the ones listed here have a meaning standardized by ANSI C.

On some platforms, an optional field width and precision specification can immediately follow the initial '%' of a directive in the following order; this is also not portable. The field width is normally 2 except for %j where it is 3.

strptime(string[, format])

Parse a string representing a time according to a format. The return value is a struct_time as returned by gmtime() or localtime(). The *format* parameter uses the same directives as those used by strftime(); it defaults to "%a %b %d %H:%M:%S %Y" which matches the formatting returned by ctime(). If *string* cannot be parsed according to *format*, ValueError is raised. If the string to be parsed has excess data after parsing, ValueError is raised. The default values used to fill in any missing data are (1900, 1, 1, 0, 0, 0, 1, -1).

¹The use of %Z is now deprecated, but the %z escape that expands to the preferred hour/minute offset is not supported by all ANSI C libraries. Also, a strict reading of the original 1982 RFC 822 standard calls for a two-digit year (%y rather than %Y), but practice moved to 4-digit years long before the year 2000. The 4-digit year has been mandated by RFC 2822, which obsoletes RFC 822.

Support for the %Z directive is based on the values contained in tzname and whether daylight is true. Because of this, it is platform-specific except for recognizing UTC and GMT which are always known (and are considered to be non-daylight savings timezones).

struct_time

The type of the time value sequence returned by gmtime(), localtime(), and strptime(). New in version 2.2.

time()

Return the time as a floating point number expressed in seconds since the epoch, in UTC. Note that even though the time is always returned as a floating point number, not all systems provide time with a better precision than 1 second. While this function normally returns non-decreasing values, it can return a lower value than a previous call if the system clock has been set back between the two calls.

timezone

The offset of the local (non-DST) timezone, in seconds west of UTC (negative in most of Western Europe, positive in the US, zero in the UK).

tzname

A tuple of two strings: the first is the name of the local non-DST timezone, the second is the name of the local DST timezone. If no DST timezone is defined, the second string should not be used.

tzset(

Resets the time conversion rules used by the library routines. The environment variable TZ specifies how this is done. New in version 2.3.

Availability: UNIX.

Note: Although in many cases, changing the TZ environment variable may affect the output of functions like localtime without calling tzset, this behavior should not be relied on.

The TZ environment variable should contain no whitespace.

The standard format of the TZ environment variable is: (whitespace added for clarity)

std offset [dst [offset[,start[/time], end[/time]]]]

Where:

std and dstThree or more alphanumerics giving the timezone abbreviations. These will be propagated into time.tzname

offsetThe offset has the form: \pm hh[:mm[:ss]]. This indicates the value added the local time to arrive at UTC. If preceded by a '-', the timezone is east of the Prime Meridian; otherwise, it is west. If no offset follows dst, summer time is assumed to be one hour ahead of standard time.

start[/time,end[/time]] Indicates when to change to and back from DST. The format of the start and end dates are one of the following:

JnThe Julian day n (1 = n = 365). Leap days are not counted, so in all years February 28 is day 59 and March 1 is day 60.

nThe zero-based Julian day (0 := n := 365). Leap days are counted, and it is possible to refer to February 29.

Mm.n.dThe d'th day $(0 \neq i \neq j = 6)$ or week n of month m of the year $(1 \neq i \neq j = 5, 1 \neq i \neq 12)$, where week 5 means "the last d day in month m" which may occur in either the fourth or the fifth week). Week 1 is the first week in which the d'th day occurs. Day zero is Sunday.

time has the same format as offset except that no leading sign ('-' or '+') is allowed. The default, if time is not given, is 02:00:00.

```
>>> os.environ['TZ'] = 'EST+05EDT,M4.1.0,M10.5.0'
>>> time.tzset()
>>> time.strftime('%X %x %Z')
'02:07:36 05/08/03 EDT'
>>> os.environ['TZ'] = 'AEST-10AEDT-11,M10.5.0,M3.5.0'
>>> time.tzset()
>>> time.strftime('%X %x %Z')
'16:08:12 05/08/03 AEST'
```

On many Unix systems (including *BSD, Linux, Solaris, and Darwin), it is more convenient to use the system's zoneinfo (*tzfile*(5)) database to specify the timezone rules. To do this, set the TZ environment variable to the path of the required timezone datafile, relative to the root of the systems 'zoneinfo' timezone database, usually located at '/usr/share/zoneinfo'. For example, 'US/Eastern', 'Australia/Melbourne', 'Egypt' or 'Europe/Amsterdam'.

```
>>> os.environ['TZ'] = 'US/Eastern'
>>> time.tzset()
>>> time.tzname
('EST', 'EDT')
>>> os.environ['TZ'] = 'Egypt'
>>> time.tzset()
>>> time.tzname
('EET', 'EEST')
```

See Also:

Module datetime (section 6.10):

More object-oriented interface to dates and times.

Module locale (section 6.27):

Internationalization services. The locale settings can affect the return values for some of the functions in the time module.

Module calendar (section 5.19):

General calendar-related functions. timeqm() is the inverse of qmtime() from this module.

6.12 sched — Event scheduler

The sched module defines a class which implements a general purpose event scheduler:

```
class scheduler(timefunc, delayfunc)
```

The scheduler class defines a generic interface to scheduling events. It needs two functions to actually deal with the "outside world" — *timefunc* should be callable without arguments, and return a number (the "time", in any units whatsoever). The *delayfunc* function should be callable with one argument, compatible with the output of *timefunc*, and should delay that many time units. *delayfunc* will also be called with the argument 0 after each event is run to allow other threads an opportunity to run in multi-threaded applications.

Example:

6.12.1 Scheduler Objects

scheduler instances have the following methods:

```
enterabs(time, priority, action, argument)
```

Schedule a new event. The *time* argument should be a numeric type compatible with the return value of the *timefunc* function passed to the constructor. Events scheduled for the same *time* will be executed in the order of their *priority*.

Executing the event means executing action(*argument). argument must be a sequence holding the parameters for action.

Return value is an event which may be used for later cancellation of the event (see cancel()).

```
enter(delay, priority, action, argument)
```

Schedule an event for *delay* more time units. Other then the relative time, the other arguments, the effect and the return value are the same as those for enterabs ().

```
cancel (event)
```

Remove the event from the queue. If *event* is not an event currently in the queue, this method will raise a RuntimeError.

empty()

Return true if the event queue is empty.

run()

Run all scheduled events. This function will wait (using the delayfunc function passed to the constructor) for the next event, then execute it and so on until there are no more scheduled events.

Either action or delayfunc can raise an exception. In either case, the scheduler will maintain a consistent state and propagate the exception. If an exception is raised by action, the event will not be attempted in future calls to run().

If a sequence of events takes longer to run than the time available before the next event, the scheduler will simply fall behind. No events will be dropped; the calling code is responsible for canceling events which are no longer pertinent.

6.13 mutex — Mutual exclusion support

The mutex module defines a class that allows mutual-exclusion via acquiring and releasing locks. It does not require (or imply) threading or multi-tasking, though it could be useful for those purposes.

The mutex module defines the following class:

class mutex()

Create a new (unlocked) mutex.

A mutex has two pieces of state — a "locked" bit and a queue. When the mutex is not locked, the queue is empty. Otherwise, the queue contains zero or more (function, argument) pairs representing functions (or methods) waiting to acquire the lock. When the mutex is unlocked while the queue is not empty, the first queue entry is removed and its function (argument) pair called, implying it now has the lock.

Of course, no multi-threading is implied – hence the funny interface for lock(), where a function is called once the lock is acquired.

6.13.1 Mutex Objects

mutex objects have following methods:

test()

Check whether the mutex is locked.

testandset()

"Atomic" test-and-set, grab the lock if it is not set, and return True, otherwise, return False.

lock(function, argument)

Execute function (argument), unless the mutex is locked. In the case it is locked, place the function and argument on the queue. See unlock for explanation of when function (argument) is executed in that case.

unlock()

Unlock the mutex if queue is empty, otherwise execute the first element in the queue.

6.14 getpass — Portable password input

The getpass module provides two functions:

getpass([prompt])

Prompt the user for a password without echoing. The user is prompted using the string *prompt*, which defaults to 'Password: '. Availability: Macintosh, UNIX, Windows.

getuser()

Return the "login name" of the user. Availability: UNIX, Windows.

This function checks the environment variables LOGNAME, USER, LNAME and USERNAME, in order, and returns the value of the first one which is set to a non-empty string. If none are set, the login name from the password database is returned on systems which support the pwd module, otherwise, an exception is raised.

6.15 curses — Terminal handling for character-cell displays

Changed in version 1.6: Added support for the ncurses library and converted to a package.

The curses module provides an interface to the curses library, the de-facto standard for portable advanced terminal handling.

While curses is most widely used in the UNIX environment, versions are available for DOS, OS/2, and possibly other systems as well. This extension module is designed to match the API of neurses, an open-source curses library hosted on Linux and the BSD variants of UNIX.

See Also:

Module curses.ascii (section 6.18):

Utilities for working with ASCII characters, regardless of your locale settings.

Module curses.panel (section 6.19):

A panel stack extension that adds depth to curses windows.

Module curses.textpad (section 6.16):

Editable text widget for curses supporting **Emacs**-like bindings.

Module curses.wrapper (section 6.17):

Convenience function to ensure proper terminal setup and resetting on application entry and exit.

Curses Programming with Python

(http://www.python.org/doc/howto/curses/curses.html)

Tutorial material on using curses with Python, by Andrew Kuchling and Eric Raymond, is available on the Python Web site.

The 'Demo/curses/' directory in the Python source distribution contains some example programs using the curses bindings provided by this module.

6.15.1 Functions

The module curses defines the following exception:

exception error

Exception raised when a curses library function returns an error.

Note: Whenever *x* or *y* arguments to a function or a method are optional, they default to the current cursor location. Whenever *attr* is optional, it defaults to A_NORMAL.

The module curses defines the following functions:

baudrate()

Returns the output speed of the terminal in bits per second. On software terminal emulators it will have a fixed high value. Included for historical reasons; in former times, it was used to write output loops for time delays and occasionally to change interfaces depending on the line speed.

beep()

Emit a short attention sound.

can_change_color()

Returns true or false, depending on whether the programmer can change the colors displayed by the terminal.

cbreak()

Enter cbreak mode. In cbreak mode (sometimes called "rare" mode) normal tty line buffering is turned off and characters are available to be read one by one. However, unlike raw mode, special characters (interrupt, quit, suspend, and flow control) retain their effects on the tty driver and calling program. Calling first raw() then cbreak() leaves the terminal in cbreak mode.

color_content(color_number)

Returns the intensity of the red, green, and blue (RGB) components in the color *color_number*, which must be between 0 and COLORS. A 3-tuple is returned, containing the R,G,B values for the given color, which will be between 0 (no component) and 1000 (maximum amount of component).

color_pair(color_number)

Returns the attribute value for displaying text in the specified color. This attribute value can be combined with A_STANDOUT, A_REVERSE, and the other A_* attributes. pair_number() is the counterpart to this function.

curs_set(visibility)

Sets the cursor state. *visibility* can be set to 0, 1, or 2, for invisible, normal, or very visible. If the terminal supports the visibility requested, the previous cursor state is returned; otherwise, an exception is raised. On many terminals, the "visible" mode is an underline cursor and the "very visible" mode is a block cursor.

def_prog_mode()

Saves the current terminal mode as the "program" mode, the mode when the running program is using curses. (Its counterpart is the "shell" mode, for when the program is not in curses.) Subsequent calls to reset_prog_mode() will restore this mode.

def_shell_mode()

Saves the current terminal mode as the "shell" mode, the mode when the running program is not using

curses. (Its counterpart is the "program" mode, when the program is using curses capabilities.) Subsequent calls to reset_shell_mode() will restore this mode.

delay_output(ms)

Inserts an ms millisecond pause in output.

doupdate()

Update the physical screen. The curses library keeps two data structures, one representing the current physical screen contents and a virtual screen representing the desired next state. The doupdate() ground updates the physical screen to match the virtual screen.

The virtual screen may be updated by a noutrefresh() call after write operations such as addstr() have been performed on a window. The normal refresh() call is simply noutrefresh() followed by doupdate(); if you have to update multiple windows, you can speed performance and perhaps reduce screen flicker by issuing noutrefresh() calls on all windows, followed by a single doupdate().

echo()

Enter echo mode. In echo mode, each character input is echoed to the screen as it is entered.

endwin(

De-initialize the library, and return terminal to normal status.

erasechar()

Returns the user's current erase character. Under UNIX operating systems this is a property of the controlling tty of the curses program, and is not set by the curses library itself.

filter()

The filter() routine, if used, must be called before initscr() is called. The effect is that, during those calls, LINES is set to 1; the capabilities clear, cup, cud, cud1, cuu1, cuu, vpa are disabled; and the home string is set to the value of cr. The effect is that the cursor is confined to the current line, and so are screen updates. This may be used for enabling character-at-a-time line editing without touching the rest of the screen.

flash()

Flash the screen. That is, change it to reverse-video and then change it back in a short interval. Some people prefer such as 'visible bell' to the audible attention signal produced by beep().

flushinp()

Flush all input buffers. This throws away any typeahead that has been typed by the user and has not yet been processed by the program.

getmouse()

After getch() returns KEY_MOUSE to signal a mouse event, this method should be call to retrieve the queued mouse event, represented as a 5-tuple (id, x, y, z, bstate). id is an ID value used to distinguish multiple devices, and x, y, z are the event's coordinates. (z is currently unused.). bstate is an integer value whose bits will be set to indicate the type of event, and will be the bitwise OR of one or more of the following constants, where n is the button number from 1 to 4: BUTTON $_{preseq}$ BUTTON

getsyx()

Returns the current coordinates of the virtual screen cursor in y and x. If leaveok is currently true, then -1,-1 is returned.

getwin(file)

Reads window related data stored in the file by an earlier putwin() call. The routine then creates and initializes a new window using that data, returning the new window object.

has colors()

Returns true if the terminal can display colors; otherwise, it returns false.

has_ic()

Returns true if the terminal has insert- and delete- character capabilities. This function is included for historical reasons only, as all modern software terminal emulators have such capabilities.

has_il()

Returns true if the terminal has insert- and delete-line capabilities, or can simulate them using scrolling regions. This function is included for historical reasons only, as all modern software terminal emulators have such capabilities.

$has_key(ch)$

Takes a key value ch, and returns true if the current terminal type recognizes a key with that value.

halfdelay(tenths)

Used for half-delay mode, which is similar to cbreak mode in that characters typed by the user are immediately available to the program. However, after blocking for *tenths* tenths of seconds, an exception is raised if nothing has been typed. The value of *tenths* must be a number between 1 and 255. Use nocbreak() to leave half-delay mode.

init_color(color_number, r, g, b)

Changes the definition of a color, taking the number of the color to be changed followed by three RGB values (for the amounts of red, green, and blue components). The value of $color_number$ must be between 0 and COLORS. Each of r, g, b, must be a value between 0 and 1000. When init_color() is used, all occurrences of that color on the screen immediately change to the new definition. This function is a no-op on most terminals; it is active only if can_change_color() returns 1.

init_pair(pair_number, fg, bg)

Changes the definition of a color-pair. It takes three arguments: the number of the color-pair to be changed, the foreground color number, and the background color number. The value of $pair_number$ must be between 1 and COLOR_PAIRS - 1 (the 0 color pair is wired to white on black and cannot be changed). The value of fg and bg arguments must be between 0 and COLORS. If the color-pair was previously initialized, the screen is refreshed and all occurrences of that color-pair are changed to the new definition.

initscr()

Initialize the library. Returns a WindowObject which represents the whole screen. **Note:** If there is an error opening the terminal, the underlying curses library may cause the interpreter to exit.

isendwin()

Returns true if endwin() has been called (that is, the curses library has been deinitialized).

keyname(k)

Return the name of the key numbered *k*. The name of a key generating printable ASCII character is the key's character. The name of a control-key combination is a two-character string consisting of a caret followed by the corresponding printable ASCII character. The name of an alt-key combination (128-255) is a string consisting of the prefix 'M-' followed by the name of the corresponding ASCII character.

killchar()

Returns the user's current line kill character. Under UNIX operating systems this is a property of the controlling tty of the curses program, and is not set by the curses library itself.

longname()

Returns a string containing the terminfo long name field describing the current terminal. The maximum length of a verbose description is 128 characters. It is defined only after the call to initscr().

meta(yes)

If yes is 1, allow 8-bit characters to be input. If yes is 0, allow only 7-bit chars.

mouseinterval(interval)

Sets the maximum time in milliseconds that can elapse between press and release events in order for them to be recognized as a click, and returns the previous interval value. The default value is 200 msec, or one fifth of a second.

mousemask (mousemask)

Sets the mouse events to be reported, and returns a tuple (availmask, oldmask). availmask indicates which of the specified mouse events can be reported; on complete failure it returns 0. oldmask is the previous value of the given window's mouse event mask. If this function is never called, no mouse events are ever reported.

napms(ms)

Sleep for ms milliseconds.

newpad(nlines, ncols)

Creates and returns a pointer to a new pad data structure with the given number of lines and columns. A pad is returned as a window object.

A pad is like a window, except that it is not restricted by the screen size, and is not necessarily associated with a particular part of the screen. Pads can be used when a large window is needed, and only a part of the window will be on the screen at one time. Automatic refreshes of pads (such as from scrolling or echoing of input) do not occur. The refresh() and noutrefresh() methods of a pad require 6 arguments to specify the part of the pad to be displayed and the location on the screen to be used for the display. The arguments are pminrow, pmincol, sminrow, smincol, smaxrow, smaxcol; the p arguments refer to the upper left corner of the pad region to be displayed and the s arguments define a clipping box on the screen within which the pad region is to be displayed.

newwin([nlines, ncols,] begin_y, begin_x)

Return a new window, whose left-upper corner is at (begin_y, begin_x), and whose height/width is nlines/ncols.

By default, the window will extend from the specified position to the lower right corner of the screen.

nl()

Enter newline mode. This mode translates the return key into newline on input, and translates newline into return and line-feed on output. Newline mode is initially on.

nocbreak()

Leave cbreak mode. Return to normal "cooked" mode with line buffering.

noecho(

Leave echo mode. Echoing of input characters is turned off.

nonl()

Leave newline mode. Disable translation of return into newline on input, and disable low-level translation of newline into newline/return on output (but this does not change the behavior of addch(' n'), which always does the equivalent of return and line feed on the virtual screen). With translation off, curses can sometimes speed up vertical motion a little; also, it will be able to detect the return key on input.

noqiflush()

When the noqiflush routine is used, normal flush of input and output queues associated with the INTR, QUIT and SUSP characters will not be done. You may want to call noqiflush() in a signal handler if you want output to continue as though the interrupt had not occurred, after the handler exits.

noraw()

Leave raw mode. Return to normal "cooked" mode with line buffering.

pair_content(pair_number)

Returns a tuple (fg, bg) containing the colors for the requested color pair. The value of $pair_number$ must be between 1 and COLOR_PAIRS - 1.

pair_number(attr)

Returns the number of the color-pair set by the attribute value *attr*. color_pair() is the counterpart to this function.

putp(string)

Equivalent to tputs(str, 1, putchar); emits the value of a specified terminfo capability for the current terminal. Note that the output of putp always goes to standard output.

qiflush(| flag |)

If *flag* is false, the effect is the same as calling noqiflush(). If *flag* is true, or no argument is provided, the queues will be flushed when these control characters are read.

raw(

Enter raw mode. In raw mode, normal line buffering and processing of interrupt, quit, suspend, and flow control keys are turned off; characters are presented to curses input functions one by one.

reset_prog_mode()

Restores the terminal to "program" mode, as previously saved by def_prog_mode().

reset_shell_mode()

Restores the terminal to "shell" mode, as previously saved by def_shell_mode().

setsyx(y, x)

Sets the virtual screen cursor to y, x. If y and x are both -1, then leaveok is set.

setupterm([termstr, fd])

Initializes the terminal. *termstr* is a string giving the terminal name; if omitted, the value of the TERM environment variable will be used. *fd* is the file descriptor to which any initialization sequences will be sent; if not supplied, the file descriptor for sys.stdout will be used.

start_color()

Must be called if the programmer wants to use colors, and before any other color manipulation routine is called. It is good practice to call this routine right after initscr().

start_color() initializes eight basic colors (black, red, green, yellow, blue, magenta, cyan, and white), and two global variables in the curses module, COLORS and COLOR_PAIRS, containing the maximum number of colors and color-pairs the terminal can support. It also restores the colors on the terminal to the values they had when the terminal was just turned on.

termattrs()

Returns a logical OR of all video attributes supported by the terminal. This information is useful when a curses program needs complete control over the appearance of the screen.

termname()

Returns the value of the environment variable TERM, truncated to 14 characters.

tigetflag(capname)

Returns the value of the Boolean capability corresponding to the terminfo capability name *capname*. The value -1 is returned if *capname* is not a Boolean capability, or 0 if it is canceled or absent from the terminal description.

tigetnum(capname)

Returns the value of the numeric capability corresponding to the terminfo capability name *capname*. The value -2 is returned if *capname* is not a numeric capability, or -1 if it is canceled or absent from the terminal description.

tigetstr(capname)

Returns the value of the string capability corresponding to the terminfo capability name *capname*. None is returned if *capname* is not a string capability, or is canceled or absent from the terminal description.

tparm(str[,...])

Instantiates the string str with the supplied parameters, where str should be a parameterized string obtained from the terminfo database. E.g. tparm(tigetstr("cup"), 5, 3) could result in '\033[6;4H', the exact result depending on terminal type.

typeahead(fd)

Specifies that the file descriptor fd be used for typeahead checking. If fd is -1, then no typeahead checking is done

The curses library does "line-breakout optimization" by looking for typeahead periodically while updating the screen. If input is found, and it is coming from a tty, the current update is postponed until refresh or doupdate is called again, allowing faster response to commands typed in advance. This function allows specifying a different file descriptor for typeahead checking.

unctrl(ch)

Returns a string which is a printable representation of the character *ch*. Control characters are displayed as a caret followed by the character, for example as ^C. Printing characters are left as they are.

ungetch(ch)

Push ch so the next getch() will return it. **Note:** Only one ch can be pushed before getch() is called.

ungetmouse(id, x, y, z, bstate)

Push a KEY_MOUSE event onto the input queue, associating the given state data with it.

use_env(flag)

If used, this function should be called before initscr() or newterm are called. When flag is false, the values of lines and columns specified in the terminfo database will be used, even if environment variables

LINES and COLUMNS (used by default) are set, or if curses is running in a window (in which case default behavior would be to use the window size if LINES and COLUMNS are not set).

use_default_colors()

Allow use of default values for colors on terminals supporting this feature. Use this to support transparency in your application. The default color is assigned to the color number -1. After calling this function, $init_pair(x, curses.COLOR_RED, -1)$ initializes, for instance, color pair x to a red foreground color on the default background.

6.15.2 Window Objects

Window objects, as returned by initscr() and newwin() above, have the following methods:

Note: A *character* means a C character (an ASCII code), rather then a Python character (a string of length 1). (This note is true whenever the documentation mentions a character.) The builtin ord() is handy for conveying strings to codes.

Paint character ch at (y, x) with attributes attr, overwriting any character previously painter at that location. By default, the character position and attributes are the current settings for the window object.

Paint at most n characters of the string str at (y, x) with attributes attr, overwriting anything previously on the display.

addstr([y, x,] str[, attr])

Paint the string str at (y, x) with attributes attr, overwriting anything previously on the display.

attroff(attr)

Remove attribute attr from the "background" set applied to all writes to the current window.

attron(attr)

Add attribute attr from the "background" set applied to all writes to the current window.

attrset(attr)

Set the "background" set of attributes to *attr*. This set is initially 0 (no attributes).

Sets the background property of the window to the character *ch*, with attributes *attr*. The change is then applied to every character position in that window:

- •The attribute of every character in the window is changed to the new background attribute.
- •Wherever the former background character appears, it is changed to the new background character.

bkgdset(ch[, attr])

Sets the window's background. A window's background consists of a character and any combination of attributes. The attribute part of the background is combined (OR'ed) with all non-blank characters that are written into the window. Both the character and attribute parts of the background are combined with the blank characters. The background becomes a property of the character and moves with the character through any scrolling and insert/delete line/character operations.

Draw a border around the edges of the window. Each parameter specifies the character to use for a specific part of the border; see the table below for more details. The characters can be specified as integers or as one-character strings.

Note: A 0 value for any parameter will cause the default character to be used for that parameter. Keyword parameters can *not* be used. The defaults are listed in this table:

Parameter	Description	Default value
ls	Left side	ACS_VLINE
rs	Right side	ACS_VLINE
ts	Тор	ACS_HLINE
bs	Bottom	ACS_HLINE
tl	Upper-left corner	ACS_ULCORNER
tr	Upper-right corner	ACS_URCORNER
bl	Bottom-left corner	ACS_LLCORNER
br	Bottom-right corner	ACS_LRCORNER

box([vertch, horch])

Similar to border(), but both *ls* and *rs* are *vertch* and both *ts* and bs are *horch*. The default corner characters are always used by this function.

clear()

Like erase(), but also causes the whole window to be repainted upon next call to refresh().

clearok(yes)

If yes is 1, the next call to refresh() will clear the window completely.

clrtobot()

Erase from cursor to the end of the window: all lines below the cursor are deleted, and then the equivalent of clrtoeol() is performed.

clrtoeol()

Erase from cursor to the end of the line.

cursyncup()

Updates the current cursor position of all the ancestors of the window to reflect the current cursor position of the window.

delch([y, x])

Delete any character at (y, x).

deleteln()

Delete the line under the cursor. All following lines are moved up by 1 line.

derwin([nlines, ncols,] begin_y, begin_x)

An abbreviation for "derive window", derwin() is the same as calling subwin(), except that *begin_y* and *begin_x* are relative to the origin of the window, rather than relative to the entire screen. Returns a window object for the derived window.

echochar(ch[, attr])

Add character *ch* with attribute *attr*, and immediately call refresh() on the window.

enclose(y, x)

Tests whether the given pair of screen-relative character-cell coordinates are enclosed by the given window, returning true or false. It is useful for determining what subset of the screen windows enclose the location of a mouse event.

erase()

Clear the window.

getbegyx()

Return a tuple (y, x) of co-ordinates of upper-left corner.

getch([y, x])

Get a character. Note that the integer returned does *not* have to be in ASCII range: function keys, keypad keys and so on return numbers higher than 256. In no-delay mode, -1 is returned if there is no input.

getkey([y, x])

Get a character, returning a string instead of an integer, as getch() does. Function keys, keypad keys and so on return a multibyte string containing the key name. In no-delay mode, an exception is raised if there is no input.

getmaxyx()

Return a tuple (y, x) of the height and width of the window.

getparyx()

Returns the beginning coordinates of this window relative to its parent window into two integer variables y and x. Returns -1, -1 if this window has no parent.

getstr([y, x])

Read a string from the user, with primitive line editing capacity.

getyx()

Return a tuple (y, x) of current cursor position relative to the window's upper-left corner.

Display a horizontal line starting at (y, x) with length n consisting of the character ch.

idcok(flag)

If *flag* is false, curses no longer considers using the hardware insert/delete character feature of the terminal; if *flag* is true, use of character insertion and deletion is enabled. When curses is first initialized, use of character insert/delete is enabled by default.

idlok(yes)

If called with yes equal to 1, curses will try and use hardware line editing facilities. Otherwise, line insertion/deletion are disabled.

immedok(flag)

If *flag* is true, any change in the window image automatically causes the window to be refreshed; you no longer have to call refresh() yourself. However, it may degrade performance considerably, due to repeated calls to wrefresh. This option is disabled by default.

inch([y, x])

Return the character at the given position in the window. The bottom 8 bits are the character proper, and upper bits are the attributes.

insch([y, x,]ch[, attr])

Paint character ch at (y, x) with attributes attr, moving the line from position x right by one character.

insdelln(nlines)

Inserts *nlines* lines into the specified window above the current line. The *nlines* bottom lines are lost. For negative *nlines*, delete *nlines* lines starting with the one under the cursor, and move the remaining lines up. The bottom *nlines* lines are cleared. The current cursor position remains the same.

insertln()

Insert a blank line under the cursor. All following lines are moved down by 1 line.

Insert a character string (as many characters as will fit on the line) before the character under the cursor, up to n characters. If n is zero or negative, the entire string is inserted. All characters to the right of the cursor are shifted right, with the rightmost characters on the line being lost. The cursor position does not change (after moving to y, x, if specified).

Insert a character string (as many characters as will fit on the line) before the character under the cursor. All characters to the right of the cursor are shifted right, with the rightmost characters on the line being lost. The cursor position does not change (after moving to y, x, if specified).

Returns a string of characters, extracted from the window starting at the current cursor position, or at y, x if specified. Attributes are stripped from the characters. If n is specified, <code>instr()</code> returns return a string at most n characters long (exclusive of the trailing NUL).

is_linetouched(line)

Returns true if the specified line was modified since the last call to refresh(); otherwise returns false. Raises a curses.error exception if *line* is not valid for the given window.

is_wintouched()

Returns true if the specified window was modified since the last call to refresh(); otherwise returns

false.

keypad(yes)

If *yes* is 1, escape sequences generated by some keys (keypad, function keys) will be interpreted by curses. If *yes* is 0, escape sequences will be left as is in the input stream.

leaveok(yes)

If yes is 1, cursor is left where it is on update, instead of being at "cursor position." This reduces cursor movement where possible. If possible the cursor will be made invisible.

If yes is 0, cursor will always be at "cursor position" after an update.

$move(new_y, new_x)$

Move cursor to (new_y, new_x) .

mvderwin(y, x)

Moves the window inside its parent window. The screen-relative parameters of the window are not changed. This routine is used to display different parts of the parent window at the same physical position on the screen.

mvwin(new_y, new_x)

Move the window so its upper-left corner is at (new_y, new_x) .

nodelay(ves

If yes is 1, getch() will be non-blocking.

notimeout(yes)

If yes is 1, escape sequences will not be timed out.

If yes is 0, after a few milliseconds, an escape sequence will not be interpreted, and will be left in the input stream as is.

noutrefresh()

Mark for refresh but wait. This function updates the data structure representing the desired state of the window, but does not force an update of the physical screen. To accomplish that, call doupdate().

overlay(destwin[, sminrow, smincol, dminrow, dmincol, dmaxrow, dmaxcol])

Overlay the window on top of *destwin*. The windows need not be the same size, only the overlapping region is copied. This copy is non-destructive, which means that the current background character does not overwrite the old contents of *destwin*.

To get fine-grained control over the copied region, the second form of overlay() can be used. *sminrow* and *smincol* are the upper-left coordinates of the source window, and the other variables mark a rectangle in the destination window.

overwrite (destwin, sminrow, smincol, dminrow, dmincol, dmaxrow, dmaxcol)

Overwrite the window on top of *destwin*. The windows need not be the same size, in which case only the overlapping region is copied. This copy is destructive, which means that the current background character overwrites the old contents of *destwin*.

To get fine-grained control over the copied region, the second form of overwrite() can be used. *sminrow* and *smincol* are the upper-left coordinates of the source window, the other variables mark a rectangle in the destination window.

putwin(file)

Writes all data associated with the window into the provided file object. This information can be later retrieved using the getwin() function.

redrawln(beg, num)

Indicates that the num screen lines, starting at line beg, are corrupted and should be completely redrawn on the next refresh() call.

redrawwin()

Touches the entire window, causing it to be completely redrawn on the next refresh() call.

refresh(|pminrow, pmincol, sminrow, smincol, smaxrow, smaxcol|)

Update the display immediately (sync actual screen with previous drawing/deleting methods).

The 6 optional arguments can only be specified when the window is a pad created with newpad(). The

additional parameters are needed to indicate what part of the pad and screen are involved. *pminrow* and *pmincol* specify the upper left-hand corner of the rectangle to be displayed in the pad. *sminrow*, *smincol*, *smaxrow*, and *smaxcol* specify the edges of the rectangle to be displayed on the screen. The lower right-hand corner of the rectangle to be displayed in the pad is calculated from the screen coordinates, since the rectangles must be the same size. Both rectangles must be entirely contained within their respective structures. Negative values of *pminrow*, *pmincol*, *sminrow*, or *smincol* are treated as if they were zero.

scroll([lines = 1])

Scroll the screen or scrolling region upward by *lines* lines.

scrollok(flag)

Controls what happens when the cursor of a window is moved off the edge of the window or scrolling region, either as a result of a newline action on the bottom line, or typing the last character of the last line. If *flag* is false, the cursor is left on the bottom line. If *flag* is true, the window is scrolled up one line. Note that in order to get the physical scrolling effect on the terminal, it is also necessary to call idlok().

setscrreg(top, bottom)

Set the scrolling region from line *top* to line *bottom*. All scrolling actions will take place in this region.

standend()

Turn off the standout attribute. On some terminals this has the side effect of turning off all attributes.

standout()

Turn on attribute $A_STANDOUT$.

subpad([nlines, ncols,] begin_y, begin_x)

Return a sub-window, whose upper-left corner is at (begin_y, begin_x), and whose width/height is ncols/nlines.

subwin([nlines, ncols,] begin_y, begin_x)

Return a sub-window, whose upper-left corner is at (begin_y, begin_x), and whose width/height is ncols/nlines.

By default, the sub-window will extend from the specified position to the lower right corner of the window.

syncdown()

Touches each location in the window that has been touched in any of its ancestor windows. This routine is called by refresh(), so it should almost never be necessary to call it manually.

syncok(flag)

If called with *flag* set to true, then <code>syncup()</code> is called automatically whenever there is a change in the window.

syncup()

Touches all locations in ancestors of the window that have been changed in the window.

timeout(delay)

Sets blocking or non-blocking read behavior for the window. If *delay* is negative, blocking read is used (which will wait indefinitely for input). If *delay* is zero, then non-blocking read is used, and -1 will be returned by getch() if no input is waiting. If *delay* is positive, then getch() will block for *delay* milliseconds, and return -1 if there is still no input at the end of that time.

touchline(start, count)

Pretend *count* lines have been changed, starting with line *start*.

touchwin()

Pretend the whole window has been changed, for purposes of drawing optimizations.

untouchwin()

Marks all lines in the window as unchanged since the last call to refresh().

vline([y, x,]ch, n)

Display a vertical line starting at (y, x) with length n consisting of the character ch.

6.15.3 Constants

The curses module defines the following data members:

ERR

Some curses routines that return an integer, such as getch(), return ERR upon failure.

OK

Some curses routines that return an integer, such as napms (), return OK upon success.

version

A string representing the current version of the module. Also available as __version__.

Several constants are available to specify character cell attributes:

Meaning
Alternate character set mode.
Blink mode.
Bold mode.
Dim mode.
Normal attribute.
Standout mode.
Underline mode.

Keys are referred to by integer constants with names starting with 'KEY_'. The exact keycaps available are system dependent.

Key constant	Key
KEY_MIN	Minimum key value
KEY_BREAK	Break key (unreliable)
KEY_DOWN	Down-arrow
KEY_UP	Up-arrow
KEY_LEFT	Left-arrow
KEY_RIGHT	Right-arrow
KEY_HOME	Home key (upward+left arrow)
KEY_BACKSPACE	Backspace (unreliable)
KEY_F0	Function keys. Up to 64 function keys are supported.
$\mathtt{KEY}_\mathtt{F} n$	Value of function key <i>n</i>
KEY_DL	Delete line
KEY_IL	Insert line
KEY_DC	Delete character
KEY_IC	Insert char or enter insert mode
KEY_EIC	Exit insert char mode
KEY_CLEAR	Clear screen
KEY_EOS	Clear to end of screen
KEY_EOL	Clear to end of line
KEY_SF	Scroll 1 line forward
KEY_SR	Scroll 1 line backward (reverse)
KEY_NPAGE	Next page
KEY_PPAGE	Previous page
KEY_STAB	Set tab
KEY_CTAB	Clear tab
KEY_CATAB	Clear all tabs
KEY_ENTER	Enter or send (unreliable)
KEY_SRESET	Soft (partial) reset (unreliable)
KEY_RESET	Reset or hard reset (unreliable)
KEY_PRINT	Print
$\mathtt{KEY_LL}$	Home down or bottom (lower left)
KEY_A1	Upper left of keypad

Key constant	Key
KEY_A3	Upper right of keypad
KEY_B2	Center of keypad
KEY_C1	Lower left of keypad
KEY_C3	Lower right of keypad
KEY_BTAB	Back tab
KEY_BEG	Beg (beginning)
KEY_CANCEL	Cancel
KEY_CLOSE	Close
KEY_COMMAND	Cmd (command)
KEY_COPY	Сору
KEY_CREATE	Create
KEY_END	End
KEY_EXIT	Exit
KEY_FIND	Find
KEY_HELP	Help
KEY_MARK	Mark
KEY_MESSAGE	Message
KEY_MOVE	Move
KEY_NEXT	Next
KEY_OPEN	Open
KEY_OPTIONS	Options
KEY_PREVIOUS	Prev (previous)
KEY_REDO	Redo
KEY_REFERENCE	Ref (reference)
KEY_REFRESH	Refresh
KEY_REPLACE	Replace
KEY_RESTART	Restart
KEY_RESUME	Resume
KEY_SAVE	Save
KEY_SBEG	Shifted Beg (beginning)
KEY_SCANCEL	Shifted Cancel
KEY_SCOMMAND	Shifted Command
KEY_SCOPY	Shifted Copy
KEY_SCREATE	Shifted Create
KEY_SDC	Shifted Delete char
KEY_SDL	Shifted Delete line
KEY_SELECT	Select
KEY_SEND	Shifted End
KEY_SEOL	Shifted Clear line
KEY_SEXIT	Shifted Dxit
KEY_SFIND	Shifted Find
KEY_SHELP	Shifted Help
KEY_SHOME	Shifted Home
KEY_SIC	Shifted Input
$\mathtt{KEY}_\mathtt{SLEFT}$	Shifted Left arrow
$\mathtt{KEY}_\mathtt{SMESSAGE}$	Shifted Message
KEY_SMOVE	Shifted Move
KEY_SNEXT	Shifted Next
KEY_SOPTIONS	Shifted Options
KEY_SPREVIOUS	Shifted Prev
KEY_SPRINT	Shifted Print
KEY_SREDO	Shifted Redo
KEY_SREPLACE	Shifted Replace
KEY_SRIGHT	Shifted Right arrow
KEY_SRSUME	Shifted Resume Shifted Save
KEY_SSAVE	Shifted Suspend
KEY_SSUSPEND	Sinned Suspend

Key constant	Key
KEY_SUNDO	Shifted Undo
KEY_SUSPEND	Suspend
KEY_UNDO	Undo
KEY_MOUSE	Mouse event has occurred
KEY_RESIZE	Terminal resize event
KEY_MAX	Maximum key value

On VT100s and their software emulations, such as X terminal emulators, there are normally at least four function keys (KEY_F1, KEY_F2, KEY_F3, KEY_F4) available, and the arrow keys mapped to KEY_UP, KEY_DOWN, KEY_LEFT and KEY_RIGHT in the obvious way. If your machine has a PC keyboard, it is safe to expect arrow keys and twelve function keys (older PC keyboards may have only ten function keys); also, the following keypad mappings are standard:

Keycap	Constant
Insert	KEY_IC
Delete	KEY_DC
Home	KEY_HOME
End	KEY_END
Page Up	KEY_NPAGE
Page Down	KEY_PPAGE

The following table lists characters from the alternate character set. These are inherited from the VT100 terminal, and will generally be available on software emulations such as X terminals. When there is no graphic available, curses falls back on a crude printable ASCII approximation. **Note:** These are available only after initscr() has been called.

ACS code	Meaning
ACS_BBSS	alternate name for upper right corner
ACS_BLOCK	solid square block
ACS_BOARD	board of squares
ACS_BSBS	alternate name for horizontal line
ACS_BSSB	alternate name for upper left corner
ACS_BSSS	alternate name for top tee
ACS_BTEE	bottom tee
ACS_BULLET	bullet
ACS_CKBOARD	checker board (stipple)
ACS_DARROW	arrow pointing down
ACS_DEGREE	degree symbol
ACS_DIAMOND	diamond
ACS_GEQUAL	greater-than-or-equal-to
ACS_HLINE	horizontal line
ACS_LANTERN	lantern symbol
ACS_LARROW	left arrow
ACS_LEQUAL	less-than-or-equal-to
ACS_LLCORNER	lower left-hand corner
ACS_LRCORNER	lower right-hand corner
ACS_LTEE	left tee
ACS_NEQUAL	not-equal sign
ACS_PI	letter pi
ACS_PLMINUS	plus-or-minus sign
ACS_PLUS	big plus sign
ACS_RARROW	right arrow
ACS_RTEE	right tee
ACS_S1	scan line 1

ACS code	Meaning
ACS_S3	scan line 3
ACS_S7	scan line 7
ACS_S9	scan line 9
ACS_SBBS	alternate name for lower right corner
ACS_SBSB	alternate name for vertical line
ACS_SBSS	alternate name for right tee
ACS_SSBB	alternate name for lower left corner
ACS_SSBS	alternate name for bottom tee
ACS_SSSB	alternate name for left tee
ACS_SSSS	alternate name for crossover or big plus
ACS_STERLING	pound sterling
ACS_TTEE	top tee
ACS_UARROW	up arrow
ACS_ULCORNER	upper left corner
ACS_URCORNER	upper right corner
ACS_VLINE	vertical line

The following table lists the predefined colors:

Constant	Color
COLOR_BLACK	Black
COLOR_BLUE	Blue
COLOR_CYAN	Cyan (light greenish blue)
COLOR_GREEN	Green
COLOR_MAGENTA	Magenta (purplish red)
COLOR_RED	Red
COLOR_WHITE	White
COLOR_YELLOW	Yellow

6.16 curses.textpad — Text input widget for curses programs

New in version 1.6.

The curses.textpad module provides a Textbox class that handles elementary text editing in a curses window, supporting a set of keybindings resembling those of Emacs (thus, also of Netscape Navigator, BBedit 6.x, FrameMaker, and many other programs). The module also provides a rectangle-drawing function useful for framing text boxes or for other purposes.

The module curses.textpad defines the following function:

rectangle(win, uly, ulx, lry, lrx)

Draw a rectangle. The first argument must be a window object; the remaining arguments are coordinates relative to that window. The second and third arguments are the y and x coordinates of the upper left hand corner of the rectangle to be drawn; the fourth and fifth arguments are the y and x coordinates of the lower right hand corner. The rectangle will be drawn using VT100/IBM PC forms characters on terminals that make this possible (including xterm and most other software terminal emulators). Otherwise it will be drawn with ASCII dashes, vertical bars, and plus signs.

6.16.1 Textbox objects

You can instantiate a Textbox object as follows:

class Textbox(win)

Return a textbox widget object. The win argument should be a curses WindowObject in which the

textbox is to be contained. The edit cursor of the textbox is initially located at the upper left hand corner of the containing window, with coordinates (0, 0). The instance's stripspaces flag is initially on.

Textbox objects have the following methods:

edit([validator])

This is the entry point you will normally use. It accepts editing keystrokes until one of the termination keystrokes is entered. If *validator* is supplied, it must be a function. It will be called for each keystroke entered with the keystroke as a parameter; command dispatch is done on the result. This method returns the window contents as a string; whether blanks in the window are included is affected by the stripspaces member.

$do_{command}(ch)$

Process a single command keystroke. Here are the supported special keystrokes:

Keystroke	Action
Control-A	Go to left edge of window.
Control-B	Cursor left, wrapping to previous line if appropriate.
Control-D	Delete character under cursor.
Control-E	Go to right edge (stripspaces off) or end of line (stripspaces on).
Control-F	Cursor right, wrapping to next line when appropriate.
Control-G	Terminate, returning the window contents.
Control-H	Delete character backward.
Control-J	Terminate if the window is 1 line, otherwise insert newline.
Control-K	If line is blank, delete it, otherwise clear to end of line.
Control-L	Refresh screen.
Control-N	Cursor down; move down one line.
Control-O	Insert a blank line at cursor location.
Control-P	Cursor up; move up one line.

Move operations do nothing if the cursor is at an edge where the movement is not possible. The following synonyms are supported where possible:

Constant	Keystroke
KEY_LEFT	Control-B
KEY_RIGHT	Control-F
KEY_UP	Control-P
KEY_DOWN	Control-N
KEY_BACKSPACE	Control-h

All other keystrokes are treated as a command to insert the given character and move right (with line wrapping).

gather()

This method returns the window contents as a string; whether blanks in the window are included is affected by the stripspaces member.

stripspaces

This data member is a flag which controls the interpretation of blanks in the window. When it is on, trailing blanks on each line are ignored; any cursor motion that would land the cursor on a trailing blank goes to the end of that line instead, and trailing blanks are stripped when the window contents are gathered.

6.17 curses.wrapper — Terminal handler for curses programs

New in version 1.6.

This module supplies one function, wrapper(), which runs another function which should be the rest of your curses-using application. If the application raises an exception, wrapper() will restore the terminal to a sane state before re-raising the exception and generating a traceback.

wrapper(func, ...)

Wrapper function that initializes curses and calls another function, *func*, restoring normal keyboard/screen behavior on error. The callable object *func* is then passed the main window 'stdscr' as its first argument,

followed by any other arguments passed to wrapper ().

Before calling the hook function, wrapper() turns on cbreak mode, turns off echo, enables the terminal keypad, and initializes colors if the terminal has color support. On exit (whether normally or by exception) it restores cooked mode, turns on echo, and disables the terminal keypad.

6.18 curses.ascii — Utilities for ASCII characters

New in version 1.6.

The curses.ascii module supplies name constants for ASCII characters and functions to test membership in various ASCII character classes. The constants supplied are names for control characters as follows:

Name	Meaning
NUL	
SOH	Start of heading, console interrupt
STX	Start of text
ETX	End of text
EOT	End of transmission
ENQ	Enquiry, goes with ACK flow control
ACK	Acknowledgement
BEL	Bell
BS	Backspace
TAB	Tab
$_{ m HT}$	Alias for TAB: "Horizontal tab"
LF	Line feed
NL	Alias for LF: "New line"
VT	Vertical tab
FF	Form feed
CR	Carriage return
SO	Shift-out, begin alternate character set
SI	Shift-in, resume default character set
DLE	Data-link escape
DC1	XON, for flow control
DC2	Device control 2, block-mode flow control
DC3	XOFF, for flow control
DC4	Device control 4
NAK	Negative acknowledgement
SYN	Synchronous idle
ETB	End transmission block
CAN	Cancel
EM	End of medium
SUB	Substitute
ESC	Escape
FS	File separator
GS	Group separator
RS	Record separator, block-mode terminator
US	Unit separator
SP	Space
DEL	Delete

Note that many of these have little practical significance in modern usage. The mnemonics derive from teleprinter conventions that predate digital computers.

The module supplies the following functions, patterned on those in the standard C library:

isalnum(c)

Checks for an ASCII alphanumeric character; it is equivalent to 'isalpha(c) or isdigit(c)'.

isalpha(c)

Checks for an ASCII alphabetic character; it is equivalent to 'isupper(c) or islower(c)'.

isascii(c)

Checks for a character value that fits in the 7-bit ASCII set.

isblank(c)

Checks for an ASCII whitespace character.

iscntrl(c)

Checks for an ASCII control character (in the range 0x00 to 0x1f).

isdigit(c)

Checks for an ASCII decimal digit, '0' through '9'. This is equivalent to 'c in string.digits'.

isgraph(c)

Checks for ASCII any printable character except space.

islower(c)

Checks for an ASCII lower-case character.

isprint(c)

Checks for any ASCII printable character including space.

ispunct(c)

Checks for any printable ASCII character which is not a space or an alphanumeric character.

isspace(c)

Checks for ASCII white-space characters; space, line feed, carriage return, form feed, horizontal tab, vertical tab.

isupper(c)

Checks for an ASCII uppercase letter.

isxdigit(c)

Checks for an ASCII hexadecimal digit. This is equivalent to 'c in string.hexdigits'.

isctrl(c)

Checks for an ASCII control character (ordinal values 0 to 31).

ismeta(c)

Checks for a non-ASCII character (ordinal values 0x80 and above).

These functions accept either integers or strings; when the argument is a string, it is first converted using the built-in function ord().

Note that all these functions check ordinal bit values derived from the first character of the string you pass in; they do not actually know anything about the host machine's character encoding. For functions that know about the character encoding (and handle internationalization properly) see the string module.

The following two functions take either a single-character string or integer byte value; they return a value of the same type.

ascii(c)

Return the ASCII value corresponding to the low 7 bits of c.

ctrl(c)

Return the control character corresponding to the given character (the character bit value is bitwise-anded with 0x1f).

alt(c)

Return the 8-bit character corresponding to the given ASCII character (the character bit value is bitwise-ored with 0x80).

The following function takes either a single-character string or integer value; it returns a string.

unctrl(c)

Return a string representation of the ASCII character c. If c is printable, this string is the character itself. If the character is a control character (0x00-0x1f) the string consists of a caret ('^') followed by the corre-

sponding uppercase letter. If the character is an ASCII delete (0x7f) the string is $'^?'$. If the character has its meta bit (0x80) set, the meta bit is stripped, the preceding rules applied, and '!' prepended to the result.

controlnames

A 33-element string array that contains the ASCII mnemonics for the thirty-two ASCII control characters from 0 (NUL) to 0x1f (US), in order, plus the mnemonic 'SP' for the space character.

6.19 curses.panel — A panel stack extension for curses.

Panels are windows with the added feature of depth, so they can be stacked on top of each other, and only the visible portions of each window will be displayed. Panels can be added, moved up or down in the stack, and removed.

6.19.1 Functions

The module curses.panel defines the following functions:

bottom_panel()

Returns the bottom panel in the panel stack.

new_panel(win)

Returns a panel object, associating it with the given window win.

top_panel()

Returns the top panel in the panel stack.

update_panels()

Updates the virtual screen after changes in the panel stack. This does not call curses.doupdate(), so you'll have to do this yourself.

6.19.2 Panel Objects

Panel objects, as returned by new_panel() above, are windows with a stacking order. There's always a window associated with a panel which determines the content, while the panel methods are responsible for the window's depth in the panel stack.

Panel objects have the following methods:

above()

Returns the panel above the current panel.

below()

Returns the panel below the current panel.

bottom()

Push the panel to the bottom of the stack.

hidden()

Returns true if the panel is hidden (not visible), false otherwise.

hide()

Hide the panel. This does not delete the object, it just makes the window on screen invisible.

move(y, x)

Move the panel to the screen coordinates (y, x).

replace(win)

Change the window associated with the panel to the window win.

set_userptr(obj)

Set the panel's user pointer to *obj*. This is used to associate an arbitrary piece of data with the panel, and can be any Python object.

show()

Display the panel (which might have been hidden).

top()

Push panel to the top of the stack.

userptr()

Returns the user pointer for the panel. This might be any Python object.

window()

Returns the window object associated with the panel.

6.20 getopt — Parser for command line options

This module helps scripts to parse the command line arguments in sys.argv. It supports the same conventions as the UNIX getopt() function (including the special meanings of arguments of the form '-' and '--'). Long options similar to those supported by GNU software may be used as well via an optional third argument. This module provides a single function and an exception:

getopt(args, options[, long_options])

Parses command line options and parameter list. *args* is the argument list to be parsed, without the leading reference to the running program. Typically, this means 'sys.argv[1:]'. *options* is the string of option letters that the script wants to recognize, with options that require an argument followed by a colon (':'; i.e., the same format that UNIX getopt() uses).

Note: Unlike GNU getopt(), after a non-option argument, all further arguments are considered also non-options. This is similar to the way non-GNU UNIX systems work.

long_options, if specified, must be a list of strings with the names of the long options which should be supported. The leading '--' characters should not be included in the option name. Long options which require an argument should be followed by an equal sign ('='). To accept only long options, options should be an empty string. Long options on the command line can be recognized so long as they provide a prefix of the option name that matches exactly one of the accepted options. For example, if long_options is ['foo', 'frob'], the option --fo will match as --foo, but --f will not match uniquely, so GetoptError will be raised.

The return value consists of two elements: the first is a list of (option, value) pairs; the second is the list of program arguments left after the option list was stripped (this is a trailing slice of args). Each option-and-value pair returned has the option as its first element, prefixed with a hyphen for short options (e.g., '-x') or two hyphens for long options (e.g., '-long-option'), and the option argument as its second element, or an empty string if the option has no argument. The options occur in the list in the same order in which they were found, thus allowing multiple occurrences. Long and short options may be mixed.

gnu_getopt(args, options[, long_options])

This function works like <code>getopt()</code>, except that GNU style scanning mode is used by default. This means that option and non-option arguments may be intermixed. The <code>getopt()</code> function stops processing options as soon as a non-option argument is encountered.

If the first character of the option string is '+', or if the environment variable POSIXLY_CORRECT is set, then option processing stops as soon as a non-option argument is encountered.

exception GetoptError

This is raised when an unrecognized option is found in the argument list or when an option requiring an argument is given none. The argument to the exception is a string indicating the cause of the error. For long options, an argument given to an option which does not require one will also cause this exception to be raised. The attributes msg and opt give the error message and related option; if there is no specific option to which the exception relates, opt is an empty string.

Changed in version 1.6: Introduced GetoptError as a synonym for error.

exception error

Alias for GetoptError; for backward compatibility.

An example using only UNIX style options:

```
>>> import getopt
>>> args = '-a -b -cfoo -d bar al a2'.split()
>>> args
['-a', '-b', '-cfoo', '-d', 'bar', 'al', 'a2']
>>> optlist, args = getopt.getopt(args, 'abc:d:')
>>> optlist
[('-a', ''), ('-b', ''), ('-c', 'foo'), ('-d', 'bar')]
>>> args
['al', 'a2']
```

Using long option names is equally easy:

```
>>> s = '--condition=foo --testing --output-file abc.def -x al a2'
>>> args = s.split()
>>> args
['--condition=foo', '--testing', '--output-file', 'abc.def', '-x', 'al', 'a2']
>>> optlist, args = getopt.getopt(args, 'x', [
... 'condition=', 'output-file=', 'testing'])
>>> optlist
[('--condition', 'foo'), ('--testing', ''), ('--output-file', 'abc.def'), ('-x', '')]
>>> args
['al', 'a2']
```

In a script, typical usage is something like this:

```
import getopt, sys
def main():
    try:
        opts, args = getopt.getopt(sys.argv[1:], "ho:v", ["help", "output="])
    except getopt.GetoptError:
        # print help information and exit:
        usage()
        sys.exit(2)
    output = None
    verbose = False
    for o, a in opts:
        if o == "-v":
            verbose = True
        if o in ("-h", "--help"):
            usage()
            sys.exit()
        if o in ("-o", "--output"):
            output = a
if __name__ == "__main__":
    main()
```

See Also:

Module optparse (section 6.21):

More object-oriented command line option parsing.

6.21 optparse — More powerful command line option parser

New in version 2.3.

optparse is a more convenient, flexible, and powerful library for parsing command-line options than getopt. optparse uses a more declarative style of command-line parsing: you create an instance of OptionParser, populate it with options, and parse the command line. optparse allows users to specify options in the conventional GNU/POSIX syntax, and additionally generates usage and help messages for you.

Here's an example of using optparse in a simple script:

With these few lines of code, users of your script can now do the "usual thing" on the command-line, for example:

```
<yourscript> --file=outfile -q
```

As it parses the command line, optparse sets attributes of the options object returned by parse_args() based on user-supplied command-line values. When parse_args() returns from parsing this command line, options.filename will be "outfile" and options.verbose will be False. optparse supports both long and short options, allows short options to be merged together, and allows options to be associated with their arguments in a variety of ways. Thus, the following command lines are all equivalent to the above example:

```
<yourscript> -f outfile --quiet
<yourscript> --quiet --file outfile
<yourscript> -q -foutfile
<yourscript> -qfoutfile
```

Additionally, users can run one of

```
<yourscript> -h
<yourscript> --help
```

and optparse will print out a brief summary of your script's options:

where the value of *yourscript* is determined at runtime (normally from sys.argv[0]).

6.21.1 Background

optparse was explicitly designed to encourage the creation of programs with straightforward, conventional command-line interfaces. To that end, it supports only the most common command-line syntax and semantics conventionally used under UNIX. If you are unfamiliar with these conventions, read this section to acquaint yourself with them.

Terminology

argument a string entered on the command-line, and passed by the shell to execl() or execv(). In Python,
arguments are elements of sys.argv[1:] (sys.argv[0] is the name of the program being executed).
UNIX shells also use the term "word".

It is occasionally desirable to substitute an argument list other than sys.argv[1:], so you should read "argument" as "an element of sys.argv[1:], or of some other list provided as a substitute for sys.argv[1:]".

option an argument used to supply extra information to guide or customize the execution of a program. There are many different syntaxes for options; the traditional UNIX syntax is a hyphen ("-") followed by a single letter, e.g. "-x" or "-F". Also, traditional UNIX syntax allows multiple options to be merged into a single argument, e.g. "-x -F" is equivalent to "-xF". The GNU project introduced "--" followed by a series of hyphen-separated words, e.g. "--file" or "--dry-run". These are the only two option syntaxes provided by optparse.

Some other option syntaxes that the world has seen include:

- a hyphen followed by a few letters, e.g. "-pf" (this is *not* the same as multiple options merged into a single argument)
- a hyphen followed by a whole word, e.g. "-file" (this is technically equivalent to the previous syntax, but they aren't usually seen in the same program)
- a plus sign followed by a single letter, or a few letters, or a word, e.g. "+f", "+rgb"
- a slash followed by a letter, or a few letters, or a word, e.g. "/f", "/file"

These option syntaxes are not supported by optparse, and they never will be. This is deliberate: the first three are non-standard on any environment, and the last only makes sense if you're exclusively targeting VMS, MS-DOS, and/or Windows.

option argument an argument that follows an option, is closely associated with that option, and is consumed from the argument list when that option is. With optparse, option arguments may either be in a separate argument from their option:

```
-f foo
--file foo
```

or included in the same argument:

```
-ffoo
--file=foo
```

Typically, a given option either takes an argument or it doesn't. Lots of people want an "optional option arguments" feature, meaning that some options will take an argument if they see it, and won't if they don't. This is somewhat controversial, because it makes parsing ambiguous: if "-a" takes an optional argument and "-b" is another option entirely, how do we interpret "-ab"? Because of this ambiguity, optparse does not support this feature.

positional argument something leftover in the argument list after options have been parsed, i.e. after options and their arguments have been parsed and removed from the argument list.

required option an option that must be supplied on the command-line; note that the phrase "required option" is self-contradictory in English. optparse doesn't prevent you from implementing required options, but doesn't give you much help at it either. See examples/required_1.py and examples/required_2.py in the optparse source distribution for two ways to implement required options with optparse.

For example, consider this hypothetical command-line:

```
prog -v --report /tmp/report.txt foo bar
```

"-v" and "--report" are both options. Assuming that **--report** takes one argument, "/tmp/report.txt" is an option argument. "foo" and "bar" are positional arguments.

What are options for?

Options are used to provide extra information to tune or customize the execution of a program. In case it wasn't clear, options are usually *optional*. A program should be able to run just fine with no options whatsoever. (Pick a random program from the UNIX or GNU toolsets. Can it run without any options at all and still make sense? The main exceptions are find, tar, and dd—all of which are mutant oddballs that have been rightly criticized for their non-standard syntax and confusing interfaces.)

Lots of people want their programs to have "required options". Think about it. If it's required, then it's *not optional*! If there is a piece of information that your program absolutely requires in order to run successfully, that's what positional arguments are for.

As an example of good command-line interface design, consider the humble cp utility, for copying files. It doesn't make much sense to try to copy files without supplying a destination and at least one source. Hence, cp fails if you run it with no arguments. However, it has a flexible, useful syntax that does not require any options at all:

```
cp SOURCE DEST
cp SOURCE ... DEST-DIR
```

You can get pretty far with just that. Most cp implementations provide a bunch of options to tweak exactly how the files are copied: you can preserve mode and modification time, avoid following symlinks, ask before clobbering existing files, etc. But none of this distracts from the core mission of cp, which is to copy either one file to another, or several files to another directory.

What are positional arguments for?

Positional arguments are for those pieces of information that your program absolutely, positively requires to run.

A good user interface should have as few absolute requirements as possible. If your program requires 17 distinct pieces of information in order to run successfully, it doesn't much matter *how* you get that information from the user—most people will give up and walk away before they successfully run the program. This applies whether the user interface is a command-line, a configuration file, or a GUI: if you make that many demands on your users, most of them will simply give up.

In short, try to minimize the amount of information that users are absolutely required to supply—use sensible defaults whenever possible. Of course, you also want to make your programs reasonably flexible. That's what options are for. Again, it doesn't matter if they are entries in a config file, widgets in the "Preferences" dialog of a GUI, or command-line options—the more options you implement, the more flexible your program is, and the more complicated its implementation becomes. Too much flexibility has drawbacks as well, of course; too many options can overwhelm users and make your code much harder to maintain.

6.21.2 Tutorial

While optparse is quite flexible and powerful, it's also straightforward to use in most cases. This section covers the code patterns that are common to any optparse-based program.

First, you need to import the OptionParser class; then, early in the main program, create an OptionParser instance:

```
from optparse import OptionParser
[...]
parser = OptionParser()
```

Then you can start defining options. The basic syntax is:

Each option has one or more option strings, such as "-f" or "--file", and several option attributes that tell optparse what to expect and what to do when it encounters that option on the command line.

Typically, each option will have one short option string and one long option string, e.g.:

```
parser.add_option("-f", "--file", ...)
```

You're free to define as many short option strings and as many long option strings as you like (including zero), as long as there is at least one option string overall.

The option strings passed to add_option() are effectively labels for the option defined by that call. For brevity, we will frequently refer to *encountering an option* on the command line; in reality, optparse encounters *option strings* and looks up options from them.

Once all of your options are defined, instruct optparse to parse your program's command line:

```
(options, args) = parser.parse_args()
```

(If you like, you can pass a custom argument list to parse_args(), but that's rarely necessary: by default it uses sys.argv[1:].)

parse_args() returns two values:

- options, an object containing values for all of your options—e.g. if "--file" takes a single string argument, then options.file will be the filename supplied by the user, or None if the user did not supply that option
- args, the list of positional arguments leftover after parsing options

This tutorial section only covers the four most important option attributes: action, type, dest (destination), and help. Of these, action is the most fundamental.

Understanding option actions

Actions tell optparse what to do when it encounters an option on the command line. There is a fixed set of actions hard-coded into optparse; adding new actions is an advanced topic covered in section ??, Extending optparse. Most actions tell optparse to store a value in some variable—for example, take a string from the command line and store it in an attribute of options.

If you don't specify an option action, optparse defaults to store.

The store action

The most common option action is store, which tells optparse to take the next argument (or the remainder of the current argument), ensure that it is of the correct type, and store it to your chosen destination.

For example:

Now let's make up a fake command line and ask optparse to parse it:

```
args = ["-f", "foo.txt"]
(options, args) = parser.parse_args(args)
```

When optparse sees the option string "-f", it consumes the next argument, "foo.txt", and stores it in options.filename. So, after this call to parse_args(), options.filename is "foo.txt".

Some other option types supported by optparse are int and float. Here's an option that expects an integer argument:

```
parser.add_option("-n", type="int", dest="num")
```

Note that this option has no long option string, which is perfectly acceptable. Also, there's no explicit action, since the default is store.

Let's parse another fake command-line. This time, we'll jam the option argument right up against the option: since "-n42" (one argument) is equivalent to "-n 42" (two arguments), the code

```
(options, args) = parser.parse_args(["-n42"])
print options.num
```

will print "42".

If you don't specify a type, optparse assumes string. Combined with the fact that the default action is store, that means our first example can be a lot shorter:

```
parser.add_option("-f", "--file", dest="filename")
```

If you don't supply a destination, optparse figures out a sensible default from the option strings: if the first long option string is "--foo-bar", then the default destination is foo_bar. If there are no long option strings, optparse looks at the first short option string: the default destination for "-f" is f.

optparse also includes built-in long and complex types. Adding types is covered in section ??, Extending optparse.

Handling boolean (flag) options

Flag options—set a variable to true or false when a particular option is seen—are quite common. optparse supports them with two separate actions, store_true and store_false. For example, you might have a verbose flag that is turned on with "-v" and off with "-q":

```
parser.add_option("-v", action="store_true", dest="verbose")
parser.add_option("-q", action="store_false", dest="verbose")
```

Here we have two different options with the same destination, which is perfectly OK. (It just means you have to be a bit careful when setting default values—see below.)

When optparse encounters "-v" on the command line, it sets options.verbose to True; when it encounters "-q", options.verbose is set to False.

Other actions

Some other actions supported by optparse are:

```
append append this option's argument to a list
count increment a counter by one
callback call a specified function
```

These are covered in section 6.21.3, Reference Guide and section 6.21.4, Option Callbacks.

Default values

All of the above examples involve setting some variable (the "destination") when certain command-line options are seen. What happens if those options are never seen? Since we didn't supply any defaults, they are all set to None. This is usually fine, but sometimes you want more control. optparse lets you supply a default value for each destination, which is assigned before the command line is parsed.

First, consider the verbose/quiet example. If we want optparse to set verbose to True unless "-q" is seen, then we can do this:

```
\label{lem:parser.add_option("-v", action="store_true", dest="verbose", default=True)} parser.add_option("-q", action="store_false", dest="verbose")
```

Since default values apply to the *destination* rather than to any particular option, and these two options happen to have the same destination, this is exactly equivalent:

```
parser.add_option("-v", action="store_true", dest="verbose")
parser.add_option("-q", action="store_false", dest="verbose", default=True)
```

Consider this:

```
parser.add_option("-v", action="store_true", dest="verbose", default=False)
parser.add_option("-q", action="store_false", dest="verbose", default=True)
```

Again, the default value for verbose will be True: the last default value supplied for any particular destination is the one that counts.

A clearer way to specify default values is the set_defaults() method of OptionParser, which you can call at any time before calling parse_args():

```
parser.set_defaults(verbose=True)
parser.add_option(...)
(options, args) = parser.parse_args()
```

As before, the last value specified for a given option destination is the one that counts. For clarity, try to use one method or the other of setting default values, not both.

Generating help

optparse's ability to generate help and usage text automatically is useful for creating user-friendly command-line interfaces. All you have to do is supply a help value for each option, and optionally a short usage message for your whole program. Here's an OptionParser populated with user-friendly (documented) options:

If optparse encounters either "-h" or "--help" on the command-line, or if you just call parser.print_help(), it prints the following to standard output:

(If the help output is triggered by a help option, optparse exits after printing the help text.)

There's a lot going on here to help optparse generate the best possible help message:

• the script defines its own usage message:

```
usage = "usage: %prog [options] arg1 arg2"
```

optparse expands "prog" in the usage string to the name of the current program, i.e. os.path.basename(sys.argv[0]). The expanded string is then printed before the detailed option help.

If you don't supply a usage string, optparse uses a bland but sensible default: "usage: %prog [options]", which is fine if your script doesn't take any positional arguments.

- every option defines a help string, and doesn't worry about line- wrapping—optparse takes care of wrapping lines and making the help output look good.
- options that take a value indicate this fact in their automatically-generated help message, e.g. for the "mode" option:

```
-m MODE, --mode=MODE
```

Here, "MODE" is called the meta-variable: it stands for the argument that the user is expected to supply to **-m/--mode**. By default, optparse converts the destination variable name to uppercase and uses that for the meta-variable. Sometimes, that's not what you want—for example, the **--filename** option explicitly sets metavar="FILE", resulting in this automatically-generated option description:

```
-f FILE, --filename=FILE
```

This is important for more than just saving space, though: the manually written help text uses the meta-variable "FILE" to clue the user in that there's a connection between the semi-formal syntax "-f FILE" and the informal semantic description "write output to FILE". This is a simple but effective way to make your help text a lot clearer and more useful for end users.

• options that have a default value can include %default in the help string—optparse will replace it with str() of the option's default value. If an option has no default value (or the default value is None), %default expands to none.

Printing a version string

Similar to the brief usage string, optparse can also print a version string for your program. You have to supply the string as the version argument to OptionParser:

```
parser = OptionParser(usage="%prog [-f] [-q]", version="%prog 1.0")
```

Note that "%prog" is expanded just like it is in usage. Apart from that, version can contain anything you like. When you supply it, optparse automatically adds a "--version" option to your parser. If it encounters this option on the command line, it expands your version string (by replacing "%prog"), prints it to stdout, and exits.

For example, if your script is called /usr/bin/foo:

```
$ /usr/bin/foo --version
foo 1.0
```

How optparse handles errors

There are two broad classes of errors that optparse has to worry about: programmer errors and user errors. Programmer errors are usually erroneous calls to parser.add_option(), e.g. invalid option strings, unknown option attributes, missing option attributes, etc. These are dealt with in the usual way: raise an exception (either optparse.OptionError or TypeError) and let the program crash.

Handling user errors is much more important, since they are guaranteed to happen no matter how stable your code is. optparse can automatically detect some user errors, such as bad option arguments (passing "-n 4x" where -n takes an integer argument), missing arguments ("-n" at the end of the command line, where -n takes an argument of any type). Also, you can call parser.error() to signal an application-defined error condition:

```
(options, args) = parser.parse_args()
[...]
if options.a and options.b:
    parser.error("options -a and -b are mutually exclusive")
```

In either case, optparse handles the error the same way: it prints the program's usage message and an error message to standard error and exits with error status 2.

Consider the first example above, where the user passes "4x" to an option that takes an integer:

```
$ /usr/bin/foo -n 4x
usage: foo [options]

foo: error: option -n: invalid integer value: '4x'
```

Or, where the user fails to pass a value at all:

```
$ /usr/bin/foo -n
usage: foo [options]
foo: error: -n option requires an argument
```

optparse-generated error messages take care always to mention the option involved in the error; be sure to do the same when calling parser.error() from your application code.

If optparse's default error-handling behaviour does not suite your needs, you'll need to subclass OptionParser and override exit() and/or error().

Putting it all together

Here's what optparse-based scripts usually look like:

```
from optparse import OptionParser
[...]
def main():
   usage = "usage: %prog [options] arg"
    parser = OptionParser(usage)
    parser.add_option("-f", "--file", dest="filename",
                      help="read data from FILENAME")
    parser.add_option("-v", "--verbose",
                      action="store_true", dest="verbose")
    parser.add_option("-q", "--quiet",
                     action="store_false", dest="verbose")
    [...]
    (options, args) = parser.parse_args()
    if len(args) != 1:
        parser.error("incorrect number of arguments")
    if options.verbose:
        print "reading %s..." % options.filename
    [...]
if __name__ == "__main__":
    main()
```

6.21.3 Reference Guide

Creating the parser

The first step in using optparse is to create an OptionParser instance:

```
parser = OptionParser(...)
```

The OptionParser constructor has no required arguments, but a number of optional keyword arguments. You

should always pass them as keyword arguments, i.e. do not rely on the order in which the arguments are declared.

- usage (default: "%prog [options]") The usage summary to print when your program is run
 incorrectly or with a help option. When optparse prints the usage string, it expands %prog to
 os.path.basename(sys.argv[0]) (or to prog if you passed that keyword argument).
 To suppress a usage message, pass the special value optparse.SUPPRESS_USAGE.
- option_class (default: optparse.Option) Class to use when adding options to the parser in add_option().
- **version** (**default: None**) A version string to print when the user supplies a version option. If you supply a true value for version, optparse automatically adds a version option with the single option string "--version". The substring "%prog" is expanded the same as for usage.
- **conflict_handler** (**default: "error"**) Specifies what to do when options with conflicting option strings are added to the parser; see section 6.21.3, Conflicts between options.
- **description** (**default: None**) A paragraph of text giving a brief overview of your program. optparse reformats this paragraph to fit the current terminal width and prints it when the user requests help (after usage, but before the list of options).
- **formatter** (**default:** a new IndentedHelpFormatter) An instance of optparse.HelpFormatter that will be used for printing help text. optparse provides two concrete classes for this purpose: IndentedHelpFormatter and TitledHelpFormatter.
- add_help_option (default: True) If true, optparse will add a help option (with option strings "-h" and "--help") to the parser.

prog

Defining options

Each Option instance represents a set of synonymous command-line option strings, e.g. **-f** and **--file**. You can specify any number of short or long option strings, but you must specify at least one overall option string.

The canonical way to create an Option instance is with the add_option() method of OptionParser:

```
parser.add_option(opt_str[, ...], attr=value, ...)
```

To define an option with only a short option string:

```
parser.add_option("-f", attr=value, ...)
```

And to define an option with only a long option string:

```
parser.add_option("--foo", attr=value, ...)
```

The keyword arguments define attributes of the new Option object. The most important option attribute is action, and it largely determines which other attributes are relevant or required. If you pass irrelevant option attributes, or fail to pass required ones, optparse raises an OptionError exception explaining your mistake.

An options's *action* determines what optparse does when it encounters this option on the command-line. The standard option actions hard-coded into optparse are:

```
store store this option's argument (default)
```

store_const store a constant value

store_**true** store a true value

store_false store a false value

append append this option's argument to a list

count increment a counter by one

callback call a specified function

help print a usage message including all options and the documentation for them

(If you don't supply an action, the default is store. For this action, you may also supply type and dest option attributes; see below.)

As you can see, most actions involve storing or updating a value somewhere. optparse always creates a special object for this, conventionally called options (it happens to be an instance of optparse. Values). Option arguments (and various other values) are stored as attributes of this object, according to the dest (destination) option attribute.

For example, when you call

```
parser.parse_args()
```

one of the first things optparse does is create the options object:

```
options = Values()
```

If one of the options in this parser is defined with

```
parser.add_option("-f", "--file", action="store", type="string", dest="filename")
```

and the command-line being parsed includes any of the following:

```
-ffoo
-f foo
--file=foo
--file foo
```

then optparse, on seeing this option, will do the equivalent of

```
options.filename = "foo"
```

The type and dest option attributes are almost as important as action, but action is the only one that makes sense for *all* options.

Standard option actions

The various option actions all have slightly different requirements and effects. Most actions have several relevant option attributes which you may specify to guide optparse's behaviour; a few have required attributes, which you must specify for any option using that action.

• store [relevant: type, dest, nargs, choices]

The option must be followed by an argument, which is converted to a value according to type and stored in dest. If nargs > 1, multiple arguments will be consumed from the command line; all will be converted according to type and stored to dest as a tuple. See the "Option types" section below.

If choices is supplied (a list or tuple of strings), the type defaults to choice.

If type is not supplied, it defaults to string.

If dest is not supplied, optparse derives a destination from the first long option string (e.g., "--foo-bar" implies foo_bar). If there are no long option strings, optparse derives a destination from the first short option string (e.g., "-f" implies f).

Example:

```
parser.add_option("-f")
parser.add_option("-p", type="float", nargs=3, dest="point")
```

As it parses the command line

```
-f foo.txt -p 1 -3.5 4 -fbar.txt
```

optparse will set

```
options.f = "foo.txt"
options.point = (1.0, -3.5, 4.0)
options.f = "bar.txt"
```

• store_const [required: const; relevant: dest]

The value const is stored in dest.

Example:

• store_true [relevant: dest]

A special case of store_const that stores a true value to dest.

• store_false [relevant: dest]

Like store_true, but stores a false value.

Example:

```
parser.add_option("--clobber", action="store_true", dest="clobber")
parser.add_option("--no-clobber", action="store_false", dest="clobber")
```

• append [relevant: type, dest, nargs, choices]

The option must be followed by an argument, which is appended to the list in dest. If no default value for dest is supplied, an empty list is automatically created when optparse first encounters this option on the command-line. If nargs > 1, multiple arguments are consumed, and a tuple of length nargs is appended to dest.

The defaults for type and dest are the same as for the store action.

Example:

```
parser.add_option("-t", "--tracks", action="append", type="int")
```

If "-t3" is seen on the command-line, optparse does the equivalent of:

```
options.tracks = []
options.tracks.append(int("3"))
```

If, a little later on, "--tracks=4" is seen, it does:

```
options.tracks.append(int("4"))
```

• count [relevant: dest]

Increment the integer stored at dest. If no default value is supplied, dest is set to zero before being incremented the first time.

Example:

```
parser.add_option("-v", action="count", dest="verbosity")
```

The first time "-v" is seen on the command line, optparse does the equivalent of:

```
options.verbosity = 0
options.verbosity += 1
```

Every subsequent occurrence of "-v" results in

```
options.verbosity += 1
```

• callback [required: callback; relevant: type, nargs, callback_args, callback_kwargs]

Call the function specified by callback, which is called as

```
func(option, opt_str, value, parser, *args, **kwargs)
```

See section 6.21.4, Option Callbacks for more detail.

• help

Prints a complete help message for all the options in the current option parser. The help message is constructed from the usage string passed to OptionParser's constructor and the help string passed to every option.

If no help string is supplied for an option, it will still be listed in the help message. To omit an option entirely, use the special value optparse.SUPPRESS_HELP.

optparse automatically adds a help option to all OptionParsers, so you do not normally need to create one.

Example:

If optparse sees either "-h" or "--help" on the command line, it will print something like the following help message to stdout (assuming sys.argv[0] is "foo.py"):

After printing the help message, optparse terminates your process with sys.exit(0).

• version

Prints the version number supplied to the OptionParser to stdout and exits. The version number is actually formatted and printed by the print_version() method of OptionParser. Generally only relevant if the version argument is supplied to the OptionParser constructor. As with help options, you will rarely create version options, since optparse automatically adds them when needed.

Option attributes

The following option attributes may be passed as keyword arguments to parser.add_option(). If you pass an option attribute that is not relevant to a particular option, or fail to pass a required option attribute, optparse raises OptionError.

• action (default: "store")

Determines optparse's behaviour when this option is seen on the command line; the available options are documented above.

• type (default: "string")

The argument type expected by this option (e.g., "string" or "int"); the available option types are documented below.

• dest (default: derived from option strings)

If the option's action implies writing or modifying a value somewhere, this tells optparse where to write it: dest names an attribute of the options object that optparse builds as it parses the command line.

• default (deprecated)

The value to use for this option's destination if the option is not seen on the command line. Deprecated; use parser.set_defaults() instead.

• nargs (default: 1)

How many arguments of type type should be consumed when this option is seen. If > 1, optparse will store a tuple of values to dest.

• const

For actions that store a constant value, the constant value to store.

• choices

For options of type "choice", the list of strings the user may choose from.

• callback

For options with action "callback", the callable to call when this option is seen. See section 6.21.4, Option Callbacks for detail on the arguments passed to callable.

• callback_args, callback_kwargs

Additional positional and keyword arguments to pass to callback after the four standard callback arguments.

• help

Help text to print for this option when listing all available options after the user supplies a help option (such as "--help"). If no help text is supplied, the option will be listed without help text. To hide this option, use the special value SUPPRESS_HELP.

• metavar (default: derived from option strings)

Stand-in for the option argument(s) to use when printing help text. See section 6.21.2, the tutorial for an example.

Standard option types

optparse has six built-in option types: string, int, long, choice, float and complex. If you need to add new option types, see section ??, Extending optparse.

Arguments to string options are not checked or converted in any way: the text on the command line is stored in the destination (or passed to the callback) as-is.

Integer arguments are passed to int() to convert them to Python integers. If int() fails, so will optparse, although with a more useful error message. (Internally, optparse raises OptionValueError; OptionParser catches this exception higher up and terminates your program with a useful error message.)

Likewise, float arguments are passed to float () for conversion, long arguments to long (), and complex arguments to complex (). Apart from that, they are handled identically to integer arguments.

choice options are a subtype of string options. The choices option attribute (a sequence of strings) defines the set of allowed option arguments. optparse.check_choice() compares user-supplied option arguments against this master list and raises OptionValueError if an invalid string is given.

Parsing arguments

The whole point of creating and populating an OptionParser is to call its parse_args() method:

```
(options, args) = parser.parse_args(args=None, options=None)
```

where the input parameters are

args the list of arguments to process (sys.argv[1:] by default)

options object to store option arguments in (a new instance of optparse. Values by default)

and the return values are

options the same object as was passed in as options, or the new optparse. Values instance created by optparse

args the leftover positional arguments after all options have been processed

The most common usage is to supply neither keyword argument. If you supply a values object, it will be repeatedly modified with a setattr() call for every option argument written to an option destination, and finally returned by parse_args().

If parse_args() encounters any errors in the argument list, it calls the OptionParser's error() method with an appropriate end-user error message. This ultimately terminates your process with an exit status of 2 (the traditional UNIX exit status for command-line errors).

Querying and manipulating your option parser

Sometimes, it's useful to poke around your option parser and see what's there. OptionParser provides a couple of methods to help you out:

has_option(opt_str) Return true if the OptionParser has an option with option string opt_str (e.g., "-q" or "--verbose").

get_option(opt_str) Returns the Option instance with the option string opt_str, or None if no options
have that option string.

remove_option(opt_str) If the OptionParser has an option corresponding to opt_str, that option is removed. If that option provided any other option strings, all of those option strings become invalid. If opt_str does not occur in any option belonging to this OptionParser, raises ValueError.

Conflicts between options

If you're not careful, it's easy to define options with conflicting option strings:

```
parser.add_option("-n", "--dry-run", ...)
[...]
parser.add_option("-n", "--noisy", ...)
```

(This is particularly true if you've defined your own OptionParser subclass with some standard options.)

Every time you add an option, optparse checks for conflicts with existing options. If it finds any, it invokes the current conflict-handling mechanism. You can set the conflict-handling mechanism either in the constructor:

```
parser = OptionParser(..., conflict_handler=handler)
```

or with a separate call:

```
parser.set_conflict_handler(handler)
```

The available conflict handlers are:

error (default) assume option conflicts are a programming error and raise OptionConflictError
resolve resolve option conflicts intelligently (see below)

As an example, let's define an OptionParser that resolves conflicts intelligently and add conflicting options to it:

```
parser = OptionParser(conflict_handler="resolve")
parser.add_option("-n", "--dry-run", ..., help="do no harm")
parser.add_option("-n", "--noisy", ..., help="be noisy")
```

At this point, optparse detects that a previously-added option is already using the "-n" option string. Since conflict_handler is "resolve", it resolves the situation by removing "-n" from the earlier option's list of option strings. Now "--dry-run" is the only way for the user to activate that option. If the user asks for help, the help message will reflect that:

It's possible to whittle away the option strings for a previously-added option until there are none left, and the user has no way of invoking that option from the command-line. In that case, optparse removes that option completely, so it doesn't show up in help text or anywhere else. Carrying on with our existing OptionParser:

```
parser.add_option("--dry-run", ..., help="new dry-run option")
```

At this point, the original **-n/--dry-run** option is no longer accessible, so optparse removes it, leaving this help text:

```
options:
  [...]
  -n, --noisy be noisy
  --dry-run new dry-run option
```

Other methods

OptionParser supports several other public methods:

• set_usage(usage)

Set the usage string according to the rules described above for the usage constructor keyword argument. Passing None sets the default usage string; use SUPPRESS_USAGE to suppress a usage message.

• enable_interspersed_args(), disable_interspersed_args()

Enable/disable positional arguments interspersed with options, similar to GNU getopt (enabled by default). For example, if "-a" and "-b" are both simple options that take no arguments, optparse normally accepts this syntax:

```
prog -a arg1 -b arg2
```

and treats it as equivalent to

```
proq -a -b arq1 arq2
```

To disable this feature, call disable_interspersed_args(). This restores traditional UNIX syntax, where option parsing stops with the first non-option argument.

• set_defaults(dest=value, ...)

Set default values for several option destinations at once. Using set_defaults() is the preferred way to set default values for options, since multiple options can share the same destination. For example, if several "mode" options all set the same destination, any one of them can set the default, and the last one wins:

To avoid this confusion, use set_defaults():

6.21.4 Option Callbacks

When optparse's built-in actions and types aren't quite enough for your needs, you have two choices: extend optparse or define a callback option. Extending optparse is more general, but overkill for a lot of simple cases. Quite often a simple callback is all you need.

There are two steps to defining a callback option:

- define the option itself using the callback action
- write the callback; this is a function (or method) that takes at least four arguments, as described below

Defining a callback option

As always, the easiest way to define a callback option is by using the parser.add_option() method. Apart from action, the only option attribute you must specify is callback, the function to call:

```
parser.add_option("-c", action="callback", callback=my_callback)
```

callback is a function (or other callable object), so you must have already defined my_callback() when you create this callback option. In this simple case, optparse doesn't even know if -c takes any arguments, which usually means that the option takes no arguments—the mere presence of -c on the command-line is all it needs to know. In some circumstances, though, you might want your callback to consume an arbitrary number of command-line arguments. This is where writing callbacks gets tricky; it's covered later in this section.

optparse always passes four particular arguments to your callback, and it will only pass additional arguments if you specify them via callback_args and callback_kwargs. Thus, the minimal callback function signature is:

```
def my_callback(option, opt, value, parser):
```

The four arguments to a callback are described below.

There are several other option attributes that you can supply when you define a callback option:

type has its usual meaning: as with the store or append actions, it instructs optparse to consume one argument and convert it to type. Rather than storing the converted value(s) anywhere, though, optparse passes it to your callback function.

nargs also has its usual meaning: if it is supplied and > 1, optparse will consume nargs arguments, each of which must be convertible to type. It then passes a tuple of converted values to your callback.

callback_args a tuple of extra positional arguments to pass to the callback

callback_kwargs a dictionary of extra keyword arguments to pass to the callback

How callbacks are called

All callbacks are called as follows:

```
func(option, opt_str, value, parser, *args, **kwargs)
```

where

option is the Option instance that's calling the callback

opt_str is the option string seen on the command-line that's triggering the callback. (If an abbreviated long option was used, opt_str will be the full, canonical option string—e.g. if the user puts "--foo" on the command-line as an abbreviation for "--foobar", then opt_str will be "--foobar".)

value is the argument to this option seen on the command-line. optparse will only expect an argument if type is set; the type of value will be the type implied by the option's type. If type for this option is None (no argument expected), then value will be None. If nargs > 1, value will be a tuple of values of the appropriate type.

parser is the OptionParser instance driving the whole thing, mainly useful because you can access some other interesting data through its instance attributes:

parser.largs the current list of leftover arguments, ie. arguments that have been consumed but are neither options nor option arguments. Feel free to modify parser.largs, e.g. by adding more arguments to it. (This list will become args, the second return value of parse_args().) parser.rargs the current list of remaining arguments, ie. with opt_str and value (if applicable)
removed, and only the arguments following them still there. Feel free to modify parser.rargs,
e.g. by consuming more arguments.

parser.values the object where option values are by default stored (an instance of opt-parse. Option Values). This lets callbacks use the same mechanism as the rest of optparse for storing option values; you don't need to mess around with globals or closures. You can also access or modify the value(s) of any options already encountered on the command-line.

args is a tuple of arbitrary positional arguments supplied via the callback_args option attribute.

kwargs is a dictionary of arbitrary keyword arguments supplied via callback_kwargs.

Raising errors in a callback

The callback function should raise OptionValueError if there are any problems with the option or its argument(s). optparse catches this and terminates the program, printing the error message you supply to stderr. Your message should be clear, concise, accurate, and mention the option at fault. Otherwise, the user will have a hard time figuring out what he did wrong.

Callback example 1: trivial callback

Here's an example of a callback option that takes no arguments, and simply records that the option was seen:

```
def record_foo_seen(option, opt_str, value, parser):
    parser.saw_foo = True

parser.add_option("--foo", action="callback", callback=record_foo_seen)
```

Of course, you could do that with the store_true action.

Callback example 2: check option order

Here's a slightly more interesting example: record the fact that "-a" is seen, but blow up if it comes after "-b" in the command-line.

```
def check_order(option, opt_str, value, parser):
    if parser.values.b:
        raise OptionValueError("can't use -a after -b")
        parser.values.a = 1
[...]
parser.add_option("-a", action="callback", callback=check_order)
parser.add_option("-b", action="store_true", dest="b")
```

Callback example 3: check option order (generalized)

If you want to re-use this callback for several similar options (set a flag, but blow up if "-b" has already been seen), it needs a bit of work: the error message and the flag that it sets must be generalized.

```
def check_order(option, opt_str, value, parser):
    if parser.values.b:
        raise OptionValueError("can't use %s after -b" % opt_str)
        setattr(parser.values, option.dest, 1)
[...]
parser.add_option("-a", action="callback", callback=check_order, dest='a')
parser.add_option("-b", action="store_true", dest="b")
parser.add_option("-c", action="callback", callback=check_order, dest='c')
```

Callback example 4: check arbitrary condition

Of course, you could put any condition in there—you're not limited to checking the values of already-defined options. For example, if you have options that should not be called when the moon is full, all you have to do is this:

(The definition of is_moon_full() is left as an exercise for the reader.)

Callback example 5: fixed arguments

Things get slightly more interesting when you define callback options that take a fixed number of arguments. Specifying that a callback option takes arguments is similar to defining a store or append option: if you define type, then the option takes one argument that must be convertible to that type; if you further define nargs, then the option takes nargs arguments.

Here's an example that just emulates the standard store action:

Note that optparse takes care of consuming 3 arguments and converting them to integers for you; all you have to do is store them. (Or whatever; obviously you don't need a callback for this example.)

Callback example 6: variable arguments

Things get hairy when you want an option to take a variable number of arguments. For this case, you must write a callback, as optparse doesn't provide any built-in capabilities for it. And you have to deal with certain intricacies of conventional UNIX command-line parsing that optparse normally handles for you. In particular, callbacks should implement the conventional rules for bare "--" and "-" arguments:

• either "--" or "-" can be option arguments

- bare "--" (if not the argument to some option): halt command-line processing and discard the "--"
- bare "-" (if not the argument to some option): halt command-line processing but keep the "-" (append it to parser.largs)

If you want an option that takes a variable number of arguments, there are several subtle, tricky issues to worry about. The exact implementation you choose will be based on which trade-offs you're willing to make for your application (which is why optparse doesn't support this sort of thing directly).

Nevertheless, here's a stab at a callback for an option with variable arguments:

```
def vararg_callback(option, opt_str, value, parser):
    assert value is None
    done = 0
    value = []
    rargs = parser.rargs
    while rargs:
        arg = rargs[0]
        # Stop if we hit an arg like "--foo", "-a", "-fx", "--file=f",
        \# etc. Note that this also stops on "-3" or "-3.0", so if
        # your option takes numeric values, you will need to handle
        # this.
        if ((arg[:2] == "--" and len(arg) > 2) or
            (arg[:1] == "-" and len(arg) > 1 and arg[1] != "-")):
        else:
            value.append(arg)
            del rargs[0]
     setattr(parser.values, option.dest, value)
[...]
parser.add_option("-c", "--callback",
                  action="callback", callback=varargs)
```

The main weakness with this particular implementation is that negative numbers in the arguments following "-c" will be interpreted as further options (probably causing an error), rather than as arguments to "-c". Fixing this is left as an exercise for the reader.

6.21.5 Extending optparse

Since the two major controlling factors in how optparse interprets command-line options are the action and type of each option, the most likely direction of extension is to add new actions and new types.

Also, the examples/ directory of the source distribution includes several demonstrations of extending optparse in different ways: e.g. a case-insensitive option parser, or two kinds of option parsers that implement "required options".

Adding new types

To add new types, you need to define your own subclass of optparse's Option class. This class has a couple of attributes that define optparse's types: TYPES and TYPE_CHECKER.

TYPES is a tuple of type names; in your subclass, simply define a new tuple TYPES that builds on the standard one.

TYPE_CHECKER is a dictionary mapping type names to type-checking functions. A type-checking function has the following signature:

```
def check_mytype(option, opt, value)
```

where option is an Option instance, opt is an option string (e.g., "-f"), and value is the string from the command line that must be checked and converted to your desired type. check_mytype() should return an object of the hypothetical type mytype. The value returned by a type-checking function will wind up in the OptionValues instance returned by OptionParser.parse_args(), or be passed to a callback as the value parameter.

Your type-checking function should raise OptionValueError if it encounters any problems. OptionValueError takes a single string argument, which is passed as-is to OptionParser's error() method, which in turn prepends the program name and the string "error: " and prints everything to stderr before terminating the process.

Here's a silly example that demonstrates adding a complex option type to parse Python-style complex numbers on the command line. (This is even sillier than it used to be, because optparse 1.3 added built-in support for complex numbers, but never mind.)

First, the necessary imports:

```
from copy import copy
from optparse import Option, OptionValueError
```

You need to define your type-checker first, since it's referred to later (in the TYPE_CHECKER class attribute of your Option subclass):

Finally, the Option subclass:

```
class MyOption (Option):
    TYPES = Option.TYPES + ("complex",)
    TYPE_CHECKER = copy(Option.TYPE_CHECKER)
    TYPE_CHECKER["complex"] = check_complex
```

(If we didn't make a copy() of Option.TYPE_CHECKER, we would end up modifying the TYPE_CHECKER attribute of optparse's Option class. This being Python, nothing stops you from doing that except good manners and common sense.)

That's it! Now you can write a script that uses the new option type just like any other optparse-based script, except you have to instruct your OptionParser to use MyOption instead of Option:

```
parser = OptionParser(option_class=MyOption)
parser.add_option("-c", type="complex")
```

Alternately, you can build your own option list and pass it to OptionParser; if you don't use $add_option()$ in the above way, you don't need to tell OptionParser which option class to use:

```
option_list = [MyOption("-c", action="store", type="complex", dest="c")]
parser = OptionParser(option_list=option_list)
```

Adding new actions

Adding new actions is a bit trickier, because you have to understand that optparse has a couple of classifications for actions:

"store" actions actions that result in optparse storing a value to an attribute of the current OptionValues instance; these options require a dest attribute to be supplied to the Option constructor

"typed" actions actions that take a value from the command line and expect it to be of a certain type; or rather, a string that can be converted to a certain type. These options require a type attribute to the Option constructor.

These are overlapping sets: some default "store" actions are store, store_const, append, and count, while the default "typed" actions are store, append, and callback.

When you add an action, you need to decide if it's a "store" action, a "typed" action, neither, or both. Three class attributes of Option (or your Option subclass) control this:

ACTIONS all actions must be listed in ACTIONS

STORE_ACTIONS "store" actions are additionally listed here

TYPED_ACTIONS "typed" actions are additionally listed here

In order to actually implement your new action, you must override Option's take_action() method and add a case that recognizes your action.

For example, let's add an extend action. This is similar to the standard append action, but instead of taking a single value from the command-line and appending it to an existing list, extend will take multiple values in a single comma-delimited string, and extend an existing list with them. That is, if "--names" is an extend option of type string, the command line

```
--names=foo,bar --names blah --names ding,dong
```

would result in a list

```
["foo", "bar", "blah", "ding", "dong"]
```

Again we define a subclass of Option:

```
class MyOption (Option):

ACTIONS = Option.ACTIONS + ("extend",)
STORE_ACTIONS = Option.STORE_ACTIONS + ("extend",)
TYPED_ACTIONS = Option.TYPED_ACTIONS + ("extend",)

def take_action(self, action, dest, opt, value, values, parser):
    if action == "extend":
        lvalue = value.split(",")
        values.ensure_value(dest, []).extend(lvalue)
    else:
        Option.take_action(
            self, action, dest, opt, value, values, parser)
```

Features of note:

- extend both expects a value on the command-line and stores that value somewhere, so it goes in both STORE_ACTIONS and TYPED_ACTIONS
- MyOption.take_action() implements just this one new action, and passes control back to Option.take_action() for the standard optparse actions
- values is an instance of the optparse_parser. Values class, which provides the very useful ensure_value() method. ensure_value() is essentially getattr() with a safety valve; it is called as

```
values.ensure_value(attr, value)
```

If the attr attribute of values doesn't exist or is None, then ensure_value() first sets it to value, and then returns 'value. This is very handy for actions like extend, append, and count, all of which accumulate data in a variable and expect that variable to be of a certain type (a list for the first two, an integer for the latter). Using ensure_value() means that scripts using your action don't have to worry about setting a default value for the option destinations in question; they can just leave the default as None and ensure_value() will take care of getting it right when it's needed.

Other reasons to extend optparse

Adding new types and new actions are the big, obvious reasons why you might want to extend optparse. I can think of at least two other areas to play with.

First, the simple one: OptionParser tries to be helpful by calling sys.exit() when appropriate, i.e. when there's an error on the command line or when the user requests help. In the former case, the traditional course of letting the script crash with a traceback is unacceptable; it will make users think there's a bug in your script when they make a command-line error. In the latter case, there's generally not much point in carrying on after printing a help message.

If this behaviour bothers you, it shouldn't be too hard to "fix" it. You'll have to

- 1) subclass OptionParser and override error()
- 2) subclass Option and override take_action()—you'll need to provide your own handling of the help action that doesn't call sys.exit()

The second, much more complex, possibility is to override the command-line syntax implemented by optparse. In this case, you'd leave the whole machinery of option actions and types alone, but rewrite the code that processes <code>sys.argv</code>. You'll need to subclass OptionParser in any case; depending on how radical a rewrite you want, you'll probably need to override one or all of <code>parse_args()</code>, <code>_process_long_opt()</code>, and <code>_process_short_opts()</code>.

Both of these are left as an exercise for the reader. I have not tried to implement either myself, since I'm quite happy with optparse's default behaviour (naturally).

Happy hacking, and don't forget: Use the Source, Luke.

6.22 tempfile — Generate temporary files and directories

This module generates temporary files and directories. It works on all supported platforms.

In version 2.3 of Python, this module was overhauled for enhanced security. It now provides three new functions, NamedTemporaryFile(), mkstemp(), and mkdtemp(), which should eliminate all remaining need to use the insecure mktemp() function. Temporary file names created by this module no longer contain the process ID; instead a string of six random characters is used.

Also, all the user-callable functions now take additional arguments which allow direct control over the location and name of temporary files. It is no longer necessary to use the global *tempdir* and *template* variables. To maintain

backward compatibility, the argument order is somewhat odd; it is recommended to use keyword arguments for clarity.

The module defines the following user-callable functions:

TemporaryFile(
$$[mode='w+b'[, bufsize=-1[, suffix[, prefix[, dir]]]]])$$
)

Return a file (or file-like) object that can be used as a temporary storage area. The file is created using mkstemp. It will be destroyed as soon as it is closed (including an implicit close when the object is garbage collected). Under UNIX, the directory entry for the file is removed immediately after the file is created. Other platforms do not support this; your code should not rely on a temporary file created using this function having or not having a visible name in the file system.

The *mode* parameter defaults to 'w+b' so that the file created can be read and written without being closed. Binary mode is used so that it behaves consistently on all platforms without regard for the data that is stored. bufsize defaults to -1, meaning that the operating system default is used.

The dir, prefix and suffix parameters are passed to mkstemp().

NamedTemporaryFile(
$$[mode='w+b'[, bufsize=-1[, suffix[, prefix[, dir]]]])$$
)

This function operates exactly as TemporaryFile() does, except that the file is guaranteed to have a visible name in the file system (on UNIX, the directory entry is not unlinked). That name can be retrieved from the name member of the file object. Whether the name can be used to open the file a second time,

tempdir

When set to a value other than None, this variable defines the default value for the *dir* argument to all the functions defined in this module.

If tempdir is unset or None at any call to any of the above functions, Python searches a standard list of directories and sets *tempdir* to the first one which the calling user can create files in. The list is:

- 1. The directory named by the TMPDIR environment variable.
- 2. The directory named by the TEMP environment variable.
- 3. The directory named by the TMP environment variable.
- 4.A platform-specific location:
 - •On RiscOS, the directory named by the Wimp\$ScrapDir environment variable.
 - •On Windows, the directories 'C:\TEMP', 'C:\TMP', '\TEMP', and '\TMP', in that order.
 - •On all other platforms, the directories '/tmp', '/var/tmp', and '/usr/tmp', in that order.
- 5.As a last resort, the current working directory.

gettempdir()

Return the directory currently selected to create temporary files in. If tempdir is not None, this simply returns its contents; otherwise, the search described above is performed, and the result returned.

template

Deprecated since release 2.0. Use gettempprefix() instead.

When set to a value other than None, this variable defines the prefix of the final component of the filenames returned by mktemp(). A string of six random letters and digits is appended to the prefix to make the filename unique. On Windows, the default prefix is 'T'; on all other systems it is 'tmp'.

Older versions of this module used to require that template be set to None after a call to os.fork(); this has not been necessary since version 1.5.2.

gettempprefix()

Return the filename prefix used to create temporary files. This does not contain the directory component. Using this function is preferred over reading the *template* variable directly. New in version 1.5.2.

6.23 errno — Standard errno system symbols

This module makes available standard errno system symbols. The value of each symbol is the corresponding integer value. The names and descriptions are borrowed from 'linux/include/errno.h', which should be pretty all-inclusive.

errorcode

Dictionary providing a mapping from the errno value to the string name in the underlying system. For instance, errno.errorcode[errno.EPERM] maps to 'EPERM'.

To translate a numeric error code to an error message, use os.strerror().

Of the following list, symbols that are not used on the current platform are not defined by the module. The specific list of defined symbols is available as errno.errorcode.keys(). Symbols available can include:

EPERM

Operation not permitted

ENOENT

No such file or directory

ESRCH

No such process

EINTR

Interrupted system call

EIO

I/O error

ENXIO

No such device or address

E2BIG

Arg list too long

ENOEXEC

Exec format error

EBADF

Bad file number

ECHILD

No child processes

EAGAIN

Try again

ENOMEM

Out of memory

EACCES

Permission denied

EFAULT

Bad address

ENOTBLK

Block device required

EBUSY

Device or resource busy

EEXIST

File exists

EXDEV

Cross-device link

ENODEV

No such device

ENOTDIR

Not a directory

EISDIR

Is a directory

EINVAL

Invalid argument

ENFILE

File table overflow

EMFILE

Too many open files

ENOTTY

Not a typewriter

ETXTBSY

Text file busy

EFBIG

File too large

ENOSPC

No space left on device

ESPIPE

Illegal seek

EROFS

Read-only file system

EMLINK

Too many links

EPIPE

Broken pipe

EDOM

Math argument out of domain of func

ERANGE

Math result not representable

EDEADLK

Resource deadlock would occur

ENAMETOOLONG

File name too long

ENOLCK

No record locks available

ENOSYS

Function not implemented

ENOTEMPTY

Directory not empty

ELOOP

Too many symbolic links encountered

EWOULDBLOCK

Operation would block

ENOMSG

No message of desired type

EIDRM

Identifier removed

ECHRNG

Channel number out of range

EL2NSYNC

Level 2 not synchronized

EL3HLT

Level 3 halted

EL3RST

Level 3 reset

ELNRNG

Link number out of range

EUNATCH

Protocol driver not attached

ENOCSI

No CSI structure available

EL2HLT

Level 2 halted

EBADE

Invalid exchange

EBADR

Invalid request descriptor

EXFULL

Exchange full

ENOANO

No anode

EBADRQC

Invalid request code

EBADSLT

Invalid slot

EDEADLOCK

File locking deadlock error

EBFONT

Bad font file format

ENOSTR

Device not a stream

ENODATA

No data available

ETIME

Timer expired

ENOSR

Out of streams resources

ENONET

Machine is not on the network

ENOPKG

Package not installed

EREMOTE

Object is remote

ENOLINK

Link has been severed

EADV

Advertise error

ESRMNT

Srmount error

ECOMM

Communication error on send

EPROTO

Protocol error

EMULTIHOP

Multihop attempted

EDOTDOT

RFS specific error

EBADMSG

Not a data message

EOVERFLOW

Value too large for defined data type

ENOTUNIQ

Name not unique on network

EBADFD

File descriptor in bad state

EREMCHG

Remote address changed

ELIBACC

Can not access a needed shared library

ELIBBAD

Accessing a corrupted shared library

ELIBSCN

.lib section in a.out corrupted

ELIBMAX

Attempting to link in too many shared libraries

ELIBEXEC

Cannot exec a shared library directly

EILSEO

Illegal byte sequence

ERESTART

Interrupted system call should be restarted

ESTRPIPE

Streams pipe error

EUSERS

Too many users

ENOTSOCK

Socket operation on non-socket

EDESTADDRREQ

Destination address required

EMSGSIZE

Message too long

EPROTOTYPE

Protocol wrong type for socket

ENOPROTOOPT

Protocol not available

EPROTONOSUPPORT

Protocol not supported

ESOCKTNOSUPPORT

Socket type not supported

EOPNOTSUPP

Operation not supported on transport endpoint

EPFNOSUPPORT

Protocol family not supported

EAFNOSUPPORT

Address family not supported by protocol

EADDRINUSE

Address already in use

EADDRNOTAVAIL

Cannot assign requested address

ENETDOWN

Network is down

ENETUNREACH

Network is unreachable

ENETRESET

Network dropped connection because of reset

ECONNABORTED

Software caused connection abort

ECONNRESET

Connection reset by peer

ENOBUFS

No buffer space available

EISCONN

Transport endpoint is already connected

ENOTCONN

Transport endpoint is not connected

ESHUTDOWN

Cannot send after transport endpoint shutdown

ETOOMANYREFS

Too many references: cannot splice

ETIMEDOUT

Connection timed out

ECONNREFUSED

Connection refused

EHOSTDOWN

Host is down

EHOSTUNREACH

No route to host

EALREADY

Operation already in progress

EINPROGRESS

Operation now in progress

ESTALE

Stale NFS file handle

EUCLEAN

Structure needs cleaning

ENOTNAM

Not a XENIX named type file

ENAVAIL

No XENIX semaphores available

EISNAM

Is a named type file

EREMOTEIO

Remote I/O error

EDQUOT

Quota exceeded

6.24 glob — UNIX style pathname pattern expansion

The glob module finds all the pathnames matching a specified pattern according to the rules used by the UNIX shell. No tilde expansion is done, but *, ?, and character ranges expressed with [] will be correctly matched. This is done by using the os.listdir() and fnmatch.fnmatch() functions in concert, and not by actually invoking a subshell. (For tilde and shell variable expansion, use os.path.expanduser() and os.path.expandvars().)

glob(pathname)

Returns a possibly-empty list of path names that match *pathname*, which must be a string containing a path specification. *pathname* can be either absolute (like '/usr/src/Python-1.5/Makefile') or relative (like '../../Tools/*/*.gif'), and can contain shell-style wildcards. Broken symlinks are included in the results (as in the shell).

For example, consider a directory containing only the following files: '1.gif', '2.txt', and 'card.gif'. glob() will produce the following results. Notice how any leading components of the path are preserved.

```
>>> import glob
>>> glob.glob('./[0-9].*')
['./1.gif', './2.txt']
>>> glob.glob('*.gif')
['1.gif', 'card.gif']
>>> glob.glob('?.gif')
['1.gif']
```

See Also:

Module fnmatch (section 6.25):

Shell-style filename (not path) expansion

6.25 fnmatch — UNIX filename pattern matching

This module provides support for UNIX shell-style wildcards, which are *not* the same as regular expressions (which are documented in the re module). The special characters used in shell-style wildcards are:

Pattern	Meaning
*	matches everything
?	matches any single character
[<i>seq</i>]	matches any character in seq
[!seq]	matches any character not in <i>seq</i>

Note that the filename separator ('/' on UNIX) is *not* special to this module. See module glob for pathname expansion (glob uses fnmatch() to match pathname segments). Similarly, filenames starting with a period are not special for this module, and are matched by the * and ? patterns.

fnmatch(filename, pattern)

Test whether the *filename* string matches the *pattern* string, returning true or false. If the operating system is case-insensitive, then both parameters will be normalized to all lower- or upper-case before the comparison is performed. If you require a case-sensitive comparison regardless of whether that's standard for your operating system, use fnmatchcase() instead.

fnmatchcase(filename, pattern)

Test whether *filename* matches *pattern*, returning true or false; the comparison is case-sensitive.

filter(names, pattern)

Return the subset of the list of *names* that match *pattern*. It is the same as [n for n in names if fnmatch(n, pattern)], but implemented more efficiently. New in version 2.2.

See Also:

Module glob (section 6.24):

UNIX shell-style path expansion.

6.26 shutil — High-level file operations

The shutil module offers a number of high-level operations on files and collections of files. In particular, functions are provided which support file copying and removal.

Caveat: On MacOS, the resource fork and other metadata are not used. For file copies, this means that resources will be lost and file type and creator codes will not be correct.

copyfile(src, dst)

Copy the contents of the file named *src* to a file named *dst*. The destination location must be writable; otherwise, an IOError exception will be raised. If *dst* already) exists, it will be said be writable with the writable of the raised. If *dst* already) exists, it will be writable with the wr

New in version 2.3.

exception Error

This exception collects exceptions that raised during a mult-file operation. For copytree, the exception argument is a list of 3-tuples (*srcname*, *dstname*, *exception*).

New in version 2.3.

6.26.1 Example

This example is the implementation of the copytree() function, described above, with the docstring omitted. It demonstrates many of the other functions provided by this module.

```
def copytree(src, dst, symlinks=0):
    names = os.listdir(src)
    os.mkdir(dst)
    for name in names:
        srcname = os.path.join(src, name)
        dstname = os.path.join(dst, name)
        try:
            if symlinks and os.path.islink(srcname):
                linkto = os.readlink(srcname)
                os.symlink(linkto, dstname)
            elif os.path.isdir(srcname):
                copytree(srcname, dstname, symlinks)
            else:
                copy2(srcname, dstname)
        except (IOError, os.error), why:
            print "Can't copy %s to %s: %s" % ('srcname', 'dstname', str(why))
```

6.27 locale — Internationalization services

The locale module opens access to the POSIX locale database and functionality. The POSIX locale mechanism allows programmers to deal with certain cultural issues in an application, without requiring the programmer to know all the specifics of each country where the software is executed.

The locale module is implemented on top of the _locale module, which in turn uses an ANSI C locale implementation if available.

The locale module defines the following exception and functions:

exception Error

Exception raised when setlocale() fails.

```
setlocale(category[, locale])
```

If *locale* is specified, it may be a string, a tuple of the form (*language code*, *encoding*), or None. If it is a tuple, it is converted to a string using the locale aliasing engine. If *locale* is given and not None, setlocale() modifies the locale setting for the *category*. The available categories are listed in the data description below. The value is the name of a locale. An empty string specifies the user's default settings. If the modification of the locale fails, the exception Error is raised. If successful, the new locale setting is returned.

If *locale* is omitted or None, the current setting for *category* is returned.

setlocale() is not thread safe on most systems. Applications typically start with a call of

```
import locale
locale.setlocale(locale.LC_ALL, '')
```

This sets the locale for all categories to the user's default setting (typically specified in the LANG environment variable). If the locale is not changed thereafter, using multithreading should not cause problems.

Changed in version 2.0: Added support for tuple values of the *locale* parameter.

localeconv()

Returns the database of the local conventions as a dictionary. This dictionary has the following strings as keys:

Key	Category	Meaning
LC_NUMERIC	'decimal_point'	Decimal point character.
	'grouping'	Sequence of numbers specifying which relative posi-
		tions the 'thousands_sep' is expected. If the
		sequence is terminated with CHAR_MAX, no further
		grouping is performed. If the sequence terminates with
		a 0, the last group size is repeatedly used.
	'thousands_sep'	Character used between groups.
LC_MONETARY	'int_curr_symbol'	International currency symbol.
	'currency_symbol'	Local currency symbol.
	'mon_decimal_point'	Decimal point used for monetary values.
	'mon_thousands_sep'	Group separator used for monetary values.
	'mon_grouping'	Equivalent to 'grouping', used for monetary val-
		ues.
	'positive_sign'	Symbol used to annotate a positive monetary value.
	'negative_sign'	Symbol used to annotate a negative monetary value.
	'frac_digits'	Number of fractional digits used in local formatting of
		monetary values.
	'int_frac_digits'	Number of fractional digits used in international for-
		matting of monetary values.

The possible values for 'p_sign_posn' and 'n_sign_posn' are given below.

Value	Explanation
0	Currency and value are surrounded by parentheses.
1	The sign should precede the value and currency symbol.
2	The sign should follow the value and currency symbol.
3	The sign should immediately precede the value.
4	The sign should immediately follow the value.
LC_MAX	Nothing is specified in this locale.

nl_langinfo(option)

Return some locale-specific information as a string. This function is not available on all systems, and the set of possible options might also vary across platforms. The possible argument values are numbers, for which symbolic constants are available in the locale module.

getdefaultlocale([envvars])

Tries to determine the default locale settings and returns them as a tuple of the form (*language code*, *encoding*).

According to POSIX, a program which has not called setlocale(LC_ALL, '') runs using the portable 'C' locale. Calling setlocale(LC_ALL, '') lets it use the default locale as defined by the LANG variable. Since we do not want to interfere with the current locale setting we thus emulate the behavior in the way described above.

To maintain compatibility with other platforms, not only the LANG variable is tested, but a list of variables given as envvars parameter. The first found to be defined will be used. *envvars* defaults to the search path used in GNU gettext; it must always contain the variable name 'LANG'. The GNU gettext search path contains 'LANGUAGE', 'LC_ALL', 'LC_CTYPE', and 'LANG', in that order.

Except for the code 'C', the language code corresponds to RFC 1766. *language code* and *encoding* may be None if their values cannot be determined. New in version 2.0.

getlocale([category])

Returns the current setting for the given locale category as sequence containing *language code*, *encoding. category* may be one of the LC_* values except LC_ALL. It defaults to LC_CTYPE.

Except for the code 'C', the language code corresponds to RFC 1766. *language code* and *encoding* may be None if their values cannot be determined. New in version 2.0.

getpreferredencoding([do_setlocale])

Return the encoding used for text data, according to user preferences. User preferences are expressed differently on different systems, and might not be available programmatically on some systems, so this function only returns a guess.

On some systems, it is necessary to invoke setlocale to obtain the user preferences, so this function is not thread-safe. If invoking setlocale is not necessary or desired, *do_setlocale* should be set to False.

New in version 2.3.

normalize(localename)

Returns a normalized locale code for the given locale name. The returned locale code is formatted for use with setlocale(). If normalization fails, the original name is returned unchanged.

If the given encoding is not known, the function defaults to the default encoding for the locale code just like setlocale(). New in version 2.0.

resetlocale([category])

Sets the locale for *category* to the default setting.

The default setting is determined by calling getdefaultlocale(). category defaults to LC_ALL. New in version 2.0.

strcoll(string1, string2)

Compares two strings according to the current LC_COLLATE setting. As any other compare function, returns a negative, or a positive value, or 0, depending on whether *string1* collates before or after *string2* or is equal to it.

strxfrm(string)

Transforms a string to one that can be used for the built-in function cmp(), and still returns locale-aware results. This function can be used when the same string is compared repeatedly, e.g. when collating a sequence of strings.

format (format, val[, grouping])

Formats a number *val* according to the current LC_NUMERIC setting. The format follows the conventions of the % operator. For floating point values, the decimal point is modified if appropriate. If *grouping* is true, also takes the grouping into account.

str(float)

Formats a floating point number using the same format as the built-in function str(float), but takes the decimal point into account.

atof(string)

Converts a string to a floating point number, following the LC_NUMERIC settings.

atoi(string)

Converts a string to an integer, following the LC_NUMERIC conventions.

LC_CTYPE

Locale category for the character type functions. Depending on the settings of this category, the functions of module string dealing with case change their behaviour.

LC_COLLATE

Locale category for sorting strings. The functions strcoll() and strxfrm() of the locale module are affected.

LC_TIME

 $Locale\ category\ for\ the\ formatting\ of\ time.\ The\ function\ \verb|time.strftime|()| follows\ these\ conventions.$

LC_MONETARY

Locale category for formatting of monetary values. The available options are available from the localeconv() function.

LC_MESSAGES

Locale category for message display. Python currently does not support application specific locale-aware

messages. Messages displayed by the operating system, like those returned by os.strerror() might be affected by this category.

LC_NUMERIC

Locale category for formatting numbers. The functions format(), atoi(), atof() and str() of the locale module are affected by that category. All other numeric formatting operations are not affected.

LC_ALL

Combination of all locale settings. If this flag is used when the locale is changed, setting the locale for all categories is attempted. If that fails for any category, no category is changed at all. When the locale is retrieved using this flag, a string indicating the setting for all categories is returned. This string can be later used to restore the settings.

CHAR_MAX

This is a symbolic constant used for different values returned by localeconv().

The nl_langinfo function accepts one of the following keys. Most descriptions are taken from the corresponding description in the GNU C library.

CODESET

Return a string with the name of the character encoding used in the selected locale.

т тит

Return a string that can be used as a format string for strftime(3) to represent time and date in a locale-specific way.

$D_{-}FMT$

Return a string that can be used as a format string for strftime(3) to represent a date in a locale-specific way.

T_FMT

Return a string that can be used as a format string for strftime(3) to represent a time in a locale-specific way.

T_FMT_AMPM

The return value can be used as a format string for 'strftime' to represent time in the am/pm format.

DAY_1 ... DAY_7

Return name of the n-th day of the week. **Warning:** This follows the US convention of DAY_1 being Sunday, not the international convention (ISO 8601) that Monday is the first day of the week.

ABDAY_1 ... ABDAY_7

Return abbreviated name of the n-th day of the week.

MON_1 ... MON_12

Return name of the n-th month.

ABMON_1 ... ABMON_12

Return abbreviated name of the n-th month.

RADIXCHAR

Return radix character (decimal dot, decimal comma, etc.)

THOUSEP

Return separator character for thousands (groups of three digits).

YESEXPR

Return a regular expression that can be used with the regex function to recognize a positive response to a yes/no question. **Warning:** The expression is in the syntax suitable for the regex() function from the C library, which might differ from the syntax used in re.

NOEXPR

Return a regular expression that can be used with the regex(3) function to recognize a negative response to a yes/no question.

CRNCYSTR

Return the currency symbol, preceded by "-" if the symbol should appear before the value, "+" if the symbol should appear after the value, or "." if the symbol should replace the radix character.

ERA

The return value represents the era used in the current locale.

Most locales do not define this value. An example of a locale which does define this value is the Japanese one. In Japan, the traditional representation of dates includes the name of the era corresponding to the then-emperor's reign.

Normally it should not be necessary to use this value directly. Specifying the E modifier in their format strings causes the strftime function to use this information. The format of the returned string is not specified, and therefore you should not assume knowledge of it on different systems.

ERA_YEAR

The return value gives the year in the relevant era of the locale.

ERA D T FMT

This return value can be used as a format string for strftime to represent dates and times in a locale-specific era-based way.

ERA D FMT

This return value can be used as a format string for strftime to represent time in a locale-specific erabased way.

ALT_DIGITS

The return value is a representation of up to 100 values used to represent the values 0 to 99.

Example:

```
>>> import locale
>>> loc = locale.getlocale(locale.LC_ALL) # get current locale
>>> locale.setlocale(locale.LC_ALL, 'de_DE') # use German locale; name might vary with platf
>>> locale.strcoll('f\xe4n', 'foo') # compare a string containing an umlaut
>>> locale.setlocale(locale.LC_ALL, '') # use user's preferred locale
>>> locale.setlocale(locale.LC_ALL, 'C') # use default (C) locale
>>> locale.setlocale(locale.LC_ALL, loc) # restore saved locale
```

6.27.1 Background, details, hints, tips and caveats

The C standard defines the locale as a program-wide property that may be relatively expensive to change. On top of that, some implementation are broken in such a way that frequent locale changes may cause core dumps. This makes the locale somewhat painful to use correctly.

Initially, when a program is started, the locale is the 'C' locale, no matter what the user's preferred locale is. The program must explicitly say that it wants the user's preferred locale settings by calling setlocale(LC_ALL, '')

It is generally a bad idea to call setlocale() in some library routine, since as a side effect it affects the entire program. Saving and restoring it is almost as bad: it is expensive and affects other threads that happen to run before the settings have been restored.

If, when coding a module for general use, you need a locale independent version of an operation that is affected by the locale (such as string.lower(), or certain formats used with time.strftime()), you will have to find a way to do it without using the standard library routine. Even better is convincing yourself that using locale settings is okay. Only as a last resort should you document that your module is not compatible with non-'C' locale settings.

The case conversion functions in the string module are affected by the locale settings. When a call to the setlocale() function changes the LC_CTYPE settings, the variables string.lowercase, string.uppercase and string.letters are recalculated. Note that this code that uses these variable through 'from ... import ...', e.g. from string import letters, is not affected by subsequent setlocale() calls.

The only way to perform numeric operations according to the locale is to use the special functions defined by this module: atof(), atoi(), format(), str().

6.27.2 For extension writers and programs that embed Python

Extension modules should never call setlocale(), except to find out what the current locale is. But since the return value can only be used portably to restore it, that is not very useful (except perhaps to find out whether or not the locale is 'C').

When Python code uses the locale module to change the locale, this also affects the embedding application. If the embedding application doesn't want this to happen, it should remove the _locale extension module (which does all the work) from the table of built-in modules in the 'config.c' file, and make sure that the _locale module is not accessible as a shared library.

6.27.3 Access to message catalogs

The locale module exposes the C library's gettext interface on systems that provide this interface. It consists of the functions gettext(), dgettext(), dcgettext(), textdomain(), bindtextdomain(), and bind_textdomain_codeset(). These are similar to the same functions in the gettext module, but use the C library's binary format for message catalogs, and the C library's search algorithms for locating message catalogs.

Python applications should normally find no need to invoke these functions, and should use gettext instead. A known exception to this rule are applications that link use additional C libraries which internally invoke gettext() or dcgettext(). For these applications, it may be necessary to bind the text domain, so that the libraries can properly locate their message catalogs.

6.28 gettext — Multilingual internationalization services

The gettext module provides internationalization (I18N) and localization (L10N) services for your Python modules and applications. It supports both the GNU gettext message catalog API and a higher level, class-based API that may be more appropriate for Python files. The interface described below allows you to write your module and application messages in one natural language, and provide a catalog of translated messages for running under different natural languages.

Some hints on localizing your Python modules and applications are also given.

6.28.1 GNU gettext API

The gettext module defines the following API, which is very similar to the GNU **gettext** API. If you use this API you will affect the translation of your entire application globally. Often this is what you want if your application is monolingual, with the choice of language dependent on the locale of your user. If you are localizing a Python module, or if your application needs to switch languages on the fly, you probably want to use the class-based API instead.

bindtextdomain(domain[, localedir])

Bind the *domain* to the locale directory *localedir*. More concretely, gettext will look for binary '.mo' files for the given domain using the path (on UNIX): '*localedir/language/*LC_MESSAGES/*domain*.mo', where *languages* is searched for in the environment variables LANGUAGE, LC_ALL, LC_MESSAGES, and LANG respectively.

If *localedir* is omitted or None, then the current binding for *domain* is returned.²

bind_textdomain_codeset(domain, codeset)

Bind the *domain* to *codeset*, changing the encoding of strings returned by the gettext() family of functions. If *codeset* is omitted, then the current binding is returned.

New in version 2.4.

²The default locale directory is system dependent; for example, on RedHat Linux it is '/usr/share/locale', but on Solaris it is '/usr/lib/locale'. The gettext module does not try to support these system dependent defaults; instead its default is 'sys.prefix/share/locale'. For this reason, it is always best to call bindtextdomain() with an explicit absolute path at the start of your application.

textdomain([domain])

Change or query the current global domain. If *domain* is None, then the current global domain is returned, otherwise the global domain is set to *domain*, which is returned.

gettext(message)

Return the localized translation of message, based on the current global domain, language, and locale directory. This function is usually aliased as $_$ in the local namespace (see examples below).

lgettext(message)

Equivalent to gettext(), but the translation is returned in the preferred system encoding, if no other encoding was explicitly set with bind_textdomain_codeset().

New in version 2.4.

dgettext(domain, message)

Like gettext(), but look the message up in the specified domain.

ldgettext(domain, message)

Equivalent to dgettext(), but the translation is returned in the preferred system encoding, if no other encoding was explicitly set with bind_textdomain_codeset().

New in version 2.4.

ngettext(singular, plural, n)

Like gettext(), but consider plural forms. If a translation is found, apply the plural formula to n, and return the resulting message (some languages have more than two plural forms). If no translation is found, return singular if n is 1; return plural otherwise.

The Plural formula is taken from the catalog header. It is a C or Python expression that has a free variable n; the expression evaluates to the index of the plural in the catalog. See the GNU gettext documentation for the precise syntax to be used in .po files, and the formulas for a variety of languages.

New in version 2.3.

lngettext(singular, plural, n)

Equivalent to ngettext(), but the translation is returned in the preferred system encoding, if no other encoding was explicitly set with bind_textdomain_codeset().

New in version 2.4.

dngettext(domain, singular, plural, n)

Like ngettext(), but look the message up in the specified domain.

New in version 2.3.

ldngettext(domain, singular, plural, n)

Equivalent to dngettext(), but the translation is returned in the preferred system encoding, if no other encoding was explicitly set with bind_textdomain_codeset().

New in version 2.4.

Note that GNU **gettext** also defines a dcgettext() method, but this was deemed not useful and so it is currently unimplemented.

Here's an example of typical usage for this API:

```
import gettext
gettext.bindtextdomain('myapplication', '/path/to/my/language/directory')
gettext.textdomain('myapplication')
_ = gettext.gettext
# ...
print _('This is a translatable string.')
```

6.28.2 Class-based API

The class-based API of the <code>gettext</code> module gives you more flexibility and greater convenience than the GNU <code>gettext</code> API. It is the recommended way of localizing your Python applications and modules. <code>gettext</code> defines a "translations" class which implements the parsing of GNU '.mo' format files, and has methods for returning either standard 8-bit strings or Unicode strings. Instances of this "translations" class can also install themselves in the built-in namespace as the function $_()$.

find(domain[, localedir[, languages[, all]]])

This function implements the standard '.mo' file search algorithm. It takes a *domain*, identical to what textdomain() takes. Optional *localedir* is as in bindtextdomain() Optional *languages* is a list of strings, where each string is a language code.

If *localedir* is not given, then the default system locale directory is used.³ If *languages* is not given, then the following environment variables are searched: LANGUAGE, LC_ALL, LC_MESSAGES, and LANG. The first one returning a non-empty value is used for the *languages* variable. The environment variables should contain a colon separated list of languages, which will be split on the colon to produce the expected list of language code strings.

find() then expands and normalizes the languages, and then iterates through them, searching for an existing file built of these components:

'localedir/language/LC_MESSAGES/domain.mo'

The first such file name that exists is returned by find(). If no such file is found, then None is returned. If *all* is given, it returns a list of all file names, in the order in which they appear in the languages list or the environment variables.

translation(domain[, localedir[, languages[, class_[, fallback[, codeset]]]]]))

Return a Translations instance based on the *domain*, *localedir*, and *languages*, which are first passed to find() to get a list of the associated '.mo' file paths. Instances with identical '.mo' file names are cached. The actual class instantiated is either *class*_ if provided, otherwise GNUTranslations. The class's constructor must take a single file object argument. If provided, *codeset* will change the charset used to encode translated strings.

If multiple files are found, later files are used as fallbacks for earlier ones. To allow setting the fallback, copy.copy is used to clone each translation object from the cache; the actual instance data is still shared with the cache.

If no '.mo' file is found, this function raises IOError if *fallback* is false (which is the default), and returns a NullTranslations instance if *fallback* is true.

Changed in version 2.4: Added the *codeset* parameter.

install(domain[, localedir[, unicode [, codeset]]])

This installs the function $_$ in Python's builtin namespace, based on *domain*, *localedir*, and *codeset* which are passed to the function translation(). The *unicode* flag is passed to the resulting translation object's install method.

As seen below, you usually mark the strings in your application that are candidates for translation, by wrapping them in a call to the $_{-}($) function, like this:

```
print _('This string will be translated.')
```

For convenience, you want the $_()$ function to be installed in Python's builtin namespace, so it is easily accessible in all modules of your application.

Changed in version 2.4: Added the *codeset* parameter.

The NullTranslations class

Translation classes are what actually implement the translation of original source file message strings to translated message strings. The base class used by all translation classes is NullTranslations; this provides

 $^{^3{}m See}$ the footnote for bindtextdomain() above.

the basic interface you can use to write your own specialized translation classes. Here are the methods of NullTranslations:

$_$ _init $_$ ([fp])

Takes an optional file object fp, which is ignored by the base class. Initializes "protected" instance variables $_info$ and $_charset$ which are set by derived classes, as well as $_fallback$, which is set through add_fallback. It then calls $self._parse(fp)$ if fp is not None.

_parse(fp)

No-op'd in the base class, this method takes file object fp, and reads the data from the file, initializing its message catalog. If you have an unsupported message catalog file format, you should override this method to parse your format.

add_fallback(fallback)

Add *fallback* as the fallback object for the current translation object. A translation object should consult the fallback if it cannot provide a translation for a given message.

gettext(message)

If a fallback has been set, forward gettext() to the fallback. Otherwise, return the translated message. Overridden in derived classes.

lgettext(message)

If a fallback has been set, forward lgettext() to the fallback. Otherwise, return the translated message. Overridden in derived classes.

New in version 2.4.

ugettext(message)

If a fallback has been set, forward ugettext() to the fallback. Otherwise, return the translated message as a Unicode string. Overridden in derived classes.

ngettext(singular, plural, n)

If a fallback has been set, forward ngettext() to the fallback. Otherwise, return the translated message. Overridden in derived classes.

New in version 2.3.

lngettext(singular, plural, n)

If a fallback has been set, forward ngettext() to the fallback. Otherwise, return the translated message. Overridden in derived classes.

New in version 2.4.

ungettext(singular, plural, n)

If a fallback has been set, forward ungettext () to the fallback. Otherwise, return the translated message as a Unicode string. Overridden in derived classes.

New in version 2.3.

info()

Return the "protected" _info variable.

charset()

Return the "protected" _charset variable.

output_charset()

Return the "protected" $_$ output $_$ charset variable, which defines the encoding used to return translated messages.

New in version 2.4.

set_output_charset(charset)

Change the "protected" _output_charset variable, which defines the encoding used to return translated messages.

New in version 2.4.

install([unicode])

If the *unicode* flag is false, this method installs self.gettext() into the built-in namespace, binding it to '_'. If *unicode* is true, it binds self.ugettext() instead. By default, *unicode* is false.

Note that this is only one way, albeit the most convenient way, to make the $_$ function available to your application. Because it affects the entire application globally, and specifically the built-in namespace, localized modules should never install $_$. Instead, they should use this code to make $_$ available to their module:

```
import gettext
t = gettext.translation('mymodule', ...)
_ = t.gettext
```

This puts _ only in the module's global namespace and so only affects calls within this module.

The GNUTranslations class

The gettext module provides one additional class derived from NullTranslations: GNUTranslations. This class overrides _parse() to enable reading GNU gettext format '.mo' files in both big-endian and little-endian format. It also coerces both message ids and message strings to Unicode.

GNUTranslations parses optional meta-data out of the translation catalog. It is convention with GNU gettext to include meta-data as the translation for the empty string. This meta-data is in RFC 822-style key: value pairs, and should contain the Project-Id-Version key. If the key Content-Type is found, then the charset property is used to initialize the "protected" _charset instance variable, defaulting to None if not found. If the charset encoding is specified, then all message ids and message strings read from the catalog are converted to Unicode using this encoding. The ugettext() method always returns a Unicode, while the gettext() returns an encoded 8-bit string. For the message id arguments of both methods, either Unicode strings or 8-bit strings containing only US-ASCII characters are acceptable. Note that the Unicode version of the methods (i.e. ugettext() and ungettext()) are the recommended interface to use for internationalized Python programs.

The entire set of key/value pairs are placed into a dictionary and set as the "protected" _info instance variable.

If the '.mo' file's magic number is invalid, or if other problems occur while reading the file, instantiating a GNUTranslations class can raise IOError.

The following methods are overridden from the base class implementation:

gettext(message)

Look up the *message* id in the catalog and return the corresponding message string, as an 8-bit string encoded with the catalog's charset encoding, if known. If there is no entry in the catalog for the *message* id, and a fallback has been set, the look up is forwarded to the fallback's gettext() method. Otherwise, the *message* id is returned.

lgettext(message)

Equivalent to gettext(), but the translation is returned in the preferred system encoding, if no other encoding was explicitly set with set_output_charset().

New in version 2.4.

ugettext(message)

Look up the *message* id in the catalog and return the corresponding message string, as a Unicode string. If there is no entry in the catalog for the *message* id, and a fallback has been set, the look up is forwarded to the fallback's ugettext() method. Otherwise, the *message* id is returned.

ngettext(singular, plural, n)

Do a plural-forms lookup of a message id. *singular* is used as the message id for purposes of lookup in the catalog, while *n* is used to determine which plural form to use. The returned message string is an 8-bit string encoded with the catalog's charset encoding, if known.

If the message id is not found in the catalog, and a fallback is specified, the request is forwarded to the fallback's ngettext() method. Otherwise, when n is 1 *singular* is returned, and *plural* is returned in all other cases.

New in version 2.3.

lngettext(singular, plural, n)

Equivalent to gettext(), but the translation is returned in the preferred system encoding, if no other encoding was explicitly set with set_output_charset().

New in version 2.4.

```
ungettext(singular, plural, n)
```

Do a plural-forms lookup of a message id. singular is used as the message id for purposes of lookup in the catalog, while n is used to determine which plural form to use. The returned message string is a Unicode string.

If the message id is not found in the catalog, and a fallback is specified, the request is forwarded to the fallback's ungettext() method. Otherwise, when n is 1 singular is returned, and plural is returned in all other cases.

Here is an example:

```
n = len(os.listdir('.'))
cat = GNUTranslations(somefile)
message = cat.ungettext(
    'There is %(num)d file in this directory',
    'There are %(num)d files in this directory',
    n) % {'num': n}
```

New in version 2.3.

Solaris message catalog support

The Solaris operating system defines its own binary '.mo' file format, but since no documentation can be found on this format, it is not supported at this time.

The Catalog constructor

GNOME uses a version of the gettext module by James Henstridge, but this version has a slightly different API. Its documented usage was:

```
import gettext
cat = gettext.Catalog(domain, localedir)
_ = cat.gettext
print _('hello world')
```

For compatibility with this older module, the function Catalog() is an alias for the translation() function described above.

One difference between this module and Henstridge's: his catalog objects supported access through a mapping API, but this appears to be unused and so is not currently supported.

6.28.3 Internationalizing your programs and modules

Internationalization (I18N) refers to the operation by which a program is made aware of multiple languages. Localization (L10N) refers to the adaptation of your program, once internationalized, to the local language and cultural habits. In order to provide multilingual messages for your Python programs, you need to take the following steps:

- 1. prepare your program or module by specially marking translatable strings
- 2. run a suite of tools over your marked files to generate raw messages catalogs
- 3. create language specific translations of the message catalogs

4. use the gettext module so that message strings are properly translated

In order to prepare your code for I18N, you need to look at all the strings in your files. Any string that needs to be translated should be marked by wrapping it in (' . . . ') — that is, a call to the function (). For example:

```
filename = 'mylog.txt'
message = _('writing a log message')
fp = open(filename, 'w')
fp.write(message)
fp.close()
```

In this example, the string 'writing a log message' is marked as a candidate for translation, while the strings 'mylog.txt' and 'w' are not.

The Python distribution comes with two tools which help you generate the message catalogs once you've prepared your source code. These may or may not be available from a binary distribution, but they can be found in a source distribution, in the 'Tools/i18n' directory.

The **pygettext**⁴ program scans all your Python source code looking for the strings you previously marked as translatable. It is similar to the GNU **gettext** program except that it understands all the intricacies of Python source code, but knows nothing about C or C++source code. You don't need GNU gettext unless you're also going to be translating C code (such as C extension modules).

pygettext generates textual Uniforum-style human readable message catalog '.pot' files, essentially structured human readable files which contain every marked string in the source code, along with a placeholder for the translation strings. **pygettext** is a command line script that supports a similar command line interface as **xgettext**; for details on its use, run:

```
pygettext.py --help
```

Copies of these '.pot' files are then handed over to the individual human translators who write language-specific versions for every supported natural language. They send you back the filled in language-specific versions as a '.po' file. Using the **msgfmt.py**⁵ program (in the 'Tools/i18n' directory), you take the '.po' files from your translators and generate the machine-readable '.mo' binary catalog files. The '.mo' files are what the gettext module uses for the actual translation processing during run-time.

How you use the gettext module in your code depends on whether you are internationalizing your entire application or a single module.

Localizing your module

If you are localizing your module, you must take care not to make global changes, e.g. to the built-in namespace. You should not use the GNU gettext API but instead the class-based API.

Let's say your module is called "spam" and the module's various natural language translation '.mo' files reside in '/usr/share/locale' in GNU **gettext** format. Here's what you would put at the top of your module:

```
import gettext
t = gettext.translation('spam', '/usr/share/locale')
_ = t.lgettext
```

If your translators were providing you with Unicode strings in their '.po' files, you'd instead do:

⁴François Pinard has written a program called **xpot** which does a similar job. It is available as part of his **po-utils** package at http://www.iro.umontreal.ca/contrib/po-utils/HTML/.

⁵msgfmt.py is binary compatible with GNU msgfmt except that it provides a simpler, all-Python implementation. With this and pyget-text.py, you generally won't need to install the GNU gettext package to internationalize your Python applications.

```
import gettext
t = gettext.translation('spam', '/usr/share/locale')
_ = t.ugettext
```

Localizing your application

If you are localizing your application, you can install the $_()$ function globally into the built-in namespace, usually in the main driver file of your application. This will let all your application-specific files just use $_(')$ without having to explicitly install it in each file.

In the simple case then, you need only add the following bit of code to the main driver file of your application:

```
import gettext
gettext.install('myapplication')
```

If you need to set the locale directory or the *unicode* flag, you can pass these into the install() function:

```
import gettext
gettext.install('myapplication', '/usr/share/locale', unicode=1)
```

Changing languages on the fly

If your program needs to support many languages at the same time, you may want to create multiple translation instances and then switch between them explicitly, like so:

```
import gettext
lang1 = gettext.translation('myapplication', languages=['en'])
lang2 = gettext.translation('myapplication', languages=['fr'])
lang3 = gettext.translation('myapplication', languages=['de'])

# start by using language1
lang1.install()

# ... time goes by, user selects language 2
lang2.install()

# ... more time goes by, user selects language 3
lang3.install()
```

Deferred translations

In most coding situations, strings are translated where they are coded. Occasionally however, you need to mark strings for translation, but defer actual translation until later. A classic example is:

Here, you want to mark the strings in the animals list as being translatable, but you don't actually want to translate them until they are printed.

Here is one way you can handle this situation:

This works because the dummy definition of $_()$ simply returns the string unchanged. And this dummy definition will temporarily override any definition of $_()$ in the built-in namespace (until the del command). Take care, though if you have a previous definition of $_()$ in the local namespace.

Note that the second use of $_()$ will not identify "a" as being translatable to the **pygettext** program, since it is not a string.

Another way to handle this is with the following example:

In this case, you are marking translatable strings with the function $N_{-}()$, which won't conflict with any definition of $_{-}()$. However, you will need to teach your message extraction program to look for translatable strings marked with $N_{-}()$. **pygettext** and **xpot** both support this through the use of command line switches.

⁶The choice of N_() here is totally arbitrary; it could have just as easily been MarkThisStringForTranslation().

```
gettext() VS. lgettext()
```

In Python 2.4 the lgettext() family of functions were introduced. The intention of these functions is to provide an alternative which is more compliant with the current implementation of GNU gettext. Unlike gettext(), which returns strings encoded with the same codeset used in the translation file, lgettext() will return strings encoded with the preferred system encoding, as returned by locale.getpreferredencoding(). Also notice that Python 2.4 introduces new functions to explicitly choose the codeset used in translated strings. If a codeset is explicitly set, even lgettext() will return translated strings in the requested codeset, as would be expected in the GNU gettext implementation.

6.28.4 Acknowledgements

The following people contributed code, feedback, design suggestions, previous implementations, and valuable experience to the creation of this module:

- Peter Funk
- James Henstridge
- Juan David Ibáñez Palomar
- Marc-André Lemburg
- Martin von Löwis
- François Pinard
- Barry Warsaw
- Gustavo Niemeyer

6.29 logging — Logging facility for Python

New in version 2.3. This module defines functions and classes which implement a flexible error logging system for applications.

Logging is performed by calling methods on instances of the Logger class (hereafter called *loggers*). Each instance has a name, and they are conceptually arranged in a name space hierarchy using dots (periods) as separators. For example, a logger named "scan" is the parent of loggers "scan.text", "scan.html" and "scan.pdf". Logger names can be anything you want, and indicate the area of an application in which a logged message originates.

Logged messages also have levels of importance associated with them. The default levels provided are DEBUG, INFO, WARNING, ERROR and CRITICAL. As a convenience, you indicate the importance of a logged message by calling an appropriate method of Logger. The methods are debug(), info(), warning(), error() and critical(), which mirror the default levels. You are not constrained to use these levels: you can specify your own and use a more general Logger method, log(), which takes an explicit level argument.

The numeric values of logging levels are given in the following table. These are primarily of interest if you want to define your own levels, and need them to have specific values relative to the predefined levels. If you define a level with the same numeric value, it overwrites the predefined value; the predefined name is lost.

Numeric value
50
40
30
20
10
0

Levels can also be associated with loggers, being set either by the developer or through loading a saved logging configuration. When a logging method is called on a logger, the logger compares its own level with the level associated with the method call. If the logger's level is higher than the method call's, no logging message is actually generated. This is the basic mechanism controlling the verbosity of logging output.

Logging messages are encoded as instances of the LogRecord class. When a logger decides to actually log an event, an LogRecord instance is created from the logging message.

Logging messages are subjected to a dispatch mechanism through the use of handlers, which are instances of subclasses of the Handler class. Handlers are responsible for ensuring that a logged message (in the form of a LogRecord) ends up in a particular location (or set of locations) which is useful for the target audience for that message (such as end users, support desk staff, system administrators, developers). Handlers are passed LogRecord instances intended for particular destinations. Each logger can have zero, one or more handlers associated with it (via the addHandler() method of Logger). In addition to any handlers directly associated with a logger, all handlers associated with all ancestors of the logger are called to dispatch the message.

Just as for loggers, handlers can have levels associated with them. A handler's level acts as a filter in the same way as a logger's level does. If a handler decides to actually dispatch an event, the <code>emit()</code> method is used to send the message to its destination. Most user-defined subclasses of <code>Handler</code> will need to override this <code>emit()</code>.

In addition to the base Handler class, many useful subclasses are provided:

- 1. StreamHandler instances send error messages to streams (file-like objects).
- 2. FileHandler instances send error messages to disk files.
- 3. BaseRotatingHandler is the base class for handlers that rotate log files at a certain point. It is not meant to be instantiated directly. Instead, use RotatingFileHandler or TimedRotatingFileHandler.
- 4. RotatingFileHandler instances send error messages to disk files, with support for maximum log file sizes and log file rotation.
- 5. TimedRotatingFileHandler instances send error messages to disk files rotating the log file at certain timed intervals.
- 6. SocketHandler instances send error messages to TCP/IP sockets.
- 7. DatagramHandler instances send error messages to UDP sockets.
- 8. SMTPHandler instances send error messages to a designated email address.
- 9. SysLogHandler instances send error messages to a UNIX syslog daemon, possibly on a remote machine.
- 10. NTEventLogHandler instances send error messages to a Windows NT/2000/XP event log.
- 11. MemoryHandler instances send error messages to a buffer in memory, which is flushed whenever specific criteria are met.
- 12. HTTPHandler instances send error messages to an HTTP server using either 'GET' or 'POST' semantics.

The StreamHandler and FileHandler classes are defined in the core logging package. The other handlers are defined in a sub- module, logging.handlers. (There is also another sub-module, logging.config, for configuration functionality.)

Logged messages are formatted for presentation through instances of the Formatter class. They are initialized with a format string suitable for use with the % operator and a dictionary.

For formatting multiple messages in a batch, instances of BufferingFormatter can be used. In addition to the format string (which is applied to each message in the batch), there is provision for header and trailer format strings.

When filtering based on logger level and/or handler level is not enough, instances of Filter can be added to both Logger and Handler instances (through their addFilter() method). Before deciding to process a message further, both loggers and handlers consult all their filters for permission. If any filter returns a false value, the message is not processed further.

The basic Filter functionality allows filtering by specific logger name. If this feature is used, messages sent to the named logger and its children are allowed through the filter, and all others dropped.

In addition to the classes described above, there are a number of module- level functions.

getLogger([name])

Return a logger with the specified name or, if no name is specified, return a logger which is the root logger of the hierarchy. If specified, the name is typically a dot-separated hierarchical name like "a", "a.b" or "a.b.c.d". Choice of these names is entirely up to the developer who is using logging.

All calls to this function with a given name return the same logger instance. This means that logger instances never need to be passed between different parts of an application.

getLoggerClass()

Return either the standard Logger class, or the last class passed to setLoggerClass(). This function may be called from within a new class definition, to ensure that installing a customised Logger class will not undo customisations already applied by other code. For example:

```
class MyLogger(logging.getLoggerClass()):
    # ... override behaviour here
```

```
debug(msg[,*args[,**kwargs]])
```

Logs a message with level DEBUG on the root logger. The msg is the message format string, and the args are the arguments which are merged into msg. The only keyword argument in kwargs which is inspected is exc_info which, if it does not evaluate as false, causes exception information to be added to the logging message. If an exception tuple (in the format returned by $sys.exc_info()$) is provided, it is used; otherwise, $sys.exc_info()$ is called to get the exception information.

```
info(msg[,*args[,**kwargs]])
```

Logs a message with level INFO on the root logger. The arguments are interpreted as for debug().

```
warning (msg[, *args[, **kwargs]])
```

Logs a message with level WARNING on the root logger. The arguments are interpreted as for debug ().

```
error (msg[, *args[, **kwargs]])
```

Logs a message with level ERROR on the root logger. The arguments are interpreted as for debug().

```
critical(msg[, *args[, **kwargs]])
```

Logs a message with level CRITICAL on the root logger. The arguments are interpreted as for debug().

```
exception(msg[,*args])
```

Logs a message with level ERROR on the root logger. The arguments are interpreted as for debug(). Exception info is added to the logging message. This function should only be called from an exception handler.

```
log(level, msg[, *args[, **kwargs]])
```

Logs a message with level level on the root logger. The other arguments are interpreted as for debug().

disable(lvl)

Provides an overriding level *lvl* for all loggers which takes precedence over the logger's own level. When the need arises to temporarily throttle logging output down across the whole application, this function can be useful.

addLevelName(lvl, levelName)

Associates level *lvl* with text *levelName* in an internal dictionary, which is used to map numeric levels to a textual representation, for example when a Formatter formats a message. This function can also be used to define your own levels. The only constraints are that all levels used must be registered using this function, levels should be positive integers and they should increase in increasing order of severity.

getLevelName(lvl)

Returns the textual representation of logging level *lvl*. If the level is one of the predefined levels CRITICAL, ERROR, WARNING, INFO or DEBUG then you get the corresponding string. If you have associated levels with names using addLevelName() then the name you have associated with *lvl* is returned. If a numeric value corresponding to one of the defined levels is passed in, the corresponding string representation is returned. Otherwise, the string "Level %s" % lvl is returned.

makeLogRecord(attrdict)

Creates and returns a new LogRecord instance whose attributes are defined by *attrdict*. This function is useful for taking a pickled LogRecord attribute dictionary, sent over a socket, and reconstituting it as a LogRecord instance at the receiving end.

basicConfig([**kwargs])

Does basic configuration for the logging system by creating a StreamHandler with a default Formatter and adding it to the root logger. The functions debug(), info(), warning(), error() and critical() will call basicConfig() automatically if no handlers are defined for the root logger.

Changed in version 2.4: Formerly, basicConfig did not take any keyword arguments.

The following keyword arguments are supported.

Format	Description
filename	Specifies that a FileHandler be created, using the specified filename, rather than a StreamHandler.
filemode	Specifies the mode to open the file, if filename is specified (if filemode is unspecified, it defaults to 'a').
format	Use the specified format string for the handler.
datefmt	Use the specified date/time format.
level	Set the root logger level to the specified level.
stream	Use the specified stream to initialize the StreamHandler. Note that this argument is incompatible with 'filena

shutdown()

Informs the logging system to perform an orderly shutdown by flushing and closing all handlers.

setLoggerClass(klass)

Tells the logging system to use the class *klass* when instantiating a logger. The class should define __init__() such that only a name argument is required, and the __init__() should call Logger.__init__(). This function is typically called before any loggers are instantiated by applications which need to use custom logger behavior.

See Also:

PEP 282, "A Logging System"

The proposal which described this feature for inclusion in the Python standard library.

Original Python logging package

This is the original source for the logging package. The version of the package available from this site is suitable for use with Python 1.5.2, 2.1.x and 2.2.x, which do not include the logging package in the standard library.

6.29.1 Logger Objects

Loggers have the following attributes and methods. Note that Loggers are never instantiated directly, but always through the module-level function logging.getLogger(name).

propagate

If this evaluates to false, logging messages are not passed by this logger or by child loggers to higher level (ancestor) loggers. The constructor sets this attribute to 1.

setLevel(lvl)

Sets the threshold for this logger to *lvl*. Logging messages which are less severe than *lvl* will be ignored. When a logger is created, the level is set to NOTSET (which causes all messages to be processed when the logger is the root logger, or delegation to the parent when the logger is a non-root logger). Note that the root logger is created with level WARNING.

isEnabledFor(lvl)

Indicates if a message of severity *lvl* would be processed by this logger. This method checks first the module-level level set by logging.disable(lvl) and then the logger's effective level as determined by getEffectiveLevel().

getEffectiveLevel()

Indicates the effective level for this logger. If a value other than NOTSET has been set using setLevel(), it is returned. Otherwise, the hierarchy is traversed towards the root until a value other than NOTSET is

found, and that value is returned.

debug(msg[,*args[,**kwargs]])

Logs a message with level DEBUG on this logger. The *msg* is the message format string, and the *args* are the arguments which are merged into *msg*. The only keyword argument in *kwargs* which is inspected is *exc_info* which, if it does not evaluate as false, causes exception information to be added to the logging message. If an exception tuple (as provided by sys.exc_info()) is provided, it is used; otherwise, sys.exc_info() is called to get the exception information.

info(msg[,*args[,**kwargs]])

Logs a message with level INFO on this logger. The arguments are interpreted as for debug().

warning (msg[, *args[, **kwargs]])

Logs a message with level WARNING on this logger. The arguments are interpreted as for debug().

error (msg[, *args[, **kwargs]])

Logs a message with level ERROR on this logger. The arguments are interpreted as for debug ().

critical(msg[, *args[, **kwargs]])

Logs a message with level CRITICAL on this logger. The arguments are interpreted as for debug().

```
log(lvl, msg[, *args[, **kwargs]])
```

Logs a message with integer level lvl on this logger. The other arguments are interpreted as for debug ().

exception(msg[, *args])

 $Logs\ a\ message\ with\ level\ {\tt ERROR}\ on\ this\ logger.\ The\ arguments\ are\ interpreted\ as\ for\ {\tt debug}\ (\)\ .\ Exception\ info\ is\ added\ to\ the\ logging\ message.\ This\ method\ should\ only\ be\ called\ from\ an\ exception\ handler.$

addFilter(filt)

Adds the specified filter filt to this logger.

removeFilter(filt)

Removes the specified filter filt from this logger.

filter(record)

Applies this logger's filters to the record and returns a true value if the record is to be processed.

addHandler(hdlr)

Adds the specified handler hdlr to this logger.

removeHandler(hdlr)

Removes the specified handler hdlr from this logger.

findCaller()

Finds the caller's source filename and line number. Returns the filename and line number as a 2-element tuple.

handle(record)

Handles a record by passing it to all handlers associated with this logger and its ancestors (until a false value of *propagate* is found). This method is used for unpickled records received from a socket, as well as those created locally. Logger-level filtering is applied using filter().

makeRecord(name, lvl, fn, lno, msg, args, exc_info)

This is a factory method which can be overridden in subclasses to create specialized LogRecord instances.

6.29.2 Basic example

Changed in version 2.4: formerly basicConfig did not take any keyword arguments.

The logging package provides a lot of flexibility, and its configuration can appear daunting. This section demonstrates that simple use of the logging package is possible.

The simplest example shows logging to the console:

```
import logging
logging.debug('A debug message')
logging.info('Some information')
logging.warning('A shot across the bows')
```

If you run the above script, you'll see this:

```
WARNING:root:A shot across the bows
```

Because no particular logger was specified, the system used the root logger. The debug and info messages didn't appear because by default, the root logger is configured to only handle messages with a severity of WARNING or above. The message format is also a configuration default, as is the output destination of the messages -sys.stderr. The severity level, the message format and destination can be easily changed, as shown in the example below:

The basicConfig() method is used to change the configuration defaults, which results in output (written to /tmp/myapp.log) which should look something like the following:

```
2004-07-02 13:00:08,743 DEBUG A debug message
2004-07-02 13:00:08,743 INFO Some information
2004-07-02 13:00:08,743 WARNING A shot across the bows
```

This time, all messages with a severity of DEBUG or above were handled, and the format of the messages was also changed, and output went to the specified file rather than the console.

Formatting uses standard Python string formatting - see section 2.3.6. The format string takes the following common specifiers. For a complete list of specifiers, consult the Formatter documentation.

Format	Description
%(name)s	Name of the logger (logging channel).
%(levelname)s	Text logging level for the message ('DEBUG', 'INFO', 'WARNING', 'ERROR', 'CRITICAL').
%(asctime)s	Human-readable time when the LogRecord was created. By default this is of the form "2003-07-08 16:49
%(message)s	The logged message.

To change the date/time format, you can pass an additional keyword parameter, datefmt, as in the following:

which would result in output like

The date format string follows the requirements of strftime() - see the documentation for the time module.

If, instead of sending logging output to the console or a file, you'd rather use a file-like object which you have created separately, you can pass it to basicConfig() using the *stream* keyword argument. Note that if both *stream* and *filename* keyword arguments are passed, the *stream* argument is ignored.

Of course, you can put variable information in your output. To do this, simply have the message be a format string and pass in additional arguments containing the variable information, as in the following example:

```
Wed, 21 Jul 2004 15:35:16 ERROR Pack my box with 5 dozen liquor jugs
```

6.29.3 Logging to multiple destinations

which would result in

Let's say you want to log to console and file with different message formats and in differing circumstances. Say you want to log messages with levels of DEBUG and higher to file, and those messages at level INFO and higher to the console. Let's also assume that the file should contain timestamps, but the console messages should not. Here's how you can achieve this:

```
import logging
# set up logging to file - see previous section for more details
logging.basicConfig(level=logging.DEBUG,
                    format='%(asctime)s %(name)-12s %(levelname)-8s %(message)s',
                    datefmt='%m-%d %H:%M',
                    filename='/temp/myapp.log',
                    filemode='w')
# define a Handler which writes INFO messages or higher to the sys.stderr
console = logging.StreamHandler()
console.setLevel(logging.INFO)
# set a format which is simpler for console use
formatter = logging.Formatter('%(name)-12s: %(levelname)-8s %(message)s')
# tell the handler to use this format
console.setFormatter(formatter)
# add the handler to the root logger
logging.getLogger('').addHandler(console)
# Now, we can log to the root logger, or any other logger. First the root...
logging.info('Jackdaws love my big sphinx of quartz.')
# Now, define a couple of other loggers which might represent areas in your
# application:
logger1 = logging.getLogger('myapp.areal')
logger2 = logging.getLogger('myapp.area2')
logger1.debug('Quick zephyrs blow, vexing daft Jim.')
logger1.info('How quickly daft jumping zebras vex.')
logger2.warning('Jail zesty vixen who grabbed pay from quack.')
logger2.error('The five boxing wizards jump quickly.')
```

When you run this, on the console you will see

```
root : INFO Jackdaws love my big sphinx of quartz.
myapp.areal : INFO How quickly daft jumping zebras vex.
myapp.area2 : WARNING Jail zesty vixen who grabbed pay from quack.
myapp.area2 : ERROR The five boxing wizards jump quickly.
```

and in the file you will see something like

```
10-22 22:19 root INFO Jackdaws love my big sphinx of quartz.

10-22 22:19 myapp.areal DEBUG Quick zephyrs blow, vexing daft Jim.

10-22 22:19 myapp.areal INFO How quickly daft jumping zebras vex.

10-22 22:19 myapp.area2 WARNING Jail zesty vixen who grabbed pay from quack.

10-22 22:19 myapp.area2 ERROR The five boxing wizards jump quickly.
```

As you can see, the DEBUG message only shows up in the file. The other messages are sent to both destinations.

This example uses console and file handlers, but you can use any number and combination of handlers you choose.

6.29.4 Sending and receiving logging events across a network

Let's say you want to send logging events across a network, and handle them at the receiving end. A simple way of doing this is attaching a SocketHandler instance to the root logger at the sending end:

```
import logging, logging.handlers
rootLogger = logging.getLogger('')
rootLogger.setLevel(logging.DEBUG)
socketHandler = logging.handlers.SocketHandler('localhost',
                   logging.handlers.DEFAULT_TCP_LOGGING_PORT)
# don't bother with a formatter, since a socket handler sends the event as
# an unformatted pickle
rootLogger.addHandler(socketHandler)
# Now, we can log to the root logger, or any other logger. First the root...
logging.info('Jackdaws love my big sphinx of quartz.')
# Now, define a couple of other loggers which might represent areas in your
# application:
logger1 = logging.getLogger('myapp.areal')
logger2 = logging.getLogger('myapp.area2')
logger1.debug('Quick zephyrs blow, vexing daft Jim.')
logger1.info('How quickly daft jumping zebras vex.')
logger2.warning('Jail zesty vixen who grabbed pay from quack.')
logger2.error('The five boxing wizards jump quickly.')
```

At the receiving end, you can set up a receiver using the SocketServer module. Here is a basic working example:

```
import cPickle
     import logging
     import logging.handlers
     import SocketServer
     import struct
     class LogRecordStreamHandler(SocketServer.StreamRequestHandler):
         """Handler for a streaming logging request.
         This basically logs the record using whatever logging policy is
         configured locally.
         def handle(self):
             Handle multiple requests - each expected to be a 4-byte length,
             followed by the LogRecord in pickle format. Logs the record
             according to whatever policy is configured locally.
             while 1:
                 chunk = self.connection.recv(4)
                 if len(chunk) < 4:
                     break
                 slen = struct.unpack(">L", chunk)[0]
                 chunk = self.connection.recv(slen)
                 while len(chunk) < slen:</pre>
                     chunk = chunk + self.connection.recv(slen - len(chunk))
                 obj = self.unPickle(chunk)
                 record = logging.makeLogRecord(obj)
                 self.handleLogRecord(record)
         def unPickle(self, data):
             return cPickle.loads(data)
         def handleLogRecord(self, record):
             # if a name is specified, we use the named logger rather than the one
             # implied by the record.
             if self.server.logname is not None:
                name = self.server.logname
             else:
                name = record.name
             logger = logging.getLogger(name)
             # is normally called AFTER logger-level filtering. If you want
             # to do filtering, do it at the client end to save wasting
             # cycles and network bandwidth!
             logger.handle(record)
     \verb|class LogRecordSocketReceiver(SocketServer.ThreadingTCPServer)|:
         """simple TCP socket-based logging receiver suitable for testing.
         allow_reuse_address = 1
         def __init__(self, host='localhost',
                      port=logging.handlers.DEFAULT_TCP_LOGGING_PORT,
                      handler=LogRecordStreamHandler):
             SocketServer.ThreadingTCPServer.__init__(self, (host, port), handler)
             self.abort = 0
             self.timeout = 1
             self.logname = None
         def serve_until_stopped(self):
6.29. logging import salectility for Python
                                                                                371
             while not abort:
```

rd, wr, ex = select.select([self.socket.fileno()],

[], [],

First run the server, and then the client. On the client side, nothing is printed on the console; on the server side, you should see something like:

```
About to start TCP server...

59 root INFO Jackdaws love my big sphinx of quartz.

59 myapp.areal DEBUG Quick zephyrs blow, vexing daft Jim.

69 myapp.areal INFO How quickly daft jumping zebras vex.

69 myapp.area2 WARNING Jail zesty vixen who grabbed pay from quack.

69 myapp.area2 ERROR The five boxing wizards jump quickly.
```

6.29.5 Handler Objects

Handlers have the following attributes and methods. Note that Handler is never instantiated directly; this class acts as a base for more useful subclasses. However, the <code>__init__()</code> method in subclasses needs to call <code>Handler.__init__()</code>.

```
__init__(level=NOTSET)
```

Initializes the Handler instance by setting its level, setting the list of filters to the empty list and creating a lock (using createLock()) for serializing access to an I/O mechanism.

createLock()

Initializes a thread lock which can be used to serialize access to underlying I/O functionality which may not be threadsafe.

acquire()

Acquires the thread lock created with createLock().

release()

Releases the thread lock acquired with acquire().

$\mathtt{setLevel}(\mathit{lvl})$

Sets the threshold for this handler to *lvl*. Logging messages which are less severe than *lvl* will be ignored. When a handler is created, the level is set to NOTSET (which causes all messages to be processed).

setFormatter(form)

Sets the Formatter for this handler to form.

addFilter(filt)

Adds the specified filter *filt* to this handler.

removeFilter(filt)

Removes the specified filter *filt* from this handler.

filter(record)

Applies this handler's filters to the record and returns a true value if the record is to be processed.

flush()

Ensure all logging output has been flushed. This version does nothing and is intended to be implemented by subclasses.

close()

Tidy up any resources used by the handler. This version does nothing and is intended to be implemented by subclasses.

handle(record)

Conditionally emits the specified logging record, depending on filters which may have been added to the handler. Wraps the actual emission of the record with acquisition/release of the I/O thread lock.

handleError(record)

This method should be called from handlers when an exception is encountered during an <code>emit()</code> call. By default it does nothing, which means that exceptions get silently ignored. This is what is mostly wanted for a logging system - most users will not care about errors in the logging system, they are more interested in application errors. You could, however, replace this with a custom handler if you wish. The specified record

is the one which was being processed when the exception occurred.

format(record)

Do formatting for a record - if a formatter is set, use it. Otherwise, use the default formatter for the module.

emit(record

Do whatever it takes to actually log the specified logging record. This version is intended to be implemented by subclasses and so raises a NotImplementedError.

StreamHandler

The StreamHandler class sends logging output to streams such as *sys.stdout*, *sys.stderr* or any file-like object (or, more precisely, any object which supports write() and flush() methods).

class StreamHandler([strm])

Returns a new instance of the StreamHandler class. If *strm* is specified, the instance will use it for logging output; otherwise, *sys.stderr* will be used.

emit(record)

If a formatter is specified, it is used to format the record. The record is then written to the stream with a trailing newline. If exception information is present, it is formatted using traceback.print_exception() and appended to the stream.

flush(

Flushes the stream by calling its flush() method. Note that the close() method is inherited from Handler and so does nothing, so an explicit flush() call may be needed at times.

FileHandler

The FileHandler class sends logging output to a disk file. It inherits the output functionality from StreamHandler.

class FileHandler(filename[, mode])

Returns a new instance of the FileHandler class. The specified file is opened and used as the stream for logging. If *mode* is not specified, 'a' is used. By default, the file grows indefinitely.

close()

Closes the file.

emit(record)

Outputs the record to the file.

RotatingFileHandler

The RotatingFileHandler class supports rotation of disk log files.

class RotatingFileHandler(filename[, mode[, maxBytes[, backupCount]]]))

Returns a new instance of the RotatingFileHandler class. The specified file is opened and used as the stream for logging. If *mode* is not specified, 'a' is used. By default, the file grows indefinitely.

You can use the *maxBytes* and *backupCount* values to allow the file to *rollover* at a predetermined size. When the size is about to be exceeded, the file is closed and a new file is silently opened for output. Rollover occurs whenever the current log file is nearly *maxBytes* in length; if *maxBytes* is zero, rollover never occurs. If *backupCount* is non-zero, the system will save old log files by appending the extensions ".1", ".2" etc., to the filename. For example, with a *backupCount* of 5 and a base file name of 'app.log', you would get 'app.log', 'app.log.1', 'app.log.2', up to 'app.log.5'. The file being written to is always 'app.log'. When this file is filled, it is closed and renamed to 'app.log.1', and if files 'app.log.1', 'app.log.2', etc. exist, then they are renamed to 'app.log.2', 'app.log.3' etc. respectively.

doRollover()

Does a rollover, as described above.

emit(record)

Outputs the record to the file, catering for rollover as described previously.

TimedRotatingFileHandler

The TimedRotatingFileHandler class supports rotation of disk log files at certain timed intervals.

class TimedRotatingFileHandler(filename[,when[,interval[,backupCount]]])

Returns a new instance of the TimedRotatingFileHandler class. The specified file is opened and used as the stream for logging. On rotating it also sets the filename suffix. Rotating happens based on the product of *when* and *interval*.

You can use the *when* to specify the type of *interval*. The list of possible values is, note that they are not case sensitive:

Value	Type of interval
S	Seconds
M	Minutes
H	Hours
D	Days
W	Week day (0=Monday)
midnight	Roll over at midnight

If *backupCount* is non-zero, the system will save old log files by appending the extensions ".1", ".2" etc., to the filename. For example, with a *backupCount* of 5 and a base file name of 'app.log', you would get 'app.log', 'app.log.1', 'app.log.2', up to 'app.log.5'. The file being written to is always 'app.log'. When this file is filled, it is closed and renamed to 'app.log.1', and if files 'app.log.1', 'app.log.2', etc. exist, then they are renamed to 'app.log.2', 'app.log.3' etc. respectively.

doRollover()

Does a rollover, as described above.

emit(record)

Outputs the record to the file, catering for rollover as described above.

SocketHandler

The SocketHandler class sends logging output to a network socket. The base class uses a TCP socket.

class SocketHandler(host, port)

Returns a new instance of the SocketHandler class intended to communicate with a remote machine whose address is given by *host* and *port*.

close()

Closes the socket.

handleError()

emit()

Pickles the record's attribute dictionary and writes it to the socket in binary format. If there is an error with the socket, silently drops the packet. If the connection was previously lost, re-establishes the connection. To unpickle the record at the receiving end into a LogRecord, use the makeLogRecord() function.

handleError()

Handles an error which has occurred during emit(). The most likely cause is a lost connection. Closes the socket so that we can retry on the next event.

makeSocket()

This is a factory method which allows subclasses to define the precise type of socket they want. The default implementation creates a TCP socket (SOCK_STREAM).

makePickle(record)

Pickles the record's attribute dictionary in binary format with a length prefix, and returns it ready for transmission across the socket.

send(packet)

Send a pickled string *packet* to the socket. This function allows for partial sends which can happen when the network is busy.

DatagramHandler

The DatagramHandler class inherits from SocketHandler to support sending logging messages over UDP sockets

class DatagramHandler(host, port)

Returns a new instance of the DatagramHandler class intended to communicate with a remote machine whose address is given by *host* and *port*.

emit()

Pickles the record's attribute dictionary and writes it to the socket in binary format. If there is an error with the socket, silently drops the packet. To unpickle the record at the receiving end into a LogRecord, use the makeLogRecord() function.

makeSocket()

The factory method of SocketHandler is here overridden to create a UDP socket (socket.SOCK_DGRAM).

send(s)

Send a pickled string to a socket.

SysLogHandler

The SysLogHandler class supports sending logging messages to a remote or local UNIX syslog.

class SysLogHandler([address[, facility]])

Returns a new instance of the SysLogHandler class intended to communicate with a remote UNIX machine whose address is given by *address* in the form of a (*host*, *port*) tuple. If *address* is not specified, ('localhost', 514) is used. The address is used to open a UDP socket. If *facility* is not specified, LOG_USER is used.

close()

Closes the socket to the remote host.

emit(record)

The record is formatted, and then sent to the syslog server. If exception information is present, it is *not* sent to the server.

encodePriority(facility, priority)

Encodes the facility and priority into an integer. You can pass in strings or integers - if strings are passed, internal mapping dictionaries are used to convert them to integers.

NTEventLogHandler

The NTEventLogHandler class supports sending logging messages to a local Windows NT, Windows 2000 or Windows XP event log. Before you can use it, you need Mark Hammond's Win32 extensions for Python installed.

class NTEventLogHandler(appname[, dllname[, logtype]])

Returns a new instance of the NTEventLogHandler class. The *appname* is used to define the application name as it appears in the event log. An appropriate registry entry is created using this name. The *dllname* should give the fully qualified pathname of a .dll or .exe which contains message definitions to hold in the log (if not specified, 'win32service.pyd' is used - this is installed with the Win32 extensions and contains some basic placeholder message definitions. Note that use of these placeholders will make your event logs big, as the entire message source is held in the log. If you want slimmer logs, you have to pass in the name of your own .dll or .exe which contains the message definitions you want to use in the event log). The *logtype* is one of 'Application', 'System' or 'Security', and defaults to 'Application'.

close()

At this point, you can remove the application name from the registry as a source of event log entries. However, if you do this, you will not be able to see the events as you intended in the Event Log Viewer - it needs to be able to access the registry to get the .dll name. The current version does not do this (in fact it doesn't do anything).

emit(record)

Determines the message ID, event category and event type, and then logs the message in the NT event log.

getEventCategory(record)

Returns the event category for the record. Override this if you want to specify your own categories. This version returns 0.

getEventType(record)

Returns the event type for the record. Override this if you want to specify your own types. This version does a mapping using the handler's typemap attribute, which is set up in __init__() to a dictionary which contains mappings for DEBUG, INFO, WARNING, ERROR and CRITICAL. If you are using your own levels, you will either need to override this method or place a suitable dictionary in the handler's *typemap* attribute.

getMessageID(record)

Returns the message ID for the record. If you are using your own messages, you could do this by having the *msg* passed to the logger being an ID rather than a format string. Then, in here, you could use a dictionary lookup to get the message ID. This version returns 1, which is the base message ID in 'win32service.pyd'.

SMTPHandler

The SMTPHandler class supports sending logging messages to an email address via SMTP.

class SMTPHandler (mailhost, fromaddr, toaddrs, subject)

Returns a new instance of the SMTPHandler class. The instance is initialized with the from and to addresses and subject line of the email. The *toaddrs* should be a list of strings. To specify a non-standard SMTP port, use the (host, port) tuple format for the *mailhost* argument. If you use a string, the standard SMTP port is used.

emit(record)

Formats the record and sends it to the specified addressees.

getSubject(record)

If you want to specify a subject line which is record-dependent, override this method.

MemoryHandler

The MemoryHandler supports buffering of logging records in memory, periodically flushing them to a *target* handler. Flushing occurs whenever the buffer is full, or when an event of a certain severity or greater is seen.

MemoryHandler is a subclass of the more general BufferingHandler, which is an abstract class. This buffers logging records in memory. Whenever each record is added to the buffer, a check is made by calling shouldFlush() to see if the buffer should be flushed. If it should, then flush() is expected to do the needful.

${\bf class} \ {\tt BufferingHandler} \ (\ capacity \)$

Initializes the handler with a buffer of the specified capacity.

emit(record)

Appends the record to the buffer. If shouldFlush() returns true, calls flush() to process the buffer.

flush()

You can override this to implement custom flushing behavior. This version just zaps the buffer to empty.

shouldFlush(record)

Returns true if the buffer is up to capacity. This method can be overridden to implement custom flushing strategies.

class MemoryHandler (capacity[, flushLevel[, target]])

Returns a new instance of the MemoryHandler class. The instance is initialized with a buffer size of *capacity*. If *flushLevel* is not specified, ERROR is used. If no *target* is specified, the target will need to be set using setTarget() before this handler does anything useful.

close()

Calls flush(), sets the target to None and clears the buffer.

flush()

For a MemoryHandler, flushing means just sending the buffered records to the target, if there is one. Override if you want different behavior.

setTarget(target)

Sets the target handler for this handler.

shouldFlush(record)

Checks for buffer full or a record at the *flushLevel* or higher.

HTTPHandler

The HTTPHandler class supports sending logging messages to a Web server, using either 'GET' or 'POST' semantics.

class HTTPHandler(host, url[, method])

Returns a new instance of the HTTPHandler class. The instance is initialized with a host address, url and HTTP method. If no *method* is specified, 'GET' is used.

emit(record)

Sends the record to the Web server as an URL-encoded dictionary.

6.29.6 Formatter Objects

Formatters have the following attributes and methods. They are responsible for converting a LogRecord to (usually) a string which can be interpreted by either a human or an external system. The base Formatter allows a formatting string to be specified. If none is supplied, the default value of '% (message)s' is used.

A Formatter can be initialized with a format string which makes use of knowledge of the LogRecord attributes - such as the default value mentioned above making use of the fact that the user's message and arguments are preformatted into a LogRecord's *message* attribute. This format string contains standard python %-style mapping keys. See section 2.3.6, "String Formatting Operations," for more information on string formatting.

Currently, the useful mapping keys in a LogRecord are:

Format	Description
%(name)s	Name of the logger (logging channel).
%(levelno)s	Numeric logging level for the message (DEBUG, INFO, WARNING, ERROR, CRITICAL).
%(levelname)s	Text logging level for the message ('DEBUG', 'INFO', 'WARNING', 'ERROR', 'CRITICAL').
%(revername)s %(pathname)s	Full pathname of the source file where the logging call was issued (if available).
%(filename)s	Filename portion of pathname.
%(IIIename)s %(module)s	Module (name portion of filename).
` '	` _
%(lineno)d	Source line number where the logging call was issued (if available).
%(created)f	Time when the LogRecord was created (as returned by time.time()).
%(asctime)s	Human-readable time when the LogRecord was created. By default this is of the form "2003-07-08 16:4
%(msecs)d	Millisecond portion of the time when the LogRecord was created.
%(thread)d	Thread ID (if available).
%(threadName)s	Thread name (if available).
%(process)d	Process ID (if available).
%(message)s	The logged message, computed as msg %args.

class Formatter([fmt[, datefmt]])

Returns a new instance of the Formatter class. The instance is initialized with a format string for the

message as a whole, as well as a format string for the date/time portion of a message. If no *fmt* is specified, '% (message) s' is used. If no *datefmt* is specified, the ISO8601 date format is used.

format(record)

The record's attribute dictionary is used as the operand to a string formatting operation. Returns the resulting string. Before formatting the dictionary, a couple of preparatory steps are carried out. The *message* attribute of the record is computed using *msg* % *args*. If the formatting string contains '(asctime)', formatTime() is called to format the event time. If there is exception information, it is formatted using formatException() and appended to the message.

formatTime(record[, datefmt])

This method should be called from format() by a formatter which wants to make use of a formatted time. This method can be overridden in formatters to provide for any specific requirement, but the basic behavior is as follows: if *datefint* (a string) is specified, it is used with time.strftime() to format the creation time of the record. Otherwise, the ISO8601 format is used. The resulting string is returned.

formatException(exc_info)

Formats the specified exception information (a standard exception tuple as returned by sys.exc_info()) as a string. This default implementation just uses traceback.print_exception(). The resulting string is returned.

6.29.7 Filter Objects

Filters can be used by Handlers and Loggers for more sophisticated filtering than is provided by levels. The base filter class only allows events which are below a certain point in the logger hierarchy. For example, a filter initialized with "A.B" will allow events logged by loggers "A.B", "A.B.C", "A.B.C.D", "A.B.D" etc. but not "A.BB", "B.A.B" etc. If initialized with the empty string, all events are passed.

class Filter([name])

Returns an instance of the Filter class. If *name* is specified, it names a logger which, together with its children, will have its events allowed through the filter. If no name is specified, allows every event.

filter(record)

Is the specified record to be logged? Returns zero for no, nonzero for yes. If deemed appropriate, the record may be modified in-place by this method.

6.29.8 LogRecord Objects

LogRecord instances are created every time something is logged. They contain all the information pertinent to the event being logged. The main information passed in is in msg and args, which are combined using msg % args to create the message field of the record. The record also includes information such as when the record was created, the source line where the logging call was made, and any exception information to be logged.

class LogRecord(name, lvl, pathname, lineno, msg, args, exc_info)

Returns an instance of LogRecord initialized with interesting information. The *name* is the logger name; *lvl* is the numeric level; *pathname* is the absolute pathname of the source file in which the logging call was made; *lineno* is the line number in that file where the logging call is found; *msg* is the user-supplied message (a format string); *args* is the tuple which, together with *msg*, makes up the user message; and *exc_info* is the exception tuple obtained by calling sys.exc_info() (or None, if no exception information is available).

getMessage()

Returns the message for this LogRecord instance after merging any user-supplied arguments with the message.

6.29.9 Thread Safety

The logging module is intended to be thread-safe without any special work needing to be done by its clients. It achieves this though using threading locks; there is one lock to serialize access to the module's shared data, and

each handler also creates a lock to serialize access to its underlying I/O.

6.29.10 Configuration

Configuration functions

The following functions allow the logging module to be configured. Before they can be used, you must import logging.config. Their use is optional — you can configure the logging module entirely by making calls to the main API (defined in logging itself) and defining handlers which are declared either in logging or logging.handlers.

fileConfig(fname[, defaults])

Reads the logging configuration from a ConfigParser-format file named *fname*. This function can be called several times from an application, allowing an end user the ability to select from various pre-canned configurations (if the developer provides a mechanism to present the choices and load the chosen configuration). Defaults to be passed to ConfigParser can be specified in the *defaults* argument.

listen([port])

Starts up a socket server on the specified port, and listens for new configurations. If no port is specified, the module's default DEFAULT_LOGGING_CONFIG_PORT is used. Logging configurations will be sent as a file suitable for processing by fileConfig(). Returns a Thread instance on which you can call start() to start the server, and which you can join() when appropriate. To stop the server, call stopListening(). To send a configuration to the socket, read in the configuration file and send it to the socket as a string of bytes preceded by a four-byte length packed in binary using struct.pack(">L", n).

stopListening()

Stops the listening server which was created with a call to listen(). This is typically called before calling join() on the return value from listen().

Configuration file format

The configuration file format understood by fileConfig() is based on ConfigParser functionality. The file must contain sections called [loggers], [handlers] and [formatters] which identify by name the entities of each type which are defined in the file. For each such entity, there is a separate section which identified how that entity is configured. Thus, for a logger named log01 in the [loggers] section, the relevant configuration details are held in a section [logger_log01]. Similarly, a handler called hand01 in the [handlers] section will have its configuration held in a section called [handler_hand01], while a formatter called form01 in the [formatters] section will have its configuration specified in a section called [formatter_form01]. The root logger configuration must be specified in a section called [logger_root].

Examples of these sections in the file are given below.

```
[loggers]
keys=root,log02,log03,log04,log05,log06,log07
[handlers]
keys=hand01,hand02,hand03,hand04,hand05,hand06,hand07,hand08,hand09
[formatters]
keys=form01,form02,form03,form04,form05,form06,form07,form08,form09
```

The root logger must specify a level and a list of handlers. An example of a root logger section is given below.

```
[logger_root]
level=NOTSET
handlers=hand01
```

The level entry can be one of DEBUG, INFO, WARNING, ERROR, CRITICAL or NOTSET. For the root logger only, NOTSET means that all messages will be logged. Level values are eval() uated in the context of

the logging package's namespace.

The handlers entry is a comma-separated list of handler names, which must appear in the [handlers] section. These names must appear in the [handlers] section and have corresponding sections in the configuration file

For loggers other than the root logger, some additional information is required. This is illustrated by the following example.

```
[logger_parser]
level=DEBUG
handlers=hand01
propagate=1
qualname=compiler.parser
```

The level and handlers entries are interpreted as for the root logger, except that if a non-root logger's level is specified as NOTSET, the system consults loggers higher up the hierarchy to determine the effective level of the logger. The propagate entry is set to 1 to indicate that messages must propagate to handlers higher up the logger hierarchy from this logger, or 0 to indicate that messages are **not** propagated to handlers up the hierarchy. The qualname entry is the hierarchical channel name of the logger, that is to say the name used by the application to get the logger.

Sections which specify handler configuration are exemplified by the following.

```
[handler_hand01]
class=StreamHandler
level=NOTSET
formatter=form01
args=(sys.stdout,)
```

The class entry indicates the handler's class (as determined by eval() in the logging package's namespace). The level is interpreted as for loggers, and NOTSET is taken to mean "log everything".

The formatter entry indicates the key name of the formatter for this handler. If blank, a default formatter (logging._defaultFormatter) is used. If a name is specified, it must appear in the [formatters] section and have a corresponding section in the configuration file.

The args entry, when eval () uated in the context of the logging package's namespace, is the list of arguments to the constructor for the handler class. Refer to the constructors for the relevant handlers, or to the examples below, to see how typical entries are constructed.

```
[handler_hand02]
class=FileHandler
level=DEBUG
formatter=form02
args=('python.log', 'w')
[handler_hand03]
\verb|class=| handlers.SocketHandler|
level=TNFO
formatter=form03
args=('localhost', handlers.DEFAULT_TCP_LOGGING_PORT)
[handler_hand04]
class=handlers.DatagramHandler
level=WARN
formatter=form04
args=('localhost', handlers.DEFAULT_UDP_LOGGING_PORT)
[handler_hand05]
class=handlers.SysLogHandler
level=ERROR
formatter=form05
args=(('localhost', handlers.SYSLOG_UDP_PORT), handlers.SysLogHandler.LOG_USER)
[handler_hand06]
class=handlers.NTEventLogHandler
level=CRITICAL
formatter=form06
args=('Python Application', '', 'Application')
[handler_hand07]
class=handlers.SMTPHandler
level=WARN
formatter=form07
args=('localhost', 'from@abc', ['userl@abc', 'user2@xyz'], 'Logger Subject')
[handler_hand08]
class=handlers.MemoryHandler
level=NOTSET
formatter=form08
target=
args=(10, ERROR)
[handler_hand09]
class=handlers.HTTPHandler
level=NOTSET
formatter=form09
args=('localhost:9022', '/log', 'GET')
```

Sections which specify formatter configuration are typified by the following.

```
[formatter_form01]
format=F1 %(asctime)s %(levelname)s %(message)s
datefmt=
```

The format entry is the overall format string, and the datefmt entry is the strftime()-compatible date/time format string. If empty, the package substitutes ISO8601 format date/times, which is almost equivalent to specifying the date format string "The ISO8601 format also specifies milliseconds, which are appended to the result of using the above format string, with a comma separator. An example time in ISO8601 format is 2003-01-23

6.30 platform — Access to underlying platform's identifying data.

New in version 2.3.

Note: Specific platforms listed alphabetically, with Linux included in the UNIX section.

6.30.1 Cross Platform

architecture(executable=sys.executable, bits=", linkage=")

Queries the given executable (defaults to the Python interpreter binary) for various architecture information.

Returns a tuple (bits, linkage) which contain information about the bit architecture and the linkage format used for the executable. Both values are returned as strings.

Values that cannot be determined are returned as given by the parameter presets. If bits is given as '', the sizeof(pointer) (or sizeof(long) on Python version; 1.5.2) is used as indicator for the supported pointer size.

The function relies on the system's 'file' command to do the actual work. This is available on most if not all UNIX platforms and some non-UNIX platforms and then only if the executable points to the Python interpreter. Reasonable defaults are used when the above needs are not met.

machine()

Returns the machine type, e.g. 'i386'. An empty string is returned if the value cannot be determined.

node()

Returns the computer's network name (may not be fully qualified!). An empty string is returned if the value cannot be determined.

platform(aliased=0, terse=0)

Returns a single string identifying the underlying platform with as much useful information as possible.

The output is intended to be *human readable* rather than machine parseable. It may look different on different platforms and this is intended.

If *aliased* is true, the function will use aliases for various platforms that report system names which differ from their common names, for example SunOS will be reported as Solaris. The <code>system_alias()</code> function is used to implement this.

Setting *terse* to true causes the function to return only the absolute minimum information needed to identify the platform.

processor()

Returns the (real) processor name, e.g. 'amdk6'.

An empty string is returned if the value cannot be determined. Note that many platforms do not provide this information or simply return the same value as for machine (). NetBSD does this.

python_build()

Returns a tuple (buildno, builddate) stating the Python build number and date as strings.

python_compiler()

Returns a string identifying the compiler used for compiling Python.

python_version()

Returns the Python version as string 'major.minor.patchlevel'

Note that unlike the Python sys.version, the returned value will always include the patchlevel (it defaults to 0).

python_version_tuple()

Returns the Python version as tuple (major, minor, patchlevel) of strings.

Note that unlike the Python sys.version, the returned value will always include the patchlevel (it defaults to '0').

release()

Returns the system's release, e.g. '2.2.0' or 'NT' An empty string is returned if the value cannot be determined.

system()

Returns the system/OS name, e.g. 'Linux', 'Windows', or 'Java'. An empty string is returned if the value cannot be determined.

system_alias(system, release, version)

Returns (*system*, *release*, *version*) aliased to common marketing names used for some systems. It also does some reordering of the information in some cases where it would otherwise cause confusion.

version()

Returns the system's release version, e.g. '#3 on degas'. An empty string is returned if the value cannot be determined.

uname()

Fairly portable uname interface. Returns a tuple of strings (*system*, *node*, *release*, *version*, *machine*, *processor*) identifying the underlying platform.

Note that unlike the os.uname() function this also returns possible processor information as additional tuple entry.

Entries which cannot be determined are set to ''.

6.30.2 Java Platform

```
java_ver(release=", vendor=", vminfo=(",","), osinfo=(",","))
```

Version interface for JPython.

Returns a tuple (release, vendor, vminfo, osinfo) with vminfo being a tuple (vm_name, vm_release, vm_vendor) and osinfo being a tuple (os_name, os_version, os_arch). Values which cannot be determined are set to the defaults given as parameters (which all default to '').

6.30.3 Windows Platform

```
win32_ver(release=", version=", csd=", ptype=")
```

Get additional version information from the Windows Registry and return a tuple (*version*, *csd*, *ptype*) referring to version number, CSD level and OS type (multi/single processor).

As a hint: ptype is 'Uniprocessor Free' on single processor NT machines and 'Multiprocessor Free' on multi processor machines. The 'Free' refers to the OS version being free of debugging code. It could also state 'Checked' which means the OS version uses debugging code, i.e. code that checks arguments, ranges, etc.

Note: This function only works if Mark Hammond's win32all package is installed and (obviously) only runs on Win32 compatible platforms.

Win95/98 specific

```
popen(cmd, mode='r', bufsize=None)
```

Portable popen() interface. Find a working popen implementation preferring win32pipe.popen(). On Windows NT, win32pipe.popen() should work; on Windows 9x it hangs due to bugs in the MS C library.

6.30.4 Mac OS Platform

```
mac_ver(release=", versioninfo=(",","), machine=")
```

Get Mac OS version information and return it as tuple (release, versioninfo, machine) with versioninfo being a tuple (version, dev_stage, non_release_version).

Entries which cannot be determined are set to ''. All tuple entries are strings.

Documentation for the underlying gestalt() API is available online at http://www.rgaros.nl/gestalt/.

6.30.5 UNIX Platforms

dist(distname=", version=", id=", supported_dists=('SuSE','debian','redhat','mandrake'))

Tries to determine the name of the OS distribution name Returns a tuple (distname, version, id) which defaults to the args given as parameters.

libc_ver(executable=sys.executable, lib=", version=", chunksize=2048)

Tries to determine the libc version against which the file executable (defaults to the Python interpreter) is linked. Returns a tuple of strings (*lib*, *version*) which default to the given parameters in case the lookup fails.

Note that this function has intimate knowledge of how different libc versions add symbols to the executable is probably only useable for executables compiled using **gcc**.

The file is read and scanned in chunks of chunksize bytes.

Optional Operating System Services

The modules described in this chapter provide interfaces to operating system features that are available on selected operating systems only. The interfaces are generally modeled after the UNIX or C interfaces but they are available on some other systems as well (e.g. Windows or NT). Here's an overview:

signal Set handlers for asynchronous events.

socket Low-level networking interface.

select Wait for I/O completion on multiple streams.

thread Create multiple threads of control within one interpreter.

threading Higher-level threading interface.

dummy_thread Drop-in replacement for the thread module.
dummy_threading Drop-in replacement for the threading module.

Queue A synchronized queue class.

mmap Interface to memory-mapped files for UNIX and Windows.

anydbm Generic interface to DBM-style database modules. **dbhash** DBM-style interface to the BSD database library.

whichdb Guess which DBM-style module created a given database.

bsddb Interface to Berkeley DB database library

dumbdbm Portable implementation of the simple DBM interface.

zlib Low-level interface to compression and decompression routines compatible with **gzip**.

gzip Interfaces for gzip compression and decompression using file objects.

bz2 Interface to compression and decompression routines compatible with bzip2.

zipfile Read and write ZIP-format archive files.

Read and write tar-format archive files.

readline GNU readline support for Python.

rlcompleter Python identifier completion for the GNU readline library.

7.1 signal — Set handlers for asynchronous events

This module provides mechanisms to use signal handlers in Python. Some general rules for working with signals and their handlers:

- A handler for a particular signal, once set, remains installed until it is explicitly reset (Python emulates the BSD style interface regardless of the underlying implementation), with the exception of the handler for SIGCHLD, which follows the underlying implementation.
- There is no way to "block" signals temporarily from critical sections (since this is not supported by all UNIX flavors).
- Although Python signal handlers are called asynchronously as far as the Python user is concerned, they can only occur between the "atomic" instructions of the Python interpreter. This means that signals arriving during long calculations implemented purely in C (such as regular expression matches on large bodies of text) may be delayed for an arbitrary amount of time.

- When a signal arrives during an I/O operation, it is possible that the I/O operation raises an exception after the signal handler returns. This is dependent on the underlying UNIX system's semantics regarding interrupted system calls.
- Because the C signal handler always returns, it makes little sense to catch synchronous errors like SIGFPE or SIGSEGV.
- Python installs a small number of signal handlers by default: SIGPIPE is ignored (so write errors on pipes and sockets can be reported as ordinary Python exceptions) and SIGINT is translated into a KeyboardInterrupt exception. All of these can be overridden.
- Some care must be taken if both signals and threads are used in the same program. The fundamental thing to remember in using signals and threads simultaneously is: always perform signal() operations in the main thread of execution. Any thread can perform an alarm(), getsignal(), or pause(); only the main thread can set a new signal handler, and the main thread will be the only one to receive signals (this is enforced by the Python signal module, even if the underlying thread implementation supports sending signals to individual threads). This means that signals can't be used as a means of inter-thread communication. Use locks instead.

The variables defined in the signal module are:

SIG DFL

This is one of two standard signal handling options; it will simply perform the default function for the signal. For example, on most systems the default action for SIGQUIT is to dump core and exit, while the default action for SIGCLD is to simply ignore it.

SIG_IGN

This is another standard signal handler, which will simply ignore the given signal.

SIG*

All the signal numbers are defined symbolically. For example, the hangup signal is defined as signal.SIGHUP; the variable names are identical to the names used in C programs, as found in <signal.h>. The UNIX man page for 'signal()' lists the existing signals (on some systems this is signal(2), on others the list is in signal(7)). Note that not all systems define the same set of signal names; only those names defined by the system are defined by this module.

NSIG

One more than the number of the highest signal number.

The signal module defines the following functions:

alarm(time)

If *time* is non-zero, this function requests that a SIGALRM signal be sent to the process in *time* seconds. Any previously scheduled alarm is canceled (only one alarm can be scheduled at any time). The returned value is then the number of seconds before any previously set alarm was to have been delivered. If *time* is zero, no alarm id scheduled, and any scheduled alarm is canceled. The return value is the number of seconds remaining before a previously scheduled alarm. If the return value is zero, no alarm is currently scheduled. (See the UNIX man page *alarm*(2).) Availability: UNIX.

getsignal(signalnum)

Return the current signal handler for the signal *signalnum*. The returned value may be a callable Python object, or one of the special values signal.SIG_IGN, signal.SIG_DFL or None. Here, signal.SIG_IGN means that the signal was previously ignored, signal.SIG_DFL means that the default way of handling the signal was previously in use, and None means that the previous signal handler was not installed from Python.

pause()

Cause the process to sleep until a signal is received; the appropriate handler will then be called. Returns nothing. Not on Windows. (See the UNIX man page signal(2).)

signal(signalnum, handler)

Set the handler for signal *signalnum* to the function *handler*. *handler* can be a callable Python object taking two arguments (see below), or one of the special values signal.SIG_IGN or signal.SIG_DFL. The

previous signal handler will be returned (see the description of getsignal() above). (See the UNIX man page signal(2).)

When threads are enabled, this function can only be called from the main thread; attempting to call it from other threads will cause a ValueError exception to be raised.

The *handler* is called with two arguments: the signal number and the current stack frame (None or a frame object; for a description of frame objects, see the reference manual section on the standard type hierarchy or see the attribute descriptions in the <code>inspect</code> module).

7.1.1 Example

Here is a minimal example program. It uses the <code>alarm()</code> function to limit the time spent waiting to open a file; this is useful if the file is for a serial device that may not be turned on, which would normally cause the <code>os.open()</code> to hang indefinitely. The solution is to set a 5-second alarm before opening the file; if the operation takes too long, the alarm signal will be sent, and the handler raises an exception.

```
import signal, os

def handler(signum, frame):
    print 'Signal handler called with signal', signum
    raise IOError, "Couldn't open device!"

# Set the signal handler and a 5-second alarm
signal.signal(signal.SIGALRM, handler)
signal.alarm(5)

# This open() may hang indefinitely
fd = os.open('/dev/ttyS0', os.O_RDWR)

signal.alarm(0)  # Disable the alarm
```

7.2 socket — Low-level networking interface

This module provides access to the BSD *socket* interface. It is available on all modern UNIX systems, Windows, MacOS, BeOS, OS/2, and probably additional platforms.

For an introduction to socket programming (in C), see the following papers: An Introductory 4.3BSD Interprocess Communication Tutorial, by Stuart Sechrest and An Advanced 4.3BSD Interprocess Communication Tutorial, by Samuel J. Leffler et al, both in the UNIX Programmer's Manual, Supplementary Documents 1 (sections PS1:7 and PS1:8). The platform-specific reference material for the various socket-related system calls are also a valuable source of information on the details of socket semantics. For UNIX, refer to the manual pages; for Windows, see the WinSock (or Winsock 2) specification. For IPv6-ready APIs, readers may want to refer to RFC 2553 titled Basic Socket Interface Extensions for IPv6.

The Python interface is a straightforward transliteration of the UNIX system call and library interface for sockets to Python's object-oriented style: the <code>socket()</code> function returns a *socket object* whose methods implement the various socket system calls. Parameter types are somewhat higher-level than in the C interface: as with <code>read()</code> and <code>write()</code> operations on Python files, buffer allocation on receive operations is automatic, and buffer length is implicit on send operations.

Socket addresses are represented as follows: A single string is used for the AF_UNIX address family. A pair (host, port) is used for the AF_INET address family, where host is a string representing either a hostname in Internet domain notation like 'daring.cwi.nl' or an IPv4 address like '100.50.200.5', and port is an integral port number. For AF_INET6 address family, a four-tuple (host, port, flowinfo, scopeid) is used, where flowinfo and scopeid represents sin6_flowinfo and sin6_scope_id member in struct sockaddr_in6 in C. For socket module methods, flowinfo and scopeid can be omitted just for backward

compatibility. Note, however, omission of *scopeid* can cause problems in manipulating scoped IPv6 addresses. Other address families are currently not supported. The address format required by a particular socket object is automatically selected based on the address family specified when the socket object was created.

For IPv4 addresses, two special forms are accepted instead of a host address: the empty string represents INADDR_ANY, and the string '

' represents INADDR_BROADCAST. The behavior is not available for IPv6 for backward compatibility, therefore, you may want to avoid these if you intend to support IPv6 with your Python programs.

```
IPPORT_*
```

INADDR_*

IP_*

IPV6_*

EAI_*

AI *

NI_*

TCP_*

Many constants of these forms, documented in the UNIX documentation on sockets and/or the IP protocol, are also defined in the socket module. They are generally used in arguments to the setsockopt() and getsockopt() methods of socket objects. In most cases, only those symbols that are defined in the UNIX header files are defined; for a few symbols, default values are provided.

has_ipv6

This constant contains a boolean value which indicates if IPv6 is supported on this platform. New in version 2.3.

getaddrinfo(host, port[, family[, socktype[, proto[, flags]]]])

Resolves the *host/port* argument, into a sequence of 5-tuples that contain all the necessary argument for the sockets manipulation. *host* is a domain name, a string representation of IPv4/v6 address or None. *port* is a string service name (like 'http'), a numeric port number or None.

The rest of the arguments are optional and must be numeric if specified. For *host* and *port*, by passing either an empty string or None, you can pass NULL to the C API. The getaddrinfo() function returns a list of 5-tuples with the following structure:

```
(family, socktype, proto, canonname, sockaddr)
```

family, socktype, proto are all integer and are meant to be passed to the socket() function. canon-name is a string representing the canonical name of the host. It can be a numeric IPv4/v6 address when AI_CANONNAME is specified for a numeric host. sockaddr is a tuple describing a socket address, as described above. See the source for the httplib and other library modules for a typical usage of the function. New in version 2.2.

getfqdn([name])

Return a fully qualified domain name for *name*. If *name* is omitted or empty, it is interpreted as the local host. To find the fully qualified name, the hostname returned by gethostbyaddr() is checked, then aliases for the host, if available. The first name which includes a period is selected. In case no fully qualified domain name is available, the hostname as returned by gethostname() is returned. New in version 2.0.

gethostbyname(hostname)

Translate a host name to IPv4 address format. The IPv4 address is returned as a string, such as '100.50.200.5'. If the host name is an IPv4 address itself it is returned unchanged. See gethostbyname_ex() for a more complete interface. gethostbyname() does not support IPv6 name resolution, and getaddrinfo() should be used instead for IPv4/v6 dual stack support.

gethostbyname_ex(hostname)

Translate a host name to IPv4 address format, extended interface. Return a triple (hostname, aliaslist, ipaddrlist) where hostname is the primary host name responding to the given ip_address, aliaslist is a (possibly empty) list of alternative host names for the same address, and ipaddrlist is a list of IPv4 addresses for the same interface on the same host (often but not always a single address). gethostbyname_ex() does not support IPv6 name resolution, and getaddrinfo() should be used instead for IPv4/v6 dual stack support.

gethostname()

Return a string containing the hostname of the machine where the Python interpreter is currently executing. If you want to know the current machine's IP address, you may want to use gethostbyname(gethostname()). This operation assumes that there is a valid address-to-host mapping for the host, and the assumption does not always hold. Note: gethostname() doesn't always return the fully qualified domain name; use gethostbyaddr(gethostname()) (see below).

gethostbyaddr(ip_address)

Return a triple (hostname, aliaslist, ipaddrlist) where hostname is the primary host name responding to

the given $ip_address$, aliaslist is a (possibly empty) list of alternative host names for the same address, and ipaddrlist is a list of IPv4/v6 addresses for the same interface on the same host (most likely containing only a single address). To find the fully qualified domain name, use the function getfqdn(). gethostbyaddr supports both IPv4 and IPv6.

getnameinfo(sockaddr, flags)

Translate a socket address *sockaddr* into a 2-tuple (*host*, *port*). Depending on the settings of *flags*, the result can contain a fully-qualified domain name or numeric address representation in *host*. Similarly, *port* can contain a string port name or a numeric port number. New in version 2.2.

getprotobyname(protocolname)

Translate an Internet protocol name (for example, 'icmp') to a constant suitable for passing as the (optional) third argument to the socket() function. This is usually only needed for sockets opened in "raw" mode (SOCK_RAW); for the normal socket modes, the correct protocol is chosen automatically if the protocol is omitted or zero.

getservbyname(servicename[, protocolname])

Translate an Internet service name and protocol name to a port number for that service. The optional protocol name, if given, should be 'tcp' or 'udp', otherwise any protocol will match.

getservbyport(port[, protocolname])

Translate an Internet port number and protocol name to a service name for that service. The optional protocol name, if given, should be 'tcp' or 'udp', otherwise any protocol will match.

socket([family[, type[, proto]]])

Create a new socket using the given address family, socket type and protocol number. The address family should be AF_INET (the default), AF_INET6 or AF_UNIX. The socket type should be SOCK_STREAM (the default), SOCK_DGRAM or perhaps one of the other 'SOCK_' constants. The protocol number is usually zero and may be omitted in that case.

ssl(sock[, keyfile, certfile])

Initiate a SSL connection over the socket *sock*. *keyfile* is the name of a PEM formatted file that contains your private key. *certfile* is a PEM formatted certificate chain file. On success, a new SSLObject is returned.

Warning: This does not do any certificate verification!

socketpair([family[, type[, proto]]])

Build a pair of connected socket objects using the given address family, socket type, and protocol number. Address family, socket type, and protocol number are as for the <code>socket()</code> function above. The default family is AF_UNIX if defined on the platform; otherwise, the default is AF_INET. Availability: UNIX. New in version 2.4.

fromfd(fd, family, type[, proto])

Build a socket object from an existing file descriptor (an integer as returned by a file object's fileno() method). Address family, socket type and protocol number are as for the socket() function above. The file descriptor should refer to a socket, but this is not checked — subsequent operations on the object may fail if the file descriptor is invalid. This function is rarely needed, but can be used to get or set socket options on a socket passed to a program as standard input or output (such as a server started by the UNIX inet daemon). The socket is assumed to be in blocking mode. Availability: UNIX.

ntohl(x)

Convert 32-bit integers from network to host byte order. On machines where the host byte order is the same as network byte order, this is a no-op; otherwise, it performs a 4-byte swap operation.

ntohs(x)

Convert 16-bit integers from network to host byte order. On machines where the host byte order is the same as network byte order, this is a no-op; otherwise, it performs a 2-byte swap operation.

htonl(x)

Convert 32-bit integers from host to network byte order. On machines where the host byte order is the same as network byte order, this is a no-op; otherwise, it performs a 4-byte swap operation.

htons(x)

Convert 16-bit integers from host to network byte order. On machines where the host byte order is the same as network byte order, this is a no-op; otherwise, it performs a 2-byte swap operation.

inet_aton(ip_string)

Convert an IPv4 address from dotted-quad string format (for example, '123.45.67.89') to 32-bit packed binary format, as a string four characters in length. This is useful when conversing with a program that uses the standard C library and needs objects of type struct in_addr, which is the C type for the 32-bit packed binary this function returns.

If the IPv4 address string passed to this function is invalid, socket.error will be raised. Note that exactly what is valid depends on the underlying C implementation of inet_aton().

 $inet_aton()$ does not support IPv6, and getnameinfo() should be used instead for IPv4/v6 dual stack support.

inet_ntoa(packed_ip)

Convert a 32-bit packed IPv4 address (a string four characters in length) to its standard dotted-quad string representation (for example, '123.45.67.89'). This is useful when conversing with a program that uses the standard C library and needs objects of type struct in_addr, which is the C type for the 32-bit packed binary data this function takes as an argument.

If the string passed to this function is not exactly 4 bytes in length, socket.error will be raised. inet_ntoa() does not support IPv6, and getnameinfo() should be used instead for IPv4/v6 dual stack support.

inet_pton(address_family, ip_string)

Convert an IP address from its family-specific string format to a packed, binary format. inet_pton() is useful when a library or network protocol calls for an object of type struct in_addr (similar to inet_aton()) or struct in6_addr.

Supported values for *address_family* are currently AF_INET and AF_INET6. If the IP address string *ip_string* is invalid, <code>socket.error</code> will be raised. Note that exactly what is valid depends on both the value of *address_family* and the underlying implementation of <code>inet_pton()</code>.

Availability: UNIX (maybe not all platforms). New in version 2.3.

inet_ntop(address_family, packed_ip)

Convert a packed IP address (a string of some number of characters) to its standard, family-specific string representation (for example, '7.10.0.5' or '5aef:2b::8') inet_ntop() is useful when a library or network protocol returns an object of type struct in_addr (similar to inet_ntoa()) or struct in6_addr.

Supported values for *address_family* are currently AF_INET and AF_INET6. If the string *packed_ip* is not the correct length for the specified address family, ValueError will be raised. A socket.error is raised for errors from the call to inet_ntop().

Availability: UNIX (maybe not all platforms). New in version 2.3.

getdefaulttimeout()

Return the default timeout in floating seconds for new socket objects. A value of None indicates that new socket objects have no timeout. When the socket module is first imported, the default is None. New in version 2.3.

setdefaulttimeout(timeout)

Set the default timeout in floating seconds for new socket objects. A value of None indicates that new socket objects have no timeout. When the socket module is first imported, the default is None. New in version 2.3.

SocketType

This is a Python type object that represents the socket object type. It is the same as type (socket (...)).

See Also:

Module SocketServer (section 11.16):

Classes that simplify writing network servers.

7.2.1 Socket Objects

Socket objects have the following methods. Except for makefile() these correspond to UNIX system calls applicable to sockets.

accept()

Accept a connection. The socket must be bound to an address and listening for connections. The return value is a pair (*conn*, *address*) where *conn* is a *new* socket object usable to send and receive data on the connection, and *address* is the address bound to the socket on the other end of the connection.

bind(address)

Bind the socket to *address*. The socket must not already be bound. (The format of *address* depends on the address family — see above.) **Note:** This method has historically accepted a pair of parameters for AF_INET addresses instead of only a tuple. This was never intentional and is no longer available in Python 2.0 and later.

close()

Close the socket. All future operations on the socket object will fail. The remote end will receive no more data (after queued data is flushed). Sockets are automatically closed when they are garbage-collected.

connect(address)

Connect to a remote socket at *address*. (The format of *address* depends on the address family — see above.) **Note:** This method has historically accepted a pair of parameters for AF_INET addresses instead of only a tuple. This was never intentional and is no longer available in Python 2.0 and later.

connect_ex(address)

Like connect (address), but return an error indicator instead of raising an exception for errors returned by the C-level connect () call (other problems, such as "host not found," can still raise exceptions). The error indicator is 0 if the operation succeeded, otherwise the value of the error variable. This is useful to support, for example, asynchronous connects. **Note:** This method has historically accepted a pair of parameters for AF_INET addresses instead of only a tuple. This was never intentional and is no longer available in Python 2.0 and later.

fileno()

Return the socket's file descriptor (a small integer). This is useful with select.select().

Under Windows the small integer returned by this method cannot be used where a file descriptor can be used (such as os.fdopen()). UNIX does not have this limitation.

getpeername()

Return the remote address to which the socket is connected. This is useful to find out the port number of a remote IPv4/v6 socket, for instance. (The format of the address returned depends on the address family — see above.) On some systems this function is not supported.

getsockname()

Return the socket's own address. This is useful to find out the port number of an IPv4/v6 socket, for instance. (The format of the address returned depends on the address family — see above.)

getsockopt(level, optname[, buflen])

Return the value of the given socket option (see the UNIX man page <code>getsockopt(2)</code>). The needed symbolic constants (SO_* etc.) are defined in this module. If <code>buflen</code> is absent, an integer option is assumed and its integer value is returned by the function. If <code>buflen</code> is present, it specifies the maximum length of the buffer used to receive the option in, and this buffer is returned as a string. It is up to the caller to decode the contents of the buffer (see the optional built-in module <code>struct</code> for a way to decode C structures encoded as strings).

listen(backlog)

Listen for connections made to the socket. The *backlog* argument specifies the maximum number of queued connections and should be at least 1; the maximum value is system-dependent (usually 5).

makefile([mode[, bufsize]])

Return a *file object* associated with the socket. (File objects are described in 2.3.9, "File Objects.") The file object references a dup() ped version of the socket file descriptor, so the file object and socket object may be closed or garbage-collected independently. The socket should be in blocking mode. The optional *mode* and *bufsize* arguments are interpreted the same way as by the built-in file() function; see "Built-in Functions" (section 2.1) for more information.

recv(bufsize[, flags])

Receive data from the socket. The return value is a string representing the data received. The maximum amount of data to be received at once is specified by *bufsize*. See the UNIX manual page *recv*(2) for the

meaning of the optional argument *flags*; it defaults to zero.

recvfrom(bufsize[, flags])

Receive data from the socket. The return value is a pair (*string*, *address*) where *string* is a string representing the data received and *address* is the address of the socket sending the data. The optional *flags* argument has the same meaning as for recv() above. (The format of *address* depends on the address family — see above.)

send(string[, flags])

Send data to the socket. The socket must be connected to a remote socket. The optional *flags* argument has the same meaning as for recv() above. Returns the number of bytes sent. Applications are responsible for checking that all data has been sent; if only some of the data was transmitted, the application needs to attempt delivery of the remaining data.

sendall(string[, flags])

Send data to the socket. The socket must be connected to a remote socket. The optional *flags* argument has the same meaning as for recv() above. Unlike send(), this method continues to send data from *string* until either all data has been sent or an error occurs. None is returned on success. On error, an exception is raised, and there is no way to determine how much data, if any, was successfully sent.

sendto(string[, flags], address)

Send data to the socket. The socket should not be connected to a remote socket, since the destination socket is specified by *address*. The optional *flags* argument has the same meaning as for recv() above. Return the number of bytes sent. (The format of *address* depends on the address family — see above.)

setblocking(flag)

Set blocking or non-blocking mode of the socket: if *flag* is 0, the socket is set to non-blocking, else to blocking mode. Initially all sockets are in blocking mode. In non-blocking mode, if a recv() call doesn't find any data, or if a send() call can't immediately dispose of the data, a error exception is raised; in blocking mode, the calls block until they can proceed. s.setblocking(0) is equivalent to s.settimeout(0); s.setblocking(1) is equivalent to s.settimeout(None).

settimeout(value)

Set a timeout on blocking socket operations. The *value* argument can be a nonnegative float expressing seconds, or None. If a float is given, subsequent socket operations will raise an timeout exception if the timeout period *value* has elapsed before the operation has completed. Setting a timeout of None disables timeouts on socket operations. s.settimeout(0.0) is equivalent to s.setblocking(0); s.settimeout(None) is equivalent to s.setblocking(1). New in version 2.3.

gettimeout()

Returns the timeout in floating seconds associated with socket operations, or None if no timeout is set. This reflects the last call to setblocking() or settimeout(). New in version 2.3.

Some notes on socket blocking and timeouts: A socket object can be in one of three modes: blocking, non-blocking, or timeout. Sockets are always created in blocking mode. In blocking mode, operations block until complete. In non-blocking mode, operations fail (with an error that is unfortunately system-dependent) if they cannot be completed immediately. In timeout mode, operations fail if they cannot be completed within the timeout specified for the socket. The setblocking() method is simply a shorthand for certain settimeout() calls.

Timeout mode internally sets the socket in non-blocking mode. The blocking and timeout modes are shared between file descriptors and socket objects that refer to the same network endpoint. A consequence of this is that file objects returned by the makefile() method should only be used when the socket is in blocking mode; in timeout or non-blocking mode file operations that cannot be completed immediately will fail.

Note that the connect() operation is subject to the timeout setting, and in general it is recommended to call settimeout() before calling connect().

setsockopt(level, optname, value)

Set the value of the given socket option (see the UNIX manual page *setsockopt*(2)). The needed symbolic constants are defined in the socket module (SO_* etc.). The value can be an integer or a string representing a buffer. In the latter case it is up to the caller to ensure that the string contains the proper bits (see the optional built-in module struct for a way to encode C structures as strings).

shutdown(how)

Shut down one or both halves of the connection. If *how* is SHUT_RD, further receives are disallowed. If *how* is SHUT_RDWR, further sends are disallowed. If *how* is SHUT_RDWR, further sends and receives are disallowed.

Note that there are no methods read() or write(); use recv() and send() without flags argument instead.

7.2.2 SSL Objects

SSL objects have the following methods.

```
write(s)
```

Writes the string s to the on the object's SSL connection. The return value is the number of bytes written.

```
read([n])
```

If *n* is provided, read *n* bytes from the SSL connection, otherwise read until EOF. The return value is a string of the bytes read.

7.2.3 Example

Here are four minimal example programs using the TCP/IP protocol: a server that echoes all data that it receives back (servicing only one client), and a client using it. Note that a server must perform the sequence <code>socket()</code>, <code>bind()</code>, <code>listen()</code>, <code>accept()</code> (possibly repeating the <code>accept()</code> to service more than one client), while a client only needs the sequence <code>socket()</code>, <code>connect()</code>. Also note that the server does not <code>send()/recv()</code> on the socket it is listening on but on the new socket returned by <code>accept()</code>.

The first two examples support IPv4 only.

```
# Echo server program
import socket
HOST = ''
                          # Symbolic name meaning the local host
PORT = 50007
                          # Arbitrary non-privileged port
s = socket.socket(socket.AF_INET, socket.SOCK_STREAM)
s.bind((HOST, PORT))
s.listen(1)
conn, addr = s.accept()
print 'Connected by', addr
while 1:
    data = conn.recv(1024)
    if not data: break
    conn.send(data)
conn.close()
# Echo client program
import socket
HOST = 'daring.cwi.nl'
                          # The remote host
                          # The same port as used by the server
PORT = 50007
s = socket.socket(socket.AF_INET, socket.SOCK_STREAM)
s.connect((HOST, PORT))
s.send('Hello, world')
data = s.recv(1024)
s.close()
print 'Received', repr(data)
```

The next two examples are identical to the above two, but support both IPv4 and IPv6. The server side will listen to the first address family available (it should listen to both instead). On most of IPv6-ready systems, IPv6 will take precedence and the server may not accept IPv4 traffic. The client side will try to connect to the all addresses returned as a result of the name resolution, and sends traffic to the first one connected successfully.

```
# Echo server program
import socket
import sys
HOST = ''
                          # Symbolic name meaning the local host
PORT = 50007
                          # Arbitrary non-privileged port
s = None
for res in socket.getaddrinfo(HOST, PORT, socket.AF_UNSPEC, socket.SOCK_STREAM, 0, socket.AI
    af, socktype, proto, canonname, sa = res
s = socket.socket(af, socktype, proto)
    except socket.error, msg:
s = None
continue
    try:
s.bind(sa)
s.listen(1)
    except socket.error, msg:
s.close()
s = None
continue
    break
if s is None:
    print 'could not open socket'
    sys.exit(1)
conn, addr = s.accept()
print 'Connected by', addr
while 1:
    data = conn.recv(1024)
    if not data: break
    conn.send(data)
conn.close()
# Echo client program
import socket
import sys
HOST = 'daring.cwi.nl'
                          # The remote host
PORT = 50007
                          # The same port as used by the server
s = None
for res in socket.getaddrinfo(HOST, PORT, socket.AF_UNSPEC, socket.SOCK_STREAM):
    af, socktype, proto, canonname, sa = res
    try:
s = socket.socket(af, socktype, proto)
    except socket.error, msg:
s = None
continue
    try:
s.connect(sa)
    except socket.error, msg:
s.close()
s = None
continue
   break
if s is None:
    print 'could not open socket'
    sys.exit(1)
s.send('Hello, world')
data = s.recv(1024)
s.close()
print 'Received', repr(data)
```

7.3 select — Waiting for I/O completion

This module provides access to the select() and poll() functions available in most operating systems. Note that on Windows, it only works for sockets; on other operating systems, it also works for other file types (in particular, on UNIX, it works on pipes). It cannot be used on regular files to determine whether a file has grown since it was last read.

The module defines the following:

exception error

The exception raised when an error occurs. The accompanying value is a pair containing the numeric error code from errno and the corresponding string, as would be printed by the C function perror ().

poll()

(Not supported by all operating systems.) Returns a polling object, which supports registering and unregistering file descriptors, and then polling them for I/O events; see section 7.3.1 below for the methods supported by polling objects.

select(iwtd, owtd, ewtd[, timeout])

This is a straightforward interface to the UNIX select() system call. The first three arguments are sequences of 'waitable objects': either integers representing file descriptors or objects with a parameterless method named fileno() returning such an integer. The three sequences of waitable objects are for input, output and 'exceptional conditions', respectively. Empty sequences are allowed, but acceptance of three empty sequences is platform-dependent. (It is known to work on UNIX but not on Windows.) The optional timeout argument specifies a time-out as a floating point number in seconds. When the timeout argument is omitted the function blocks until at least one file descriptor is ready. A time-out value of zero specifies a poll and never blocks.

The return value is a triple of lists of objects that are ready: subsets of the first three arguments. When the time-out is reached without a file descriptor becoming ready, three empty lists are returned.

Among the acceptable object types in the sequences are Python file objects (e.g. sys.stdin, or objects returned by open() or os.popen()), socket objects returned by socket.socket(). You may also define a *wrapper* class yourself, as long as it has an appropriate fileno() method (that really returns a file descriptor, not just a random integer). **Note:** File objects on Windows are not acceptable, but sockets are. On Windows, the underlying select() function is provided by the WinSock library, and does not handle file descriptors that don't originate from WinSock.

7.3.1 Polling Objects

The poll() system call, supported on most UNIX systems, provides better scalability for network servers that service many, many clients at the same time. poll() scales better because the system call only requires listing the file descriptors of interest, while select() builds a bitmap, turns on bits for the fds of interest, and then afterward the whole bitmap has to be linearly scanned again. select() is O(highest file descriptor), while poll() is O(number of file descriptors).

register(fd[, eventmask])

Register a file descriptor with the polling object. Future calls to the poll() method will then check whether the file descriptor has any pending I/O events. *fd* can be either an integer, or an object with a fileno() method that returns an integer. File objects implement fileno(), so they can also be used as the argument.

eventmask is an optional bitmask describing the type of events you want to check for, and can be a combination of the constants POLLIN, POLLPRI, and POLLOUT, described in the table below. If not specified, the default value used will check for all 3 types of events.

Constant	Meaning
POLLIN	There is data to read
POLLPRI	There is urgent data to read
POLLOUT	Ready for output: writing will not block
POLLERR	Error condition of some sort
POLLHUP	Hung up
POLLNVAL	Invalid request: descriptor not open

Registering a file descriptor that's already registered is not an error, and has the same effect as registering the descriptor exactly once.

unregister(fd)

Remove a file descriptor being tracked by a polling object. Just like the register() method, fd can be an integer or an object with a fileno() method that returns an integer.

Attempting to remove a file descriptor that was never registered causes a KeyError exception to be raised.

poll([timeout])

Polls the set of registered file descriptors, and returns a possibly-empty list containing (fd, event) 2-tuples for the descriptors that have events or errors to report. fd is the file descriptor, and event is a bitmask with bits set for the reported events for that descriptor — POLLIN for waiting input, POLLOUT to indicate that the descriptor can be written to, and so forth. An empty list indicates that the call timed out and no file descriptors had any events to report. If timeout is given, it specifies the length of time in milliseconds which the system will wait for events before returning. If timeout is omitted, negative, or None, the call will block until there is an event for this poll object.

7.4 thread — Multiple threads of control

This module provides low-level primitives for working with multiple threads (a.k.a. *light-weight processes* or *tasks*) — multiple threads of control sharing their global data space. For synchronization, simple locks (a.k.a. *mutexes* or *binary semaphores*) are provided.

The module is optional. It is supported on Windows, Linux, SGI IRIX, Solaris 2.x, as well as on systems that have a POSIX thread (a.k.a. "pthread") implementation. For systems lacking the thread module, the dummy_thread module is available. It duplicates this module's interface and can be used as a drop-in replacement.

It defines the following constant and functions:

exception error

Raised on thread-specific errors.

LockType

This is the type of lock objects.

start_new_thread(function, args[, kwargs])

Start a new thread and return its identifier. The thread executes the function *function* with the argument list *args* (which must be a tuple). The optional *kwargs* argument specifies a dictionary of keyword arguments. When the function returns, the thread silently exits. When the function terminates with an unhandled exception, a stack trace is printed and then the thread exits (but other threads continue to run).

interrupt_main()

Raise a KeyboardInterrupt in the main thread. A subthread can use this function to interrupt the main thread. New in version 2.3.

exit()

Raise the SystemExit exception. When not caught, this will cause the thread to exit silently.

allocate_lock()

Return a new lock object. Methods of locks are described below. The lock is initially unlocked.

get_ident()

Return the 'thread identifier' of the current thread. This is a nonzero integer. Its value has no direct meaning; it is intended as a magic cookie to be used e.g. to index a dictionary of thread-specific data. Thread

identifiers may be recycled when a thread exits and another thread is created.

Lock objects have the following methods:

acquire([waitflag])

Without the optional argument, this method acquires the lock unconditionally, if necessary waiting until it is released by another thread (only one thread at a time can acquire a lock — that's their reason for existence). If the integer *waitflag* argument is present, the action depends on its value: if it is zero, the lock is only acquired if it can be acquired immediately without waiting, while if it is nonzero, the lock is acquired unconditionally as before. The return value is True if the lock is acquired successfully, False if not.

release()

Releases the lock. The lock must have been acquired earlier, but not necessarily by the same thread.

locked()

Return the status of the lock: True if it has been acquired by some thread, False if not.

Caveats:

- Threads interact strangely with interrupts: the KeyboardInterrupt exception will be received by an arbitrary thread. (When the signal module is available, interrupts always go to the main thread.)
- Calling sys.exit() or raising the SystemExit exception is equivalent to calling exit().
- Not all built-in functions that may block waiting for I/O allow other threads to run. (The most popular ones (time.sleep(), file.read(), select.select()) work as expected.)
- It is not possible to interrupt the acquire() method on a lock the KeyboardInterrupt exception will happen after the lock has been acquired.
- When the main thread exits, it is system defined whether the other threads survive. On SGI IRIX using the
 native thread implementation, they survive. On most other systems, they are killed without executing try
 ... finally clauses or executing object destructors.
- When the main thread exits, it does not do any of its usual cleanup (except that try ... finally clauses are honored), and the standard I/O files are not flushed.

7.5 threading — Higher-level threading interface

This module constructs higher-level threading interfaces on top of the lower level thread module.

The dummy_threading module is provided for situations where threading cannot be used because thread is missing.

This module defines the following functions and objects:

activeCount()

Return the number of currently active $\tt Thread$ objects. The returned count is equal to the length of the list returned by $\tt enumerate()$. A function that returns the number of currently active threads.

Condition()

A factory function that returns a new condition variable object. A condition variable allows one or more threads to wait until they are notified by another thread.

currentThread()

Return the current Thread object, corresponding to the caller's thread of control. If the caller's thread of control was not created through the threading module, a dummy thread object with limited functionality is returned.

enumerate()

Return a list of all currently active Thread objects. The list includes daemonic threads, dummy thread objects created by currentThread(), and the main thread. It excludes terminated threads and threads that have not yet been started.

Event()

A factory function that returns a new event object. An event manages a flag that can be set to true with the set() method and reset to false with the clear() method. The wait() method blocks until the flag is true.

class local

A class that represents thread-local data. Thread-local data are data whose values are thread specific. To manage thread-local data, just create an instance of local (or a subclass) and store attributes on it:

```
mydata = threading.local()
mydata.x = 1
```

The instance's values will be different for separate threads.

For more details and extensive examples, see the documentation string of the _threading_local module

New in version 2.4.

Lock()

A factory function that returns a new primitive lock object. Once a thread has acquired it, subsequent attempts to acquire it block, until it is released; any thread may release it.

RLock()

A factory function that returns a new reentrant lock object. A reentrant lock must be released by the thread that acquired it. Once a thread has acquired a reentrant lock, the same thread may acquire it again without blocking; the thread must release it once for each time it has acquired it.

Semaphore([value])

A factory function that returns a new semaphore object. A semaphore manages a counter representing the number of release() calls minus the number of acquire() calls, plus an initial value. The acquire() method blocks if necessary until it can return without making the counter negative. If not given, *value* defaults to 1.

BoundedSemaphore([value])

A factory function that returns a new bounded semaphore object. A bounded semaphore checks to make sure its current value doesn't exceed its initial value. If it does, ValueError is raised. In most situations semaphores are used to guard resources with limited capacity. If the semaphore is released too many times it's a sign of a bug. If not given, *value* defaults to 1.

class Thread

A class that represents a thread of control. This class can be safely subclassed in a limited fashion.

class Timer

A thread that executes a function after a specified interval has passed.

settrace(func)

Set a trace function for all threads started from the threading module. The *func* will be passed to sys.settrace() for each thread, before its run() method is called. New in version 2.3.

setprofile(func)

Set a profile function for all threads started from the threading module. The *func* will be passed to sys.setprofile() for each thread, before its run() method is called. New in version 2.3.

Detailed interfaces for the objects are documented below.

The design of this module is loosely based on Java's threading model. However, where Java makes locks and condition variables basic behavior of every object, they are separate objects in Python. Python's Thread class supports a subset of the behavior of Java's Thread class; currently, there are no priorities, no thread groups, and threads cannot be destroyed, stopped, suspended, resumed, or interrupted. The static methods of Java's Thread class, when implemented, are mapped to module-level functions.

All of the methods described below are executed atomically.

7.5.1 Lock Objects

A primitive lock is a synchronization primitive that is not owned by a particular thread when locked. In Python, it is currently the lowest level synchronization primitive available, implemented directly by the thread extension module.

A primitive lock is in one of two states, "locked" or "unlocked". It is created in the unlocked state. It has two basic methods, acquire() and release(). When the state is unlocked, acquire() changes the state to locked and returns immediately. When the state is locked, acquire() blocks until a call to release() in another thread changes it to unlocked, then the acquire() call resets it to locked and returns. The release() method should only be called in the locked state; it changes the state to unlocked and returns immediately. When more than one thread is blocked in acquire() waiting for the state to turn to unlocked, only one thread proceeds when a release() call resets the state to unlocked; which one of the waiting threads proceeds is not defined, and may vary across implementations.

All methods are executed atomically.

```
acquire([blocking = 1])
```

Acquire a lock, blocking or non-blocking.

When invoked without arguments, block until the lock is unlocked, then set it to locked, and return true.

When invoked with the *blocking* argument set to true, do the same thing as when called without arguments, and return true.

When invoked with the *blocking* argument set to false, do not block. If a call without an argument would block, return false immediately; otherwise, do the same thing as when called without arguments, and return true.

release()

Release a lock.

When the lock is locked, reset it to unlocked, and return. If any other threads are blocked waiting for the lock to become unlocked, allow exactly one of them to proceed.

Do not call this method when the lock is unlocked.

There is no return value.

7.5.2 RLock Objects

A reentrant lock is a synchronization primitive that may be acquired multiple times by the same thread. Internally, it uses the concepts of "owning thread" and "recursion level" in addition to the locked/unlocked state used by primitive locks. In the locked state, some thread owns the lock; in the unlocked state, no thread owns it.

To lock the lock, a thread calls its acquire() method; this returns once the thread owns the lock. To unlock the lock, a thread calls its release() method. acquire()/release() call pairs may be nested; only the final release() (the release() of the outermost pair) resets the lock to unlocked and allows another thread blocked in acquire() to proceed.

```
acquire([blocking = 1])
```

Acquire a lock, blocking or non-blocking.

When invoked without arguments: if this thread already owns the lock, increment the recursion level by one, and return immediately. Otherwise, if another thread owns the lock, block until the lock is unlocked. Once the lock is unlocked (not owned by any thread), then grab ownership, set the recursion level to one, and return. If more than one thread is blocked waiting until the lock is unlocked, only one at a time will be able to grab ownership of the lock. There is no return value in this case.

When invoked with the *blocking* argument set to true, do the same thing as when called without arguments, and return true.

When invoked with the *blocking* argument set to false, do not block. If a call without an argument would block, return false immediately; otherwise, do the same thing as when called without arguments, and return true.

release()

Release a lock, decrementing the recursion level. If after the decrement it is zero, reset the lock to unlocked (not owned by any thread), and if any other threads are blocked waiting for the lock to become unlocked, allow exactly one of them to proceed. If after the decrement the recursion level is still nonzero, the lock remains locked and owned by the calling thread.

Only call this method when the calling thread owns the lock. Do not call this method when the lock is unlocked.

There is no return value.

7.5.3 Condition Objects

A condition variable is always associated with some kind of lock; this can be passed in or one will be created by default. (Passing one in is useful when several condition variables must share the same lock.)

A condition variable has acquire() and release() methods that call the corresponding methods of the associated lock. It also has a wait() method, and notify() and notifyAll() methods. These three must only be called when the calling thread has acquired the lock.

The wait() method releases the lock, and then blocks until it is awakened by a notify() or notifyAll() call for the same condition variable in another thread. Once awakened, it re-acquires the lock and returns. It is also possible to specify a timeout.

The notify() method wakes up one of the threads waiting for the condition variable, if any are waiting. The notifyAll() method wakes up all threads waiting for the condition variable.

Note: the notify() and notifyAll() methods don't release the lock; this means that the thread or threads awakened will not return from their wait() call immediately, but only when the thread that called notify() or notifyAll() finally relinquishes ownership of the lock.

Tip: the typical programming style using condition variables uses the lock to synchronize access to some shared state; threads that are interested in a particular change of state call wait()

Release the underlying lock. This method calls the corresponding method on the underlying lock; there is no return value.

wait([timeout])

Wait until notified or until a timeout occurs. This must only be called when the calling thread has acquired the lock.

This method releases the underlying lock, and then blocks until it is awakened by a notify() or notifyAll() call for the same condition variable in another thread, or until the optional timeout occurs. Once awakened or timed out, it re-acquires the lock and returns.

When the *timeout* argument is present and not None, it should be a floating point number specifying a timeout for the operation in seconds (or fractions thereof).

When the underlying lock is an RLock, it is not released using its release() method, since this may not actually unlock the lock when it was acquired multiple times recursively. Instead, an internal interface of the RLock class is used, which really unlocks it even when it has been recursively acquired several times. Another internal interface is then used to restore the recursion level when the lock is reacquired.

notify()

Wake up a thread waiting on this condition, if any. This must only be called when the calling thread has acquired the lock.

This method wakes up one of the threads waiting for the condition variable, if any are waiting; it is a no-op if no threads are waiting.

The current implementation wakes up exactly one thread, if any are waiting. However, it's not safe to rely on this behavior. A future, optimized implementation may occasionally wake up more than one thread.

Note: the awakened thread does not actually return from its wait() call until it can reacquire the lock. Since notify() does not release the lock, its caller should.

notifyAll()

Wake up all threads waiting on this condition. This method acts like notify(), but wakes up all waiting threads instead of one.

7.5.4 Semaphore Objects

This is one of the oldest synchronization primitives in the history of computer science, invented by the early Dutch computer scientist Edsger W. Dijkstra (he used P() and V() instead of acquire() and release()).

A semaphore manages an internal counter which is decremented by each acquire() call and incremented by each release() call. The counter can never go below zero; when acquire() finds that it is zero, it blocks, waiting until some other thread calls release().

class Semaphore ([value])

The optional argument gives the initial value for the internal counter; it defaults to 1.

acquire([blocking])

Acquire a semaphore.

When invoked without arguments: if the internal counter is larger than zero on entry, decrement it by one and return immediately. If it is zero on entry, block, waiting until some other thread has called release() to make it larger than zero. This is done with proper interlocking so that if multiple acquire() calls are blocked, release() will wake exactly one of them up. The implementation may pick one at random, so the order in which blocked threads are awakened should not be relied on. There is no return value in this case.

When invoked with *blocking* set to true, do the same thing as when called without arguments, and return true.

When invoked with *blocking* set to false, do not block. If a call without an argument would block, return false immediately; otherwise, do the same thing as when called without arguments, and return true.

release()

Release a semaphore, incrementing the internal counter by one. When it was zero on entry and another thread is waiting for it to become larger than zero again, wake up that thread.

Semaphore Example

Semaphores are often used to guard resources with limited capacity, for example, a database server. In any situation where the size of the resource size is fixed, you should use a bounded semaphore. Before spawning any worker threads, your main thread would initialize the semaphore:

```
maxconnections = 5
...
pool_sema = BoundedSemaphore(value=maxconnections)
```

Once spawned, worker threads call the semaphore's acquire and release methods when they need to connect to the server:

```
pool_sema.acquire()
conn = connectdb()
... use connection ...
conn.close()
pool_sema.release()
```

The use of a bounded semaphore reduces the chance that a programming error which causes the semaphore to be released more than it's acquired will go undetected.

7.5.5 Event Objects

This is one of the simplest mechanisms for communication between threads: one thread signals an event and other threads wait for it.

An event object manages an internal flag that can be set to true with the set() method and reset to false with the clear() method. The wait() method blocks until the flag is true.

class Event()

The internal flag is initially false.

isSet()

Return true if and only if the internal flag is true.

set()

Set the internal flag to true. All threads waiting for it to become true are awakened. Threads that call wait() once the flag is true will not block at all.

clear()

Reset the internal flag to false. Subsequently, threads calling wait () will block until set() is called to set the internal flag to true again.

```
wait([timeout])
```

Block until the internal flag is true. If the internal flag is true on entry, return immediately. Otherwise, block until another thread calls set () to set the flag to true, or until the optional timeout occurs.

When the timeout argument is present and not None, it should be a floating point number specifying a timeout for the operation in seconds (or fractions thereof).

7.5.6 Thread Objects

This class represents an activity that is run in a separate thread of control. There are two ways to specify the activity: by passing a callable object to the constructor, or by overriding the run() method in a subclass. No other methods (except for the constructor) should be overridden in a subclass. In other words, *only* override the <code>__init__()</code> and run() methods of this class.

Once a thread object is created, its activity must be started by calling the thread's start() method. This invokes the run() method in a separate thread of control.

Once the thread's activity is started, the thread is considered 'alive' and 'active' (these concepts are almost, but not quite exactly, the same; their definition is intentionally somewhat vague). It stops being alive and active when its run() method terminates – either normally, or by raising an unhandled exception. The isAlive() method tests whether the thread is alive.

Other threads can call a thread's join() method. This blocks the calling thread until the thread whose join() method is called is terminated.

A thread has a name. The name can be passed to the constructor, set with the setName() method, and retrieved with the getName() method.

A thread can be flagged as a "daemon thread". The significance of this flag is that the entire Python program exits when only daemon threads are left. The initial value is inherited from the creating thread. The flag can be set with the setDaemon() method and retrieved with the isDaemon() method.

There is a "main thread" object; this corresponds to the initial thread of control in the Python program. It is not a daemon thread.

There is the possibility that "dummy thread objects" are created. These are thread objects corresponding to "alien threads". These are threads of control started outside the threading module, such as directly from C code. Dummy thread objects have limited functionality; they are always considered alive, active, and daemonic, and cannot be <code>join()</code> ed. They are never deleted, since it is impossible to detect the termination of alien threads.

```
class Thread(group=None, target=None, name=None, args=(), kwargs={})
```

This constructor should always be called with keyword arguments. Arguments are:

group should be None; reserved for future extension when a ThreadGroup class is implemented.

target is the callable object to be invoked by the run() method. Defaults to None, meaning nothing is called.

name is the thread name. By default, a unique name is constructed of the form "Thread-N" where N is a small decimal number.

args is the argument tuple for the target invocation. Defaults to ().

kwargs is a dictionary of keyword arguments for the target invocation. Defaults to {}.

If the subclass overrides the constructor, it must make sure to invoke the base class constructor (Thread.__init__()) before doing anything else to the thread.

start()

Start the thread's activity.

This must be called at most once per thread object. It arranges for the object's run() method to be invoked in a separate thread of control.

run()

Method representing the thread's activity.

You may override this method in a subclass. The standard run() method invokes the callable object passed to the object's constructor as the target argument, if any, with sequential and keyword arguments taken from the args and kwargs arguments, respectively.

join([timeout])

Wait until the thread terminates. This blocks the calling thread until the thread whose join() method is called terminates – either normally or through an unhandled exception – or until the optional timeout occurs.

When the *timeout* argument is present and not None, it should be a floating point number specifying a timeout for the operation in seconds (or fractions thereof). As join() always returns None, you must call isAlive() to decide whether a timeout happened.

When the timeout argument is not present or None, the operation will block until the thread terminates.

A thread can be join() ed many times.

A thread cannot join itself because this would cause a deadlock.

It is an error to attempt to join() a thread before it has been started.

getName()

Return the thread's name.

setName(name)

Set the thread's name.

The name is a string used for identification purposes only. It has no semantics. Multiple threads may be given the same name. The initial name is set by the constructor.

isAlive()

Return whether the thread is alive.

Roughly, a thread is alive from the moment the start() method returns until its run() method terminates.

isDaemon()

Return the thread's daemon flag.

setDaemon(daemonic)

Set the thread's daemon flag to the Boolean value daemonic. This must be called before start () is called.

The initial value is inherited from the creating thread.

The entire Python program exits when no active non-daemon threads are left.

7.5.7 Timer Objects

This class represents an action that should be run only after a certain amount of time has passed — a timer. Timer is a subclass of Thread and as such also functions as an example of creating custom threads.

Timers are started, as with threads, by calling their start() method. The timer can be stopped (before its action has begun) by calling the cancel() method. The interval the timer will wait before executing its action may not be exactly the same as the interval specified by the user.

For example:

```
def hello():
    print "hello, world"

t = Timer(30.0, hello)
t.start() # after 30 seconds, "hello, world" will be printed
```

```
class Timer (interval, function, args=[], kwargs={})
```

Create a timer that will run *function* with arguments *args* and keyword arguments *kwargs*, after *interval* seconds have passed.

cancel()

Stop the timer, and cancel the execution of the timer's action. This will only work if the timer is still in its waiting stage.

7.6 dummy_thread — Drop-in replacement for the thread module

This module provides a duplicate interface to the thread module. It is meant to be imported when the thread module is not provided on a platform.

Suggested usage is:

```
try:
    import thread as _thread
except ImportError:
    import dummy_thread as _thread
```

Be careful to not use this module where deadlock might occur from a thread being created that blocks waiting for another thread to be created. This often occurs with blocking I/O.

7.7 dummy_threading — Drop-in replacement for the threading module

This module provides a duplicate interface to the threading module. It is meant to be imported when the thread module is not provided on a platform.

Suggested usage is:

```
try:
    import threading as _threading
except ImportError:
    import dummy_threading as _threading
```

Be careful to not use this module where deadlock might occur from a thread being created that blocks waiting for another thread to be created. This often occurs with blocking I/O.

7.8 Queue — A synchronized queue class

The Queue module implements a multi-producer, multi-consumer FIFO queue. It is especially useful in threads programming when information must be exchanged safely between multiple threads. The Queue class in this module implements all the required locking semantics. It depends on the availability of thread support in Python.

The Queue module defines the following class and exception:

class Queue (maxsize)

Constructor for the class. *maxsize* is an integer that sets the upperbound limit on the number of items that can be placed in the queue. Insertion will block once this size has been reached, until queue items are consumed. If *maxsize* is less than or equal to zero, the queue size is infinite.

exception Empty

Exception raised when non-blocking get() (or get_nowait()) is called on a Queue object which is empty.

exception Full

Exception raised when non-blocking put() (or put_nowait()) is called on a Queue object which is full.

7.8.1 Queue Objects

Class Queue implements queue objects and has the methods described below. This class can be derived from in order to implement other queue organizations (e.g. stack) but the inheritable interface is not described here. See the source code for details. The public methods are:

qsize()

Return the approximate size of the queue. Because of multithreading semantics, this number is not reliable.

empty(

Return True if the queue is empty, False otherwise. Because of multithreading semantics, this is not reliable.

full()

Return True if the queue is full, False otherwise. Because of multithreading semantics, this is not reliable.

```
put(item[, block[, timeout]])
```

Put *item* into the queue. If optional args *block* is true and *timeout* is None (the default), block if necessary until a free slot is available. If *timeout* is a positive number, it blocks at most *timeout* seconds and raises the Full exception if no free slot was available within that time. Otherwise (*block* is false), put an item on the queue if a free slot is immediately available, else raise the Full exception (*timeout* is ignored in that case).

New in version 2.3: the timeout parameter.

```
put_nowait(item)
```

Equivalent to put (item, False).

```
get([block[, timeout]])
```

Remove and return an item from the queue. If optional args *block* is true and *timeout* is None (the default), block if necessary until an item is available. If *timeout* is a positive number, it blocks at most *timeout* seconds and raises the Empty exception if no item was available within that time. Otherwise (*block* is false), return an item if one is immediately available, else raise the Empty exception (*timeout* is ignored in that case).

New in version 2.3: the timeout parameter.

```
get_nowait()
```

Equivalent to get (False).

7.9 mmap — Memory-mapped file support

Memory-mapped file objects behave like both strings and like file objects. Unlike normal string objects, however, these are mutable. You can use mmap objects in most places where strings are expected; for example, you can use the re module to search through a memory-mapped file. Since they're mutable, you can change a single character by doing obj[index] = 'a', or change a substring by assigning to a slice: obj[i1:i2] = '...'. You can also read and write data starting at the current file position, and seek() through the file to different positions.

A memory-mapped file is created by the mmap() function, which is different on UNIX and on Windows. In either case you must provide a file descriptor for a file opened for update. If you wish to map an existing Python file object, use its fileno() method to obtain the correct value for the *fileno* parameter. Otherwise, you can open the file using the os.open() function, which returns a file descriptor directly (the file still needs to be closed when done).

For both the UNIX and Windows versions of the function, *access* may be specified as an optional keyword parameter. *access* accepts one of three values: ACCESS_READ, ACCESS_WRITE, or ACCESS_COPY to specify readonly, write-through or copy-on-write memory respectively. *access* can be used on both UNIX and Windows. If *access* is not specified, Windows mmap returns a write-through mapping. The initial memory values for all three access types are taken from the specified file. Assignment to an ACCESS_READ memory map raises a TypeError exception. Assignment to an ACCESS_WRITE memory map affects both memory and the underlying file. Assignment to an ACCESS_COPY memory map affects memory but does not update the underlying file

```
mmap (fileno, length[, tagname[, access]])
```

(Windows version) Maps *length* bytes from the file specified by the file handle *fileno*, and returns a mmap object. If *length* is larger than the current size of the file, the file is extended to contain *length* bytes. If *length* is 0, the maximum length of the map is the current size of the file, except that if the file is empty Windows raises an exception (you cannot create an empty mapping on Windows).

tagname, if specified and not None, is a string giving a tag name for the mapping. Windows allows you to have many different mappings against the same file. If you specify the name of an existing tag, that tag is opened, otherwise a new tag of this name is created. If this parameter is omitted or None, the mapping is created without a name. Avoiding the use of the tag parameter will assist in keeping your code portable between UNIX and Windows.

```
mmap(fileno, length[, flags[, prot[, access]]])
```

(UNIX **version**) Maps *length* bytes from the file specified by the file descriptor *fileno*, and returns a mmap object.

flags specifies the nature of the mapping. MAP_PRIVATE creates a private copy-on-write mapping, so

changes to the contents of the mmap object will be private to this process, and MAP_SHARED creates a mapping that's shared with all other processes mapping the same areas of the file. The default value is MAP_SHARED.

prot, if specified, gives the desired memory protection; the two most useful values are PROT_READ
and PROT_WRITE, to specify that the pages may be read or written. prot defaults to PROT_READ |
PROT_WRITE.

access may be specified in lieu of flags and prot as an optional keyword parameter. It is an error to specify both flags, prot and access. See the description of access above for information on how to use this parameter.

Memory-mapped file objects support the following methods:

close()

Close the file. Subsequent calls to other methods of the object will result in an exception being raised.

find(string[, start])

Returns the lowest index in the object where the substring *string* is found. Returns -1 on failure. *start* is the index at which the search begins, and defaults to zero.

flush([offset, size])

Flushes changes made to the in-memory copy of a file back to disk. Without use of this call there is no guarantee that changes are written back before the object is destroyed. If *offset* and *size* are specified, only changes to the given range of bytes will be flushed to disk; otherwise, the whole extent of the mapping is flushed.

move(dest, src, count)

Copy the *count* bytes starting at offset *src* to the destination index *dest*. If the mmap was created with ACCESS_READ, then calls to move will throw a TypeError exception.

read(num)

Return a string containing up to *num* bytes starting from the current file position; the file position is updated to point after the bytes that were returned.

read_byte()

Returns a string of length 1 containing the character at the current file position, and advances the file position by 1.

readline()

Returns a single line, starting at the current file position and up to the next newline.

resize(newsize)

Resizes the map and the underlying file, if any. If the mmap was created with ACCESS_READ or ACCESS_COPY, resizing the map will throw a TypeError exception.

seek(pos[, whence])

Set the file's current position. *whence* argument is optional and defaults to 0 (absolute file positioning); other values are 1 (seek relative to the current position) and 2 (seek relative to the file's end).

size()

Return the length of the file, which can be larger than the size of the memory-mapped area.

tell()

Returns the current position of the file pointer.

write(string)

Write the bytes in *string* into memory at the current position of the file pointer; the file position is updated to point after the bytes that were written. If the mmap was created with ACCESS_READ, then writing to it will throw a TypeError exception.

write_byte(byte)

Write the single-character string *byte* into memory at the current position of the file pointer; the file position is advanced by 1.If the mmap was created with ACCESS_READ, then writing to it will throw a TypeError exception.

7.10 anydbm — Generic access to DBM-style databases

anydbm is a generic interface to variants of the DBM database — dbhash (requires bsddb), gdbm, or dbm. If none of these modules is installed, the slow-but-simple implementation in module dumbdbm will be used.

```
open(filename[, flag[, mode]])
```

Open the database file *filename* and return a corresponding object.

If the database file already exists, the whichdb module is used to determine its type and the appropriate module is used; if it does not exist, the first module listed above that can be imported is used.

The optional *flag* argument can be 'r' to open an existing database for reading only, 'w' to open an existing database for reading and writing, 'c' to create the database if it doesn't exist, or 'n', which will always create a new empty database. If not specified, the default value is 'r'.

The optional *mode* argument is the UNIX mode of the file, used only when the database has to be created. It defaults to octal 0666 (and will be modified by the prevailing umask).

exception error

A tuple containing the exceptions that can be raised by each of the supported modules, with a unique exception anydbm.error as the first item — the latter is used when anydbm.error is raised.

The object returned by open() supports most of the same functionality as dictionaries; keys and their corresponding values can be stored, retrieved, and deleted, and the has_key() and keys() methods are available. Keys and values must always be strings.

See Also:

Module dbhash (section 7.11):

BSD db database interface.

Module dbm (section 8.6):

Standard UNIX database interface.

Module dumbdbm (section 7.14):

Portable implementation of the dbm interface.

Module gdbm (section 8.7):

GNU database interface, based on the dbm interface.

Module shelve (section 3.17):

General object persistence built on top of the Python dbm interface.

Module whichdb (section 7.12):

Utility module used to determine the type of an existing database.

7.11 dbhash — DBM-style interface to the BSD database library

The dbhash module provides a function to open databases using the BSD db library. This module mirrors the interface of the other Python database modules that provide access to DBM-style databases. The bsddb module is required to use dbhash.

This module provides an exception and a function:

exception error

Exception raised on database errors other than KeyError. It is a synonym for bsddb.error.

```
open(path[, flag[, mode]])
```

Open a db database and return the database object. The path argument is the name of the database file.

The *flag* argument can be 'r' (the default), 'w', 'c' (which creates the database if it doesn't exist), or 'n' (which always creates a new empty database). For platforms on which the BSD db library supports locking, an '1' can be appended to indicate that locking should be used.

The optional *mode* parameter is used to indicate the UNIX permission bits that should be set if a new database must be created; this will be masked by the current umask value for the process.

See Also:

```
Module anydbm (section 7.10):
```

Generic interface to dbm-style databases.

```
Module bsddb (section 7.13):
```

Lower-level interface to the BSD db library.

Module whichdb (section 7.12):

Utility module used to determine the type of an existing database.

7.11.1 Database Objects

The database objects returned by open() provide the methods common to all the DBM-style databases and mapping objects. The following methods are available in addition to the standard methods.

first()

It's possible to loop over every key/value pair in the database using this method and the next() method. The traversal is ordered by the databases internal hash values, and won't be sorted by the key values. This method returns the starting key.

last()

Return the last key/value pair in a database traversal. This may be used to begin a reverse-order traversal; see previous().

next()

Returns the key next key/value pair in a database traversal. The following code prints every key in the database db, without having to create a list in memory that contains them all:

```
print db.first()
for i in xrange(1, len(db)):
    print db.next()
```

previous()

Returns the previous key/value pair in a forward-traversal of the database. In conjunction with last(), this may be used to implement a reverse-order traversal.

sync()

This method forces any unwritten data to be written to the disk.

7.12 whichdb — Guess which DBM module created a database

The single function in this module attempts to guess which of the several simple database modules available—dbm, gdbm, or dbhash—should be used to open a given file.

whichdb(filename)

Returns one of the following values: None if the file can't be opened because it's unreadable or doesn't exist; the empty string ('') if the file's format can't be guessed; or a string containing the required module name, such as 'dbm' or 'gdbm'.

7.13 bsddb — Interface to Berkeley DB library

The bsddb module provides an interface to the Berkeley DB library. Users can create hash, btree or record based library files using the appropriate open call. Bsddb objects behave generally like dictionaries. Keys and values must be strings, however, so to use other objects as keys or to store other kinds of objects the user must serialize them somehow, typically using marshal.dumps or pickle.dumps.

Starting with Python 2.3 the bsddb module requires the Berkeley DB library version 3.2 or later (it is known to work with 3.2 through 4.3 at the time of this writing).

See Also:

http://pybsddb.sourceforge.net/

Website with documentation for the new python Berkeley DB interface that closely mirrors the sleepycat object oriented interface provided in Berkeley DB 3 and 4.

http://www.sleepycat.com/

Sleepycat Software produces the modern Berkeley DB library.

The following is a description of the legacy bsddb interface compatible with the old python bsddb module. For details about the more modern Db and DbEnv object oriented interface see the above mentioned pybsddb URL.

The bsddb module defines the following functions that create objects that access the appropriate type of Berkeley DB file. The first two arguments of each function are the same. For ease of portability, only the first two arguments should be used in most instances.

hashopen (filename, flag, mode, bsize, ffactor, nelem, cachesize, hash, lorder]]]]]]]))
Open the hash format file named filename. Files never intended to be preserved on disk may be created by passing None as the filename. The optional flag identifies the mode used to open the file. It may be 'r' (read only), 'w' (read-write), 'c' (read-write - create if necessary; the default) or 'n' (read-write - truncate to zero length). The other arguments are rarely used and are just passed to the low-level dbopen() function. Consult the Berkeley DB documentation for their use and interpretation.

btopen (filename [, flag [, mode [, btflags [, cachesize [, maxkeypage [, minkeypage [, pgsize [, lorder]]]]]]]]]
Open the btree format file named filename. Files never intended to be preserved on disk may be created by

passing None as the *filename*. The optional *flag* identifies the mode used to open the file. It may be 'r' (read only), 'w' (read-write), 'c' (read-write - create if necessary; the default) or 'n' (read-write - truncate to zero length). The other arguments are rarely used and are just passed to the low-level dbopen function. Consult the Berkeley DB documentation for their use and interpretation.

rnopen (filename [, flag [, mode [, rnflags [, cachesize [, pgsize [, lorder [, reclen [, bval [, bfname]]]]]]]]]])) Open a DB record format file named filename. Files never intended to be preserved on disk may be created by passing None as the filename. The optional flag identifies the mode used to open the file. It may be 'r' (read only), 'w' (read-write), 'c' (read-write - create if necessary; the default) or 'n' (read-write - truncate to zero length). The other arguments are rarely used and are just passed to the low-level dbopen function. Consult the Berkeley DB documentation for their use and interpretation.

Note: Beginning in 2.3 some Unix versions of Python may have a bsddb185 module. This is present *only* to allow backwards compatibility with systems which ship with the old Berkeley DB 1.85 database library. The bsddb185 module should never be used directly in new code.

See Also:

Module dbhash (section 7.11):

DBM-style interface to the bsddb

7.13.1 Hash, BTree and Record Objects

Once instantiated, hash, btree and record objects support the same methods as dictionaries. In addition, they support the methods listed below. Changed in version 2.3.1: Added dictionary methods.

close()

Close the underlying file. The object can no longer be accessed. Since there is no open open method for these objects, to open the file again a new bsddb module open function must be called.

keys()

Return the list of keys contained in the DB file. The order of the list is unspecified and should not be relied on. In particular, the order of the list returned is different for different file formats.

has_key(key)

Return 1 if the DB file contains the argument as a key.

set_location(key)

Set the cursor to the item indicated by key and return a tuple containing the key and its value. For binary tree

databases (opened using btopen()), if *key* does not actually exist in the database, the cursor will point to the next item in sorted order and return that key and value. For other databases, KeyError will be raised if *key* is not found in the database.

first()

Set the cursor to the first item in the DB file and return it. The order of keys in the file is unspecified, except in the case of B-Tree databases. This method raises bsddb.error if the database is empty.

next()

Set the cursor to the next item in the DB file and return it. The order of keys in the file is unspecified, except in the case of B-Tree databases.

previous()

Set the cursor to the previous item in the DB file and return it. The order of keys in the file is unspecified, except in the case of B-Tree databases. This is not supported on hashtable databases (those opened with hashopen()).

last()

Set the cursor to the last item in the DB file and return it. The order of keys in the file is unspecified. This is not supported on hashtable databases (those opened with hashopen()). This method raises bsddb.error if the database is empty.

sync()

Synchronize the database on disk.

Example:

```
>>> import bsddb
>>> db = bsddb.btopen('/tmp/spam.db', 'c')
>>> for i in range(10): db['%d'%i] = '%d'% (i*i)
>>> db['3']
191
>>> db.keys()
['0', '1', '2', '3', '4', '5', '6', '7', '8', '9']
>>> db.first()
('0', '0')
>>> db.next()
('1', '1')
>>> db.last()
('9', '81')
>>> db.set_location('2')
('2', '4')
>>> db.previous()
('1', '1')
>>> for k, v in db.iteritems():
        print k, v
0 0
1 1
2 4
3 9
4 16
5 25
6 36
7 49
8 64
9 81
>>> '8' in db
True
>>> db.sync()
```

7.14 dumbdbm — Portable DBM implementation

Note: The dumbdbm module is intended as a last resort fallback for the anydbm module when no more robust module is available. The dumbdbm module is not written for speed and is not nearly as heavily used as the other database modules.

The dumbdbm module provides a persistent dictionary-like interface which is written entirely in Python. Unlike other modules such as gdbm and bsddb, no external library is required. As with other persistent mappings, the keys and values must always be strings.

The module defines the following:

exception error

Raised on dumbdbm-specific errors, such as I/O errors. KeyError is raised for general mapping errors like specifying an incorrect key.

```
open(filename[, flag[, mode]])
```

Open a dumbdbm database and return a dumbdbm object. The *filename* argument is the basename of the database file (without any specific extensions). When a dumbdbm database is created, files with '.dat' and '.dir' extensions are created.

The optional *flag* argument is currently ignored; the database is always opened for update, and will be created if it does not exist.

The optional *mode* argument is the UNIX mode of the file, used only when the database has to be created. It defaults to octal 0666 (and will be modified by the prevailing umask). Changed in version 2.2: The *mode* argument was ignored in earlier versions.

See Also:

Module anydbm (section 7.10):

Generic interface to dbm-style databases.

Module dbm (section 8.6):

Similar interface to the DBM/NDBM library.

Module gdbm (section 8.7):

Similar interface to the GNU GDBM library.

Module shelve (section 3.17):

Persistence module which stores non-string data.

Module whichdb (section 7.12):

Utility module used to determine the type of an existing database.

7.14.1 Dumbdbm Objects

In addition to the methods provided by the UserDict.DictMixin class, dumbdbm objects provide the following methods.

```
svnc()
```

Synchronize the on-disk directory and data files. This method is called by the sync method of Shelve objects.

7.15 zlib — Compression compatible with gzip

For applications that require data compression, the functions in this module allow compression and decompression, using the zlib library. The zlib library has its own home page at http://www.gzip.org/zlib/. There are known incompatibilities between the Python module and versions of the zlib library earlier than 1.1.3; 1.1.3 has a security vulnerability, so we recommend using 1.1.4 or later.

The available exception and functions in this module are:

exception error

Exception raised on compression and decompression errors.

adler32(string[, value])

Computes a Adler-32 checksum of *string*. (An Adler-32 checksum is almost as reliable as a CRC32 but can be computed much more quickly.) If *value* is present, it is used as the starting value of the checksum; otherwise, a fixed default value is used. This allows computing a running checksum over the concatenation of several input strings. The algorithm is not cryptographically strong, and should not be used for authentication or digital signatures. Since the algorithm is designed for use as a checksum algorithm, it is not suitable for use as a general hash algorithm.

compress(string[, level])

Compresses the data in *string*, returning a string contained compressed data. *level* is an integer from 1 to 9 controlling the level of compression; 1 is fastest and produces the least compression, 9 is slowest and produces the most. The default value is 6. Raises the error exception if any error occurs.

compressobj([level])

Returns a compression object, to be used for compressing data streams that won't fit into memory at once. *level* is an integer from 1 to 9 controlling the level of compression; 1 is fastest and produces the least compression, 9 is slowest and produces the most. The default value is 6.

crc32(string[, value])

Computes a CRC (Cyclic Redundancy Check) checksum of *string*. If *value* is present, it is used as the starting value of the checksum; otherwise, a fixed default value is used. This allows computing a running checksum over the concatenation of several input strings. The algorithm is not cryptographically strong, and should not be used for authentication or digital signatures. Since the algorithm is designed for use as a checksum algorithm, it is not suitable for use as a general hash algorithm.

decompress(string[, wbits[, bufsize]])

Decompresses the data in *string*, returning a string containing the uncompressed data. The *wbits* parameter controls the size of the window buffer. If *bufsize* is given, it is used as the initial size of the output buffer. Raises the error exception if any error occurs.

The absolute value of *wbits* is the base two logarithm of the size of the history buffer (the "window size") used when compressing data. Its absolute value should be between 8 and 15 for the most recent versions of the zlib library, larger values resulting in better compression at the expense of greater memory usage. The default value is 15. When *wbits* is negative, the standard **gzip** header is suppressed; this is an undocumented feature of the zlib library, used for compatibility with **unzip**'s compression file format.

bufsize is the initial size of the buffer used to hold decompressed data. If more space is required, the buffer size will be increased as needed, so you don't have to get this value exactly right; tuning it will only save a few calls to malloc(). The default size is 16384.

decompressobj(|wbits|)

Returns a decompression object, to be used for decompressing data streams that won't fit into memory at once. The *wbits* parameter controls the size of the window buffer.

Compression objects support the following methods:

compress(string)

Compress *string*, returning a string containing compressed data for at least part of the data in *string*. This data should be concatenated to the output produced by any preceding calls to the compress() method. Some input may be kept in internal buffers for later processing.

flush([mode])

All pending input is processed, and a string containing the remaining compressed output is returned. *mode* can be selected from the constants Z_SYNC_FLUSH, Z_FULL_FLUSH, or Z_FINISH, defaulting to Z_FINISH. Z_SYNC_FLUSH and Z_FULL_FLUSH allow compressing further strings of data and are used to allow partial error recovery on decompression, while Z_FINISH finishes the compressed stream and prevents compressing any more data. After calling flush() with *mode* set to Z_FINISH, the compress() method cannot be called again; the only realistic action is to delete the object.

Decompression objects support the following methods, and two attributes:

$unused_data$

A string which contains any bytes past the end of the compressed data. That is, this remains " " until the last byte that contains compression data is available. If the whole string turned out to contain compressed data, this is " ", the empty string.

The only way to determine where a string of compressed data ends is by actually decompressing it. This means that when compressed data is contained part of a larger file, you can only find the end of it by reading data and feeding it followed by some non-empty string into a decompression object's decompress method until the unused_data attribute is no longer the empty string.

unconsumed_tail

A string that contains any data that was not consumed by the last decompress call because it exceeded the limit for the uncompressed data buffer. This data has not yet been seen by the zlib machinery, so you must feed it (possibly with further data concatenated to it) back to a subsequent decompress method call in order to get correct output.

decompress(string[, max_length])

Decompress *string*, returning a string containing the uncompressed data corresponding to at least part of the data in *string*. This data should be concatenated to the output produced by any preceding calls to the decompress() method. Some of the input data may be preserved in internal buffers for later processing.

If the optional parameter max_length is supplied then the return value will be no longer than max_length . This may mean that not all of the compressed input can be processed; and unconsumed data will be stored in the attribute unconsumed_tail. This string must be passed to a subsequent call to decompress() if decompression is to continue. If max_length is not supplied then the whole input is decompressed, and unconsumed_tail is an empty string.

flush()

All pending input is processed, and a string containing the remaining uncompressed output is returned. After calling flush(), the decompress() method cannot be called again; the only realistic action is to delete the object.

See Also:

Module gzip (section 7.16):

Reading and writing gzip-format files.

http://www.gzip.org/zlib/

The zlib library home page.

7.16 gzip — Support for gzip files

The data compression provided by the zlib module is compatible with that used by the GNU compression program gzip. Accordingly, the gzip module provides the GzipFile class to read and write gzip-format files, automatically compressing or decompressing the data so it looks like an ordinary file object. Note that additional file formats which can be decompressed by the gzip and gunzip programs, such as those produced by compress and pack, are not supported by this module.

The module defines the following items:

```
class GzipFile([filename[, mode[, compresslevel[, fileobj]]]])
```

Constructor for the GzipFile class, which simulates most of the methods of a file object, with the exception of the readinto() and truncate() methods. At least one of *fileobj* and *filename* must be given a non-trivial value.

The new class instance is based on *fileobj*, which can be a regular file, a StringIO object, or any other object which simulates a file. It defaults to None, in which case *filename* is opened to provide a file object.

When *fileobj* is not None, the *filename* argument is only used to be included in the **gzip** file header, which may includes the original filename of the uncompressed file. It defaults to the filename of *fileobj*, if discernible; otherwise, it defaults to the empty string, and in this case the original filename is not included in the header.

The *mode* argument can be any of 'r', 'rb', 'a', 'ab', 'w', or 'wb', depending on whether the file will be read or written. The default is the mode of *fileobj* if discernible; otherwise, the default is 'rb'. If not

given, the 'b' flag will be added to the mode to ensure the file is opened in binary mode for cross-platform portability.

The *compresslevel* argument is an integer from 1 to 9 controlling the level of compression; 1 is fastest and produces the least compression, and 9 is slowest and produces the most compression. The default is 9.

Calling a GzipFile object's close() method does not close *fileobj*, since you might wish to append more material after the compressed data. This also allows you to pass a StringIO object opened for writing as *fileobj*, and retrieve the resulting memory buffer using the StringIO object's getvalue() method.

```
open(filename[, mode[, compresslevel]])
```

This is a shorthand for GzipFile(filename, mode, compresslevel). The filename argument is required; mode defaults to 'rb' and compresslevel defaults to 9.

See Also:

Module zlib (section 7.15):

The basic data compression module needed to support the gzip file format.

7.17 bz2 — Compression compatible with bzip2

New in version 2.3.

This module provides a comprehensive interface for the bz2 compression library. It implements a complete file interface, one-shot (de)compression functions, and types for sequential (de)compression.

Here is a resume of the features offered by the bz2 module:

- BZ2File class implements a complete file interface, including readline(), readlines(), writelines(), seek(), etc;
- BZ2File class implements emulated seek() support;
- BZ2File class implements universal newline support;
- BZ2File class offers an optimized line iteration using the readahead algorithm borrowed from file objects;
- Sequential (de)compression supported by BZ2Compressor and BZ2Decompressor classes;
- One-shot (de)compression supported by compress() and decompress() functions;
- Thread safety uses individual locking mechanism;
- Complete inline documentation;

7.17.1 (De)compression of files

Handling of compressed files is offered by the BZ2File class.

```
class BZ2File (filename[, mode[, buffering[, compresslevel]]])
```

Open a bz2 file. Mode can be either 'r' or 'w', for reading (default) or writing. When opened for writing, the file will be created if it doesn't exist, and truncated otherwise. If buffering is given, 0 means unbuffered, and larger numbers specify the buffer size; the default is 0. If compresslevel is given, it must be a number between 1 and 9; the default is 9. Add a 'U' to mode to open the file for input with universal newline support. Any line ending in the input file will be seen as a '\n' in Python. Also, a file so opened gains the attribute newlines; the value for this attribute is one of None (no newline read yet), '\r', '\n', '\r'\n' or a tuple containing all the newline types seen. Universal newlines are available only when reading. Instances support iteration in the same way as normal file instances.

close()

Close the file. Sets data attribute closed to true. A closed file cannot be used for further I/O operations. close() may be called more than once without error.

read([size])

Read at most *size* uncompressed bytes, returned as a string. If the *size* argument is negative or omitted, read until EOF is reached.

readline([size])

Return the next line from the file, as a string, retaining newline. A non-negative *size* argument limits the maximum number of bytes to return (an incomplete line may be returned then). Return an empty string at EOF.

readlines([size])

Return a list of lines read. The optional *size* argument, if given, is an approximate bound on the total number of bytes in the lines returned.

xreadlines()

For backward compatibility. BZ2File objects now include the performance optimizations previously implemented in the xreadlines module. **Deprecated since release 2.3.** This exists only for compatibility with the method by this name on file objects, which is deprecated. Use for line in file instead.

seek(offset[, whence])

Move to new file position. Argument *offset* is a byte count. Optional argument *whence* defaults to 0 (offset from start of file, offset should be >= 0); other values are 1 (move relative to current position, positive or negative), and 2 (move relative to end of file, usually negative, although many platforms allow seeking beyond the end of a file).

Note that seeking of bz2 files is emulated, and depending on the parameters the operation may be extremely slow

tell()

Return the current file position, an integer (may be a long integer).

write(data)

Write string *data* to file. Note that due to buffering, close() may be needed before the file on disk reflects the data written.

writelines(sequence_of_strings)

Write the sequence of strings to the file. Note that newlines are not added. The sequence can be any iterable object producing strings. This is equivalent to calling write() for each string.

7.17.2 Sequential (de)compression

Sequential compression and decompression is done using the classes BZ2Compressor and BZ2Decompressor.

class BZ2Compressor([compresslevel])

Create a new compressor object. This object may be used to compress data sequentially. If you want to compress data in one shot, use the compress() function instead. The *compresslevel* parameter, if given, must be a number between 1 and 9; the default is 9.

compress(data)

Provide more data to the compressor object. It will return chunks of compressed data whenever possible. When you've finished providing data to compress, call the flush() method to finish the compression process, and return what is left in internal buffers.

flush()

Finish the compression process and return what is left in internal buffers. You must not use the compressor object after calling this method.

class BZ2Decompressor()

Create a new decompressor object. This object may be used to decompress data sequentially. If you want to decompress data in one shot, use the decompress () function instead.

decompress(data)

Provide more data to the decompressor object. It will return chunks of decompressed data whenever possible. If you try to decompress data after the end of stream is found, EOFError will be raised. If any data

was found after the end of stream, it'll be ignored and saved in unused_data attribute.

7.17.3 One-shot (de)compression

One-shot compression and decompression is provided through the compress() and decompress() functions.

compress(data[, compresslevel])

Compress *data* in one shot. If you want to compress data sequentially, use an instance of BZ2Compressor instead. The *compresslevel* parameter, if given, must be a number between 1 and 9; the default is 9.

decompress(data)

Decompress *data* in one shot. If you want to decompress data sequentially, use an instance of BZ2Decompressor instead.

7.18 zipfile — Work with ZIP archives

New in version 1.6.

The ZIP file format is a common archive and compression standard. This module provides tools to create, read, write, append, and list a ZIP file. Any advanced use of this module will require an understanding of the format, as defined in *PKZIP Application Note*.

This module does not currently handle ZIP files which have appended comments, or multi-disk ZIP files.

The available attributes of this module are:

exception error

The error raised for bad ZIP files.

class ZipFile

The class for reading and writing ZIP files. See "ZipFile Objects" (section 7.18.1) for constructor details.

class PyZipFile

Class for creating ZIP archives containing Python libraries.

class ZipInfo([filename[, date_time]])

Class used to represent information about a member of an archive. Instances of this class are returned by the getinfo() and infolist() methods of ZipFile objects. Most users of the zipfile module will not need to create these, but only use those created by this module. *filename* should be the full name of the archive member, and *date_time* should be a tuple containing six fields which describe the time of the last modification to the file; the fields are described in section 7.18.3, "ZipInfo Objects."

is_zipfile(filename)

Returns True if *filename* is a valid ZIP file based on its magic number, otherwise returns False. This module does not currently handle ZIP files which have appended comments.

ZIP_STORED

The numeric constant for an uncompressed archive member.

ZIP_DEFLATED

The numeric constant for the usual ZIP compression method. This requires the zlib module. No other compression methods are currently supported.

See Also:

PKZIP Application Note

(http://www.pkware.com/appnote.html)

Documentation on the ZIP file format by Phil Katz, the creator of the format and algorithms used.

Info-ZIP Home Page

(http://www.info-zip.org/pub/infozip/)

Information about the Info-ZIP project's ZIP archive programs and development libraries.

7.18.1 ZipFile Objects

class ZipFile(file[, mode[, compression]])

Open a ZIP file, where *file* can be either a path to a file (a string) or a file-like object. The *mode* parameter should be 'r' to read an existing file, 'w' to truncate and write a new file, or 'a' to append to an existing file. For *mode* is 'a' and *file* refers to an existing ZIP file, then additional files are added to it. If *file* does not refer to a ZIP file, then a new ZIP archive is appended to the file. This is meant for adding a ZIP archive to another file, such as 'python.exe'. Using

```
cat myzip.zip >> python.exe
```

also works, and at least **WinZip** can read such files. *compression* is the ZIP compression method to use when writing the archive, and should be ZIP_STORED or ZIP_DEFLATED; unrecognized values will cause RuntimeError to be raised. If ZIP_DEFLATED is specified but the zlib module is not available, RuntimeError is also raised. The default is ZIP_STORED.

close()

Close the archive file. You must call close() before exiting your program or essential records will not be written.

getinfo(name)

Return a ZipInfo object with information about the archive member *name*.

infolist()

Return a list containing a ZipInfo object for each member of the archive. The objects are in the same order as their entries in the actual ZIP file on disk if an existing archive was opened.

namelist()

Return a list of archive members by name.

printdir()

Print a table of contents for the archive to sys.stdout.

read(name)

Return the bytes of the file in the archive. The archive must be open for read or append.

testzip()

Read all the files in the archive and check their CRC's. Return the name of the first bad file, or else return

write(filename[, arcname[, compress_type]])

Write the file named *filename* to the archive, giving it the archive name *arcname* (by default, this will be the same as *filename*). If given, *compress_type* overrides the value given for the *compression* parameter to the constructor for the new entry. The archive must be open with mode 'w' or 'a'.

writestr(zinfo_or_arcname, bytes)

Write the string *bytes* to the archive; *zinfo_or_arcname* is either the file name it will be given in the archive, or a ZipInfo instance. If it's an instance, at least the filename, date, and time must be given. If it's a name, the date and time is set to the current date and time. The archive must be opened with mode 'w' or 'a'.

The following data attribute is also available:

debug

The level of debug output to use. This may be set from 0 (the default, no output) to 3 (the most output). Debugging information is written to sys.stdout.

7.18.2 PyZipFile Objects

The PyZipFile constructor takes the same parameters as the ZipFile constructor. Instances have one method in addition to those of ZipFile objects.

writepy(pathname[, basename])

Search for files '*.py' and add the corresponding file to the archive. The corresponding file is a '*.pyo' file if available, else a '*.pyc' file, compiling if necessary. If the pathname is a file, the filename must end with

'.py', and just the (corresponding '*.py[co]') file is added at the top level (no path information). If it is a directory, and the directory is not a package directory, then all the files '*.py[co]' are added at the top level. If the directory is a package directory, then all '*.py[oc]' are added under the package name as a file path, and if any subdirectories are package directories, all of these are added recursively. *basename* is intended for internal use only. The writepy() method makes archives with file names like this:

7.18.3 ZipInfo Objects

Instances of the ZipInfo class are returned by the getinfo() and infolist() methods of ZipFile objects. Each object stores information about a single member of the ZIP archive.

Instances have the following attributes:

filename

Name of the file in the archive.

date_time

The time and date of the last modification to the archive member. This is a tuple of six values:

Index	Value
0	Year
1	Month (one-based)
2	Day of month (one-based)
3	Hours (zero-based)
4	Minutes (zero-based)
5	Seconds (zero-based)

compress_type

Type of compression for the archive member.

comment

Comment for the individual archive member.

extra

Expansion field data. The *PKZIP Application Note* contains some comments on the internal structure of the data contained in this string.

create_system

System which created ZIP archive.

create_version

PKZIP version which created ZIP archive.

extract_version

PKZIP version needed to extract archive.

reserved

Must be zero.

flag_bits

ZIP flag bits.

volume

Volume number of file header.

internal_attr

Internal attributes.

external_attr

External file attributes.

header offset

Byte offset to the file header.

file_offset

Byte offset to the start of the file data.

CRC

CRC-32 of the uncompressed file.

compress_size

Size of the compressed data.

file_size

Size of the uncompressed file.

7.19 tarfile — Read and write tar archive files

New in version 2.3.

The tarfile module makes it possible to read and create tar archives. Some facts and figures:

- reads and writes gzip and bzip2 compressed archives.
- creates POSIX 1003.1-1990 compliant or GNU tar compatible archives.
- reads GNU tar extensions *longname*, *longlink* and *sparse*.
- stores pathnames of unlimited length using GNU tar extensions.
- handles directories, regular files, hardlinks, symbolic links, fifos, character devices and block devices and is able to acquire and restore file information like timestamp, access permissions and owner.
- can handle tape devices.

Return a TarFile object for the pathname *name*. For detailed information on TarFile objects, see *TarFile Objects* (section 7.19.1).

mode has to be a string of the form 'filemode[:compression]', it defaults to 'r'. Here is a full list of mode combinations:

mode	action
'r'	Open for reading with transparent compression (recommended).
'r:'	Open for reading exclusively without compression.
'r:gz'	Open for reading with gzip compression.
'r:bz2'	Open for reading with bzip2 compression.
'a' or 'a:'	Open for appending with no compression.
'w' or 'w:'	Open for uncompressed writing.
'w:gz'	Open for gzip compressed writing.
'w:bz2'	Open for bzip2 compressed writing.

Note that 'a:gz' or 'a:bz2' is not possible. If *mode* is not suitable to open a certain (compressed) file for reading, ReadError is raised. Use *mode* 'r' to avoid this. If a compression method is not supported, CompressionError is raised.

If *fileobj* is specified, it is used as an alternative to a file object opened for *name*.

For special purposes, there is a second format for <code>mode</code>: 'filemode | [compression]'.open() will return a TarFile object that processes its data as a stream of blocks. No random seeking will be done on the file. If given, <code>fileobj</code> may be any object that has a <code>read()</code> or <code>write()</code> method (depending on the <code>mode</code>). <code>bufsize</code> specifies the blocksize and defaults to 20 * 512 bytes. Use this variant in combination with e.g. <code>sys.stdin</code>, a socket file object or a tape device. However, such a <code>TarFile</code> object is limited in that it does not allow to be accessed randomly, see "Examples" (section 7.19.3). The currently possible modes:

Mode	Action
'r '	Open a <i>stream</i> of uncompressed tar blocks for reading.
'r gz'	Open a gzip compressed <i>stream</i> for reading.
'r bz2'	Open a bzip2 compressed <i>stream</i> for reading.
'w '	Open an uncompressed <i>stream</i> for writing.
'w gz'	Open an gzip compressed <i>stream</i> for writing.
'w bz2'	Open an bzip2 compressed <i>stream</i> for writing.

class TarFile

Class for reading and writing tar archives. Do not use this class directly, better use open() instead. See "TarFile Objects" (section 7.19.1).

is_tarfile(name)

Return True if *name* is a tar archive file, that the tarfile module can read.

class TarFileCompat(filename[, mode[, compression]])

Class for limited access to tar archives with a zipfile-like interface. Please consult the documentation of the zipfile module for more details. *compression* must be one of the following constants:

TAR_PLAIN

Constant for an uncompressed tar archive.

TAR_GZIPPED

Constant for a gzip compressed tar archive.

exception TarError

Base class for all tarfile exceptions.

exception ReadError

Is raised when a tar archive is opened, that either cannot be handled by the tarfile module or is somehow invalid.

exception CompressionError

Is raised when a compression method is not supported or when the data cannot be decoded properly.

exception StreamError

Is raised for the limitations that are typical for stream-like TarFile objects.

exception ExtractError

Is raised for *non-fatal* errors when using extract(), but only if TarFile.errorlevel == 2.

See Also:

Module zipfile (section 7.18):

Documentation of the zipfile standard module.

GNU tar manual, Basic Tar Format

(http://www.gnu.org/software/tar/manual/html_chapter/tar_8.html#SEC134)

Documentation for tar archive files, including GNU tar extensions.

7.19.1 TarFile Objects

The TarFile object provides an interface to a tar archive. A tar archive is a sequence of blocks. An archive member (a stored file) is made up of a header block followed by data blocks. It is possible, to store a file in a tar archive several times. Each archive member is represented by a TarInfo object, see *TarInfo Objects* (section 7.19.2) for details.

class TarFile([name[, mode[, fileobj]]])

Open an (uncompressed) tar archive name. mode is either 'r' to read from an existing archive, 'a' to append data to an existing file or 'w' to create a new file overwriting an existing one. mode defaults to 'r'.

If *fileobj* is given, it is used for reading or writing data. If it can be determined, *mode* is overridden by *fileobj*'s mode.

Note: fileobj is not closed, when TarFile is closed.

open(...)

Alternative constructor. The open() function on module level is actually a shortcut to this classmethod. See section 7.19 for details.

getmember(name)

Return a TarInfo object for member *name*. If *name* can not be found in the archive, KeyError is raised

Note: If a member occurs more than once in the archive, its last occurrence is assumed to be the most up-to-date version.

getmembers()

Return the members of the archive as a list of TarInfo objects. The list has the same order as the members in the archive

getnames()

Return the members as a list of their names. It has the same order as the list returned by getmembers ().

list(verbose=True)

Print a table of contents to sys.stdout. If *verbose* is False, only the names of the members are printed. If it is True, output similar to that of **ls** -**l** is produced.

next()

Return the next member of the archive as a TarInfo object, when TarFile is opened for reading. Return None if there is no more available.

extract(member[, path])

Extract a member from the archive to the current working directory, using its full name. Its file information is extracted as accurately as possible. *member* may be a filename or a TarInfo object. You can specify a different directory using *path*.

extractfile(member)

Extract a member from the archive as a file object. *member* may be a filename or a TarInfo object. If *member* is a regular file, a file-like object is returned. If *member* is a link, a file-like object is constructed from the link's target. If *member* is none of the above, None is returned.

Note: The file-like object is read-only and provides the following methods: read(), readline(), readlines(), seek(), tell().

add(name[, arcname[, recursive]])

Add the file *name* to the archive. *name* may be any type of file (directory, fifo, symbolic link, etc.). If given, *arcname* specifies an alternative name for the file in the archive. Directories are added recursively by default. This can be avoided by setting *recursive* to False; the default is True.

addfile(tarinfo[, fileobj])

Add the TarInfo object *tarinfo* to the archive. If *fileobj* is given, *tarinfo*. size bytes are read from it and added to the archive. You can create TarInfo objects using gettarinfo().

Note: On Windows platforms, *fileobj* should always be opened with mode 'rb' to avoid irritation about the file size.

gettarinfo(|name|, arcname|, fileobj|||)

Create a TarInfo object for either the file *name* or the file object *fileobj* (using os.fstat() on its file descriptor). You can modify some of the TarInfo's attributes before you add it using addfile(). If given, *arcname* specifies an alternative name for the file in the archive.

close()

Close the TarFile. In write mode, two finishing zero blocks are appended to the archive.

posix

If true, create a POSIX 1003.1-1990 compliant archive. GNU extensions are not used, because they are not part of the POSIX standard. This limits the length of filenames to at most 256, link names to 100 characters and the maximum file size to 8 gigabytes. A ValueError is raised if a file exceeds this limit. If false, create a GNU tar compatible archive. It will not be POSIX compliant, but can store files without any of the above restrictions. Changed in version 2.4: posix defaults to False.

dereference

If false, add symbolic and hard links to archive. If true, add the content of the target files to the archive. This has no effect on systems that do not support symbolic links.

ignore_zeros

If false, treat an empty block as the end of the archive. If true, skip empty (and invalid) blocks and try to get as many members as possible. This is only useful for concatenated or damaged archives.

debug=0

To be set from 0 (no debug messages; the default) up to 3 (all debug messages). The messages are written to sys.stderr.

errorlevel

If 0 (the default), all errors are ignored when using extract(). Nevertheless, they appear as error messages in the debug output, when debugging is enabled. If 1, all *fatal* errors are raised as OSError or IOError exceptions. If 2, all *non-fatal* errors are raised as Tarerror exceptions as well.

7.19.2 TarInfo Objects

A TarInfo object represents one member in a TarFile. Aside from storing all required attributes of a file (like file type, size, time, permissions, owner etc.), it provides some useful methods to determine its type. It does *not* contain the file's data itself.

TarInfo objects are returned by TarFile's methods getmember(), getmembers() and gettarinfo().

class TarInfo([name])

Create a TarInfo object.

frombuf()

Create and return a TarInfo object from a string buffer.

tobuf()

Create a string buffer from a TarInfo object.

A Tarinfo object has the following public data attributes:

name

Name of the archive member.

size

Size in bytes.

mtime

Time of last modification.

mode

Permission bits.

type

File type. *type* is usually one of these constants: REGTYPE, AREGTYPE, LNKTYPE, SYMTYPE, DIRTYPE, FIFOTYPE, CONTTYPE, CHRTYPE, BLKTYPE, GNUTYPE_SPARSE. To determine the type of a TarInfo object more conveniently, use the is_*() methods below.

linkname

Name of the target file name, which is only present in TarInfo objects of type LNKTYPE and SYMTYPE.

uid

User ID of the user who originally stored this member.

gid

Group ID of the user who originally stored this member.

uname

User name.

gname

Group name.

A TarInfo object also provides some convenient query methods:

```
isfile()
```

Return True if the Tarinfo object is a regular file.

```
isreg()
```

Same as isfile().

isdir()

Return True if it is a directory.

issym()

Return True if it is a symbolic link.

islnk()

Return True if it is a hard link.

ischr()

Return True if it is a character device.

isblk()

Return True if it is a block device.

isfifo()

Return True if it is a FIFO.

isdev()

Return True if it is one of character device, block device or FIFO.

7.19.3 Examples

How to create an uncompressed tar archive from a list of filenames:

```
import tarfile
tar = tarfile.open("sample.tar", "w")
for name in ["foo", "bar", "quux"]:
    tar.add(name)
tar.close()
```

How to read a gzip compressed tar archive and display some member information:

```
import tarfile
tar = tarfile.open("sample.tar.gz", "r:gz")
for tarinfo in tar:
    print tarinfo.name, "is", tarinfo.size, "bytes in size and is",
    if tarinfo.isreg():
        print "a regular file."
    elif tarinfo.isdir():
        print "a directory."
    else:
        print "something else."
tar.close()
```

How to create a tar archive with faked information:

```
import tarfile
tar = tarfile.open("sample.tar.gz", "w:gz")
for name in namelist:
    tarinfo = tar.gettarinfo(name, "fakeproj-1.0/" + name)
    tarinfo.uid = 123
    tarinfo.gid = 456
    tarinfo.uname = "johndoe"
    tarinfo.gname = "fake"
    tar.addfile(tarinfo, file(name))
tar.close()
```

The *only* way to extract an uncompressed tar stream from sys.stdin:

```
import sys
import tarfile
tar = tarfile.open(mode="r|", fileobj=sys.stdin)
for tarinfo in tar:
    tar.extract(tarinfo)
tar.close()
```

7.20 readline — GNU readline interface

The readline module defines a number of functions used either directly or from the rlcompleter module to facilitate completion and history file read and write from the Python interpreter.

The readline module defines the following functions:

```
parse_and_bind(string)
```

Parse and execute single line of a readline init file.

```
get_line_buffer()
```

Return the current contents of the line buffer.

```
insert_text(string)
```

Insert text into the command line.

```
read_init_file([filename])
```

Parse a readline initialization file. The default filename is the last filename used.

```
read_history_file([filename])
```

Load a readline history file. The default filename is "/.history".

```
write_history_file([filename])
```

Save a readline history file. The default filename is "/.history".

```
clear_history()
```

Clear the current history. (Note: this function is not available if the installed version of GNU readline doesn't support it.) New in version 2.4.

```
get_history_length()
```

Return the desired length of the history file. Negative values imply unlimited history file size.

```
set_history_length(length)
```

Set the number of lines to save in the history file. write_history_file() uses this value to truncate the history file when saving. Negative values imply unlimited history file size.

```
get_current_history_length()
```

Return the number of lines currently in the history. (This is different from get_history_length(), which returns the maximum number of lines that will be written to a history file.) New in version 2.3.

get_history_item(index)

Return the current contents of history item at index. New in version 2.3.

remove_history_item(pos)

Remove history item specified by its position from the history. New in version 2.4.

replace_history_item(pos, line)

Replace history item specified by its position with the given line. New in version 2.4.

redisplay()

Change what's displayed on the screen to reflect the current contents of the line buffer. New in version 2.3.

set_startup_hook([function])

Set or remove the startup_hook function. If *function* is specified, it will be used as the new startup_hook function; if omitted or None, any hook function already installed is removed. The startup_hook function is called with no arguments just before readline prints the first prompt.

set_pre_input_hook([function])

Set or remove the pre_input_hook function. If *function* is specified, it will be used as the new pre_input_hook function; if omitted or None, any hook function already installed is removed. The pre_input_hook function is called with no arguments after the first prompt has been printed and just before readline starts reading input characters.

set_completer([function])

Set or remove the completer function. If *function* is specified, it will be used as the new completer function; if omitted or None, any completer function already installed is removed. The completer function is called as *function* (*text* , *state*) , for *state* in 0, 1, 2, ..., until it returns a non-string value. It should return the next possible completion starting with *text*.

get_completer()

Get the completer function, or None if no completer function has been set. New in version 2.3.

get_begidx()

Get the beginning index of the readline tab-completion scope.

get_endidx()

Get the ending index of the readline tab-completion scope.

set_completer_delims(string)

Set the readline word delimiters for tab-completion.

get_completer_delims()

Get the readline word delimiters for tab-completion.

add_history(line)

Append a line to the history buffer, as if it was the last line typed.

See Also:

Module rlcompleter (section 7.21):

Completion of Python identifiers at the interactive prompt.

7.20.1 Example

The following example demonstrates how to use the readline module's history reading and writing functions to automatically load and save a history file named '.pyhist' from the user's home directory. The code below would normally be executed automatically during interactive sessions from the user's PYTHONSTARTUP file.

```
import os
histfile = os.path.join(os.environ["HOME"], ".pyhist")
try:
    readline.read_history_file(histfile)
except IOError:
    pass
import atexit
atexit.register(readline.write_history_file, histfile)
del os, histfile
```

The following example extends the code. InteractiveConsole class to support history save/restore.

```
import code
import readline
import atexit
import os
class HistoryConsole(code.InteractiveConsole):
   def __init__(self, locals=None, filename="<console>",
                 histfile=os.path.expanduser("~/.console-history")):
        code.InteractiveConsole.__init__(self)
        self.init_history(histfile)
   def init_history(self, histfile):
        readline.parse_and_bind("tab: complete")
        if hasattr(readline, "read_history_file"):
                readline.read_history_file(histfile)
            except IOError:
               pass
            atexit.register(self.save_history, histfile)
   def save_history(self, histfile):
        readline.write_history_file(histfile)
```

7.21 rlcompleter — Completion function for GNU readline

The rlcompleter module defines a completion function for the readline module by completing valid Python identifiers and keywords.

This module is UNIX-specific due to its dependence on the readline module.

The ${\tt rlcompleter}$ module defines the Completer class.

Example:

```
>>> import rlcompleter
>>> import readline
>>> readline.parse_and_bind("tab: complete")
>>> readline. <TAB PRESSED>
readline.__doc__ readline.get_line_buffer readline.read_init_file
readline.__file__ readline.insert_text readline.set_completer
readline.__name__ readline.parse_and_bind
>>> readline.
```

The rlcompleter module is designed for use with Python's interactive mode. A user can add the following

lines to his or her initialization file (identified by the PYTHONSTARTUP environment variable) to get automatic Tab completion:

```
try:
    import readline
except ImportError:
    print "Module readline not available."
else:
    import rlcompleter
    readline.parse_and_bind("tab: complete")
```

7.21.1 Completer Objects

Completer objects have the following method:

```
complete(text, state)
```

Return the *state*th completion for *text*.

If called for *text* that doesn't include a period character ('.'), it will complete from names currently defined in __main__, __builtin__ and keywords (as defined by the keyword module).

If called for a dotted name, it will try to evaluate anything without obvious side-effects (functions will not be evaluated, but it can generate calls to $__getattr__()$) up to the last part, and find matches for the rest via the dir() function.

Unix Specific Services

The modules described in this chapter provide interfaces to features that are unique to the UNIX operating system, or in some cases to some or many variants of it. Here's an overview:

posix The most common POSIX system calls (normally used via module os).

pwd The password database (getpwnam() and friends).
grp The group database (getgrnam() and friends).
crypt The crypt() function used to check UNIX passwords.

dl Call C functions in shared objects.

dbm The standard "database" interface, based on ndbm.

gdbm GNU's reinterpretation of dbm.

termios POSIX style tty control.

Utility functions that perform common terminal control operations.

pty Pseudo-Terminal Handling for SGI and Linux.

fcntl The fcntl() and ioctl() system calls.

pipes A Python interface to UNIX shell pipelines.

posixfile A file-like object with support for locking.

resource An interface to provide resource usage information on the current process.

nis Interface to Sun's NIS (Yellow Pages) library.

syslog An interface to the UNIX syslog library routines.

Commands Utility functions for running external commands.

8.1 posix — The most common POSIX system calls

This module provides access to operating system functionality that is standardized by the C Standard and the POSIX standard (a thinly disguised UNIX interface).

Do not import this module directly. Instead, import the module os, which provides a *portable* version of this interface. On UNIX, the os module provides a superset of the posix interface. On non-UNIX operating systems the posix module is not available, but a subset is always available through the os interface. Once os is imported, there is *no* performance penalty in using it instead of posix. In addition, os provides some additional functionality, such as automatically calling putenv() when an entry in os.environ is changed.

The descriptions below are very terse; refer to the corresponding UNIX manual (or POSIX documentation) entry for more information. Arguments called *path* refer to a pathname given as a string.

Errors are reported as exceptions; the usual exceptions are given for type errors, while errors reported by the system calls raise error (a synonym for the standard exception OSError), described below.

8.1.1 Large File Support

Several operating systems (including AIX, HPUX, Irix and Solaris) provide support for files that are larger than 2 Gb from a C programming model where int and long are 32-bit values. This is typically accomplished by defining the relevant size and offset types as 64-bit values. Such files are sometimes referred to as *large files*.

Large file support is enabled in Python when the size of an off_t is larger than a long and the long long

type is available and is at least as large as an off_t. Python longs are then used to represent file sizes, offsets and other values that can exceed the range of a Python int. It may be necessary to configure and compile Python with certain compiler flags to enable this mode. For example, it is enabled by default with recent versions of Irix, but with Solaris 2.6 and 2.7 you need to do something like:

On large-file-capable Linux systems, this might work:

```
CFLAGS='-D_LARGEFILE64_SOURCE -D_FILE_OFFSET_BITS=64' OPT="-g -O2 $CFLAGS" \ ./configure
```

8.1.2 Module Contents

Module posix defines the following data item:

environ

A dictionary representing the string environment at the time the interpreter was started. For example, environ['HOME'] is the pathname of your home directory, equivalent to getenv("HOME") in C.

Modifying this dictionary does not affect the string environment passed on by <code>execv()</code>, <code>popen()</code> or <code>system()</code>; if you need to change the environment, pass <code>environ</code> to <code>execve()</code> or add variable assignments and export statements to the command string for <code>system()</code> or <code>popen()</code>.

Note: The os module provides an alternate implementation of environ which updates the environment on modification. Note also that updating os.environ will render this dictionary obsolete. Use of the os module version of this is recommended over direct access to the posix module.

Additional contents of this module should only be accessed via the os module; refer to the documentation for that module for further information.

8.2 pwd — The password database

This module provides access to the UNIX user account and password database. It is available on all UNIX versions.

Password database entries are reported as a tuple-like object, whose attributes correspond to the members of the passwd structure (Attribute field below, see <pwd.h>):

Index	Attribute	Meaning
0	pw_name	Login name
1	pw_passwd	Optional encrypted password
2	pw_uid	Numerical user ID
3	pw_gid	Numerical group ID
4	pw_gecos	User name or comment field
5	pw_dir	User home directory
6	pw_shell	User command interpreter

The uid and gid items are integers, all others are strings. KeyError is raised if the entry asked for cannot be found.

Note: In traditional UNIX the field pw_passwd usually contains a password encrypted with a DES derived algorithm (see module crypt). However most modern unices use a so-called *shadow password* system. On those unices the *pw_passwd* field only contains an asterisk ('*') or the letter 'x' where the encrypted password is stored in a file '/etc/shadow' which is not world readable. Whether the *pw_passwd* field contains anything useful is system-dependent.

It defines the following items:

getpwuid(uid)

Return the password database entry for the given numeric user ID.

getpwnam(name)

Return the password database entry for the given user name.

getpwall()

Return a list of all available password database entries, in arbitrary order.

See Also:

Module grp (section 8.3):

An interface to the group database, similar to this.

8.3 grp — The group database

This module provides access to the UNIX group database. It is available on all UNIX versions.

Group database entries are reported as a tuple-like object, whose attributes correspond to the members of the group structure (Attribute field below, see <pwd.h>):

Index	Attribute	Meaning
0	gr_name	the name of the group
1	gr_passwd	the (encrypted) group password; often empty
2	gr_gid	the numerical group ID
3	gr_mem	all the group member's user names

The gid is an integer, name and password are strings, and the member list is a list of strings. (Note that most users are not explicitly listed as members of the group they are in according to the password database. Check both databases to get complete membership information.)

It defines the following items:

getgrgid(gid)

Return the group database entry for the given numeric group ID. KeyError is raised if the entry asked for cannot be found.

getgrnam(name)

Return the group database entry for the given group name. KeyError is raised if the entry asked for cannot be found.

getgrall()

Return a list of all available group entries, in arbitrary order.

See Also:

Module pwd (section 8.2):

An interface to the user database, similar to this.

8.4 crypt — Function to check UNIX passwords

This module implements an interface to the *crypt*(3) routine, which is a one-way hash function based upon a modified DES algorithm; see the UNIX man page for further details. Possible uses include allowing Python scripts to accept typed passwords from the user, or attempting to crack UNIX passwords with a dictionary.

Notice that the behavior of this module depends on the actual implementation of the *crypt*(3) routine in the running system. Therefore, any extensions available on the current implementation will also be available on this module. **crypt**(*word*, *salt*)

word will usually be a user's password as typed at a prompt or in a graphical interface. salt is usually a random two-character string which will be used to perturb the DES algorithm in one of 4096 ways. The characters in salt must be in the set $\lceil [./a-zA-Z0-9] \rfloor$. Returns the hashed password as a string, which

will be composed of characters from the same alphabet as the salt (the first two characters represent the salt itself).

Since a few *crypt*(3) extensions allow different values, with different sizes in the *salt*, it is recommended to use the full crypted password as salt when checking for a password.

A simple example illustrating typical use:

```
import crypt, getpass, pwd

def login():
    username = raw_input('Python login:')
    cryptedpasswd = pwd.getpwnam(username)[1]
    if cryptedpasswd:
        if cryptedpasswd == 'x' or cryptedpasswd == '*':
            raise "Sorry, currently no support for shadow passwords"
        cleartext = getpass.getpass()
        return crypt.crypt(cleartext, cryptedpasswd) == cryptedpasswd
    else:
        return 1
```

8.5 dl — Call C functions in shared objects

The dl module defines an interface to the dlopen() function, which is the most common interface on UNIX platforms for handling dynamically linked libraries. It allows the program to call arbitrary functions in such a library.

Note: This module will not work unless sizeof(int) == sizeof(long) == sizeof(char *) If this is not the case, SystemError will be raised on import.

The dl module defines the following function:

```
open(name[, mode = RTLD_LAZY])
```

Open a shared object file, and return a handle. Mode signifies late binding (RTLD_LAZY) or immediate binding (RTLD_NOW). Default is RTLD_LAZY. Note that some systems do not support RTLD_NOW.

Return value is a dlobject.

The dl module defines the following constants:

RTLD_LAZY

Useful as an argument to open().

RTLD_NOW

Useful as an argument to open(). Note that on systems which do not support immediate binding, this constant will not appear in the module. For maximum portability, use hasattr() to determine if the system supports immediate binding.

The dl module defines the following exception:

exception error

Exception raised when an error has occurred inside the dynamic loading and linking routines.

Example:

```
>>> import d1, time
>>> a=d1.open('/lib/libc.so.6')
>>> a.call('time'), time.time()
(929723914, 929723914.498)
```

This example was tried on a Debian GNU/Linux system, and is a good example of the fact that using this module

is usually a bad alternative.

8.5.1 DI Objects

Dl objects, as returned by open () above, have the following methods:

close()

Free all resources, except the memory.

sym(name)

Return the pointer for the function named *name*, as a number, if it exists in the referenced shared object, otherwise None. This is useful in code like:

```
>>> if a.sym('time'):
... a.call('time')
... else:
... time.time()
```

(Note that this function will return a non-zero number, as zero is the NULL pointer)

```
call(name[, arg1[, arg2...]])
```

Call the function named *name* in the referenced shared object. The arguments must be either Python integers, which will be passed as is, Python strings, to which a pointer will be passed, or None, which will be passed as NULL. Note that strings should only be passed to functions as const char*, as Python will not like its string mutated.

There must be at most 10 arguments, and arguments not given will be treated as None. The function's return value must be a Clong, which is a Python integer.

8.6 dbm — Simple "database" interface

The dbm module provides an interface to the UNIX (n)dbm library. Dbm objects behave like mappings (dictionaries), except that keys and values are always strings. Printing a dbm object doesn't print the keys and values, and the items() and values() methods are not supported.

This module can be used with the "classic" ndbm interface, the BSD DB compatibility interface, or the GNU GDBM compatibility interface. On UNIX, the **configure** script will attempt to locate the appropriate header file to simplify building this module.

The module defines the following:

exception error

Raised on dbm-specific errors, such as I/O errors. KeyError is raised for general mapping errors like specifying an incorrect key.

library

Name of the ndbm implementation library used.

```
open (filename [, flag [, mode ]])
```

Open a dbm database and return a dbm object. The *filename* argument is the name of the database file (without the '.dir' or '.pag' extensions; note that the BSD DB implementation of the interface will append the extension '.db' and only create one file).

The optional *flag* argument must be one of these values:

Value	Meaning
'r'	Open existing database for reading only (default)
'w'	Open existing database for reading and writing
' C '	Open database for reading and writing, creating it if it doesn't exist
'n	Always create a new, empty database, open for reading and writing

The optional *mode* argument is the UNIX mode of the file, used only when the database has to be created. It defaults to octal 0666.

See Also:

```
Module anydbm (section 7.10):
```

Generic interface to dbm-style databases.

Module gdbm (section 8.7):

Similar interface to the GNU GDBM library.

Module whichdb (section 7.12):

Utility module used to determine the type of an existing database.

8.7 gdbm — GNU's reinterpretation of dbm

This module is quite similar to the dbm module, but uses gdbm instead to provide some additional functionality. Please note that the file formats created by gdbm and dbm are incompatible.

The gdbm module provides an interface to the GNU DBM library. gdbm objects behave like mappings (dictionaries), except that keys and values are always strings. Printing a gdbm object doesn't print the keys and values, and the items() and values() methods are not supported.

The module defines the following constant and functions:

exception error

Raised on gdbm-specific errors, such as I/O errors. KeyError is raised for general mapping errors like specifying an incorrect key.

```
open (filename, [flag, [mode]])
```

Open a gdbm database and return a gdbm object. The *filename* argument is the name of the database file.

The optional flag argument can be 'r' (to open an existing database for reading only — default), 'w' (to open an existing database for reading and writing), 'c' (which creates the database if it doesn't exist), or 'n' (which always creates a new empty database).

The following additional characters may be appended to the flag to control how the database is opened:

- 'f' Open the database in fast mode. Writes to the database will not be synchronized.
- 's' Synchronized mode. This will cause changes to the database will be immediately written to the file.
- 'u' Do not lock database.

Not all flags are valid for all versions of gdbm. The module constant open_flags is a string of supported flag characters. The exception error is raised if an invalid flag is specified.

The optional *mode* argument is the UNIX mode of the file, used only when the database has to be created. It defaults to octal 0666.

In addition to the dictionary-like methods, gdbm objects have the following methods:

firstkey()

It's possible to loop over every key in the database using this method and the nextkey() method. The traversal is ordered by gdbm's internal hash values, and won't be sorted by the key values. This method returns the starting key.

nextkey(key)

Returns the key that follows *key* in the traversal. The following code prints every key in the database db, without having to create a list in memory that contains them all:

```
k = db.firstkey()
while k != None:
    print k
    k = db.nextkey(k)
```

reorganize()

If you have carried out a lot of deletions and would like to shrink the space used by the gdbm file, this

routine will reorganize the database. gdbm will not shorten the length of a database file except by using this reorganization; otherwise, deleted file space will be kept and reused as new (key, value) pairs are added.

sync()

When the database has been opened in fast mode, this method forces any unwritten data to be written to the disk.

See Also:

Module anydbm (section 7.10):

Generic interface to dbm-style databases.

Module whichdb (section 7.12):

Utility module used to determine the type of an existing database.

8.8 termios — POSIX style tty control

This module provides an interface to the POSIX calls for tty I/O control. For a complete description of these calls, see the POSIX or UNIX manual pages. It is only available for those UNIX versions that support POSIX *termios* style tty I/O control (and then only if configured at installation time).

All functions in this module take a file descriptor *fd* as their first argument. This can be an integer file descriptor, such as returned by sys.stdin.fileno(), or a file object, such as sys.stdin itself.

This module also defines all the constants needed to work with the functions provided here; these have the same name as their counterparts in C. Please refer to your system documentation for more information on using these terminal control interfaces.

The module defines the following functions:

tcgetattr(fd)

Return a list containing the tty attributes for file descriptor fd, as follows: [iflag, oflag, cflag, lflag, ispeed, ospeed, cc] where cc is a list of the tty special characters (each a string of length 1, except the items with indices VMIN and VTIME, which are integers when these fields are defined). The interpretation of the flags and the speeds as well as the indexing in the cc array must be done using the symbolic constants defined in the termios module.

tcsetattr(fd, when, attributes)

Set the tty attributes for file descriptor *fd* from the *attributes*, which is a list like the one returned by tcgetattr(). The *when* argument determines when the attributes are changed: TCSANOW to change immediately, TCSADRAIN to change after transmitting all queued output, or TCSAFLUSH to change after transmitting all queued output and discarding all queued input.

tcsendbreak(fd, duration)

Send a break on file descriptor *fd*. A zero *duration* sends a break for 0.25–0.5 seconds; a nonzero *duration* has a system dependent meaning.

tcdrain(fd)

Wait until all output written to file descriptor fd has been transmitted.

tcflush(fd. aueue)

Discard queued data on file descriptor fd. The *queue* selector specifies which queue: TCIFLUSH for the input queue, TCOFLUSH for the output queue, or TCIOFLUSH for both queues.

tcflow(fd, action)

Suspend or resume input or output on file descriptor *fd*. The *action* argument can be TCOOFF to suspend output, TCOON to restart output, TCIOFF to suspend input, or TCION to restart input.

See Also:

Module tty (section 8.9):

Convenience functions for common terminal control operations.

8.8.1 Example

Here's a function that prompts for a password with echoing turned off. Note the technique using a separate tcgetattr() call and a try ... finally statement to ensure that the old tty attributes are restored exactly no matter what happens:

```
def getpass(prompt = "Password: "):
    import termios, sys
    fd = sys.stdin.fileno()
    old = termios.tcgetattr(fd)
    new = termios.tcgetattr(fd)
    new[3] = new[3] & ~termios.ECHO  # lflags
    try:
        termios.tcsetattr(fd, termios.TCSADRAIN, new)
        passwd = raw_input(prompt)
    finally:
        termios.tcsetattr(fd, termios.TCSADRAIN, old)
    return passwd
```

8.9 tty — Terminal control functions

The tty module defines functions for putting the tty into cbreak and raw modes.

Because it requires the termios module, it will work only on UNIX.

The tty module defines the following functions:

```
setraw(fd, when)
```

Change the mode of the file descriptor fd to raw. If when is omitted, it defaults to termios. TCSAFLUSH, and is passed to termios.tcsetattr().

```
setcbreak(fd[, when])
```

Change the mode of file descriptor fd to cbreak. If when is omitted, it defaults to termios. TCSAFLUSH, and is passed to termios.tcsetattr().

See Also:

Module termios (section 8.8):

Low-level terminal control interface.

8.10 pty — Pseudo-terminal utilities

The pty module defines operations for handling the pseudo-terminal concept: starting another process and being able to write to and read from its controlling terminal programmatically.

Because pseudo-terminal handling is highly platform dependant, there is code to do it only for SGI and Linux. (The Linux code is supposed to work on other platforms, but hasn't been tested yet.)

The pty module defines the following functions:

fork()

Fork. Connect the child's controlling terminal to a pseudo-terminal. Return value is (pid, fd). Note that the child gets pid 0, and the fd is invalid. The parent's return value is the pid of the child, and fd is a file descriptor connected to the child's controlling terminal (and also to the child's standard input and output).

openpty()

Open a new pseudo-terminal pair, using os.openpty() if possible, or emulation code for SGI and generic UNIX systems. Return a pair of file descriptors (*master*, *slave*), for the master and the slave end, respectively.

```
spawn(argv[, master_read[, stdin_read]])
```

Spawn a process, and connect its controlling terminal with the current process's standard io. This is often used to baffle programs which insist on reading from the controlling terminal.

The functions *master_read* and *stdin_read* should be functions which read from a file-descriptor. The defaults try to read 1024 bytes each time they are called.

8.11 fcntl — The fcntl() and ioctl() system calls

This module performs file control and I/O control on file descriptors. It is an interface to the fcntl() and ioctl() UNIX routines.

All functions in this module take a file descriptor fd as their first argument. This can be an integer file descriptor, such as returned by sys.stdin.fileno(), or a file object, such as sys.stdin itself, which provides a fileno() which returns a genuine file descriptor.

The module defines the following functions:

```
fcntl(fd, op[, arg])
```

Perform the requested operation on file descriptor fd (file objects providing a fileno() method are accepted as well). The operation is defined by op and is operating system dependent. These codes are also found in the fcntl module. The argument arg is optional, and defaults to the integer value 0. When present, it can either be an integer value, or a string. With the argument missing or an integer value, the return value of this function is the integer return value of the Cfcntl() call. When the argument is a string it represents a binary structure, e.g. created by struct.pack(). The binary data is copied to a buffer whose address is passed to the Cfcntl() call. The return value after a successful call is the contents of the buffer, converted to a string object. The length of the returned string will be the same as the length of the arg argument. This is limited to 1024 bytes. If the information returned in the buffer by the operating system is larger than 1024 bytes, this is most likely to result in a segmentation violation or a more subtle data corruption.

If the fcntl() fails, an IOError is raised.

```
ioctl(fd, op[, arg[, mutate_flag]])
```

This function is identical to the fcntl() function, except that the operations are typically defined in the library module termios and the argument handling is even more complicated.

The parameter *arg* can be one of an integer, absent (treated identically to the integer 0), an object supporting the read-only buffer interface (most likely a plain Python string) or an object supporting the read-write buffer interface.

In all but the last case, behaviour is as for the fcntl() function.

If a mutable buffer is passed, then the behaviour is determined by the value of the *mutate_flag* parameter.

If it is false, the buffer's mutability is ignored and behaviour is as for a read-only buffer, except that the 1024 byte limit mentioned above is avoided – so long as the buffer you pass is longer than what the operating system wants to put there, things should work.

If *mutate_flag* is true, then the buffer is (in effect) passed to the underlying <code>ioctl()</code> system call, the latter's return code is passed back to the calling Python, and the buffer's new contents reflect the action of the <code>ioctl()</code>. This is a slight simplification, because if the supplied buffer is less than 1024 bytes long it is first copied into a static buffer 1024 bytes long which is then passed to <code>ioctl()</code> and copied back into the supplied buffer.

If *mutate_flag* is not supplied, then in 2.3 it defaults to false. This is planned to change over the next few Python versions: in 2.4 failing to supply *mutate_flag* will get a warning but the same behavior and in versions later than 2.5 it will default to true.

An example:

```
>>> import array, fcntl, struct, termios, os
>>> os.getpgrp()
13341
>>> struct.unpack('h', fcntl.ioctl(0, termios.TIOCGPGRP, " "))[0]
13341
>>> buf = array.array('h', [0])
>>> fcntl.ioctl(0, termios.TIOCGPGRP, buf, 1)
0
>>> buf
array('h', [13341])
```

flock(fd, op)

Perform the lock operation op on file descriptor fd (file objects providing a fileno() method are accepted as well). See the UNIX manual flock(3) for details. (On some systems, this function is emulated using fcntl().)

```
lockf(fd, operation, [length, [start, [whence]]])
```

This is essentially a wrapper around the fcntl() locking calls. fd is the file descriptor of the file to lock or unlock, and *operation* is one of the following values:

- ●LOCK_UN unlock
- ●LOCK_SH acquire a shared lock
- ●LOCK_EX acquire an exclusive lock

When *operation* is LOCK_SH or LOCK_EX, it can also be bit-wise OR'd with LOCK_NB to avoid blocking on lock acquisition. If LOCK_NB is used and the lock cannot be acquired, an IOError will be raised and the exception will have an *errno* attribute set to EACCES or EAGAIN (depending on the operating system; for portability, check for both values). On at least some systems, LOCK_EX can only be used if the file descriptor refers to a file opened for writing.

length is the number of bytes to lock, *start* is the byte offset at which the lock starts, relative to *whence*, and *whence* is as with fileobj.seek(), specifically:

- •0 relative to the start of the file (SEEK_SET)
- •1 relative to the current buffer position (SEEK_CUR)
- •2 relative to the end of the file (SEEK_END)

The default for *start* is 0, which means to start at the beginning of the file. The default for *length* is 0 which means to lock to the end of the file. The default for *whence* is also 0.

Examples (all on a SVR4 compliant system):

```
import struct, fcntl, os

f = open(...)
rv = fcntl.fcntl(f, fcntl.F_SETFL, os.O_NDELAY)

lockdata = struct.pack('hhllhh', fcntl.F_WRLCK, 0, 0, 0, 0, 0)
rv = fcntl.fcntl(f, fcntl.F_SETLKW, lockdata)
```

Note that in the first example the return value variable rv will hold an integer value; in the second example it will hold a string value. The structure lay-out for the *lockdata* variable is system dependent — therefore using the flock() call may be better.

See Also:

Module os (section 6.1):

The os.open() function supports locking flags and is available on a wider variety of platforms than the lockf() and flock() functions, providing a more platform-independent file locking facility.

8.12 pipes — Interface to shell pipelines

The pipes module defines a class to abstract the concept of a *pipeline* — a sequence of convertors from one file to another.

Because the module uses /bin/sh command lines, a POSIX or compatible shell for os.system() and os.popen() is required.

The pipes module defines the following class:

class Template()

An abstraction of a pipeline.

Example:

```
>>> import pipes
>>> t=pipes.Template()
>>> t.append('tr a-z A-Z', '--')
>>> f=t.open('/tmp/1', 'w')
>>> f.write('hello world')
>>> f.close()
>>> open('/tmp/1').read()
'HELLO WORLD'
```

8.12.1 Template Objects

Template objects following methods:

reset()

Restore a pipeline template to its initial state.

clone(

Return a new, equivalent, pipeline template.

debug(flag)

If *flag* is true, turn debugging on. Otherwise, turn debugging off. When debugging is on, commands to be executed are printed, and the shell is given set -x command to be more verbose.

append(cmd, kind)

Append a new action at the end. The *cmd* variable must be a valid bourne shell command. The *kind* variable consists of two letters.

The first letter can be either of '-' (which means the command reads its standard input), 'f' (which means the commands reads a given file on the command line) or '.' (which means the commands reads no input, and hence must be first.)

Similarly, the second letter can be either of '-' (which means the command writes to standard output), 'f' (which means the command writes a file on the command line) or '. ' (which means the command does not write anything, and hence must be last.)

prepend(cmd, kind)

Add a new action at the beginning. See append() for explanations of the arguments.

open(file, mode)

Return a file-like object, open to *file*, but read from or written to by the pipeline. Note that only one of 'r', 'w' may be given.

copy(infile, outfile)

Copy infile to outfile through the pipe.

8.13 posixfile — File-like objects with locking support

Deprecated since release 1.5. The locking operation that this module provides is done better and more portably by the fcntl.lockf() call.

This module implements some additional functionality over the built-in file objects. In particular, it implements file locking, control over the file flags, and an easy interface to duplicate the file object. The module defines a new file object, the posixfile object. It has all the standard file object methods and adds the methods described below. This module only works for certain flavors of UNIX, since it uses fcntl.fcntl() for file locking.

To instantiate a posixfile object, use the open() function in the posixfile module. The resulting object looks and feels roughly the same as a standard file object.

The posixfile module defines the following constants:

SEEK_SET

Offset is calculated from the start of the file.

SEEK CUR

Offset is calculated from the current position in the file.

SEEK_END

Offset is calculated from the end of the file.

The posixfile module defines the following functions:

open(filename[, mode[, bufsize]])

Create a new posixfile object with the given filename and mode. The *filename*, *mode* and *bufsize* arguments are interpreted the same way as by the built-in open() function.

fileopen(fileobject)

Create a new posixfile object with the given standard file object. The resulting object has the same filename and mode as the original file object.

The posixfile object defines the following additional methods:

```
lock (fmt, [len[, start[, whence]]])
```

Lock the specified section of the file that the file object is referring to. The format is explained below in a table. The *len* argument specifies the length of the section that should be locked. The default is 0. *start* specifies the starting offset of the section, where the default is 0. The *whence* argument specifies where the offset is relative to. It accepts one of the constants SEEK_SET, SEEK_CUR or SEEK_END. The default is SEEK_SET. For more information about the arguments refer to the *fcntl*(2) manual page on your system.

flags([flags])

Set the specified flags for the file that the file object is referring to. The new flags are ORed with the old flags, unless specified otherwise. The format is explained below in a table. Without the *flags* argument a string indicating the current flags is returned (this is the same as the '?' modifier). For more information about the flags refer to the *fcntl*(2) manual page on your system.

dup()

Duplicate the file object and the underlying file pointer and file descriptor. The resulting object behaves as if it were newly opened.

dup2(fd)

Duplicate the file object and the underlying file pointer and file descriptor. The new object will have the given file descriptor. Otherwise the resulting object behaves as if it were newly opened.

file()

Return the standard file object that the posixfile object is based on. This is sometimes necessary for functions that insist on a standard file object.

All methods raise IOError when the request fails.

Format characters for the lock() method have the following meaning:

Format	Meaning	
ʻu'	unlock the specified region	
r'	request a read lock for the specified section	
'w'	request a write lock for the specified section	

In addition the following modifiers can be added to the format:

Modifier	er Meaning	
' '	wait until the lock has been granted	
, 3,	return the first lock conflicting with the requested lock, or None if there is no conflict.	(1)

Note:

(1) The lock returned is in the format (*mode*, *len*, *start*, *whence*, *pid*) where *mode* is a character representing the type of lock ('r' or 'w'). This modifier prevents a request from being granted; it is for query purposes only.

Format characters for the flags() method have the following meanings:

Format	Meaning
ʻa'	append only flag
'c'	close on exec flag
'n'	no delay flag (also called non-blocking flag)
's'	synchronization flag

In addition the following modifiers can be added to the format:

Modifier	Meaning	Notes
'!'	turn the specified flags 'off', instead of the default 'on'	(1)
'='	replace the flags, instead of the default 'OR' operation	(1)
' ?'	return a string in which the characters represent the flags that are set.	(2)

Notes:

- (1) The '!' and '=' modifiers are mutually exclusive.
- (2) This string represents the flags after they may have been altered by the same call.

Examples:

```
import posixfile
file = posixfile.open('/tmp/test', 'w')
file.lock('w|')
...
file.lock('u')
file.close()
```

8.14 resource — Resource usage information

This module provides basic mechanisms for measuring and controlling system resources utilized by a program.

Symbolic constants are used to specify particular system resources and to request usage information about either the current process or its children.

A single exception is defined for errors:

exception error

The functions described below may raise this error if the underlying system call failures unexpectedly.

8.14.1 Resource Limits

Resources usage can be limited using the setrlimit() function described below. Each resource is controlled by a pair of limits: a soft limit and a hard limit. The soft limit is the current limit, and may be lowered or raised by a process over time. The soft limit can never exceed the hard limit. The hard limit can be lowered to any value greater than the soft limit, but not raised. (Only processes with the effective UID of the super-user can raise a hard limit.)

The specific resources that can be limited are system dependent. They are described in the *getrlimit*(2) man page. The resources listed below are supported when the underlying operating system supports them; resources which cannot be checked or controlled by the operating system are not defined in this module for those platforms.

getrlimit(resource)

Returns a tuple (*soft*, *hard*) with the current soft and hard limits of *resource*. Raises ValueError if an invalid resource is specified, or error if the underlying system call fails unexpectedly.

setrlimit(resource, limits)

Sets new limits of consumption of *resource*. The *limits* argument must be a tuple (soft, hard) of two integers describing the new limits. A value of -1 can be used to specify the maximum possible upper limit.

Raises ValueError if an invalid resource is specified, if the new soft limit exceeds the hard limit, or if a process tries to raise its hard limit (unless the process has an effective UID of super-user). Can also raise error if the underlying system call fails.

These symbols define resources whose consumption can be controlled using the setrlimit() and getrlimit() functions described below. The values of these symbols are exactly the constants used by C programs.

The UNIX man page for *getrlimit*(2) lists the available resources. Note that not all systems use the same symbol or same value to denote the same resource. This module does not attempt to mask platform differences — symbols not defined for a platform will not be available from this module on that platform.

RLIMIT_CORE

The maximum size (in bytes) of a core file that the current process can create. This may result in the creation of a partial core file if a larger core would be required to contain the entire process image.

RLIMIT_CPU

The maximum amount of processor time (in seconds) that a process can use. If this limit is exceeded, a SIGXCPU signal is sent to the process. (See the signal module documentation for information about how to catch this signal and do something useful, e.g. flush open files to disk.)

RLIMIT_FSIZE

The maximum size of a file which the process may create. This only affects the stack of the main thread in a multi-threaded process.

RLIMIT_DATA

The maximum size (in bytes) of the process's heap.

RLIMIT_STACK

The maximum size (in bytes) of the call stack for the current process.

RLIMIT_RSS

The maximum resident set size that should be made available to the process.

RLIMIT_NPROC

The maximum number of processes the current process may create.

RLIMIT_NOFILE

The maximum number of open file descriptors for the current process.

RLIMIT_OFILE

The BSD name for RLIMIT_NOFILE.

RLIMIT_MEMLOCK

The maximum address space which may be locked in memory.

RLIMIT_VMEM

The largest area of mapped memory which the process may occupy.

RLIMIT_AS

The maximum area (in bytes) of address space which may be taken by the process.

8.14.2 Resource Usage

These functions are used to retrieve resource usage information:

getrusage(who)

This function returns an object that describes the resources consumed by either the current process or its children, as specified by the *who* parameter. The *who* parameter should be specified using one of the RUSAGE_* constants described below.

The fields of the return value each describe how a particular system resource has been used, e.g. amount of time spent running is user mode or number of times the process was swapped out of main memory. Some values are dependent on the clock tick internal, e.g. the amount of memory the process is using.

For backward compatibility, the return value is also accessible as a tuple of 16 elements.

The fields ru_utime and ru_stime of the return value are floating point values representing the amount of time spent executing in user mode and the amount of time spent executing in system mode, respectively. The remaining values are integers. Consult the *getrusage*(2) man page for detailed information about these values. A brief summary is presented here:

Index	Field	Resource
0	ru_utime	time in user mode (float)
1	ru_stime	time in system mode (float)
2	ru_maxrss	maximum resident set size
3	ru_ixrss	shared memory size
4	ru_idrss	unshared memory size
5	ru_isrss	unshared stack size
6	ru_minflt	page faults not requiring I/O
7	ru_majflt	page faults requiring I/O
8	ru_nswap	number of swap outs
9	ru_inblock	block input operations
10	ru_oublock	block output operations
11	ru_msgsnd	messages sent
12	ru_msgrcv	messages received
13	ru_nsignals	signals received
14	ru_nvcsw	voluntary context switches
15	ru_nivcsw	involuntary context switches

This function will raise a ValueError if an invalid *who* parameter is specified. It may also raise error exception in unusual circumstances.

Changed in version 2.3: Added access to values as attributes of the returned object.

getpagesize()

Returns the number of bytes in a system page. (This need not be the same as the hardware page size.) This function is useful for determining the number of bytes of memory a process is using. The third element of the tuple returned by getrusage() describes memory usage in pages; multiplying by page size produces number of bytes.

The following $RUSAGE_*$ symbols are passed to the getrusage() function to specify which processes information should be provided for.

${ t RUSAGE_SELF}$

RUSAGE_SELF should be used to request information pertaining only to the process itself.

RUSAGE_CHILDREN

Pass to getrusage () to request resource information for child processes of the calling process.

RUSAGE_BOTH

Pass to getrusage() to request resources consumed by both the current process and child processes. May not be available on all systems.

8.15 nis — Interface to Sun's NIS (Yellow Pages)

The nis module gives a thin wrapper around the NIS library, useful for central administration of several hosts.

Because NIS exists only on UNIX systems, this module is only available for UNIX.

The nis module defines the following functions:

match(key, mapname)

Return the match for *key* in map *mapname*, or raise an error (nis.error) if there is none. Both should be strings, *key* is 8-bit clean. Return value is an arbitrary array of bytes (may contain NULL and other joys).

Note that *mapname* is first checked if it is an alias to another name.

cat(mapname)

Return a dictionary mapping key to value such that match (key, mapname) ==value. Note that both keys and values of the dictionary are arbitrary arrays of bytes.

Note that *mapname* is first checked if it is an alias to another name.

maps()

Return a list of all valid maps.

The nis module defines the following exception:

exception error

An error raised when a NIS function returns an error code.

8.16 syslog — UNIX syslog library routines

This module provides an interface to the UNIX syslog library routines. Refer to the UNIX manual pages for a detailed description of the syslog facility.

The module defines the following functions:

syslog([priority,] message)

Send the string *message* to the system logger. A trailing newline is added if necessary. Each message is tagged with a priority composed of a *facility* and a *level*. The optional *priority* argument, which defaults to LOG_INFO, determines the message priority. If the facility is not encoded in *priority* using logical-or (LOG_INFO | LOG_USER), the value given in the openlog() call is used.

openlog(ident[, logopt[, facility]])

Logging options other than the defaults can be set by explicitly opening the log file with openlog() prior to calling syslog(). The defaults are (usually) *ident* = 'syslog', *logopt* = 0, *facility* = LOG_USER. The *ident* argument is a string which is prepended to every message. The optional *logopt* argument is a bit field - see below for possible values to combine. The optional *facility* argument sets the default facility for messages which do not have a facility explicitly encoded.

closelog()

Close the log file.

setlogmask(maskpri)

Set the priority mask to *maskpri* and return the previous mask value. Calls to syslog() with a priority level not set in *maskpri* are ignored. The default is to log all priorities. The function LOG_MASK(*pri*) calculates the mask for the individual priority *pri*. The function LOG_UPTO(*pri*) calculates the mask for all priorities up to and including *pri*.

The module defines the following constants:

Priority levels (high to low): LOG_EMERG, LOG_ALERT, LOG_CRIT, LOG_ERR, LOG_WARNING, LOG_NOTICE, LOG_INFO, LOG_DEBUG.

Facilities: LOG_KERN, LOG_USER, LOG_MAIL, LOG_DAEMON, LOG_AUTH, LOG_LPR, LOG_NEWS, LOG_UUCP, LOG_CRON and LOG_LOCALO to LOG_LOCALO.

Log options: LOG_PID, LOG_CONS, LOG_NDELAY, LOG_NOWAIT and LOG_PERROR if defined in <syslog.h>.

8.17 commands — Utilities for running commands

The commands module contains wrapper functions for os.popen() which take a system command as a string and return any output generated by the command and, optionally, the exit status.

The commands module defines the following functions:

getstatusoutput(cmd)

Execute the string cmd in a shell with os.popen() and return a 2-tuple (status, output). cmd is actually run as $\{cmd : \}2>\&1$, so that the returned output will contain output or error messages. A trailing newline is stripped from the output. The exit status for the command can be interpreted according to the rules for the C function wait().

getoutput(cmd)

Like getstatusoutput(), except the exit status is ignored and the return value is a string containing the command's output.

getstatus(file)

Return the output of 'ls -ld *file*' as a string. This function uses the getoutput() function, and properly escapes backslashes and dollar signs in the argument.

Example:

```
>>> import commands
>>> commands.getstatusoutput('ls /bin/ls')
(0, '/bin/ls')
>>> commands.getstatusoutput('cat /bin/junk')
(256, 'cat: /bin/junk: No such file or directory')
>>> commands.getstatusoutput('/bin/junk')
(256, 'sh: /bin/junk: not found')
>>> commands.getoutput('ls /bin/ls')
'/bin/ls'
>>> commands.getstatus('/bin/ls')
'-rwxr-xr-x 1 root 13352 Oct 14 1994 /bin/ls'
```

The Python Debugger

The module pdb defines an interactive source code debugger for Python programs. It supports setting (conditional) breakpoints and single stepping at the source line level, inspection of stack frames, source code listing, and evaluation of arbitrary Python code in the context of any stack frame. It also supports post-mortem debugging and can be called under program control.

The debugger is extensible — it is actually defined as the class Pdb. This is currently undocumented but easily understood by reading the source. The extension interface uses the modules bdb (undocumented) and cmd.

The debugger's prompt is '(Pdb) '. Typical usage to run a program under control of the debugger is:

```
>>> import pdb
>>> import mymodule
>>> pdb.run('mymodule.test()')
> <string>(0)?()
(Pdb) continue
> <string>(1)?()
(Pdb) continue
NameError: 'spam'
> <string>(1)?()
(Pdb)
```

'pdb.py' can also be invoked as a script to debug other scripts. For example:

```
python -m pdb myscript.py
```

When invoked as a script, pdb will automatically enter post-mortem debugging if the program being debugged exits abnormally. After post-mortem debugging (or after normal exit of the program), pdb will restart the program. Automatic restarting preserves pdb's state (such as breakpoints) and in most cases is more useful than quitting the debugger upon program's exit. New in version 2.4: Restarting post-mortem behavior added.

Typical usage to inspect a crashed program is:

```
>>> import pdb
>>> import mymodule
>>> mymodule.test()
Traceback (most recent call last):
   File "<stdin>", line 1, in ?
   File "./mymodule.py", line 4, in test
        test2()
   File "./mymodule.py", line 3, in test2
        print spam
NameError: spam
>>> pdb.pm()
> ./mymodule.py(3)test2()
-> print spam
(Pdb)
```

The module defines the following functions; each enters the debugger in a slightly different way:

```
run(statement[, globals[, locals]])
```

Execute the *statement* (given as a string) under debugger control. The debugger prompt appears before any code is executed; you can set breakpoints and type 'continue', or you can step through the statement using 'step' or 'next' (all these commands are explained below). The optional *globals* and *locals* arguments specify the environment in which the code is executed; by default the dictionary of the module __main__ is used. (See the explanation of the exec statement or the eval() built-in function.)

```
runeval(expression[, globals[, locals]])
```

Evaluate the *expression* (given as a string) under debugger control. When runeval() returns, it returns the value of the expression. Otherwise this function is similar to run().

```
runcall(function[, argument, ...])
```

Call the *function* (a function or method object, not a string) with the given arguments. When runcall() returns, it returns whatever the function call returned. The debugger prompt appears as soon as the function is entered.

```
set_trace()
```

Enter the debugger at the calling stack frame. This is useful to hard-code a breakpoint at a given point in a program, even if the code is not otherwise being debugged (e.g. when an assertion fails).

```
post_mortem(traceback)
```

Enter post-mortem debugging of the given traceback object.

pm()

Enter post-mortem debugging of the traceback found in sys.last_traceback.

9.1 Debugger Commands

The debugger recognizes the following commands. Most commands can be abbreviated to one or two letters; e.g. 'h(elp)' means that either 'h' or 'help' can be used to enter the help command (but not 'he' or 'hel', nor 'Help' or 'Help' or 'Help'). Arguments to commands must be separated by whitespace (spaces or tabs). Optional arguments are enclosed in square brackets ('[]') in the command syntax; the square brackets must not be typed. Alternatives in the command syntax are separated by a vertical bar ('[').

Entering a blank line repeats the last command entered. Exception: if the last command was a 'list' command, the next 11 lines are listed.

Commands that the debugger doesn't recognize are assumed to be Python statements and are executed in the context of the program being debugged. Python statements can also be prefixed with an exclamation point ('!'). This is a powerful way to inspect the program being debugged; it is even possible to change a variable or call a function. When an exception occurs in such a statement, the exception name is printed but the debugger's state is not changed.

Multiple commands may be entered on a single line, separated by '; '.' (A single ';' is not used as it is the

separator for multiple commands in a line that is passed to the Python parser.) No intelligence is applied to separating the commands; the input is split at the first ';' pair, even if it is in the middle of a quoted string.

The debugger supports aliases. Aliases can have parameters which allows one a certain level of adaptability to the context under examination.

If a file '.pdbrc' exists in the user's home directory or in the current directory, it is read in and executed as if it had been typed at the debugger prompt. This is particularly useful for aliases. If both files exist, the one in the home directory is read first and aliases defined there can be overridden by the local file.

- h(elp) [command] Without argument, print the list of available commands. With a command as argument, print help about that command. 'help pdb' displays the full documentation file; if the environment variable PAGER is defined, the file is piped through that command instead. Since the command argument must be an identifier, 'help exec' must be entered to get help on the '!' command.
- **w(here)** Print a stack trace, with the most recent frame at the bottom. An arrow indicates the current frame, which determines the context of most commands.
- d(own) Move the current frame one level down in the stack trace (to an newer frame).
- $\mathbf{u}(\mathbf{p})$ Move the current frame one level up in the stack trace (to a older frame).
- b(reak) [[filename:]lineno | function[, condition]] With a lineno argument, set a break there in the current file. With a function argument, set a break at the first executable statement within that function. The line number may be prefixed with a filename and a colon, to specify a breakpoint in another file (probably one that hasn't been loaded yet). The file is searched on sys.path. Note that each breakpoint is assigned a number to which all the other breakpoint commands refer.

If a second argument is present, it is an expression which must evaluate to true before the breakpoint is honored.

Without argument, list all breaks, including for each breakpoint, the number of times that breakpoint has been hit, the current ignore count, and the associated condition if any.

- **tbreak** [[filename:]lineno | function[, condition]] Temporary breakpoint, which is removed automatically when it is first hit. The arguments are the same as break.
- **cl(ear)** [bpnumber [bpnumber ...]] With a space separated list of breakpoint numbers, clear those breakpoints. Without argument, clear all breaks (but first ask confirmation).
- **disable** [bpnumber [bpnumber ...]] Disables the breakpoints given as a space separated list of breakpoint numbers. Disabling a breakpoint means it cannot cause the program to stop execution, but unlike clearing a breakpoint, it remains in the list of breakpoints and can be (re-)enabled.
- enable [bpnumber [bpnumber ...]] Enables the breakpoints specified.
- **ignore** *bpnumber* [*count*] Sets the ignore count for the given breakpoint number. If count is omitted, the ignore count is set to 0. A breakpoint becomes active when the ignore count is zero. When non-zero, the count is decremented each time the breakpoint is reached and the breakpoint is not disabled and any associated condition evaluates to true.
- **condition** *bpnumber* [*condition*] Condition is an expression which must evaluate to true before the breakpoint is honored. If condition is absent, any existing condition is removed; i.e., the breakpoint is made unconditional.
- s(tep) Execute the current line, stop at the first possible occasion (either in a function that is called or on the next line in the current function).
- n(ext) Continue execution until the next line in the current function is reached or it returns. (The difference between 'next' and 'step' is that 'step' stops inside a called function, while 'next' executes called functions at (nearly) full speed, only stopping at the next line in the current function.)
- $\mathbf{r}(\mathbf{eturn})$ Continue execution until the current function returns.
- c(ont(inue)) Continue execution, only stop when a breakpoint is encountered.

j(ump) *lineno* Set the next line that will be executed. Only available in the bottom-most frame. This lets you jump back and execute code again, or jump forward to skip code that you don't want to run.

It should be noted that not all jumps are allowed — for instance it is not possible to jump into the middle of a for loop or out of a finally clause.

- l(ist) [first[, last]] List source code for the current file. Without arguments, list 11 lines around the current line or continue the previous listing. With one argument, list 11 lines around at that line. With two arguments, list the given range; if the second argument is less than the first, it is interpreted as a count.
- **a(rgs)** Print the argument list of the current function.
- **p** *expression* Evaluate the *expression* in the current context and print its value. **Note:** 'print' can also be used, but is not a debugger command this executes the Python print statement.
- **pp** expression Like the 'p' command, except the value of the expression is pretty-printed using the pprint module.
- alias [name [command]] Creates an alias called name that executes command. The command must not be enclosed in quotes. Replaceable parameters can be indicated by '%1', '%2', and so on, while '%*' is replaced by all the parameters. If no command is given, the current alias for name is shown. If no arguments are given, all aliases are listed.

Aliases may be nested and can contain anything that can be legally typed at the pdb prompt. Note that internal pdb commands *can* be overridden by aliases. Such a command is then hidden until the alias is removed. Aliasing is recursively applied to the first word of the command line; all other words in the line are left alone.

As an example, here are two useful aliases (especially when placed in the '.pdbrc' file):

```
#Print instance variables (usage "pi classInst")
alias pi for k in %1.__dict__.keys(): print "%1.",k,"=",%1.__dict__[k]
#Print instance variables in self
alias ps pi self
```

unalias name Deletes the specified alias.

[!] statement Execute the (one-line) statement in the context of the current stack frame. The exclamation point can be omitted unless the first word of the statement resembles a debugger command. To set a global variable, you can prefix the assignment command with a 'global' command on the same line, e.g.:

```
(Pdb) global list_options; list_options = ['-l']
(Pdb)
```

q(uit) Quit from the debugger. The program being executed is aborted.

9.2 How It Works

Some changes were made to the interpreter:

- ullet sys.settrace(func) sets the global trace function
- there can also a local trace function (see later)

Trace functions have three arguments: *frame*, *event*, and *arg. frame* is the current stack frame. *event* is a string: 'call', 'line', 'return', 'exception', 'c_call', 'c_return', or 'c_exception'. *arg* depends on the event type.

The global trace function is invoked (with *event* set to 'call') whenever a new local scope is entered; it should return a reference to the local trace function to be used that scope, or None if the scope shouldn't be traced.

The local trace function should return a reference to itself (or to another function for further tracing in that scope), or None to turn off tracing in that scope.

Instance methods are accepted (and very useful!) as trace functions.

The events have the following meaning:

- 'call' A function is called (or some other code block entered). The global trace function is called; *arg* is None; the return value specifies the local trace function.
- 'line' The interpreter is about to execute a new line of code (sometimes multiple line events on one line exist).

 The local trace function is called; *arg* is None; the return value specifies the new local trace function.
- **'return'** A function (or other code block) is about to return. The local trace function is called; *arg* is the value that will be returned. The trace function's return value is ignored.
- **'exception'** An exception has occurred. The local trace function is called; *arg* is a triple (*exception*, *value*, *traceback*); the return value specifies the new local trace function.
- 'c_call' A C function is about to be called. This may be an extension function or a builtin. *arg* is the C function object.
- 'c_return' A C function has returned. arg is None.
- 'c_exception' A C function has thrown an exception. arg is None.

Note that as an exception is propagated down the chain of callers, an 'exception' event is generated at each level

For more information on code and frame objects, refer to the *Python Reference Manual*.

9.2. How It Works 453

The Python Profiler

Copyright © 1994, by InfoSeek Corporation, all rights reserved.

Written by James Roskind.1

Permission to use, copy, modify, and distribute this Python software and its associated documentation for any purpose (subject to the restriction in the following sentence) without fee is hereby granted, provided that the above copyright notice appears in all copies, and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of InfoSeek not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission. This permission is explicitly restricted to the copying and modification of the software to remain in Python, compiled Python, or other languages (such as C) wherein the modified or derived code is exclusively imported into a Python module.

INFOSEEK CORPORATION DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL INFOSEEK CORPORATION BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

The profiler was written after only programming in Python for 3 weeks. As a result, it is probably clumsy code, but I don't know for sure yet 'cause I'm a beginner:-). I did work hard to make the code run fast, so that profiling would be a reasonable thing to do. I tried not to repeat code fragments, but I'm sure I did some stuff in really awkward ways at times. Please send suggestions for improvements to: jar@netscape.com. I won't promise *any* support. ...but I'd appreciate the feedback.

10.1 Introduction to the profiler

A *profiler* is a program that describes the run time performance of a program, providing a variety of statistics. This documentation describes the profiler functionality provided in the modules profile and pstats. This profiler provides *deterministic profiling* of any Python programs. It also provides a series of report generation tools to allow users to rapidly examine the results of a profile operation.

10.2 How Is This Profiler Different From The Old Profiler?

(This section is of historical importance only; the old profiler discussed here was last seen in Python 1.1.)

The big changes from old profiling module are that you get more information, and you pay less CPU time. It's not a trade-off, it's a trade-up.

To be specific:

Bugs removed: Local stack frame is no longer molested, execution time is now charged to correct functions.

¹Updated and converted to LATEX by Guido van Rossum. The references to the old profiler are left in the text, although it no longer exists.

Accuracy increased: Profiler execution time is no longer charged to user's code, calibration for platform is supported, file reads are not done *by* profiler *during* profiling (and charged to user's code!).

Speed increased: Overhead CPU cost was reduced by more than a factor of two (perhaps a factor of five), lightweight profiler module is all that must be loaded, and the report generating module (pstats) is not needed during profiling.

Recursive functions support: Cumulative times in recursive functions are correctly calculated; recursive entries are counted.

Large growth in report generating UI: Distinct profiles runs can be added together forming a comprehensive report; functions that import statistics take arbitrary lists of files; sorting criteria is now based on keywords (instead of 4 integer options); reports shows what functions were profiled as well as what profile file was referenced; output format has been improved.

10.3 Instant Users Manual

This section is provided for users that "don't want to read the manual." It provides a very brief overview, and allows a user to rapidly perform profiling on an existing application.

To profile an application with a main entry point of foo(), you would add the following to your module:

```
import profile
profile.run('foo()')
```

The above action would cause foo() to be run, and a series of informative lines (the profile) to be printed. The above approach is most useful when working with the interpreter. If you would like to save the results of a profile into a file for later examination, you can supply a file name as the second argument to the run() function:

```
import profile
profile.run('foo()', 'fooprof')
```

The file 'profile.py' can also be invoked as a script to profile another script. For example:

```
python -m profile myscript.py
```

'profile.py' accepts two optional arguments on the command line:

```
profile.py [-o output_file] [-s sort_order]
```

-s only applies to standard output (-o is not supplied). Look in the Stats documentation for valid sort values.

When you wish to review the profile, you should use the methods in the pstats module. Typically you would load the statistics data as follows:

```
import pstats
p = pstats.Stats('fooprof')
```

The class Stats (the above code just created an instance of this class) has a variety of methods for manipulating and printing the data that was just read into p. When you ran profile.run() above, what was printed was the result of three method calls:

```
p.strip_dirs().sort_stats(-1).print_stats()
```

The first method removed the extraneous path from all the module names. The second method sorted all the entries according to the standard module/line/name string that is printed (this is to comply with the semantics of the old profiler). The third method printed out all the statistics. You might try the following sort calls:

```
p.sort_stats('name')
p.print_stats()
```

The first call will actually sort the list by function name, and the second call will print out the statistics. The following are some interesting calls to experiment with:

```
p.sort_stats('cumulative').print_stats(10)
```

This sorts the profile by cumulative time in a function, and then only prints the ten most significant lines. If you want to understand what algorithms are taking time, the above line is what you would use.

If you were looking to see what functions were looping a lot, and taking a lot of time, you would do:

```
p.sort_stats('time').print_stats(10)
```

to sort according to time spent within each function, and then print the statistics for the top ten functions.

You might also try:

```
p.sort_stats('file').print_stats('__init__')
```

This will sort all the statistics by file name, and then print out statistics for only the class init methods (since they are spelled with __init__ in them). As one final example, you could try:

```
p.sort_stats('time', 'cum').print_stats(.5, 'init')
```

This line sorts statistics with a primary key of time, and a secondary key of cumulative time, and then prints out some of the statistics. To be specific, the list is first culled down to 50% (re: '.5') of its original size, then only lines containing init are maintained, and that sub-sub-list is printed.

If you wondered what functions called the above functions, you could now (p is still sorted according to the last criteria) do:

```
p.print_callers(.5, 'init')
```

and you would get a list of callers for each of the listed functions.

If you want more functionality, you're going to have to read the manual, or guess what the following functions do:

```
p.print_callees()
p.add('fooprof')
```

Invoked as a script, the pstats module is a statistics browser for reading and examining profile dumps. It has a simple line-oriented interface (implemented using cmd) and interactive help.

10.4 What Is Deterministic Profiling?

Deterministic profiling is meant to reflect the fact that all function call, function return, and exception events are monitored, and precise timings are made for the intervals between these events (during which time the user's code is executing). In contrast, statistical profiling (which is not done by this module) randomly samples the effective instruction pointer, and deduces where time is being spent. The latter technique traditionally involves less overhead (as the code does not need to be instrumented), but provides only relative indications of where time is being spent.

In Python, since there is an interpreter active during execution, the presence of instrumented code is not required to do deterministic profiling. Python automatically provides a *hook* (optional callback) for each event. In addition, the interpreted nature of Python tends to add so much overhead to execution, that deterministic profiling tends to only add small processing overhead in typical applications. The result is that deterministic profiling is not that expensive, yet provides extensive run time statistics about the execution of a Python program.

Call count statistics can be used to identify bugs in code (surprising counts), and to identify possible inline-expansion points (high call counts). Internal time statistics can be used to identify "hot loops" that should be carefully optimized. Cumulative time statistics should be used to identify high level errors in the selection of algorithms. Note that the unusual handling of cumulative times in this profiler allows statistics for recursive implementations of algorithms to be directly compared to iterative implementations.

10.5 Reference Manual

The primary entry point for the profiler is the global function profile.run(). It is typically used to create any profile information. The reports are formatted and printed using methods of the class pstats. Stats. The following is a description of all of these standard entry points and functions. For a more in-depth view of some of the code, consider reading the later section on Profiler Extensions, which includes discussion of how to derive "better" profilers from the classes presented, or reading the source code for these modules.

```
run (command, filename)
```

This function takes a single argument that has can be passed to the exec statement, and an optional file name. In all cases this routine attempts to exec its first argument, and gather profiling statistics from the execution. If no file name is present, then this function automatically prints a simple profiling report, sorted by the standard name string (file/line/function-name) that is presented in each line. The following is a typical output from such a call:

```
main()
    2706 function calls (2004 primitive calls) in 4.504 CPU seconds

Ordered by: standard name

ncalls tottime percall cumtime percall filename:lineno(function)
    2    0.006    0.003    0.953    0.477 pobject.py:75(save_objects)
43/3    0.533    0.012    0.749    0.250 pobject.py:99(evaluate)
```

The first line indicates that this profile was generated by the call:

profile.run('main()'), and hence the exec'ed string is 'main()'. The second line indicates that 2706 calls were monitored. Of those calls, 2004 were *primitive*. We define *primitive* to mean that the call was not induced via recursion. The next line: Ordered by: standard name, indicates that the text string in the far right column was used to sort the output. The column headings include:

ncalls for the number of calls,

tottime for the total time spent in the given function (and excluding time made in calls to sub-functions),

percall is the quotient of tottime divided by ncalls

cumtime is the total time spent in this and all subfunctions (from invocation till exit). This figure is accurate *even* for recursive functions.

percall is the quotient of cumtime divided by primitive calls

filename:lineno(function) provides the respective data of each function

When there are two numbers in the first column (for example, '43/3'), then the latter is the number of primitive calls, and the former is the actual number of calls. Note that when the function does not recurse, these two values are the same, and only the single figure is printed.

runctx(command, globals, locals[, filename])

This function is similar to profile.run(), with added arguments to supply the globals and locals dictionaries for the *command* string.

Analysis of the profiler data is done using this class from the pstats module:

class Stats(filename[, ...])

This class constructor creates an instance of a "statistics object" from a *filename* (or set of filenames). Stats objects are manipulated by methods, in order to print useful reports.

The file selected by the above constructor must have been created by the corresponding version of profile. To be specific, there is *no* file compatibility guaranteed with future versions of this profiler, and there is no compatibility with files produced by other profilers (such as the old system profiler).

If several files are provided, all the statistics for identical functions will be coalesced, so that an overall view of several processes can be considered in a single report. If additional files need to be combined with data in an existing Stats object, the add() method can be used.

10.5.1 The Stats Class

Stats objects have the following methods:

strip_dirs()

This method for the Stats class removes all leading path information from file names. It is very useful in reducing the size of the printout to fit within (close to) 80 columns. This method modifies the object, and the stripped information is lost. After performing a strip operation, the object is considered to have its entries in a "random" order, as it was just after object initialization and loading. If strip_dirs() causes two function names to be indistinguishable (they are on the same line of the same filename, and have the same function name), then the statistics for these two entries are accumulated into a single entry.

add(filename[, ...])

This method of the Stats class accumulates additional profiling information into the current profiling object. Its arguments should refer to filenames created by the corresponding version of profile.run(). Statistics for identically named (re: file, line, name) functions are automatically accumulated into single function statistics.

dump_stats(filename)

Save the data loaded into the Stats object to a file named *filename*. The file is created if it does not exist, and is overwritten if it already exists. This is equivalent to the method of the same name on the profile.Profile class. New in version 2.3.

sort_stats(key[, ...])

This method modifies the Stats object by sorting it according to the supplied criteria. The argument is typically a string identifying the basis of a sort (example: 'time' or 'name').

When more than one key is provided, then additional keys are used as secondary criteria when there is equality in all keys selected before them. For example, <code>sort_stats('name', 'file')</code> will sort all the entries according to their function name, and resolve all ties (identical function names) by sorting by file name

Abbreviations can be used for any key names, as long as the abbreviation is unambiguous. The following are the keys currently defined:

10.5. Reference Manual 459

Valid Arg	Meaning
'calls'	call count
'cumulative'	cumulative time
'file'	file name
'module'	file name
'pcalls'	primitive call count
'line'	line number
'name'	function name
'nfl'	name/file/line
'stdname'	standard name
'time'	internal time

Note that all sorts on statistics are in descending order (placing most time consuming items first), where as name, file, and line number searches are in ascending order (alphabetical). The subtle distinction between 'nfl' and 'stdname' is that the standard name is a sort of the name as printed, which means that the embedded line numbers get compared in an odd way. For example, lines 3, 20, and 40 would (if the file names were the same) appear in the string order 20, 3 and 40. In contrast, 'nfl' does a numeric compare of the line numbers. In fact, sort_stats('nfl') is the same as sort_stats('name', 'file', 'line').

For compatibility with the old profiler, the numeric arguments -1, 0, 1, and 2 are permitted. They are interpreted as 'stdname', 'calls', 'time', and 'cumulative' respectively. If this old style format (numeric) is used, only one sort key (the numeric key) will be used, and additional arguments will be silently ignored.

reverse_order()

This method for the Stats class reverses the ordering of the basic list within the object. This method is provided primarily for compatibility with the old profiler. Its utility is questionable now that ascending vs descending order is properly selected based on the sort key of choice.

print_stats([restriction, ...])

This method for the Stats class prints out a report as described in the profile.run() definition.

The order of the printing is based on the last sort_stats() operation done on the object (subject to caveats in add() and strip_dirs()).

The arguments provided (if any) can be used to limit the list down to the significant entries. Initially, the list is taken to be the complete set of profiled functions. Each restriction is either an integer (to select a count of lines), or a decimal fraction between 0.0 and 1.0 inclusive (to select a percentage of lines), or a regular expression (to pattern match the standard name that is printed; as of Python 1.5b1, this uses the Perl-style regular expression syntax defined by the re module). If several restrictions are provided, then they are applied sequentially. For example:

```
print_stats(.1, 'foo:')
```

would first limit the printing to first 10% of list, and then only print functions that were part of filename '.*foo:'. In contrast, the command:

```
print_stats('foo:', .1)
```

would limit the list to all functions having file names '.*foo:', and then proceed to only print the first 10% of them.

print_callers([restriction, ...])

This method for the Stats class prints a list of all functions that called each function in the profiled database. The ordering is identical to that provided by print_stats(), and the definition of the restricting argument is also identical. For convenience, a number is shown in parentheses after each caller to show how many times this specific call was made. A second non-parenthesized number is the cumulative time spent in the function at the right.

print_callees([restriction, ...])

This method for the Stats class prints a list of all function that were called by the indicated function.

Aside from this reversal of direction of calls (re: called vs was called by), the arguments and ordering are identical to the print_callers() method.

ignore()

Deprecated since release 1.5.1. This is not needed in modern versions of Python.²

10.6 Limitations

One limitation has to do with accuracy of timing information. There is a fundamental problem with deterministic profilers involving accuracy. The most obvious restriction is that the underlying "clock" is only ticking at a rate (typically) of about .001 seconds. Hence no measurements will be more accurate than the underlying clock. If enough measurements are taken, then the "error" will tend to average out. Unfortunately, removing this first error induces a second source of error.

The second problem is that it "takes a while" from when an event is dispatched until the profiler's call to get the time actually *gets* the state of the clock. Similarly, there is a certain lag when exiting the profiler event handler from the time that the clock's value was obtained (and then squirreled away), until the user's code is once again executing. As a result, functions that are called many times, or call many functions, will typically accumulate this error. The error that accumulates in this fashion is typically less than the accuracy of the clock (less than one clock tick), but it *can* accumulate and become very significant. This profiler provides a means of calibrating itself for a given platform so that this error can be probabilistically (on the average) removed. After the profiler is calibrated, it will be more accurate (in a least square sense), but it will sometimes produce negative numbers (when call counts are exceptionally low, and the gods of probability work against you:-).) Do *not* be alarmed by negative numbers in the profile. They should *only* appear if you have calibrated your profiler, and the results are actually better than without calibration.

10.7 Calibration

The profiler subtracts a constant from each event handling time to compensate for the overhead of calling the time function, and socking away the results. By default, the constant is 0. The following procedure can be used to obtain a better constant for a given platform (see discussion in section Limitations above).

```
import profile
pr = profile.Profile()
for i in range(5):
    print pr.calibrate(10000)
```

The method executes the number of Python calls given by the argument, directly and again under the profiler, measuring the time for both. It then computes the hidden overhead per profiler event, and returns that as a float. For example, on an 800 MHz Pentium running Windows 2000, and using Python's time.clock() as the timer, the magical number is about 12.5e-6.

The object of this exercise is to get a fairly consistent result. If your computer is *very* fast, or your timer function has poor resolution, you might have to pass 100000, or even 1000000, to get consistent results.

When you have a consistent answer, there are three ways you can use it:³

10.6. Limitations 461

²This was once necessary, when Python would print any unused expression result that was not None. The method is still defined for backward compatibility.

³Prior to Python 2.2, it was necessary to edit the profiler source code to embed the bias as a literal number. You still can, but that method is no longer described, because no longer needed.

```
import profile

# 1. Apply computed bias to all Profile instances created hereafter.
profile.Profile.bias = your_computed_bias

# 2. Apply computed bias to a specific Profile instance.
pr = profile.Profile()
pr.bias = your_computed_bias

# 3. Specify computed bias in instance constructor.
pr = profile.Profile(bias=your_computed_bias)
```

If you have a choice, you are better off choosing a smaller constant, and then your results will "less often" show up as negative in profile statistics.

10.8 Extensions — Deriving Better Profilers

The Profile class of module profile was written so that derived classes could be developed to extend the profiler. The details are not described here, as doing this successfully requires an expert understanding of how the Profile class works internally. Study the source code of module profile carefully if you want to pursue this.

If all you want to do is change how current time is determined (for example, to force use of wall-clock time or elapsed process time), pass the timing function you want to the Profile class constructor:

```
pr = profile.Profile(your_time_func)
```

The resulting profiler will then call your_time_func(). The function should return a single number, or a list of numbers whose sum is the current time (like what os.times() returns). If the function returns a single time number, or the list of returned numbers has length 2, then you will get an especially fast version of the dispatch routine.

Be warned that you should calibrate the profiler class for the timer function that you choose. For most machines, a timer that returns a lone integer value will provide the best results in terms of low overhead during profiling. (os.times() is *pretty* bad, as it returns a tuple of floating point values). If you want to substitute a better timer in the cleanest fashion, derive a class and hardwire a replacement dispatch method that best handles your timer call, along with the appropriate calibration constant.

10.9 hotshot — High performance logging profiler

New in version 2.2.

This module provides a nicer interface to the _hotshot C module. Hotshot is a replacement for the existing profile module. As it's written mostly in C, it should result in a much smaller performance impact than the existing profile module.

Warning: The hotshot profiler does not yet work well with threads. It is useful to use an unthreaded script to run the profiler over the code you're interested in measuring if at all possible.

```
class Profile(logfile[, lineevents[, linetimings]])
```

The profiler object. The argument *logfile* is the name of a log file to use for logged profile data. The argument *lineevents* specifies whether to generate events for every source line, or just on function call/return. It defaults to 0 (only log function call/return). The argument *linetimings* specifies whether to record timing information. It defaults to 1 (store timing information).

10.9.1 Profile Objects

Profile objects have the following methods:

addinfo(key, value)

Add an arbitrary labelled value to the profile output.

close()

Close the logfile and terminate the profiler.

fileno()

Return the file descriptor of the profiler's log file.

run(cmd)

Profile an exec-compatible string in the script environment. The globals from the __main__ module are used as both the globals and locals for the script.

```
runcall(func, *args, **keywords)
```

Profile a single call of a callable. Additional positional and keyword arguments may be passed along; the result of the call is returned, and exceptions are allowed to propagate cleanly, while ensuring that profiling is disabled on the way out.

runctx(cmd, globals, locals)

Evaluate an exec-compatible string in a specific environment. The string is compiled before profiling begins.

start()

Start the profiler.

stop()

Stop the profiler.

10.9.2 Using hotshot data

New in version 2.2.

This module loads hotshot profiling data into the standard pstats Stats objects.

load(filename)

Load hotshot data from *filename*. Returns an instance of the pstats. Stats class.

See Also:

```
Module profile (section 10.5):
```

The profile module's Stats class

10.9.3 Example Usage

Note that this example runs the python "benchmark" pystones. It can take some time to run, and will produce large output files.

10.10 timeit — Measure execution time of small code snippets

New in version 2.3.

This module provides a simple way to time small bits of Python code. It has both command line as well as callable interfaces. It avoids a number of common traps for measuring execution times. See also Tim Peters' introduction to the "Algorithms" chapter in the *Python Cookbook*, published by O'Reilly.

The module defines the following public class:

```
class Timer([stmt='pass' [, setup='pass' [, timer=;timer function;]]]) Class for timing execution speed of small code snippets.
```

The constructor takes a statement to be timed, an additional statement used for setup, and a timer function. Both statements default to 'pass'; the timer function is platform-dependent (see the module doc string). The statements may contain newlines, as long as they don't contain multi-line string literals.

To measure the execution time of the first statement, use the timeit() method. The repeat() method is a convenience to call timeit() multiple times and return a list of results.

```
print_exc([file=None])
```

Helper to print a traceback from the timed code.

Typical use:

```
t = Timer(...)  # outside the try/except
try:
    t.timeit(...)  # or t.repeat(...)
except:
    t.print_exc()
```

The advantage over the standard traceback is that source lines in the compiled template will be displayed. The optional *file* argument directs where the traceback is sent; it defaults to sys.stderr.

```
repeat([repeat=3 [, number=1000000]])
Call timeit() a few times.
```

This is a convenience function that calls the timeit() repeatedly, returning a list of results. The first argument specifies how many times to call timeit(). The second argument specifies the *number* argument for timeit().

Note: It's tempting to calculate mean and standard deviation from the result vector and report these. However, this is not very useful. In a typical case, the lowest value gives a lower bound for how fast your machine can run the given code snippet; higher values in the result vector are typically not caused by variability in Python's speed, but by other processes interfering with your timing accuracy. So the min() of the result is probably the only number you should be interested in. After that, you should look at the entire vector and apply common sense rather than statistics.

```
timeit([number=1000000])
```

Time *number* executions of the main statement. This executes the setup statement once, and then returns the time it takes to execute the main statement a number of times, measured in seconds as a float. The argument is the number of times through the loop, defaulting to one million. The main statement, the setup statement and the timer function to be used are passed to the constructor.

Note: By default, timeit() temporarily turns off garbage collection during the timing. The advantage of this approach is that it makes independent timings more comparable. This disadvantage is that GC may be an important component of the performance of the function being measured. If so, GC can be re-enabled as the first statement in the *setup* string. For example:

```
timeit.Timer('for i in xrange(10): oct(i)', 'gc.enable()').timeit()
```

10.10.1 Command Line Interface

When called as a program from the command line, the following form is used:

```
python timeit.py [-n N] [-r N] [-s S] [-t] [-c] [-h] [statement ...]
```

where the following options are understood:

- **-n N/--number=N** how many times to execute 'statement'
- **-r N/--repeat=N** how many times to repeat the timer (default 3)
- -s S/--setup=S statement to be executed once initially (default 'pass')
- -t/--time use time.time() (default on all platforms but Windows)
- $\textbf{-c/--clock} \ \ use \ \texttt{time.clock()} \ \ (default \ on \ Windows)$
- -v/--verbose print raw timing results; repeat for more digits precision
- -h/--help print a short usage message and exit

A multi-line statement may be given by specifying each line as a separate statement argument; indented lines are possible by enclosing an argument in quotes and using leading spaces. Multiple **-s** options are treated similarly.

If **-n** is not given, a suitable number of loops is calculated by trying successive powers of 10 until the total time is at least 0.2 seconds.

The default timer function is platform dependent. On Windows, time.clock() has microsecond granularity but time.time()'s granularity is 1/60th of a second; on UNIX, time.clock() has 1/100th of a second granularity and time.time() is much more precise. On either platform, the default timer functions measure wall clock time, not the CPU time. This means that other processes running on the same computer may interfere with the timing. The best thing to do when accurate timing is necessary is to repeat the timing a few times and use the best time. The -r option is good for this; the default of 3 repetitions is probably enough in most cases. On UNIX, you can use time.clock() to measure CPU time.

Note: There is a certain baseline overhead associated with executing a pass statement. The code here doesn't try to hide it, but you should be aware of it. The baseline overhead can be measured by invoking the program without arguments.

The baseline overhead differs between Python versions! Also, to fairly compare older Python versions to Python 2.3, you may want to use Python's **-O** option for the older versions to avoid timing SET_LINENO instructions.

10.10.2 Examples

Here are two example sessions (one using the command line, one using the module interface) that compare the cost of using hasattr() vs. try/except to test for missing and present object attributes.

```
% timeit.py 'try:' ' str.__nonzero__' 'except AttributeError:' ' pass'
100000 loops, best of 3: 15.7 usec per loop
% timeit.py 'if hasattr(str, "__nonzero__"): pass'
100000 loops, best of 3: 4.26 usec per loop
% timeit.py 'try:' ' int.__nonzero__' 'except AttributeError:' ' pass'
1000000 loops, best of 3: 1.43 usec per loop
% timeit.py 'if hasattr(int, "__nonzero__"): pass'
100000 loops, best of 3: 2.23 usec per loop
>>> import timeit
>>> s = """\
... try:
      str.__nonzero_
. . .
... except AttributeError:
      pass
. . .
... """
>>> t = timeit.Timer(stmt=s)
>>> print "%.2f usec/pass" % (1000000 * t.timeit(number=100000)/100000)
17.09 usec/pass
>>> s = """\
... if hasattr(str, '__nonzero__'): pass
>>> t = timeit.Timer(stmt=s)
>>> print "%.2f usec/pass" % (1000000 * t.timeit(number=100000)/100000)
4.85 usec/pass
>>> s = """\
... try:
      int.__nonzero__
... except AttributeError:
... pass
... """
>>> t = timeit.Timer(stmt=s)
>>> print "%.2f usec/pass" % (1000000 * t.timeit(number=100000)/100000)
1.97 usec/pass
>>> s = """\
... if hasattr(int, '__nonzero__'): pass
... """
>>> t = timeit.Timer(stmt=s)
>>> print "%.2f usec/pass" % (1000000 * t.timeit(number=100000)/100000)
3.15 usec/pass
```

To give the timeit module access to functions you define, you can pass a setup parameter which contains an import statement:

```
def test():
    "Stupid test function"
    L = []
    for i in range(100):
        L.append(i)

if __name__ == '__main__':
    from timeit import Timer
    t = Timer("test()", "from __main__ import test")
    print t.timeit()
```

Internet Protocols and Support

The modules described in this chapter implement Internet protocols and support for related technology. They are all implemented in Python. Most of these modules require the presence of the system-dependent module socket, which is currently supported on most popular platforms. Here is an overview:

webbrowser Easy-to-use controller for Web browsers.

cgi Common Gateway Interface support, used to interpret forms in server-side scripts.

cgitb Configurable traceback handler for CGI scripts.

urllib Open an arbitrary network resource by URL (requires sockets).
urllib2 An extensible library for opening URLs using a variety of protocols

HTTP and HTTPS protocol client (requires sockets).

ftplib FTP protocol client (requires sockets).

gopherlib Gopher protocol client (requires sockets).

poplib POP3 protocol client (requires sockets).

imaplib IMAP4 protocol client (requires sockets).

nntplib NNTP protocol client (requires sockets).

smtplib SMTP protocol client (requires sockets).

smtpd Implement a flexible SMTP server

telnetlib Telnet client class.

httplib

urlparse Parse URLs into components.

SocketServer A framework for network servers.

Basic HTTP server (base class for SimpleHTTPServer and CGIHTTPServer).

SimpleHTTPServer This module provides a basic request handler for HTTP servers.

CGIHTTPServer This module provides a request handler for HTTP servers which can run CGI scripts.

cookielib Cookie handling for HTTP clients

Cookie Support for HTTP state management (cookies).

xmlrpclib XML-RPC client access.

SimpleXMLRPCServer Basic XML-RPC server implementation.

DocxMLRPCServer Self-documenting XML-RPC server implementation.

asyncore A base class for developing asynchronous socket handling services.

asynchat Support for asynchronous command/response protocols.

11.1 webbrowser — Convenient Web-browser controller

The webbrowser module provides a very high-level interface to allow displaying Web-based documents to users. The controller objects are easy to use and are platform-independent. Under most circumstances, simply calling the open() function from this module will do the right thing.

Under UNIX, graphical browsers are preferred under X11, but text-mode browsers will be used if graphical browsers are not available or an X11 display isn't available. If text-mode browsers are used, the calling process will block until the user exits the browser.

Under UNIX, if the environment variable BROWSER exists, it is interpreted to override the platform default list of browsers, as a colon-separated list of browsers to try in order. When the value of a list part contains the string %s, then it is interpreted as a literal browser command line to be used with the argument URL substituted for the

%s; if the part does not contain %s, it is simply interpreted as the name of the browser to launch.

For non-UNIX platforms, or when X11 browsers are available on UNIX, the controlling process will not wait for the user to finish with the browser, but allow the browser to maintain its own window on the display.

The following exception is defined:

exception Error

Exception raised when a browser control error occurs.

The following functions are defined:

$$open(url[, new=0][, autoraise=1])$$

Display *url* using the default browser. If *new* is true, a new browser window is opened if possible. If *autoraise* is true, the window is raised if possible (note that under many window managers this will occur regardless of the setting of this variable).

open_new(url)

Open *url* in a new window of the default browser, if possible, otherwise, open *url* in the only browser window.

get([name])

Return a controller object for the browser type *name*. If *name* is empty, return a controller for a default browser appropriate to the caller's environment.

register(name, constructor[, instance])

Register the browser type *name*. Once a browser type is registered, the get() function can return a controller for that browser type. If *instance* is not provided, or is None, *constructor* will be called without parameters to create an instance when needed. If *instance* is provided, *constructor* will never be called, and may be None.

This entry point is only useful if you plan to either set the BROWSER variable or call get with a nonempty argument matching the name of a handler you declare.

A number of browser types are predefined. This table gives the type names that may be passed to the get() function and the corresponding instantiations for the controller classes, all defined in this module.

Type Name	Class Name	Notes
'mozilla'	Netscape('mozilla')	
'netscape'	Netscape('netscape')	
'mosaic'	GenericBrowser('mosaic %s &')	
′kfm′	Konqueror()	(1)
'grail'	Grail()	
'links'	GenericBrowser('links %s')	
'lynx'	GenericBrowser('lynx %s')	
'w3m'	GenericBrowser('w3m %s')	
'windows-default'	WindowsDefault	(2)
'internet-config'	InternetConfig	(3)

Notes:

- (1) "Konqueror" is the file manager for the KDE desktop environment for UNIX, and only makes sense to use if KDE is running. Some way of reliably detecting KDE would be nice; the KDEDIR variable is not sufficient. Note also that the name "kfm" is used even when using the **konqueror** command with KDE 2—the implementation selects the best strategy for running Konqueror.
- (2) Only on Windows platforms; requires the common extension modules win32api and win32con.
- (3) Only on MacOS platforms; requires the standard MacPython ic module, described in the *Macintosh Library Modules* manual.

11.1.1 Browser Controller Objects

Browser controllers provide two methods which parallel two of the module-level convenience functions:

```
open(url[, new])
```

Display *url* using the browser handled by this controller. If *new* is true, a new browser window is opened if possible.

open_new(url)

Open *url* in a new window of the browser handled by this controller, if possible, otherwise, open *url* in the only browser window.

11.2 cgi — Common Gateway Interface support.

Support module for Common Gateway Interface (CGI) scripts.

This module defines a number of utilities for use by CGI scripts written in Python.

11.2.1 Introduction

A CGI script is invoked by an HTTP server, usually to process user input submitted through an HTML <FORM> or <ISINDEX> element.

Most often, CGI scripts live in the server's special 'cgi-bin' directory. The HTTP server places all sorts of information about the request (such as the client's hostname, the requested URL, the query string, and lots of other goodies) in the script's shell environment, executes the script, and sends the script's output back to the client.

The script's input is connected to the client too, and sometimes the form data is read this way; at other times the form data is passed via the "query string" part of the URL. This module is intended to take care of the different cases and provide a simpler interface to the Python script. It also provides a number of utilities that help in debugging scripts, and the latest addition is support for file uploads from a form (if your browser supports it — Grail 0.3 and Netscape 2.0 do).

The output of a CGI script should consist of two sections, separated by a blank line. The first section contains a number of headers, telling the client what kind of data is following. Python code to generate a minimal header section looks like this:

```
print "Content-Type: text/html"  # HTML is following
print  # blank line, end of headers
```

The second section is usually HTML, which allows the client software to display nicely formatted text with header, in-line images, etc. Here's Python code that prints a simple piece of HTML:

```
print "<TITLE>CGI script output</TITLE>"
print "<H1>This is my first CGI script</H1>"
print "Hello, world!"
```

11.2.2 Using the cgi module

Begin by writing 'import cgi'. Do not use 'from cgi import *'—the module defines all sorts of names for its own use or for backward compatibility that you don't want in your namespace.

When you write a new script, consider adding the line:

```
import cgitb; cgitb.enable()
```

This activates a special exception handler that will display detailed reports in the Web browser if any errors occur. If you'd rather not show the guts of your program to users of your script, you can have the reports saved to files

instead, with a line like this:

```
import cgitb; cgitb.enable(display=0, logdir="/tmp")
```

It's very helpful to use this feature during script development. The reports produced by cgitb provide information that can save you a lot of time in tracking down bugs. You can always remove the cgitb line later when you have tested your script and are confident that it works correctly.

To get at submitted form data, it's best to use the FieldStorage class. The other classes defined in this module are provided mostly for backward compatibility. Instantiate it exactly once, without arguments. This reads the form contents from standard input or the environment (depending on the value of various environment variables set according to the CGI standard). Since it may consume standard input, it should be instantiated only once.

The FieldStorage instance can be indexed like a Python dictionary, and also supports the standard dictionary methods has_key() and keys(). The built-in len() is also supported. Form fields containing empty strings are ignored and do not appear in the dictionary; to keep such values, provide a true value for the optional <code>keep_blank_values</code> keyword parameter when creating the FieldStorage instance.

For instance, the following code (which assumes that the Content-Type: header and blank line have already been printed) checks that the fields name and addr are both set to a non-empty string:

```
form = cgi.FieldStorage()
if not (form.has_key("name") and form.has_key("addr")):
    print "<H1>Error</H1>"
    print "Please fill in the name and addr fields."
    return
print "name:", form["name"].value
print "addr:", form["addr"].value
...further form processing here...
```

Here the fields, accessed through 'form[key]', are themselves instances of FieldStorage (or MiniFieldStorage, depending on the form encoding). The value attribute of the instance yields the string value of the field. The getvalue() method returns this string value directly; it also accepts an optional second argument as a default to return if the requested key is not present.

If the submitted form data contains more than one field with the same name, the object retrieved by 'form[key]' is not a FieldStorage or MiniFieldStorage instance but a list of such instances. Similarly, in this situation, 'form.getvalue(key)' would return a list of strings. If you expect this possibility (when your HTML form contains multiple fields with the same name), use the getlist() function, which always returns a list of values (so that you do not need to special-case the single item case). For example, this code concatenates any number of username fields, separated by commas:

```
value = form.getlist("username")
usernames = ",".join(value)
```

If a field represents an uploaded file, accessing the value via the value attribute or the <code>getvalue()</code> method reads the entire file in memory as a string. This may not be what you want. You can test for an uploaded file by testing either the <code>filename</code> attribute or the <code>file</code> attribute. You can then read the data at leisure from the <code>file</code> attribute:

```
fileitem = form["userfile"]
if fileitem.file:
    # It's an uploaded file; count lines
    linecount = 0
    while 1:
        line = fileitem.file.readline()
        if not line: break
        linecount = linecount + 1
```

The file upload draft standard entertains the possibility of uploading multiple files from one field (using a recursive multipart/* encoding). When this occurs, the item will be a dictionary-like FieldStorage item. This can be determined by testing its type attribute, which should be multipart/form-data (or perhaps another MIME type matching multipart/*). In this case, it can be iterated over recursively just like the top-level form object.

When a form is submitted in the "old" format (as the query string or as a single data part of type application/x-www-form-urlencoded), the items will actually be instances of the class MiniFieldStorage. In this case, the list, file, and filename attributes are always None.

11.2.3 Higher Level Interface

New in version 2.2.

The previous section explains how to read CGI form data using the FieldStorage class. This section describes a higher level interface which was added to this class to allow one to do it in a more readable and intuitive way. The interface doesn't make the techniques described in previous sections obsolete — they are still useful to process file uploads efficiently, for example.

The interface consists of two simple methods. Using the methods you can process form data in a generic way, without the need to worry whether only one or more values were posted under one name.

In the previous section, you learned to write following code anytime you expected a user to post more than one value under one name:

```
item = form.getvalue("item")
if isinstance(item, list):
    # The user is requesting more than one item.
else:
    # The user is requesting only one item.
```

This situation is common for example when a form contains a group of multiple checkboxes with the same name:

```
<input type="checkbox" name="item" value="1" />
<input type="checkbox" name="item" value="2" />
```

In most situations, however, there's only one form control with a particular name in a form and then you expect and need only one value associated with this name. So you write a script containing for example this code:

```
user = form.getvalue("user").upper()
```

The problem with the code is that you should never expect that a client will provide valid input to your scripts. For example, if a curious user appends another 'user=foo' pair to the query string, then the script would crash, because in this situation the <code>getvalue("user")</code> method call returns a list instead of a string. Calling the <code>toupper()</code> method on a list is not valid (since lists do not have a method of this name) and results in an <code>AttributeError</code> exception.

Therefore, the appropriate way to read form data values was to always use the code which checks whether the obtained value is a single value or a list of values. That's annoying and leads to less readable scripts.

A more convenient approach is to use the methods <code>getfirst()</code> and <code>getlist()</code> provided by this higher level interface.

```
getfirst(name[, default])
```

This method always returns only one value associated with form field *name*. The method returns only the first value in case that more values were posted under such name. Please note that the order in which the values are received may vary from browser to browser and should not be counted on.¹ If no such form field or value exists then the method returns the value specified by the optional parameter *default*. This parameter defaults to None if not specified.

```
getlist(name)
```

This method always returns a list of values associated with form field *name*. The method returns an empty list if no such form field or value exists for *name*. It returns a list consisting of one item if only one such value exists.

Using these methods you can write nice compact code:

```
import cgi
form = cgi.FieldStorage()
user = form.getfirst("user", "").upper()  # This way it's safe.
for item in form.getlist("item"):
    do_something(item)
```

11.2.4 Old classes

These classes, present in earlier versions of the cgi module, are still supported for backward compatibility. New applications should use the FieldStorage class.

SvFormContentDict stores single value form content as dictionary; it assumes each field name occurs in the form only once.

FormContentDict stores multiple value form content as a dictionary (the form items are lists of values). Useful if your form contains multiple fields with the same name.

Other classes (FormContent, InterpFormContentDict) are present for backwards compatibility with really old applications only. If you still use these and would be inconvenienced when they disappeared from a next version of this module, drop me a note.

11.2.5 Functions

These are useful if you want more control, or if you want to employ some of the algorithms implemented in this module in other circumstances.

```
parse(fp[, keep_blank_values[, strict_parsing]])
```

Parse a query in the environment or from a file (the file defaults to sys.stdin). The *keep_blank_values* and *strict_parsing* parameters are passed to parse_qs() unchanged.

```
parse_qs(qs[, keep_blank_values[, strict_parsing]])
```

Parse a query string given as a string argument (data of type application/x-www-form-urlencoded). Data are returned as a dictionary. The dictionary keys are the unique query variable names and the values are lists of values for each name.

The optional argument *keep_blank_values* is a flag indicating whether blank values in URL encoded queries should be treated as blank strings. A true value indicates that blanks should be retained as blank strings. The default false value indicates that blank values are to be ignored and treated as if they were not included.

¹Note that some recent versions of the HTML specification do state what order the field values should be supplied in, but knowing whether a request was received from a conforming browser, or even from a browser at all, is tedious and error-prone.

The optional argument *strict_parsing* is a flag indicating what to do with parsing errors. If false (the default), errors are silently ignored. If true, errors raise a ValueError exception.

Use the urllib.urlencode() function to convert such dictionaries into query strings.

```
parse_qsl(qs[, keep_blank_values[, strict_parsing]])
```

Parse a query string given as a string argument (data of type application/x-www-form-urlencoded). Data are returned as a list of name, value pairs.

The optional argument *keep_blank_values* is a flag indicating whether blank values in URL encoded queries should be treated as blank strings. A true value indicates that blanks should be retained as blank strings. The default false value indicates that blank values are to be ignored and treated as if they were not included.

The optional argument *strict_parsing* is a flag indicating what to do with parsing errors. If false (the default), errors are silently ignored. If true, errors raise a ValueError exception.

Use the urllib.urlencode() function to convert such lists of pairs into query strings.

parse_multipart(fp, pdict)

Parse input of type multipart/form-data (for file uploads). Arguments are fp for the input file and pdict for a dictionary containing other parameters in the Content-Type: header.

Returns a dictionary just like parse_qs() keys are the field names, each value is a list of values for that field. This is easy to use but not much good if you are expecting megabytes to be uploaded — in that case, use the FieldStorage class instead which is much more flexible.

Note that this does not parse nested multipart parts — use FieldStorage for that.

parse_header(string)

Parse a MIME header (such as Content-Type:) into a main value and a dictionary of parameters.

test()

Robust test CGI script, usable as main program. Writes minimal HTTP headers and formats all information provided to the script in HTML form.

print_environ()

Format the shell environment in HTML.

print_form(form)

Format a form in HTML.

print_directory()

Format the current directory in HTML.

print_environ_usage()

Print a list of useful (used by CGI) environment variables in HTML.

```
escape(s, quote)
```

Convert the characters '&', '<' and '>' in string s to HTML-safe sequences. Use this if you need to display text that might contain such characters in HTML. If the optional flag *quote* is true, the double-quote character ('"') is also translated; this helps for inclusion in an HTML attribute value, as in . If the value to be quoted might include single- or double-quote characters, or both, consider using the quoteattr() function in the xml.sax.saxutils module instead.

11.2.6 Caring about security

There's one important rule: if you invoke an external program (via the os.system() or os.popen() functions. or others with similar functionality), make very sure you don't pass arbitrary strings received from the client to the shell. This is a well-known security hole whereby clever hackers anywhere on the Web can exploit a gullible CGI script to invoke arbitrary shell commands. Even parts of the URL or field names cannot be trusted, since the request doesn't have to come from your form!

To be on the safe side, if you must pass a string gotten from a form to a shell command, you should make sure the string contains only alphanumeric characters, dashes, underscores, and periods.

11.2.7 Installing your CGI script on a UNIX system

Read the documentation for your HTTP server and check with your local system administrator to find the directory where CGI scripts should be installed; usually this is in a directory 'cgi-bin' in the server tree.

Make sure that your script is readable and executable by "others"; the UNIX file mode should be 0755 octal (use 'chmod 0755 *filename*'). Make sure that the first line of the script contains #! starting in column 1 followed by the pathname of the Python interpreter, for instance:

```
#!/usr/local/bin/python
```

Make sure the Python interpreter exists and is executable by "others".

Make sure that any files your script needs to read or write are readable or writable, respectively, by "others" — their mode should be 0644 for readable and 0666 for writable. This is because, for security reasons, the HTTP server executes your script as user "nobody", without any special privileges. It can only read (write, execute) files that everybody can read (write, execute). The current directory at execution time is also different (it is usually the server's cgi-bin directory) and the set of environment variables is also different from what you get when you log in. In particular, don't count on the shell's search path for executables (PATH) or the Python module search path (PYTHONPATH) to be set to anything interesting.

If you need to load modules from a directory which is not on Python's default module search path, you can change the path in your script, before importing other modules. For example:

```
import sys
sys.path.insert(0, "/usr/home/joe/lib/python")
sys.path.insert(0, "/usr/local/lib/python")
```

(This way, the directory inserted last will be searched first!)

Instructions for non-UNIX systems will vary; check your HTTP server's documentation (it will usually have a section on CGI scripts).

11.2.8 Testing your CGI script

Unfortunately, a CGI script will generally not run when you try it from the command line, and a script that works perfectly from the command line may fail mysteriously when run from the server. There's one reason why you should still test your script from the command line: if it contains a syntax error, the Python interpreter won't execute it at all, and the HTTP server will most likely send a cryptic error to the client.

Assuming your script has no syntax errors, yet it does not work, you have no choice but to read the next section.

11.2.9 Debugging CGI scripts

First of all, check for trivial installation errors — reading the section above on installing your CGI script carefully can save you a lot of time. If you wonder whether you have understood the installation procedure correctly, try installing a copy of this module file ('cgi.py') as a CGI script. When invoked as a script, the file will dump its environment and the contents of the form in HTML form. Give it the right mode etc, and send it a request. If it's installed in the standard 'cgi-bin' directory, it should be possible to send it a request by entering a URL into your browser of the form:

```
http://yourhostname/cgi-bin/cgi.py?name=Joe+Blow&addr=At+Home
```

If this gives an error of type 404, the server cannot find the script – perhaps you need to install it in a different directory. If it gives another error, there's an installation problem that you should fix before trying to go any

further. If you get a nicely formatted listing of the environment and form content (in this example, the fields should be listed as "addr" with value "At Home" and "name" with value "Joe Blow"), the 'cgi.py' script has been installed correctly. If you follow the same procedure for your own script, you should now be able to debug it.

The next step could be to call the cgi module's test() function from your script: replace its main code with the single statement

```
cgi.test()
```

This should produce the same results as those gotten from installing the 'cgi.py' file itself.

When an ordinary Python script raises an unhandled exception (for whatever reason: of a typo in a module name, a file that can't be opened, etc.), the Python interpreter prints a nice traceback and exits. While the Python interpreter will still do this when your CGI script raises an exception, most likely the traceback will end up in one of the HTTP server's log files, or be discarded altogether.

Fortunately, once you have managed to get your script to execute *some* code, you can easily send tracebacks to the Web browser using the cgitb module. If you haven't done so already, just add the line:

```
import cgitb; cgitb.enable()
```

to the top of your script. Then try running it again; when a problem occurs, you should see a detailed report that will likely make apparent the cause of the crash.

If you suspect that there may be a problem in importing the cgitb module, you can use an even more robust approach (which only uses built-in modules):

```
import sys
sys.stderr = sys.stdout
print "Content-Type: text/plain"
print
...your code here...
```

This relies on the Python interpreter to print the traceback. The content type of the output is set to plain text, which disables all HTML processing. If your script works, the raw HTML will be displayed by your client. If it raises an exception, most likely after the first two lines have been printed, a traceback will be displayed. Because no HTML interpretation is going on, the traceback will be readable.

11.2.10 Common problems and solutions

- Most HTTP servers buffer the output from CGI scripts until the script is completed. This means that it is not possible to display a progress report on the client's display while the script is running.
- Check the installation instructions above.
- Check the HTTP server's log files. ('tail -f logfile' in a separate window may be useful!)
- Always check a script for syntax errors first, by doing something like 'python script.py'.
- If your script does not have any syntax errors, try adding 'import cgitb; cgitb.enable()' to the top of the script.
- When invoking external programs, make sure they can be found. Usually, this means using absolute path names PATH is usually not set to a very useful value in a CGI script.
- When reading or writing external files, make sure they can be read or written by the userid under which your CGI script will be running: this is typically the userid under which the web server is running, or some explicitly specified userid for a web server's 'suexec' feature.

• Don't try to give a CGI script a set-uid mode. This doesn't work on most systems, and is a security liability as well.

11.3 cgitb — Traceback manager for CGI scripts

New in version 2.2.

The cgitb module provides a special exception handler for Python scripts. (Its name is a bit misleading. It was originally designed to display extensive traceback information in HTML for CGI scripts. It was later generalized to also display this information in plain text.) After this module is activated, if an uncaught exception occurs, a detailed, formatted report will be displayed. The report includes a traceback showing excerpts of the source code for each level, as well as the values of the arguments and local variables to currently running functions, to help you debug the problem. Optionally, you can save this information to a file instead of sending it to the browser.

To enable this feature, simply add one line to the top of your CGI script:

```
import cgitb; cgitb.enable()
```

The options to the enable() function control whether the report is displayed in the browser and whether the report is logged to a file for later analysis.

```
enable([display[, logdir[, context[, format]]]])
```

This function causes the cgitb module to take over the interpreter's default handling for exceptions by setting the value of sys.excepthook.

The optional argument *display* defaults to 1 and can be set to 0 to suppress sending the traceback to the browser. If the argument *logdir* is present, the traceback reports are written to files. The value of *logdir* should be a directory where these files will be placed. The optional argument *context* is the number of lines of context to display around the current line of source code in the traceback; this defaults to 5. If the optional argument *format* is "html", the output is formatted as HTML. Any other value forces plain text output. The default value is "html".

```
handler([info])
```

This function handles an exception using the default settings (that is, show a report in the browser, but don't log to a file). This can be used when you've caught an exception and want to report it using cgitb. The optional *info* argument should be a 3-tuple containing an exception type, exception value, and traceback object, exactly like the tuple returned by sys.exc_info(). If the *info* argument is not supplied, the current exception is obtained from sys.exc_info().

11.4 urllib — Open arbitrary resources by URL

This module provides a high-level interface for fetching data across the World Wide Web. In particular, the urlopen() function is similar to the built-in function open(), but accepts Universal Resource Locators (URLs) instead of filenames. Some restrictions apply — it can only open URLs for reading, and no seek operations are available.

It defines the following public functions:

```
urlopen(url[, data[, proxies]])
```

Open a network object denoted by a URL for reading. If the URL does not have a scheme identifier, or if it has 'file:' as its scheme identifier, this opens a local file (without universal newlines); otherwise it opens a socket to a server somewhere on the network. If the connection cannot be made, or if the server returns an error code, the IOError exception is raised. If all went well, a file-like object is returned. This supports the following methods: read(), readline(), readlines(), fileno(), close(), info() and geturl(). It also has proper support for the iterator protocol. One caveat: the read() method, if the size argument is omitted or negative, may not read until the end of the data stream; there is no good way to determine that the entire stream from a socket has been read in the general case.

Except for the info() and geturl() methods, these methods have the same interface as for file objects — see section 2.3.9 in this manual. (It is not a built-in file object, however, so it can't be used at those few places where a true built-in file object is required.)

The info() method returns an instance of the class mimetools. Message containing meta-information associated with the URL. When the method is HTTP, these headers are those returned by the server at the head of the retrieved HTML page (including Content-Length and Content-Type). When the method is FTP, a Content-Length header will be present if (as is now usual) the server passed back a file length in response to the FTP retrieval request. A Content-Type header will be present if the MIME type can be guessed. When the method is local-file, returned headers will include a Date representing the file's last-modified time, a Content-Length giving file size, and a Content-Type containing a guess at the file's type. See also the description of the mimetools module.

The <code>geturl()</code> method returns the real URL of the page. In some cases, the HTTP server redirects a client to another URL. The <code>urlopen()</code> function handles this transparently, but in some cases the caller needs to know which URL the client was redirected to. The <code>geturl()</code> method can be used to get at this redirected URL.

If the *url* uses the 'http:' scheme identifier, the optional *data* argument may be given to specify a POST request (normally the request type is GET). The *data* argument must be in standard application/x-www-form-urlencoded format; see the urlencode() function below.

The urlopen() function works transparently with proxies which do not require authentication. In a UNIX or Windows environment, set the http_proxy, ftp_proxy or gopher_proxy environment variables to a URL that identifies the proxy server before starting the Python interpreter. For example (the '%' is the command prompt):

```
% http_proxy="http://www.someproxy.com:3128"
% export http_proxy
% python
```

In a Windows environment, if no proxy environment variables are set, proxy settings are obtained from the registry's Internet Settings section.

In a Macintosh environment, urlopen() will retrieve proxy information from Internet Config.

Alternatively, the optional *proxies* argument may be used to explicitly specify proxies. It must be a dictionary mapping scheme names to proxy URLs, where an empty dictionary causes no proxies to be used, and None (the default value) causes environmental proxy settings to be used as discussed above. For example:

```
# Use http://www.someproxy.com:3128 for http proxying
proxies = {'http': 'http://www.someproxy.com:3128'}
filehandle = urllib.urlopen(some_url, proxies=proxies)
# Don't use any proxies
filehandle = urllib.urlopen(some_url, proxies={})
# Use proxies from environment - both versions are equivalent
filehandle = urllib.urlopen(some_url, proxies=None)
filehandle = urllib.urlopen(some_url)
```

The urlopen() function does not support explicit proxy specification. If you need to override environmental proxy settings, use URLopener, or a subclass such as FancyURLopener.

Proxies which require authentication for use are not currently supported; this is considered an implementation limitation.

Changed in version 2.3: Added the proxies support.

```
urlretrieve(url[, filename[, reporthook[, data]]])
```

Copy a network object denoted by a URL to a local file, if necessary. If the URL points to a local file, or a valid cached copy of the object exists, the object is not copied. Return a tuple (*filename*, *headers*) where *filename* is the local file name under which the object can be found, and *headers* is whatever the info() method of the object returned by urlopen() returned (for a remote object, possibly cached). Exceptions are the same as for urlopen().

The second argument, if present, specifies the file location to copy to (if absent, the location will be a tempfile with a generated name). The third argument, if present, is a hook function that will be called once on establishment of the network connection and once after each block read thereafter. The hook will be passed three arguments; a count of blocks transferred so far, a block size in bytes, and the total size of the file. The third argument may be -1 on older FTP servers which do not return a file size in response to a retrieval request.

If the *url* uses the 'http:' scheme identifier, the optional *data* argument may be given to specify a POST request (normally the request type is GET). The *data* argument must in standard application/x-www-form-urlencoded format; see the urlencode() function below.

_urlopener

The public functions urlopen() and urlretrieve() create an instance of the FancyURLopener class and use it to perform their requested actions. To override this functionality, programmers can create a subclass of URLopener or FancyURLopener, then assign an instance of that class to the urllib._urlopener variable before calling the desired function. For example, applications may want to specify a different User-Agent: header than URLopener defines. This can be accomplished with the following code:

```
import urllib

class AppURLopener(urllib.FancyURLopener):
    version = "App/1.7"

urllib._urlopener = AppURLopener()
```

urlcleanup()

Clear the cache that may have been built up by previous calls to urlretrieve().

quote(string[, safe])

Replace special characters in *string* using the '%xx' escape. Letters, digits, and the characters '_.-' are never quoted. The optional *safe* parameter specifies additional characters that should not be quoted — its default value is '/'.

Example: quote('/~connolly/') yields '/%7econnolly/'.

quote_plus(string[, safe])

Like quote(), but also replaces spaces by plus signs, as required for quoting HTML form values. Plus signs in the original string are escaped unless they are included in safe. It also does not have safe default to '/'.

unquote(string)

Replace '%xx' escapes by their single-character equivalent.

Example: unquote('/%7Econnolly/') yields '/ $^{\sim}$ connolly/'.

unquote_plus(string)

Like unquote (), but also replaces plus signs by spaces, as required for unquoting HTML form values.

urlencode(query[, doseq])

Convert a mapping object or a sequence of two-element tuples to a "url-encoded" string, suitable to pass to urlopen() above as the optional *data* argument. This is useful to pass a dictionary of form fields to a POST request. The resulting string is a series of *key=value* pairs separated by '&' characters, where both *key* and *value* are quoted using quote_plus() above. If the optional parameter *doseq* is present and evaluates to true, individual *key=value* pairs are generated for each element of the sequence. When a sequence of two-element tuples is used as the *query* argument, the first element of each tuple is a key and the second is a value. The order of parameters in the encoded string will match the order of parameter tuples in the sequence. The cgi module provides the functions parse_qs() and parse_qsl() which are used to parse query strings into Python data structures.

pathname2url(path)

Convert the pathname *path* from the local syntax for a path to the form used in the path component of a URL. This does not produce a complete URL. The return value will already be quoted using the quote() function.

url2pathname(path)

Convert the path component *path* from an encoded URL to the local syntax for a path. This does not accept a complete URL. This function uses unquote() to decode *path*.

class URLopener ([proxies[, **x509]])

Base class for opening and reading URLs. Unless you need to support opening objects using schemes other than 'http:', 'ftp:', 'gopher:' or 'file:', you probably want to use FancyURLopener.

By default, the URLopener class sends a User-Agent: header of 'urllib/VVV', where VVV is the urllib version number. Applications can define their own User-Agent: header by subclassing URLopener or FancyURLopener and setting the class attribute version to an appropriate string value in the subclass definition.

The optional *proxies* parameter should be a dictionary mapping scheme names to proxy URLs, where an empty dictionary turns proxies off completely. Its default value is None, in which case environmental proxy settings will be used if present, as discussed in the definition of urlopen(), above.

Additional keyword parameters, collected in *x509*, are used for authentication with the 'https:' scheme. The keywords *key_file* and *cert_file* are supported; both are needed to actually retrieve a resource at an 'https:' URL.

class FancyURLopener(...)

FancyURLopener subclasses URLopener providing default handling for the following HTTP response codes: 301, 302, 303, 307 and 401. For the 30x response codes listed above, the Location: header is used to fetch the actual URL. For 401 response codes (authentication required), basic HTTP authentication is performed. For the 30x response codes, recursion is bounded by the value of the *maxtries* attribute, which defaults to 10.

Note: According to the letter of RFC 2616, 301 and 302 responses to POST requests must not be automatically redirected without confirmation by the user. In reality, browsers do allow automatic redirection of these responses, changing the POST to a GET, and urllib reproduces this behaviour.

The parameters to the constructor are the same as those for URLopener.

Note: When performing basic authentication, a FancyURLopener instance calls its prompt_user_passwd() method. The default implementation asks the users for the required information on the controlling terminal. A subclass may override this method to support more appropriate behavior if needed.

Restrictions:

- Currently, only the following protocols are supported: HTTP, (versions 0.9 and 1.0), Gopher (but not Gopher-+), FTP, and local files.
- The caching feature of urlretrieve() has been disabled until I find the time to hack proper processing of Expiration time headers.
- There should be a function to query whether a particular URL is in the cache.
- For backward compatibility, if a URL appears to point to a local file but the file can't be opened, the URL is re-interpreted using the FTP protocol. This can sometimes cause confusing error messages.
- The urlopen() and urlretrieve() functions can cause arbitrarily long delays while waiting for a network connection to be set up. This means that it is difficult to build an interactive Web client using these functions without using threads.
- The data returned by urlopen() or urlretrieve() is the raw data returned by the server. This may be binary data (e.g. an image), plain text or (for example) HTML. The HTTP protocol provides type information in the reply header, which can be inspected by looking at the Content-Type: header. For the Gopher protocol, type information is encoded in the URL; there is currently no easy way to extract it. If the returned data is HTML, you can use the module htmllib to parse it.
- The code handling the FTP protocol cannot differentiate between a file and a directory. This can lead to unexpected behavior when attempting to read a URL that points to a file that is not accessible. If the URL ends in a /, it is assumed to refer to a directory and will be handled accordingly. But if an attempt to read a file leads to a 550 error (meaning the URL cannot be found or is not accessible, often for permission

reasons), then the path is treated as a directory in order to handle the case when a directory is specified by a URL but the trailing / has been left off. This can cause misleading results when you try to fetch a file whose read permissions make it inaccessible; the FTP code will try to read it, fail with a 550 error, and then perform a directory listing for the unreadable file. If fine-grained control is needed, consider using the ftplib module, subclassing FancyURLOpener, or changing _urlopener to meet your needs.

- This module does not support the use of proxies which require authentication. This may be implemented in the future.
- Although the urllib module contains (undocumented) routines to parse and unparse URL strings, the recommended interface for URL manipulation is in module urlparse.

11.4.1 URLopener Objects

URLopener and FancyURLopener objects have the following attributes.

```
open(fullurl[, data])
```

Open *fullurl* using the appropriate protocol. This method sets up cache and proxy information, then calls the appropriate open method with its input arguments. If the scheme is not recognized, open_unknown() is called. The *data* argument has the same meaning as the *data* argument of urlopen().

```
open_unknown(fullurl[, data])
```

Overridable interface to open unknown URL types.

```
retrieve(url[, filename[, reporthook[, data]]])
```

Retrieves the contents of *url* and places it in *filename*. The return value is a tuple consisting of a local filename and either a mimetools.Message object containing the response headers (for remote URLs) or None (for local URLs). The caller must then open and read the contents of *filename*. If *filename* is not given and the URL refers to a local file, the input filename is returned. If the URL is non-local and *filename* is not given, the filename is the output of tempfile.mktemp() with a suffix that matches the suffix of the last path component of the input URL. If *reporthook* is given, it must be a function accepting three numeric parameters. It will be called after each chunk of data is read from the network. *reporthook* is ignored for local URLs.

If the *url* uses the 'http:' scheme identifier, the optional *data* argument may be given to specify a POST request (normally the request type is GET). The *data* argument must in standard application/x-www-form-urlencoded format; see the urlencode() function below.

version

Variable that specifies the user agent of the opener object. To get urllib to tell servers that it is a particular user agent, set this in a subclass as a class variable or in the constructor before calling the base constructor.

The FancyURLopener class offers one additional method that should be overloaded to provide the appropriate behavior:

```
prompt_user_passwd(host, realm)
```

Return information needed to authenticate the user at the given host in the specified security realm. The return value should be a tuple, (*user*, *password*), which can be used for basic authentication.

The implementation prompts for this information on the terminal; an application should override this method to use an appropriate interaction model in the local environment.

11.4.2 Examples

Here is an example session that uses the 'GET' method to retrieve a URL containing parameters:

```
>>> import urllib
>>> params = urllib.urlencode({'spam': 1, 'eggs': 2, 'bacon': 0})
>>> f = urllib.urlopen("http://www.musi-cal.com/cgi-bin/query?%s" % params)
>>> print f.read()
```

The following example uses the 'POST' method instead:

```
>>> import urllib
>>> params = urllib.urlencode({'spam': 1, 'eggs': 2, 'bacon': 0})
>>> f = urllib.urlopen("http://www.musi-cal.com/cgi-bin/query", params)
>>> print f.read()
```

The following example uses an explicitly specified HTTP proxy, overriding environment settings:

```
>>> import urllib
>>> proxies = {'http': 'http://proxy.example.com:8080/'}
>>> opener = urllib.FancyURLopener(proxies)
>>> f = opener.open("http://www.python.org")
>>> f.read()
```

The following example uses no proxies at all, overriding environment settings:

```
>>> import urllib
>>> opener = urllib.FancyURLopener({})
>>> f = opener.open("http://www.python.org/")
>>> f.read()
```

11.5 urllib2 — extensible library for opening URLs

The urllib2 module defines functions and classes which help in opening URLs (mostly HTTP) in a complex world — basic and digest authentication, redirections, cookies and more.

The urllib2 module defines the following functions:

```
urlopen(url[, data])
```

Open the URL url, which can be either a string or a Request object.

data should be a string, which specifies additional data to send to the server. In HTTP requests, which are the only ones that support data, it should be a buffer in the format of application/x-www-form-urlencoded, for example one returned from urllib.urlencode().

This function returns a file-like object with two additional methods:

```
geturl() — return the URL of the resource retrieved
info() — return the meta-information of the page, as a dictionary-like object
```

Raises URLError on errors.

Note that None may be returned if no handler handles the request (though the default installed global OpenerDirector uses UnknownHandler to ensure this never happens).

```
install_opener(opener)
```

Install an OpenerDirector instance as the default global opener. Installing an opener is only necessary if you want urlopen to use that opener; otherwise, simply call OpenerDirector.open() instead of urlopen(). The code does not check for a real OpenerDirector, and any class with the appropriate interface will work.

```
build_opener([handler, ...])
```

Return an OpenerDirector instance, which chains the handlers in the order given. *handlers* can be either instances of BaseHandler, or subclasses of BaseHandler (in which case it must be possible to call the constructor without any parameters). Instances of the following classes will be in front of the

handlers, unless the handlers contain them, instances of them or subclasses of them: ProxyHandler, UnknownHandler, HTTPHandler, HTTPDefaultErrorHandler, HTTPRedirectHandler, FTPHandler, FileHandler, HTTPErrorProcessor.

If the Python installation has SSL support (socket.ssl() exists), HTTPSHandler will also be added.

Beginning in Python 2.3, a BaseHandler subclass may also change its handler_order member variable to modify its position in the handlers list. Besides ProxyHandler, which has handler_order of 100, all handlers currently have it set to 500.

The following exceptions are raised as appropriate:

exception URLError

The handlers raise this exception (or derived exceptions) when they run into a problem. It is a subclass of IOError.

exception HTTPError

A subclass of URLError, it can also function as a non-exceptional file-like return value (the same thing that urlopen() returns). This is useful when handling exotic HTTP errors, such as requests for authentication.

exception GopherError

A subclass of URLError, this is the error raised by the Gopher handler.

The following classes are provided:

```
\textbf{class Request} (\textit{url}[\textit{, data}][\textit{, headers}][\textit{, origin\_req\_host}][\textit{, unverifiable}])
```

This class is an abstraction of a URL request.

url should be a string which is a valid URL. For a description of data see the add_data() description. headers should be a dictionary, and will be treated as if add_header() was called with each key and value as arguments.

The final two arguments are only of interest for correct handling of third-party HTTP cookies:

origin_req_host should be the request-host of the origin transaction, as defined by RFC 2965. It defaults to cookielib.request_host(self). This is the host name or IP address of the original request that was initiated by the user. For example, if the request is for an image in an HTML document, this should be the request-host of the request for the page containing the image.

unverifiable should indicate whether the request is unverifiable, as defined by RFC 2965. It defaults to False. An unverifiable request is one whose URL the user did not have the option to approve. For example, if the request is for an image in an HTML document, and the user had no option to approve the automatic fetching of the image, this should be true.

class OpenerDirector()

The OpenerDirector class opens URLs via BaseHandlers chained together. It manages the chaining of handlers, and recovery from errors.

class BaseHandler()

This is the base class for all registered handlers — and handles only the simple mechanics of registration.

class HTTPDefaultErrorHandler()

A class which defines a default handler for HTTP error responses; all responses are turned into HTTPError exceptions.

class HTTPRedirectHandler()

A class to handle redirections.

class HTTPCookieProcessor([cookiejar])

A class to handle HTTP Cookies.

class ProxyHandler([proxies])

Cause requests to go through a proxy. If *proxies* is given, it must be a dictionary mapping protocol names to URLs of proxies. The default is to read the list of proxies from the environment variables protocol; proxy.

class HTTPPasswordMgr()

Keep a database of (realm, uri) -> (user, password) mappings.

class HTTPPasswordMgrWithDefaultRealm()

Keep a database of (realm, uri) -> (user, password) mappings. A realm of None is considered a

catch-all realm, which is searched if no other realm fits.

class AbstractBasicAuthHandler($[password_mgr]$)

This is a mixin class that helps with HTTP authentication, both to the remote host and to a proxy. *password_mgr*, if given, should be something that is compatible with HTTPPasswordMgr; refer to section 11.5.7 for information on the interface that must be supported.

class HTTPBasicAuthHandler([password_mgr])

Handle authentication with the remote host. *password_mgr*, if given, should be something that is compatible with HTTPPasswordMgr; refer to section 11.5.7 for information on the interface that must be supported.

class ProxyBasicAuthHandler([password_mgr])

Handle authentication with the proxy. *password_mgr*, if given, should be something that is compatible with HTTPPasswordMgr; refer to section 11.5.7 for information on the interface that must be supported.

${\bf class} \ {\bf AbstractDigestAuthHandler} \ (\left[password_mgr\right])$

This is a mixin class that helps with HTTP authentication, both to the remote host and to a proxy. *password_mgr*, if given, should be something that is compatible with HTTPPasswordMgr; refer to section 11.5.7 for information on the interface that must be supported.

class HTTPDigestAuthHandler ($[password_mgr]$)

Handle authentication with the remote host. *password_mgr*, if given, should be something that is compatible with HTTPPasswordMgr; refer to section 11.5.7 for information on the interface that must be supported.

class ProxyDigestAuthHandler($[password_mgr]$)

Handle authentication with the proxy. *password_mgr*, if given, should be something that is compatible with HTTPPasswordMgr; refer to section 11.5.7 for information on the interface that must be supported.

class HTTPHandler()

A class to handle opening of HTTP URLs.

class HTTPSHandler()

A class to handle opening of HTTPS URLs.

class FileHandler()

Open local files.

class FTPHandler()

Open FTP URLs.

class CacheFTPHandler()

Open FTP URLs, keeping a cache of open FTP connections to minimize delays.

class GopherHandler()

Open gopher URLs.

${\bf class} \; {\tt UnknownHandler} \, (\)$

A catch-all class to handle unknown URLs.

11.5.1 Request Objects

The following methods describe all of Request's public interface, and so all must be overridden in subclasses.

add_data(data)

Set the Request data to *data*. This is ignored by all handlers except HTTP handlers — and there it should be a byte string, and will change the request to be POST rather than GET.

get_method()

Return a string indicating the HTTP request method. This is only meaningful for HTTP requests, and currently always returns 'GET' or 'POST'.

has_data()

Return whether the instance has a non-None data.

get_data()

Return the instance's data.

add_header(key, val)

Add another header to the request. Headers are currently ignored by all handlers except HTTP handlers, where they are added to the list of headers sent to the server. Note that there cannot be more than one header with the same name, and later calls will overwrite previous calls in case the *key* collides. Currently, this is no loss of HTTP functionality, since all headers which have meaning when used more than once have a (header-specific) way of gaining the same functionality using only one header.

add_unredirected_header(key, header)

Add a header that will not be added to a redirected request. New in version 2.4.

has_header(header)

Return whether the instance has the named header (checks both regular and unredirected). New in version 2.4.

get_full_url()

Return the URL given in the constructor.

get_type()

Return the type of the URL — also known as the scheme.

get_host()

Return the host to which a connection will be made.

get_selector()

Return the selector — the part of the URL that is sent to the server.

set_proxy(host, type)

Prepare the request by connecting to a proxy server. The *host* and *type* will replace those of the instance, and the instance's selector will be the original URL given in the constructor.

get_origin_req_host()

Return the request-host of the origin transaction, as defined by RFC 2965. See the documentation for the Request constructor.

is_unverifiable()

Return whether the request is unverifiable, as defined by RFC 2965. See the documentation for the Request constructor.

11.5.2 OpenerDirector Objects

OpenerDirector instances have the following methods:

add_handler(handler)

handler should be an instance of BaseHandler. The following methods are searched, and added to the possible chains (note that HTTP errors are a special case).

- •protocol_open() signal that the handler knows how to open protocol URLs.
- •http_error_type() signal that the handler knows how to handle HTTP errors with HTTP error code type.
- •protocol_error() signal that the handler knows how to handle errors from (non-http) protocol.
- $\bullet protocol_\texttt{request}$ () signal that the handler knows how to pre-process protocol requests.
- •protocol_response() signal that the handler knows how to post-process protocol responses.

open(url, data)

Open the given *url* (which can be a request object or a string), optionally passing the given *data*. Arguments, return values and exceptions raised are the same as those of urlopen() (which simply calls the open() method on the currently installed global OpenerDirector).

error(*proto*[, *arg*[, ...]])

Handle an error of the given protocol. This will call the registered error handlers for the given protocol with the given arguments (which are protocol specific). The HTTP protocol is a special case which uses the HTTP response code to determine the specific error handler; refer to the http_error_*() methods of the handler classes.

Return values and exceptions raised are the same as those of urlopen().

OpenerDirector objects open URLs in three stages:

The order in which these methods are called within each stage is determined by sorting the handler instances.

- 1. Every handler with a method named like *protocol_request()* has that method called to pre-process the request.
- 2. Handlers with a method named like *protocol_open()* are called to handle the request. This stage ends when a handler either returns a non-None value (ie. a response), or raises an exception (usually URLError). Exceptions are allowed to propagate.

In fact, the above algorithm is first tried for methods named default_open. If all such methods return None, the algorithm is repeated for methods named like *protocol_open()*. If all such methods return None, the algorithm is repeated for methods named unknown_open().

Note that the implementation of these methods may involve calls of the parent OpenerDirector instance's .open() and .error() methods.

3. Every handler with a method named like *protocol_*response() has that method called to post-process the response.

11.5.3 BaseHandler Objects

BaseHandler objects provide a couple of methods that are directly useful, and others that are meant to be used by derived classes. These are intended for direct use:

add_parent(director)

Add a director as parent.

close()

Remove any parents.

The following members and methods should only be used by classes derived from BaseHandler. **Note:** The convention has been adopted that subclasses defining $protocol_request()$ or $protocol_response()$ methods are named *Processor; all others are named *Handler.

parent

A valid OpenerDirector, which can be used to open using a different protocol, or handle errors.

default_open(req)

This method is *not* defined in BaseHandler, but subclasses should define it if they want to catch all URLs.

This method, if implemented, will be called by the parent OpenerDirector. It should return a file-like object as described in the return value of the open() of OpenerDirector, or None. It should raise URLError, unless a truly exceptional thing happens (for example, MemoryError should not be mapped to URLError).

This method will be called before any protocol-specific open method.

protocol_open(req)

This method is *not* defined in BaseHandler, but subclasses should define it if they want to handle URLs with the given protocol.

This method, if defined, will be called by the parent OpenerDirector. Return values should be the same as for default_open().

unknown_open(req)

This method is *not* defined in BaseHandler, but subclasses should define it if they want to catch all URLs with no specific registered handler to open it.

This method, if implemented, will be called by the parent OpenerDirector. Return values should be the same as for default_open().

http_error_default(req, fp, code, msg, hdrs)

This method is *not* defined in BaseHandler, but subclasses should override it if they intend to provide a catch-all for otherwise unhandled HTTP errors. It will be called automatically by the OpenerDirector getting the error, and should not normally be called in other circumstances.

req will be a Request object, fp will be a file-like object with the HTTP error body, code will be the three-digit code of the error, msg will be the user-visible explanation of the code and hdrs will be a mapping object with the headers of the error.

Return values and exceptions raised should be the same as those of urlopen().

http_error_nnn (req, fp, code, msg, hdrs)

nnn should be a three-digit HTTP error code. This method is also not defined in BaseHandler, but will be called, if it exists, on an instance of a subclass, when an HTTP error with code *nnn* occurs.

Subclasses should override this method to handle specific HTTP errors.

Arguments, return values and exceptions raised should be the same as for http_error_default().

protocol_request(req)

This method is *not* defined in BaseHandler, but subclasses should define it if they want to pre-process requests of the given protocol.

This method, if defined, will be called by the parent OpenerDirector. *req* will be a Request object. The return value should be a Request object.

protocol_response(req, response)

This method is *not* defined in BaseHandler, but subclasses should define it if they want to post-process responses of the given protocol.

This method, if defined, will be called by the parent OpenerDirector. *req* will be a Request object. *response* will be an object implementing the same interface as the return value of urlopen(). The return value should implement the same interface as the return value of urlopen().

11.5.4 HTTPRedirectHandler Objects

Note: Some HTTP redirections require action from this module's client code. If this is the case, HTTPError is raised. See RFC 2616 for details of the precise meanings of the various redirection codes.

redirect_request(req, fp, code, msg, hdrs)

Return a Request or None in response to a redirect. This is called by the default implementations of the http_error_30*() methods when a redirection is received from the server. If a redirection should take place, return a new Request to allow http_error_30*() to perform the redirect. Otherwise, raise HTTPError if no other handler should try to handle this URL, or return None if you can't but another handler might.

Note: The default implementation of this method does not strictly follow RFC 2616, which says that 301 and 302 responses to POST requests must not be automatically redirected without confirmation by the user. In reality, browsers do allow automatic redirection of these responses, changing the POST to a GET, and the default implementation reproduces this behavior.

http_error_301(req, fp, code, msg, hdrs)

Redirect to the Location: URL. This method is called by the parent OpenerDirector when getting an HTTP 'moved permanently' response.

http_error_302(req, fp, code, msg, hdrs)

The same as http_error_301(), but called for the 'found' response.

http_error_303(req, fp, code, msg, hdrs)

The same as http_error_301(), but called for the 'see other' response.

http_error_307 (req, fp, code, msg, hdrs)

The same as $http_error_301()$, but called for the 'temporary redirect' response.

11.5.5 HTTPCookieProcessor Objects

HTTPCookieProcessor instances have one attribute:

cookiejar

The cookielib.CookieJar in which cookies are stored.

11.5.6 ProxyHandler Objects

protocol_open(request)

The ProxyHandler will have a method *protocol*_open() for every *protocol* which has a proxy in the *proxies* dictionary given in the constructor. The method will modify requests to go through the proxy, by calling request.set_proxy(), and call the next handler in the chain to actually execute the protocol.

11.5.7 HTTPPasswordMgr Objects

These methods are available on HTTPPasswordMgr and HTTPPasswordMgrWithDefaultRealm objects.

add_password(realm, uri, user, passwd)

uri can be either a single URI, or a sequence of URIs. *realm*, *user* and *passwd* must be strings. This causes (*user*, *passwd*) to be used as authentication tokens when authentication for *realm* and a super-URI of any of the given URIs is given.

find_user_password(realm, authuri)

Get user/password for given realm and URI, if any. This method will return (None, None) if there is no matching user/password.

For HTTPPasswordMgrWithDefaultRealm objects, the realm None will be searched if the given *realm* has no matching user/password.

11.5.8 AbstractBasicAuthHandler Objects

handle_authentication_request(authreq, host, req, headers)

Handle an authentication request by getting a user/password pair, and re-trying the request. *authreq* should be the name of the header where the information about the realm is included in the request, *host* is the host to authenticate to, *req* should be the (failed) Request object, and *headers* should be the error headers.

11.5.9 HTTPBasicAuthHandler Objects

http_error_401(req, fp, code, msg, hdrs)

Retry the request with authentication information, if available.

11.5.10 ProxyBasicAuthHandler Objects

http_error_407 (req, fp, code, msg, hdrs)

Retry the request with authentication information, if available.

11.5.11 AbstractDigestAuthHandler Objects

handle_authentication_request(authreq, host, req, headers)

authreq should be the name of the header where the information about the realm is included in the request, host should be the host to authenticate to, req should be the (failed) Request object, and headers should be the error headers.

11.5.12 HTTPDigestAuthHandler Objects

http_error_401(req, fp, code, msg, hdrs)

Retry the request with authentication information, if available.

11.5.13 ProxyDigestAuthHandler Objects

http_error_407 (req, fp, code, msg, hdrs)

Retry the request with authentication information, if available.

11.5.14 HTTPHandler Objects

http_open(req)

Send an HTTP request, which can be either GET or POST, depending on req.has_data().

11.5.15 HTTPSHandler Objects

https_open(req)

Send an HTTPS request, which can be either GET or POST, depending on req.has_data().

11.5.16 FileHandler Objects

file_open(req)

Open the file locally, if there is no host name, or the host name is 'localhost'. Change the protocol to ftp otherwise, and retry opening it using parent.

11.5.17 FTPHandler Objects

ftp_open(req)

Open the FTP file indicated by req. The login is always done with empty username and password.

11.5.18 CacheFTPHandler Objects

CacheFTPHandler objects are FTPHandler objects with the following additional methods:

setTimeout(t)

Set timeout of connections to t seconds.

setMaxConns(m)

Set maximum number of cached connections to m.

11.5.19 GopherHandler Objects

gopher_open(req)

Open the gopher resource indicated by req.

11.5.20 UnknownHandler Objects

unknown_open()

Raise a URLError exception.

11.5.21 HTTPErrorProcessor Objects

New in version 2.4.

```
unknown_open()
```

Process HTTP error responses.

For 200 error codes, the response object is returned immediately.

For non-200 error codes, this simply passes the job on to the $protocol_error_code()$ handler methods, via OpenerDirector.error(). Eventually, urllib2.HTTPDefaultErrorHandler will raise an HTTPError if no other handler handles the error.

11.5.22 Examples

This example gets the python.org main page and displays the first 100 bytes of it:

```
>>> import urllib2
>>> f = urllib2.urlopen('http://www.python.org/')
>>> print f.read(100)
<!DOCTYPE html PUBLIC "-//W3C//DTD HTML 4.01 Transitional//EN">
<?xml-stylesheet href="./css/ht2html</pre>
```

Here we are sending a data-stream to the stdin of a CGI and reading the data it returns to us:

```
>>> import urllib2
>>> req = urllib2.Request(url='https://localhost/cgi-bin/test.cgi',
... data='This data is passed to stdin of the CGI')
>>> f = urllib2.urlopen(req)
>>> print f.read()
Got Data: "This data is passed to stdin of the CGI"
```

The code for the sample CGI used in the above example is:

```
#!/usr/bin/env python
import sys
data = sys.stdin.read()
print 'Content-type: text-plain\n\nGot Data: "%s"' % data
```

Use of Basic HTTP Authentication:

```
import urllib2
# Create an OpenerDirector with support for Basic HTTP Authentication...
auth_handler = urllib2.HTTPBasicAuthHandler()
auth_handler.add_password('realm', 'host', 'username', 'password')
opener = urllib2.build_opener(auth_handler)
# ...and install it globally so it can be used with urlopen.
urllib2.install_opener(opener)
urllib2.urlopen('http://www.example.com/login.html')
```

build_opener() provides many handlers by default, including a ProxyHandler. By default, ProxyHandler uses the environment variables named <scheme>_proxy, where <scheme> is the URL scheme involved. For example, the http_proxy environment variable is read to obtain the HTTP proxy's URL.

This example replaces the default ProxyHandler with one that uses programatically-supplied proxy URLs, and adds proxy authorization support with ProxyBasicAuthHandler.

```
proxy_handler = urllib2.ProxyHandler({'http': 'http://www.example.com:3128/'})
proxy_auth_handler = urllib2.HTTPBasicAuthHandler()
proxy_auth_handler.add_password('realm', 'host', 'username', 'password')

opener = build_opener(proxy_handler, proxy_auth_handler)
# This time, rather than install the OpenerDirector, we use it directly:
opener.open('http://www.example.com/login.html')
```

Adding HTTP headers:

Use the *headers* argument to the Request constructor, or:

```
import urllib2
req = urllib2.Request('http://www.example.com/')
req.add_header('Referer', 'http://www.python.org/')
r = urllib2.urlopen(req)
```

OpenerDirector automatically adds a User-Agent: header to every Request. To change this:

```
import urllib2
opener = urllib2.build_opener()
opener.addheaders = [('User-agent', 'Mozilla/5.0')]
opener.open('http://www.example.com/')
```

Also, remember that a few standard headers (Content-Length:, Content-Type: and Host:) are added when the Request is passed to urlopen() (or OpenerDirector.open()).

11.6 httplib — HTTP protocol client

This module defines classes which implement the client side of the HTTP and HTTPS protocols. It is normally not used directly — the module urllib uses it to handle URLs that use HTTP and HTTPS.

Note: HTTPS support is only available if the socket module was compiled with SSL support.

Note: The public interface for this module changed substantially in Python 2.0. The HTTP class is retained only for backward compatibility with 1.5.2. It should not be used in new code. Refer to the online docstrings for usage.

The module provides the following classes:

```
class HTTPConnection(host[, port])
```

An HTTPConnection instance represents one transaction with an HTTP server. It should be instantiated passing it a host and optional port number. If no port number is passed, the port is extracted from the host string if it has the form *host:port*, else the default HTTP port (80) is used. For example, the following calls all create instances that connect to the server at the same host and port:

```
>>> h1 = httplib.HTTPConnection('www.cwi.nl')
>>> h2 = httplib.HTTPConnection('www.cwi.nl:80')
>>> h3 = httplib.HTTPConnection('www.cwi.nl', 80)
```

New in version 2.0.

```
class HTTPSConnection(host[, port, key_file, cert_file])
```

A subclass of HTTPConnection that uses SSL for communication with secure servers. Default port is 443. *key_file* is the name of a PEM formatted file that contains your private key. *cert_file* is a PEM formatted certificate chain file.

Warning: This does not do any certificate verification!

New in version 2.0.

492

```
class HTTPResponse (sock[, debuglevel=0][, strict=0])
```

Class whose instances are returned upon successful connection. Not instantiated directly by user. New in version 2.0.

The following exceptions are raised as appropriate:

exception HTTPException

The base class of the other exceptions in this module. It is a subclass of Exception. New in version 2.0.

exception NotConnected

A subclass of HTTPException. New in version 2.0.

exception InvalidURL

A subclass of HTTPException, raised if a port is given and is either non-numeric or empty. New in version 2.3.

exception UnknownProtocol

A subclass of HTTPException. New in version 2.0.

exception UnknownTransferEncoding

A subclass of HTTPException. New in version 2.0.

exception UnimplementedFileMode

A subclass of HTTPException. New in version 2.0.

exception IncompleteRead

A subclass of HTTPException. New in version 2.0.

exception ImproperConnectionState

A subclass of HTTPException. New in version 2.0.

exception CannotSendRequest

A subclass of ImproperConnectionState. New in version 2.0.

exception CannotSendHeader

A subclass of ImproperConnectionState. New in version 2.0.

exception ResponseNotReady

A subclass of ImproperConnectionState. New in version 2.0.

exception BadStatusLine

A subclass of HTTPException. Raised if a server responds with a HTTP status code that we don't understand. New in version 2.0.

The constants defined in this module are:

HTTP_PORT

The default port for the HTTP protocol (always 80).

HTTPS_PORT

The default port for the HTTPS protocol (always 443).

and also the following constants for integer status codes:

DOTESTINGEDED 100	Constant	Value	Definition
DROCESSING 10.2 WEBDAW, RFC 2518, Section 10.1 CREATED 201 HTTP/1.1, RFC 2616, Section 10.2.1 CREATED 201 HTTP/1.1, RFC 2616, Section 10.2.2 ACCEPTED 202 HTTP/1.1, RFC 2616, Section 10.2.3 NON_AUTHORITATIVE_INFORMATION 203 HTTP/1.1, RFC 2616, Section 10.2.5 HTTP/1.1, RFC 2616, Section 10.2.6 HTTP/1.1, RFC 2616, Section 10.2.7 WEBDAW RFC 2518, Section 10.2. Delta encoding in HTTP, RFC 3229, Section 10.3. MULTIPLE_CHOICES 300 HTTP/1.1, RFC 2616, Section 10.3. HTTP/1.1, RFC 2616, Section 10.3.1 HTTP/1.1, RFC 2616, Section 10.3.2 POUND 302 HTTP/1.1, RFC 2616, Section 10.3.3 HTTP/1.1, RFC 2616, Section 10.3.4 HTTP/1.1, RFC 2616, Section 10.3.4 HTTP/1.1, RFC 2616, Section 10.3.5 USE_PROXY 305 HTTP/1.1, RFC 2616, Section 10.3.5 USE_PROXY 305 HTTP/1.1, RFC 2616, Section 10.3.5 USE_PROXY 305 HTTP/1.1, RFC 2616, Section 10.3.4 HTTP/1.1, RFC 2616, Section 10.3.5 USE_PROXY 305 HTTP/1.1, RFC 2616, Section 10.3.4 HTTP/1.1, RFC 2616, Section 10.3.4 HTTP/1.1, RFC 2616, Section 10.3.5 USE_PROXY 400 HTTP/1.1, RFC 2616, Section 10.3.8 HTTP/1.1, RFC 2616, Section 10.3.8 HTTP/1.1, RFC 2616, Section 10.4.1 HTTP/1.1, RFC 2616, Section 10.4.1 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.4 HTTP/1.1, RFC 2616, Section 10.4.5 HTTP/1.1, RFC 2616, Section 10.4.1 HTTP/1.1, RFC 2616, Section	CONTINUE	100	HTTP/1.1, RFC 2616, Section 10.1.1
OK 200 HTTP/1.1, RFC 2616, Section 10.2.1 CREATED 201 HTTP/1.1, RFC 2616, Section 10.2.2 ACCEPTED 202 HTTP/1.1, RFC 2616, Section 10.2.3 NON_AUTHORITATIVE_INFORMATION 203 HTTP/1.1, RFC 2616, Section 10.2.5 RESET_CONTENT 205 HTTP/1.1, RFC 2616, Section 10.2.5 PARTIAL_CONTENT 206 HTTP/1.1, RFC 2616, Section 10.2.6 MULTISTATUS 207 HTTP/1.1, RFC 2616, Section 10.2.7 MULTIPLE_CHOICES 300 HTTP/1.1, RFC 2616, Section 10.2.7 MULTIPLE_CHOICES 300 HTTP/1.1, RFC 2616, Section 10.3.1 MULTIPLE_CHOICES 300 HTTP/1.1, RFC 2616, Section 10.3.1 MULTIPLE_CHOICES 301 HTTP/1.1, RFC 2616, Section 10.3.1 MULTIPLE_CHOICES 302 HTTP/1.1, RFC 2616, Section 10.3.2 MULTIPLE_CHOICES 303 HTTP/1.1, RFC 2616, Section 10.3.3 SEE_OTHER 303 HTTP/1.1, RFC 2616, Section 10.3.3 NOT_ACCEPTABLE 400 HTTP/1.1, RFC 2616, Section 10.3.4 HOTHOLIT, RFC 2616, Section 10.4.1 HTTP/1.1, RFC 2616, Section 10.4.2 HOTHOLIT, RFC 2616, Section 10.4.3	SWITCHING_PROTOCOLS	101	HTTP/1.1, RFC 2616, Section 10.1.2
CREATED	PROCESSING	102	
ACCEPTED 202 HTTP/1.1, RFC 2616, Section 10.2.3 NON_AUTHORITATIVE_INFORMATION 203 HTTP/1.1, RFC 2616, Section 10.2.4 RESET_CONTENT 204 HTTP/1.1, RFC 2616, Section 10.2.5 PARTIAL_CONTENT 205 HTTP/1.1, RFC 2616, Section 10.2.6 HTTP/1.1, RFC 2616, Section 10.2.6 HTTP/1.1, RFC 2616, Section 10.2.7 MULTI_STATUS 207 WEBDAW RFC 2518, Section 10.2.7 MULTI_PLE_CHOICES 300 HTTP/1.1, RFC 2616, Section 10.3.1 MULTIPLE_CHOICES 300 HTTP/1.1, RFC 2616, Section 10.3.1 MULTIPLE_CHOICES 300 HTTP/1.1, RFC 2616, Section 10.3.2 FOUND 302 HTTP/1.1, RFC 2616, Section 10.3.3 SEE_OTHER 303 HTTP/1.1, RFC 2616, Section 10.3.3 SEE_OTHER 303 HTTP/1.1, RFC 2616, Section 10.3.4 NOT_MODIFIED 304 HTTP/1.1, RFC 2616, Section 10.3.5 HTTP/1.1, RFC 2616, Section 10.3.5 HTTP/1.1, RFC 2616, Section 10.3.6 HTTP/1.1, RFC 2616, Section 10.4.1 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.4 HTTP/1.1, RFC 2616, Section 10.4.5 HTTP/1.1, RFC 2616, Section 10.4.6 HTTP/1.1, RFC 2616, Section 10.4.6 HTTP/1.1, RFC 2616, Section 10.4.6 HTTP/1.1, RFC 2616, Section 10.4.7 HTTP/1.1, RFC 2616, Section 10.4.9 HTTP/1.1, RFC 2616, Section 10.4.9 HTTP/1.1, RFC 2616, Section 10.4.1 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.5 HTTP/1.1, RFC 2616, Section 10.4.1 HT	OK	200	HTTP/1.1, RFC 2616, Section 10.2.1
NOL_AUTHORITATIVE_INFORMATION 203 NTTP/1.1, RFC 2616, Section 10.2.4 NO_CONTENT 205 HTTP/1.1, RFC 2616, Section 10.2.6 PARTIAL_CONTENT 205 HTTP/1.1, RFC 2616, Section 10.2.6 PARTIAL_CONTENT 205 HTTP/1.1, RFC 2616, Section 10.2.7 MULTI_STATUS 207 WEBDAV RFC 2518, Section 10.2.7 MULTI_STATUS 207 WEBDAV RFC 2518, Section 10.2.7 MULTI_DEL_CHOICES 300 HTTP/1.1, RFC 2616, Section 10.3.1 MUVED_PERMANENTLY 301 HTTP/1.1, RFC 2616, Section 10.3.1 MOVED_PERMANENTLY 301 HTTP/1.1, RFC 2616, Section 10.3.2 FOUND 302 HTTP/1.1, RFC 2616, Section 10.3.3 SEE_OTHER 303 HTTP/1.1, RFC 2616, Section 10.3.5 USE_PROXY 305 HTTP/1.1, RFC 2616, Section 10.3.5 USE_PROXY 305 HTTP/1.1, RFC 2616, Section 10.3.5 USE_PROXY 307 HTTP/1.1, RFC 2616, Section 10.3.6 HTTP/1.1, RFC 2616, Section 10.4.1 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.4 HTTP/1.1, RFC 2616, Section 10.4.5 HTTP/1.1, RFC 2616, Section 10.4.5 HTTP/1.1, RFC 2616, Section 10.4.5 HTTP/1.1, RFC 2616, Section 10.4.6 HTTP/1.1, RFC 2616, Section 10.4.7 HTTP/1.1, RFC 2616, Section 10.4.1 HTTP/1.1, RFC 2616, Sec	CREATED	201	HTTP/1.1, RFC 2616, Section 10.2.2
NO_CONTENT 204 HTTP/1.1, RFC 2616, Section 10.2.5 HTTP/1.1, RFC 2616, Section 10.2.6 HTTP/1.1, RFC 2616, Section 10.2.7 MULTI_STATUS 207 WEBDAW RFC 2518, Section 10.2.7 WEBDAW RFC 2518, Section 10.3.1 HTTP/1.1, RFC 2616, Section 10.3.1 HTTP/1.1, RFC 2616, Section 10.3.1 HTTP/1.1, RFC 2616, Section 10.3.2 HTTP/1.1, RFC 2616, Section 10.3.3 HTTP/1.1, RFC 2616, Section 10.3.3 HTTP/1.1, RFC 2616, Section 10.3.4 HTTP/1.1, RFC 2616, Section 10.3.5 HTTP/1.1, RFC 2616, Section 10.3.5 HTTP/1.1, RFC 2616, Section 10.3.6 HTTP/1.1, RFC 2616, Section 10.3.6 HTTP/1.1, RFC 2616, Section 10.3.8 HTTP/1.1, RFC 2616, Section 10.4.1 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.3 HTTP/1.1, RFC 2616, Section 10.4.5 HTTP/1.1, RFC 2616, Section 10.4.6 HTTP/1.1, RFC 2616, Section 10.4.10 HTTP/1.1, RFC 2616, Section 10.4.11 HTTP/1.1, RFC 2616, Section 10.5.1 HTTP/1.1, RFC	ACCEPTED	202	HTTP/1.1, RFC 2616, Section 10.2.3
RESET_CONTENT 205	NON_AUTHORITATIVE_INFORMATION	203	HTTP/1.1, RFC 2616, Section 10.2.4
PARTIAL_CONTENT 206 MTTP/1.1, RFC 2616, Section 10.2.7 MULTI_STATUS 207 Delta encoding in HTTP, RFC 3229, Section 10.4.1 MULTIPLE_CHOICES 300 MULTIPLE_CHOICES 300 MULTIPLE_CHOICES 301 MTTP/1.1, RFC 2616, Section 10.3.1 MTTP/1.1, RFC 2616, Section 10.3.2 MTTP/1.1, RFC 2616, Section 10.3.3 MTTP/1.1, RFC 2616, Section 10.3.4 MTTP/1.1, RFC 2616, Section 10.3.5 MTTP/1.1, RFC 2616, Section 10.3.6 MTTP/1.1, RFC 2616, Section 10.3.8 MTTP/1.1, RFC 2616, Section 10.4.1 MTTP/1.1, RFC 2616, Section 10.4.2 MTTP/1.1, RFC 2616, Section 10.4.4 MTTP/1.1, RFC 2616, Section 10.4.5 MTTP/1.1, RFC 2616, Section 10.4.7 MTTP/1.1, RFC 2616, Section 10.4.7 MTTP/1.1, RFC 2616, Section 10.4.10 MTTP/1.1, RFC 2616, Section 10.4.11 MTTP/1.1, RFC 2616, Section 10.5.1 MTTP/1.1, RFC 2616, Section 10.5.1 MTTP	NO_CONTENT	204	HTTP/1.1, RFC 2616, Section 10.2.5
MULTI_STATUS 207 WEBDAV RFC 2518, Section 10.2 IM_USED 226 Delta encoding in HTTP, RFC 3229, Section 10.4.1 MULTIPLE_CHOICES 301 HTTP/1.1, RFC 2616, Section 10.3.1 MOVED_PERMANENTLY 301 HTTP/1.1, RFC 2616, Section 10.3.2 FOUND 302 HTTP/1.1, RFC 2616, Section 10.3.4 NOT_MODIFIED 304 HTTP/1.1, RFC 2616, Section 10.3.4 NOT_MODIFIED 305 HTTP/1.1, RFC 2616, Section 10.3.5 TEMPORARY_REDIRECT 307 HTTP/1.1, RFC 2616, Section 10.3.8 BAD_REQUEST 400 HTTP/1.1, RFC 2616, Section 10.3.8 UNAUTHORIZED 401 HTTP/1.1, RFC 2616, Section 10.4.2 PAYMENT_REQUIRED 402 HTTP/1.1, RFC 2616, Section 10.4.3 FORBIDDEN 403 HTTP/1.1, RFC 2616, Section 10.4.4 NOT_ACCEPTABLE 406 HTTP/1.1, RFC 2616, Section 10.4.5 MEEHOD_NOT_ALLOWED 407 HTTP/1.1, RFC 2616, Section 10.4.7 MOT_ACCEPTABLE 408 HTTP/1.1, RFC 2616, Section 10.4.7 MOT_ACCEPTABLE 408 HTTP/1.1, RFC 2616, Section 10.4.1 MENGUEST_URL_TOLOMG 401	RESET_CONTENT	205	HTTP/1.1, RFC 2616, Section 10.2.6
MULTIPLE_CHOICES 300 MTTP/1.1, RFC 2616, Section 10.3.1 MTTP/1.1, RFC 2616, Section 10.3.2 MTTP/1.1, RFC 2616, Section 10.3.2 MTTP/1.1, RFC 2616, Section 10.3.2 MTTP/1.1, RFC 2616, Section 10.3.3 MTTP/1.1, RFC 2616, Section 10.3.3 MTTP/1.1, RFC 2616, Section 10.3.4 MTTP/1.1, RFC 2616, Section 10.3.4 MTTP/1.1, RFC 2616, Section 10.3.5 MTTP/1.1, RFC 2616, Section 10.3.6 MTTP/1.1, RFC 2616, Section 10.4.2 MTTP/1.1, RFC 2616, Section 10.4.2 MTTP/1.1, RFC 2616, Section 10.4.5 MTTP/1.1, RFC 2616, Section 10.4.6 MTTP/1.1, RFC 2616, Section 10.4.6 MTTP/1.1, RFC 2616, Section 10.4.10 MTTP/1.1, RFC 2616, Section 10.4.10 MTTP/1.1, RFC 2616, Section 10.4.11 MTTP/1.1, RFC 2616, Section 10.4.12 MTTP/1.1, RFC 2616, Section 10.4.13 MTTP/1.1, RFC 2616, Section 10.4.15 MTTP/1.1, RFC 2616, Section 10.4.15 MTTP/1.1, RFC 2616, Section 10.4.16 M	PARTIAL_CONTENT	206	HTTP/1.1, RFC 2616, Section 10.2.7
MULTIPLE_CHOICES 300 HTTP/1.1, RFC 2616, Section 10.3.2 MOVED_PERMANENTLY 301 HTTP/1.1, RFC 2616, Section 10.3.2 FOUND 302 HTTP/1.1, RFC 2616, Section 10.3.3 SEE_OTHER 303 HTTP/1.1, RFC 2616, Section 10.3.4 NOT_MODIFIED 304 HTTP/1.1, RFC 2616, Section 10.3.5 USE_PROXY 305 HTTP/1.1, RFC 2616, Section 10.3.6 TEMPORARY_REDIRECT 307 HTTP/1.1, RFC 2616, Section 10.3.6 BAD_REQUEST 400 HTTP/1.1, RFC 2616, Section 10.3.8 HATTP/1.1, RFC 2616, Section 10.4.1 HTTP/1.1, RFC 2616, Section 10.4.2 HAYMENT_REQUIRED 402 HTTP/1.1, RFC 2616, Section 10.4.2 HAYMENT_REQUIRED 403 HTTP/1.1, RFC 2616, Section 10.4.3 MOT_ACCEPTABLE 406 HTTP/1.1, RFC 2616, Section 10.4.5 MOT_ACCEPTABLE 406 HTTP/1.1, RFC 2616, Section 10.4.6 MOT_ACCEPTABLE 407 HTTP/1.1, RFC 2616, Section 10.4.7 MEQUEST_TIMEOUT 409 HTTP/1.1, RFC 2616, Section 10.4.9 CONFLICT 409 HTTP/1.1, RFC 2616, Section 10.4.9 MEDUSST_ENTITY_TOO_LARGE 412	MULTI_STATUS	207	WEBDAV RFC 2518, Section 10.2
MOVED_PERMANENTLY 301	IM_USED	226	Delta encoding in HTTP, RFC 3229, Section 10.4.1
FOUND 302 HTTP/1.1, RFC 2616, Section 10.3.3 HTTP/1.1, RFC 2616, Section 10.3.4 HTTP/1.1, RFC 2616, Section 10.3.4 HTTP/1.1, RFC 2616, Section 10.3.5 HTTP/1.1, RFC 2616, Section 10.3.5 HTTP/1.1, RFC 2616, Section 10.3.5 HTTP/1.1, RFC 2616, Section 10.3.6 HTTP/1.1, RFC 2616, Section 10.3.8 HTTP/1.1, RFC 2616, Section 10.3.8 HTTP/1.1, RFC 2616, Section 10.4.1 HTTP/1.1, RFC 2616, Section 10.4.1 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.3 HTTP/1.1, RFC 2616, Section 10.4.4 HTTP/1.1, RFC 2616, Section 10.4.5 HTTP/1.1, RFC 2616, Section 10.4.5 HTTP/1.1, RFC 2616, Section 10.4.5 HTTP/1.1, RFC 2616, Section 10.4.6 HTTP/1.1, RFC 2616, Section 10.4.7 HTTP/1.1, RFC 2616, Section 10.4.7 HTTP/1.1, RFC 2616, Section 10.4.8 HTTP/1.1, RFC 2616, Section 10.4.9 HTTP/1.1, RFC 2616, Section 10.4.10 HTTP/1.1, RFC 2616, Section 10.4.10 HTTP/1.1, RFC 2616, Section 10.4.11 HTTP/1.1, RFC 2616, Section 10.4.12 HTTP/1.1, RFC 2616, Section 10.4.13 HTTP/1.1, RFC 2616, Section 10.4.14 HTTP/1.1, RFC 2616, Section 10.4.15 HTTP/1.1, RFC 2616, Section 10.4.16 HTTP/1.1, RFC 2616, Section 10.4.17 HTTP/1.1, RFC 2616, Section 10.4.18 WEBDAV, RFC 2518, Section 10.5.1 HTTP/1.1, RFC 2616, Section 10.5.2 HTTP/1.1, RFC 2616, Section 10.5.2 HTTP/1.1, RFC 2616, Section 10.5.5 HTTP/1.1, RFC 2616, Section 10.5.6 WEBDAV, RFC 2518, Section 10.5.6 HTTP/1.1, RFC 2616,	MULTIPLE_CHOICES	300	HTTP/1.1, RFC 2616, Section 10.3.1
SEE_OTHER	MOVED_PERMANENTLY	301	HTTP/1.1, RFC 2616, Section 10.3.2
NOT_MODIFIED 304 HTTP/1.1, RFC 2616, Section 10.3.5 HTTP/1.1, RFC 2616, Section 10.3.6 HTTP/1.1, RFC 2616, Section 10.3.6 HTTP/1.1, RFC 2616, Section 10.3.8 HTTP/1.1, RFC 2616, Section 10.4.1 HTTP/1.1, RFC 2616, Section 10.4.1 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.3 HTTP/1.1, RFC 2616, Section 10.4.4 HTTP/1.1, RFC 2616, Section 10.4.4 HTTP/1.1, RFC 2616, Section 10.4.5 HTTP/1.1, RFC 2616, Section 10.4.5 HTTP/1.1, RFC 2616, Section 10.4.6 HTTP/1.1, RFC 2616, Section 10.4.6 HTTP/1.1, RFC 2616, Section 10.4.7 REQUEST_INTEGUT 408 HTTP/1.1, RFC 2616, Section 10.4.9 HTTP/1.1, RFC 2616, Section 10.4.10 HTTP/1.1, RFC 2616, Section 10.4.10 HTTP/1.1, RFC 2616, Section 10.4.11 HTTP/1.1, RFC 2616, Section 10.4.11 HTTP/1.1, RFC 2616, Section 10.4.12 HTTP/1.1, RFC 2616, Section 10.4.13 REQUEST_URI_TOO_LONG 414 HTTP/1.1, RFC 2616, Section 10.4.14 HTTP/1.1, RFC 2616, Section 10.4.16 HTTP/1.1, RFC 2616, Section 10.4.17 REQUESTED_RANGE_NOT_SATISFIABLE 416 HTTP/1.1, RFC 2616, Section 10.4.18 HTTP/1.1, RFC 2616, Section 10.4.18 HTTP/1.1, RFC 2616, Section 10.4.18 HTTP/1.1, RFC 2616, Section 10.5.1 HTTP/1.1, RFC 2616, Section 10.5.2 HTTP/1.1, RFC 2616, Section 10.5.4 HTTP/1.1, RFC 2616, Section 10.5.5 HTTP/1.1, RFC 2616, Section 10.5.6 WEBDAV, RFC 2518, Section 10.5.6 WEBDAV, RFC	FOUND	302	HTTP/1.1, RFC 2616, Section 10.3.3
USE_PROXY 305 HTTP/1.1, RFC 2616, Section 10.3.6 HTTP/1.1, RFC 2616, Section 10.3.8 HTTP/1.1, RFC 2616, Section 10.4.1 HTTP/1.1, RFC 2616, Section 10.4.1 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.2 HTTP/1.1, RFC 2616, Section 10.4.3 HTTP/1.1, RFC 2616, Section 10.4.3 HTTP/1.1, RFC 2616, Section 10.4.3 HTTP/1.1, RFC 2616, Section 10.4.5 HTTP/1.1, RFC 2616, Section 10.4.6 HTTP/1.1, RFC 2616, Section 10.4.7 HTTP/1.1, RFC 2616, Section 10.4.7 HTTP/1.1, RFC 2616, Section 10.4.8 HTTP/1.1, RFC 2616, Section 10.4.9 HTTP/1.1, RFC 2616, Section 10.4.9 HTTP/1.1, RFC 2616, Section 10.4.10 HTTP/1.1, RFC 2616, Section 10.4.10 HTTP/1.1, RFC 2616, Section 10.4.11 HTTP/1.1, RFC 2616, Section 10.4.12 HTTP/1.1, RFC 2616, Section 10.4.13 REQUEST_URI_TOO_LONG 414 HTTP/1.1, RFC 2616, Section 10.4.14 HTTP/1.1, RFC 2616, Section 10.4.16 HTTP/1.1, RFC 2616, Section 10.5.1 HTTP/1.1, RFC 2616, Section 10.5.1 HTTP/1.1, RFC 2616, Section 10.5.2 HTTP/1.1, RFC 2616, Section 10.5.2 HTTP/1.1, RFC 2616, Section 10.5.5 HTTP/1.1, RFC 2616, Section 10.5.5 HTTP/1.1, RFC 2616, Section 10.5.6 WEBDAV, RFC 2518, Section 10.5.6	SEE_OTHER	303	HTTP/1.1, RFC 2616, Section 10.3.4
TEMPORARY_REDIRECT	NOT_MODIFIED	304	HTTP/1.1, RFC 2616, Section 10.3.5
BAD_REQUEST	USE_PROXY	305	HTTP/1.1, RFC 2616, Section 10.3.6
UNAUTHORIZED PAYMENT REQUIRED PRECONDITION REQUIRED PRECONDITION FAILED PRECONDITION FAILED PREQUEST ENTITY TOO LARGE PREQUEST ENTITY TOO LARGE PREQUESTED RANGE NOT SATISFIABLE PRECORDITION FAILED	TEMPORARY_REDIRECT	307	HTTP/1.1, RFC 2616, Section 10.3.8
PAYMENT_REQUIRED	BAD_REQUEST	400	HTTP/1.1, RFC 2616, Section 10.4.1
FORBIDDEN	UNAUTHORIZED	401	HTTP/1.1, RFC 2616, Section 10.4.2
NOT_FOUND 404 HTTP/1.1, RFC 2616, Section 10.4.5 METHOD_NOT_ALLOWED 405 HTTP/1.1, RFC 2616, Section 10.4.6 NOT_ACCEPTABLE 406 HTTP/1.1, RFC 2616, Section 10.4.7 PROXY_AUTHENTICATION_REQUIRED 407 HTTP/1.1, RFC 2616, Section 10.4.8 REQUEST_TIMEOUT 408 HTTP/1.1, RFC 2616, Section 10.4.9 CONFLICT 409 HTTP/1.1, RFC 2616, Section 10.4.10 GONE 410 HTTP/1.1, RFC 2616, Section 10.4.11 LENGTH_REQUIRED 411 HTTP/1.1, RFC 2616, Section 10.4.12 PRECONDITION_FAILED 412 HTTP/1.1, RFC 2616, Section 10.4.13 REQUEST_URI_TOO_LONG 414 HTTP/1.1, RFC 2616, Section 10.4.13 UNSUPPORTED_MEDIA_TYPE 415 HTTP/1.1, RFC 2616, Section 10.4.15 EXPECTATION_FAILED 416 HTTP/1.1, RFC 2616, Section 10.4.16 UNPROCESSABLE_ENTITY 422 WEBDAV, RFC 2518, Section 10.3 LOCKED 423 WEBDAV, RFC 2518, Section 10.5 UPGRADE_REQUIRED 424 HTTP Upgrade to TLS, RFC 2817, Section 6 INTERNAL_SERVER_ERROR 500 HTTP/1.1, RFC 2616, Section 10.5.1 NOT_	PAYMENT_REQUIRED	402	HTTP/1.1, RFC 2616, Section 10.4.3
METHOD_NOT_ALLOWED 405 HTTP/1.1, RFC 2616, Section 10.4.6 NOT_ACCEPTABLE 406 HTTP/1.1, RFC 2616, Section 10.4.7 PROXY_AUTHENTICATION_REQUIRED 407 HTTP/1.1, RFC 2616, Section 10.4.8 REQUEST_INEOUT 408 HTTP/1.1, RFC 2616, Section 10.4.9 CONFLICT 409 HTTP/1.1, RFC 2616, Section 10.4.10 GONE 410 HTTP/1.1, RFC 2616, Section 10.4.11 LENGTH_REQUIRED 411 HTTP/1.1, RFC 2616, Section 10.4.12 PRECONDITION_FAILED 412 HTTP/1.1, RFC 2616, Section 10.4.12 PREQUEST_URI_TOO_LONG 414 HTTP/1.1, RFC 2616, Section 10.4.13 REQUEST_URI_TOO_LONG 414 HTTP/1.1, RFC 2616, Section 10.4.16 UNSUPPORTED_MEDIA_TYPE 415 HTTP/1.1, RFC 2616, Section 10.4.16 REQUEST_D_RANGE_NOT_SATISFIABLE 416 HTTP/1.1, RFC 2616, Section 10.4.17 EXPECTATION_FAILED 417 HTTP/1.1, RFC 2616, Section 10.4.18 UNPROCESSABLE_ENTITY 422 WEBDAV, RFC 2518, Section 10.3 LOCKED 423 WEBDAV, RFC 2518, Section 10.5 FAILED_DEPENDENCY 424 WEBDAV, RFC 2518, Section 10.5.1	FORBIDDEN	403	HTTP/1.1, RFC 2616, Section 10.4.4
NOT_ACCEPTABLE	NOT_FOUND	404	HTTP/1.1, RFC 2616, Section 10.4.5
PROXY_AUTHENTICATION_REQUIRED 407 REQUEST_TIMEOUT 408 HTTP/1.1, RFC 2616, Section 10.4.9 HTTP/1.1, RFC 2616, Section 10.4.10 HTTP/1.1, RFC 2616, Section 10.4.10 HTTP/1.1, RFC 2616, Section 10.4.11 HTTP/1.1, RFC 2616, Section 10.4.11 HTTP/1.1, RFC 2616, Section 10.4.12 HTTP/1.1, RFC 2616, Section 10.4.13 REQUEST_ENTITY_TOO_LARGE 413 HTTP/1.1, RFC 2616, Section 10.4.13 HTTP/1.1, RFC 2616, Section 10.4.14 HTTP/1.1, RFC 2616, Section 10.4.15 UNSUPPORTED_MEDIA_TYPE 415 HTTP/1.1, RFC 2616, Section 10.4.16 HTTP/1.1, RFC 2616, Section 10.4.16 HTTP/1.1, RFC 2616, Section 10.4.17 HTTP/1.1, RFC 2616, Section 10.4.18 UNPROCESSABLE_ENTITY 422 WEBDAV, RFC 2518, Section 10.3 WEBDAV, RFC 2518, Section 10.4 WEBDAV, RFC 2518, Section 10.5 UPGRADE_REQUIRED 426 HTTP/1.1, RFC 2616, Section 10.5.1 NOT_IMPLEMENTED 501 HTTP/1.1, RFC 2616, Section 10.5.2 HTTP/1.1, RFC 2616, Section 10.5.2 HTTP/1.1, RFC 2616, Section 10.5.3 SERVICE_UNAVAILABLE 503 HTTP/1.1, RFC 2616, Section 10.5.5 HTTP/1.1, RFC 2616, Section 10.5.6 WEBDAV, RFC 2518, Section 10.6 WEBDAV, RFC 2518, Section 10.6 WEBDAV, RFC 2518, Section 10.6 WEBDAV, RFC 251	METHOD_NOT_ALLOWED	405	HTTP/1.1, RFC 2616, Section 10.4.6
REQUEST_TIMEOUT	NOT_ACCEPTABLE	406	HTTP/1.1, RFC 2616, Section 10.4.7
CONFLICT 409 HTTP/1.1, RFC 2616, Section 10.4.10 GONE 410 HTTP/1.1, RFC 2616, Section 10.4.11 LENGTH_REQUIRED 411 HTTP/1.1, RFC 2616, Section 10.4.12 PRECONDITION_FAILED 412 HTTP/1.1, RFC 2616, Section 10.4.13 REQUEST_ENTITY_TOO_LARGE 413 HTTP/1.1, RFC 2616, Section 10.4.14 REQUEST_URI_TOO_LONG 414 HTTP/1.1, RFC 2616, Section 10.4.15 UNSUPPORTED_MEDIA_TYPE 415 HTTP/1.1, RFC 2616, Section 10.4.16 REQUESTED_RANGE_NOT_SATISFIABLE 416 HTTP/1.1, RFC 2616, Section 10.4.17 EXPECTATION_FAILED 417 HTTP/1.1, RFC 2616, Section 10.4.18 UNPROCESSABLE_ENTITY 422 WEBDAV, RFC 2518, Section 10.3 LOCKED 423 WEBDAV, RFC 2518, Section 10.5 FAILED_DEPENDENCY 424 WEBDAV, RFC 2518, Section 10.5 UPGRADE_REQUIRED 426 HTTP/1.1, RFC 2616, Section 10.5.1 NOT_IMPLEMENTED 501 HTTP/1.1, RFC 2616, Section 10.5.2 BAD_GATEWAY 502 HTTP/1.1, RFC 2616, Section 10.5.3 SERVICE_UNAVAILABLE 503 HTTP/1.1, RFC 2616, Section 10.5.6 H	PROXY_AUTHENTICATION_REQUIRED	407	HTTP/1.1, RFC 2616, Section 10.4.8
GONE	REQUEST_TIMEOUT	408	HTTP/1.1, RFC 2616, Section 10.4.9
LENGTH_REQUIRED	CONFLICT	409	HTTP/1.1, RFC 2616, Section 10.4.10
PRECONDITION_FAILED 412 HTTP/1.1, RFC 2616, Section 10.4.13 REQUEST_ENTITY_TOO_LARGE 413 HTTP/1.1, RFC 2616, Section 10.4.14 REQUEST_URI_TOO_LONG 414 HTTP/1.1, RFC 2616, Section 10.4.15 UNSUPPORTED_MEDIA_TYPE 415 HTTP/1.1, RFC 2616, Section 10.4.16 REQUESTED_RANGE_NOT_SATISFIABLE 416 HTTP/1.1, RFC 2616, Section 10.4.17 EXPECTATION_FAILED 417 HTTP/1.1, RFC 2616, Section 10.4.18 UNPROCESSABLE_ENTITY 422 WEBDAV, RFC 2518, Section 10.3 LOCKED 423 WEBDAV, RFC 2518, Section 10.4 FAILED_DEPENDENCY 424 WEBDAV, RFC 2518, Section 10.5 UPGRADE_REQUIRED 426 HTTP Upgrade to TLS, RFC 2817, Section 6 INTERNAL_SERVER_ERROR 500 HTTP/1.1, RFC 2616, Section 10.5.1 NOT_IMPLEMENTED 501 HTTP/1.1, RFC 2616, Section 10.5.2 BAD_GATEWAY 502 HTTP/1.1, RFC 2616, Section 10.5.4 GATEWAY_TIMEOUT 504 HTTP/1.1, RFC 2616, Section 10.5.6 HTTP/1.1, RFC 2616, Section 10.5.6 HTTP/1.1, RFC 2616, Section 10.5.6 INSUFFICIENT_STORAGE 507 WEBDAV, RFC 2518, Section 10.6	GONE	410	HTTP/1.1, RFC 2616, Section 10.4.11
REQUEST_ENTITY_TOO_LARGE 413 HTTP/1.1, RFC 2616, Section 10.4.14 REQUEST_URI_TOO_LONG 414 HTTP/1.1, RFC 2616, Section 10.4.15 UNSUPPORTED_MEDIA_TYPE 415 HTTP/1.1, RFC 2616, Section 10.4.16 REQUESTED_RANGE_NOT_SATISFIABLE 416 HTTP/1.1, RFC 2616, Section 10.4.17 EXPECTATION_FAILED 417 HTTP/1.1, RFC 2616, Section 10.4.18 UNPROCESSABLE_ENTITY 422 WEBDAV, RFC 2518, Section 10.3 LOCKED 423 WEBDAV RFC 2518, Section 10.4 FAILED_DEPENDENCY 424 WEBDAV, RFC 2518, Section 10.5 UPGRADE_REQUIRED 426 HTTP Upgrade to TLS, RFC 2817, Section 6 INTERNAL_SERVER_ERROR 500 HTTP/1.1, RFC 2616, Section 10.5.1 NOT_IMPLEMENTED 501 HTTP/1.1, RFC 2616, Section 10.5.3 SERVICE_UNAVAILABLE 502 HTTP/1.1, RFC 2616, Section 10.5.4 GATEWAY_TIMEOUT 504 HTTP/1.1, RFC 2616, Section 10.5.5 HTTP/1.1, RFC 2616, Section 10.5.6 HTTP/1.1, RFC 2616, Section 10.5.6 INSUFFICIENT_STORAGE 507 WEBDAV, RFC 2518, Section 10.6	LENGTH_REQUIRED	411	HTTP/1.1, RFC 2616, Section 10.4.12
REQUEST_URI_TOO_LONG 414 HTTP/1.1, RFC 2616, Section 10.4.15 UNSUPPORTED_MEDIA_TYPE 415 HTTP/1.1, RFC 2616, Section 10.4.16 REQUESTED_RANGE_NOT_SATISFIABLE 416 HTTP/1.1, RFC 2616, Section 10.4.17 EXPECTATION_FAILED 417 HTTP/1.1, RFC 2616, Section 10.4.18 UNPROCESSABLE_ENTITY 422 WEBDAV, RFC 2518, Section 10.3 LOCKED 423 WEBDAV RFC 2518, Section 10.4 FAILED_DEPENDENCY 424 WEBDAV, RFC 2518, Section 10.5 UPGRADE_REQUIRED 426 HTTP Upgrade to TLS, RFC 2817, Section 6 INTERNAL_SERVER_ERROR 500 HTTP/1.1, RFC 2616, Section 10.5.1 NOT_IMPLEMENTED 501 HTTP/1.1, RFC 2616, Section 10.5.2 BAD_GATEWAY 502 HTTP/1.1, RFC 2616, Section 10.5.3 SERVICE_UNAVAILABLE 503 HTTP/1.1, RFC 2616, Section 10.5.4 GATEWAY_TIMEOUT 504 HTTP/1.1, RFC 2616, Section 10.5.6 HTTP/1.1, RFC 2616, Section 10.5.6 HTTP/1.1, RFC 2616, Section 10.5.6 INSUFFICIENT_STORAGE 507 WEBDAV, RFC 2518, Section 10.6	PRECONDITION_FAILED	412	HTTP/1.1, RFC 2616, Section 10.4.13
UNSUPPORTED_MEDIA_TYPE 415 HTTP/1.1, RFC 2616, Section 10.4.16 REQUESTED_RANGE_NOT_SATISFIABLE 416 HTTP/1.1, RFC 2616, Section 10.4.17 EXPECTATION_FAILED 417 HTTP/1.1, RFC 2616, Section 10.4.18 UNPROCESSABLE_ENTITY 422 WEBDAV, RFC 2518, Section 10.3 LOCKED 423 WEBDAV RFC 2518, Section 10.4 FAILED_DEPENDENCY 424 WEBDAV, RFC 2518, Section 10.5 UPGRADE_REQUIRED 426 HTTP Upgrade to TLS, RFC 2817, Section 6 INTERNAL_SERVER_ERROR 500 HTTP/1.1, RFC 2616, Section 10.5.1 NOT_IMPLEMENTED 501 HTTP/1.1, RFC 2616, Section 10.5.2 BAD_GATEWAY 502 HTTP/1.1 RFC 2616, Section 10.5.3 SERVICE_UNAVAILABLE 503 HTTP/1.1, RFC 2616, Section 10.5.4 GATEWAY_TIMEOUT 504 HTTP/1.1 RFC 2616, Section 10.5.5 HTTP/1.1, RFC 2616, Section 10.5.6 HTTP/1.1, RFC 2616, Section 10.5.6 INSUFFICIENT_STORAGE 507 WEBDAV, RFC 2518, Section 10.6	REQUEST_ENTITY_TOO_LARGE	413	HTTP/1.1, RFC 2616, Section 10.4.14
REQUESTED_RANGE_NOT_SATISFIABLE 416 HTTP/1.1, RFC 2616, Section 10.4.17 EXPECTATION_FAILED 417 HTTP/1.1, RFC 2616, Section 10.4.18 UNPROCESSABLE_ENTITY 422 WEBDAV, RFC 2518, Section 10.3 LOCKED 423 WEBDAV RFC 2518, Section 10.4 FAILED_DEPENDENCY 424 WEBDAV, RFC 2518, Section 10.5 UPGRADE_REQUIRED 426 HTTP Upgrade to TLS, RFC 2817, Section 6 INTERNAL_SERVER_ERROR 500 HTTP/1.1, RFC 2616, Section 10.5.1 NOT_IMPLEMENTED 501 HTTP/1.1, RFC 2616, Section 10.5.2 BAD_GATEWAY 502 HTTP/1.1, RFC 2616, Section 10.5.3 SERVICE_UNAVAILABLE 503 HTTP/1.1, RFC 2616, Section 10.5.4 GATEWAY_TIMEOUT 504 HTTP/1.1 RFC 2616, Section 10.5.5 HTTP_URRSION_NOT_SUPPORTED 505 HTTP/1.1, RFC 2616, Section 10.5.6 INSUFFICIENT_STORAGE 507 WEBDAV, RFC 2518, Section 10.6	REQUEST_URI_TOO_LONG	414	HTTP/1.1, RFC 2616, Section 10.4.15
EXPECTATION_FAILED 417 HTTP/1.1, RFC 2616, Section 10.4.18 UNPROCESSABLE_ENTITY 422 WEBDAV, RFC 2518, Section 10.3 LOCKED 423 WEBDAV RFC 2518, Section 10.4 FAILED_DEPENDENCY 424 WEBDAV, RFC 2518, Section 10.5 UPGRADE_REQUIRED 426 HTTP Upgrade to TLS, RFC 2817, Section 6 INTERNAL_SERVER_ERROR 500 HTTP/1.1, RFC 2616, Section 10.5.1 NOT_IMPLEMENTED 501 HTTP/1.1, RFC 2616, Section 10.5.2 BAD_GATEWAY 502 HTTP/1.1 RFC 2616, Section 10.5.3 SERVICE_UNAVAILABLE 503 HTTP/1.1, RFC 2616, Section 10.5.4 GATEWAY_TIMEOUT 504 HTTP/1.1 RFC 2616, Section 10.5.5 HTTP_URRSION_NOT_SUPPORTED 505 HTTP/1.1, RFC 2616, Section 10.5.6 INSUFFICIENT_STORAGE 507 WEBDAV, RFC 2518, Section 10.6	UNSUPPORTED_MEDIA_TYPE	415	HTTP/1.1, RFC 2616, Section 10.4.16
UNPROCESSABLE_ENTITY 422 WEBDAV, RFC 2518, Section 10.3 LOCKED 423 WEBDAV RFC 2518, Section 10.4 FAILED_DEPENDENCY 424 WEBDAV, RFC 2518, Section 10.5 UPGRADE_REQUIRED 426 HTTP Upgrade to TLS, RFC 2817, Section 6 INTERNAL_SERVER_ERROR 500 HTTP/1.1, RFC 2616, Section 10.5.1 NOT_IMPLEMENTED 501 HTTP/1.1, RFC 2616, Section 10.5.2 BAD_GATEWAY 502 HTTP/1.1 RFC 2616, Section 10.5.3 SERVICE_UNAVAILABLE 503 HTTP/1.1, RFC 2616, Section 10.5.4 GATEWAY_TIMEOUT 504 HTTP/1.1 RFC 2616, Section 10.5.5 HTTP_UERSION_NOT_SUPPORTED 505 HTTP/1.1, RFC 2616, Section 10.5.6 INSUFFICIENT_STORAGE 507 WEBDAV, RFC 2518, Section 10.6	REQUESTED_RANGE_NOT_SATISFIABLE	416	HTTP/1.1, RFC 2616, Section 10.4.17
LOCKED 423 WEBDAV RFC 2518, Section 10.4 FAILED_DEPENDENCY 424 WEBDAV, RFC 2518, Section 10.5 UPGRADE_REQUIRED 426 HTTP Upgrade to TLS, RFC 2817, Section 6 INTERNAL_SERVER_ERROR 500 HTTP/1.1, RFC 2616, Section 10.5.1 NOT_IMPLEMENTED 501 HTTP/1.1, RFC 2616, Section 10.5.2 BAD_GATEWAY 502 HTTP/1.1 RFC 2616, Section 10.5.3 SERVICE_UNAVAILABLE 503 HTTP/1.1, RFC 2616, Section 10.5.4 GATEWAY_TIMEOUT 504 HTTP/1.1 RFC 2616, Section 10.5.5 HTTP_VERSION_NOT_SUPPORTED 505 HTTP/1.1, RFC 2616, Section 10.5.6 INSUFFICIENT_STORAGE 507 WEBDAV, RFC 2518, Section 10.6	EXPECTATION_FAILED	417	HTTP/1.1, RFC 2616, Section 10.4.18
FAILED_DEPENDENCY 424 WEBDAV, RFC 2518, Section 10.5 UPGRADE_REQUIRED 426 HTTP Upgrade to TLS, RFC 2817, Section 6 INTERNAL_SERVER_ERROR 500 HTTP/1.1, RFC 2616, Section 10.5.1 NOT_IMPLEMENTED 501 HTTP/1.1, RFC 2616, Section 10.5.2 BAD_GATEWAY 502 HTTP/1.1 RFC 2616, Section 10.5.3 SERVICE_UNAVAILABLE 503 HTTP/1.1, RFC 2616, Section 10.5.4 GATEWAY_TIMEOUT 504 HTTP/1.1 RFC 2616, Section 10.5.5 HTTP_VERSION_NOT_SUPPORTED 505 HTTP/1.1, RFC 2616, Section 10.5.6 INSUFFICIENT_STORAGE 507 WEBDAV, RFC 2518, Section 10.6	UNPROCESSABLE_ENTITY	422	WEBDAV, RFC 2518, Section 10.3
UPGRADE_REQUIRED 426 HTTP Upgrade to TLS, RFC 2817, Section 6 INTERNAL_SERVER_ERROR 500 HTTP/1.1, RFC 2616, Section 10.5.1 NOT_IMPLEMENTED 501 HTTP/1.1, RFC 2616, Section 10.5.2 BAD_GATEWAY 502 HTTP/1.1 RFC 2616, Section 10.5.3 SERVICE_UNAVAILABLE 503 HTTP/1.1, RFC 2616, Section 10.5.4 GATEWAY_TIMEOUT 504 HTTP/1.1 RFC 2616, Section 10.5.5 HTTP_VERSION_NOT_SUPPORTED 505 HTTP/1.1, RFC 2616, Section 10.5.6 INSUFFICIENT_STORAGE 507 WEBDAV, RFC 2518, Section 10.6	LOCKED	423	WEBDAV RFC 2518, Section 10.4
INTERNAL_SERVER_ERROR 500 HTTP/1.1, RFC 2616, Section 10.5.1 NOT_IMPLEMENTED 501 HTTP/1.1, RFC 2616, Section 10.5.2 BAD_GATEWAY 502 HTTP/1.1 RFC 2616, Section 10.5.3 SERVICE_UNAVAILABLE 503 HTTP/1.1, RFC 2616, Section 10.5.4 GATEWAY_TIMEOUT 504 HTTP/1.1 RFC 2616, Section 10.5.5 HTTP_VERSION_NOT_SUPPORTED 505 HTTP/1.1, RFC 2616, Section 10.5.6 INSUFFICIENT_STORAGE 507 WEBDAV, RFC 2518, Section 10.6	FAILED_DEPENDENCY	424	WEBDAV, RFC 2518, Section 10.5
NOT_IMPLEMENTED 501 HTTP/1.1, RFC 2616, Section 10.5.2 BAD_GATEWAY 502 HTTP/1.1 RFC 2616, Section 10.5.3 SERVICE_UNAVAILABLE 503 HTTP/1.1, RFC 2616, Section 10.5.4 GATEWAY_TIMEOUT 504 HTTP/1.1 RFC 2616, Section 10.5.5 HTTP_VERSION_NOT_SUPPORTED 505 HTTP/1.1, RFC 2616, Section 10.5.6 INSUFFICIENT_STORAGE 507 WEBDAV, RFC 2518, Section 10.6	UPGRADE_REQUIRED	426	HTTP Upgrade to TLS, RFC 2817, Section 6
BAD_GATEWAY 502 HTTP/1.1 RFC 2616, Section 10.5.3 SERVICE_UNAVAILABLE 503 HTTP/1.1, RFC 2616, Section 10.5.4 GATEWAY_TIMEOUT 504 HTTP/1.1 RFC 2616, Section 10.5.5 HTTP_VERSION_NOT_SUPPORTED 505 HTTP/1.1, RFC 2616, Section 10.5.6 INSUFFICIENT_STORAGE 507 WEBDAV, RFC 2518, Section 10.6	INTERNAL_SERVER_ERROR	500	HTTP/1.1, RFC 2616, Section 10.5.1
SERVICE_UNAVAILABLE 503 HTTP/1.1, RFC 2616, Section 10.5.4 GATEWAY_TIMEOUT 504 HTTP/1.1 RFC 2616, Section 10.5.5 HTTP_VERSION_NOT_SUPPORTED 505 HTTP/1.1, RFC 2616, Section 10.5.6 INSUFFICIENT_STORAGE 507 WEBDAV, RFC 2518, Section 10.6	NOT_IMPLEMENTED	501	HTTP/1.1, RFC 2616, Section 10.5.2
GATEWAY_TIMEOUT HTTP_VERSION_NOT_SUPPORTED INSUFFICIENT_STORAGE 504 HTTP/1.1 RFC 2616, Section 10.5.5 HTTP/1.1, RFC 2616, Section 10.5.6 WEBDAV, RFC 2518, Section 10.6	BAD_GATEWAY	502	HTTP/1.1 RFC 2616, Section 10.5.3
HTTP_VERSION_NOT_SUPPORTED 505 HTTP/1.1, RFC 2616, Section 10.5.6 INSUFFICIENT_STORAGE 507 WEBDAV, RFC 2518, Section 10.6	SERVICE_UNAVAILABLE	503	HTTP/1.1, RFC 2616, Section 10.5.4
INSUFFICIENT_STORAGE 507 WEBDAV, RFC 2518, Section 10.6	GATEWAY_TIMEOUT	504	HTTP/1.1 RFC 2616, Section 10.5.5
	HTTP_VERSION_NOT_SUPPORTED	505	HTTP/1.1, RFC 2616, Section 10.5.6
NOT_EXTENDED 510 An HTTP Extension Framework, RFC 2774, Section 7	INSUFFICIENT_STORAGE	507	WEBDAV, RFC 2518, Section 10.6
	NOT_EXTENDED	510	An HTTP Extension Framework, RFC 2774, Section 7

11.6.1 HTTPConnection Objects

 ${\tt HTTPConnection}\ instances\ have\ the\ following\ methods:$

```
request(method, url[, body[, headers]])
```

This will send a request to the server using the HTTP request method method and the selector url. If the body argument is present, it should be a string of data to send after the headers are finished. The header

Content-Length is automatically set to the correct value. The *headers* argument should be a mapping of extra HTTP headers to send with the request.

getresponse()

Should be called after a request is sent to get the response from the server. Returns an HTTPResponse instance. **Note:** Note that you must have read the whole response before you can send a new request to the server.

set_debuglevel(level)

Set the debugging level (the amount of debugging output printed). The default debug level is 0, meaning no debugging output is printed.

connect()

Connect to the server specified when the object was created.

close()

Close the connection to the server.

As an alternative to using the request () method described above, you can also send your request step by step, by using the four functions below.

```
putrequest (request, selector[, skip_host[, skip_accept_encoding]])
```

This should be the first call after the connection to the server has been made. It sends a line to the server consisting of the *request* string, the *selector* string, and the HTTP version (HTTP/1.1). To disable automatic sending of Host: or Accept-Encoding: headers (for example to accept additional content encodings), specify *skip_host* or *skip_accept_encoding* with non-False values. Changed in version 2.4: *skip_accept_encoding* argument added.

putheader(header, argument[, ...])

Send an RFC 822-style header to the server. It sends a line to the server consisting of the header, a colon and a space, and the first argument. If more arguments are given, continuation lines are sent, each consisting of a tab and an argument.

endheaders()

Send a blank line to the server, signalling the end of the headers.

\mathtt{send} (data)

Send data to the server. This should be used directly only after the endheaders() method has been called and before getresponse() is called.

11.6.2 HTTPResponse Objects

HTTPResponse instances have the following methods and attributes:

read([amt])

Reads and returns the response body, or up to the next amt bytes.

getheader(name | , default |)

Get the contents of the header *name*, or *default* if there is no matching header.

getheaders()

Return a list of (header, value) tuples. New in version 2.4.

msg

A mimetools. Message instance containing the response headers.

version

HTTP protocol version used by server. 10 for HTTP/1.0, 11 for HTTP/1.1.

status

Status code returned by server.

reason

Reason phrase returned by server.

11.6.3 Examples

Here is an example session that uses the 'GET' method:

```
>>> import httplib
>>> conn = httplib.HTTPConnection("www.python.org")
>>> conn.request("GET", "/index.html")
>>> r1 = conn.getresponse()
>>> print r1.status, r1.reason
200 OK
>>> data1 = r1.read()
>>> conn.request("GET", "/parrot.spam")
>>> r2 = conn.getresponse()
>>> print r2.status, r2.reason
404 Not Found
>>> data2 = r2.read()
>>> conn.close()
```

Here is an example session that shows how to 'POST' requests:

11.7 ftplib — FTP protocol client

This module defines the class FTP and a few related items. The FTP class implements the client side of the FTP protocol. You can use this to write Python programs that perform a variety of automated FTP jobs, such as mirroring other ftp servers. It is also used by the module urllib to handle URLs that use FTP. For more information on FTP (File Transfer Protocol), see Internet RFC 959.

Here's a sample session using the ftplib module:

```
>>> from ftplib import FTP
>>> ftp = FTP('ftp.cwi.nl')
                              # connect to host, default port
>>> ftp.login()
                               # user anonymous, passwd anonymous@
>>> ftp.retrlines('LIST')
                              # list directory contents
total 24418
             5 ftp-usr pdmaint
                                      1536 Mar 20 09:48
drwxrwsr-x
dr-xr-srwt 105 ftp-usr pdmaint
-rw-r--r- 1 ftp-usr pdmaint
                                      1536 Mar 21 14:32
                                      5305 Mar 20 09:48 INDEX
>>> ftp.retrbinary('RETR README', open('README', 'wb').write)
'226 Transfer complete.'
>>> ftp.quit()
```

The module defines the following items:

class FTP([host[, user[, passwd[, acct]]]])

Return a new instance of the FTP class. When *host* is given, the method call connect(*host*) is made. When *user* is given, additionally the method call login(*user*, *passwd*, *acct*) is made (where *passwd* and *acct* default to the empty string when not given).

all_errors

The set of all exceptions (as a tuple) that methods of FTP instances may raise as a result of problems with the FTP connection (as opposed to programming errors made by the caller). This set includes the four exceptions listed below as well as socket.error and IOError.

exception error_reply

Exception raised when an unexpected reply is received from the server.

exception error_temp

Exception raised when an error code in the range 400–499 is received.

exception error_perm

Exception raised when an error code in the range 500–599 is received.

exception error_proto

Exception raised when a reply is received from the server that does not begin with a digit in the range 1–5.

See Also:

Module netrc (section 12.18):

Parser for the '.netrc' file format. The file '.netrc' is typically used by FTP clients to load user authentication information before prompting the user.

The file 'Tools/scripts/ftpmirror.py' in the Python source distribution is a script that can mirror FTP sites, or portions thereof, using the ftplib module. It can be used as an extended example that applies this module.

11.7.1 FTP Objects

Several methods are available in two flavors: one for handling text files and another for binary files. These are named for the command which is used followed by 'lines' for the text version or 'binary' for the binary version.

FTP instances have the following methods:

set_debuglevel(level)

Set the instance's debugging level. This controls the amount of debugging output printed. The default, 0, produces no debugging output. A value of 1 produces a moderate amount of debugging output, generally a single line per request. A value of 2 or higher produces the maximum amount of debugging output, logging each line sent and received on the control connection.

connect(host[, port])

Connect to the given host and port. The default port number is 21, as specified by the FTP protocol specification. It is rarely needed to specify a different port number. This function should be called only once for each instance; it should not be called at all if a host was given when the instance was created. All other methods can only be used after a connection has been made.

getwelcome()

Return the welcome message sent by the server in reply to the initial connection. (This message sometimes contains disclaimers or help information that may be relevant to the user.)

login([user[, passwd[, acct]]])

Log in as the given *user*. The *passwd* and *acct* parameters are optional and default to the empty string. If no *user* is specified, it defaults to 'anonymous'. If *user* is 'anonymous', the default *passwd* is 'anonymous@'. This function should be called only once for each instance, after a connection has been established; it should not be called at all if a host and user were given when the instance was created. Most FTP commands are only allowed after the client has logged in.

abort()

Abort a file transfer that is in progress. Using this does not always work, but it's worth a try.

sendcmd(command)

Send a simple command string to the server and return the response string.

voidcmd(command)

Send a simple command string to the server and handle the response. Return nothing if a response code in the range 200–299 is received. Raise an exception otherwise.

retrbinary(command, callback[, maxblocksize[, rest]])

Retrieve a file in binary transfer mode. *command* should be an appropriate 'RETR' command: 'RETR *filename'*. The *callback* function is called for each block of data received, with a single string argument giving the data block. The optional *maxblocksize* argument specifies the maximum chunk size to read on the low-level socket object created to do the actual transfer (which will also be the largest size of the data blocks passed to *callback*). A reasonable default is chosen. *rest* means the same thing as in the transfercmd() method.

retrlines(command[, callback])

Retrieve a file or directory listing in ASCII transfer mode. *command* should be an appropriate 'RETR' command (see retrbinary()) or a 'LIST' command (usually just the string 'LIST'). The *callback* function is called for each line, with the trailing CRLF stripped. The default *callback* prints the line to sys.stdout.

set_pasv(boolean)

Enable "passive" mode if *boolean* is true, other disable passive mode. (In Python 2.0 and before, passive mode was off by default; in Python 2.1 and later, it is on by default.)

storbinary(command, file[, blocksize])

Store a file in binary transfer mode. *command* should be an appropriate 'STOR' command: "STOR *file-name*". *file* is an open file object which is read until EOF using its read() method in blocks of size *blocksize* to provide the data to be stored. The *blocksize* argument defaults to 8192. Changed in version 2.1: default for *blocksize* added.

storlines(command, file)

Store a file in ASCII transfer mode. *command* should be an appropriate 'STOR' command (see storbinary()). Lines are read until EOF from the open file object *file* using its readline() method to provide the data to be stored.

transfercmd(cmd[, rest])

Initiate a transfer over the data connection. If the transfer is active, send a 'EPRT' or 'PORT' command and the transfer command specified by *cmd*, and accept the connection. If the server is passive, send a 'EPSV' or 'PASV' command, connect to it, and start the transfer command. Either way, return the socket for the connection

If optional *rest* is given, a 'REST' command is sent to the server, passing *rest* as an argument. *rest* is usually a byte offset into the requested file, telling the server to restart sending the file's bytes at the requested offset, skipping over the initial bytes. Note however that RFC 959 requires only that *rest* be a string containing characters in the printable range from ASCII code 33 to ASCII code 126. The transfercmd() method, therefore, converts *rest* to a string, but no check is performed on the string's contents. If the server does not recognize the 'REST' command, an error_reply exception will be raised. If this happens, simply call transfercmd() without a *rest* argument.

ntransfercmd(cmd[, rest])

Like transfercmd(), but returns a tuple of the data connection and the expected size of the data. If the expected size could not be computed, None will be returned as the expected size. cmd and rest means the same thing as in transfercmd().

nlst(argument[, ...])

Return a list of files as returned by the 'NLST' command. The optional *argument* is a directory to list (default is the current server directory). Multiple arguments can be used to pass non-standard options to the 'NLST' command.

dir(argument[,...])

Produce a directory listing as returned by the 'LIST' command, printing it to standard output. The optional *argument* is a directory to list (default is the current server directory). Multiple arguments can be used to

pass non-standard options to the 'LIST' command. If the last argument is a function, it is used as a *callback* function as for retrlines(); the default prints to sys.stdout. This method returns None.

rename (fromname, toname)

Rename file fromname on the server to toname.

delete(filename)

Remove the file named *filename* from the server. If successful, returns the text of the response, otherwise raises error_perm on permission errors or error_reply on other errors.

cwd (pathname)

Set the current directory on the server.

mkd (*pathname*)

Create a new directory on the server.

pwd()

Return the pathname of the current directory on the server.

rmd(dirname)

Remove the directory named dirname on the server.

size(filename)

Request the size of the file named *filename* on the server. On success, the size of the file is returned as an integer, otherwise None is returned. Note that the 'SIZE' command is not standardized, but is supported by many common server implementations.

quit()

Send a 'QUIT' command to the server and close the connection. This is the "polite" way to close a connection, but it may raise an exception of the server reponds with an error to the 'QUIT' command. This implies a call to the close() method which renders the FTP instance useless for subsequent calls (see below).

close()

Close the connection unilaterally. This should not be applied to an already closed connection such as after a successful call to quit(). After this call the FTP instance should not be used any more (after a call to close() or quit() you cannot reopen the connection by issuing another login() method).

11.8 gopherlib — Gopher protocol client

This module provides a minimal implementation of client side of the Gopher protocol. It is used by the module urllib to handle URLs that use the Gopher protocol.

The module defines the following functions:

send_selector(selector, host[, port])

Send a *selector* string to the gopher server at *host* and *port* (default 70). Returns an open file object from which the returned document can be read.

send_query(selector, query, host[, port])

Send a *selector* string and a *query* string to a gopher server at *host* and *port* (default 70). Returns an open file object from which the returned document can be read.

Note that the data returned by the Gopher server can be of any type, depending on the first character of the selector string. If the data is text (first character of the selector is '0'), lines are terminated by CRLF, and the data is terminated by a line consisting of a single '.', and a leading '.' should be stripped from lines that begin with '..'. Directory listings (first character of the selector is '1') are transferred using the same protocol.

11.9 poplib — POP3 protocol client

This module defines a class, POP3, which encapsulates a connection to a POP3 server and implements the protocol as defined in RFC 1725. The POP3 class supports both the minimal and optional command sets. Additionally, this module provides a class POP3_SSL, which provides support for connecting to POP3 servers that use SSL as

an underlying protocol layer.

Note that POP3, though widely supported, is obsolescent. The implementation quality of POP3 servers varies widely, and too many are quite poor. If your mailserver supports IMAP, you would be better off using the imaplib.IMAP4 class, as IMAP servers tend to be better implemented.

A single class is provided by the poplib module:

```
class POP3 (host[, port])
```

This class implements the actual POP3 protocol. The connection is created when the instance is initialized. If *port* is omitted, the standard POP3 port (110) is used.

```
class POP3_SSL(host[, port[, keyfile[, certfile]]])
```

This is a subclass of POP3 that connects to the server over an SSL encrypted socket. If *port* is not specified, 995, the standard POP3-over-SSL port is used. *keyfile* and *certfile* are also optional - they can contain a PEM formatted private key and certificate chain file for the SSL connection.

New in version 2.4.

One exception is defined as an attribute of the poplib module:

exception error_proto

Exception raised on any errors. The reason for the exception is passed to the constructor as a string.

See Also:

```
Module imaplib (section 11.10):
```

The standard Python IMAP module.

Frequently Asked Questions About Fetchmail

(http://www.catb.org/~esr/fetchmail/fetchmail-FAQ.html)

The FAQ for the **fetchmail** POP/IMAP client collects information on POP3 server variations and RFC noncompliance that may be useful if you need to write an application based on the POP protocol.

11.9.1 POP3 Objects

All POP3 commands are represented by methods of the same name, in lower-case; most return the response text sent by the server.

An POP3 instance has the following methods:

```
set_debuglevel(level)
```

Set the instance's debugging level. This controls the amount of debugging output printed. The default, 0, produces no debugging output. A value of 1 produces a moderate amount of debugging output, generally a single line per request. A value of 2 or higher produces the maximum amount of debugging output, logging each line sent and received on the control connection.

getwelcome()

Returns the greeting string sent by the POP3 server.

```
user(username)
```

Send user command, response should indicate that a password is required.

```
pass_(password)
```

Send password, response includes message count and mailbox size. Note: the mailbox on the server is locked until quit () is called.

```
apop(user, secret)
```

Use the more secure APOP authentication to log into the POP3 server.

rpop(user)

Use RPOP authentication (similar to UNIX r-commands) to log into POP3 server.

stat()

Get mailbox status. The result is a tuple of 2 integers: (message count, mailbox size).

```
list([which])
```

Request message list, result is in the form (response, ['mesg_num octets', ...], octets). If which is set, it is the message to list.

retr(which)

Retrieve whole message number *which*, and set its seen flag. Result is in form (*response*, ['line', ...], *octets*).

dele(which)

Flag message number *which* for deletion. On most servers deletions are not actually performed until QUIT (the major exception is Eudora QPOP, which deliberately violates the RFCs by doing pending deletes on any disconnect).

rset()

Remove any deletion marks for the mailbox.

noop()

Do nothing. Might be used as a keep-alive.

quit()

Signoff: commit changes, unlock mailbox, drop connection.

top(which. howmuch)

Retrieves the message header plus *howmuch* lines of the message after the header of message number *which*. Result is in form (*response*, ['line', ...], *octets*).

The POP3 TOP command this method uses, unlike the RETR command, doesn't set the message's seen flag; unfortunately, TOP is poorly specified in the RFCs and is frequently broken in off-brand servers. Test this method by hand against the POP3 servers you will use before trusting it.

uidl([which])

Return message digest (unique id) list. If *which* is specified, result contains the unique id for that message in the form 'response mesgnum uid, otherwise result is list (response, ['mesgnum uid', ...], octets).

Instances of POP3_SSL have no additional methods. The interface of this subclass is identical to its parent.

11.9.2 POP3 Example

Here is a minimal example (without error checking) that opens a mailbox and retrieves and prints all messages:

```
import getpass, poplib

M = poplib.POP3('localhost')
M.user(getpass.getuser())
M.pass_(getpass.getpass())
numMessages = len(M.list()[1])
for i in range(numMessages):
    for j in M.retr(i+1)[1]:
        print j
```

At the end of the module, there is a test section that contains a more extensive example of usage.

11.10 imaplib — IMAP4 protocol client

This module defines three classes, IMAP4, IMAP4_SSL and IMAP4_stream, which encapsulate a connection to an IMAP4 server and implement a large subset of the IMAP4rev1 client protocol as defined in RFC 2060. It is backward compatible with IMAP4 (RFC 1730) servers, but note that the 'STATUS' command is not supported in IMAP4.

Three classes are provided by the imaplib module, IMAP4 is the base class:

class IMAP4 ([host[, port]])

This class implements the actual IMAP4 protocol. The connection is created and protocol version (IMAP4 or IMAP4rev1) is determined when the instance is initialized. If *host* is not specified, ' ' (the local host) is used. If *port* is omitted, the standard IMAP4 port (143) is used.

Three exceptions are defined as attributes of the IMAP4 class:

exception IMAP4.error

Exception raised on any errors. The reason for the exception is passed to the constructor as a string.

exception IMAP4.abort

IMAP4 server errors cause this exception to be raised. This is a sub-class of IMAP4.error. Note that closing the instance and instantiating a new one will usually allow recovery from this exception.

exception IMAP4.readonly

This exception is raised when a writable mailbox has its status changed by the server. This is a sub-class of IMAP4.error. Some other client now has write permission, and the mailbox will need to be re-opened to re-obtain write permission.

There's also a subclass for secure connections:

class IMAP4_SSL([host[, port[, keyfile[, certfile]]]])

This is a subclass derived from IMAP4 that connects over an SSL encrypted socket (to use this class you need a socket module that was compiled with SSL support). If *host* is not specified, '' (the local host) is used. If *port* is omitted, the standard IMAP4-over-SSL port (993) is used. *keyfile* and *certfile* are also optional - they can contain a PEM formatted private key and certificate chain file for the SSL connection.

The second subclass allows for connections created by a child process:

class IMAP4_stream(command)

This is a subclass derived from IMAP4 that connects to the stdin/stdout file descriptors created by passing *command* to os.popen2(). New in version 2.3.

The following utility functions are defined:

Internaldate2tuple(datestr)

Converts an IMAP4 INTERNALDATE string to Coordinated Universal Time. Returns a time module tuple.

${\tt Int2AP}\,(\,num\,)$

Converts an integer into a string representation using characters from the set [A .. P].

ParseFlags(flagstr)

Converts an IMAP4 'FLAGS' response to a tuple of individual flags.

Time2Internaldate(date_time)

Converts a time module tuple to an IMAP4 'INTERNALDATE' representation. Returns a string in the form: "DD-Mmm-YYYY HH:MM:SS +HHMM" (including double-quotes).

Note that IMAP4 message numbers change as the mailbox changes; in particular, after an 'EXPUNGE' command performs deletions the remaining messages are renumbered. So it is highly advisable to use UIDs instead, with the UID command.

At the end of the module, there is a test section that contains a more extensive example of usage.

See Also:

Documents describing the protocol, and sources and binaries for servers implementing it, can all be found at the University of Washington's *IMAP Information Center* (http://www.cac.washington.edu/imap/).

11.10.1 IMAP4 Objects

All IMAP4rev1 commands are represented by methods of the same name, either upper-case or lower-case.

All arguments to commands are converted to strings, except for 'AUTHENTICATE', and the last argument to 'APPEND' which is passed as an IMAP4 literal. If necessary (the string contains IMAP4 protocol-sensitive characters and isn't enclosed with either parentheses or double quotes) each string is quoted. However, the *password*

argument to the 'LOGIN' command is always quoted. If you want to avoid having an argument string quoted (eg: the *flags* argument to 'STORE') then enclose the string in parentheses (eg: r'(\Deleted)').

Each command returns a tuple: (type, [data, ...]) where type is usually 'OK' or 'NO', and data is either the text from the command response, or mandated results from the command. Each data is either a string, or a tuple. If a tuple, then the first part is the header of the response, and the second part contains the data (ie: 'literal' value).

The *message_set* options to commands below is a string specifying one or more messages to be acted upon. It may be a simple message number ('1'), a range of message numbers ('2:4'), or a group of non-contiguous ranges separated by commas ('1:3,6:9'). A range can contain an asterisk to indicate an infinite upper bound ('3:*').

An IMAP4 instance has the following methods:

append(mailbox, flags, date_time, message)

Append message to named mailbox.

authenticate(mechanism, authobject)

Authenticate command — requires response processing.

mechanism specifies which authentication mechanism is to be used - it should appear in the instance variable capabilities in the form AUTH=mechanism.

authobject must be a callable object:

```
data = authobject(response)
```

It will be called to process server continuation responses. It should return data that will be encoded and sent to server. It should return None if the client abort response '*' should be sent instead.

check()

Checkpoint mailbox on server.

close()

Close currently selected mailbox. Deleted messages are removed from writable mailbox. This is the recommended command before 'LOGOUT'.

copy(message_set, new_mailbox)

Copy message_set messages onto end of new_mailbox.

create(mailbox)

Create new mailbox named mailbox.

delete(mailbox)

Delete old mailbox named mailbox.

deleteacl(mailbox, who)

Delete the ACLs (remove any rights) set for who on mailbox. New in version 2.4.

expunge()

Permanently remove deleted items from selected mailbox. Generates an 'EXPUNGE' response for each deleted message. Returned data contains a list of 'EXPUNGE' message numbers in order received.

fetch(message_set, message_parts)

Fetch (parts of) messages. *message_parts* should be a string of message part names enclosed within parentheses, eg: '" (UID BODY[TEXT]) "'. Returned data are tuples of message part envelope and data.

getacl(mailbox)

Get the 'ACL's for mailbox. The method is non-standard, but is supported by the 'Cyrus' server.

getquota(root)

Get the 'quota' *root*'s resource usage and limits. This method is part of the IMAP4 QUOTA extension defined in rfc2087. New in version 2.3.

getquotaroot(mailbox)

Get the list of 'quota' 'roots' for the named *mailbox*. This method is part of the IMAP4 QUOTA extension defined in rfc2087. New in version 2.3.

```
list([directory[, pattern]])
```

List mailbox names in *directory* matching *pattern. directory* defaults to the top-level mail folder, and *pattern* defaults to match anything. Returned data contains a list of 'LIST' responses.

login(user, password)

Identify the client using a plaintext password. The password will be quoted.

login_cram_md5(user, password)

Force use of 'CRAM-MD5' authentication when identifying the client to protect the password. Will only work if the server 'CAPABILITY' response includes the phrase 'AUTH-CRAM-MD5'. New in version 2.3.

logout()

Shutdown connection to server. Returns server 'BYE' response.

lsub([directory[, pattern]])

List subscribed mailbox names in directory matching pattern. *directory* defaults to the top level directory and *pattern* defaults to match any mailbox. Returned data are tuples of message part envelope and data.

myrights (mailbox)

Show my ACLs for a mailbox (i.e. the rights that I have on mailbox). New in version 2.4.

namespace()

Returns IMAP namespaces as defined in RFC2342. New in version 2.3.

noop()

Send 'NOOP' to server.

open (host, port)

Opens socket to *port* at *host*. The connection objects established by this method will be used in the read, readline, send, and shutdown methods. You may override this method.

partial(message_num, message_part, start, length)

Fetch truncated part of a message. Returned data is a tuple of message part envelope and data.

proxyauth(user)

Assume authentication as *user*. Allows an authorised administrator to proxy into any user's mailbox. New in version 2.3.

read(size)

Reads *size* bytes from the remote server. You may override this method.

readline()

Reads one line from the remote server. You may override this method.

recent()

Prompt server for an update. Returned data is None if no new messages, else value of 'RECENT' response.

rename(oldmailbox, newmailbox)

Rename mailbox named *oldmailbox* to *newmailbox*.

response(code)

Return data for response code if received, or None. Returns the given code, instead of the usual type.

search(charset, criterion[, ...])

select([mailbox[, readonly]])

Search mailbox for matching messages. *charset* may be None, in which case no 'CHARSET' will be specified in the request to the server. The IMAP protocol requires that at least one criterion be specified; an exception will be raised when the server returns an error.

Example:

```
# M is a connected IMAP4 instance...
typ, msgnums = M.search(None, 'FROM', '"LDJ"')
# or:
typ, msgnums = M.search(None, '(FROM "LDJ")')
```

Select a mailbox. Returned data is the count of messages in *mailbox* ('EXISTS' response). The default *mailbox* is 'INBOX'. If the *readonly* flag is set, modifications to the mailbox are not allowed.

send(data)

Sends data to the remote server. You may override this method.

```
setacl(mailbox, who, what)
```

Set an 'ACL' for mailbox. The method is non-standard, but is supported by the 'Cyrus' server.

```
setquota(root, limits)
```

Set the 'quota' *root*'s resource *limits*. This method is part of the IMAP4 QUOTA extension defined in rfc2087. New in version 2.3.

shutdown()

Close connection established in open. You may override this method.

socket()

Returns socket instance used to connect to server.

```
sort(sort_criteria, charset, search_criterion[, ...])
```

The sort command is a variant of search with sorting semantics for the results. Returned data contains a space separated list of matching message numbers.

Sort has two arguments before the <code>search_criterion</code> argument(s); a parenthesized list of <code>sort_criteria</code>, and the searching <code>charset</code>. Note that unlike <code>search</code>, the searching <code>charset</code> argument is mandatory. There is also a <code>uid sort</code> command which corresponds to <code>sort</code> the way that <code>uid search</code> corresponds to <code>search</code>. The <code>sort</code> command first searches the mailbox for messages that match the given searching criteria using the charset argument for the interpretation of strings in the searching criteria. It then returns the numbers of matching messages.

This is an 'IMAP4rev1' extension command.

status(mailbox, names)

Request named status conditions for mailbox.

```
store(message_set, command, flag_list)
```

Alters flag dispositions for messages in mailbox. *command* is specified by section 6.4.6 of RFC 2060 as being one of "FLAGS", "+FLAGS", or "-FLAGS", optionally with a suffix of ".SILENT".

For example, to set the delete flag on all messages:

```
typ, data = M.search(None, 'ALL')
for num in data[0].split():
    M.store(num, '+FLAGS', '\Deleted')
M.expunge()
```

subscribe(mailbox)

Subscribe to new mailbox.

```
thread(threading_algorithm, charset, search_criterion[, ...])
```

The thread command is a variant of search with threading semantics for the results. Returned data contains a space separated list of thread members.

Thread members consist of zero or more messages numbers, delimited by spaces, indicating successive parent and child.

Thread has two arguments before the <code>search_criterion</code> argument(s); a <code>threading_algorithm</code>, and the searching <code>charset</code>. Note that unlike <code>search</code>, the searching <code>charset</code> argument is mandatory. There is also a <code>uid</code> thread command which corresponds to <code>thread</code> the way that <code>uid search</code> corresponds to <code>search</code>. The <code>thread</code> command first searches the mailbox for messages that match the given searching criteria using the charset argument for the interpretation of strings in the searching criteria. It then returns the matching messages threaded according to the specified threading algorithm.

This is an 'IMAP4rev1' extension command. New in version 2.4.

```
uid(command, arg[, ...])
```

Execute command args with messages identified by UID, rather than message number. Returns response

appropriate to command. At least one argument must be supplied; if none are provided, the server will return an error and an exception will be raised.

unsubscribe(mailbox)

Unsubscribe from old mailbox.

```
xatom(name[, arg[, ...]])
```

Allow simple extension commands notified by server in 'CAPABILITY' response.

Instances of IMAP4_SSL have just one additional method:

```
ssl()
```

Returns SSLObject instance used for the secure connection with the server.

The following attributes are defined on instances of IMAP4:

PROTOCOL_VERSION

The most recent supported protocol in the 'CAPABILITY' response from the server.

debug

Integer value to control debugging output. The initialize value is taken from the module variable Debug. Values greater than three trace each command.

11.10.2 IMAP4 Example

Here is a minimal example (without error checking) that opens a mailbox and retrieves and prints all messages:

```
import getpass, imaplib

M = imaplib.IMAP4()
M.login(getpass.getuser(), getpass.getpass())
M.select()
typ, data = M.search(None, 'ALL')
for num in data[0].split():
    typ, data = M.fetch(num, '(RFC822)')
    print 'Message %s\n%s\n' % (num, data[0][1])
M.close()
M.logout()
```

11.11 nntplib — NNTP protocol client

This module defines the class NNTP which implements the client side of the NNTP protocol. It can be used to implement a news reader or poster, or automated news processors. For more information on NNTP (Network News Transfer Protocol), see Internet RFC 977.

Here are two small examples of how it can be used. To list some statistics about a newsgroup and print the subjects of the last 10 articles:

```
>>> s = NNTP('news.cwi.nl')
>>> resp, count, first, last, name = s.group('comp.lang.python')
>>> print 'Group', name, 'has', count, 'articles, range', first, 'to', last Group comp.lang.python has 59 articles, range 3742 to 3803
>>> resp, subs = s.xhdr('subject', first + '-' + last)
>>> for id, sub in subs[-10:]: print id, sub
3792 Re: Removing elements from a list while iterating...
3793 Re: Who likes Info files?
3794 Emacs and doc strings
3795 a few questions about the Mac implementation
3796 Re: executable python scripts
3797 Re: executable python scripts
3798 Re: a few questions about the Mac implementation
3799 Re: PROPOSAL: A Generic Python Object Interface for Python C Modules
3802 Re: executable python scripts
3803 Re: \POSIX{} wait and SIGCHLD
>>> s.quit()
'205 news.cwi.nl closing connection. Goodbye.'
```

To post an article from a file (this assumes that the article has valid headers):

```
>>> s = NNTP('news.cwi.nl')
>>> f = open('/tmp/article')
>>> s.post(f)
'240 Article posted successfully.'
>>> s.quit()
'205 news.cwi.nl closing connection. Goodbye.'
```

The module itself defines the following items:

```
class NNTP (host[, port[, user[, password[, readermode][, usenetrc]]]])
```

Return a new instance of the NNTP class, representing a connection to the NNTP server running on host host, listening at port port. The default port is 119. If the optional user and password are provided, or if suitable credentials are present in '!netrc' and the optional flag usenetrc is true (the default), the 'AUTHINFO USER' and 'AUTHINFO PASS' commands are used to identify and authenticate the user to the server. If the optional flag readermode is true, then a 'mode reader' command is sent before authentication is performed. Reader mode is sometimes necessary if you are connecting to an NNTP server on the local machine and intend to call reader-specific commands, such as 'group'. If you get unexpected NNTPPermanentErrors, you might need to set readermode. readermode defaults to None. usenetrc defaults to True.

Changed in version 2.4: usenetrc argument added.

class NNTPError()

Derived from the standard exception Exception, this is the base class for all exceptions raised by the nntplib module.

class NNTPReplyError()

Exception raised when an unexpected reply is received from the server. For backwards compatibility, the exception error_reply is equivalent to this class.

class NNTPTemporaryError()

Exception raised when an error code in the range 400–499 is received. For backwards compatibility, the exception error_temp is equivalent to this class.

class NNTPPermanentError()

Exception raised when an error code in the range 500–599 is received. For backwards compatibility, the exception error_perm is equivalent to this class.

class NNTPProtocolError()

Exception raised when a reply is received from the server that does not begin with a digit in the range 1–5. For backwards compatibility, the exception error_proto is equivalent to this class.

class NNTPDataError()

Exception raised when there is some error in the response data. For backwards compatibility, the exception error_data is equivalent to this class.

11.11.1 NNTP Objects

NNTP instances have the following methods. The *response* that is returned as the first item in the return tuple of almost all methods is the server's response: a string beginning with a three-digit code. If the server's response indicates an error, the method raises one of the above exceptions.

getwelcome()

Return the welcome message sent by the server in reply to the initial connection. (This message sometimes contains disclaimers or help information that may be relevant to the user.)

set_debuglevel(level)

Set the instance's debugging level. This controls the amount of debugging output printed. The default, 0, produces no debugging output. A value of 1 produces a moderate amount of debugging output, generally a single line per request or response. A value of 2 or higher produces the maximum amount of debugging output, logging each line sent and received on the connection (including message text).

newgroups (date, time, [file])

Send a 'NEWGROUPS' command. The *date* argument should be a string of the form 'yymmdd' indicating the date, and *time* should be a string of the form 'hhmmss' indicating the time. Return a pair (response, groups) where groups is a list of group names that are new since the given date and time. If the file parameter is supplied, then the output of the 'NEWGROUPS' command is stored in a file. If file is a string, then the method will open a file object with that name, write to it then close it. If file is a file object, then it will start calling write() on it to store the lines of the command output. If file is supplied, then the returned list is an empty list.

newnews (group, date, time, [file])

Send a 'NEWNEWS' command. Here, *group* is a group name or '*', and *date* and *time* have the same meaning as for newgroups(). Return a pair (*response*, *articles*) where *articles* is a list of message ids. If the *file* parameter is supplied, then the output of the 'NEWNEWS' command is stored in a file. If *file* is a string, then the method will open a file object with that name, write to it then close it. If *file* is a file object, then it will start calling write() on it to store the lines of the command output. If *file* is supplied, then the returned *list* is an empty list.

list([file])

Send a 'LIST' command. Return a pair (response, list) where list is a list of tuples. Each tuple has the form (group, last, first, flag), where group is a group name, last and first are the last and first article numbers (as strings), and flag is 'y' if posting is allowed, 'n' if not, and 'm' if the newsgroup is moderated. (Note the ordering: last, first.) If the file parameter is supplied, then the output of the 'LIST' command is stored in a file. If file is a string, then the method will open a file object with that name, write to it then close it. If file is a file object, then it will start calling write() on it to store the lines of the command output. If file is supplied, then the returned list is an empty list.

descriptions(grouppattern)

Send a 'LIST NEWSGROUPS' command, where *grouppattern* is a wildmat string as specified in RFC2980 (it's essentially the same as DOS or UNIX shell wildcard strings). Return a pair (response, list), where list is a list of tuples containing (name, title).

New in version 2.4.

description(group)

Get a description for a single group *group*. If more than one group matches (if 'group' is a real wildmat string), return the first match. If no group matches, return an empty string.

This elides the response code from the server. If the response code is needed, use descriptions().

New in version 2.4.

group(name)

Send a 'GROUP' command, where *name* is the group name. Return a tuple (*response*, *count*, *first*, *last*, *name*) where *count* is the (estimated) number of articles in the group, *first* is the first article number in the group, *last* is the last article number in the group, and *name* is the group name. The numbers are returned as strings.

help([file])

Send a 'HELP' command. Return a pair (response, list) where list is a list of help strings. If the file parameter is supplied, then the output of the 'HELP' command is stored in a file. If file is a string, then the method will open a file object with that name, write to it then close it. If file is a file object, then it will start calling write() on it to store the lines of the command output. If file is supplied, then the returned list is an empty list.

stat(id)

Send a 'STAT' command, where *id* is the message id (enclosed in '<' and '>') or an article number (as a string). Return a triple (*response*, *number*, *id*) where *number* is the article number (as a string) and *id* is the message id (enclosed in '<' and '>').

next()

Send a 'NEXT' command. Return as for stat().

last()

Send a 'LAST' command. Return as for stat().

head(id)

Send a 'HEAD' command, where *id* has the same meaning as for stat(). Return a tuple (*response*, *number*, *id*, *list*) where the first three are the same as for stat(), and *list* is a list of the article's headers (an uninterpreted list of lines, without trailing newlines).

body(*id*,[*file*])

Send a 'BODY' command, where *id* has the same meaning as for stat(). If the *file* parameter is supplied, then the body is stored in a file. If *file* is a string, then the method will open a file object with that name, write to it then close it. If *file* is a file object, then it will start calling write() on it to store the lines of the body. Return as for head(). If *file* is supplied, then the returned *list* is an empty list.

article(id)

Send an 'ARTICLE' command, where *id* has the same meaning as for stat(). Return as for head().

slave()

Send a 'SLAVE' command. Return the server's response.

xhdr (header, string, [file])

Send an 'XHDR' command. This command is not defined in the RFC but is a common extension. The *header* argument is a header keyword, e.g. 'subject'. The *string* argument should have the form 'first-last' where first and last are the first and last article numbers to search. Return a pair (response, list), where list is a list of pairs (id, text), where id is an article number (as a string) and text is the text of the requested header for that article. If the file parameter is supplied, then the output of the 'XHDR' command is stored in a file. If file is a string, then the method will open a file object with that name, write to it then close it. If file is a file object, then it will start calling write() on it to store the lines of the command output. If file is supplied, then the returned list is an empty list.

post(file)

Post an article using the 'POST' command. The *file* argument is an open file object which is read until EOF using its readline() method. It should be a well-formed news article, including the required headers. The post() method automatically escapes lines beginning with '.'.

ihave(id, file)

Send an 'IHAVE' command. *id* is a message id (enclosed in '<' and '>'). If the response is not an error, treat *file* exactly as for the post () method.

date()

Return a triple (*response*, *date*, *time*), containing the current date and time in a form suitable for the newnews() and newgroups() methods. This is an optional NNTP extension, and may not be supported by all servers.

xgtitle(name, [file])

Process an 'XGTITLE' command, returning a pair (response, list), where list is a list of tuples containing (name, title). If the file parameter is supplied, then the output of the 'XGTITLE' command is stored in a file. If file is a string, then the method will open a file object with that name, write to it then close it. If file is a file object, then it will start calling write() on it to store the lines of the command output. If file is supplied, then the returned list is an empty list. This is an optional NNTP extension, and may not be supported by all servers.

RFC2980 says "It is suggested that this extension be deprecated". Use descriptions() or description() instead.

xover(start, end, [file])

Return a pair (resp, list). list is a list of tuples, one for each article in the range delimited by the start and end article numbers. Each tuple is of the form (article number, subject, poster, date, id, references, size, lines). If the file parameter is supplied, then the output of the 'XOVER' command is stored in a file. If file is a string, then the method will open a file object with that name, write to it then close it. If file is a file object, then it will start calling write() on it to store the lines of the command output. If file is supplied, then the returned list is an empty list. This is an optional NNTP extension, and may not be supported by all servers.

xpath(id)

Return a pair (*resp*, *path*), where *path* is the directory path to the article with message ID *id*. This is an optional NNTP extension, and may not be supported by all servers.

quit()

Send a 'QUIT' command and close the connection. Once this method has been called, no other methods of the NNTP object should be called.

11.12 smtplib — SMTP protocol client

The smtplib module defines an SMTP client session object that can be used to send mail to any Internet machine with an SMTP or ESMTP listener daemon. For details of SMTP and ESMTP operation, consult RFC 821 (Simple Mail Transfer Protocol) and RFC 1869 (SMTP Service Extensions).

${\bf class} \; {\bf SMTP} \left(\left[host \left[, port \left[, local_hostname \right] \right] \right] \right)$

A SMTP instance encapsulates an SMTP connection. It has methods that support a full repertoire of SMTP and ESMTP operations. If the optional host and port parameters are given, the SMTP connect() method is called with those parameters during initialization. An SMTPConnectError is raised if the specified host doesn't respond correctly.

For normal use, you should only require the initialization/connect, sendmail(), and quit() methods. An example is included below.

A nice selection of exceptions is defined as well:

exception SMTPException

Base exception class for all exceptions raised by this module.

exception SMTPServerDisconnected

This exception is raised when the server unexpectedly disconnects, or when an attempt is made to use the SMTP instance before connecting it to a server.

exception SMTPResponseException

Base class for all exceptions that include an SMTP error code. These exceptions are generated in some instances when the SMTP server returns an error code. The error code is stored in the smtp_code attribute of the error, and the smtp_error attribute is set to the error message.

exception SMTPSenderRefused

Sender address refused. In addition to the attributes set by on all SMTPResponseException exceptions, this sets 'sender' to the string that the SMTP server refused.

exception SMTPRecipientsRefused

All recipient addresses refused. The errors for each recipient are accessible through the attribute

recipients, which is a dictionary of exactly the same sort as SMTP.sendmail() returns.

exception SMTPDataError

The SMTP server refused to accept the message data.

exception SMTPConnectError

Error occurred during establishment of a connection with the server.

exception SMTPHeloError

The server refused our 'HELO' message.

See Also:

RFC 821, "Simple Mail Transfer Protocol"

Protocol definition for SMTP. This document covers the model, operating procedure, and protocol details for SMTP.

RFC 1869, "SMTP Service Extensions"

Definition of the ESMTP extensions for SMTP. This describes a framework for extending SMTP with new commands, supporting dynamic discovery of the commands provided by the server, and defines a few additional commands.

11.12.1 SMTP Objects

An SMTP instance has the following methods:

set_debuglevel(level)

Set the debug output level. A true value for *level* results in debug messages for connection and for all messages sent to and received from the server.

connect([host[, port]])

Connect to a host on a given port. The defaults are to connect to the local host at the standard SMTP port (25). If the hostname ends with a colon (':') followed by a number, that suffix will be stripped off and the number interpreted as the port number to use. This method is automatically invoked by the constructor if a host is specified during instantiation.

docmd(cmd, , argstring)

Send a command *cmd* to the server. The optional argument *argstring* is simply concatenated to the command, separated by a space.

This returns a 2-tuple composed of a numeric response code and the actual response line (multiline responses are joined into one long line.)

In normal operation it should not be necessary to call this method explicitly. It is used to implement other methods and may be useful for testing private extensions.

If the connection to the server is lost while waiting for the reply, SMTPServerDisconnected will be raised.

helo([hostname])

Identify yourself to the SMTP server using 'HELO'. The hostname argument defaults to the fully qualified domain name of the local host.

In normal operation it should not be necessary to call this method explicitly. It will be implicitly called by the sendmail() when necessary.

ehlo([hostname])

Identify yourself to an ESMTP server using 'EHLO'. The hostname argument defaults to the fully qualified domain name of the local host. Examine the response for ESMTP option and store them for use by has_extn().

Unless you wish to use has_extn() before sending mail, it should not be necessary to call this method explicitly. It will be implicitly called by sendmail() when necessary.

has_extn(name)

Return True if *name* is in the set of SMTP service extensions returned by the server, False otherwise. Case is ignored.

verify(address)

Check the validity of an address on this server using SMTP 'VRFY'. Returns a tuple consisting of code 250 and a full RFC 822 address (including human name) if the user address is valid. Otherwise returns an SMTP error code of 400 or greater and an error string.

Note: Many sites disable SMTP 'VRFY' in order to foil spammers.

login(user, password)

Log in on an SMTP server that requires authentication. The arguments are the username and the password to authenticate with. If there has been no previous 'EHLO' or 'HELO' command this session, this method tries ESMTP 'EHLO' first. This method will return normally if the authentication was successful, or may raise the following exceptions:

SMTPHeloErrorThe server didn't reply properly to the 'HELO' greeting.

SMTPAuthenticationErrorThe server didn't accept the username/password combination.

SMTPErrorNo suitable authentication method was found.

```
starttls([keyfile[, certfile]])
```

Put the SMTP connection in TLS (Transport Layer Security) mode. All SMTP commands that follow will be encrypted. You should then call ehlo() again.

If keyfile and certfile are provided, these are passed to the socket module's ssl() function.

```
sendmail(from_addr, to_addrs, msg[, mail_options, rcpt_options])
```

Send mail. The required arguments are an RFC 822 from-address string, a list of RFC 822 to-address strings (a bare string will be treated as a list with 1 address), and a message string. The caller may pass a list of ESMTP options (such as '8bitmime') to be used in 'MAIL FROM' commands as *mail_options*. ESMTP options (such as 'DSN' commands) that should be used with all 'RCPT' commands can be passed as *rcpt_options*. (If you need to use different ESMTP options to different recipients you have to use the low-level methods such as mail, rcpt and data to send the message.)

Note: The *from_addr* and *to_addrs* parameters are used to construct the message envelope used by the transport agents. The SMTP does not modify the message headers in any way.

If there has been no previous 'EHLO' or 'HELO' command this session, this method tries ESMTP 'EHLO' first. If the server does ESMTP, message size and each of the specified options will be passed to it (if the option is in the feature set the server advertises). If 'EHLO' fails, 'HELO' will be tried and ESMTP options suppressed.

This method will return normally if the mail is accepted for at least one recipient. Otherwise it will throw an exception. That is, if this method does not throw an exception, then someone should get your mail. If this method does not throw an exception, it returns a dictionary, with one entry for each recipient that was refused. Each entry contains a tuple of the SMTP error code and the accompanying error message sent by the server.

This method may raise the following exceptions:

SMTPRecipientsRefusedAll recipients were refused. Nobody got the mail. The recipients attribute of the exception object is a dictionary with information about the refused recipients (like the one returned when at least one recipient was accepted).

SMTPHeloErrorThe server didn't reply properly to the 'HELO' greeting.

SMTPSenderRefusedThe server didn't accept the *from_addr*.

SMTPDataErrorThe server replied with an unexpected error code (other than a refusal of a recipient).

Unless otherwise noted, the connection will be open even after an exception is raised.

quit()

Terminate the SMTP session and close the connection.

Low-level methods corresponding to the standard SMTP/ESMTP commands 'HELP', 'RSET', 'NOOP', 'MAIL', 'RCPT', and 'DATA' are also supported. Normally these do not need to be called directly, so they are not documented here. For details, consult the module code.

11.12.2 SMTP Example

This example prompts the user for addresses needed in the message envelope ('To' and 'From' addresses), and the message to be delivered. Note that the headers to be included with the message must be included in the message as entered; this example doesn't do any processing of the RFC 822 headers. In particular, the 'To' and 'From' addresses must be included in the message headers explicitly.

```
import smtplib
def prompt(prompt):
    return raw_input(prompt).strip()
fromaddr = prompt("From: ")
toaddrs = prompt("To: ").split()
print "Enter message, end with ^D (Unix) or ^Z (Windows):"
# Add the From: and To: headers at the start!
msg = ("From: %s\r\nTo: %s\r\n"
       % (fromaddr, ", ".join(toaddrs)))
while 1:
    try:
        line = raw_input()
    except EOFError:
       break
    if not line:
       break
    msg = msg + line
print "Message length is " + repr(len(msg))
server = smtplib.SMTP('localhost')
server.set_debuglevel(1)
server.sendmail(fromaddr, toaddrs, msg)
server.quit()
```

11.13 smtpd — SMTP Server

This module offers several classes to implement SMTP servers. One is a generic do-nothing implementation, which can be overridden, while the other two offer specific mail-sending strategies.

11.13.1 SMTPServer Objects

class SMTPServer(localaddr, remoteaddr)

Create a new SMTPServer object, which binds to local address *localaddr*. It will treat *remoteaddr* as an upstream SMTP relayer. It inherits from asyncore.dispatcher, and so will insert itself into asyncore's event loop on instantiation.

process_message(peer, mailfrom, rcpttos, data)

Raise NotImplementedError exception. Override this in subclasses to do something useful with this message. Whatever was passed in the constructor as *remoteaddr* will be available as the _remoteaddr attribute. *peer* is the remote host's address, *mailfrom* is the envelope originator, *rcpttos* are the envelope recipients and *data* is a string containing the contents of the e-mail (which should be in RFC 2822 format).

11.13.2 DebuggingServer Objects

class DebuggingServer (localaddr, remoteaddr)

Create a new debugging server. Arguments are as per SMTPServer. Messages will be discarded, and printed on stdout.

11.13.3 PureProxy Objects

class PureProxy(localaddr, remoteaddr)

Create a new pure proxy server. Arguments are as per SMTPServer. Everything will be relayed to *remoteaddr*. Note that running this has a good chance to make you into an open relay, so please be careful.

11.13.4 MailmanProxy Objects

class MailmanProxy(localaddr, remoteaddr)

Create a new pure proxy server. Arguments are as per SMTPServer. Everything will be relayed to *remoteaddr*, unless local mailman configurations knows about an address, in which case it will be handled via mailman. Note that running this has a good chance to make you into an open relay, so please be careful.

11.14 telnetlib — Telnet client

The telnetlib module provides a Telnet class that implements the Telnet protocol. See RFC 854 for details about the protocol. In addition, it provides symbolic constants for the protocol characters (see below), and for the telnet options. The symbolic names of the telnet options follow the definitions in arpa/telnet.h, with the leading TELOPT_ removed. For symbolic names of options which are traditionally not included in arpa/telnet.h, see the module source itself.

The symbolic constants for the telnet commands are: IAC, DONT, DO, WONT, WILL, SE (Subnegotiation End), NOP (No Operation), DM (Data Mark), BRK (Break), IP (Interrupt process), AO (Abort output), AYT (Are You There), EC (Erase Character), EL (Erase Line), GA (Go Ahead), SB (Subnegotiation Begin).

$\mathbf{class}\; \mathbf{Telnet}\,(\,\big[\mathit{host}\big[,\mathit{port}\,\big]\,\big]\,)$

Telnet represents a connection to a Telnet server. The instance is initially not connected by default; the open() method must be used to establish a connection. Alternatively, the host name and optional port number can be passed to the constructor, to, in which case the connection to the server will be established before the constructor returns.

Do not reopen an already connected instance.

This class has many read_*() methods. Note that some of them raise EOFError when the end of the connection is read, because they can return an empty string for other reasons. See the individual descriptions below.

See Also:

RFC 854, "Telnet Protocol Specification"

Definition of the Telnet protocol.

11.14.1 Telnet Objects

Telnet instances have the following methods:

read_until(expected[, timeout])

Read until a given string, expected, is encountered or until timeout seconds have passed.

When no match is found, return whatever is available instead, possibly the empty string. Raise EOFError if the connection is closed and no cooked data is available.

read all()

Read all data until EOF; block until connection closed.

read_some()

Read at least one byte of cooked data unless EOF is hit. Return '' if EOF is hit. Block if no data is immediately available.

read_very_eager()

Read everything that can be without blocking in I/O (eager).

Raise EOFError if connection closed and no cooked data available. Return '' if no cooked data available otherwise. Do not block unless in the midst of an IAC sequence.

read_eager()

Read readily available data.

Raise EOFError if connection closed and no cooked data available. Return '' if no cooked data available otherwise. Do not block unless in the midst of an IAC sequence.

read_lazy()

Process and return data already in the queues (lazy).

Raise EOFError if connection closed and no data available. Return '' if no cooked data available otherwise. Do not block unless in the midst of an IAC sequence.

read_very_lazy()

Return any data available in the cooked queue (very lazy).

Raise EOFError if connection closed and no data available. Return '' if no cooked data available otherwise. This method never blocks.

read_sb_data()

Return the data collected between a SB/SE pair (suboption begin/end). The callback should access these data when it was invoked with a SE command. This method never blocks.

New in version 2.3.

open(host[, port])

Connect to a host. The optional second argument is the port number, which defaults to the standard Telnet port (23).

Do not try to reopen an already connected instance.

msg(msg[,*args])

Print a debug message when the debug level is > 0. If extra arguments are present, they are substituted in the message using the standard string formatting operator.

set_debuglevel(debuglevel)

Set the debug level. The higher the value of debuglevel, the more debug output you get (on sys.stdout).

close()

Close the connection.

get_socket()

Return the socket object used internally.

fileno()

Return the file descriptor of the socket object used internally.

write(buffer)

Write a string to the socket, doubling any IAC characters. This can block if the connection is blocked. May raise socket, error if the connection is closed.

interact()

Interaction function, emulates a very dumb Telnet client.

mt_interact()

Multithreaded version of interact().

expect(list[, timeout])

Read until one from a list of a regular expressions matches.

The first argument is a list of regular expressions, either compiled (re.RegexObject instances) or uncompiled (strings). The optional second argument is a timeout, in seconds; the default is to block indefi-

nitely.

Return a tuple of three items: the index in the list of the first regular expression that matches; the match object returned; and the text read up till and including the match.

If end of file is found and no text was read, raise EOFError. Otherwise, when nothing matches, return (-1, None, *text*) where *text* is the text received so far (may be the empty string if a timeout happened).

If a regular expression ends with a greedy match (such as [, *]) or if more than one expression can match the same input, the results are indeterministic, and may depend on the I/O timing.

set_option_negotiation_callback(callback)

Each time a telnet option is read on the input flow, this *callback* (if set) is called with the following parameters: callback(telnet socket, command (DO/DONT/WILL/WONT), option). No other action is done afterwards by telnetlib.

11.14.2 Telnet Example

A simple example illustrating typical use:

```
import getpass
import sys
import telnetlib

HOST = "localhost"
user = raw_input("Enter your remote account: ")
password = getpass.getpass()

tn = telnetlib.Telnet(HOST)

tn.read_until("login: ")
tn.write(user + "\n")
if password:
        tn.read_until("Password: ")
        tn.write(password + "\n")

tn.write("ls\n")
tn.write("exit\n")
print tn.read_all()
```

11.15 urlparse — Parse URLs into components

This module defines a standard interface to break Uniform Resource Locator (URL) strings up in components (addressing scheme, network location, path etc.), to combine the components back into a URL string, and to convert a "relative URL" to an absolute URL given a "base URL."

The module has been designed to match the Internet RFC on Relative Uniform Resource Locators (and discovered a bug in an earlier draft!).

It defines the following functions:

```
urlparse(urlstring[, default_scheme[, allow_fragments]])
```

Parse a URL into 6 components, returning a 6-tuple: (addressing scheme, network location, path, parameters, query, fragment identifier). This corresponds to the general structure of a URL: scheme://netloc/path:parameters?query#fragment. Each tuple item is a string, possibly empty. The components are not broken up in smaller parts (e.g. the network location is a single string), and % escapes are not expanded. The delimiters as shown above are not part of the tuple items, except for a leading slash in the path component, which is retained if present.

Example:

If the *default_scheme* argument is specified, it gives the default addressing scheme, to be used only if the URL string does not specify one. The default value for this argument is the empty string.

If the *allow_fragments* argument is zero, fragment identifiers are not allowed, even if the URL's addressing scheme normally does support them. The default value for this argument is 1.

urlunparse(tuple)

Construct a URL string from a tuple as returned by urlparse(). This may result in a slightly different, but equivalent URL, if the URL that was parsed originally had redundant delimiters, e.g. a? with an empty query (the draft states that these are equivalent).

urlsplit(urlstring[, default_scheme[, allow_fragments]])

This is similar to urlparse(), but does not split the params from the URL. This should generally be used instead of urlparse() if the more recent URL syntax allowing parameters to be applied to each segment of the *path* portion of the URL (see RFC 2396) is wanted. A separate function is needed to separate the path segments and parameters. This function returns a 5-tuple: (addressing scheme, network location, path, query, fragment identifier). New in version 2.2.

urlunsplit(tuple)

Combine the elements of a tuple as returned by urlsplit() into a complete URL as a string. New in version 2.2.

urljoin(base, url[, allow_fragments])

Construct a full ("absolute") URL by combining a "base URL" (base) with a "relative URL" (url). Informally, this uses components of the base URL, in particular the addressing scheme, the network location and (part of) the path, to provide missing components in the relative URL.

Example:

```
urljoin('http://www.cwi.nl/%7Eguido/Python.html', 'FAQ.html')
yields the string
    'http://www.cwi.nl/%7Eguido/FAQ.html'
```

The *allow_fragments* argument has the same meaning as for urlparse().

urldefrag(url)

If *url* contains a fragment identifier, returns a modified version of *url* with no fragment identifier, and the fragment identifier as a separate string. If there is no fragment identifier in *url*, returns *url* unmodified and an empty string.

See Also:

RFC 1738, "Uniform Resource Locators (URL)"

This specifies the formal syntax and semantics of absolute URLs.

RFC 1808, "Relative Uniform Resource Locators"

This Request For Comments includes the rules for joining an absolute and a relative URL, including a fair number of "Abnormal Examples" which govern the treatment of border cases.

RFC 2396, "Uniform Resource Identifiers (URI): Generic Syntax"

Document describing the generic syntactic requirements for both Uniform Resource Names (URNs) and Uniform Resource Locators (URLs).

11.16 SocketServer — A framework for network servers

The SocketServer module simplifies the task of writing network servers.

There are four basic server classes: TCPServer uses the Internet TCP protocol, which provides for continuous streams of data between the client and server. UDPServer uses datagrams, which are discrete packets of information that may arrive out of order or be lost while in transit. The more infrequently used UnixStreamServer and UnixDatagramServer classes are similar, but use UNIX domain sockets; they're not available on non-UNIX platforms. For more details on network programming, consult a book such as W. Richard Steven's UNIX Network Programming or Ralph Davis's Win32 Network Programming.

These four classes process requests *synchronously*; each request must be completed before the next request can be started. This isn't suitable if each request takes a long time to complete, because it requires a lot of computation, or because it returns a lot of data which the client is slow to process. The solution is to create a separate process or thread to handle each request; the ForkingMixIn and ThreadingMixIn mix-in classes can be used to support asynchronous behaviour.


Creating a server requires several steps. First, you must create a request handler class by subclassing the BaseRequestHandler class and overriding its handle() method; this method will process incoming requests. Second, you must instantiate one of the server classes, passing it the server's address and the request handler class. Finally, call the handle_request() or serve_forever() method of the server object to process one or many requests.

When inheriting from ThreadingMixIn for threaded connection behavior, you should explicitly declare how you want your threads to behave on an abrupt shutdown. The ThreadingMixIn class defines an attribute *daemon_threads*, which indicates whether or not the server should wait for thread termination. You should set the flag explicitly if you would like threads to behave autonomously; the default is False, meaning that Python will not exit until all threads created by ThreadingMixIn have exited.

Server classes have the same external methods and attributes, no matter what network protocol they use:

11.16.1 Server Creation Notes

There are five classes in an inheritance diagram, four of which represent synchronous servers of four types:



Note that UnixDatagramServer derives from UDPServer, not from UnixStreamServer – the only difference between an IP and a Unix stream server is the address family, which is simply repeated in both unix server classes.

Forking and threading versions of each type of server can be created using the ForkingMixIn and ThreadingMixIn mix-in classes. For instance, a threading UDP server class is created as follows:

class ThreadingUDPServer(ThreadingMixIn, UDPServer): pass

The mix-in class must come first, since it overrides a method defined in UDPServer. Setting the various member variables also changes the behavior of the underlying server mechanism.

To implement a service, you must derive a class from BaseRequestHandler and redefine its handle() method. You can then run various versions of the service by combining one of the server classes with your request handler class. The request handler class must be different for datagram or stream services. This can be hidden by using the handler subclasses StreamRequestHandler or DatagramRequestHandler.

Of course, you still have to use your head! For instance, it makes no sense to use a forking server if the service contains state in memory that can be modified by different requests, since the modifications in the child process would never reach the initial state kept in the parent process and passed to each child. In this case, you can use a threading server, but you will probably have to use locks to protect the integrity of the shared data.

On the other hand, if you are building an HTTP server where all data is stored externally (for instance, in the file system), a synchronous class will essentially render the service "deaf" while one request is being handled – which may be for a very long time if a client is slow to receive all the data it has requested. Here a threading or forking server is appropriate.

In some cases, it may be appropriate to process part of a request synchronously, but to finish processing in a forked child depending on the request data. This can be implemented by using a synchronous server and doing an explicit fork in the request handle class handle () method.

Another approach to handling multiple simultaneous requests in an environment that supports neither threads nor fork() (or where these are too expensive or inappropriate for the service) is to maintain an explicit table of partially finished requests and to use select() to decide which request to work on next (or whether to handle a new incoming request). This is particularly important for stream services where each client can potentially be connected for a long time (if threads or subprocesses cannot be used).

11.16.2 Server Objects

fileno()

Return an integer file descriptor for the socket on which the server is listening. This function is most commonly passed to select.select(), to allow monitoring multiple servers in the same process.

handle_request()

Process a single request. This function calls the following methods in order: get_request(), verify_request(), and process_request(). If the user-provided handle() method of the handler class raises an exception, the server's handle_error() method will be called.

serve_forever()

Handle an infinite number of requests. This simply calls handle_request() inside an infinite loop.

address_family

The family of protocols to which the server's socket belongs. socket.AF_INET and socket.AF_UNIX are two possible values.

RequestHandlerClass

The user-provided request handler class; an instance of this class is created for each request.

server_address

The address on which the server is listening. The format of addresses varies depending on the protocol family; see the documentation for the socket module for details. For Internet protocols, this is a tuple containing a string giving the address, and an integer port number: ('127.0.0.1', 80), for example.

socket

The socket object on which the server will listen for incoming requests.

The server classes support the following class variables:

allow_reuse_address

Whether the server will allow the reuse of an address. This defaults to False, and can be set in subclasses to change the policy.

request_queue_size

The size of the request queue. If it takes a long time to process a single request, any requests that arrive

while the server is busy are placed into a queue, up to request_queue_size requests. Once the queue is full, further requests from clients will get a "Connection denied" error. The default value is usually 5, but this can be overridden by subclasses.

socket_type

The type of socket used by the server; socket.SOCK_STREAM and socket.SOCK_DGRAM are two possible values.

There are various server methods that can be overridden by subclasses of base server classes like TCPServer; these methods aren't useful to external users of the server object.

finish_request()

Actually processes the request by instantiating RequestHandlerClass and calling its handle() method.

get_request()

Must accept a request from the socket, and return a 2-tuple containing the *new* socket object to be used to communicate with the client, and the client's address.

handle_error(request, client_address)

This function is called if the RequestHandlerClass's handle() method raises an exception. The default action is to print the traceback to standard output and continue handling further requests.

process_request(request, client_address)

Calls finish_request() to create an instance of the RequestHandlerClass. If desired, this function can create a new process or thread to handle the request; the ForkingMixIn and ThreadingMixIn classes do this.

server_activate()

Called by the server's constructor to activate the server. The default behavior just listens to the server's socket. May be overridden.

server_bind()

Called by the server's constructor to bind the socket to the desired address. May be overridden.

verify_request(request, client_address)

Must return a Boolean value; if the value is True, the request will be processed, and if it's False, the request will be denied. This function can be overridden to implement access controls for a server. The default implementation always returns True.

11.16.3 RequestHandler Objects

The request handler class must define a new handle() method, and can override any of the following methods. A new instance is created for each request.

finish()

Called after the handle() method to perform any clean-up actions required. The default implementation does nothing. If setup() or handle() raise an exception, this function will not be called.

handle()

This function must do all the work required to service a request. The default implementation does nothing. Several instance attributes are available to it; the request is available as self.request; the client address as self.client_address; and the server instance as self.server, in case it needs access to perserver information.

The type of self.request is different for datagram or stream services. For stream services, self.request is a socket object; for datagram services, self.request is a string. However, this can be hidden by using the request handler subclasses StreamRequestHandler or DatagramRequestHandler, which override the setup() and finish() methods, and provide self.rfile and self.wfile attributes. self.rfile and self.wfile can be read or written, respectively, to get the request data or return data to the client.

setup()

Called before the handle () method to perform any initialization actions required. The default implemen-

11.17 BaseHTTPServer — Basic HTTP server

This module defines two classes for implementing HTTP servers (Web servers). Usually, this module isn't used directly, but is used as a basis for building functioning Web servers. See the SimpleHTTPServer and CGIHTTPServer modules.

The first class, HTTPServer, is a SocketServer.TCPServer subclass. It creates and listens at the HTTP socket, dispatching the requests to a handler. Code to create and run the server looks like this:

class HTTPServer (server_address, RequestHandlerClass)

This class builds on the TCPServer class by storing the server address as instance variables named server_name and server_port. The server is accessible by the handler, typically through the handler's server instance variable.

class BaseHTTPRequestHandler(request, client_address, server)

This class is used to handle the HTTP requests that arrive at the server. By itself, it cannot respond to any actual HTTP requests; it must be subclassed to handle each request method (e.g. GET or POST). BaseHTTPRequestHandler provides a number of class and instance variables, and methods for use by subclasses.

The handler will parse the request and the headers, then call a method specific to the request type. The method name is constructed from the request. For example, for the request method 'SPAM', the do_SPAM() method will be called with no arguments. All of the relevant information is stored in instance variables of the handler. Subclasses should not need to override or extend the __init__() method.

BaseHTTPRequestHandler has the following instance variables:

client_address

Contains a tuple of the form (host, port) referring to the client's address.

command

Contains the command (request type). For example, 'GET'.

path

Contains the request path.

request_version

Contains the version string from the request. For example, 'HTTP/1.0'.

headers

Holds an instance of the class specified by the MessageClass class variable. This instance parses and manages the headers in the HTTP request.

rfile

Contains an input stream, positioned at the start of the optional input data.

wfile

Contains the output stream for writing a response back to the client. Proper adherence to the HTTP protocol must be used when writing to this stream.

BaseHTTPRequestHandler has the following class variables:

server_version

Specifies the server software version. You may want to override this. The format is multiple whitespace-separated strings, where each string is of the form name[/version]. For example, 'BaseHTTP/0.2'.

sys_version

Contains the Python system version, in a form usable by the version_string method and the server_version class variable. For example, 'Python/1.4'.

error_message_format

Specifies a format string for building an error response to the client. It uses parenthesized, keyed format specifiers, so the format operand must be a dictionary. The *code* key should be an integer, specifying the numeric HTTP error code value. *message* should be a string containing a (detailed) error message of what occurred, and *explain* should be an explanation of the error code number. Default *message* and *explain* values can found in the *responses* class variable.

protocol_version

This specifies the HTTP protocol version used in responses. If set to 'HTTP/1.1', the server will permit HTTP persistent connections; however, your server *must* then include an accurate Content-Length header (using send_header()) in all of its responses to clients. For backwards compatibility, the setting defaults to 'HTTP/1.0'.

MessageClass

Specifies a rfc822. Message-like class to parse HTTP headers. Typically, this is not overridden, and it defaults to mimetools. Message.

responses

This variable contains a mapping of error code integers to two-element tuples containing a short and long message. For example, {code: (shortmessage, longmessage)}. The shortmessage is usually used as the message key in an error response, and longmessage as the explain key (see the error_message_format class variable).

A BaseHTTPRequestHandler instance has the following methods:

handle()

Calls handle_one_request() once (or, if persistent connections are enabled, multiple times) to handle incoming HTTP requests. You should never need to override it; instead, implement appropriate do_*() methods.

handle_one_request()

This method will parse and dispatch the request to the appropriate do_* () method. You should never need to override it.

send_error(code[, message])

Sends and logs a complete error reply to the client. The numeric *code* specifies the HTTP error code, with *message* as optional, more specific text. A complete set of headers is sent, followed by text composed using the error_message_format class variable.

send_response(code, message)

Sends a response header and logs the accepted request. The HTTP response line is sent, followed by *Server* and *Date* headers. The values for these two headers are picked up from the version_string() and date_time_string() methods, respectively.

send_header(keyword, value)

Writes a specific HTTP header to the output stream. *keyword* should specify the header keyword, with *value* specifying its value.

end_headers()

Sends a blank line, indicating the end of the HTTP headers in the response.

log_request(|code|, size||)

Logs an accepted (successful) request. *code* should specify the numeric HTTP code associated with the response. If a size of the response is available, then it should be passed as the *size* parameter.

${\tt log_error}\,(\dots)$

Logs an error when a request cannot be fulfilled. By default, it passes the message to log_message(), so it takes the same arguments (*format* and additional values).

log_message(format, ...)

Logs an arbitrary message to sys.stderr. This is typically overridden to create custom error logging

mechanisms. The *format* argument is a standard printf-style format string, where the additional arguments to log_message() are applied as inputs to the formatting. The client address and current date and time are prefixed to every message logged.

version_string()

Returns the server software's version string. This is a combination of the server_version and sys_version class variables.

date_time_string()

Returns the current date and time, formatted for a message header.

log_data_time_string()

Returns the current date and time, formatted for logging.

address_string()

Returns the client address, formatted for logging. A name lookup is performed on the client's IP address.

See Also:

Module CGIHTTPServer (section 11.19):

Extended request handler that supports CGI scripts.

Module SimpleHTTPServer (section 11.18):

Basic request handler that limits response to files actually under the document root.

11.18 SimpleHTTPServer — Simple HTTP request handler

The SimpleHTTPServer module defines a request-handler class, interface-compatible with BaseHTTPServer.BaseHTTPRequestHandler, that serves files only from a base directory.

The SimpleHTTPServer module defines the following class:

class SimpleHTTPRequestHandler(request, client_address, server)

This class is used to serve files from the current directory and below, directly mapping the directory structure to HTTP requests.

A lot of the work, such as parsing the request, is done by the base class ${\tt BaseHTTPServer.BaseHTTPRequestHandler}$. This class implements the ${\tt do_GET()}$ and ${\tt do_HEAD()}$ functions.

The SimpleHTTPRequestHandler defines the following member variables:

server_version

This will be "SimpleHTTP/" + __version__, where __version__ is defined in the module.

extensions_map

A dictionary mapping suffixes into MIME types. The default is signified by an empty string, and is considered to be application/octet-stream. The mapping is used case-insensitively, and so should contain only lower-cased keys.

The SimpleHTTPRequestHandler defines the following methods:

do_HEAD(

This method serves the 'HEAD' request type: it sends the headers it would send for the equivalent GET request. See the do_GET() method for a more complete explanation of the possible headers.

do_GET()

The request is mapped to a local file by interpreting the request as a path relative to the current working directory.

If the request was mapped to a directory, the directory is checked for a file named index.html or index.htm (in that order). If found, the file's contents are returned; otherwise a directory listing is generated by calling the <code>list_directory()</code> method. This method uses <code>os.listdir()</code> to scan the directory, and returns a 404 error response if the <code>listdir()</code> fails.

If the request was mapped to a file, it is opened and the contents are returned. Any IOError exception in opening the requested file is mapped to a 404, 'File not found' error. Otherwise, the content type

is guessed by calling the guess_type() method, which in turn uses the extensions_map variable.

A 'Content-type:' header with the guessed content type is output, followed by a blank line signifying the end of the headers, and then the contents of the file are output. If the file's MIME type starts with text/ the file is opened in text mode; otherwise binary mode is used.

For example usage, see the implementation of the test() function.

See Also:

Module BaseHTTPServer (section 11.17):

Base class implementation for Web server and request handler.

11.19 CGIHTTPServer — CGI-capable HTTP request handler

The CGIHTTPServer module defines a request-handler class, interface compatible with BaseHTTPServer.BaseHTTPRequestHandler and inherits behavior from SimpleHTTPServer.SimpleHTTPRequestHandler but can also run CGI scripts.

Note: This module can run CGI scripts on UNIX and Windows systems; on Mac OS it will only be able to run Python scripts within the same process as itself.

The CGIHTTPServer module defines the following class:

class CGIHTTPRequestHandler (request, client_address, server)

This class is used to serve either files or output of CGI scripts from the current directory and below. Note that mapping HTTP hierarchic structure to local directory structure is exactly as in SimpleHTTPServer.SimpleHTTPRequestHandler.

The class will however, run the CGI script, instead of serving it as a file, if it guesses it to be a CGI script. Only directory-based CGI are used — the other common server configuration is to treat special extensions as denoting CGI scripts.

The do_GET() and do_HEAD() functions are modified to run CGI scripts and serve the output, instead of serving files, if the request leads to somewhere below the cgi_directories path.

The CGIHTTPRequestHandler defines the following data member:

cgi_directories

This th17lthis

2965 cookies. Note that the great majority of cookies on the Internet are Netscape cookies. cookielib attempts to follow the de-facto Netscape cookie protocol (which differs substantially from that set out in the original Netscape specification), including taking note of the max-age and port cookie-attributes introduced with RFC 2109. **Note:** The various named parameters found in Set-Cookie: and Set-Cookie2: headers (eg. domain and expires) are conventionally referred to as *attributes*. To distinguish them from Python attributes, the documentation for this module uses the term *cookie-attribute* instead.

The module defines the following exception:

exception LoadError

Instances of FileCookieJar raise this exception on failure to load cookies from a file.

The following classes are provided:

class CookieJar (policy=None)

policy is an object implementing the CookiePolicy interface.

The CookieJar class stores HTTP cookies. It extracts cookies from HTTP requests, and returns them in HTTP responses. CookieJar instances automatically expire contained cookies when necessary. Subclasses are also responsible for storing and retrieving cookies from a file or database.

class FileCookieJar (filename, delayload=None, policy=None)

policy is an object implementing the CookiePolicy interface. For the other arguments, see the documentation for the corresponding attributes.

A CookieJar which can load cookies from, and perhaps save cookies to, a file on disk. Cookies are **NOT** loaded from the named file until either the load() or revert() method is called. Subclasses of this class are documented in section 11.20.2.

class CookiePolicy()

This class is responsible for deciding whether each cookie should be accepted from / returned to the server.

Constructor arguments should be passed as keyword arguments only. *blocked_domains* is a sequence of domain names that we never accept cookies from, nor return cookies to. *allowed_domains* if not None, this is a sequence of the only domains for which we accept and return cookies. For all other arguments, see the documentation for CookiePolicy and DefaultCookiePolicy objects.

DefaultCookiePolicy implements the standard accept / reject rules for Netscape and RFC 2965 cookies. RFC 2109 cookies (ie. cookies received in a Set-Cookie: header with a version cookie-attribute of 1) are treated according to the RFC 2965 rules. DefaultCookiePolicy also provides some parameters to allow some fine-tuning of policy.

class Cookie()

This class represents Netscape, RFC 2109 and RFC 2965 cookies. It is not expected that users of cookielib construct their own Cookie instances. Instead, if necessary, call make_cookies() on a CookieJar instance.

See Also:

Module urllib2 (section 11.5):

URL opening with automatic cookie handling.

Module Cookie (section 11.21):

HTTP cookie classes, principally useful for server-side code. The cookielib and Cookie modules do not depend on each other.

http://wwwsearch.sf.net/ClientCookie/

Extensions to this module, including a class for reading Microsoft Internet Explorer cookies on Windows.

http://www.netscape.com/newsref/std/cookie_spec.html

The specification of the original Netscape cookie protocol. Though this is still the dominant protocol, the 'Netscape cookie protocol' implemented by all the major browsers (and cookielib) only bears a passing

resemblance to the one sketched out in cookie_spec.html.

RFC 2109, "HTTP State Management Mechanism"

Obsoleted by RFC 2965. Uses Set-Cookie: with version=1.

RFC 2965, "HTTP State Management Mechanism"

The Netscape protocol with the bugs fixed. Uses Set-Cookie2: in place of Set-Cookie:. Not widely used.

http://kristol.org/cookie/errata.html

Unfinished errata to RFC 2965.

RFC 2964, "Use of HTTP State Management"

11.20.1 CookieJar and FileCookieJar Objects

CookieJar objects support the iterator protocol for iterating over contained Cookie objects.

CookieJar has the following methods:

add_cookie_header(request)

Add correct Cookie: header to request.

If policy allows (ie. the rfc2965 and hide_cookie2 attributes of the CookieJar's CookiePolicy instance are true and false respectively), the Cookie2: header is also added when appropriate.

The request object (usually a urllib2.Request instance) must support the methods get_full_url(), get_host(), get_type(), unverifiable(), get_origin_req_host(), has_header(), get_header(), header_items(), and add_unredirected_header(), as documented by urllib2.

extract_cookies(response, request)

Extract cookies from HTTP response and store them in the CookieJar, where allowed by policy.

The CookieJar will look for allowable Set-Cookie: and Set-Cookie2: headers in the *response* argument, and store cookies as appropriate (subject to the CookiePolicy.set_ok() method's approval).

The response object (usually the result of a call to urllib2.urlopen(), or similar) should support an info() method, which returns an object with a getallmatchingheaders() method (usually a mimetools.Message instance).

The request object (usually a urllib2.Request instance) must support the methods get_full_url(), get_host(), unverifiable(), and get_origin_req_host(), as documented by urllib2. The request is used to set default values for cookie-attributes as well as for checking that the cookie is allowed to be set.

set_policy(policy)

Set the CookiePolicy instance to be used.

make_cookies(response, request)

Return sequence of Cookie objects extracted from response object.

See the documentation for extract_cookies for the interfaces required of the *response* and *request* arguments.

set_cookie_if_ok(cookie, request)

Set a Cookie if policy says it's OK to do so.

set_cookie(cookie)

Set a Cookie, without checking with policy to see whether or not it should be set.

clear([domain[, path[, name]]])

Clear some cookies.

If invoked without arguments, clear all cookies. If given a single argument, only cookies belonging to that *domain* will be removed. If given two arguments, cookies belonging to the specified *domain* and URL *path* are removed. If given three arguments, then the cookie with the specified *domain*, *path* and *name* is removed.

Raises KeyError if no matching cookie exists.

clear_session_cookies()

Discard all session cookies.

Discards all contained cookies that have a true discard attribute (usually because they had either no max-age or expires cookie-attribute, or an explicit discard cookie-attribute). For interactive browsers, the end of a session usually corresponds to closing the browser window.

Note that the save() method won't save session cookies anyway, unless you ask otherwise by passing a true *ignore_discard* argument.

FileCookieJar implements the following additional methods:

save (filename=None, ignore_discard=False, ignore_expires=False)
Save cookies to a file.

This base class raises NotImplementedError. Subclasses may leave this method unimplemented.

filename is the name of file in which to save cookies. If filename is not specified, self.filename is used (whose default is the value passed to the constructor, if any); if self.filename is None, ValueError is raised

ignore_discard: save even cookies set to be discarded. ignore_expires: save even cookies that have expired
The file is overwritten if it already exists, thus wiping all the cookies it contains. Saved cookies can be
restored later using the load() or revert()

11.20.3 CookiePolicy Objects

Objects implementing the CookiePolicy interface have the following methods:

set_ok(cookie, request)

Return boolean value indicating whether cookie should be accepted from server.

cookie is a cookielib. Cookie instance. *request* is an object implementing the interface defined by the documentation for CookieJar.extract_cookies().

return_ok(cookie, request)

Return boolean value indicating whether cookie should be returned to server.

cookie is a cookielib.Cookie instance. *request* is an object implementing the interface defined by the documentation for CookieJar.add_cookie_header().

domain_return_ok(domain, request)

Return false if cookies should not be returned, given cookie domain.

This method is an optimization. It removes the need for checking every cookie with a particular domain (which might involve reading many files). Returning true from domain_return_ok() and path_return_ok() leaves all the work to return_ok().

If domain_return_ok() returns true for the cookie domain, path_return_ok() is called for the cookie path. Otherwise, path_return_ok() and return_ok() are never called for that cookie domain. If path_return_ok() returns true, return_ok() is called with the Cookie object itself for a full check. Otherwise, return_ok() is never called for that cookie path.

Note that domain_return_ok() is called for every *cookie* domain, not just for the *request* domain. For example, the function might be called with both ".example.com" and "www.example.com" if the request domain is "www.example.com". The same goes for path_return_ok().

The *request* argument is as documented for return_ok().

path_return_ok(path, request)

Return false if cookies should not be returned, given cookie path.

See the documentation for domain_return_ok().

In addition to implementing the methods above, implementations of the CookiePolicy interface must also supply the following attributes, indicating which protocols should be used, and how. All of these attributes may be assigned to.

netscape

Implement Netscape protocol.

rfc2965

Implement RFC 2965 protocol.

hide_cookie2

Don't add Cookie2: header to requests (the presence of this header indicates to the server that we understand RFC 2965 cookies).

The most useful way to define a CookiePolicy class is by subclassing from DefaultCookiePolicy and overriding some or all of the methods above. CookiePolicy itself may be used as a 'null policy' to allow setting and receiving any and all cookies (this is unlikely to be useful).

11.20.4 DefaultCookiePolicy Objects

Implements the standard rules for accepting and returning cookies.

Both RFC 2965 and Netscape cookies are covered. RFC 2965 handling is switched off by default.

The easiest way to provide your own policy is to override this class and call its methods in your overridden implementations before adding your own additional checks:

```
import cookielib
class MyCookiePolicy(cookielib.DefaultCookiePolicy):
    def set_ok(self, cookie, request):
        if not cookielib.DefaultCookiePolicy.set_ok(self, cookie, request):
            return False
        if i_dont_want_to_store_this_cookie(cookie):
            return False
        return True
```

In addition to the features required to implement the CookiePolicy interface, this class allows you to block and allow domains from setting and receiving cookies. There are also some strictness switches that allow you to tighten up the rather loose Netscape protocol rules a little bit (at the cost of blocking some benign cookies).

A domain blacklist and whitelist is provided (both off by default). Only domains not in the blacklist and present in the whitelist (if the whitelist is active) participate in cookie setting and returning. Use the <code>blocked_domains</code> constructor argument, and <code>blocked_domains()</code> and <code>set_blocked_domains()</code> methods (and the corresponding argument and methods for <code>allowed_domains()</code>. If you set a whitelist, you can turn it off again by setting it to <code>None</code>.

Domains in block or allow lists that do not start with a dot must equal the cookie domain to be matched. For example, "example.com" matches a blacklist entry of "example.com", but "www.example.com" does not. Domains that do start with a dot are matched by more specific domains too. For example, both "www.example.com" and "www.coyote.example.com" match ".example.com" (but "example.com" itself does not). IP addresses are an exception, and must match exactly. For example, if blocked_domains contains "192.168.1.2" and ".168.1.2", 192.168.1.2 is blocked, but 193.168.1.2 is not.

DefaultCookiePolicy implements the following additional methods:

blocked_domains()

Return the sequence of blocked domains (as a tuple).

set_blocked_domains(blocked_domains)

Set the sequence of blocked domains.

is_blocked(domain)

Return whether *domain* is on the blacklist for setting or receiving cookies.

allowed_domains()

Return None, or the sequence of allowed domains (as a tuple).

set_allowed_domains(allowed_domains)

Set the sequence of allowed domains, or None.

is_not_allowed(domain)

Return whether *domain* is not on the whitelist for setting or receiving cookies.

DefaultCookiePolicy instances have the following attributes, which are all initialised from the constructor arguments of the same name, and which may all be assigned to.

General strictness switches:

strict_domain

Don't allow sites to set two-component domains with country-code top-level domains like .co.uk, .gov.uk, .co.nz.etc. This is far from perfect and isn't guaranteed to work!

RFC 2965 protocol strictness switches:

strict_rfc2965_unverifiable

Follow RFC 2965 rules on unverifiable transactions (usually, an unverifiable transaction is one resulting from a redirect or a request for an image hosted on another site). If this is false, cookies are *never* blocked on the basis of verifiability

Netscape protocol strictness switches:

strict_ns_unverifiable

apply RFC 2965 rules on unverifiable transactions even to Netscape cookies

strict_ns_domain

Flags indicating how strict to be with domain-matching rules for Netscape cookies. See below for acceptable values.

strict_ns_set_initial_dollar

Ignore cookies in Set-Cookie: headers that have names starting with '\$'.

strict_ns_set_path

Don't allow setting cookies whose path doesn't path-match request URI.

strict_ns_domain is a collection of flags. Its value is constructed by or-ing together (for example, DomainStrictNonDots | DomainStrictNonDomain means both flags are set).

DomainStrictNoDots

When setting cookies, the 'host prefix' must not contain a dot (eg. www.foo.bar.com can't set a cookie for .bar.com, because www.foo contains a dot).

DomainStrictNonDomain

Cookies that did not explicitly specify a domain cookie-attribute can only be returned to a domain equal to the domain that set the cookie (eg. spam.example.com won't be returned cookies from example.com that had no domain cookie-attribute).

DomainRFC2965Match

When setting cookies, require a full RFC 2965 domain-match.

The following attributes are provided for convenience, and are the most useful combinations of the above flags:

DomainLiberal

Equivalent to 0 (ie. all of the above Netscape domain strictness flags switched off).

DomainStrict

Equivalent to DomainStrictNoDots | DomainStrictNonDomain.

11.20.5 Cookie Objects

Cookie instances have Python attributes roughly corresponding to the standard cookie-attributes specified in the various cookie standards. The correspondence is not one-to-one, because there are complicated rules for assigning default values, and because the max-age and expires cookie-attributes contain equivalent information.

Assignment to these attributes should not be necessary other than in rare circumstances in a CookiePolicy method. The class does not enforce internal consistency, so you should know what you're doing if you do that.

version

Integer or None. Netscape cookies have version 0. RFC 2965 and RFC 2109 cookies have version 1.

name

Cookie name (a string).

value

Cookie value (a string), or None.

port

String representing a port or a set of ports (eg. '80', or '80,8080'), or None.

path

Cookie path (a string, eg. '/acme/rocket_launchers').

secure

True if cookie should only be returned over a secure connection.

expires

Integer expiry date in seconds since epoch, or None. See also the is_expired() method.

discard

True if this is a session cookie.

comment

String comment from the server explaining the function of this cookie, or None.

comment_url

URL linking to a comment from the server explaining the function of this cookie, or None.

port_specified

True if a port or set of ports was explicitly specified by the server (in the Set-Cookie: / Set-Cookie2: header).

domain_specified

True if a domain was explicitly specified by the server.

domain_initial_dot

True if the domain explicitly specified by the server began with a dot ('.').

Cookies may have additional non-standard cookie-attributes. These may be accessed using the following methods:

has_nonstandard_attr(name)

Return true if cookie has the named cookie-attribute.

get_nonstandard_attr(name, default=None)

If cookie has the named cookie-attribute, return its value. Otherwise, return default.

set_nonstandard_attr(name, value)

Set the value of the named cookie-attribute.

The Cookie class also defines the following method:

```
is_expired([now=None])
```

True if cookie has passed the time at which the server requested it should expire. If *now* is given (in seconds since the epoch), return whether the cookie has expired at the specified time.

11.20.6 Examples

The first example shows the most common usage of cookielib:

```
import cookielib, urllib2
cj = cookielib.CookieJar()
opener = urllib2.build_opener(urllib2.HTTPCookieProcessor(cj))
r = opener.open("http://example.com/")
```

This example illustrates how to open a URL using your Netscape, Mozilla, or Lynx cookies (assumes UNIX/Netscape convention for location of the cookies file):

```
import os, cookielib, urllib2
cj = cookielib.MozillaCookieJar()
cj.load(os.path.join(os.environ["HOME"], ".netscape/cookies.txt"))
opener = urllib2.build_opener(urllib2.HTTPCookieProcessor(cj))
r = opener.open("http://example.com/")
```

The next example illustrates the use of DefaultCookiePolicy. Turn on RFC 2965 cookies, be more strict about domains when setting and returning Netscape cookies, and block some domains from setting cookies or having them returned:

```
import urllib2
from cookielib import CookieJar, DefaultCookiePolicy
policy = DefaultCookiePolicy(
    rfc2965=True, strict_ns_domain=Policy.DomainStrict,
    blocked_domains=["ads.net", ".ads.net"])
cj = CookieJar(policy)
opener = urllib2.build_opener(urllib2.HTTPCookieProcessor(cj))
r = opener.open("http://example.com/")
```

11.21 Cookie — HTTP state management

The Cookie module defines classes for abstracting the concept of cookies, an HTTP state management mechanism. It supports both simple string-only cookies, and provides an abstraction for having any serializable data-type as cookie value.

The module formerly strictly applied the parsing rules described in the RFC 2109 and RFC 2068 specifications. It has since been discovered that MSIE 3.0x doesn't follow the character rules outlined in those specs. As a result, the parsing rules used are a bit less strict.

exception CookieError

Exception failing because of RFC 2109 invalidity: incorrect attributes, incorrect Set-Cookie: header, etc.

class BaseCookie([input])

This class is a dictionary-like object whose keys are strings and whose values are Morsel instances. Note that upon setting a key to a value, the value is first converted to a Morsel containing the key and the value.

If *input* is given, it is passed to the load() method.

class SimpleCookie([input])

This class derives from BaseCookie and overrides $value_decode()$ and $value_encode()$ to be the identity and str() respectively.

class SerialCookie([input])

This class derives from BaseCookie and overrides value_decode() and value_encode() to be the pickle.loads() and pickle.dumps().

Deprecated since release 2.3. Reading pickled values from untrusted cookie data is a huge security hole, as pickle strings can be crafted to cause arbitrary code to execute on your server. It is supported for backwards compatibility only, and may eventually go away.

class SmartCookie([input])

This class derives from BaseCookie. It overrides value_decode() to be pickle.loads() if it is a valid pickle, and otherwise the value itself. It overrides value_encode() to be pickle.dumps() unless it is a string, in which case it returns the value itself.

Deprecated since release 2.3. The same security warning from SerialCookie applies here.

A further security note is warranted. For backwards compatibility, the Cookie module exports a class named Cookie which is just an alias for SmartCookie. This is probably a mistake and will likely be removed in a future version. You should not use the Cookie class in your applications, for the same reason why you should not use the SerialCookie class.

See Also:

Module cookielib (section 11.20):

HTTP cookie handling for for web *clients*. The cookielib and Cookie modules do not depend on each other.

RFC 2109, "HTTP State Management Mechanism"

This is the state management specification implemented by this module.

11.21.1 Cookie Objects

value_decode(val)

Return a decoded value from a string representation. Return value can be any type. This method does nothing in BaseCookie — it exists so it can be overridden.

$value_encode(val)$

Return an encoded value. *val* can be any type, but return value must be a string. This method does nothing in BaseCookie — it exists so it can be overridden

In general, it should be the case that value_encode() and value_decode() are inverses on the range of *value_decode*.

output([attrs[, header[, sep]]])

Return a string representation suitable to be sent as HTTP headers. *attrs* and *header* are sent to each Morsel's output() method. *sep* is used to join the headers together, and is by default a newline.

js_output([attrs])

Return an embeddable JavaScript snippet, which, if run on a browser which supports JavaScript, will act the same as if the HTTP headers was sent.

The meaning for *attrs* is the same as in output().

load(rawdata)

If *rawdata* is a string, parse it as an HTTP_COOKIE and add the values found there as Morsels. If it is a dictionary, it is equivalent to:

```
for k, v in rawdata.items():
    cookie[k] = v
```

11.21.2 Morsel Objects

class Morsel()

Abstract a key/value pair, which has some RFC 2109 attributes.

Morsels are dictionary-like objects, whose set of keys is constant — the valid RFC 2109 attributes, which are

- •expires
- •path
- •comment
- •domain
- •max-age
- •secure
- •version

The keys are case-insensitive.

value

The value of the cookie.

coded value

The encoded value of the cookie — this is what should be sent.

key

The name of the cookie.

set(key, value, coded_value)

Set the *key*, *value* and *coded_value* members.

isReservedKey(K)

Whether *K* is a member of the set of keys of a Morsel.

output([attrs[, header]])

Return a string representation of the Morsel, suitable to be sent as an HTTP header. By default, all the attributes are included, unless *attrs* is given, in which case it should be a list of attributes to use. *header* is by default "Set-Cookie:".

js_output([attrs])

Return an embeddable JavaScript snippet, which, if run on a browser which supports JavaScript, will act the same as if the HTTP header was sent.

The meaning for *attrs* is the same as in output().

OutputString([attrs])

Return a string representing the Morsel, without any surrounding HTTP or JavaScript.

The meaning for *attrs* is the same as in output().

11.21.3 Example

The following example demonstrates how to use the Cookie module.

```
>>> import Cookie
>>> C = Cookie.SimpleCookie()
>>> C = Cookie.SerialCookie()
>>> C = Cookie.SmartCookie()
>>> C["fig"] = "newton"
>>> C["sugar"] = "wafer"
>>> print C # generate HTTP headers
Set-Cookie: sugar=wafer;
Set-Cookie: fig=newton;
>>> print C.output() # same thing
Set-Cookie: sugar=wafer;
Set-Cookie: fig=newton;
>>> C = Cookie.SmartCookie()
>>> C["rocky"] = "road"
>>> C["rocky"]["path"] = "/cookie"
>>> print C.output(header="Cookie:")
Cookie: rocky=road; Path=/cookie;
>>> print C.output(attrs=[], header="Cookie:")
Cookie: rocky=road;
>>> C = Cookie.SmartCookie()
>>> C.load("chips=ahoy; vienna=finger") # load from a string (HTTP header)
>>> print C
Set-Cookie: vienna=finger;
Set-Cookie: chips=ahoy;
>>> C = Cookie.SmartCookie()
>>> C.load('keebler="E=everybody; L=\\"Loves\\"; fudge=\\012;";')
>>> print C
Set-Cookie: keebler="E=everybody; L=\"Loves\"; fudge=\012;";
>>> C = Cookie.SmartCookie()
>>> C["oreo"] = "doublestuff"
>>> C["oreo"]["path"] = "/"
>>> print C
Set-Cookie: oreo=doublestuff; Path=/;
>>> C = Cookie.SmartCookie()
>>> C["twix"] = "none for you"
>>> C["twix"].value
'none for you'
>>> C = Cookie.SimpleCookie()
>>> C["number"] = 7 # equivalent to C["number"] = str(7)
>>> C["string"] = "seven"
>>> C["number"].value
>>> C["string"].value
'seven'
>>> print C
Set-Cookie: number=7;
Set-Cookie: string=seven;
>>> C = Cookie.SerialCookie()
>>> C["number"] = 7
>>> C["string"] = "seven"
>>> C["number"].value
>>> C["string"].value
'seven'
>>> print C
Set-Cookie: number="I7\012.";
Set-Cookie: string="S'seven'\012p1\012.";
>>> C = Cookie.SmartCookie()
>>> C["number"] = 7
>>> C["string"] = "seven"
>>> C["number"].value
>>> C["string"].value
'seven'
```

11.22 xmlrpclib — XML-RPC client access

New in version 2.2.

XML-RPC is a Remote Procedure Call method that uses XML passed via HTTP as a transport. With it, a client can call methods with parameters on a remote server (the server is named by a URI) and get back structured data. This module supports writing XML-RPC client code; it handles all the details of translating between conformable Python objects and XML on the wire.

class ServerProxy(uri[, transport[, encoding[, verbose[, allow_none]]]]))

A ServerProxy instance is an object that manages communication with a remote XML-RPC server. The required first argument is a URI (Uniform Resource Indicator), and will normally be the URL of the server. The optional second argument is a transport factory instance; by default it is an internal SafeTransport instance for https: URLs and an internal HTTP Transport instance otherwise. The optional third argument is an encoding, by default UTF-8. The optional fourth argument is a debugging flag. If *allow_none* is true, the Python constant None will be translated into XML; the default behaviour is for None to raise a TypeError. This is a commonly-used extension to the XML-RPC specification, but isn't supported by all clients and servers; see http://ontosys.com/xml-rpc/extensions.php for a description.

Both the HTTP and HTTPS transports support the URL syntax extension for HTTP Basic Authentication: http://user:pass@host:port/path. The user:pass portion will be base64-encoded as an HTTP 'Authorization' header, and sent to the remote server as part of the connection process when invoking an XML-RPC method. You only need to use this if the remote server requires a Basic Authentication user and password.

The returned instance is a proxy object with methods that can be used to invoke corresponding RPC calls on the remote server. If the remote server supports the introspection API, the proxy can also be used to query the remote server for the methods it supports (service discovery) and fetch other server-associated metadata.

ServerProxy instance methods take Python basic types and objects as arguments and return Python basic types and classes. Types that are conformable (e.g. that can be marshalled through XML), include the following (and except where noted, they are unmarshalled as the same Python type):

Name	Meaning
boolean	The True and False constants
integers	Pass in directly
floating-point numbers	Pass in directly
strings	Pass in directly
arrays	Any Python sequence type containing conformable elements. Arrays are returned as list
structures	A Python dictionary. Keys must be strings, values may be any conformable type.
dates	in seconds since the epoch; pass in an instance of the DateTime wrapper class
binary data	pass in an instance of the Binary wrapper class

This is the full set of data types supported by XML-RPC. Method calls may also raise a special Fault instance, used to signal XML-RPC server errors, or ProtocolError used to signal an error in the HTTP/HTTPS transport layer. Note that even though starting with Python 2.2 you can subclass builtin types, the xmlrpclib module currently does not marshal instances of such subclasses.

When passing strings, characters special to XML such as '<', '>', and '&' will be automatically escaped. However, it's the caller's responsibility to ensure that the string is free of characters that aren't allowed in XML, such as the control characters with ASCII values between 0 and 31; failing to do this will result in an XML-RPC request that isn't well-formed XML. If you have to pass arbitrary strings via XML-RPC, use the Binary wrapper class described below.

Server is retained as an alias for ServerProxy for backwards compatibility. New code should use ServerProxy.

See Also:

XML-RPC HOWTO

(http://xmlrpc-c.sourceforge.net/xmlrpc-howto/xmlrpc-howto.html)

A good description of XML operation and client software in several languages. Contains pretty much everything an XML-RPC client developer needs to know.

XML-RPC-Hacks page

(http://xmlrpc-c.sourceforge.net/hacks.php)

Extensions for various open-source libraries to support introspection and multicall.

11.22.1 ServerProxy Objects

A ServerProxy instance has a method corresponding to each remote procedure call accepted by the XML-RPC server. Calling the method performs an RPC, dispatched by both name and argument signature (e.g. the same method name can be overloaded with multiple argument signatures). The RPC finishes by returning a value, which may be either returned data in a conformant type or a Fault or ProtocolError object indicating an error

Servers that support the XML introspection API support some common methods grouped under the reserved system member:

system.listMethods()

This method returns a list of strings, one for each (non-system) method supported by the XML-RPC server.

system.methodSignature(name)

This method takes one parameter, the name of a method implemented by the XML-RPC server.It returns an array of possible signatures for this method. A signature is an array of types. The first of these types is the return type of the method, the rest are parameters.

Because multiple signatures (ie. overloading) is permitted, this method returns a list of signatures rather than a singleton.

Signatures themselves are restricted to the top level parameters expected by a method. For instance if a method expects one array of structs as a parameter, and it returns a string, its signature is simply "string, array". If it expects three integers and returns a string, its signature is "string, int, int, int".

If no signature is defined for the method, a non-array value is returned. In Python this means that the type of the returned value will be something other that list.

system.methodHelp(name)

This method takes one parameter, the name of a method implemented by the XML-RPC server. It returns a documentation string describing the use of that method. If no such string is available, an empty string is returned. The documentation string may contain HTML markup.

Introspection methods are currently supported by servers written in PHP, C and Microsoft .NET. Partial introspection support is included in recent updates to UserLand Frontier. Introspection support for Perl, Python and Java is available at the XML-RPC Hacks page.

11.22.2 Boolean Objects

This class may be initialized from any Python value; the instance returned depends only on its truth value. It supports various Python operators through __cmp__(), __repr__(), __int__(), and __nonzero__() methods, all implemented in the obvious ways.

It also has the following method, supported mainly for internal use by the unmarshalling code:

encode(out)

Write the XML-RPC encoding of this Boolean item to the out stream object.

11.22.3 DateTime Objects

This class may be initialized with seconds since the epoch, a time tuple, or an ISO 8601 time/date string. It has the following methods, supported mainly for internal use by the marshalling/unmarshalling code:

decode(string)

Accept a string as the instance's new time value.

encode(out)

Write the XML-RPC encoding of this DateTime item to the out stream object.

It also supports certain of Python's built-in operators through __cmp__ and __repr__ methods.

11.22.4 Binary Objects

This class may initialized from string data (which may include NULs). The primary access to the content of a Binary object is provided by an attribute:

data

The binary data encapsulated by the Binary instance. The data is provided as an 8-bit string.

Binary objects have the following methods, supported mainly for internal use by the marshalling/unmarshalling code:

decode(string)

Accept a base64 string and decode it as the instance's new data.

encode (out)

Write the XML-RPC base 64 encoding of this binary item to the out stream object.

It also supports certain of Python's built-in operators through a __cmp__() method.

11.22.5 Fault Objects

A Fault object encapsulates the content of an XML-RPC fault tag. Fault objects have the following members:

faultCode

A string indicating the fault type.

faultString

A string containing a diagnostic message associated with the fault.

11.22.6 ProtocolError Objects

A ProtocolError object describes a protocol error in the underlying transport layer (such as a 404 'not found' error if the server named by the URI does not exist). It has the following members:

url

The URI or URL that triggered the error.

errcode

The error code.

errmsg

The error message or diagnostic string.

headers

A string containing the headers of the HTTP/HTTPS request that triggered the error.

11.22.7 MultiCall Objects

New in version 2.4.

In http://www.xmlrpc.com/discuss/msgReader%241208, an approach is presented to encapsulate multiple calls to a remote server into a single request.

class MultiCall(server)

Create an object used to boxcar method calls. *server* is the eventual target of the call. Calls can be made to the result object, but they will immediately return *None*, and only store the call name and parameters in the MultiCall object. Calling the object itself causes all stored calls to be transmitted as a single system.multicall request. The result of this call is a generator; iterating over this generator yields the individual results.

A usage example of this class is

```
multicall = MultiCall(server_proxy)
multicall.add(2,3)
multicall.get_address("Guido")
add result, address = multicall()
```

11.22.8 Convenience Functions

boolean(value)

Convert any Python value to one of the XML-RPC Boolean constants, True or False.

binary(data)

Trivially convert any Python string to a Binary object.

```
dumps(params[, methodname[, methodresponse[, encoding[, allow_none]]]]])
```

Convert *params* into an XML-RPC request. or into a response if *methodresponse* is true. *params* can be either a tuple of arguments or an instance of the Fault exception class. If *methodresponse* is true, only a single value can be returned, meaning that *params* must be of length 1. *encoding*, if supplied, is the encoding to use in the generated XML; the default is UTF-8. Python's None value cannot be used in standard XML-RPC; to allow using it via an extension, provide a true value for *allow_none*.

loads(data)

Convert an XML-RPC request or response into Python objects, a (*params*, *methodname*). *params* is a tuple of argument; *methodname* is a string, or None if no method name is present in the packet. If the XML-RPC packet represents a fault condition, this function will raise a Fault exception.

11.22.9 Example of Client Usage

```
# simple test program (from the XML-RPC specification)

# server = ServerProxy("http://localhost:8000") # local server
server = ServerProxy("http://betty.userland.com")

print server

try:
    print server.examples.getStateName(41)
except Error, v:
    print "ERROR", v
```

11.23 SimpleXMLRPCServer — Basic XML-RPC server

The SimpleXMLRPCServer module provides a basic server framework for XML-RPC servers written in Python. Servers can either be free standing, using SimpleXMLRPCServer, or embedded in a CGI environment, using CGIXMLRPCRequestHandler.

```
class SimpleXMLRPCServer (addr[, requestHandler[, logRequests]])
```

Create a new server instance. The *requestHandler* parameter should be a factory for request handler instances; it defaults to SimpleXMLRPCRequestHandler. The *addr* and *requestHandler* parameters are passed to the SocketServer.TCPServer constructor. If *logRequests* is true (the default), requests will be logged; setting this parameter to false will turn off logging. This class provides methods for registration of functions that can be called by the XML-RPC protocol.

class CGIXMLRPCRequestHandler()

Create a new instance to handle XML-RPC requests in a CGI environment. New in version 2.3.

class SimpleXMLRPCRequestHandler()

Create a new request handler instance. This request handler supports POST requests and modifies logging so that the *logRequests* parameter to the SimpleXMLRPCServer constructor parameter is honored.

11.23.1 SimpleXMLRPCServer Objects

The SimpleXMLRPCServer class is based on SocketServer.TCPServer and provides a means of creating simple, stand alone XML-RPC servers.

register_function(function[, name])

Register a function that can respond to XML-RPC requests. If *name* is given, it will be the method name associated with *function*, otherwise *function*. __name__ will be used. *name* can be either a normal or Unicode string, and may contain characters not legal in Python identifiers, including the period character.

register_instance(instance[, allow_dotted_names])

Register an object which is used to expose method names which have not been registered using register_function(). If instance contains a _dispatch() method, it is called with the requested method name and the parameters from the request. Its API is def _dispatch(self, method, params) (note that params does not represent a variable argument list). If it calls an underlying function to perform its task, that function is called as func(*params), expanding the parameter list. The return value from _dispatch() is returned to the client as the result. If instance does not have a _dispatch() method, it is searched for an attribute matching the name of the requested method.

If the optional <code>allow_dotted_names</code> argument is true and the instance does not have a <code>_dispatch()</code> method, then if the requested method name contains periods, each component of the method name is searched for individually, with the effect that a simple hierarchical search is performed. The value found from this search is then called with the parameters from the request, and the return value is passed back to the client.

Warning: Enabling the *allow_dotted_names* option allows intruders to access your module's global variables and may allow intruders to execute arbitrary code on your machine. Only use this option on a secure, closed network.

Changed in version 2.3.5, 2.4.1: *allow_dotted_names* was added to plug a security hole; prior versions are insecure.

register_introspection_functions()

Registers the XML-RPC introspection functions system.listMethods, system.methodHelp and system.methodSignature. New in version 2.3.

register_multicall_functions()

Registers the XML-RPC multicall function system.multicall.

Example:

```
class MyFuncs:
    def div(self, x, y) : return x // y

server = SimpleXMLRPCServer(("localhost", 8000))
server.register_function(pow)
server.register_function(lambda x,y: x+y, 'add')
server.register_introspection_functions()
server.register_instance(MyFuncs())
server.serve_forever()
```

11.23.2 CGIXMLRPCRequestHandler

 $The \verb| CGIXMLRPCRequest| Handler class can be used to handle XML-RPC requests sent to Python CGI scripts.$

register_function(function[, name])

Register a function that can respond to XML-RPC requests. If *name* is given, it will be the method name associated with function, otherwise *function*.__*name*__ will be used.

Create a new request handler instance. This request handler supports XML-RPC POST requests, documentation GET requests, and modifies logging so that the *logRequests* parameter to the DocXMLRPCServer constructor parameter is honored.

11.24.1 DocXMLRPCServer Objects

The DocXMLRPCServer class is derived from SimpleXMLRPCServer. SimpleXMLRPCServer and provides a means of creating self-documenting, stand alone XML-RPC servers. HTTP POST requests are handled as XML-RPC method calls. HTTP GET requests are handled by generating pydoc-style HTML documentation. This allows a server to provide its own web-based documentation.

set_server_title(server_title)

Set the title used in the generated HTML documentation. This title will be used inside the HTML "title" element

set_server_name(server_name)

Set the name used in the generated HTML documentation. This name will appear at the top of the generated documentation inside a "h1" element.

set_server_documentation(server_documentation)

Set the description used in the generated HTML documentation. This description will appear as a paragraph, below the server name, in the documentation.

11.24.2 DocCGIXMLRPCRequestHandler

The DocCGIXMLRPCRequestHandler class is derived from SimpleXMLRPCServer.CGIXMLRPCRequestHandler and provides a means of creating self-documenting, XML-RPC CGI scripts. HTTP POST requests are handled as XML-RPC method calls. HTTP GET requests are handled by generating pydoc-style HTML documentation. This allows a server to provide its own web-based documentation.

set_server_title(server_title)

Set the title used in the generated HTML documentation. This title will be used inside the HTML "title" element.

set_server_name(server_name)

Set the name used in the generated HTML documentation. This name will appear at the top of the generated documentation inside a "h1" element.

set_server_documentation(server_documentation)

Set the description used in the generated HTML documentation. This description will appear as a paragraph, below the server name, in the documentation.

11.25 asyncore — Asynchronous socket handler

This module provides the basic infrastructure for writing asynchronous socket service clients and servers.

There are only two ways to have a program on a single processor do "more than one thing at a time." Multi-threaded programming is the simplest and most popular way to do it, but there is another very different technique, that lets you have nearly all the advantages of multi-threading, without actually using multiple threads. It's really only practical if your program is largely I/O bound. If your program is processor bound, then pre-emptive scheduled threads are probably what you really need. Network servers are rarely processor bound, however.

If your operating system supports the select() system call in its I/O library (and nearly all do), then you can use it to juggle multiple communication channels at once; doing other work while your I/O is taking place in the "background." Although this strategy can seem strange and complex, especially at first, it is in many ways easier to understand and control than multi-threaded programming. The asyncore module solves many of the difficult problems for you, making the task of building sophisticated high-performance network servers and clients a snap. For "conversational" applications and protocols the companion asynchat module is invaluable.

The basic idea behind both modules is to create one or more network *channels*, instances of class asyncore.dispatcher and asynchat.async_chat. Creating the channels adds them to a global map, used by the loop() function if you do not provide it with your own *map*.

Once the initial channel(s) is(are) created, calling the loop() function activates channel service, which continues until the last channel (including any that have been added to the map during asynchronous service) is closed.

```
loop([timeout[, use_poll[, map[,count]]]])
```

Enter a polling loop that terminates after count passes or all open channels have been closed. All arguments are optional. The (count) parameter defaults to None, resulting in the loop terminating only when all channels have been closed. The *timeout* argument sets the timeout parameter for the appropriate <code>select()</code> or <code>poll()</code> call, measured in seconds; the default is 30 seconds. The <code>use_poll</code> parameter, if true, indicates that <code>poll()</code> should be used in preference to <code>select()</code> (the default is <code>False</code>). The <code>map</code> parameter is a dictionary whose items are the channels to watch. As channels are closed they are deleted from their map. If <code>map</code> is omitted, a global map is used (this map is updated by the default class <code>__init__()</code> – make sure you extend, rather than override, <code>__init__()</code> if you want to retain this behavior).

Channels (instances of asyncore.dispatcher, asynchat.async_chat and subclasses thereof) can freely be mixed in the map.

class dispatcher()

The dispatcher class is a thin wrapper around a low-level socket object. To make it more useful, it has a few methods for event-handling which are called from the asynchronous loop. Otherwise, it can be treated as a normal non-blocking socket object.

Two class attributes can be modified, to improve performance, or possibly even to conserve memory.

ac_in_buffer_size

The asynchronous input buffer size (default 4096).

ac_out_buffer_size

The asynchronous output buffer size (default 4096).

The firing of low-level events at certain times or in certain connection states tells the asynchronous loop that certain higher-level events have taken place. For example, if we have asked for a socket to connect to another host, we know that the connection has been made when the socket becomes writable for the first time (at this point you know that you may write to it with the expectation of success). The implied higher-level events are:

Event	Description
handle_connect()	Implied by the first write event
handle_close()	Implied by a read event with no data available
handle_accept()	Implied by a read event on a listening socket

During asynchronous processing, each mapped channel's readable() and writable() methods are used to determine whether the channel's socket should be added to the list of channels select()ed or poll()ed for read and write events.

Thus, the set of channel events is larger than the basic socket events. The full set of methods that can be overridden in your subclass follows:

handle_read()

 $Called \ when \ the \ asynchronous \ loop \ detects \ that \ a \ \verb"read" (\) \ call \ on \ the \ channel's \ socket \ will \ succeed.$

handle_write()

Called when the asynchronous loop detects that a writable socket can be written. Often this method will implement the necessary buffering for performance. For example:

```
def handle_write(self):
    sent = self.send(self.buffer)
    self.buffer = self.buffer[sent:]
```

handle_expt()

Called when there is out of band (OOB) data for a socket connection. This will almost never happen, as OOB is tenuously supported and rarely used.

handle_connect()

Called when the active opener's socket actually makes a connection. Might send a "welcome" banner, or initiate a protocol negotiation with the remote endpoint, for example.

handle_close()

Called when the socket is closed.

handle_error()

Called when an exception is raised and not otherwise handled. The default version prints a condensed traceback.

handle_accept()

Called on listening channels (passive openers) when a connection can be established with a new remote endpoint that has issued a connect () call for the local endpoint.

readable()

Called each time around the asynchronous loop to determine whether a channel's socket should be added to the list on which read events can occur. The default method simply returns True, indicating that by default, all channels will be interested in read events.

writable()

Called each time around the asynchronous loop to determine whether a channel's socket should be added to the list on which write events can occur. The default method simply returns True, indicating that by default, all channels will be interested in write events.

In addition, each channel delegates or extends many of the socket methods. Most of these are nearly identical to their socket partners.

create_socket(family, type)

This is identical to the creation of a normal socket, and will use the same options for creation. Refer to the socket documentation for information on creating sockets.

connect (address)

As with the normal socket object, *address* is a tuple with the first element the host to connect to, and the second the port number.

send(data)

Send data to the remote end-point of the socket.

recv(buffer_size)

Read at most *buffer_size* bytes from the socket's remote end-point. An empty string implies that the channel has been closed from the other end.

listen(backlog)

Listen for connections made to the socket. The *backlog* argument specifies the maximum number of queued connections and should be at least 1; the maximum value is system-dependent (usually 5).

bind(address)

Bind the socket to *address*. The socket must not already be bound. (The format of *address* depends on the address family — see above.)

accept()

Accept a connection. The socket must be bound to an address and listening for connections. The return value is a pair (*conn*, *address*) where *conn* is a *new* socket object usable to send and receive data on the connection, and *address* is the address bound to the socket on the other end of the connection.

close()

Close the socket. All future operations on the socket object will fail. The remote end-point will receive no more data (after queued data is flushed). Sockets are automatically closed when they are garbage-collected.

11.25.1 asyncore Example basic HTTP client

As a basic example, below is a very basic HTTP client that uses the dispatcher class to implement its socket handling:

```
class http_client(asyncore.dispatcher):
   def __init__(self, host,path):
        asyncore.dispatcher.__init__(self)
        self.path = path
        self.create_socket(socket.AF_INET, socket.SOCK_STREAM)
        self.connect( (host, 80) )
        self.buffer = 'GET %s HTTP/1.0\r\n\r\n' % self.path
   def handle_connect(self):
       pass
   def handle_read(self):
        data = self.recv(8192)
        print data
   def writable(self):
        return (len(self.buffer) > 0)
   def handle_write(self):
        sent = self.send(self.buffer)
        self.buffer = self.buffer[sent:]
```

11.26 asynchat — Asynchronous socket command/response handler

This module builds on the asyncore infrastructure, simplifying asynchronous clients and servers and making it easier to handle protocols whose elements are terminated by arbitrary strings, or are of variable length. asynchat defines the abstract class async_chat that you subclass, providing implementations of the collect_incoming_data() and found_terminator() methods. It uses the same asynchronous loop as asyncore, and the two types of channel, asyncore.dispatcher and asynchat.async_chat, can freely be mixed in the channel map. Typically an asyncore.dispatcher server channel generates new asynchat.async_chat channel objects as it receives incoming connection requests.

class async_chat()

This class is an abstract subclass of asyncore.dispatcher. To make practical use of the code you must subclass async_chat, providing meaningful collect_incoming_data() and found_terminator() methods. The asyncore.dispatcher methods can be used, although not all make sense in a message/response context.

Like asyncore.dispatcher, async_chat defines a set of events that are generated by an analysis of socket conditions after a select() call. Once the polling loop has been started the async_chat object's methods are called by the event-processing framework with no action on the part of the programmer.

Unlike asyncore.dispatcher, async_chat allows you to define a first-in-first-out queue (fifo) of producers. A producer need have only one method, more(), which should return data to be transmitted on the channel. The producer indicates exhaustion (i.e. that it contains no more data) by having its more() method return the empty string. At this point the async_chat object removes the producer from the fifo and starts using the next producer, if any. When the producer fifo is empty the handle_write() method does nothing. You use the channel object's set_terminator() method to describe how to recognize the end of, or an important breakpoint in, an incoming transmission from the remote endpoint.

To build a functioning async_chat subclass your input methods collect_incoming_data() and found_terminator() must handle the data that the channel receives asynchronously. The methods are described below.

close_when_done()

Pushes a None on to the producer fifo. When this producer is popped off the fifo it causes the channel to be closed.

collect_incoming_data(data)

Called with *data* holding an arbitrary amount of received data. The default method, which must be overridden, raises a NotImplementedError exception.

discard_buffers()

In emergencies this method will discard any data held in the input and/or output buffers and the producer fife

found_terminator()

Called when the incoming data stream matches the termination condition set by set_terminator. The default method, which must be overridden, raises a NotImplementedError exception. The buffered input data should be available via an instance attribute.

get_terminator()

Returns the current terminator for the channel.

handle_close()

Called when the channel is closed. The default method silently closes the channel's socket.

handle_read()

Called when a read event fires on the channel's socket in the asynchronous loop. The default method checks for the termination condition established by set_terminator(), which can be either the appearance of a particular string in the input stream or the receipt of a particular number of characters. When the terminator is found, handle_read calls the found_terminator() method after calling collect_incoming_data() with any data preceding the terminating condition.

handle_write()

Called when the application may write data to the channel. The default method calls the initiate_send() method, which in turn will call refill_buffer() to collect data from the producer fifo associated with the channel.

push(data)

Creates a simple_producer object (*see below*) containing the data and pushes it on to the channel's producer_fifo to ensure its transmission. This is all you need to do to have the channel write the data out to the network, although it is possible to use your own producers in more complex schemes to implement encryption and chunking, for example.

push_with_producer(producer)

Takes a producer object and adds it to the producer fifo associated with the channel. When all currently-pushed producers have been exhausted the channel will consume this producer's data by calling its more () method and send the data to the remote endpoint.

readable()

Should return True for the channel to be included in the set of channels tested by the select() loop for readability.

refill_buffer()

Refills the output buffer by calling the more() method of the producer at the head of the fifo. If it is exhausted then the producer is popped off the fifo and the next producer is activated. If the current producer is, or becomes, None then the channel is closed.

set_terminator(term)

Sets the terminating condition to be recognised on the channel. term may be any of three types of value, corresponding to three different ways to handle incoming protocol data.

term	Description
string	Will call found_terminator() when the string is found in the input stream
integer	Will call found_terminator() when the indicated number of characters have been received
None	The channel continues to collect data forever

Note that any data following the terminator will be available for reading by the channel after found_terminator() is called.

writable()

Should return True as long as items remain on the producer fifo, or the channel is connected and the

channel's output buffer is non-empty.

11.26.1 asynchat - Auxiliary Classes and Functions

class simple_producer(data[, buffer_size=512])

A simple_producer takes a chunk of data and an optional buffer size. Repeated calls to its more() method yield successive chunks of the data no larger than *buffer_size*.

more()

Produces the next chunk of information from the producer, or returns the empty string.

```
class fifo([list=None])
```

Each channel maintains a fifo holding data which has been pushed by the application but not yet popped for writing to the channel. A fifo is a list used to hold data and/or producers until they are required. If the *list* argument is provided then it should contain producers or data items to be written to the channel.

is_empty()

Returns True iff the fifo is empty.

first()

Returns the least-recently push () ed item from the fifo.

push(data)

Adds the given data (which may be a string or a producer object) to the producer fifo.

pop()

If the fifo is not empty, returns True, first(), deleting the popped item. Returns False, None for an empty fifo.

The asynchat module also defines one utility function, which may be of use in network and textual analysis operations.

find_prefix_at_end(haystack, needle)

Returns True if string *haystack* ends with any non-empty prefix of string *needle*.

11.26.2 asynchat Example

The following partial example shows how HTTP requests can be read with async_chat. A web server might create an http_request_handler object for each incoming client connection. Notice that initially the channel terminator is set to match the blank line at the end of the HTTP headers, and a flag indicates that the headers are being read.

Once the headers have been read, if the request is of type POST (indicating that further data are present in the input stream) then the Content-Length: header is used to set a numeric terminator to read the right amount of data from the channel.

The handle_request() method is called once all relevant input has been marshalled, after setting the channel terminator to None to ensure that any extraneous data sent by the web client are ignored.

```
class http_request_handler(asynchat.async_chat):
    def __init__(self, conn, addr, sessions, log):
        asynchat.async_chat.__init__(self, conn=conn)
        self.addr = addr
        self.sessions = sessions
        self.ibuffer = []
        self.obuffer = ""
        self.set\_terminator("\r\n")
        self.reading_headers = True
        self.handling = False
        self.cgi_data = None
        self.log = log
    def collect_incoming_data(self, data):
        """Buffer the data"""
        self.ibuffer.append(data)
    def found_terminator(self):
        if self.reading_headers:
            self.reading_headers = False
            self.parse_headers("".join(self.ibuffer))
            self.ibuffer = []
            if self.op.upper() == "POST":
                clen = self.headers.getheader("content-length")
                self.set_terminator(int(clen))
            else:
                self.handling = True
                self.set_terminator(None)
                self.handle_request()
        elif not self.handling:
            self.set_terminator(None) # browsers sometimes over-send
            self.cgi_data = parse(self.headers, "".join(self.ibuffer))
            self.handling = True
            self.ibuffer = []
            self.handle_request()
```

Internet Data Handling

This chapter describes modules which support handling data formats commonly used on the Internet.

formatter Generic output formatter and device interface.

email.Iterators Iterate over a message object tree.

mailcap Mailcap file handling.

mailbox Read various mailbox formats.

mhlib Manipulate MH mailboxes from Python.

mimetools Tools for parsing MIME-style message bodies.

mimetypes Mapping of filename extensions to MIME types.

MimeWriter Generic MIME file writer.

mimify Mimification and unmimification of mail messages.

multifile Support for reading files which contain distinct parts, such as some MIME data.

rfc822 Parse RFC 2822 style mail messages.

base64 RFC 3548: Base16, Base32, Base64 Data Encodings

binascii Tools for converting between binary and various ASCII-encoded binary representations.

binhex Encode and decode files in binhex4 format.

quopri Encode and decode files using the MIME quoted-printable encoding.

uu Encode and decode files in uuencode format.

xdrlib Encoders and decoders for the External Data Representation (XDR).

netrc Loading of '.netrc' files.

robotparser Loads a 'robots.txt' file and answers questions about fetchability of other URLs.

Write and read tabular data to and from delimited files.

12.1 formatter — Generic output formatting

This module supports two interface definitions, each with multiple implementations. The *formatter* interface is used by the HTMLParser class of the htmllib module, and the *writer* interface is required by the formatter interface.

Formatter objects transform an abstract flow of formatting events into specific output events on writer objects. Formatters manage several stack structures to allow various properties of a writer object to be changed and restored; writers need not be able to handle relative changes nor any sort of "change back" operation. Specific writer properties which may be controlled via formatter objects are horizontal alignment, font, and left margin indentations. A mechanism is provided which supports providing arbitrary, non-exclusive style settings to a writer as well. Additional interfaces facilitate formatting events which are not reversible, such as paragraph separation.

Writer objects encapsulate device interfaces. Abstract devices, such as file formats, are supported as well as physical devices. The provided implementations all work with abstract devices. The interface makes available mechanisms for setting the properties which formatter objects manage and inserting data into the output.

12.1.1 The Formatter Interface

Interfaces to create formatters are dependent on the specific formatter class being instantiated. The interfaces described below are the required interfaces which all formatters must support once initialized.

One data element is defined at the module level:

AS IS

Value which can be used in the font specification passed to the push_font() method described below, or as the new value to any other push_property() method. Pushing the AS_IS value allows the corresponding pop_property() method to be called without having to track whether the property was changed.

The following attributes are defined for formatter instance objects:

writer

The writer instance with which the formatter interacts.

end_paragraph(blanklines)

Close any open paragraphs and insert at least blanklines before the next paragraph.

add_line_break()

Add a hard line break if one does not already exist. This does not break the logical paragraph.

add_hor_rule(*args, **kw)

Insert a horizontal rule in the output. A hard break is inserted if there is data in the current paragraph, but the logical paragraph is not broken. The arguments and keywords are passed on to the writer's send_line_break() method.

add_flowing_data(data)

Provide data which should be formatted with collapsed whitespace. Whitespace from preceding and successive calls to add_flowing_data() is considered as well when the whitespace collapse is performed. The data which is passed to this method is expected to be word-wrapped by the output device. Note that any word-wrapping still must be performed by the writer object due to the need to rely on device and font information.

add_literal_data(data)

Provide data which should be passed to the writer unchanged. Whitespace, including newline and tab characters, are considered legal in the value of *data*.

add_label_data(format, counter)

Insert a label which should be placed to the left of the current left margin. This should be used for constructing bulleted or numbered lists. If the *format* value is a string, it is interpreted as a format specification for *counter*, which should be an integer. The result of this formatting becomes the value of the label; if *format* is not a string it is used as the label value directly. The label value is passed as the only argument to the writer's send_label_data() method. Interpretation of non-string label values is dependent on the associated writer.

Format specifications are strings which, in combination with a counter value, are used to compute label values. Each character in the format string is copied to the label value, with some characters recognized to indicate a transform on the counter value. Specifically, the character '1' represents the counter value formatter as an Arabic number, the characters 'A' and 'a' represent alphabetic representations of the counter value in upper and lower case, respectively, and '1' and 'i' represent the counter value in Roman numerals, in upper and lower case. Note that the alphabetic and roman transforms require that the counter value be greater than zero.

flush_softspace()

Send any pending whitespace buffered from a previous call to add_flowing_data() to the associated writer object. This should be called before any direct manipulation of the writer object.

push_alignment(align)

Push a new alignment setting onto the alignment stack. This may be AS_IS if no change is desired. If the alignment value is changed from the previous setting, the writer's $new_alignment()$ method is called with the align value.

pop_alignment()

Restore the previous alignment.

push_font((size, italic, bold, teletype))

Change some or all font properties of the writer object. Properties which are not set to AS_IS are set to the values passed in while others are maintained at their current settings. The writer's new_font() method is called with the fully resolved font specification.

pop_font()

Restore the previous font.

push_margin(margin)

Increase the number of left margin indentations by one, associating the logical tag *margin* with the new indentation. The initial margin level is 0. Changed values of the logical tag must be true values; false values other than AS_IS are not sufficient to change the margin.

pop_margin()

Restore the previous margin.

push_style(*styles)

Push any number of arbitrary style specifications. All styles are pushed onto the styles stack in order. A tuple representing the entire stack, including AS_IS values, is passed to the writer's new_styles() method.

$pop_style([n = 1])$

Pop the last n style specifications passed to push_style(). A tuple representing the revised stack, including AS_IS values, is passed to the writer's new_styles() method.

set_spacing(spacing)

Set the spacing style for the writer.

assert_line_data([flag = 1])

Inform the formatter that data has been added to the current paragraph out-of-band. This should be used when the writer has been manipulated directly. The optional *flag* argument can be set to false if the writer manipulations produced a hard line break at the end of the output.

12.1.2 Formatter Implementations

Two implementations of formatter objects are provided by this module. Most applications may use one of these classes without modification or subclassing.

class NullFormatter([writer])

A formatter which does nothing. If *writer* is omitted, a NullWriter instance is created. No methods of the writer are called by NullFormatter instances. Implementations should inherit from this class if implementing a writer interface but don't need to inherit any implementation.

class AbstractFormatter(writer)

The standard formatter. This implementation has demonstrated wide applicability to many writers, and may be used directly in most circumstances. It has been used to implement a full-featured World Wide Web browser.

12.1.3 The Writer Interface

Interfaces to create writers are dependent on the specific writer class being instantiated. The interfaces described below are the required interfaces which all writers must support once initialized. Note that while most applications can use the AbstractFormatter class as a formatter, the writer must typically be provided by the application.

flush()

Flush any buffered output or device control events.

new_alignment(align)

Set the alignment style. The *align* value can be any object, but by convention is a string or None, where None indicates that the writer's "preferred" alignment should be used. Conventional *align* values are 'left', 'center', 'right', and 'justify'.

new_font(font)

Set the font style. The value of *font* will be None, indicating that the device's default font should be used, or a tuple of the form (*size*, *italic*, *bold*, *teletype*). Size will be a string indicating the size of font that should be used; specific strings and their interpretation must be defined by the application. The *italic*, *bold*, and *teletype* values are Boolean values specifying which of those font attributes should be used.

new_margin(margin, level)

Set the margin level to the integer *level* and the logical tag to *margin*. Interpretation of the logical tag is at the writer's discretion; the only restriction on the value of the logical tag is that it not be a false value for non-zero values of *level*.

new_spacing(spacing)

Set the spacing style to spacing.

new_styles(styles)

Set additional styles. The *styles* value is a tuple of arbitrary values; the value AS_IS should be ignored. The *styles* tuple may be interpreted either as a set or as a stack depending on the requirements of the application and writer implementation.

send_line_break()

Break the current line.

send_paragraph(blankline)

Produce a paragraph separation of at least *blankline* blank lines, or the equivalent. The *blankline* value will be an integer. Note that the implementation will receive a call to <code>send_line_break()</code> before this call if a line break is needed; this method should not include ending the last line of the paragraph. It is only responsible for vertical spacing between paragraphs.

send_hor_rule(*args, **kw)

Display a horizontal rule on the output device. The arguments to this method are entirely application- and writer-specific, and should be interpreted with care. The method implementation may assume that a line break has already been issued via send_line_break().

send_flowing_data(data)

Output character data which may be word-wrapped and re-flowed as needed. Within any sequence of calls to this method, the writer may assume that spans of multiple whitespace characters have been collapsed to single space characters.

send_literal_data(data)

Output character data which has already been formatted for display. Generally, this should be interpreted to mean that line breaks indicated by newline characters should be preserved and no new line breaks should be introduced. The data may contain embedded newline and tab characters, unlike data provided to the send_formatted_data() interface.

send_label_data(data)

Set *data* to the left of the current left margin, if possible. The value of *data* is not restricted; treatment of non-string values is entirely application- and writer-dependent. This method will only be called at the beginning of a line.

12.1.4 Writer Implementations

Three implementations of the writer object interface are provided as examples by this module. Most applications will need to derive new writer classes from the NullWriter class.

class NullWriter()

Nature which only provides the interface definition; no ab02(be)(wr262(siztau)1(nln2(which)-268(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is)-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12is-316s(no)-267(an)12i

12.2 email — An email and MIME handling package

New in version 2.2.

The email package is a library for managing email messages, including MIME and other RFC 2822-based message documents. It subsumes most of the functionality in several older standard modules such as rfc822, mimetools, multifile, and other non-standard packages such as mimecntl. It is specifically not designed to do any sending of email messages to SMTP (RFC 2821) servers; that is the function of the smtplib module. The email package attempts to be as RFC-compliant as possible, supporting in addition to RFC 2822, such MIME-related RFCs as RFC 2045, RFC 2046, RFC 2047, and RFC 2231.

The primary distinguishing feature of the email package is that it splits the parsing and generating of email messages from the internal *object model* representation of email. Applications using the email package deal primarily with objects; you can add sub-objects to messages, remove sub-objects from messages, completely rearrange the contents, etc. There is a separate parser and a separate generator which handles the transformation from flat text to the object model, and then back to flat text again. There are also handy subclasses for some common MIME object types, and a few miscellaneous utilities that help with such common tasks as extracting and parsing message field values, creating RFC-compliant dates, etc.

The following sections describe the functionality of the email package. The ordering follows a progression that should be common in applications: an email message is read as flat text from a file or other source, the text is parsed to produce the object structure of the email message, this structure is manipulated, and finally rendered back into flat text.

It is perfectly feasible to create the object structure out of whole cloth — i.e. completely from scratch. From there, a similar progression can be taken as above.

Also included are detailed specifications of all the classes and modules that the email package provides, the exception classes you might encounter while using the email package, some auxiliary utilities, and a few examples. For users of the older mimelib package, or previous versions of the email package, a section on differences and porting is provided.

See Also:

Module smtplib (section 11.12): SMTP protocol client

12.2.1 Representing an email message

The central class in the email package is the Message class; it is the base class for the email object model. Message provides the core functionality for setting and querying header fields, and for accessing message bodies.

Conceptually, a Message object consists of *headers* and *payloads*. Headers are RFC 2822 style field names and values where the field name and value are separated by a colon. The colon is not part of either the field name or the field value.

Headers are stored and returned in case-preserving form but are matched case-insensitively. There may also be a single envelope header, also known as the *Unix-From* header or the From_ header. The payload is either a string in the case of simple message objects or a list of Message objects for MIME container documents (e.g. multipart/* and message/rfc822).

Message objects provide a mapping style interface for accessing the message headers, and an explicit interface for accessing both the headers and the payload. It provides convenience methods for generating a flat text representation of the message object tree, for accessing commonly used header parameters, and for recursively walking over the object tree.

Here are the methods of the Message class:

class Message()

The constructor takes no arguments.

as_string([unixfrom])

Return the entire message flatten as a string. When optional *unixfrom* is True, the envelope header is included in the returned string. *unixfrom* defaults to False.

Note that this method is provided as a convenience and may not always format the message the way you want. For example, by default it mangles lines that begin with From . For more flexibility, instantiate a Generator instance and use its flatten() method directly. For example:

```
from cStringIO import StringIO
from email.Generator import Generator
fp = StringIO()
g = Generator(fp, mangle_from_=False, maxheaderlen=60)
g.flatten(msg)
text = fp.getvalue()
```

__str__()

Equivalent to as_string(unixfrom=True).

is_multipart()

Return True if the message's payload is a list of sub-Message objects, otherwise return False. When is_multipart() returns False, the payload should be a string object.

set_unixfrom(unixfrom)

Set the message's envelope header to *unixfrom*, which should be a string.

get_unixfrom()

Return the message's envelope header. Defaults to None if the envelope header was never set.

attach(payload)

Add the given *payload* to the current payload, which must be None or a list of Message objects before the call. After the call, the payload will always be a list of Message objects. If you want to set the payload to a scalar object (e.g. a string), use set_payload() instead.

$get_payload([i[, decode]])$

Return a reference the current payload, which will be a list of Message objects when is_multipart() is True, or a string when is_multipart() is False. If the payload is a list and you mutate the list object, you modify the message's payload in place.

With optional argument i, $get_payload()$ will return the i-th element of the payload, counting from zero, if $is_multipart()$ is True. An IndexError will be raised if i is less than 0 or greater than or equal to the number of items in the payload. If the payload is a string (i.e. $is_multipart()$ is False) and i is given, a TypeError is raised.

Optional *decode* is a flag indicating whether the payload should be decoded or not, according to the Content-Transfer-Encoding: header. When True and the message is not a multipart, the payload will be decoded if this header's value is 'quoted-printable' or 'base64'. If some other encoding is used, or Content-Transfer-Encoding: header is missing, or if the payload has bogus base64 data, the payload is returned as-is (undecoded). If the message is a multipart and the *decode* flag is True, then None is returned. The default for *decode* is False.

set_payload(payload[, charset])

Set the entire message object's payload to *payload*. It is the client's responsibility to ensure the payload invariants. Optional *charset* sets the message's default character set; see set_charset() for details.

Changed in version 2.2.2: *charset* argument added.

set_charset(charset)

Set the character set of the payload to *charset*, which can either be a Charset instance (see email.Charset), a string naming a character set, or None. If it is a string, it will be converted to a Charset instance. If *charset* is None, the charset parameter will be removed from the Content-Type: header. Anything else will generate a TypeError.

The message will be assumed to be of type text/* encoded with charset.input_charset. It will be converted to charset.output_charset and encoded properly, if needed, when generating the plain text representation of the message. MIME headers (MIME-Version:, Content-Type:, Content-Transfer-Encoding:) will be added as needed.

New in version 2.2.2.

get_charset()

Return the Charset instance associated with the message's payload. New in version 2.2.2.

The following methods implement a mapping-like interface for accessing the message's RFC 2822 headers. Note that there are some semantic differences between these methods and a normal mapping (i.e. dictionary) interface. For example, in a dictionary there are no duplicate keys, but here there may be duplicate message headers. Also, in dictionaries there is no guaranteed order to the keys returned by keys(), but in a Message object, headers are always returned in the order they appeared in the original message, or were added to the message later. Any header deleted and then re-added are always appended to the end of the header list.

These semantic differences are intentional and are biased toward maximal convenience.

Note that in all cases, any envelope header present in the message is not included in the mapping interface.

```
__len__()
```

Return the total number of headers, including duplicates.

```
__contains__(name)
```

Return true if the message object has a field named *name*. Matching is done case-insensitively and *name* should not include the trailing colon. Used for the in operator, e.g.:

```
if 'message-id' in myMessage:
    print 'Message-ID:', myMessage['message-id']
```

```
__getitem__(name)
```

Return the value of the named header field. *name* should not include the colon field separator. If the header is missing, None is returned; a KeyError is never raised.

Note that if the named field appears more than once in the message's headers, exactly which of those field values will be returned is undefined. Use the get_all() method to get the values of all the extant named headers.

```
__setitem__(name, val)
```

Add a header to the message with field name *name* and value *val*. The field is appended to the end of the message's existing fields.

Note that this does *not* overwrite or delete any existing header with the same name. If you want to ensure that the new header is the only one present in the message with field name *name*, delete the field first, e.g.:

```
del msg['subject']
msg['subject'] = 'Python roolz!'
```

```
\_\_\mathtt{delitem}\_\_(\mathit{name}\,)
```

Delete all occurrences of the field with name *name* from the message's headers. No exception is raised if the named field isn't present in the headers.

```
has_key(name)
```

Return true if the message contains a header field named *name*, otherwise return false.

keys()

Return a list of all the message's header field names.

values()

Return a list of all the message's field values.

items()

Return a list of 2-tuples containing all the message's field headers and values.

```
get(name[, failobj])
```

Return the value of the named header field. This is identical to __getitem__() except that optional *failobj* is returned if the named header is missing (defaults to None).

Here are some additional useful methods:

```
get_all(name[, failobj])
```

Return a list of all the values for the field named *name*. If there are no such named headers in the message, *failobj* is returned (defaults to None).

add_header(_name, _value, **_params)

Extended header setting. This method is similar to __setitem__() except that additional header parameters can be provided as keyword arguments. _name is the header field to add and _value is the primary value for the header.

For each item in the keyword argument dictionary *_params*, the key is taken as the parameter name, with underscores converted to dashes (since dashes are illegal in Python identifiers). Normally, the parameter will be added as key="value" unless the value is None, in which case only the key will be added.

Here's an example:

```
msg.add_header('Content-Disposition', 'attachment', filename='bud.gif')
```

This will add a header that looks like

```
Content-Disposition: attachment; filename="bud.gif"
```

replace_header(_name, _value)

Replace a header. Replace the first header found in the message that matches *_name*, retaining header order and field name case. If no matching header was found, a KeyError is raised.

New in version 2.2.2.

get_content_type()

Return the message's content type. The returned string is coerced to lower case of the form main-type/subtype. If there was no Content-Type: header in the message the default type as given by get_default_type() will be returned. Since according to RFC 2045, messages always have a default type, get_content_type() will always return a value.

RFC 2045 defines a message's default type to be text/plain unless it appears inside a multipart/digest container, in which case it would be message/rfc822. If the Content-Type: header has an invalid type specification, RFC 2045 mandates that the default type be text/plain.

New in version 2.2.2.

get_content_maintype()

Return the message's main content type. This is the maintype part of the string returned by $get_content_type()$.

New in version 2.2.2.

get_content_subtype()

Return the message's sub-content type. This is the subtype part of the string returned by get_content_type().

New in version 2.2.2.

get_default_type()

Return the default content type. Most messages have a default content type of text/plain, except for messages that are subparts of multipart/digest containers. Such subparts have a default content type of message/rfc822.

New in version 2.2.2.

set_default_type(ctype)

Set the default content type. *ctype* should either be text/plain or message/rfc822, although this is not enforced. The default content type is not stored in the Content-Type: header.

New in version 2.2.2.

get_params([failobj[, header[, unquote]]])

Return the message's Content-Type: parameters, as a list. The elements of the returned list are 2-tuples of key/value pairs, as split on the '=' sign. The left hand side of the '=' is the key, while the right hand side is the value. If there is no '=' sign in the parameter the value is the empty string, otherwise the value is as described in get_param() and is unquoted if optional *unquote* is True (the default).

Optional *failobj* is the object to return if there is no Content-Type: header. Optional *header* is the header to search instead of Content-Type:.

Changed in version 2.2.2: unquote argument added.

get_param(param[, failobj[, header[, unquote]]])

Return the value of the Content-Type: header's parameter *param* as a string. If the message has no Content-Type: header or if there is no such parameter, then *failobj* is returned (defaults to None).

Optional *header* if given, specifies the message header to use instead of Content-Type:.

Parameter keys are always compared case insensitively. The return value can either be a string, or a 3-tuple if the parameter was RFC 2231 encoded. When it's a 3-tuple, the elements of the value are of the form (CHARSET, LANGUAGE, VALUE). Note that both CHARSET and LANGUAGE can be None, in which case you should consider VALUE to be encoded in the us-ascii charset. You can usually ignore LANGUAGE.

If your application doesn't care whether the parameter was encoded as in RFC 2231, you can collapse the parameter value by calling email.Utils.collapse_rfc2231_value(), passing in the return value from get_param(). This will return a suitably decoded Unicode string who the value is a tuple, or the original string unquoted if it isn't. For example:

```
rawparam = msg.get_param('foo')
param = email.Utils.collapse_rfc2231_value(rawparam)
```

In any case, the parameter value (either the returned string, or the VALUE item in the 3-tuple) is always unquoted, unless *unquote* is set to False.

Changed in version 2.2.2: *unquote* argument added, and 3-tuple return value possible.

set_param(param, value[, header[, requote[, charset[, language]]]]))

Set a parameter in the Content-Type: header. If the parameter already exists in the header, its value will be replaced with *value*. If the Content-Type: header as not yet been defined for this message, it will be set to text/plain and the new parameter value will be appended as per RFC 2045.

Optional *header* specifies an alternative header to Content-Type:, and all parameters will be quoted as necessary unless optional *requote* is False (the default is True).

If optional *charset* is specified, the parameter will be encoded according to RFC 2231. Optional *language* specifies the RFC 2231 language, defaulting to the empty string. Both *charset* and *language* should be strings.

New in version 2.2.2.

del_param(param[, header[, requote]])

Remove the given parameter completely from the Content-Type: header. The header will be re-written in place without the parameter or its value. All values will be quoted as necessary unless *requote* is False (the default is True). Optional *header* specifies an alternative to Content-Type:.

New in version 2.2.2.

$set_type(type[, header][, requote])$

Set the main type and subtype for the Content-Type: header. *type* must be a string in the form main-type/subtype, otherwise a ValueError is raised.

This method replaces the Content-Type: header, keeping all the parameters in place. If *requote* is False, this leaves the existing header's quoting as is, otherwise the parameters will be quoted (the default).

An alternative header can be specified in the *header* argument. When the Content-Type: header is set a MIME-Version: header is also added.

New in version 2.2.2.

get_filename([failobj])

Return the value of the filename parameter of the Content-Disposition: header of the message, or *failobj* if either the header is missing, or has no filename parameter. The returned string will always be unquoted as per Utils.unquote().

$\verb"get_boundary"(\left[\mathit{failobj}\right])$

Return the value of the boundary parameter of the Content-Type: header of the message, or *failobj* if either the header is missing, or has no boundary parameter. The returned string will always be unquoted as per Utils.unquote().

set_boundary(boundary)

Set the boundary parameter of the Content-Type: header to *boundary*. set_boundary() will always quote *boundary* if necessary. A HeaderParseError is raised if the message object has no Content-Type: header.

Note that using this method is subtly different than deleting the old Content-Type: header and adding a new one with the new boundary via add_header(), because set_boundary() preserves the order of the Content-Type: header in the list of headers. However, it does *not* preserve any continuation lines which may have been present in the original Content-Type: header.

get_content_charset([failobj])

Return the charset parameter of the Content-Type: header, coerced to lower case. If there is no Content-Type: header, or if that header has no charset parameter, *failobj* is returned.

Note that this method differs from get_charset() which returns the Charset instance for the default encoding of the message body.

New in version 2.2.2.

$get_charsets([failobj])$

Return a list containing the character set names in the message. If the message is a multipart, then the list will contain one element for each subpart in the payload, otherwise, it will be a list of length 1.

Each item in the list will be a string which is the value of the charset parameter in the Content-Type: header for the represented subpart. However, if the subpart has no Content-Type: header, no charset parameter, or is not of the text main MIME type, then that item in the returned list will be *failobj*.

walk()

The walk() method is an all-purpose generator which can be used to iterate over all the parts and subparts of a message object tree, in depth-first traversal order. You will typically use walk() as the iterator in a for loop; each iteration returns the next subpart.

Here's an example that prints the MIME type of every part of a multipart message structure:

```
>>> for part in msg.walk():
... print part.get_content_type()
multipart/report
text/plain
message/delivery-status
text/plain
text/plain
message/rfc822
```

Message objects can also optionally contain two instance attributes, which can be used when generating the plain text of a MIME message.

preamble

The format of a MIME document allows for some text between the blank line following the headers, and the first multipart boundary string. Normally, this text is never visible in a MIME-aware mail reader because it falls outside the standard MIME armor. However, when viewing the raw text of the message, or when viewing the message in a non-MIME aware reader, this text can become visible.

The *preamble* attribute contains this leading extra-armor text for MIME documents. When the Parser discovers some text after the headers but before the first boundary string, it assigns this text to the message's *preamble* attribute. When the Generator is writing out the plain text representation of a MIME message, and it finds the message has a *preamble* attribute, it will write this text in the area between the headers and the first boundary. See email.Parser and email.Generator for details.

Note that if the message object has no preamble, the *preamble* attribute will be None.

epilogue

The *epilogue* attribute acts the same way as the *preamble* attribute, except that it contains text that appears between the last boundary and the end of the message.

One note: when generating the flat text for a multipart message that has no *epilogue* (using the standard Generator class), no newline is added after the closing boundary line. If the message object has an *epilogue* and its value does not start with a newline, a newline is printed after the closing boundary. This

seems a little clumsy, but it makes the most practical sense. The upshot is that if you want to ensure that a newline get printed after your closing multipart boundary, set the *epilogue* to the empty string.

defects

The *defects* attribute contains a list of all the problems found when parsing this message. See email.Errors for a detailed description of the possible parsing defects.

New in version 2.4.

Deprecated methods

Changed in version 2.4: The add_payload() method was removed; use the attach() method instead.

The following methods are deprecated. They are documented here for completeness.

get_type([failobj])

Return the message's content type, as a string of the form maintype/subtype as taken from the Content-Type: header. The returned string is coerced to lowercase.

If there is no Content-Type: header in the message, failobj is returned (defaults to None).

Deprecated since release 2.2.2. Use the get_content_type() method instead.

get_main_type([failobj])

Return the message's *main* content type. This essentially returns the *maintype* part of the string returned by get_type(), with the same semantics for *failobj*.

Deprecated since release 2.2.2. Use the get_content_maintype() method instead.

get_subtype([failobj])

Return the message's sub-content type. This essentially returns the *subtype* part of the string returned by get_type(), with the same semantics for *failobj*.

Deprecated since release 2.2.2. Use the get_content_subtype() method instead.

12.2.2 Parsing email messages

Message object structures can be created in one of two ways: they can be created from whole cloth by instantiating Message objects and stringing them together via attach() and set_payload() calls, or they can be created by parsing a flat text representation of the email message.

The email package provides a standard parser that understands most email document structures, including MIME documents. You can pass the parser a string or a file object, and the parser will return to you the root Message instance of the object structure. For simple, non-MIME messages the payload of this root object will likely be a string containing the text of the message. For MIME messages, the root object will return True from its is_multipart() method, and the subparts can be accessed via the get_payload() and walk() methods.

There are actually two parser interfaces available for use, the classic Parser API and the incremental FeedParser API. The classic Parser API is fine if you have the entire text of the message in memory as a string, or if the entire message lives in a file on the file system. FeedParser is more appropriate for when you're reading the message from a stream which might block waiting for more input (e.g. reading an email message from a socket). The FeedParser can consume and parse the message incrementally, and only returns the root object when you close the parser.

Note that the parser can be extended in limited ways, and of course you can implement your own parser completely from scratch. There is no magical connection between the <code>email</code> package's bundled parser and the <code>Message</code> class, so your custom parser can create message object trees any way it finds necessary.

FeedParser API

New in version 2.4.

¹As of email package version 3.0, introduced in Python 2.4, the classic Parser was re-implemented in terms of the FeedParser, so the semantics and results are identical between the two parsers.

The FeedParser provides an API that is conducive to incremental parsing of email messages, such as would be necessary when reading the text of an email message from a source that can block (e.g. a socket). The FeedParser can of course be used to parse an email message fully contained in a string or a file, but the classic Parser API may be more convenient for such use cases. The semantics and results of the two parser APIs are identical.

The FeedParser's API is simple; you create an instance, feed it a bunch of text until there's no more to feed it, then close the parser to retrieve the root message object. The FeedParser is extremely accurate when parsing standards-compliant messages, and it does a very good job of parsing non-compliant messages, providing information about how a message was deemed broken. It will populate a message object's *defects* attribute with a list of any problems it found in a message. See the email. Errors module for the list of defects that it can find.

Here is the API for the FeedParser:

class FeedParser([_factory])

Create a FeedParser instance. Optional _factory is a no-argument callable that will be called whenever a new message object is needed. It defaults to the email.Message.Message class.

feed(data)

Feed the FeedParser some more data. *data* should be a string containing one or more lines. The lines can be partial and the FeedParser will stitch such partial lines together properly. The lines in the string can have any of the common three line endings, carriage return, newline, or carriage return and newline (they can even be mixed).

close()

Closing a FeedParser completes the parsing of all previously fed data, and returns the root message object. It is undefined what happens if you feed more data to a closed FeedParser.

Parser class API

The Parser provides an API that can be used to parse a message when the complete contents of the message are available in a string or file. The email.Parser module also provides a second class, called HeaderParser which can be used if you're only interested in the headers of the message. HeaderParser can be much faster in these situations, since it does not attempt to parse the message body, instead setting the payload to the raw body as a string. HeaderParser has the same API as the Parser class.

class Parser([_class[, strict]])

The constructor for the Parser class takes an optional argument _class. This must be a callable factory (such as a function or a class), and it is used whenever a sub-message object needs to be created. It defaults to Message (see email.Message). The factory will be called without arguments.

The optional *strict* flag is ignored. **Deprecated since release 2.4.** Because the Parser class is a backward compatible API wrapper around the new-in-Python 2.4 FeedParser, *all* parsing is effectively non-strict. You should simply stop passing a *strict* flag to the Parser constructor.

Changed in version 2.2.2: The *strict* flag was added. Changed in version 2.4: The *strict* flag was depre-

The other public Parser methods are:

parse(fp[, headersonly])

Read all the data from the file-like object fp, parse the resulting text, and return the root message object. fp must support both the readline() and the read() methods on file-like objects.

The text contained in *fp* must be formatted as a block of RFC 2822 style headers and header continuation lines, optionally preceded by a envelope header. The header block is terminated either by the end of the data or by a blank line. Following the header block is the body of the message (which may contain MIME-encoded subparts).

Optional *headersonly* is as with the parse() method.

Changed in version 2.2.2: The headersonly flag was added.

parsestr(text[, headersonly])

Similar to the parse() method, except it takes a string object instead of a file-like object. Calling

this method on a string is exactly equivalent to wrapping *text* in a StringIO instance first and calling parse().

Optional *headersonly* is a flag specifying whether to stop parsing after reading the headers or not. The default is False, meaning it parses the entire contents of the file.

Changed in version 2.2.2: The *headersonly* flag was added.

Since creating a message object structure from a string or a file object is such a common task, two functions are provided as a convenience. They are available in the top-level email package namespace.

```
message_from_string(s[, _class[, strict]])
```

Return a message object structure from a string. This is exactly equivalent to Parser().parsestr(s). Optional _class and strict are interpreted as with the Parser class constructor.

Changed in version 2.2.2: The strict flag was added.

```
message\_from\_file(fp[, \_class[, strict]])
```

Return a message object structure tree from an open file object. This is exactly equivalent to Parser(). Optional $_class$ and strict are interpreted as with the Parser class constructor.

Changed in version 2.2.2: The strict flag was added.

Here's an example of how you might use this at an interactive Python prompt:

```
>>> import email
>>> msg = email.message_from_string(myString)
```

Additional notes

Here are some notes on the parsing semantics:

- Most non-multipart type messages are parsed as a single message object with a string payload. These objects will return False for is_multipart(). Their get_payload() method will return a string object.
- All multipart type messages will be parsed as a container message object with a list of sub-message objects for their payload. The outer container message will return True for is_multipart() and their get_payload() method will return the list of Message subparts.
- Most messages with a content type of message/* (e.g. message/delivery-status and message/rfc822J/F30 9.963 Tf 68.91-@

Here are the public methods of the Generator class:

```
class Generator(outfp[, mangle_from_[, maxheaderlen]])
```

The constructor for the Generator class takes a file-like object called outfp for an argument. outfp must support the write() method and be usable as the output file in a Python extended print statement.

Optional <code>mangle_from_</code> is a flag that, when <code>True</code>, puts a '>' character in front of any line in the body that starts exactly as 'From', i.e. From followed by a space at the beginning of the line. This is the only guaranteed portable way to avoid having such lines be mistaken for a Unix mailbox format envelope header separator (see <code>WHY THE CONTENT-LENGTH FORMAT IS BAD</code> for details). <code>mangle_from_</code> defaults to <code>True</code>, but you might want to set this to <code>False</code> if you are not writing Unix mailbox format files.

Optional *maxheaderlen* specifies the longest length for a non-continued header. When a header line is longer than *maxheaderlen* (in characters, with tabs expanded to 8 spaces), the header will be split as defined in the email. Header class. Set to zero to disable header wrapping. The default is 78, as recommended (but not required) by RFC 2822.

The other public Generator methods are:

flatten(msg[, unixfrom])

Print the textual representation of the message object structure rooted at *msg* to the output file specified when the Generator instance was created. Subparts are visited depth-first and the resulting text will be properly MIME encoded.

Optional *unixfrom* is a flag that forces the printing of the envelope header delimiter before the first RFC 2822 header of the root message object. If the root object has no envelope header, a standard one is crafted. By default, this is set to False to inhibit the printing of the envelope delimiter.

Note that for subparts, no envelope header is ever printed.

New in version 2.2.2.

clone(fp)

Return an independent clone of this Generator instance with the exact same options.

New in version 2.2.2.

write(s)

Write the string *s* to the underlying file object, i.e. *outfp* passed to Generator's constructor. This provides just enough file-like API for Generator instances to be used in extended print statements.

As a convenience, see the methods Message.as_string() and str(aMessage), a.k.a. Message.__str__(), which simplify the generation of a formatted string representation of a message object. For more detail, see email.Message.

The email.Generator module also provides a derived class, called DecodedGenerator which is like the Generator base class, except that non-text parts are substituted with a format string representing the part.

```
class DecodedGenerator(outfp[, mangle_from_[, maxheaderlen[, fmt]]])
```

This class, derived from Generator walks through all the subparts of a message. If the subpart is of main type text, then it prints the decoded payload of the subpart. Optional *_mangle_from_* and *maxheaderlen* are as with the Generator base class.

If the subpart is not of main type text, optional *fmt* is a format string that is used instead of the message payload. *fmt* is expanded with the following keywords, '% (keyword) s' format:

- •type Full MIME type of the non-text part
- •maintype Main MIME type of the non-text part
- •subtype Sub-MIME type of the non-text part
- •filename Filename of the non-text part
- •description Description associated with the non-text part
- •encoding Content transfer encoding of the non-text part

The default value for fmt is None, meaning

```
[\texttt{Non-text (\%(type)s) part of message omitted, filename \%(filename)s}]
```

New in version 2.2.2.

Deprecated methods

The following methods are deprecated in email version 2. They are documented here for completeness.

```
\_\_call\_\_(msg[, unixfrom])
```

This method is identical to the flatten() method.

Deprecated since release 2.2.2. Use the flatten() method instead.

12.2.4 Creating email and MIME objects from scratch

Ordinarily, you get a message object structure by passing a file or some text to a parser, which parses the text and returns the root message object. However you can also build a complete message structure from scratch, or even individual Message objects by hand. In fact, you can also take an existing structure and add new Message objects, move them around, etc. This makes a very convenient interface for slicing-and-dicing MIME messages.

You can create a new object structure by creating Message instances, adding attachments and all the appropriate headers manually. For MIME messages though, the email package provides some convenient subclasses to make things easier. Each of these classes should be imported from a module with the same name as the class, from within the email package. E.g.:

```
import email.MIMEImage.MIMEImage
```

or

```
from email.MIMEText import MIMEText
```

Here are the classes:

```
class MIMEBase ( _maintype, _subtype, **_params )
```

This is the base class for all the MIME-specific subclasses of Message. Ordinarily you won't create instances specifically of MIMEBase, although you could. MIMEBase is provided primarily as a convenient base class for more specific MIME-aware subclasses.

_maintype is the Content-Type: major type (e.g. text or image), and _subtype is the Content-Type: minor type (e.g. plain or gif). _params is a parameter key/value dictionary and is passed directly to Message.add_header().

The MIMEBase class always adds a Content-Type: header (based on *_maintype*, *_subtype*, and *_params*), and a MIME-Version: header (always set to 1.0).

class MIMENonMultipart()

A subclass of MIMEBase, this is an intermediate base class for MIME messages that are not multipart. The primary purpose of this class is to prevent the use of the attach() method, which only makes sense for multipart messages. If attach() is called, a MultipartConversionError exception is raised.

New in version 2.2.2.

```
class MIMEMultipart([subtype[, boundary[, _subparts[, _params]]]]))
```

A subclass of MIMEBase, this is an intermediate base class for MIME messages that are multipart. Optional _subtype defaults to mixed, but can be used to specify the subtype of the message. A Content-Type: header of multipart/_subtype will be added to the message object. A MIME-Version: header will also be added.

Optional *boundary* is the multipart boundary string. When None (the default), the boundary is calculated when needed.

_subparts is a sequence of initial subparts for the payload. It must be possible to convert this sequence to a list. You can always attach new subparts to the message by using the Message.attach() method.

Additional parameters for the Content-Type: header are taken from the keyword arguments, or passed into the *_params* argument, which is a keyword dictionary.

New in version 2.2.2.

class MIMEAudio (_audiodata[, _subtype[, _encoder[, **_params]]]))

A subclass of MIMENonMultipart, the MIMEAudio class is used to create MIME message objects of major type audio. _audiodata is a string containing the raw audio data. If this data can be decoded by the standard Python module sndhdr, then the subtype will be automatically included in the Content-Type: header. Otherwise you can explicitly specify the audio subtype via the _subtype parameter. If the minor type could not be guessed and _subtype was not given, then TypeError is raised.

Optional _encoder is a callable (i.e. function) which will perform the actual encoding of the audio data for transport. This callable takes one argument, which is the MIMEAudio instance. It should use get_payload() and set_payload() to change the payload to encoded form. It should also add any Content-Transfer-Encoding: or other headers to the message object as necessary. The default encoding is base64. See the email.Encoders module for a list of the built-in encoders.

_params are passed straight through to the base class constructor.

class MIMEImage (_imagedata[, _subtype[, _encoder[, **_params]]])

A subclass of MIMENonMultipart, the MIMEImage class is used to create MIME message objects of major type image. _imagedata is a string containing the raw image data. If this data can be decoded by the standard Python module imghdr, then the subtype will be automatically included in the Content-Type: header. Otherwise you can explicitly specify the image subtype via the _subtype parameter. If the minor type could not be guessed and _subtype was not given, then TypeError is raised.

Optional _encoder is a callable (i.e. function) which will perform the actual encoding of the image data for transport. This callable takes one argument, which is the MIMEImage instance. It should use get_payload() and set_payload() to change the payload to encoded form. It should also add any Content-Transfer-Encoding: or other headers to the message object as necessary. The default encoding is base64. See the email.Encoders module for a list of the built-in encoders.

_params are passed straight through to the MIMEBase constructor.

class MIMEMessage(_msg[, _subtype])

A subclass of MIMENonMultipart, the MIMEMessage class is used to create MIME objects of main type message. _msg is used as the payload, and must be an instance of class Message (or a subclass thereof), otherwise a TypeError is raised.

Optional _subtype sets the subtype of the message; it defaults to rfc822.

class MIMEText (_text[, _subtype[, _charset]])

A subclass of MIMENonMultipart, the MIMEText class is used to create MIME objects of major type text. _text is the string for the payload. _subtype is the minor type and defaults to plain. _charset is the character set of the text and is passed as a parameter to the MIMENonMultipart constructor; it defaults to us-ascii. No guessing or encoding is performed on the text data.

Changed in version 2.4: The previously deprecated _encoding

```
>>> from email.Message import Message
>>> from email.Header import Header
>>> msg = Message()
>>> h = Header('p\xf6stal', 'iso-8859-1')
>>> msg['Subject'] = h
>>> print msg.as_string()
Subject: =?iso-8859-1?q?p=F6stal?=
```

Notice here how we wanted the Subject: field to contain a non-ASCII character? We did this by creating a Header instance and passing in the character set that the byte string was encoded in. When the subsequent Message instance was flattened, the Subject: field was properly RFC 2047 encoded. MIME-aware mail readers would show this header using the embedded ISO-8859-1 character.

New in version 2.2.2.

Here is the Header class description:

```
class Header ([s[, charset[, maxlinelen[, header_name[, continuation_ws[, errors]]]]]]]) Create a MIME-compliant header that can contain strings in different character sets.
```

Optional s is the initial header value. If None (the default), the initial header value is not set. You can later append to the header with append () method calls. s may be a byte string or a Unicode string, but see the append () documentation for semantics.

Optional *charset* serves two purposes: it has the same meaning as the *charset* argument to the append() method. It also sets the default character set for all subsequent append() calls that omit the *charset* argument. If *charset* is not provided in the constructor (the default), the us-ascii character set is used both as s's initial charset and as the default for subsequent append() calls.

The maximum line length can be specified explicit via *maxlinelen*. For splitting the first line to a shorter value (to account for the field header which isn't included in *s*, e.g. Subject:) pass in the name of the field in *header_name*. The default *maxlinelen* is 76, and the default value for *header_name* is None, meaning it is not taken into account for the first line of a long, split header.

Optional *continuation_ws* must be RFC 2822-compliant folding whitespace, and is usually either a space or a hard tab character. This character will be prepended to continuation lines.

Optional errors is passed straight through to the append() method.

```
append(s[, charset[, errors]])
```

Append the string *s* to the MIME header.

Optional *charset*, if given, should be a Charset instance (see email.Charset) or the name of a character set, which will be converted to a Charset instance. A value of None (the default) means that the *charset* given in the constructor is used.

s may be a byte string or a Unicode string. If it is a byte string (i.e. isinstance(s, str) is true), then *charset* is the encoding of that byte string, and a UnicodeError will be raised if the string cannot be decoded with that character set.

If *s* is a Unicode string, then *charset* is a hint specifying the character set of the characters in the string. In this case, when producing an RFC 2822-compliant header using RFC 2047 rules, the Unicode string will be encoded using the following charsets in order: us-ascii, the *charset* hint, utf-8. The first character set to not provoke a UnicodeError is used.

Optional errors is passed through to any unicode() or ustr.encode() call, and defaults to "strict".

```
encode([splitchars])
```

Encode a message header into an RFC-compliant format, possibly wrapping long lines and encapsulating non-ASCII parts in base64 or quoted-printable encodings. Optional *splitchars* is a string containing characters to split long ASCII lines on, in rough support of RFC 2822's *highest level syntactic breaks*. This doesn't affect RFC 2047 encoded lines.

The Header class also provides a number of methods to support standard operators and built-in functions.

```
__str__()
A synonym for Header.encode(). Useful for str(aHeader).
__unicode__()
A helper for the built-in unicode() function. Returns the header as a Unicode string.
__eq__(other)
This method allows you to compare two Header instances for equality.
__ne__(other)
```

The email. Header module also provides the following convenient functions.

This method allows you to compare two Header instances for inequality.

```
decode_header(header)
```

Decode a message header value without converting the character set. The header value is in header.

This function returns a list of (decoded_string, charset) pairs containing each of the decoded parts of the header. *charset* is None for non-encoded parts of the header, otherwise a lower case string containing the name of the character set specified in the encoded string.

Here's an example:

```
>>> from email.Header import decode_header
>>> decode_header('=?iso-8859-1?q?p=F6stal?=')
[('p\xf6stal', 'iso-8859-1')]
```

```
make_header(decoded_seq[, maxlinelen[, header_name[, continuation_ws]]])
```

Create a Header instance from a sequence of pairs as returned by decode_header().

decode_header() takes a header value string and returns a sequence of pairs of the format (decoded_string, charset) where *charset* is the name of the character set.

This function takes one of those sequence of pairs and returns a Header instance. Optional *maxlinelen*, *header_name*, and *continuation_ws* are as in the Header constructor.

12.2.6 Representing character sets

This module provides a class Charset for representing character sets and character set conversions in email messages, as well as a character set registry and several convenience methods for manipulating this registry. Instances of Charset are used in several other modules within the email package.

New in version 2.2.2.

```
class Charset ( [input_charset ])
```

Map character sets to their email properties.

This class provides information about the requirements imposed on email for a specific character set. It also provides convenience routines for converting between character sets, given the availability of the applicable codecs. Given a character set, it will do its best to provide information on how to use that character set in an email message in an RFC-compliant way.

Certain character sets must be encoded with quoted-printable or base64 when used in email headers or bodies. Certain character sets must be converted outright, and are not allowed in email.

Optional *input_charset* is as described below; it is always coerced to lower case. After being alias normalized it is also used as a lookup into the registry of character sets to find out the header encoding, body encoding, and output conversion codec to be used for the character set. For example, if *input_charset* is iso-8859-1, then headers and bodies will be encoded using quoted-printable and no output conversion codec is necessary. If *input_charset* is euc-jp, then headers will be encoded with base64, bodies will not be encoded, but output text will be converted from the euc-jp character set to the iso-2022-jp character set.

Charset instances have the following data attributes:

input_charset

The initial character set specified. Common aliases are converted to their *official* email names (e.g. latin_1 is converted to iso-8859-1). Defaults to 7-bit us-ascii.

header_encoding

If the character set must be encoded before it can be used in an email header, this attribute will be set to Charset.QP (for quoted-printable), Charset.BASE64 (for base64 encoding), or Charset.SHORTEST for the shortest of QP or BASE64 encoding. Otherwise, it will be None.

body_encoding

Same as *header_encoding*, but describes the encoding for the mail message's body, which indeed may be different than the header encoding. Charset.SHORTEST is not allowed for *body_encoding*.

output_charset

Some character sets must be converted before they can be used in email headers or bodies. If the *in-put_charset* is one of them, this attribute will contain the name of the character set output will be converted to. Otherwise, it will be None.

input_codec

The name of the Python codec used to convert the *input_charset* to Unicode. If no conversion codec is necessary, this attribute will be None.

output_codec

The name of the Python codec used to convert Unicode to the *output_charset*. If no conversion codec is necessary, this attribute will have the same value as the *input_codec*.

Charset instances also have the following methods:

get_body_encoding()

Return the content transfer encoding used for body encoding.

This is either the string 'quoted-printable' or 'base64' depending on the encoding used, or it is a function, in which case you should call the function with a single argument, the Message object being encoded. The function should then set the Content-Transfer-Encoding: header itself to whatever is appropriate.

Returns the string 'quoted-printable' if $body_encoding$ is QP, returns the string 'base64' if $body_encoding$ is BASE64, and returns the string '7bit' otherwise.

convert(s)

Convert the string *s* from the *input_codec* to the *output_codec*.

to_splittable(s)

Convert a possibly multibyte string to a safely splittable format. s is the string to split.

Uses the *input_codec* to try and convert the string to Unicode, so it can be safely split on character boundaries (even for multibyte characters).

Returns the string as-is if it isn't known how to convert s to Unicode with the *input_charset*.

Characters that could not be converted to Unicode will be replaced with the Unicode replacement character 'U+FFFD'.

from_splittable(ustr[, to_output])

Convert a splittable string back into an encoded string. ustr is a Unicode string to "unsplit".

This method uses the proper codec to try and convert the string from Unicode back into an encoded format. Return the string as-is if it is not Unicode, or if it could not be converted from Unicode.

Characters that could not be converted from Unicode will be replaced with an appropriate character (usually '?').

If to_output is True (the default), uses $output_codec$ to convert to an encoded format. If to_output is False, it uses $input_codec$.

get_output_charset()

Return the output character set.

This is the *output_charset* attribute if that is not None, otherwise it is *input_charset*.

encoded header len()

Return the length of the encoded header string, properly calculating for quoted-printable or base64 encoding.

header_encode(s[, convert])

Header-encode the string s.

If *convert* is True, the string will be converted from the input charset to the output charset automatically. This is not useful for multibyte character sets, which have line length issues (multibyte characters must be split on a character, not a byte boundary); use the higher-level Header class to deal with these issues (see email.Header). *convert* defaults to False.

The type of encoding (base64 or quoted-printable) will be based on the *header_encoding* attribute.

$body_encode(s[, convert])$

Body-encode the string s.

If *convert* is True (the default), the string will be converted from the input charset to output charset automatically. Unlike header_encode(), there are no issues with byte boundaries and multibyte charsets in email bodies, so this is usually pretty safe.

The type of encoding (base64 or quoted-printable) will be based on the *body_encoding* attribute.

The Charset class also provides a number of methods to support standard operations and built-in functions.

```
__str__()
    Returns input_charset as a string coerced to lower case. __repr__() is an alias for __str__().
__eq__(other)
    This method allows you to compare two Charset instances for equality.
__ne__(other)
```

This method allows you to compare two Charset instances for inequality.

The email. Charset module also provides the following functions for adding new entries to the global character set, alias, and codec registries:

```
\verb|add_charset|(charset[, header\_enc[, body\_enc[, output\_charset]]])|
```

Add character properties to the global registry.

charset is the input character set, and must be the canonical name of a character set.

Optional <code>header_enc</code> and <code>body_enc</code> is either <code>Charset.QP</code> for quoted-printable, <code>Charset.BASE64</code> for base64 encoding, <code>Charset.SHORTEST</code> for the shortest of quoted-printable or base64 encoding, or <code>None</code> for no encoding. <code>SHORTEST</code> is only valid for <code>header_enc</code>. The default is <code>None</code> for no encoding.

Optional *output_charset* is the character set that the output should be in. Conversions will proceed from input charset, to Unicode, to the output charset when the method Charset.convert() is called. The default is to output in the same character set as the input.

Both *input_charset* and *output_charset* must have Unicode codec entries in the module's character set-to-codec mapping; use add_codec() to add codecs the module does not know about. See the codecs module's documentation for more information.

The global character set registry is kept in the module global dictionary CHARSETS.

add_alias(alias, canonical)

Add a character set alias. *alias* is the alias name, e.g. latin-1. *canonical* is the character set's canonical name, e.g. iso-8859-1.

The global charset alias registry is kept in the module global dictionary ALIASES.

add_codec(charset, codecname)

Add a codec that map characters in the given character set to and from Unicode.

charset is the canonical name of a character set. *codecname* is the name of a Python codec, as appropriate for the second argument to the unicode() built-in, or to the encode() method of a Unicode string.

12.2.7 Encoders

When creating Message objects from scratch, you often need to encode the payloads for transport through compliant mail servers. This is especially true for image/* and text/* type messages containing binary data.

The email package provides some convenient encodings in its Encoders module. These encoders are actually used by the MIMEAudio and MIMEImage class constructors to provide default encodings. All encoder functions take exactly one argument, the message object to encode. They usually extract the payload, encode it, and reset the payload to this newly encoded value. They should also set the Content-Transfer-Encoding: header as appropriate.

Here are the encoding functions provided:

encode_quopri(msg)

Encodes the payload into quoted-printable form and sets the Content-Transfer-Encoding: header to quoted-printable². This is a good encoding to use when most of your payload is normal printable data, but contains a few unprintable characters.

encode_base64(msg)

Encodes the payload into base64 form and sets the Content-Transfer-Encoding: header to base64. This is a good encoding to use when most of your payload is unprintable data since it is a more compact form than quoted-printable. The drawback of base64 encoding is that it renders the text non-human readable.

encode_7or8bit(msg)

This doesn't actually modify the message's payload, but it does set the Content-Transfer-Encoding: header to either 7bit or 8bit as appropriate, based on the payload data.

encode_noop(msg)

This does nothing; it doesn't even set the Content-Transfer-Encoding: header.

12.2.8 Exception and Defect classes

The following exception classes are defined in the email. Errors module:

exception MessageError()

This is the base class for all exceptions that the email package can raise. It is derived from the standard Exception class and defines no additional methods.

exception MessageParseError()

This is the base class for exceptions thrown by the Parser class. It is derived from MessageError.

exception HeaderParseError()

Raised under some error conditions when parsing the RFC 2822 headers of a message, this class is derived from MessageParseError. It can be raised from the Parser.parse() or Parser.parsestr() methods.

Situations where it can be raised include finding an envelope header after the first RFC 2822 header of the message, finding a continuation line before the first RFC 2822 header is found, or finding a line in the headers which is neither a header or a continuation line.

exception BoundaryError()

Raised under some error conditions when parsing the RFC 2822 headers of a message, this class is derived from MessageParseError. It can be raised from the Parser.parse() or Parser.parsestr() methods.

Situations where it can be raised include not being able to find the starting or terminating boundary in a multipart/* message when strict parsing is used.

exception MultipartConversionError()

Raised when a payload is added to a Message object using add_payload(), but the payload is already a scalar and the message's Content-Type: main type is not either multipart or missing. MultipartConversionError multiply inherits from MessageError and the built-in TypeError.

Since Message.add_payload() is deprecated, this exception is rarely raised in practice. However the exception may also be raised if the attach() method is called on an instance of a class derived from MIMENonMultipart (e.g. MIMEImage).

Here's the list of the defects that the FeedParser can find while parsing messages. Note that the defects are added to the message where the problem was found, so for example, if a message nested inside a mul-

²Note that encoding with encode_quopri() also encodes all tabs and space characters in the data.

tipart/alternative had a malformed header, that nested message object would have a defect, but the containing messages would not.

All defect classes are subclassed from email. Errors. MessageDefect, but this class is *not* an exception! New in version 2.4: All the defect classes were added.

- NoBoundaryInMultipartDefect A message claimed to be a multipart, but had no boundary parameter.
- StartBoundaryNotFoundDefect The start boundary claimed in the Content-Type: header was never found.
- FirstHeaderLineIsContinuationDefect The message had a continuation line as its first header line.
- MisplacedEnvelopeHeaderDefect A "Unix From" header was found in the middle of a header block.
- MalformedHeaderDefect A header was found that was missing a colon, or was otherwise malformed.
- MultipartInvariantViolationDefect A message claimed to be a multipart, but no subparts were found. Note that when a message has this defect, its is_multipart() method may return false even though its content type claims to be multipart.

12.2.9 Miscellaneous utilities

There are several useful utilities provided in the email. Utils module:

quote(str)

Return a new string with backslashes in *str* replaced by two backslashes, and double quotes replaced by backslash-double quote.

unquote(str)

Return a new string which is an *unquoted* version of *str*. If *str* ends and begins with double quotes, they are stripped off. Likewise if *str* ends and begins with angle brackets, they are stripped off.

parseaddr(address)

Parse address – which should be the value of some address-containing field such as To: or Cc: – into its constituent *realname* and *email address* parts. Returns a tuple of that information, unless the parse fails, in which case a 2-tuple of ('', '') is returned.

formataddr(pair)

The inverse of parseaddr(), this takes a 2-tuple of the form (realname, email_address) and returns the string value suitable for a To: or Cc: header. If the first element of *pair* is false, then the second element is returned unmodified.

getaddresses(fieldvalues)

This method returns a list of 2-tuples of the form returned by parseaddr(). *fieldvalues* is a sequence of header field values as might be returned by Message.get_all(). Here's a simple example that gets all the recipients of a message:

```
from email.Utils import getaddresses

tos = msg.get_all('to', [])
ccs = msg.get_all('cc', [])
resent_tos = msg.get_all('resent-to', [])
resent_ccs = msg.get_all('resent-cc', [])
all_recipients = getaddresses(tos + ccs + resent_tos + resent_ccs)
```

parsedate(date)

Attempts to parse a date according to the rules in RFC 2822. however, some mailers don't follow that format as specified, so parsedate() tries to guess correctly in such cases. *date* is a string containing

an RFC 2822 date, such as "Mon, 20 Nov 1995 19:12:08 -0500". If it succeeds in parsing the date, parsedate() returns a 9-tuple that can be passed directly to time.mktime(); otherwise None will be returned. Note that fields 6, 7, and 8 of the result tuple are not usable.

parsedate_tz(date)

Performs the same function as parsedate(), but returns either None or a 10-tuple; the first 9 elements make up a tuple that can be passed directly to time.mktime(), and the tenth is the offset of the date's timezone from UTC (which is the official term for Greenwich Mean Time)³. If the input string has no timezone, the last element of the tuple returned is None. Note that fields 6, 7, and 8 of the result tuple are not usable.

mktime_tz(tuple)

Turn a 10-tuple as returned by parsedate_tz() into a UTC timestamp. It the timezone item in the tuple is None, assume local time. Minor deficiency: mktime_tz() interprets the first 8 elements of *tuple* as a local time and then compensates for the timezone difference. This may yield a slight error around changes in daylight savings time, though not worth worrying about for common use.

formatdate([timeval[, localtime][, usegmt]])

Returns a date string as per RFC 2822, e.g.:

```
Fri, 09 Nov 2001 01:08:47 -0000
```

Optional *timeval* if given is a floating point time value as accepted by time.gmtime() and time.localtime(), otherwise the current time is used.

Optional *localtime* is a flag that when True, interprets *timeval*, and returns a date relative to the local timezone instead of UTC, properly taking daylight savings time into account. The default is False meaning UTC is used.

Optional *usegmt* is a flag that when True, outputs a date string with the timezone as an ascii string GMT, rather than a numeric -0000. This is needed for some protocols (such as HTTP). This only applies when *localtime* is False. New in version 2.4.

make_msgid([idstring])

Returns a string suitable for an RFC 2822-compliant Message-ID: header. Optional *idstring* if given, is a string used to strengthen the uniqueness of the message id.

decode_rfc2231(s)

Decode the string *s* according to RFC 2231.

encode_rfc2231(s[, charset[, language]])

Encode the string *s* according to RFC 2231. Optional *charset* and *language*, if given is the character set name and language name to use. If neither is given, *s* is returned as-is. If *charset* is given but *language* is not, the string is encoded using the empty string for *language*.

collapse_rfc2231_value(value[, errors[, fallback_charset]])

When a header parameter is encoded in RFC 2231 format, Message.get_param() may return a 3-tuple containing the character set, language, and value. collapse_rfc2231_value() turns this into a unicode string. Optional *errors* is passed to the *errors* argument of the built-in unicode() function; it defaults to replace. Optional *fallback_charset* specifies the character set to use if the one in the RFC 2231 header is not known by Python; it defaults to us-ascii.

For convenience, if the *value* passed to collapse_rfc2231_value() is not a tuple, it should be a string and it is returned unquoted.

decode_params(params)

Decode parameters list according to RFC 2231. *params* is a sequence of 2-tuples containing elements of the form (content-type, string-value).

Changed in version 2.4: The dump_address_pair() function has been removed; use formataddr() instead..

³Note that the sign of the timezone offset is the opposite of the sign of the time.timezone variable for the same timezone; the latter variable follows the POSIX standard while this module follows RFC 2822.

Changed in version 2.4: The decode() function has been removed; use the Header.decode_header() method instead..

Changed in version 2.4: The encode() function has been removed; use the Header.encode() method instead..

12.2.10 Iterators

Iterating over a message object tree is fairly easy with the Message.walk() method. The email.Iterators module provides some useful higher level iterations over message object trees.

```
body_line_iterator(msg[, decode])
```

This iterates over all the payloads in all the subparts of *msg*, returning the string payloads line-by-line. It skips over all the subpart headers, and it skips over any subpart with a payload that isn't a Python string. This is somewhat equivalent to reading the flat text representation of the message from a file using readline(), skipping over all the intervening headers.

Optional decode is passed through to Message.get_payload().

```
typed_subpart_iterator(msg[, maintype[, subtype]])
```

This iterates over all the subparts of *msg*, returning only those subparts that match the MIME type specified by *maintype* and *subtype*.

Note that *subtype* is optional; if omitted, then subpart MIME type matching is done only with the main type. *maintype* is optional too; it defaults to text.

Thus, by default typed_subpart_iterator() returns each subpart that has a MIME type of text/*.

The following function has been added as a useful debugging tool. It should *not* be considered part of the supported public interface for the package.

```
\_structure(msg[, fp[, level]])
```

Prints an indented representation of the content types of the message object structure. For example:

```
>>> msg = email.message_from_file(somefile)
>>> _structure(msg)
multipart/mixed
    text/plain
    text/plain
    multipart/digest
        message/rfc822
            text/plain
        message/rfc822
            text/plain
        message/rfc822
            text/plain
        message/rfc822
            text/plain
        message/rfc822
            text/plain
    text/plain
```

Optional fp is a file-like object to print the output to. It must be suitable for Python's extended print statement. level is used internally.

12.2.11 Package History

Version 1 of the email package was bundled with Python releases up to Python 2.2.1. Version 2 was developed for the Python 2.3 release, and backported to Python 2.2.2. It was also available as a separate distutils-based package, and is compatible back to Python 2.1.

email version 3.0 was released with Python 2.4 and as a separate distutils-based package. It is compatible back to Python 2.3.

Here are the differences between email version 3 and version 2:

- The FeedParser class was introduced, and the Parser class was implemented in terms of the FeedParser. All parsing there for is non-strict, and parsing will make a best effort never to raise an exception. Problems found while parsing messages are stored in the message's *defect* attribute.
- All aspects of the API which raised DeprecationWarnings in version 2 have been removed. These include the *_encoder* argument to the MIMEText constructor, the Message.add_payload() method, the Utils.dump_address_pair() function, and the functions Utils.decode() and Utils.encode().
- New DeprecationWarnings have been added to: Generator.__call__(), Message.get_type(), Message.get_main_type(), Message.get_subtype(), and the *strict* argument to the Parser class. These are expected to be removed in email 3.1.
- Support for Pythons earlier than 2.3 has been removed.

Here are the differences between email version 2 and version 1:

- The email. Header and email. Charset modules have been added.
- The pickle format for Message instances has changed. Since this was never (and still isn't) formally defined, this isn't considered a backward incompatibility. However if your application pickles and unpickles Message instances, be aware that in email version 2, Message instances now have private variables _charset and _default_type.
- Several methods in the Message class have been deprecated, or their signatures changed. Also, many new methods have been added. See the documentation for the Message class for details. The changes should be completely backward compatible.
- The object structure has changed in the face of message/rfc822 content types. In email version 1, such a type would be represented by a scalar payload, i.e. the container message's is_multipart() returned false, get_payload() was not a list object, but a single Message instance.
 - This structure was inconsistent with the rest of the package, so the object representation for message/rfc822 content types was changed. In email version 2, the container *does* return True from is_multipart(), and get_payload() returns a list containing a single Message item.
 - Note that this is one place that backward compatibility could not be completely maintained. However, if you're already testing the return type of get_payload(), you should be fine. You just need to make sure your code doesn't do a set_payload() with a Message instance on a container with a content type of message/rfc822.
- The Parser constructor's *strict* argument was added, and its parse() and parsestr() methods grew a *headersonly* argument. The *strict* flag was also added to functions email.message_from_file() and email.message_from_string().
- Generator.__call__() is deprecated; use Generator.flatten() instead. The Generator class has also grown the clone() method.
- The DecodedGenerator class in the email.Generator module was added.
- The intermediate base classes MIMENonMultipart and MIMEMultipart have been added, and interposed in the class hierarchy for most of the other MIME-related derived classes.
- The _encoder argument to the MIMEText constructor has been deprecated. Encoding now happens implicitly based on the _charset argument.
- The following functions in the email.Utils module have been deprecated: dump_address_pairs(), decode(), and encode(). The following functions have been added to the module: make_msgid(), decode_rfc2231(), encode_rfc2231(), and decode_params().
- \bullet The non-public function email.Iterators._structure() was added.

12.2.12 Differences from mimelib

The email package was originally prototyped as a separate library called mimelib. Changes have been made so that method names are more consistent, and some methods or modules have either been added or removed. The semantics of some of the methods have also changed. For the most part, any functionality available in mimelib is still available in the email package, albeit often in a different way. Backward compatibility between the mimelib package and the email package was not a priority.

Here is a brief description of the differences between the mimelib and the email packages, along with hints on how to port your applications.

Of course, the most visible difference between the two packages is that the package name has been changed to email. In addition, the top-level package has the following differences:

- messageFromString() has been renamed to message_from_string().
- messageFromFile() has been renamed to message_from_file().

The Message class has the following differences:

- The method asString() was renamed to as_string().
- The method ismultipart() was renamed to is_multipart().
- The get_payload() method has grown a *decode* optional argument.
- The method getall() was renamed to get_all().
- The method addheader() was renamed to add_header().
- The method gettype() was renamed to get_type().
- The method getmaintype() was renamed to get_main_type().
- The method getsubtype() was renamed to get_subtype().
- The method getparams () was renamed to get_params (). Also, whereas getparams () returned a list of strings, get_params () returns a list of 2-tuples, effectively the key/value pairs of the parameters, split on the '=' sign.
- The method getparam() was renamed to get_param().
- The method getcharsets() was renamed to get_charsets().
- The method getfilename() was renamed to get_filename().
- The method getboundary() was renamed to get_boundary().
- The method setboundary() was renamed to set_boundary().
- The method getdecodedpayload() was removed. To get similar functionality, pass the value 1 to the *decode* flag of the get_payload() method.
- The method getpayloadastext() was removed. Similar functionality is supported by the DecodedGenerator class in the email.Generator module.
- The method getbodyastext() was removed. You can get similar functionality by creating an iterator with typed_subpart_iterator() in the email.Iterators module.

The Parser class has no differences in its public interface. It does have some additional smarts to recognize message/delivery-status type messages, which it represents as a Message instance containing separate Message subparts for each header block in the delivery status notification⁴.

⁴Delivery Status Notifications (DSN) are defined in RFC 1894.

The Generator class has no differences in its public interface. There is a new class in the email.Generator module though, called DecodedGenerator which provides most of the functionality previously available in the Message.getpayloadastext() method.

The following modules and classes have been changed:

- The MIMEBase class constructor arguments *_major* and *_minor* have changed to *_maintype* and *_subtype* respectively.
- The Image class/module has been renamed to MIMEImage. The *_minor* argument has been renamed to *_subtype*.
- The Text class/module has been renamed to MIMEText. The *_minor* argument has been renamed to *_subtype*.
- The MessageRFC822 class/module has been renamed to MIMEMessage. Note that an earlier version of mimelib called this class/module RFC822, but that clashed with the Python standard library module rfc822 on some case-insensitive file systems.

Also, the MIMEMessage class now represents any kind of MIME message with main type message. It takes an optional argument _subtype which is used to set the MIME subtype. _subtype defaults to rfc822.

mimelib provided some utility functions in its address and date modules. All of these functions have been moved to the email.Utils module.

The MsgReader class/module has been removed. Its functionality is most closely supported in the body_line_iterator() function in the email.Iterators module.

12.2.13 Examples

Here are a few examples of how to use the email package to read, write, and send simple email messages, as well as more complex MIME messages.

First, let's see how to create and send a simple text message:

```
# Import smtplib for the actual sending function
import smtplib
# Import the email modules we'll need
from email.MIMEText import MIMEText
# Open a plain text file for reading. For this example, assume that
# the text file contains only ASCII characters.
fp = open(textfile, 'rb')
# Create a text/plain message
msg = MIMEText(fp.read())
fp.close()
# me == the sender's email address
# you == the recipient's email address
msg['Subject'] = 'The contents of %s' % textfile
msg['From'] = me
msg['To'] = you
# Send the message via our own SMTP server, but don't include the
# envelope header.
s = smtplib.SMTP()
s.connect()
s.sendmail(me, [you], msg.as_string())
```

Here's an example of how to send a MIME message containing a bunch of family pictures that may be residing in a directory:

```
# Import smtplib for the actual sending function
     import smtplib
     # Here are the email pacakge modules we'll need
     from email.MIMEImage import MIMEImage
     from email.MIMEMultipart import MIMEMultipart
     COMMASPACE = ', '
     # Create the container (outer) email message.
     msg = MIMEMultipart()
     msg['Subject'] = 'Our family reunion'
     # me == the sender's email address
     # family = the list of all recipients' email addresses
     msg['From'] = me
     msg['To'] = COMMASPACE.join(family)
     msg.preamble = 'Our family reunion'
     # Guarantees the message ends in a newline
     msg.epilogue = ''
     # Assume we know that the image files are all in PNG format
     for file in pngfiles:
         # Open the files in binary mode. Let the MIMEImage class automatically
         # guess the specific image type.
         fp = open(file, 'rb')
         img = MIMEImage(fp.read())
         fp.close()
         msg.attach(img)
     # Send the email via our own SMTP server.
     s = smtplib.SMTP()
     s.connect()
     s.sendmail(me, family, msg.as_string())
     s.close()
Here's an example of how to send the entire contents of a directory as an email message: <sup>5</sup>
     #!/usr/bin/env python
     """Send the contents of a directory as a MIME message.
     Usage: dirmail [options] from to [to ...]*
     Options:
         -h / --help
             Print this message and exit.
         -d directory
         --directory=directory
             Mail the contents of the specified directory, otherwise use the
             current directory. Only the regular files in the directory are sent,
             and we don't recurse to subdirectories.
     'from' is the email address of the sender of the message.
     'to' is the email address of the recipient of the message, and multiple
     recipients may be given.
     The email is sent by forwarding to your local SMTP server, which then does the
     normal delivery process. Your local machine must be running an SMTP server.
```

⁵Thanks to Matthew Dixon Cowles for the original inspiration and examples.

```
import sys
import os
import getopt
import smtplib
# For guessing MIME type based on file name extension
import mimetypes
from email import Encoders
from email.Message import Message
from email.MIMEAudio import MIMEAudio
from email.MIMEBase import MIMEBase
from email.MIMEMultipart import MIMEMultipart
from email.MIMEImage import MIMEImage
from email.MIMEText import MIMEText
COMMASPACE = ', '
def usage(code, msg=''):
    print >> sys.stderr, __doc__
    if msg:
       print >> sys.stderr, msg
    sys.exit(code)
def main():
    try:
        opts, args = getopt.getopt(sys.argv[1:], 'hd:', ['help', 'directory='])
    except getopt.error, msg:
        usage(1, msg)
    dir = os.curdir
    for opt, arg in opts:
        if opt in ('-h', '--help'):
            usage(0)
        elif opt in ('-d', '--directory'):
            dir = arg
    if len(args) < 2:
       usage(1)
    sender = args[0]
    recips = args[1:]
    # Create the enclosing (outer) message
    outer = MIMEMultipart()
    outer['Subject'] = 'Contents of directory %s' % os.path.abspath(dir)
    outer['To'] = COMMASPACE.join(recips)
    outer['From'] = sender
    outer.preamble = 'You will not see this in a MIME-aware mail reader.\n'
    # To guarantee the message ends with a newline
    outer.epilogue = ''
    for filename in os.listdir(dir):
        path = os.path.join(dir, filename)
        if not os.path.isfile(path):
        # Guess the content type based on the file's extension. Encoding
        # will be ignored, although we should check for simple things like
        # gzip'd or compressed files.
        ctype, encoding = mimetypes.guess_type(path)
        if ctype is None or encoding is not None:
            # No guess could be made, or the file is encoded (compressed), so
```

```
# use a generic bag-of-bits type.
            ctype = 'application/octet-stream'
        maintype, subtype = ctype.split('/', 1)
        if maintype == 'text':
            fp = open(path)
            # Note: we should handle calculating the charset
            msg = MIMEText(fp.read(), _subtype=subtype)
            fp.close()
        elif maintype == 'image':
            fp = open(path, 'rb')
            msg = MIMEImage(fp.read(), _subtype=subtype)
            fp.close()
        elif maintype == 'audio':
            fp = open(path, 'rb')
            msg = MIMEAudio(fp.read(), _subtype=subtype)
            fp.close()
        else:
            fp = open(path, 'rb')
            msg = MIMEBase(maintype, subtype)
            msg.set_payload(fp.read())
            fp.close()
            # Encode the payload using Base64
            Encoders.encode_base64(msg)
        # Set the filename parameter
        msg.add_header('Content-Disposition', 'attachment', filename=filename)
        outer.attach(msg)
   # Now send the message
   s = smtplib.SMTP()
   s.connect()
   s.sendmail(sender, recips, outer.as_string())
   s.close()
if __name__ == '__main__':
   main()
```

And finally, here's an example of how to unpack a MIME message like the one above, into a directory of files:

```
#!/usr/bin/env python
"""Unpack a MIME message into a directory of files.
Usage: unpackmail [options] msgfile
Options:
    -h / --help
        Print this message and exit.
    -d directory
    --directory=directory
        Unpack the MIME message into the named directory, which will be
        created if it doesn't already exist.
msgfile is the path to the file containing the MIME message.
import sys
import os
import getopt
import errno
import mimetypes
import email
```

```
def usage(code, msg=''):
    print >> sys.stderr, __doc__
    if msg:
        print >> sys.stderr, msg
    sys.exit(code)
def main():
    try:
        opts, args = getopt.getopt(sys.argv[1:], 'hd:', ['help', 'directory='])
    except getopt.error, msg:
        usage(1, msg)
    dir = os.curdir
    for opt, arg in opts:
        if opt in ('-h', '--help'):
            usage(0)
        elif opt in ('-d', '--directory'):
            dir = arg
    try:
        msgfile = args[0]
    except IndexError:
        usage(1)
    try:
        os.mkdir(dir)
    except OSError, e:
        # Ignore directory exists error
        if e.errno <> errno.EEXIST: raise
    fp = open(msqfile)
    msg = email.message_from_file(fp)
    fp.close()
    counter = 1
    for part in msg.walk():
        # multipart/* are just containers
        if part.get_content_maintype() == 'multipart':
            continue
        \ensuremath{\sharp} Applications should really sanitize the given filename so that an
        # email message can't be used to overwrite important files
        filename = part.get_filename()
        if not filename:
            ext = mimetypes.guess_extension(part.get_type())
            if not ext:
                # Use a generic bag-of-bits extension
                ext = '.bin'
            filename = 'part-%03d%s' % (counter, ext)
        counter += 1
        fp = open(os.path.join(dir, filename), 'wb')
        fp.write(part.get_payload(decode=1))
        fp.close()
if __name__ == '__main__':
    main()
```

12.3 mailcap — Mailcap file handling.

Mailcap files are used to configure how MIME-aware applications such as mail readers and Web browsers react to files with different MIME types. (The name "mailcap" is derived from the phrase "mail capability".) For example, a mailcap file might contain a line like 'video/mpeg; xmpeg %s'. Then, if the user encounters an email message or Web document with the MIME type video/mpeg, '%s' will be replaced by a filename (usually one belonging to a temporary file) and the **xmpeg** program can be automatically started to view the file.

The mailcap format is documented in RFC 1524, "A User Agent Configuration Mechanism For Multimedia Mail Format Information," but is not an Internet standard. However, mailcap files are supported on most UNIX systems.

```
findmatch(caps, MIMEtype[, key[, filename[, plist]]])
```

Return a 2-tuple; the first element is a string containing the command line to be executed (which can be passed to os.system()), and the second element is the mailcap entry for a given MIME type. If no matching MIME type can be found, (None, None) is returned.

key is the name of the field desired, which represents the type of activity to be performed; the default value is 'view', since in the most common case you simply want to view the body of the MIME-typed data. Other possible values might be 'compose' and 'edit', if you wanted to create a new body of the given MIME type or alter the existing body data. See RFC 1524 for a complete list of these fields.

filename is the filename to be substituted for '%s' in the command line; the default value is '/dev/null' which is almost certainly not what you want, so usually you'll override it by specifying a filename.

plist can be a list containing named parameters; the default value is simply an empty list. Each entry in the list must be a string containing the parameter name, an equals sign ('='), and the parameter's value. Mailcap entries can contain named parameters like % {foo}, which will be replaced by the value of the parameter named 'foo'. For example, if the command line 'showpartial % {id} % {number} % {total}' was in a mailcap file, and plist was set to ['id=1', 'number=2', 'total=3'], the resulting command line would be 'showpartial 1 2 3'.

In a mailcap file, the "test" field can optionally be specified to test some external condition (such as the machine architecture, or the window system in use) to determine whether or not the mailcap line applies. findmatch() will automatically check such conditions and skip the entry if the check fails.

getcaps()

Returns a dictionary mapping MIME types to a list of mailcap file entries. This dictionary must be passed to the findmatch() function. An entry is stored as a list of dictionaries, but it shouldn't be necessary to know the details of this representation.

The information is derived from all of the mailcap files found on the system. Settings in the user's mailcap file '\$HOME/.mailcap' will override settings in the system mailcap files '/etc/mailcap', '/usr/etc/mailcap', and '/usr/local/etc/mailcap'.

An example usage:

```
>>> import mailcap
>>> d=mailcap.getcaps()
>>> mailcap.findmatch(d, 'video/mpeg', filename='/tmp/tmp1223')
('xmpeg /tmp/tmp1223', {'view': 'xmpeg %s'})
```

12.4 mailbox — Read various mailbox formats

This module defines a number of classes that allow easy and uniform access to mail messages in a (UNIX) mailbox.

```
class UnixMailbox(fp[, factory])
```

Access to a classic UNIX-style mailbox, where all messages are contained in a single file and separated by 'From' (a.k.a. 'From_') lines. The file object fp points to the mailbox file. The optional factory parameter is a callable that should create new message objects. factory is called with one argument, fp by the next() method of the mailbox object. The default is the rfc822. Message class (see the rfc822 module – and the note below).

Note: For reasons of this module's internal implementation, you will probably want to open the *fp* object in binary mode. This is especially important on Windows.

For maximum portability, messages in a UNIX-style mailbox are separated by any line that begins exactly with the string 'From' (note the trailing space) if preceded by exactly two newlines. Because of the widerange of variations in practice, nothing else on the From_line should be considered. However, the current implementation doesn't check for the leading two newlines. This is usually fine for most applications.

The UnixMailbox class implements a more strict version of From_line checking, using a regular expression that usually correctly matched From_delimiters. It considers delimiter line to be separated by 'From name time' lines. For maximum portability, use the PortableUnixMailbox class instead. This class is identical to UnixMailbox except that individual messages are separated by only 'From' lines.

For more information, see Configuring Netscape Mail on UNIX: Why the Content-Length Format is Bad.

class PortableUnixMailbox(fp[, factory])

A less-strict version of UnixMailbox, which considers only the 'From' at the beginning of the line separating messages. The "name time" portion of the From line is ignored, to protect against some variations that are observed in practice. This works since lines in the message which begin with 'From' are quoted by mail handling software at delivery-time.

class MmdfMailbox(fp[, factory])

Access an MMDF-style mailbox, where all messages are contained in a single file and separated by lines consisting of 4 control-A characters. The file object *fp* points to the mailbox file. Optional *factory* is as with the UnixMailbox class.

class MHMailbox(dirname[, factory])

Access an MH mailbox, a directory with each message in a separate file with a numeric name. The name of the mailbox directory is passed in *dirname*. *factory* is as with the UnixMailbox class.

class Maildir(dirname[, factory])

Access a Qmail mail directory. All new and current mail for the mailbox specified by *dirname* is made available. *factory* is as with the UnixMailbox class.

class BabylMailbox(fp[, factory])

Access a Babyl mailbox, which is similar to an MMDF mailbox. In Babyl format, each message has two sets of headers, the *original* headers and the *visible* headers. The original headers appear before a line containing only '*** EOOH ***' (End-Of-Original-Headers) and the visible headers appear after the EOOH line. Babyl-compliant mail readers will show you only the visible headers, and BabylMailbox objects will return messages containing only the visible headers. You'll have to do your own parsing of the mailbox file to get at the original headers. Mail messages start with the EOOH line and end with a line containing only '\037\014'. *factory* is as with the UnixMailbox class.

Note that because the rfc822 module is deprecated, it is recommended that you use the email package to create message objects from a mailbox. (The default can't be changed for backwards compatibility reasons.) The safest way to do this is with bit of code:

```
import email
import email.Errors
import mailbox

def msgfactory(fp):
    try:
        return email.message_from_file(fp)
    except email.Errors.MessageParseError:
        # Don't return None since that will
# stop the mailbox iterator
return ''

mbox = mailbox.UnixMailbox(fp, msgfactory)
```

The above wrapper is defensive against ill-formed MIME messages in the mailbox, but you have to be prepared to receive the empty string from the mailbox's next() method. On the other hand, if you know your mailbox contains only well-formed MIME messages, you can simplify this to:

```
import email
import mailbox

mbox = mailbox.UnixMailbox(fp, email.message_from_file)
```

See Also:

```
mbox - file containing mail messages
(http://www.qmail.org/man/man5/mbox.html)
```

Description of the traditional "mbox" mailbox format.

maildir - directory for incoming mail messages (http://www.gmail.org/man/man5/maildir.html)

Description of the "maildir" mailbox format.

Configuring Netscape Mail on UNIX: Why the Content-Length Format is Bad (http://home.netscape.com/eng/mozilla/2.0/relnotes/demo/content-length.html)

A description of problems with relying on the Content-Length: header for messages stored in mailbox files.

12.4.1 Mailbox Objects

All implementations of mailbox objects are iterable objects, and have one externally visible method. This method is used by iterators created from mailbox objects and may also be used directly.

next()

Return the next message in the mailbox, created with the optional *factory* argument passed into the mailbox object's constructor. By default this is an rfc822. Message object (see the rfc822 module). Depending on the mailbox implementation the *fp* attribute of this object may be a true file object or a class instance simulating a file object, taking care of things like message boundaries if multiple mail messages are contained in a single file, etc. If no more messages are available, this method returns None.

12.5 mhlib — Access to MH mailboxes

The mhlib module provides a Python interface to MH folders and their contents.

The module contains three basic classes, MH, which represents a particular collection of folders, Folder, which represents a single folder, and Message, which represents a single message.

```
class MH ( [path[, profile]])
```

MH represents a collection of MH folders.

```
{\bf class} \; {\bf Folder} \, (\, mh, \, name \, )
```

The Folder class represents a single folder and its messages.

```
class Message (folder, number [, name])
```

Message objects represent individual messages in a folder. The Message class is derived from mimetools.Message.

12.5.1 MH Objects

MH instances have the following methods:

```
error(format[, ...])
```

Print an error message – can be overridden.

```
getprofile(key)
```

Return a profile entry (None if not set).

getpath()

Return the mailbox pathname.

getcontext()

Return the current folder name.

setcontext(name)

Set the current folder name.

listfolders()

Return a list of top-level folders.

listallfolders()

Return a list of all folders.

listsubfolders(name)

Return a list of direct subfolders of the given folder.

${\tt listall subfolders} \, (\, name \,)$

Return a list of all subfolders of the given folder.

makefolder(name)

Create a new folder.

deletefolder(name)

Delete a folder – must have no subfolders.

openfolder(name)

Return a new open folder object.

12.5.2 Folder Objects

Folder instances represent open folders and have the following methods:

error(format[, ...])

Print an error message – can be overridden.

getfullname()

Return the folder's full pathname.

getsequencesfilename()

Return the full pathname of the folder's sequences file.

${\tt getmessagefilename}\,(\,n\,)$

Return the full pathname of message n of the folder.

listmessages()

Return a list of messages in the folder (as numbers).

getcurrent()

Return the current message number.

setcurrent(n)

Set the current message number to n.

parsesequence(seq)

Parse msgs syntax into list of messages.

getlast()

Get last message, or 0 if no messages are in the folder.

setlast(n)

Set last message (internal use only).

getsequences()

Return dictionary of sequences in folder. The sequence names are used as keys, and the values are the lists of message numbers in the sequences.

putsequences(dict)

Return dictionary of sequences in folder name: list.

removemessages (list)

Remove messages in list from folder.

refilemessages(list, tofolder)

Move messages in list to other folder.

movemessage(n, tofolder, ton)

Move one message to a given destination in another folder.

copymessage(n, tofolder, ton)

Copy one message to a given destination in another folder.

12.5.3 Message Objects

The Message class adds one method to those of mimetools. Message:

openmessage(n)

Return a new open message object (costs a file descriptor).

12.6 mimetools — Tools for parsing MIME messages

Deprecated since release 2.3. The email package should be used in preference to the mimetools module. This module is present only to maintain backward compatibility.

This module defines a subclass of the rfc822 module's Message class and a number of utility functions that are useful for the manipulation for MIME multipart or encoded message.

It defines the following items:

class Message (fp | , seekable |)

Return a new instance of the Message class. This is a subclass of the rfc822. Message class, with some additional methods (see below). The seekable argument has the same meaning as for rfc822. Message.

choose_boundary()

Return a unique string that has a high likelihood of being usable as a part boundary. The string has the form 'hostipaddr.uid.pid.timestamp.random'.

decode(input, output, encoding)

Read data encoded using the allowed MIME *encoding* from open file object *input* and write the decoded data to open file object *output*. Valid values for *encoding* include 'base64', 'quoted-printable', 'uuencode', 'x-uuencode', 'x-uue', 'x-uue', '7bit', and '8bit'. Decoding messages encoded in '7bit' or '8bit' has no effect. The input is simply copied to the output.

encode(input, output, encoding)

Read data from open file object *input* and write it encoded using the allowed MIME *encoding* to open file object *output*. Valid values for *encoding* are the same as for decode().

copyliteral(input, output)

Read lines from open file *input* until EOF and write them to open file *output*.

copybinary(input, output)

Read blocks until EOF from open file *input* and write them to open file *output*. The block size is currently fixed at 8192.

See Also:

Module email (section 12.2):

Comprehensive email handling package; supersedes the mimetools module.

Module rfc822 (section 12.11):

Provides the base class for mimetools. Message.

Module multifile (section 12.10):

Support for reading files which contain distinct parts, such as MIME data.

http://www.cs.uu.nl/wais/html/na-dir/mail/mime-faq/.html

The MIME Frequently Asked Questions document. For an overview of MIME, see the answer to question 1.1 in Part 1 of this document.

12.6.1 Additional Methods of Message Objects

The Message class defines the following methods in addition to the rfc822. Message methods:

getplist()

Return the parameter list of the Content-Type: header. This is a list of strings. For parameters of the form 'key=value', key is converted to lower case but value is not. For example, if the message contains the header 'Content-type: text/html; spam=1; Spam=2; Spam' then getplist() will return the Python list ['spam=1', 'spam=2', 'Spam'].

getparam(name)

Return the *value* of the first parameter (as returned by getplist()) of the form 'name=value' for the given *name*. If *value* is surrounded by quotes of the form '<...>' or '"..."', these are removed.

getencoding()

Return the encoding specified in the Content-Transfer-Encoding: message header. If no such header exists, return '7bit'. The encoding is converted to lower case.

gettype()

Return the message type (of the form 'type/subtype') as specified in the Content-Type: header. If no such header exists, return 'text/plain'. The type is converted to lower case.

getmaintype()

Return the main type as specified in the Content-Type: header. If no such header exists, return 'text'. The main type is converted to lower case.

getsubtype()

Return the subtype as specified in the Content-Type: header. If no such header exists, return 'plain'. The subtype is converted to lower case.

12.7 mimetypes — Map filenames to MIME types

The mimetypes module converts between a filename or URL and the MIME type associated with the filename extension. Conversions are provided from filename to MIME type and from MIME type to filename extension; encodings are not supported for the latter conversion.

The module provides one class and a number of convenience functions. The functions are the normal interface to this module, but some applications may be interested in the class as well.

The functions described below provide the primary interface for this module. If the module has not been initialized, they will call init() if they rely on the information init() sets up.

guess_type(filename|, strict|)

Guess the type of a file based on its filename or URL, given by *filename*. The return value is a tuple (*type*, *encoding*) where *type* is None if the type can't be guessed (missing or unknown suffix) or a string of the form 'type/subtype', usable for a MIME content-type: header.

encoding is None for no encoding or the name of the program used to encode (e.g. **compress** or **gzip**). The encoding is suitable for use as a Content-Encoding: header, *not* as a Content-Transfer-Encoding: header. The mappings are table driven. Encoding suffixes are case sensitive; type suffixes are first tried case sensitively, then case insensitively.

Optional *strict* is a flag specifying whether the list of known MIME types is limited to only the official types registered with IANA are recognized. When *strict* is true (the default), only the IANA types are supported; when *strict* is false, some additional non-standard but commonly used MIME types are also recognized.

guess_all_extensions(type[, strict])

Guess the extensions for a file based on its MIME type, given by *type*. The return value is a list of strings giving all possible filename extensions, including the leading dot ('.'). The extensions are not guaranteed to have been associated with any particular data stream, but would be mapped to the MIME type *type* by guess_type().

Optional *strict* has the same meaning as with the guess_type() function.

guess_extension(type[, strict])

Guess the extension for a file based on its MIME type, given by *type*. The return value is a string giving a filename extension, including the leading dot ('.'). The extension is not guaranteed to have been associated with any particular data stream, but would be mapped to the MIME type *type* by guess_type(). If no extension can be guessed for *type*, None is returned.

Optional *strict* has the same meaning as with the guess_type() function.

Some additional functions and data items are available for controlling the behavior of the module.

init([files])

Initialize the internal data structures. If given, *files* must be a sequence of file names which should be used to augment the default type map. If omitted, the file names to use are taken from knownfiles. Each file named in *files* or knownfiles takes precedence over those named before it. Calling init() repeatedly is allowed.

read_mime_types(filename)

Load the type map given in the file *filename*, if it exists. The type map is returned as a dictionary mapping filename extensions, including the leading dot ('.'), to strings of the form 'type/subtype'. If the file *filename* does not exist or cannot be read, None is returned.

add_type(type, ext[, strict])

Add a mapping from the mimetype *type* to the extension *ext*. When the extension is already known, the new type will replace the old one. When the type is already known the extension will be added to the list of known extensions.

When *strict* is the mapping will added to the official MIME types, otherwise to the non-standard ones.

inited

Flag indicating whether or not the global data structures have been initialized. This is set to true by init().

knownfiles

List of type map file names commonly installed. These files are typically named 'mime.types' and are installed in different locations by different packages.

suffix_map

Dictionary mapping suffixes to suffixes. This is used to allow recognition of encoded files for which the encoding and the type are indicated by the same extension. For example, the '.tgz' extension is mapped to '.tar.gz' to allow the encoding and type to be recognized separately.

encodings_map

Dictionary mapping filename extensions to encoding types.

types_map

Dictionary mapping filename extensions to MIME types.

common_types

Dictionary mapping filename extensions to non-standard, but commonly found MIME types.

The MimeTypes class may be useful for applications which may want more than one MIME-type database:

class MimeTypes([filenames])

This class represents a MIME-types database. By default, it provides access to the same database as the rest of this module. The initial database is a copy of that provided by the module, and may be extended by loading additional 'mime.types'-style files into the database using the read() or readfp() methods. The mapping dictionaries may also be cleared before loading additional data if the default data is not desired.

The optional *filenames* parameter can be used to cause additional files to be loaded "on top" of the default database.

New in version 2.2.

12.7.1 MimeTypes Objects

MimeTypes instances provide an interface which is very like that of the mimetypes module.

suffix_map

Dictionary mapping suffixes to suffixes. This is used to allow recognition of encoded files for which the encoding and the type are indicated by the same extension. For example, the '.tgz' extension is mapped to '.tar.gz' to allow the encoding and type to be recognized separately. This is initially a copy of the global suffix_map defined in the module.

encodings_map

Dictionary mapping filename extensions to encoding types. This is initially a copy of the global encodings_map defined in the module.

types_map

Dictionary mapping filename extensions to MIME types. This is initially a copy of the global types_map defined in the module.

common_types

Dictionary mapping filename extensions to non-standard, but commonly found MIME types. This is initially a copy of the global common_types defined in the module.

guess_extension(type[, strict])

Similar to the guess_extension() function, using the tables stored as part of the object.

guess_type(url[, strict])

Similar to the guess_type() function, using the tables stored as part of the object.

read(path)

Load MIME information from a file named path. This uses readfp() to parse the file.

readfp(file)

Load MIME type information from an open file. The file must have the format of the standard 'mime.types' files.

12.8 MimeWriter — Generic MIME file writer

Deprecated since release 2.3. The email package should be used in preference to the MimeWriter module. This module is present only to maintain backward compatibility.

This module defines the class MimeWriter. The MimeWriter class implements a basic formatter for creating MIME multi-part files. It doesn't seek around the output file nor does it use large amounts of buffer space. You must write the parts out in the order that they should occur in the final file. MimeWriter does buffer the headers you add, allowing you to rearrange their order.

${f class} \; {f MimeWriter} \, (fp \,)$

Return a new instance of the MimeWriter class. The only argument passed, fp, is a file object to be used for writing. Note that a StringIO object could also be used.

12.8.1 MimeWriter Objects

MimeWriter instances have the following methods:

addheader (key, value, prefix)

Add a header line to the MIME message. The *key* is the name of the header, where the *value* obviously provides the value of the header. The optional argument *prefix* determines where the header is inserted; '0' means append at the end, '1' is insert at the start. The default is to append.

flushheaders()

Causes all headers accumulated so far to be written out (and forgotten). This is useful if you don't need a body part at all, e.g. for a subpart of type message/rfc822 that's (mis)used to store some header-like information.

startbody(ctype[, plist[, prefix]])

Returns a file-like object which can be used to write to the body of the message. The content-type is set to the provided *ctype*, and the optional parameter *plist* provides additional parameters for the content-type declaration. *prefix* functions as in addheader () except that the default is to insert at the start.

startmultipartbody(subtype[, boundary[, plist[, prefix]]])

Returns a file-like object which can be used to write to the body of the message. Additionally, this method initializes the multi-part code, where *subtype* provides the multipart subtype, *boundary* may provide a user-defined boundary specification, and *plist* provides optional parameters for the subtype. *prefix* functions as in startbody(). Subparts should be created using nextpart().

nextpart()

Returns a new instance of MimeWriter which represents an individual part in a multipart message. This may be used to write the part as well as used for creating recursively complex multipart messages. The message must first be initialized with startmultipartbody() before using nextpart().

lastpart()

This is used to designate the last part of a multipart message, and should *always* be used when writing multipart messages.

12.9 mimify — MIME processing of mail messages

Deprecated since release 2.3. The email package should be used in preference to the mimify module. This module is present only to maintain backward compatibility.

The mimify module defines two functions to convert mail messages to and from MIME format. The mail message can be either a simple message or a so-called multipart message. Each part is treated separately. Mimifying (a part of) a message entails encoding the message as quoted-printable if it contains any characters that cannot be represented using 7-bit ASCII. Unmimifying (a part of) a message entails undoing the quoted-printable encoding. Mimify and unmimify are especially useful when a message has to be edited before being sent. Typical use would be:

```
unmimify message
edit message
mimify message
send message
```

The modules defines the following user-callable functions and user-settable variables:

mimify(infile, outfile)

Copy the message in *infile* to *outfile*, converting parts to quoted-printable and adding MIME mail headers when necessary. *infile* and *outfile* can be file objects (actually, any object that has a readline() method (for *infile*) or a write() method (for *outfile*)) or strings naming the files. If *infile* and *outfile* are both strings, they may have the same value.

unmimify(infile, outfile[, decode_base64])

Copy the message in *infile* to *outfile*, decoding all quoted-printable parts. *infile* and *outfile* can be file objects (actually, any object that has a readline() method (for *infile*) or a write() method (for *outfile*)) or strings naming the files. If *infile* and *outfile* are both strings, they may have the same value. If the $decode_base64$ argument is provided and tests true, any parts that are coded in the base64 encoding are decoded as well.

mime_decode_header(line)

Return a decoded version of the encoded header line in *line*. This only supports the ISO 8859-1 charset (Latin-1).

mime_encode_header(line)

Return a MIME-encoded version of the header line in line.

MAXLEN

By default, a part will be encoded as quoted-printable when it contains any non-ASCII characters (characters with the 8th bit set), or if there are any lines longer than MAXLEN characters (default value 200).

CHARSET

When not specified in the mail headers, a character set must be filled in. The string used is stored in CHARSET, and the default value is ISO-8859-1 (also known as Latin1 (latin-one)).

This module can also be used from the command line. Usage is as follows:

```
mimify.py -e [-l length] [infile [outfile]]
mimify.py -d [-b] [infile [outfile]]
```

to encode (mimify) and decode (unmimify) respectively. *infile* defaults to standard input, *outfile* defaults to standard output. The same file can be specified for input and output.

If the -1 option is given when encoding, if there are any lines longer than the specified *length*, the containing part will be encoded.

If the **-b** option is given when decoding, any base64 parts will be decoded as well.

See Also:

Module quopri (section 12.15):

Encode and decode MIME quoted-printable files.

12.10 multifile — Support for files containing distinct parts

The MultiFile object enables you to treat sections of a text file as file-like input objects, with '' being returned by readline() when a given delimiter pattern is encountered. The defaults of this class are designed to make it useful for parsing MIME multipart messages, but by subclassing it and overriding methods it can be easily adapted for more general use.

class MultiFile(fp[, seekable])

Create a multi-file. You must instantiate this class with an input object argument for the MultiFile instance to get lines from, such as a file object returned by open().

MultiFile only ever looks at the input object's readline(), seek() and tell() methods, and the latter two are only needed if you want random access to the individual MIME parts. To use MultiFile on a non-seekable stream object, set the optional *seekable* argument to false; this will prevent using the input object's seek() and tell() methods.

It will be useful to know that in MultiFile's view of the world, text is composed of three kinds of lines: data, section-dividers, and end-markers. MultiFile is designed to support parsing of messages that may have multiple nested message parts, each with its own pattern for section-divider and end-marker lines.

See Also:

Module email (section 12.2):

 $Comprehensive\ email\ handling\ package;\ supersedes\ the\ multifile\ module.$

12.10.1 MultiFile Objects

A MultiFile instance has the following methods:

readline(str)

Read a line. If the line is data (not a section-divider or end-marker or real EOF) return it. If the line matches the most-recently-stacked boundary, return '' and set self.last to 1 or 0 according as the match is or is not an end-marker. If the line matches any other stacked boundary, raise an error. On encountering end-of-file on the underlying stream object, the method raises Error unless all boundaries have been popped.

readlines(str)

Return all lines remaining in this part as a list of strings.

read()

Read all lines, up to the next section. Return them as a single (multiline) string. Note that this doesn't take a size argument!

seek(pos[, whence])

Seek. Seek indices are relative to the start of the current section. The *pos* and *whence* arguments are interpreted as for a file seek.

tell()

Return the file position relative to the start of the current section.

next()

Skip lines to the next section (that is, read lines until a section-divider or end-marker has been consumed). Return true if there is such a section, false if an end-marker is seen. Re-enable the most-recently-pushed boundary.

is_data(str)

Return true if *str* is data and false if it might be a section boundary. As written, it tests for a prefix other than '--' at start of line (which all MIME boundaries have) but it is declared so it can be overridden in derived classes.

Note that this test is used intended as a fast guard for the real boundary tests; if it always returns false it will merely slow processing, not cause it to fail.

push(str)

Push a boundary string. When an appropriately decorated version of this boundary is found as an input line, it will be interpreted as a section-divider or end-marker. All subsequent reads will return the empty string to indicate end-of-file, until a call to pop() removes the boundary a or next() call reenables it.

It is possible to push more than one boundary. Encountering the most-recently-pushed boundary will return EOF; encountering any other boundary will raise an error.

pop()

Pop a section boundary. This boundary will no longer be interpreted as EOF.

section_divider(str)

Turn a boundary into a section-divider line. By default, this method prepends '--' (which MIME section boundaries have) but it is declared so it can be overridden in derived classes. This method need not append LF or CR-LF, as comparison with the result ignores trailing whitespace.

end_marker(str)

Turn a boundary string into an end-marker line. By default, this method prepends '--' and appends '--' (like a MIME-multipart end-of-message marker) but it is declared so it can be overridden in derived classes. This method need not append LF or CR-LF, as comparison with the result ignores trailing whitespace.

Finally, MultiFile instances have two public instance variables:

level

Nesting depth of the current part.

last

True if the last end-of-file was for an end-of-message marker.

12.10.2 MultiFile Example

```
import mimetools
import multifile
import StringIO
def extract_mime_part_matching(stream, mimetype):
    """Return the first element in a multipart MIME message on stream
    matching mimetype.""
    msg = mimetools.Message(stream)
    msgtype = msg.gettype()
    params = msg.getplist()
    data = StringIO.StringIO()
    if msgtype[:10] == "multipart/":
        file = multifile.MultiFile(stream)
        file.push(msg.getparam("boundary"))
        while file.next():
            submsg = mimetools.Message(file)
                data = StringIO.StringIO()
                mimetools.decode(file, data, submsg.getencoding())
            except ValueError:
                continue
            if submsg.gettype() == mimetype:
                break
        file.pop()
    return data.getvalue()
```

12.11 rfc822 — Parse RFC 2822 mail headers

Deprecated since release 2.3. The email package should be used in preference to the rfc822 module. This module is present only to maintain backward compatibility.

This module defines a class, Message, which represents an "email message" as defined by the Internet standard RFC 2822. Such messages consist of a collection of message headers, and a message body. This module also defines a helper class AddressList for parsing RFC 2822 addresses. Please refer to the RFC for information on the specific syntax of RFC 2822 messages.

The mailbox module provides classes to read mailboxes produced by various end-user mail programs.

```
class Message(file[, seekable])
```

A Message instance is instantiated with an input object as parameter. Message relies only on the input object having a readline() method; in particular, ordinary file objects qualify. Instantiation reads headers from the input object up to a delimiter line (normally a blank line) and stores them in the instance. The message body, following the headers, is not consumed.

This class can work with any input object that supports a readline() method. If the input object has seek and tell capability, the rewindbody() method will work; also, illegal lines will be pushed back onto the input stream. If the input object lacks seek but has an unread() method that can push back a line of input, Message will use that to push back illegal lines. Thus this class can be used to parse messages coming from a buffered stream.

The optional *seekable* argument is provided as a workaround for certain stdio libraries in which tell() discards buffered data before discovering that the lseek() system call doesn't work. For maximum

⁶This module originally conformed to RFC 822, hence the name. Since then, RFC 2822 has been released as an update to RFC 822. This module should be considered RFC 2822-conformant, especially in cases where the syntax or semantics have changed since RFC 822.

portability, you should set the seekable argument to zero to prevent that initial tell() when passing in an unseekable object such as a file object created from a socket object.

Input lines as read from the file may either be terminated by CR-LF or by a single linefeed; a terminating CR-LF is replaced by a single linefeed before the line is stored.

All header matching is done independent of upper or lower case; e.g. m['From'], m['from'] and m['FROM'] all yield the same result.

class AddressList(field)

You may instantiate the AddressList helper class using a single string parameter, a comma-separated list of RFC 2822 addresses to be parsed. (The parameter None yields an empty list.)

quote(str)

Return a new string with backslashes in *str* replaced by two backslashes and double quotes replaced by backslash-double quote.

unquote(str)

Return a new string which is an *unquoted* version of *str*. If *str* ends and begins with double quotes, they are stripped off. Likewise if *str* ends and begins with angle brackets, they are stripped off.

parseaddr (address)

Parse *address*, which should be the value of some address-containing field such as To: or Cc:, into its constituent "realname" and "email address" parts. Returns a tuple of that information, unless the parse fails, in which case a 2-tuple (None, None) is returned.

dump_address_pair(pair)

The inverse of parseaddr(), this takes a 2-tuple of the form (*realname*, *email_address*) and returns the string value suitable for a To: or Cc: header. If the first element of *pair* is false, then the second element is returned unmodified.

parsedate(date)

Attempts to parse a date according to the rules in RFC 2822. however, some mailers don't follow that format as specified, so parsedate() tries to guess correctly in such cases. *date* is a string containing an RFC 2822 date, such as 'Mon, 20 Nov 1995 19:12:08 -0500'. If it succeeds in parsing the date, parsedate() returns a 9-tuple that can be passed directly to time.mktime(); otherwise None will be returned. Note that fields 6, 7, and 8 of the result tuple are not usable.

parsedate_tz(date)

Performs the same function as parsedate(), but returns either None or a 10-tuple; the first 9 elements make up a tuple that can be passed directly to time.mktime(), and the tenth is the offset of the date's timezone from UTC (which is the offscial term for Greenwich Mean Time). (Note that the sign of the timezone offset is the opposite of the sign of the time.timezone variable for the same timezone; the latter variable follows the POSIX standard while this module follows RFC 2822.) If the input string has no timezone, the last element of the tuple returned is None. Note that fields 6, 7, and 8 of the result tuple are not usable.

mktime_tz(tuple)

Turn a 10-tuple as returned by parsedate_tz() into a UTC timestamp. If the timezone item in the tuple is None, assume local time. Minor deficiency: this first interprets the first 8 elements as a local time and then compensates for the timezone difference; this may yield a slight error around daylight savings time switch dates. Not enough to worry about for common use.

See Also:

Module email (section 12.2):

Comprehensive email handling package; supersedes the rfc822 module.

Module mailbox (section 12.4):

Classes to read various mailbox formats produced by end-user mail programs.

Module mimetools (section 12.6):

 $Subclass\ of\ \verb"rfc822.Message" that\ handles\ MIME\ encoded\ messages.$

12.11.1 Message Objects

A Message instance has the following methods:

rewindbody()

Seek to the start of the message body. This only works if the file object is seekable.

isheader(line)

Returns a line's canonicalized fieldname (the dictionary key that will be used to index it) if the line is a legal RFC 2822 header; otherwise returns None (implying that parsing should stop here and the line be pushed back on the input stream). It is sometimes useful to override this method in a subclass.

islast(line)

Return true if the given line is a delimiter on which Message should stop. The delimiter line is consumed, and the file object's read location positioned immediately after it. By default this method just checks that the line is blank, but you can override it in a subclass.

iscomment(line)

Return True if the given line should be ignored entirely, just skipped. By default this is a stub that always returns False, but you can override it in a subclass.

getallmatchingheaders(name)

Return a list of lines consisting of all headers matching *name*, if any. Each physical line, whether it is a continuation line or not, is a separate list item. Return the empty list if no header matches *name*.

getfirstmatchingheader(name)

Return a list of lines comprising the first header matching *name*, and its continuation line(s), if any. Return None if there is no header matching *name*.

getrawheader(name)

Return a single string consisting of the text after the colon in the first header matching *name*. This includes leading whitespace, the trailing linefeed, and internal linefeeds and whitespace if there any continuation line(s) were present. Return None if there is no header matching *name*.

getheader(name[, default])

Like getrawheader(name), but strip leading and trailing whitespace. Internal whitespace is not stripped. The optional *default* argument can be used to specify a different default to be returned when there is no header matching *name*.

get(name[, default])

An alias for getheader (), to make the interface more compatible with regular dictionaries.

getaddr(name)

Return a pair (*full name*, *email address*) parsed from the string returned by getheader(*name*). If no header matching *name* exists, return (None, None); otherwise both the full name and the address are (possibly empty) strings.

Example: If m's first From: header contains the string 'jack@cwi.nl (Jack Jansen)', then m.getaddr('From') will yield the pair ('Jack Jansen', 'jack@cwi.nl'). If the header contained 'Jack Jansen <jack@cwi.nl>' instead, it would yield the exact same result.

getaddrlist(name)

This is similar to <code>getaddr(list)</code>, but parses a header containing a list of email addresses (e.g. a To: header) and returns a list of (*full name*, *email address*) pairs (even if there was only one address in the header). If there is no header matching *name*, return an empty list.

If multiple headers exist that match the named header (e.g. if there are several Cc: headers), all are parsed for addresses. Any continuation lines the named headers contain are also parsed.

getdate(name)

Retrieve a header using getheader() and parse it into a 9-tuple compatible with time.mktime(); note that fields 6, 7, and 8 are not usable. If there is no header matching *name*, or it is unparsable, return None.

Date parsing appears to be a black art, and not all mailers adhere to the standard. While it has been tested and found correct on a large collection of email from many sources, it is still possible that this function may occasionally yield an incorrect result.

getdate_tz(name)

Retrieve a header using getheader() and parse it into a 10-tuple; the first 9 elements will make a tuple compatible with time.mktime(), and the 10th is a number giving the offset of the date's timezone from UTC. Note that fields 6, 7, and 8 are not usable. Similarly to getdate(), if there is no header matching name, or it is unparsable, return None.

Message instances also support a limited mapping interface. In particular: m[name] is like m.getheader(name) but raises KeyError if there is no matching header; and len(m), m.get(name], default), $m.has_key(name)$, m.keys(), m.values() m.items(), and m.setdefault(name], default)) act as expected, with the one difference that setdefault() uses an empty string as the default value. Message instances also support the mapping writable interface m[name] = value and del m[name]. Message objects do not support the clear(), copy(), popitem(), or update() methods of the mapping interface. (Support for get()) and setdefault() was only added in Python 2.2.)

Finally, Message instances have some public instance variables:

headers

A list containing the entire set of header lines, in the order in which they were read (except that setitem calls may disturb this order). Each line contains a trailing newline. The blank line terminating the headers is not contained in the list.

fp

The file or file-like object passed at instantiation time. This can be used to read the message content.

unixfrom

The UNIX 'From' line, if the message had one, or an empty string. This is needed to regenerate the message in some contexts, such as an mbox-style mailbox file.

12.11.2 AddressList Objects

An AddressList instance has the following methods:

__len__()

Return the number of addresses in the address list.

__str__()

Return a canonicalized string representation of the address list. Addresses are rendered in "name" ;host@domain; form, comma-separated.

__**add**__(*alist*)

Return a new AddressList instance that contains all addresses in both AddressList operands, with duplicates removed (set union).

__iadd__(alist)

In-place version of __add__(); turns this AddressList instance into the union of itself and the right-hand instance, *alist*.

__**sub**__(*alist*)

Return a new AddressList instance that contains every address in the left-hand AddressList operand that is not present in the right-hand address operand (set difference).

__isub__(alist)

In-place version of __sub__(), removing addresses in this list which are also in *alist*.

Finally, AddressList instances have one public instance variable:

addresslist

A list of tuple string pairs, one per address. In each member, the first is the canonicalized name part, the second is the actual route-address ('@'-separated username-host.domain pair).

12.12 base64 — RFC 3548: Base16, Base32, Base64 Data Encodings

This module provides data encoding and decoding as specified in RFC 3548. This standard defines the Base16, Base32, and Base64 algorithms for encoding and decoding arbitrary binary strings into text strings that can be safely sent by email, used as parts of URLs, or included as part of an HTTP POST request. The encoding algorithm is not the same as the **uuencode** program.

There are two interfaces provided by this module. The modern interface supports encoding and decoding string objects using all three alphabets. The legacy interface provides for encoding and decoding to and from file-like objects as well as strings, but only using the Base64 standard alphabet.

The modern interface provides:

b64encode(s[, altchars])

Encode a string use Base64.

s is the string to encode. Optional altchars must be a string of at least length 2 (additional characters are ignored) which specifies an alternative alphabet for the + and / characters. This allows an application to e.g. generally (Idn) 2350(stafibless) (Base(o)] TJ98.438J 0 -11.955 Td[(alphabem)-250(is)-235(ubet.)].

b16decode(s[, casefold])

Decode a Base16 encoded string.

s is the string to decode. Optional *casefold* is a flag specifying whether a lowercase alphabet is acceptable as input. For security purposes, the default is False.

The decoded string is returned. A TypeError is raised if *s* were incorrectly padded or if there are non-alphabet characters present in the string.

The legacy interface:

decode(input, output)

Decode the contents of the *input* file and write the resulting binary data to the *output* file. *input* and *output* must either be file objects or objects that mimic the file object interface. *input* will be read until *input*.read() returns an empty string.

decodestring(s)

Decode the string s, which must contain one or more lines of base64 encoded data, and return a string containing the resulting binary data.

encode(input, output)

Encode the contents of the *input* file and write the resulting base64 encoded data to the *output* file. *input* and *output* must either be file objects or objects that mimic the file object interface. *input* will be read until input.read() returns an empty string. encode() returns the encoded data plus a trailing newline character ('\n').

encodestring(s)

Encode the string s, which can contain arbitrary binary data, and return a string containing one or more lines of base64-encoded data. encodestring() returns a string containing one or more lines of base64-encoded data always including an extra trailing newline ('\n').

See Also:

Module binascii (section 12.13):

Support module containing ASCII-to-binary and binary-to-ASCII conversions.

RFC 1521, "MIME (Multipurpose Internet Mail Extensions) Part One: Mechanisms for Specifying and Describing the Format of Internet Section 5.2, "Base64 Content-Transfer-Encoding," provides the definition of the base64 encoding.

12.13 binascii — Convert between binary and ASCII

The binascii module contains a number of methods to convert between binary and various ASCII-encoded binary representations. Normally, you will not use these functions directly but use wrapper modules like uu or binhex instead, this module solely exists because bit-manipulation of large amounts of data is slow in Python.

The binascii module defines the following functions:

a2b_uu(string)

Convert a single line of uuencoded data back to binary and return the binary data. Lines normally contain 45 (binary) bytes, except for the last line. Line data may be followed by whitespace.

b2a_uu(data)

Convert binary data to a line of ASCII characters, the return value is the converted line, including a newline char. The length of *data* should be at most 45.

a2b_base64(string)

Convert a block of base64 data back to binary and return the binary data. More than one line may be passed at a time.

b2a_base64(data)

Convert binary data to a line of ASCII characters in base64 coding. The return value is the converted line, including a newline char. The length of *data* should be at most 57 to adhere to the base64 standard.

a2b_qp(string, header)

Convert a block of quoted-printable data back to binary and return the binary data. More than one line may

be passed at a time. If the optional argument *header* is present and true, underscores will be decoded as spaces.

b2a_**qp**(data[, quotetabs, istext, header])

Convert binary data to a line(s) of ASCII characters in quoted-printable encoding. The return value is the converted line(s). If the optional argument *quotetabs* is present and true, all tabs and spaces will be encoded. If the optional argument *istext* is present and true, newlines are not encoded but trailing whitespace will be encoded. If the optional argument *header* is present and true, spaces will be encoded as underscores per RFC1522. If the optional argument *header* is present and false, newline characters will be encoded as well; otherwise linefeed conversion might corrupt the binary data stream.

a2b_hqx(string)

Convert binhex4 formatted ASCII data to binary, without doing RLE-decompression. The string should contain a complete number of binary bytes, or (in case of the last portion of the binhex4 data) have the remaining bits zero.

rledecode_hqx(data)

Perform RLE-decompression on the data, as per the binhex4 standard. The algorithm uses 0x90 after a byte as a repeat indicator, followed by a count. A count of 0 specifies a byte value of 0x90. The routine returns the decompressed data, unless data input data ends in an orphaned repeat indicator, in which case the Incomplete exception is raised.

rlecode_hqx(data)

Perform binhex4 style RLE-compression on data and return the result.

b2a_hgx(data)

Perform hexbin4 binary-to-ASCII translation and return the resulting string. The argument should already be RLE-coded, and have a length divisible by 3 (except possibly the last fragment).

crc_hqx(data, crc)

Compute the binhex4 crc value of *data*, starting with an initial *crc* and returning the result.

crc32(data[, crc])

Compute CRC-32, the 32-bit checksum of data, starting with an initial crc. This is consistent with the ZIP file checksum. Since the algorithm is designed for use as a checksum algorithm, it is not suitable for use as a general hash algorithm. Use as follows:

```
print binascii.crc32("hello world")
# Or, in two pieces:
crc = binascii.crc32("hello")
crc = binascii.crc32(" world", crc)
print crc
```

b2a_hex(data)

hexlify(data)

Return the hexadecimal representation of the binary *data*. Every byte of *data* is converted into the corresponding 2-digit hex representation. The resulting string is therefore twice as long as the length of *data*.

a2b_hex(hexstr)

unhexlify(hexstr)

Return the binary data represented by the hexadecimal string *hexstr*. This function is the inverse of b2a_hex(). *hexstr* must contain an even number of hexadecimal digits (which can be upper or lower case), otherwise a TypeError is raised.

exception Error

Exception raised on errors. These are usually programming errors.

exception Incomplete

Exception raised on incomplete data. These are usually not programming errors, but may be handled by reading a little more data and trying again.

See Also:

```
Module base64 (section 12.12):
```

Support for base64 encoding used in MIME email messages.

Module binhex (section 12.14):

Support for the binhex format used on the Macintosh.

Module uu (section 12.16):

Support for UU encoding used on UNIX.

Module quopri (section 12.15):

Support for quoted-printable encoding used in MIME email messages.

12.14 binhex — Encode and decode binhex4 files

This module encodes and decodes files in binhex4 format, a format allowing representation of Macintosh files in ASCII. On the Macintosh, both forks of a file and the finder information are encoded (or decoded), on other platforms only the data fork is handled.

The binhex module defines the following functions:

binhex(input, output)

Convert a binary file with filename *input* to binhex file *output*. The *output* parameter can either be a filename or a file-like object (any object supporting a write() and close() method).

hexbin(input[, output])

Decode a binhex file *input*. *input* may be a filename or a file-like object supporting read() and close() methods. The resulting file is written to a file named *output*, unless the argument is omitted in which case the output filename is read from the binhex file.

The following exception is also defined:

exception Error

Exception raised when something can't be encoded using the binhex format (for example, a filename is too long to fit in the filename field), or when input is not properly encoded binhex data.

See Also:

Module binascii (section 12.13):

Support module containing ASCII-to-binary and binary-to-ASCII conversions.

12.14.1 Notes

There is an alternative, more powerful interface to the coder and decoder, see the source for details.

If you code or decode textfiles on non-Macintosh platforms they will still use the Macintosh newline convention (carriage-return as end of line).

As of this writing, hexbin() appears to not work in all cases.

12.15 quopri — Encode and decode MIME quoted-printable data

This module performs quoted-printable transport encoding and decoding, as defined in RFC 1521: "MIME (Multipurpose Internet Mail Extensions) Part One: Mechanisms for Specifying and Describing the Format of Internet Message Bodies". The quoted-printable encoding is designed for data where there are relatively few nonprintable characters; the base64 encoding scheme available via the base64 module is more compact if there are many such characters, as when sending a graphics file.

decode(input, output[,header])

Decode the contents of the *input* file and write the resulting decoded binary data to the *output* file. *input* and *output* must either be file objects or objects that mimic the file object interface. *input* will be read until *input*.readline() returns an empty string. If the optional argument *header* is present and true, underscore will be decoded as space. This is used to decode "Q"-encoded headers as described in RFC

1522: "MIME (Multipurpose Internet Mail Extensions) Part Two: Message Header Extensions for Non-ASCII Text".

encode(input, output, quotetabs)

Encode the contents of the *input* file and write the resulting quoted-printable data to the *output* file. *input* and *output* must either be file objects or objects that mimic the file object interface. *input* will be read until *input*.readline() returns an empty string. *quotetabs* is a flag which controls whether to encode embedded spaces and tabs; when true it encodes such embedded whitespace, and when false it leaves them unencoded. Note that spaces and tabs appearing at the end of lines are always encoded, as per RFC 1521.

decodestring(s[,header])

Like decode(), except that it accepts a source string and returns the corresponding decoded string.

encodestring(s[, quotetabs])

Like encode(), except that it accepts a source string and returns the corresponding encoded string. *quotetabs* is optional (defaulting to 0), and is passed straight through to encode().

See Also:

Module mimify (section 12.9):

General utilities for processing of MIME messages.

Module base64 (section 12.12):

Encode and decode MIME base64 data

12.16 uu — Encode and decode uuencode files

This module encodes and decodes files in uuencode format, allowing arbitrary binary data to be transferred over ASCII-only connections. Wherever a file argument is expected, the methods accept a file-like object. For backwards compatibility, a string containing a pathname is also accepted, and the corresponding file will be opened for reading and writing; the pathname '-' is understood to mean the standard input or output. However, this interface is deprecated; it's better for the caller to open the file itself, and be sure that, when required, the mode is 'rb' or 'wb' on Windows.

This code was contributed by Lance Ellinghouse, and modified by Jack Jansen.

The uu module defines the following functions:

```
encode(in_file, out_file[, name[, mode]])
```

Uuencode file *in_file* into file *out_file*. The uuencoded file will have the header specifying *name* and *mode* as the defaults for the results of decoding the file. The default defaults are taken from *in_file*, or '-' and 0666 respectively.

```
decode(in_file, out_file, mode, quiet]])
```

This call decodes unencoded file *in_file* placing the result on file *out_file*. If *out_file* is a pathname, *mode* is used to set the permission bits if the file must be created. Defaults for *out_file* and *mode* are taken from the unencode header. However, if the file specified in the header already exists, a un. Error is raised.

decode() may print a warning to standard error if the input was produced by an incorrect unencoder and Python could recover from that error. Setting *quiet* to a true value silences this warning.

exception Error()

Subclass of Exception, this can be raised by uu.decode() under various situations, such as described above, but also including a badly formatted header, or truncated input file.

See Also:

Module binascii (section 12.13):

Support module containing ASCII-to-binary and binary-to-ASCII conversions.

12.17 xdrlib — Encode and decode XDR data

The xdrlib module supports the External Data Representation Standard as described in RFC 1014, written by Sun Microsystems, Inc. June 1987. It supports most of the data types described in the RFC.

The xdrlib module defines two classes, one for packing variables into XDR representation, and another for unpacking from XDR representation. There are also two exception classes.

class Packer ()

Packer is the class for packing data into XDR representation. The Packer class is instantiated with no arguments.

class Unpacker (data)

Unpacker is the complementary class which unpacks XDR data values from a string buffer. The input buffer is given as *data*.

See Also:

RFC 1014, "XDR: External Data Representation Standard"

This RFC defined the encoding of data which was XDR at the time this module was originally written. It has apparently been obsoleted by RFC 1832.

RFC 1832, "XDR: External Data Representation Standard"

Newer RFC that provides a revised definition of XDR.

12.17.1 Packer Objects

Packer instances have the following methods:

get_buffer()

Returns the current pack buffer as a string.

reset()

Resets the pack buffer to the empty string.

In general, you can pack any of the most common XDR data types by calling the appropriate pack_type() method. Each method takes a single argument, the value to pack. The following simple data type packing methods are supported: pack_uint(), pack_int(), pack_enum(), pack_bool(), pack_uhyper(), and pack_hyper().

pack_float(value)

Packs the single-precision floating point number value.

pack_double(value)

Packs the double-precision floating point number value.

The following methods support packing strings, bytes, and opaque data:

pack_fstring(n, s)

Packs a fixed length string, s. n is the length of the string but it is not packed into the data buffer. The string is padded with null bytes if necessary to guaranteed 4 byte alignment.

pack_fopaque(n, data)

Packs a fixed length opaque data stream, similarly to pack_fstring().

pack_string(s)

Packs a variable length string, s. The length of the string is first packed as an unsigned integer, then the string data is packed with pack_fstring().

pack_opaque(data)

Packs a variable length opaque data string, similarly to pack_string().

pack_bytes(bytes)

Packs a variable length byte stream, similarly to pack_string().

The following methods support packing arrays and lists:

pack_list(list, pack_item)

Packs a *list* of homogeneous items. This method is useful for lists with an indeterminate size; i.e. the size is not available until the entire list has been walked. For each item in the list, an unsigned integer 1 is packed first, followed by the data value from the list. *pack_item* is the function that is called to pack the individual item. At the end of the list, an unsigned integer 0 is packed.

For example, to pack a list of integers, the code might appear like this:

```
import xdrlib
p = xdrlib.Packer()
p.pack_list([1, 2, 3], p.pack_int)
```

pack_farray(n, array, pack_item)

Packs a fixed length list (array) of homogeneous items. n is the length of the list; it is not packed into the buffer, but a ValueError exception is raised if len(array) is not equal to n. As above, $pack_item$ is the function used to pack each element.

pack_array(list, pack_item)

Packs a variable length *list* of homogeneous items. First, the length of the list is packed as an unsigned integer, then each element is packed as in pack_farray() above.

12.17.2 Unpacker Objects

The Unpacker class offers the following methods:

reset(data)

Resets the string buffer with the given data.

get_position()

Returns the current unpack position in the data buffer.

set_position(position)

Sets the data buffer unpack position to *position*. You should be careful about using get_position() and set_position().

get_buffer()

Returns the current unpack data buffer as a string.

done()

Indicates unpack completion. Raises an Error exception if all of the data has not been unpacked.

In addition, every data type that can be packed with a Packer, can be unpacked with an Unpacker. Unpacking methods are of the form unpack_type(), and take no arguments. They return the unpacked object.

unpack_float()

Unpacks a single-precision floating point number.

unpack_double()

Unpacks a double-precision floating point number, similarly to unpack_float().

In addition, the following methods unpack strings, bytes, and opaque data:

unpack_fstring(n)

Unpacks and returns a fixed length string. *n* is the number of characters expected. Padding with null bytes to guaranteed 4 byte alignment is assumed.

$unpack_fopaque(n)$

Unpacks and returns a fixed length opaque data stream, similarly to unpack_fstring().

unpack_string()

Unpacks and returns a variable length string. The length of the string is first unpacked as an unsigned integer, then the string data is unpacked with unpack_fstring().

unpack_opaque()

Unpacks and returns a variable length opaque data string, similarly to unpack_string().

unpack_bytes()

Unpacks and returns a variable length byte stream, similarly to unpack_string().

The following methods support unpacking arrays and lists:

```
unpack_list(unpack_item)
```

Unpacks and returns a list of homogeneous items. The list is unpacked one element at a time by first unpacking an unsigned integer flag. If the flag is 1, then the item is unpacked and appended to the list. A flag of 0 indicates the end of the list. *unpack_item* is the function that is called to unpack the items.

unpack_farray(n, unpack_item)

Unpacks and returns (as a list) a fixed length array of homogeneous items. n is number of list elements to expect in the buffer. As above, $unpack_item$ is the function used to unpack each element.

```
unpack_array(unpack_item)
```

Unparchomodentous itemsia biestenberhengalektische list is unpacked as

nteger, then each element is unpacked as in unpack

_farray() above.

12.17.3 Exceptions

Exceptions in this module are coded as class instances:

exception Error

The base exception class. Error has a single public data member msg containing the description of the error.

exception ConversionError

Class derived from Error. Contains no additional instance variables.

Here is an example of how you would catch one of these exceptions:

```
import xdrlib
p = xdrlib.Packer()
try:
    p.pack_double(8.01)
except xdrlib.ConversionError, instance:
    print 'packing the double failed:', instance.msg
```

12.18 netrc — netrc file processing

authenticators(host)

Return a 3-tuple (*login*, *account*, *password*) of authenticators for *host*. If the netrc file did not contain an entry for the given host, return the tuple associated with the 'default' entry. If neither matching host nor default entry is available, return None.

```
repr ()
```

Dump the class data as a string in the format of a netrc file. (This discards comments and may reorder the entries.)

Instances of netrc have public instance variables:

hosts

Dictionary mapping host names to (*login*, *account*, *password*) tuples. The 'default' entry, if any, is represented as a pseudo-host by that name.

macros

Dictionary mapping macro names to string lists.

Note: Passwords are limited to a subset of the ASCII character set. Versions of this module prior to 2.3 were extremely limited. Starting with 2.3, all ASCII punctuation is allowed in passwords. However, note that whitespace and non-printable characters are not allowed in passwords. This is a limitation of the way the .netrc file is parsed and may be removed in the future.

12.19 robotparser — Parser for robots.txt

This module provides a single class, RobotFileParser, which answers questions about whether or not a particular user agent can fetch a URL on the Web site that published the 'robots.txt' file. For more details on the structure of 'robots.txt' files, see http://www.robotstxt.org/wc/norobots.html.

class RobotFileParser()

This class provides a set of methods to read, parse and answer questions about a single 'robots.txt' file.

```
set_url(url)
```

Sets the URL referring to a 'robots.txt' file.

read()

Reads the 'robots.txt' URL and feeds it to the parser.

parse(lines)

Parses the lines argument.

```
can_fetch(useragent, url)
```

Returns True if the *useragent* is allowed to fetch the *url* according to the rules contained in the parsed 'robots.txt' file.

mtime(

Returns the time the robots.txt file was last fetched. This is useful for long-running web spiders that need to check for new robots.txt files periodically.

modified(

Sets the time the robots.txt file was last fetched to the current time.

The following example demonstrates basic use of the RobotFileParser class.

```
>>> import robotparser
>>> rp = robotparser.RobotFileParser()
>>> rp.set_url("http://www.musi-cal.com/robots.txt")
>>> rp.read()
>>> rp.can_fetch("*", "http://www.musi-cal.com/cgi-bin/search?city=San+Francisco")
False
>>> rp.can_fetch("*", "http://www.musi-cal.com/")
True
```

12.20 CSV — CSV File Reading and Writing

New in version 2.3.

The so-called CSV (Comma Separated Values) format is the most common import and export format for spreadsheets and databases. There is no "CSV standard", so the format is operationally defined by the many applications which read and write it. The lack of a standard means that subtle differences often exist in the data produced and consumed by different applications. These differences can make it annoying to process CSV files from multiple sources. Still, while the delimiters and quoting characters vary, the overall format is similar enough that it is possible to write a single module which can efficiently manipulate such data, hiding the details of reading and writing the data from the programmer.

The csv module implements classes to read and write tabular data in CSV format. It allows programmers to say, "write this data in the format preferred by Excel," or "read data from this file which was generated by Excel," without knowing the precise details of the CSV format used by Excel. Programmers can also describe the CSV formats understood by other applications or define their own special-purpose CSV formats.

The csv module's reader and writer objects read and write sequences. Programmers can also read and write data in dictionary form using the DictReader and DictWriter classes.

Note: This version of the csv module doesn't support Unicode input. Also, there are currently some issues regarding ASCII NUL characters. Accordingly, all input should generally be printable ASCII to be safe. These restrictions will be removed in the future.

See Also:

PEP 305, "CSV File API"

The Python Enhancement Proposal which proposed this addition to Python.

12.20.1 Module Contents

The csv module defines the following functions:

```
reader(csvfile[, dialect='excel'[, fmtparam]])
```

Return a reader object which will iterate over lines in the given *csvfile*. *csvfile* can be any object which supports the iterator protocol and returns a string each time its next method is called. If *csvfile* is a file object, it must be opened with the 'b' flag on platforms where that makes a difference. An optional *dialect* parameter can be given which is used to define a set of parameters specific to a particular CSV dialect. It may be an instance of a subclass of the Dialect class or one of the strings returned by the list_dialects function. The other optional *fmtparam* keyword arguments can be given to override individual formatting parameters in the current dialect. For more information about the dialect and formatting parameters, see section 12.20.2, "Dialects and Formatting Parameters" for details of these parameters.

All data read are returned as strings. No automatic data type conversion is performed.

```
writer(csvfile[, dialect='excel'[, fmtparam]])
```

Return a writer object responsible for converting the user's data into delimited strings on the given file-like object. <code>csvfile</code> can be any object with a write method. If <code>csvfile</code> is a file object, it must be opened with the 'b' flag on platforms where that makes a difference. An optional <code>dialect</code> parameter can be given which is used to define a set of parameters specific to a particular CSV dialect. It may be an instance of a subclass of the <code>Dialect</code> class or one of the strings returned by the <code>list_dialects</code> function. The other optional <code>fmtparam</code> keyword arguments can be given to override individual formatting parameters in the current dialect. For more information about the dialect and formatting parameters, see section 12.20.2, "Dialects and Formatting Parameters" for details of these parameters. To make it as easy as possible to interface with modules which implement the DB API, the value <code>None</code> is written as the empty string. While this isn't a reversible transformation, it makes it easier to dump SQL NULL data values to CSV files without preprocessing the data returned from a <code>cursor.fetch*()</code> call. All other non-string data are stringified with <code>str()</code> before being written.

register_dialect(name, dialect)

Associate *dialect* with *name*. *dialect* must be a subclass of csv.Dialect. *name* must be a string or Unicode object.

unregister_dialect(name)

Delete the dialect associated with *name* from the dialect registry. An Error is raised if *name* is not a registered dialect name.

get_dialect(name)

Return the dialect associated with *name*. An Error is raised if *name* is not a registered dialect name.

list_dialects()

Return the names of all registered dialects.

The csv module defines the following classes:

Create an object which operates like a regular reader but maps the information read into a dict whose keys are given by the optional *fieldnames* parameter. If the *fieldnames* parameter is omitted, the values in the first row of the *csvfile* will be used as the fieldnames. If the row read has fewer fields than the fieldnames sequence, the value of *restval* will be used as the default value. If the row read has more fields than the fieldnames sequence, the remaining data is added as a sequence keyed by the value of *restkey*. If the row read has fewer fields than the fieldnames sequence, the remaining keys take the value of the optional *restval* parameter. Any other optional or keyword arguments are passed to the underlying reader instance.

Create an object which operates like a regular writer but maps dictionaries onto output rows. The *fieldnames* parameter identifies the order in which values in the dictionary passed to the writerow() method are written to the *csvfile*. The optional *restval* parameter specifies the value to be written if the dictionary is missing a key in *fieldnames*. If the dictionary passed to the writerow() method contains a key not found in *fieldnames*, the optional *extrasaction* parameter indicates what action to take. If it is set to 'raise' a ValueError is raised. If it is set to 'ignore', extra values in the dictionary are ignored. Any other optional or keyword arguments are passed to the underlying writer instance.

Note that unlike the DictReader class, the *fieldnames* parameter of the DictWriter is not optional. Since Python's dict objects are not ordered, there is not enough information available to deduce the order in which the row should be written to the *csvfile*.

class Dialect

The Dialect class is a container class relied on primarily for its attributes, which are used to define the parameters for a specific reader or writer instance.

class Sniffer()

The Sniffer class is used to deduce the format of a CSV file.

The Sniffer class provides a single method:

sniff(sample[,delimiters=None])

Analyze the given *sample* and return a Dialect subclass reflecting the parameters found. If the optional *delimiters* parameter is given, it is interpreted as a string containing possible valid delimiter characters.

has_header(sample)

Analyze the sample text (presumed to be in CSV format) and return True if the first row appears to be a series of column headers.

The csv module defines the following constants:

QUOTE_ALL

Instructs writer objects to quote all fields.

QUOTE_MINIMAL

Instructs writer objects to only quote those fields which contain the current *delimiter* or begin with the current *quotechar*.

QUOTE_NONNUMERIC

Instructs writer objects to quote all non-numeric fields.

QUOTE_NONE

Instructs writer objects to never quote fields. When the current delimiter occurs in output data it is

preceded by the current *escapechar* character. When QUOTE_NONE is in effect, it is an error not to have a single-character *escapechar* defined, even if no data to be written contains the *delimiter* character.

The csv module defines the following exception:

exception Error

Raised by any of the functions when an error is detected.

12.20.2 Dialects and Formatting Parameters

To make it easier to specify the format of input and output records, specific formatting parameters are grouped together into dialects. A dialect is a subclass of the Dialect class having a set of specific methods and a single validate() method. When creating reader or writer objects, the programmer can specify a string or a subclass of the Dialect class as the dialect parameter. In addition to, or instead of, the *dialect* parameter, the programmer can also specify individual formatting parameters, which have the same names as the attributes defined below for the Dialect class.

Dialects support the following attributes:

delimiter

A one-character string used to separate fields. It defaults to ', '.

doublequote

Controls how instances of *quotechar* appearing inside a field should be themselves be quoted. When True, the character is doubled. When False, the *escapechar* must be a one-character string which is used as a prefix to the *quotechar*. It defaults to True.

escapechar

A one-character string used to escape the *delimiter* if *quoting* is set to QUOTE_NONE. It defaults to None.

lineterminator

The string used to terminate lines in the CSV file. It defaults to $'\r\n'$.

quotechar

A one-character string used to quote elements containing the *delimiter* or which start with the *quotechar*. It defaults to '"'.

quoting

Controls when quotes should be generated by the writer. It can take on any of the QUOTE_* constants (see section 12.20.1) and defaults to QUOTE_MINIMAL.

skipinitialspace

When True, whitespace immediately following the delimiter is ignored. The default is False.

12.20.3 Reader Objects

Reader objects (DictReader instances and objects returned by the reader() function) have the following public methods:

next()

Return the next row of the reader's iterable object as a list, parsed according to the current dialect.

12.20.4 Writer Objects

Writer objects (DictWriter instances and objects returned by the writer() function) have the following public methods. A *row* must be a sequence of strings or numbers for Writer objects and a dictionary mapping fieldnames to strings or numbers (by passing them through str() first) for DictWriter objects. Note that complex numbers are written out surrounded by parens. This may cause some problems for other programs which read CSV files (assuming they support complex numbers at all).

writerow(row)

Write the *row* parameter to the writer's file object, formatted according to the current dialect.

```
writerows(rows)
```

Write all the *rows* parameters (a list of *row* objects as described above) to the writer's file object, formatted according to the current dialect.

12.20.5 Examples

The "Hello, world" of csv reading is

```
import csv
reader = csv.reader(open("some.csv", "rb"))
for row in reader:
    print row
```

To print just the first and last columns of each row try

```
import csv
reader = csv.reader(open("some.csv", "rb"))
for row in reader:
    print row[0], row[-1]
```

The corresponding simplest possible writing example is

```
import csv
writer = csv.writer(open("some.csv", "wb"))
for row in someiterable:
    writer.writerow(row)
```

Structured Markup Processing Tools

Python supports a variety of modules to work with various forms of structured data markup. This includes modules to work with the Standard Generalized Markup Language (SGML) and the Hypertext Markup Language (HTML), and several interfaces for working with the Extensible Markup Language (XML).

It is important to note that modules in the xml package require that there be at least one SAX-compliant XML parser available. Starting with Python 2.3, the Expat parser is included with Python, so the xml.parsers.expat module will always be available. You may still want to be aware of the PyXML add-on package; that package provides an extended set of XML libraries for Python.

The documentation for the xml.dom and xml.sax packages are the definition of the Python bindings for the DOM and SAX interfaces.

HTMLParser	A simple parser that can handle HTML and XHTML.
sgmllib	Only as much of an SGML parser as needed to parse HTML.
htmllib	A parser for HTML documents.
htmlentitydefs	Definitions of HTML general entities.
xml.parsers.expat	An interface to the Expat non-validating XML parser.
xml.dom	Document Object Model API for Python.
xml.dom.minidom	Lightweight Document Object Model (DOM) implementation.
xml.dom.pulldom	Support for building partial DOM trees from SAX events.
xml.sax	Package containing SAX2 base classes and convenience functions.
xml.sax.handler	Base classes for SAX event handlers.
xml.sax.saxutils	Convenience functions and classes for use with SAX.
xml.sax.xmlreader	Interface which SAX-compliant XML parsers must implement.
xmllib	A parser for XML documents.

See Also:

Python/XML Libraries
(http://pyxml.sourceforge.net/)

Home page for the PyXML package, containing an extension of xml package bundled with Python.

13.1 HTMLParser — Simple HTML and XHTML parser

New in version 2.2.

This module defines a class HTMLParser which serves as the basis for parsing text files formatted in HTML (HyperText Mark-up Language) and XHTML. Unlike the parser in htmllib, this parser is not based on the SGML parser in sgmllib.

class HTMLParser()

The HTMLParser class is instantiated without arguments.

An HTMLParser instance is fed HTML data and calls handler functions when tags begin and end. The HTMLParser class is meant to be overridden by the user to provide a desired behavior.

Unlike the parser in htmllib, this parser does not check that end tags match start tags or call the end-tag handler for elements which are closed implicitly by closing an outer element.

An exception is defined as well:

exception HTMLParseError

Exception raised by the HTMLParser class when it encounters an error while parsing. This exception provides three attributes: msg is a brief message explaining the error, lineno is the number of the line on which the broken construct was detected, and offset is the number of characters into the line at which the construct starts.

HTMLParser instances have the following methods:

reset(

Reset the instance. Loses all unprocessed data. This is called implicitly at instantiation time.

feed(data)

Feed some text to the parser. It is processed insofar as it consists of complete elements; incomplete data is buffered until more data is fed or close() is called.

close()

Force processing of all buffered data as if it were followed by an end-of-file mark. This method may be redefined by a derived class to define additional processing at the end of the input, but the redefined version should always call the HTMLParser base class method close().

getpos()

Return current line number and offset.

get_starttag_text()

Return the text of the most recently opened start tag. This should not normally be needed for structured processing, but may be useful in dealing with HTML "as deployed" or for re-generating input with minimal changes (whitespace between attributes can be preserved, etc.).

handle_starttag(tag, attrs)

This method is called to handle the start of a tag. It is intended to be overridden by a derived class; the base class implementation does nothing.

The *tag* argument is the name of the tag converted to lower case. The *attrs* argument is a list of (*name*, *value*) pairs containing the attributes found inside the tag's <> brackets. The *name* will be translated to lower case and double quotes and backslashes in the *value* have been interpreted. For instance, for the tag , this method would be called as 'handle_starttag('a', [('href', 'http://www.cwi.nl/')])'.

handle_startendtag(tag, attrs)

Similar to handle_starttag(), but called when the parser encounters an XHTML-style empty tag (<a . . . />). This method may be overridden by subclasses which require this particular lexical information; the default implementation simple calls handle_starttag() and handle_endtag().

handle_endtag(tag)

This method is called to handle the end tag of an element. It is intended to be overridden by a derived class; the base class implementation does nothing. The *tag* argument is the name of the tag converted to lower case.

handle_data(data)

This method is called to process arbitrary data. It is intended to be overridden by a derived class; the base class implementation does nothing.

handle_charref(name)

This method is called to process a character reference of the form '&#ref'. It is intended to be overridden by a derived class; the base class implementation does nothing.

handle_entityref(name)

This method is called to process a general entity reference of the form '&name;' where name is an general entity reference. It is intended to be overridden by a derived class; the base class implementation does nothing.

handle_comment(data)

This method is called when a comment is encountered. The *comment* argument is a string containing the text between the '--' and '--' delimiters, but not the delimiters themselves. For example, the comment

'<!--text-->' will cause this method to be called with the argument 'text'. It is intended to be overridden by a derived class; the base class implementation does nothing.

handle_decl(decl)

Method called when an SGML declaration is read by the parser. The *decl* parameter will be the entire contents of the declaration inside the <!...> markup.It is intended to be overridden by a derived class; the base class implementation does nothing.

handle_pi(data)

Method called when a processing instruction is encountered. The *data* parameter will contain the entire processing instruction. For example, for the processing instruction <?proc color='red'>, this method would be called as handle_pi("proc color='red'"). It is intended to be overridden by a derived class; the base class implementation does nothing.

Note: The HTMLParser class uses the SGML syntactic rules for processing instructions. An XHTML processing instruction using the trailing '?' will cause the '?' to be included in *data*.

13.1.1 Example HTML Parser Application

As a basic example, below is a very basic HTML parser that uses the HTMLParser class to print out tags as they are encountered:

```
from HTMLParser import HTMLParser

class MyHTMLParser(HTMLParser):

    def handle_starttag(self, tag, attrs):
        print "Encountered the beginning of a %s tag" % tag

def handle_endtag(self, tag):
        print "Encountered the end of a %s tag" % tag
```

13.2 sgmllib — Simple SGML parser

This module defines a class SGMLParser which serves as the basis for parsing text files formatted in SGML (Standard Generalized Mark-up Language). In fact, it does not provide a full SGML parser — it only parses SGML insofar as it is used by HTML, and the module only exists as a base for the htmllib module. Another HTML parser which supports XHTML and offers a somewhat different interface is available in the HTMLParser module.

class SGMLParser()

The SGMLParser class is instantiated without arguments. The parser is hardcoded to recognize the following constructs:

- •Opening and closing tags of the form '<tag attr="value" ...>' and '</tag>', respectively.
- •Numeric character references of the form '&#name;'.
- •Entity references of the form '&name;'.
- •SGML comments of the form '<!--text-->'. Note that spaces, tabs, and newlines are allowed between the trailing '>' and the immediately preceding '--'.

A single exception is defined as well:

exception SGMLParseError

Exception raised by the SGMLParser class when it encounters an error while parsing. New in version 2.1.

SGMLParser instances have the following methods:

reset()

Reset the instance. Loses all unprocessed data. This is called implicitly at instantiation time.

setnomoretags()

Stop processing tags. Treat all following input as literal input (CDATA). (This is only provided so the HTML tag <PLAINTEXT> can be implemented.)

setliteral()

Enter literal mode (CDATA mode).

feed(data)

Feed some text to the parser. It is processed insofar as it consists of complete elements; incomplete data is buffered until more data is fed or close() is called.

close()

Force processing of all buffered data as if it were followed by an end-of-file mark. This method may be redefined by a derived class to define additional processing at the end of the input, but the redefined version should always call close().

get_starttag_text()

Return the text of the most recently opened start tag. This should not normally be needed for structured processing, but may be useful in dealing with HTML "as deployed" or for re-generating input with minimal changes (whitespace between attributes can be preserved, etc.).

handle_starttag(tag, method, attributes)

This method is called to handle start tags for which either a <code>start_tag()</code> or <code>do_tag()</code> method has been defined. The <code>tag</code> argument is the name of the tag converted to lower case, and the <code>method</code> argument is the bound method which should be used to support semantic interpretation of the start tag. The <code>attributes</code> argument is a list of <code>(name, value)</code> pairs containing the attributes found inside the tag's <code><></code> brackets. The <code>name</code> has been translated to lower case and double quotes and backslashes in the <code>value</code> have been interpreted. For instance, for the tag <code>, this method would be called as 'unknown_starttag('a', [('href', 'http://www.cwi.nl/')])'. The base implementation simply calls <code>method</code> with <code>attributes</code> as the only argument.</code>

handle_endtag(tag, method)

This method is called to handle endtags for which an end_tag() method has been defined. The tag argument is the name of the tag converted to lower case, and the method argument is the bound method which should be used to support semantic interpretation of the end tag. If no end_tag() method is defined for the closing element, this handler is not called. The base implementation simply calls method.

handle_data(data)

This method is called to process arbitrary data. It is intended to be overridden by a derived class; the base class implementation does nothing.

handle_charref(ref)

This method is called to process a character reference of the form '&#ref;'. In the base implementation, ref must be a decimal number in the range 0-255. It translates the character to ASCII and calls the method handle_data() with the character as argument. If ref is invalid or out of range, the method unknown_charref(ref) is called to handle the error. A subclass must override this method to provide support for named character entities.

handle_entityref(ref)

This method is called to process a general entity reference of the form '&ref;' where ref is an general entity reference. It looks for ref in the instance (or class) variable entitydefs which should be a mapping from entity names to corresponding translations. If a translation is found, it calls the method handle_data() with the translation; otherwise, it calls the method unknown_entityref(ref). The default entitydefs defines translations for & &apos, > < and "

handle_comment(comment)

This method is called when a comment is encountered. The *comment* argument is a string containing the text between the '<!--' and '-->' delimiters, but not the delimiters themselves. For example, the comment '<!--text-->' will cause this method to be called with the argument 'text'. The default method does

nothing.

handle_decl(data)

Method called when an SGML declaration is read by the parser. In practice, the DOCTYPE declaration is the only thing observed in HTML, but the parser does not discriminate among different (or broken) declarations. Internal subsets in a DOCTYPE declaration are not supported. The *data* parameter will be the entire contents of the declaration inside the <!...> markup. The default implementation does nothing.

report_unbalanced(tag)

This method is called when an end tag is found which does not correspond to any open element.

unknown_starttag(tag, attributes)

This method is called to process an unknown start tag. It is intended to be overridden by a derived class; the base class implementation does nothing.

unknown_endtag(tag)

This method is called to process an unknown end tag. It is intended to be overridden by a derived class; the base class implementation does nothing.

unknown_charref(ref)

This method is called to process unresolvable numeric character references. Refer to handle_charref() to determine what is handled by default. It is intended to be overridden by a derived class; the base class implementation does nothing.

unknown_entityref(ref)

This method is called to process an unknown entity reference. It is intended to be overridden by a derived class; the base class implementation does nothing.

Apart from overriding or extending the methods listed above, derived classes may also define methods of the following form to define processing of specific tags. Tag names in the input stream are case independent; the *tag* occurring in method names must be in lower case:

start_tag(attributes)

This method is called to process an opening tag *tag*. It has preference over do_*tag*(). The *attributes* argument has the same meaning as described for handle_starttag() above.

do_tag (attributes)

This method is called to process an opening tag *tag* that does not come with a matching closing tag. The *attributes* argument has the same meaning as described for handle_starttag() above.

end_tag()

This method is called to process a closing tag tag.

Note that the parser maintains a stack of open elements for which no end tag has been found yet. Only tags processed by $start_tag()$ are pushed on this stack. Definition of an $end_tag()$ method is optional for these tags. For tags processed by $do_tag()$ or by $unknown_tag()$, no $end_tag()$ method must be defined; if defined, it will not be used. If both $start_tag()$ and $do_tag()$ methods exist for a tag, the $start_tag()$ method takes precedence.

13.3 htmllib — A parser for HTML documents

This module defines a class which can serve as a base for parsing text files formatted in the HyperText Mark-up Language (HTML). The class is not directly concerned with I/O — it must be provided with input in string form via a method, and makes calls to methods of a "formatter" object in order to produce output. The HTMLParser class is designed to be used as a base class for other classes in order to add functionality, and allows most of its methods to be extended or overridden. In turn, this class is derived from and extends the SGMLParser class defined in module sgmllib. The HTMLParser implementation supports the HTML 2.0 language as described in RFC 1866. Two implementations of formatter objects are provided in the formatter module; refer to the documentation for that module for information on the formatter interface.

The following is a summary of the interface defined by sgmllib. SGMLParser:

• The interface to feed data to an instance is through the feed() method, which takes a string argument.

This can be called with as little or as much text at a time as desired; 'p.feed(a); p.feed(b)' has the same effect as 'p.feed(a+b)'. When the data contains complete HTML markup constructs, these are processed immediately; incomplete constructs are saved in a buffer. To force processing of all unprocessed data, call the close() method.

For example, to parse the entire contents of a file, use:

```
parser.feed(open('myfile.html').read())
parser.close()
```

• The interface to define semantics for HTML tags is very simple: derive a class and define methods called start_tag(), end_tag(), or do_tag(). The parser will call these at appropriate moments: start_tag or do_tag() is called when an opening tag of the form <tag ...> is encountered; end_tag() is called when a closing tag of the form <tag> is encountered. If an opening tag requires a corresponding closing tag, like <H1> ... </H1>, the class should define the start_tag() method; if a tag requires no closing tag, like <P>, the class should define the do_tag() method.

The module defines a parser class and an exception:

class HTMLParser(formatter)

This is the basic HTML parser class. It supports all entity names required by the XHTML 1.0 Recommendation (http://www.w3.org/TR/xhtml1). It also defines handlers for all HTML 2.0 and many HTML 3.0 and 3.2 elements.

exception HTMLParseError

Exception raised by the HTMLParser class when it encounters an error while parsing. New in version 2.4.

See Also:

Module formatter (section 12.1):

Interface definition for transforming an abstract flow of formatting events into specific output events on writer objects.

Module HTMLParser (section 13.1):

Alternate HTML parser that offers a slightly lower-level view of the input, but is designed to work with XHTML, and does not implement some of the SGML syntax not used in "HTML as deployed" and which isn't legal for XHTML.

Module htmlentitydefs (section 13.4):

Definition of replacement text for XHTML 1.0 entities.

Module sqmllib (section 13.2):

Base class for HTMLParser.

13.3.1 HTMLParser Objects

In addition to tag methods, the HTMLParser class provides some additional methods and instance variables for use within tag methods.

formatter

This is the formatter instance associated with the parser.

nofill

Boolean flag which should be true when whitespace should not be collapsed, or false when it should be. In general, this should only be true when character data is to be treated as "preformatted" text, as within a <PRE> element. The default value is false. This affects the operation of handle_data() and save_end().

anchor_bgn(href, name, type)

This method is called at the start of an anchor region. The arguments correspond to the attributes of the <A> tag with the same names. The default implementation maintains a list of hyperlinks (defined by the

HREF attribute for <A> tags) within the document. The list of hyperlinks is available as the data attribute anchorlist.

anchor_end()

This method is called at the end of an anchor region. The default implementation adds a textual footnote marker using an index into the list of hyperlinks created by anchor_bgn().

handle_image(source, alt[, ismap[, align[, width[, height]]]])

This method is called to handle images. The default implementation simply passes the *alt* value to the handle_data() method.

save_bqn()

Begins saving character data in a buffer instead of sending it to the formatter object. Retrieve the stored data via save_end(). Use of the save_bgn() / save_end() pair may not be nested.

save_end()

Ends buffering character data and returns all data saved since the preceding call to save_bgn(). If the nofill flag is false, whitespace is collapsed to single spaces. A call to this method without a preceding call to save_bgn() will raise a TypeError exception.

13.4 htmlentitydefs — Definitions of HTML general entities

This module defines three dictionaries, name2codepoint, codepoint2name, and entitydefs. entitydefs is used by the html1ib module to provide the entitydefs member of the HTMLParser class. The definition provided here contains all the entities defined by XHTML 1.0 that can be handled using simple textual substitution in the Latin-1 character set (ISO-8859-1).

entitydefs

A dictionary mapping XHTML 1.0 entity definitions to their replacement text in ISO Latin-1.

name2codepoint

A dictionary that maps HTML entity names to the Unicode codepoints. New in version 2.3.

codepoint2name

A dictionary that maps Unicode codepoints to HTML entity names. New in version 2.3.

13.5 xml.parsers.expat — Fast XML parsing using Expat

New in version 2.0.

The xml.parsers.expat module is a Python interface to the Expat non-validating XML parser. The module provides a single extension type, xmlparser, that represents the current state of an XML parser. After an xmlparser object has been created, various attributes of the object can be set to handler functions. When an XML document is then fed to the parser, the handler functions are called for the character data and markup in the XML document.

This module uses the pyexpat module to provide access to the Expat parser. Direct use of the pyexpat module is deprecated.

This module provides one exception and one type object:

exception ExpatError

The exception raised when Expat reports an error. See section 13.5.2, "ExpatError Exceptions," for more information on interpreting Expat errors.

exception error

Alias for ExpatError.

XMLParserType

The type of the return values from the ParserCreate() function.

The xml.parsers.expat module contains two functions:

ErrorString(errno)

Returns an explanatory string for a given error number errno.

ParserCreate([encoding[, namespace_separator]])

Creates and returns a new xmlparser object. *encoding*, if specified, must be a string naming the encoding used by the XML data. Expat doesn't support as many encodings as Python does, and its repertoire of encodings can't be extended; it supports UTF-8, UTF-16, ISO-8859-1 (Latin1), and ASCII. If *encoding* is given it will override the implicit or explicit encoding of the document.

Expat can optionally do XML namespace processing for you, enabled by providing a value for *namespace_separator*. The value must be a one-character string; a ValueError will be raised if the string has an illegal length (None is considered the same as omission). When namespace processing is enabled, element type names and attribute names that belong to a namespace will be expanded. The element name passed to the element handlers StartElementHandler and EndElementHandler will be the concatenation of the namespace URI, the namespace separator character, and the local part of the name. If the namespace separator is a zero byte (chr(0)) then the namespace URI and the local part will be concatenated without any separator.

For example, if *namespace_separator* is set to a space character ('') and the following document is parsed:

```
<?xml version="1.0"?>
<root xmlns = "http://default-namespace.org/"
     xmlns:py = "http://www.python.org/ns/">
     <py:elem1 />
     <elem2 xmlns="" />
     </root>
```

StartElementHandler will receive the following strings for each element:

```
http://default-namespace.org/ root
http://www.python.org/ns/ elem1
elem2
```

See Also:

The Expat XML Parser

(http://www.libexpat.org/)

Home page of the Expat project.

13.5.1 XMLParser Objects

xmlparser objects have the following methods:

```
Parse(data[, isfinal])
```

Parses the contents of the string *data*, calling the appropriate handler functions to process the parsed data. *isfinal* must be true on the final call to this method. *data* can be the empty string at any time.

ParseFile(file)

Parse XML data reading from the object *file*. *file* only needs to provide the read (*nbytes*) method, returning the empty string when there's no more data.

SetBase(base)

Sets the base to be used for resolving relative URIs in system identifiers in declarations. Resolving relative identifiers is left to the application: this value will be passed through as the *base* argument to the ExternalEntityRefHandler, NotationDeclHandler, and UnparsedEntityDeclHandler functions.

GetBase()

Returns a string containing the base set by a previous call to SetBase(), or None if SetBase() hasn't been called.

GetInputContext()

Returns the input data that generated the current event as a string. The data is in the encoding of the entity

which contains the text. When called while an event handler is not active, the return value is None. New in version 2.1.

ExternalEntityParserCreate(context[, encoding])

Create a "child" parser which can be used to parse an external parsed entity referred to by content parsed by the parent parser. The *context* parameter should be the string passed to the ExternalEntityRefHandler() handler function, described below. The child parser is created with the ordered_attributes, returns_unicode and specified_attributes set to the values of this parser.

UseForeignDTD([flag])

Calling this with a true value for *flag* (the default) will cause Expat to call the ExternalEntityRefHandler with None for all arguments to allow an alternate DTD to be loaded. If the document does not contain a document type declaration, the ExternalEntityRefHandler will still be called, but the StartDoctypeDeclHandler and EndDoctypeDeclHandler will not be called.

Passing a false value for flag will cancel a previous call that passed a true value, but otherwise has no effect.

This method can only be called before the Parse() or ParseFile() methods are called; calling it after either of those have been called causes ExpatError to be raised with the code attribute set to errors.XML_ERROR_CANT_CHANGE_FEATURE_ONCE_PARSING.

New in version 2.3.

xmlparser objects have the following attributes:

buffer_size

The size of the buffer used when buffer_text is true. This value cannot be changed at this time. New in version 2.3.

buffer_text

Setting this to true causes the xmlparser object to buffer textual content returned by Expat to avoid multiple calls to the CharacterDataHandler() callback whenever possible. This can improve performance substantially since Expat normally breaks character data into chunks at every line ending. This attribute is false by default, and may be changed at any time. New in version 2.3.

buffer_used

If buffer_text is enabled, the number of bytes stored in the buffer. These bytes represent UTF-8 encoded text. This attribute has no meaningful interpretation when buffer_text is false. New in version 2.3.

ordered_attributes

Setting this attribute to a non-zero integer causes the attributes to be reported as a list rather than a dictionary. The attributes are presented in the order found in the document text. For each attribute, two list entries are presented: the attribute name and the attribute value. (Older versions of this module also used this format.) By default, this attribute is false; it may be changed at any time. New in version 2.1.

returns_unicode

If this attribute is set to a non-zero integer, the handler functions will be passed Unicode strings. If returns_unicode is 0, 8-bit strings containing UTF-8 encoded data will be passed to the handlers. Changed in version 1.6: Can be changed at any time to affect the result type.

specified_attributes

If set to a non-zero integer, the parser will report only those attributes which were specified in the document instance and not those which were derived from attribute declarations. Applications which set this need to be especially careful to use what additional information is available from the declarations as needed to comply with the standards for the behavior of XML processors. By default, this attribute is false; it may be changed at any time. New in version 2.1.

The following attributes contain values relating to the most recent error encountered by an xmlparser object, and will only have correct values once a call to Parse() or ParseFile() has raised a xml.parsers.expat.ExpatError exception.

ErrorByteIndex

Byte index at which an error occurred.

ErrorCode

Numeric code specifying the problem. This value can be passed to the ErrorString() function, or compared to one of the constants defined in the errors object.

ErrorColumnNumber

Column number at which an error occurred.

ErrorLineNumber

Line number at which an error occurred.

The following attributes contain values relating to the current parse location in an xmlparser object. During a callback reporting a parse event they indicate the location of the first of the sequence of characters that generated the event. When called outside of a callback, the position indicated will be just past the last parse event (regardless of whether there was an associated callback). New in version 2.4.

CurrentByteIndex

Current byte index in the parser input.

CurrentColumnNumber

Current column number in the parser input.

CurrentLineNumber

Current line number in the parser input.

Here is the list of handlers that can be set. To set a handler on an xmlparser object o, use o. handlername = func. handlername must be taken from the following list, and func must be a callable object accepting the correct number of arguments. The arguments are all strings, unless otherwise stated.

XmlDeclHandler(version, encoding, standalone)

Called when the XML declaration is parsed. The XML declaration is the (optional) declaration of the applicable version of the XML recommendation, the encoding of the document text, and an optional "standalone" declaration. *version* and *encoding* will be strings of the type dictated by the returns_unicode attribute, and *standalone* will be 1 if the document is declared standalone, 0 if it is declared not to be standalone, or -1 if the standalone clause was omitted. This is only available with Expat version 1.95.0 or newer. New in version 2.1.

${\tt StartDoctypeDeclHandler}(\textit{doctypeName}, \textit{systemId}, \textit{publicId}, \textit{has_internal_subset})$

Called when Expat begins parsing the document type declaration (<!DOCTYPE ...). The *doctypeName* is provided exactly as presented. The *systemId* and *publicId* parameters give the system and public identifiers if specified, or None if omitted. *has_internal_subset* will be true if the document contains and internal document declaration subset. This requires Expat version 1.2 or newer.

EndDoctypeDeclHandler()

Called when Expat is done parsing the document type declaration. This requires Expat version 1.2 or newer.

${\tt ElementDeclHandler} \, (\, name, \, model \,)$

Called once for each element type declaration. *name* is the name of the element type, and *model* is a representation of the content model.

AttlistDeclHandler (elname, attname, type, default, required)

Called for each declared attribute for an element type. If an attribute list declaration declares three attributes, this handler is called three times, once for each attribute. *elname* is the name of the element to which the declaration applies and *attname* is the name of the attribute declared. The attribute type is a string passed as *type*; the possible values are 'CDATA', 'ID', 'IDREF', ... *default* gives the default value for the attribute used when the attribute is not specified by the document instance, or None if there is no default value (#IMPLIED values). If the attribute is required to be given in the document instance, *required* will be true. This requires Expat version 1.95.0 or newer.

StartElementHandler(name, attributes)

Called for the start of every element. *name* is a string containing the element name, and *attributes* is a dictionary mapping attribute names to their values.

${\tt EndElementHandler} \, (\, name \,)$

Called for the end of every element.

ProcessingInstructionHandler(target, data)

Called for every processing instruction.

CharacterDataHandler(data)

Called for character data. This will be called for normal character data, CDATA marked content, and ignorable whitespace. Applications which must distinguish these cases can use the StartCdataSectionHandler, EndCdataSectionHandler, and ElementDeclHandler callbacks to collect the required information.

UnparsedEntityDeclHandler(entityName, base, systemId, publicId, notationName)

Called for unparsed (NDATA) entity declarations. This is only present for version 1.2 of the Expat library; for more recent versions, use EntityDeclHandler instead. (The underlying function in the Expat library has been declared obsolete.)

EntityDeclHandler(entityName, is_parameter_entity, value, base, systemId, publicId, notationName)

Called for all entity declarations. For parameter and internal entities, *value* will be a string giving the declared contents of the entity; this will be None for external entities. The *notationName* parameter will be None for parsed entities, and the name of the notation for unparsed entities. *is_parameter_entity* will be true if the entity is a parameter entity or false for general entities (most applications only need to be concerned with general entities). This is only available starting with version 1.95.0 of the Expat library. New in version 2.1.

NotationDeclHandler(notationName, base, systemId, publicId)

Called for notation declarations. *notationName*, *base*, and *systemId*, and *publicId* are strings if given. If the public identifier is omitted, *publicId* will be None.

StartNamespaceDeclHandler(prefix, uri)

Called when an element contains a namespace declaration. Namespace declarations are processed before the StartElementHandler is called for the element on which declarations are placed.

EndNamespaceDeclHandler(prefix)

Called when the closing tag is reached for an element that contained a namespace declaration. This is called once for each namespace declaration on the element in the reverse of the order for which the StartNamespaceDeclHandler was called to indicate the start of each namespace declaration's scope. Calls to this handler are made after the corresponding EndElementHandler for the end of the element.

CommentHandler(data)

Called for comments. data is the text of the comment, excluding the leading '<!--' and trailing '-->'.

StartCdataSectionHandler()

Called at the start of a CDATA section. This and StartCdataSectionHandler are needed to be able to identify the syntactical start and end for CDATA sections.

EndCdataSectionHandler()

Called at the end of a CDATA section.

DefaultHandler(data)

Called for any characters in the XML document for which no applicable handler has been specified. This means characters that are part of a construct which could be reported, but for which no handler has been supplied.

DefaultHandlerExpand(data)

This is the same as the DefaultHandler, but doesn't inhibit expansion of internal entities. The entity reference will not be passed to the default handler.

NotStandaloneHandler()

Called if the XML document hasn't been declared as being a standalone document. This happens when there is an external subset or a reference to a parameter entity, but the XML declaration does not set standalone to yes in an XML declaration. If this handler returns 0, then the parser will throw an XML_ERROR_NOT_STANDALONE error. If this handler is not set, no exception is raised by the parser for this condition.

ExternalEntityRefHandler(context, base, systemId, publicId)

Called for references to external entities. *base* is the current base, as set by a previous call to SetBase(). The public and system identifiers, *systemId* and *publicId*, are strings if given; if the public identifier is not given, *publicId* will be None. The *context* value is opaque and should only be used as described below.

For external entities to be parsed, this handler must be implemented. It is responsible for creating the sub-parser using <code>ExternalEntityParserCreate(context)</code>, initializing it with the appropriate callbacks, and parsing the entity. This handler should return an integer; if it returns 0, the parser will throw an <code>XML_ERROR_EXTERNAL_ENTITY_HANDLING</code> error, otherwise parsing will continue.

If this handler is not provided, external entities are reported by the DefaultHandler callback, if provided.

13.5.2 ExpatError Exceptions

ExpatError exceptions have a number of interesting attributes:

code

Expat's internal error number for the specific error. This will match one of the constants defined in the errors object from this module. New in version 2.1.

lineno

Line number on which the error was detected. The first line is numbered 1. New in version 2.1.

offset

Character offset into the line where the error occurred. The first column is numbered 0. New in version 2.1.

13.5.3 Example

The following program defines three handlers that just print out their arguments.

```
import xml.parsers.expat
# 3 handler functions
def start_element(name, attrs):
    print 'Start element:', name, attrs
def end_element(name):
    print 'End element:', name
def char_data(data):
    print 'Character data:', repr(data)
p = xml.parsers.expat.ParserCreate()
p.StartElementHandler = start_element
p.EndElementHandler = end_element
p.CharacterDataHandler = char_data
p.Parse("""<?xml version="1.0"?>
<parent id="top"><child1 name="paul">Text goes here</child1>
<child2 name="fred">More text</child2>
</parent>""", 1)
```

The output from this program is:

```
Start element: parent {'id': 'top'}
Start element: child1 {'name': 'paul'}
Character data: 'Text goes here'
End element: child1
Character data: '\n'
Start element: child2 {'name': 'fred'}
Character data: 'More text'
End element: child2
Character data: '\n'
End element: parent
```

13.5.4 Content Model Descriptions

Content modules are described using nested tuples. Each tuple contains four values: the type, the quantifier, the name, and a tuple of children. Children are simply additional content module descriptions.

The values of the first two fields are constants defined in the model object of the xml.parsers.expat module. These constants can be collected in two groups: the model type group and the quantifier group.

The constants in the model type group are:

XML_CTYPE_ANY

The element named by the model name was declared to have a content model of ANY.

XML_CTYPE_CHOICE

The named element allows a choice from a number of options; this is used for content models such as $(A \mid B \mid C)$.

XML_CTYPE_EMPTY

Elements which are declared to be EMPTY have this model type.

XML_CTYPE_MIXED

XML_CTYPE_NAME

XML_CTYPE_SEQ

Models which represent a series of models which follow one after the other are indicated with this model type. This is used for models such as (A, B, C).

The constants in the quantifier group are:

XML_CQUANT_NONE

No modifier is given, so it can appear exactly once, as for A.

XML_CQUANT_OPT

The model is optional: it can appear once or not at all, as for A?.

XML_CQUANT_PLUS

The model must occur one or more times (like A+).

XML_CQUANT_REP

The model must occur zero or more times, as for A*.

13.5.5 Expat error constants

The following constants are provided in the errors object of the xml.parsers.expat module. These constants are useful in interpreting some of the attributes of the ExpatError exception objects raised when an error has occurred.

The errors object has the following attributes:

XML_ERROR_ASYNC_ENTITY

XML_ERROR_ATTRIBUTE_EXTERNAL_ENTITY_REF

An entity reference in an attribute value referred to an external entity instead of an internal entity.

XML_ERROR_BAD_CHAR_REF

A character reference referred to a character which is illegal in XML (for example, character 0, or '�').

XML_ERROR_BINARY_ENTITY_REF

An entity reference referred to an entity which was declared with a notation, so cannot be parsed.

XML_ERROR_DUPLICATE_ATTRIBUTE

An attribute was used more than once in a start tag.

XML_ERROR_INCORRECT_ENCODING

XML_ERROR_INVALID_TOKEN

Raised when an input byte could not properly be assigned to a character; for example, a NUL byte (value 0) in a UTF-8 input stream.

XML_ERROR_JUNK_AFTER_DOC_ELEMENT

Something other than whitespace occurred after the document element.

XML_ERROR_MISPLACED_XML_PI

An XML declaration was found somewhere other than the start of the input data.

XML_ERROR_NO_ELEMENTS

The document contains no elements (XML requires all documents to contain exactly one top-level element)...

XML_ERROR_NO_MEMORY

Expat was not able to allocate memory internally.

XML_ERROR_PARAM_ENTITY_REF

A parameter entity reference was found where it was not allowed.

XML_ERROR_PARTIAL_CHAR

An incomplete character was found in the input.

XML_ERROR_RECURSIVE_ENTITY_REF

An entity reference contained another reference to the same entity; possibly via a different name, and possibly indirectly.

XML_ERROR_SYNTAX

Some unspecified syntax error was encountered.

XML_ERROR_TAG_MISMATCH

An end tag did not match the innermost open start tag.

XML_ERROR_UNCLOSED_TOKEN

Some token (such as a start tag) was not closed before the end of the stream or the next token was encountered.

XML_ERROR_UNDEFINED_ENTITY

A reference was made to a entity which was not defined.

XML_ERROR_UNKNOWN_ENCODING

The document encoding is not supported by Expat.

XML_ERROR_UNCLOSED_CDATA_SECTION

A CDATA marked section was not closed.

XML_ERROR_EXTERNAL_ENTITY_HANDLING

XML_ERROR_NOT_STANDALONE

The parser determined that the document was not "standalone" though it declared itself to be in the XML declaration, and the NotStandaloneHandler was set and returned 0.

XML_ERROR_UNEXPECTED_STATE

XML_ERROR_ENTITY_DECLARED_IN_PE

XML_ERROR_FEATURE_REQUIRES_XML_DTD

An operation was requested that requires DTD support to be compiled in, but Expat was configured without DTD support. This should never be reported by a standard build of the xml.parsers.expat module.

XML_ERROR_CANT_CHANGE_FEATURE_ONCE_PARSING

A behavioral change was requested after parsing started that can only be changed before parsing has started. This is (currently) only raised by UseForeignDTD().

XML_ERROR_UNBOUND_PREFIX

An undeclared prefix was found when namespace processing was enabled.

XML_ERROR_UNDECLARING_PREFIX

The document attempted to remove the namespace declaration associated with a prefix.

XML_ERROR_INCOMPLETE_PE

A parameter entity contained incomplete markup.

XML_ERROR_XML_DECL

The document contained no document element at all.

XML_ERROR_TEXT_DECL

There was an error parsing a text declaration in an external entity.

XML_ERROR_PUBLICID

Characters were found in the public id that are not allowed.

XML_ERROR_SUSPENDED

The requested operation was made on a suspended parser, but isn't allowed. This includes attempts to provide additional input or to stop the parser.

XML_ERROR_NOT_SUSPENDED

An attempt to resume the parser was made when the parser had not been suspended.

XML_ERROR_ABORTED

This should not be reported to Python applications.

XML_ERROR_FINISHED

The requested operation was made on a parser which was finished parsing input, but isn't allowed. This includes attempts to provide additional input or to stop the parser.

XML_ERROR_SUSPEND_PE

13.6 xml.dom — The Document Object Model API

New in version 2.0.

The Document Object Model, or "DOM," is a cross-language API from the World Wide Web Consortium (W3C) for accessing and modifying XML documents. A DOM implementation presents an XML document as a tree structure, or allows client code to build such a structure from scratch. It then gives access to the structure through a set of objects which provided well-known interfaces.

The DOM is extremely useful for random-access applications. SAX only allows you a view of one bit of the document at a time. If you are looking at one SAX element, you have no access to another. If you are looking at a text node, you have no access to a containing element. When you write a SAX application, you need to keep track of your program's position in the document somewhere in your own code. SAX does not do it for you. Also, if you need to look ahead in the XML document, you are just out of luck.

Some applications are simply impossible in an event driven model with no access to a tree. Of course you could build some sort of tree yourself in SAX events, but the DOM allows you to avoid writing that code. The DOM is a standard tree representation for XML data.

The Document Object Model is being defined by the W3C in stages, or "levels" in their terminology. The Python mapping of the API is substantially based on the DOM Level 2 recommendation. The mapping of the Level 3 specification, currently only available in draft form, is being developed by the Python XML Special Interest Group as part of the PyXML package. Refer to the documentation bundled with that package for information on the current state of DOM Level 3 support.

DOM applications typically start by parsing some XML into a DOM. How this is accomplished is not covered at all by DOM Level 1, and Level 2 provides only limited improvements: There is a DOMImplementation object class which provides access to Document creation methods, but no way to access an XML reader/parser/Document builder in an implementation-independent way. There is also no well-defined way to access these methods without an existing Document object. In Python, each DOM implementation will provide a function <code>getDOMImplementation()</code>. DOM Level 3 adds a Load/Store specification, which defines an interface to the reader, but this is not yet available in the Python standard library.

Once you have a DOM document object, you can access the parts of your XML document through its properties and methods. These properties are defined in the DOM specification; this portion of the reference manual describes the interpretation of the specification in Python.

The specification provided by the W3C defines the DOM API for Java, ECMAScript, and OMG IDL. The Python mapping defined here is based in large part on the IDL version of the specification, but strict compliance is not required (though implementations are free to support the strict mapping from IDL). See section 13.6.3, "Conformance," for a detailed discussion of mapping requirements.

See Also:

Document Object Model (DOM) Level 2 Specification

(http://www.w3.org/TR/DOM-Level-2-Core/)

The W3C recommendation upon which the Python DOM API is based.

Document Object Model (DOM) Level 1 Specification

(http://www.w3.org/TR/REC-DOM-Level-1/)

The W3C recommendation for the DOM supported by xml.dom.minidom.

PyXML

(http://pyxml.sourceforge.net)

Users that require a full-featured implementation of DOM should use the PyXML package.

Python Language Mapping Specification

(http://www.omg.org/docs/formal/02-11-05.pdf)

This specifies the mapping from OMG IDL to Python.

13.6.1 Module Contents

The xml.dom contains the following functions:

registerDOMImplementation(name, factory)

Register the *factory* function with the name *name*. The factory function should return an object which implements the DOMImplementation interface. The factory function can return the same object every time, or a new one for each call, as appropriate for the specific implementation (e.g. if that implementation supports some customization).

getDOMImplementation([name[, features]])

Return a suitable DOM implementation. The *name* is either well-known, the module name of a DOM implementation, or None. If it is not None, imports the corresponding module and returns a DOMImplementation object if the import succeeds. If no name is given, and if the environment variable PYTHON_DOM is set, this variable is used to find the implementation.

If name is not given, this examines the available implementations to find one with the required feature set. If no implementation can be found, raise an ImportError. The features list must be a sequence of (*feature*, *version*) pairs which are passed to the hasFeature() method on available DOMImplementation objects.

Some convenience constants are also provided:

EMPTY_NAMESPACE

The value used to indicate that no namespace is associated with a node in the DOM. This is typically found as the namespaceURI of a node, or used as the *namespaceURI* parameter to a namespaces-specific method. New in version 2.2.

XML_NAMESPACE

The namespace URI associated with the reserved prefix xml, as defined by *Namespaces in XML* (section 4). New in version 2.2.

XMLNS_NAMESPACE

The namespace URI for namespace declarations, as defined by *Document Object Model (DOM) Level 2 Core Specification* (section 1.1.8). New in version 2.2.

XHTML_NAMESPACE

The URI of the XHTML namespace as defined by XHTML 1.0: The Extensible HyperText Markup Language (section 3.1.1). New in version 2.2.

In addition, xml.dom contains a base Node class and the DOM exception classes. The Node class provided by this module does not implement any of the methods or attributes defined by the DOM specification; concrete DOM implementations must provide those. The Node class provided as part of this module does provide the constants used for the nodeType attribute on concrete Node objects; they are located within the class rather than at the module level to conform with the DOM specifications.

13.6.2 Objects in the DOM

The definitive documentation for the DOM is the DOM specification from the W3C.

Note that DOM attributes may also be manipulated as nodes instead of as simple strings. It is fairly rare that you must do this, however, so this usage is not yet documented.

Interface	Section	Purpose
DOMImplementation	13.6.2	Interface to the underlying implementation.
Node	13.6.2	Base interface for most objects in a document.
NodeList	13.6.2	Interface for a sequence of nodes.
DocumentType	13.6.2	Information about the declarations needed to process a document.
Document	13.6.2	Object which represents an entire document.
Element	13.6.2	Element nodes in the document hierarchy.
Attr	13.6.2	Attribute value nodes on element nodes.
Comment	13.6.2	Representation of comments in the source document.
Text	13.6.2	Nodes containing textual content from the document.
ProcessingInstruction	13.6.2	Processing instruction representation.

An additional section describes the exceptions defined for working with the DOM in Python.

DOMImplementation Objects

The DOMImplementation interface provides a way for applications to determine the availability of particular features in the DOM they are using. DOM Level 2 added the ability to create new Document and DocumentType objects using the DOMImplementation as well.

hasFeature(feature, version)

Return true if the feature identified by the pair of strings feature and version is implemented.

createDocument(namespaceUri, qualifiedName, doctype)

Return a new Document object (the root of the DOM), with a child Element object having the given namespaceUri and qualifiedName. The doctype must be a DocumentType object created by createDocumentType(), or None. In the Python DOM API, the first two arguments can also be None in order to indicate that no Element child is to be created.

createDocumentType(qualifiedName, publicId, systemId)

Return a new DocumentType object that encapsulates the given *qualifiedName*, *publicId*, and *systemId* strings, representing the information contained in an XML document type declaration.

Node Objects

All of the components of an XML document are subclasses of Node.

nodeType

An integer representing the node type. Symbolic constants for the types are on the Node object: ELEMENT_NODE, ATTRIBUTE_NODE, TEXT_NODE, CDATA_SECTION_NODE, ENTITY_NODE, PROCESSING_INSTRUCTION_NODE, COMMENT_NODE, DOCUMENT_NODE, DOCUMENT_TYPE_NODE, NOTATION_NODE. This is a read-only attribute.

parentNode

The parent of the current node, or None for the document node. The value is always a Node object or None. For Element nodes, this will be the parent element, except for the root element, in which case it will be the Document object. For Attr nodes, this is always None. This is a read-only attribute.

attributes

A NamedNodeMap of attribute objects. Only elements have actual values for this; others provide None for this attribute. This is a read-only attribute.

previousSibling

The node that immediately precedes this one with the same parent. For instance the element with an end-tag that comes just before the *self* element's start-tag. Of course, XML documents are made up of more than just elements so the previous sibling could be text, a comment, or something else. If this node is the first child of the parent, this attribute will be None. This is a read-only attribute.

nextSibling

The node that immediately follows this one with the same parent. See also previousSibling. If this is the last child of the parent, this attribute will be None. This is a read-only attribute.

childNodes

A list of nodes contained within this node. This is a read-only attribute.

firstChild

The first child of the node, if there are any, or None. This is a read-only attribute.

lastChild

The last child of the node, if there are any, or None. This is a read-only attribute.

localName

The part of the tagName following the colon if there is one, else the entire tagName. The value is a string.

prefix

The part of the tagName preceding the colon if there is one, else the empty string. The value is a string, or None

namespaceURI

The namespace associated with the element name. This will be a string or None. This is a read-only attribute.

nodeName

This has a different meaning for each node type; see the DOM specification for details. You can always get the information you would get here from another property such as the tagName property for elements or the name property for attributes. For all node types, the value of this attribute will be either a string or None. This is a read-only attribute.

nodeValue

This has a different meaning for each node type; see the DOM specification for details. The situation is similar to that with nodeName. The value is a string or None.

hasAttributes()

Returns true if the node has any attributes.

hasChildNodes()

Returns true if the node has any child nodes.

isSameNode(other)

Returns true if *other* refers to the same node as this node. This is especially useful for DOM implementations which use any sort of proxy architecture (because more than one object can refer to the same node).

Note: This is based on a proposed DOM Level 3 API which is still in the "working draft" stage, but this particular interface appears uncontroversial. Changes from the W3C will not necessarily affect this method in the Python DOM interface (though any new W3C API for this would also be supported).

appendChild(newChild)

Add a new child node to this node at the end of the list of children, returning newChild.

insertBefore(newChild, refChild)

Insert a new child node before an existing child. It must be the case that *refChild* is a child of this node; if not, ValueError is raised. *newChild* is returned. If *refChild* is None, it inserts *newChild* at the end of the children's list.

removeChild(oldChild)

Remove a child node. *oldChild* must be a child of this node; if not, ValueError is raised. *oldChild* is returned on success. If *oldChild* will not be used further, its unlink() method should be called.

replaceChild(newChild, oldChild)

Replace an existing node with a new node. It must be the case that *oldChild* is a child of this node; if not, ValueError is raised.

normalize()

Join adjacent text nodes so that all stretches of text are stored as single Text instances. This simplifies processing text from a DOM tree for many applications. New in version 2.1.

cloneNode(deep)

Clone this node. Setting *deep* means to clone all child nodes as well. This returns the clone.

NodeList Objects

A NodeList represents a sequence of nodes. These objects are used in two ways in the DOM Core recommendation: the Element objects provides one as its list of child nodes, and the getElementsByTagName() and getElementsByTagNameNS() methods of Node return objects with this interface to represent query results.

The DOM Level 2 recommendation defines one method and one attribute for these objects:

item(i)

Return the i'th item from the sequence, if there is one, or None. The index i is not allowed to be less then zero or greater than or equal to the length of the sequence.

length

The number of nodes in the sequence.

In addition, the Python DOM interface requires that some additional support is provided to allow NodeList objects to be used as Python sequences. All NodeList implementations must include support for __len__() and __getitem__(); this allows iteration over the NodeList in for statements and proper support for the len() built-in function.

If a DOM implementation supports modification of the document, the NodeList implementation must also support the __setitem__() and __delitem__() methods.

DocumentType Objects

Information about the notations and entities declared by a document (including the external subset if the parser uses it and can provide the information) is available from a DocumentType object. The DocumentType for a document is available from the Document object's doctype attribute; if there is no DOCTYPE declaration for the document, the document's doctype attribute will be set to None instead of an instance of this interface.

DocumentType is a specialization of Node, and adds the following attributes:

publicId

The public identifier for the external subset of the document type definition. This will be a string or None.

systemId

The system identifier for the external subset of the document type definition. This will be a URI as a string, or None.

internalSubset

A string giving the complete internal subset from the document. This does not include the brackets which enclose the subset. If the document has no internal subset, this should be None.

name

The name of the root element as given in the DOCTYPE declaration, if present.

entities

This is a NamedNodeMap giving the definitions of external entities. For entity names defined more than once, only the first definition is provided (others are ignored as required by the XML recommendation). This may be None if the information is not provided by the parser, or if no entities are defined.

notations

This is a NamedNodeMap giving the definitions of notations. For notation names defined more than once, only the first definition is provided (others are ignored as required by the XML recommendation). This may be None if the information is not provided by the parser, or if no notations are defined.

Document Objects

A Document represents an entire XML document, including its constituent elements, attributes, processing instructions, comments etc. Remeber that it inherits properties from Node.

documentElement

The one and only root element of the document.

createElement(tagName)

Create and return a new element node. The element is not inserted into the document when it is created. You need to explicitly insert it with one of the other methods such as insertBefore() or appendChild().

createElementNS(namespaceURI, tagName)

Create and return a new element with a namespace. The *tagName* may have a prefix. The element is not inserted into the document when it is created. You need to explicitly insert it with one of the other methods such as insertBefore() or appendChild().

createTextNode(data)

Create and return a text node containing the data passed as a parameter. As with the other creation methods, this one does not insert the node into the tree.

createComment(data)

Create and return a comment node containing the data passed as a parameter. As with the other creation methods, this one does not insert the node into the tree.

createProcessingInstruction(target, data)

Create and return a processing instruction node containing the *target* and *data* passed as parameters. As with the other creation methods, this one does not insert the node into the tree.

createAttribute(name)

Create and return an attribute node. This method does not associate the attribute node with any particular element. You must use setAttributeNode() on the appropriate Element object to use the newly created attribute instance.

createAttributeNS(namespaceURI, qualifiedName)

Create and return an attribute node with a namespace. The *tagName* may have a prefix. This method does not associate the attribute node with any particular element. You must use setAttributeNode() on the appropriate Element object to use the newly created attribute instance.

getElementsByTagName(tagName)

Search for all descendants (direct children, children's children, etc.) with a particular element type name.

getElementsByTagNameNS(namespaceURI, localName)

Search for all descendants (direct children, children's children, etc.) with a particular namespace URI and

localname. The localname is the part of the namespace after the prefix.

Element Objects

Element is a subclass of Node, so inherits all the attributes of that class.

tagName

The element type name. In a namespace-using document it may have colons in it. The value is a string.

${\tt getElementsByTagName} \ (\ tagName\)$

Same as equivalent method in the Document class.

getElementsByTagNameNS(tagName)

Same as equivalent method in the Document class.

hasAttribute(name)

Returns true if the element has an attribute named by name.

hasAttributeNS(namespaceURI, localName)

Returns true if the element has an attribute named by *namespaceURI* and *localName*.

getAttribute(name)

Return the value of the attribute named by *name* as a string. If no such attribute exists, an empty string is returned, as if the attribute had no value.

getAttributeNode(attrname)

Return the Attr node for the attribute named by attrname.

getAttributeNS(namespaceURI, localName)

Return the value of the attribute named by *namespaceURI* and *localName* as a string. If no such attribute exists, an empty string is returned, as if the attribute had no value.

getAttributeNodeNS(namespaceURI, localName)

Return an attribute value as a node, given a namespaceURI and localName.

removeAttribute(name)

Remove an attribute by name. No exception is raised if there is no matching attribute.

removeAttributeNode(oldAttr)

Remove and return *oldAttr* from the attribute list, if present. If *oldAttr* is not present, NotFoundErr is raised.

removeAttributeNS(namespaceURI, localName)

Remove an attribute by name. Note that it uses a localName, not a quame. No exception is raised if there is no matching attribute.

setAttribute(name, value)

Set an attribute value from a string.

setAttributeNode(newAttr)

Add a new attribute node to the element, replacing an existing attribute if necessary if the name attribute matches. If a replacement occurs, the old attribute node will be returned. If *newAttr* is already in use, ThuseAttributeErr will be raised.

setAttributeNodeNS(newAttr)

Add a new attribute node to the element, replacing an existing attribute if necessary if the namespaceURI and localName attributes match. If a replacement occurs, the old attribute node will be returned. If newAttr is already in use, InuseAttributeErr will be raised.

setAttributeNS(namespaceURI, qname, value)

Set an attribute value from a string, given a *namespaceURI* and a *qname*. Note that a qname is the whole attribute name. This is different than above.

Attr Objects

Attr inherits from Node, so inherits all its attributes.

name

The attribute name. In a namespace-using document it may have colons in it.

localName

The part of the name following the colon if there is one, else the entire name. This is a read-only attribute.

prefix

The part of the name preceding the colon if there is one, else the empty string.

NamedNodeMap Objects

NamedNodeMap does not inherit from Node.

length

The length of the attribute list.

item(index)

Return an attribute with a particular index. The order you get the attributes in is arbitrary but will be consistent for the life of a DOM. Each item is an attribute node. Get its value with the value attribute.

There are also experimental methods that give this class more mapping behavior. You can use them or you can use the standardized getAttribute*() family of methods on the Element objects.

Comment Objects

Comment represents a comment in the XML document. It is a subclass of Node, but cannot have child nodes.

data

The content of the comment as a string. The attribute contains all characters between the leading <!-- and trailing -->, but does not include them.

Text and CDATASection Objects

The Text interface represents text in the XML document. If the parser and DOM implementation support the DOM's XML extension, portions of the text enclosed in CDATA marked sections are stored in CDATASection objects. These two interfaces are identical, but provide different values for the nodeType attribute.

These interfaces extend the Node interface. They cannot have child nodes.

data

The content of the text node as a string.

Note: The use of a CDATASection node does not indicate that the node represents a complete CDATA marked section, only that the content of the node was part of a CDATA section. A single CDATA section may be represented by more than one node in the document tree. There is no way to determine whether two adjacent CDATASection nodes represent different CDATA marked sections.

ProcessingInstruction Objects

Represents a processing instruction in the XML document; this inherits from the Node interface and cannot have child nodes.

target

The content of the processing instruction up to the first whitespace character. This is a read-only attribute.

data

The content of the processing instruction following the first whitespace character.

Exceptions

New in version 2.1.

The DOM Level 2 recommendation defines a single exception, DOMException, and a number of constants that allow applications to determine what sort of error occurred. DOMException instances carry a code attribute that provides the appropriate value for the specific exception.

The Python DOM interface provides the constants, but also expands the set of exceptions so that a specific exception exists for each of the exception codes defined by the DOM. The implementations must raise the appropriate specific exception, each of which carries the appropriate value for the code attribute.

exception DOMException

Base exception class used for all specific DOM exceptions. This exception class cannot be directly instantiated.

exception DomstringSizeErr

Raised when a specified range of text does not fit into a string. This is not known to be used in the Python DOM implementations, but may be received from DOM implementations not written in Python.

exception HierarchyRequestErr

Raised when an attempt is made to insert a node where the node type is not allowed.

exception IndexSizeErr

Raised when an index or size parameter to a method is negative or exceeds the allowed values.

exception InuseAttributeErr

Raised when an attempt is made to insert an Attr node that is already present elsewhere in the document.

exception InvalidAccessErr

Raised if a parameter or an operation is not supported on the underlying object.

exception InvalidCharacterErr

This exception is raised when a string parameter contains a character that is not permitted in the context it's being used in by the XML 1.0 recommendation. For example, attempting to create an Element node with a space in the element type name will cause this error to be raised.

exception InvalidModificationErr

Raised when an attempt is made to modify the type of a node.

exception InvalidStateErr

Raised when an attempt is made to use an object that is not defined or is no longer usable.

exception NamespaceErr

If an attempt is made to change any object in a way that is not permitted with regard to the *Namespaces in XML* recommendation, this exception is raised.

exception NotFoundErr

Exception when a node does not exist in the referenced context. For example, NamedNodeMap.removeNamedItem() will raise this if the node passed in does not exist in the map.

exception NotSupportedErr

Raised when the implementation does not support the requested type of object or operation.

exception NoDataAllowedErr

This is raised if data is specified for a node which does not support data.

exception NoModificationAllowedErr

Raised on attempts to modify an object where modifications are not allowed (such as for read-only nodes).

exception SyntaxErr

Raised when an invalid or illegal string is specified.

exception WrongDocumentErr

Raised when a node is inserted in a different document than it currently belongs to, and the implementation does not support migrating the node from one document to the other.

The exception codes defined in the DOM recommendation map to the exceptions described above according to this table:

Constant	Exception
DOMSTRING_SIZE_ERR	DomstringSizeErr
HIERARCHY_REQUEST_ERR	HierarchyRequestErr
INDEX_SIZE_ERR	IndexSizeErr
INUSE_ATTRIBUTE_ERR	InuseAttributeErr
INVALID_ACCESS_ERR	InvalidAccessErr
INVALID_CHARACTER_ERR	InvalidCharacterErr
INVALID_MODIFICATION_ERR	InvalidModificationErr
INVALID_STATE_ERR	InvalidStateErr
NAMESPACE_ERR	NamespaceErr
NOT_FOUND_ERR	NotFoundErr
NOT_SUPPORTED_ERR	NotSupportedErr
NO_DATA_ALLOWED_ERR	NoDataAllowedErr
NO_MODIFICATION_ALLOWED_ERR	NoModificationAllowedErr
SYNTAX_ERR	SyntaxErr
WRONG_DOCUMENT_ERR	WrongDocumentErr

13.6.3 Conformance

This section describes the conformance requirements and relationships between the Python DOM API, the W3C DOM recommendations, and the OMG IDL mapping for Python.

Type Mapping

The primitive IDL types used in the DOM specification are mapped to Python types according to the following table.

IDL Type	Python Type
boolean	IntegerType (with a value of 0 or 1)
int	IntegerType
long int	IntegerType
unsigned int	IntegerType

Additionally, the DOMString defined in the recommendation is mapped to a Python string or Unicode string. Applications should be able to handle Unicode whenever a string is returned from the DOM.

The IDL null value is mapped to None, which may be accepted or provided by the implementation whenever null is allowed by the API.

Accessor Methods

The mapping from OMG IDL to Python defines accessor functions for IDL attribute declarations in much the way the Java mapping does. Mapping the IDL declarations

```
readonly attribute string someValue;
    attribute string anotherValue;
```

yields three accessor functions: a "get" method for someValue(_get_someValue()), and "get" and "set" methods for anotherValue(_get_anotherValue() and _set_anotherValue()). The mapping, in particular, does not require that the IDL attributes are accessible as normal Python attributes: object.someValue is not required to work, and may raise an AttributeError.

The Python DOM API, however, *does* require that normal attribute access work. This means that the typical surrogates generated by Python IDL compilers are not likely to work, and wrapper objects may be needed on the client if the DOM objects are accessed via CORBA. While this does require some additional consideration for CORBA DOM clients, the implementers with experience using DOM over CORBA from Python do not consider this a problem. Attributes that are declared readonly may not restrict write access in all DOM implementations.

In the Python DOM API, accessor functions are not required. If provided, they should take the form defined by the Python IDL mapping, but these methods are considered unnecessary since the attributes are accessible directly from Python. "Set" accessors should never be provided for readonly attributes.

The IDL definitions do not fully embody the requirements of the W3C DOM API, such as the notion of certain objects, such as the return value of getElementsByTagName(), being "live". The Python DOM API does not require implementations to enforce such requirements.

13.7 xml.dom.minidom — Lightweight DOM implementation

New in version 2.0.

xml.dom.minidom is a light-weight implementation of the Document Object Model interface. It is intended to be simpler than the full DOM and also significantly smaller.

DOM applications typically start by parsing some XML into a DOM. With xml.dom.minidom, this is done through the parse functions:

```
from xml.dom.minidom import parse, parseString

dom1 = parse('c:\\temp\\mydata.xml') # parse an XML file by name

datasource = open('c:\\temp\\mydata.xml')
dom2 = parse(datasource) # parse an open file

dom3 = parseString('<myxml>Some data<empty/> some more data</myxml>')
```

The parse() function can take either a filename or an open file object.

```
parse(filename_or_file, parser)
```

Return a Document from the given input. *filename_or_file* may be either a file name, or a file-like object. *parser*, if given, must be a SAX2 parser object. This function will change the document handler of the parser and activate namespace support; other parser configuration (like setting an entity resolver) must have been done in advance.

If you have XML in a string, you can use the parseString() function instead:

```
parseString(string[, parser])
```

Return a Document that represents the *string*. This method creates a StringIO object for the string and passes that on to parse.

Both functions return a Document object representing the content of the document.

What the parse() and parseString() functions do is connect an XML parser with a "DOM builder" that can accept parse events from any SAX parser and convert them into a DOM tree. The name of the functions are perhaps misleading, but are easy to grasp when learning the interfaces. The parsing of the document will be completed before these functions return; it's simply that these functions do not provide a parser implementation themselves.

You can also create a Document by calling a method on a "DOM Implementation" object. You can get this object either by calling the getDOMImplementation() function in the xml.dom package or the xml.dom.minidom module. Using the implementation from the xml.dom.minidom module will always return a Document instance from the minidom implementation, while the version from xml.dom may provide an alternate implementation (this is likely if you have the PyXML package installed). Once you have a Document, you can add child nodes to it to populate the DOM:

```
from xml.dom.minidom import getDOMImplementation
impl = getDOMImplementation()

newdoc = impl.createDocument(None, "some_tag", None)
top_element = newdoc.documentElement
text = newdoc.createTextNode('Some textual content.')
top_element.appendChild(text)
```

Once you have a DOM document object, you can access the parts of your XML document through its properties and methods. These properties are defined in the DOM specification. The main property of the document object is the document property. It gives you the main element in the XML document: the one that holds all others. Here is an example program:

```
dom3 = parseString("<myxml>Some data</myxml>")
assert dom3.documentElement.tagName == "myxml"
```

When you are finished with a DOM, you should clean it up. This is necessary because some versions of Python do not support garbage collection of objects that refer to each other in a cycle. Until this restriction is removed from all versions of Python, it is safest to write your code as if cycles would not be cleaned up.

The way to clean up a DOM is to call its unlink() method:

```
dom1.unlink()
dom2.unlink()
dom3.unlink()
```

unlink() is a xml.dom.minidom-specific extension to the DOM API. After calling unlink() on a node, the node and its descendants are essentially useless.

See Also:

Document Object Model (DOM) Level 1 Specification (http://www.w3.org/TR/REC-DOM-Level-1/)

The W3C recommendation for the DOM supported by xml.dom.minidom.

13.7.1 DOM Objects

The definition of the DOM API for Python is given as part of the xml.dom module documentation. This section lists the differences between the API and xml.dom.minidom.

```
unlink()
```

Break internal references within the DOM so that it will be garbage collected on versions of Python without cyclic GC. Even when cyclic GC is available, using this can make large amounts of memory available sooner, so calling this on DOM objects as soon as they are no longer needed is good practice. This only needs to be called on the Document object, but may be called on child nodes to discard children of that node.

```
writexml(writer[,indent=""[,addindent=""[,newl=""]]])
```

Write XML to the writer object. The writer should have a write() method which matches that of the file object interface. The *indent* parameter is the indentation of the current node. The *addindent* parameter is the incremental indentation to use for subnodes of the current one. The *newl* parameter specifies the string to use to terminate newlines.

Changed in version 2.1: The optional keyword parameters *indent*, *addindent*, and *newl* were added to support pretty output.

Changed in version 2.3: For the Document node, an additional keyword argument *encoding* can be used to specify the encoding field of the XML header.

```
toxml([encoding])
```

Return the XML that the DOM represents as a string.

With no argument, the XML header does not specify an encoding, and the result is Unicode string if the default encoding cannot represent all characters in the document. Encoding this string in an encoding other than UTF-8 is likely incorrect, since UTF-8 is the default encoding of XML.

With an explicit *encoding* argument, the result is a byte string in the specified encoding. It is recommended that this argument is always specified. To avoid UnicodeError exceptions in case of unrepresentable text data, the encoding argument should be specified as "utf-8".

Changed in version 2.3: the *encoding* argument was introduced.

```
toprettyxml([indent[, newl]])
```

Return a pretty-printed version of the document. *indent* specifies the indentation string and defaults to a tabulator; *newl* specifies the string emitted at the end of each line and defaults to

New in version 2.1. Changed in version 2.3: the encoding argument; see toxml().

The following standard DOM methods have special considerations with xml.dom.minidom:

cloneNode(deep)

Although this method was present in the version of xml.dom.minidom packaged with Python 2.0, it was seriously broken. This has been corrected for subsequent releases.

13.7.2 DOM Example

This example program is a fairly realistic example of a simple program. In this particular case, we do not take much advantage of the flexibility of the DOM.

```
import xml.dom.minidom
document = """\
<slideshow>
<title>Demo slideshow</title>
<slide><title>Slide title</title>
<point>This is a demo</point>
<point>Of a program for processing slides</point>
</slide>
<slide><title>Another demo slide</title>
<point>It is important
<point>To have more than</point>
<point>one slide</point>
</slide>
</slideshow>
dom = xml.dom.minidom.parseString(document)
def getText(nodelist):
    rc = ""
    for node in nodelist:
        if node.nodeType == node.TEXT_NODE:
           rc = rc + node.data
    return rc
def handleSlideshow(slideshow):
    handleSlideshowTitle(slideshow.getElementsByTagName("title")[0])
    slides = slideshow.getElementsByTagName("slide")
    handleToc(slides)
    handleSlides(slides)
    print "</html>"
```

```
def handleSlides(slides):
    for slide in slides:
       handleSlide(slide)
def handleSlide(slide):
   handleSlideTitle(slide.getElementsByTagName("title")[0])
   handlePoints(slide.getElementsByTagName("point"))
def handleSlideshowTitle(title):
   print "<title>%s</title>" % getText(title.childNodes)
def handleSlideTitle(title):
   print "<h2>%s</h2>" % getText(title.childNodes)
def handlePoints(points):
   print ""
   for point in points:
       handlePoint(point)
   print ""
def handlePoint(point):
   print "%s" % getText(point.childNodes)
def handleToc(slides):
    for slide in slides:
        title = slide.getElementsByTagName("title")[0]
       print "%s" % getText(title.childNodes)
handleSlideshow(dom)
```

13.7.3 minidom and the DOM standard

The xml.dom.minidom module is essentially a DOM 1.0-compatible DOM with some DOM 2 features (primarily namespace features).

Usage of the DOM interface in Python is straight-forward. The following mapping rules apply:

- Interfaces are accessed through instance objects. Applications should not instantiate the classes themselves; they should use the creator functions available on the Document object. Derived interfaces support all operations (and attributes) from the base interfaces, plus any new operations.
- Operations are used as methods. Since the DOM uses only in parameters, the arguments are passed in normal order (from left to right). There are no optional arguments. void operations return None.
- IDL attributes map to instance attributes. For compatibility with the OMG IDL language mapping for Python, an attribute foo can also be accessed through accessor methods _get_foo() and _set_foo(). readonly attributes must not be changed; this is not enforced at runtime.
- The types short int, unsigned int, unsigned long long, and boolean all map to Python integer objects.
- The type DOMString maps to Python strings. xml.dom.minidom supports either byte or Unicode strings, but will normally produce Unicode strings. Values of type DOMString may also be None where allowed to have the IDL null value by the DOM specification from the W3C.
- const declarations map to variables in their respective scope (e.g. xml.dom.minidom.Node.PROCESSING_INSTRUCTION_NODE); they must not be changed.
- DOMException is currently not supported in xml.dom.minidom. Instead, xml.dom.minidom uses standard Python exceptions such as TypeError and AttributeError.

• NodeList objects are implemented using Python's built-in list type. Starting with Python 2.2, these objects provide the interface defined in the DOM specification, but with earlier versions of Python they do not support the official API. They are, however, much more "Pythonic" than the interface defined in the W3C recommendations.

The following interfaces have no implementation in xml.dom.minidom:

- DOMTimeStamp
- DocumentType (added in Python 2.1)
- DOMImplementation (added in Python 2.1)
- CharacterData
- CDATASection
- Notation
- Entity
- EntityReference
- DocumentFragment

Most of these reflect information in the XML document that is not of general utility to most DOM users.

13.8 xml.dom.pulldom — Support for building partial DOM trees

New in version 2.0.

xml.dom.pulldom allows building only selected portions of a Document Object Model representation of a document from SAX events.

```
class PullDOM([documentFactory])
     xml.sax.handler.ContentHandler implementation that ...
class DOMEventStream(stream, parser, bufsize)
     ...
class SAX2DOM([documentFactory])
     xml.sax.handler.ContentHandler implementation that ...
parse(stream_or_string[, parser[, bufsize]])
     ...
parseString(string[, parser])
     ...
default_bufsize
```

Default value for the *busize* parameter to parse(). Changed in version 2.1: The value of this variable can be changed before calling parse() and the new value will take effect.

13.8.1 DOMEventStream Objects

```
getEvent()
...
expandNode(node)
...
reset()
```

13.9 xml.sax — Support for SAX2 parsers

New in version 2.0.

The xml.sax package provides a number of modules which implement the Simple API for XML (SAX) interface for Python. The package itself provides the SAX exceptions and the convenience functions which will be most used by users of the SAX API.

The convenience functions are:

make_parser([parser_list])

Create and return a SAX XMLReader object. The first parser found will be used. If <code>parser_list</code> is provided, it must be a sequence of strings which name modules that have a function named <code>create_parser()</code>. Modules listed in <code>parser_list</code> will be used before modules in the default list of parsers.

parse(filename_or_stream, handler[, error_handler])

Create a SAX parser and use it to parse a document. The document, passed in as <code>filename_or_stream</code>, can be a filename or a file object. The <code>handler</code> parameter needs to be a SAX <code>ContentHandler</code> instance. If <code>error_handler</code> is given, it must be a SAX <code>ErrorHandler</code> instance; if omitted, <code>SAXParseException</code> will be raised on all errors. There is no return value; all work must be done by the <code>handler</code> passed in.

parseString(string, handler[, error_handler])

Similar to parse (), but parses from a buffer *string* received as a parameter.

A typical SAX application uses three kinds of objects: readers, handlers and input sources. "Reader" in this context is another term for parser, i.e. some piece of code that reads the bytes or characters from the input source, and produces a sequence of events. The events then get distributed to the handler objects, i.e. the reader invokes a method on the handler. A SAX application must therefore obtain a reader object, create or open the input sources, create the handlers, and connect these objects all together. As the final step of preparation, the reader is called to parse the input. During parsing, methods on the handler objects are called based on structural and syntactic events from the input data.

For these objects, only the interfaces are relevant; they are normally not instantiated by the application itself. Since Python does not have an explicit notion of interface, they are formally introduced as classes, but applications may use implementations which do not inherit from the provided classes. The InputSource, Locator, Attributes, AttributesNS, and XMLReader interfaces are defined in the module xml.sax.xmlreader. The handler interfaces are defined in xml.sax.handler. For convenience, InputSource (which is often instantiated directly) and the handler classes are also available from xml.sax. These interfaces are described below.

In addition to these classes, xml.sax provides the following exception classes.

exception SAXException (msg |, exception |)

Encapsulate an XML error or warning. This class can contain basic error or warning information from either the XML parser or the application: it can be subclassed to provide additional functionality or to add localization. Note that although the handlers defined in the ErrorHandler interface receive instances of this exception, it is not required to actually raise the exception — it is also useful as a container for information.

When instantiated, *msg* should be a human-readable description of the error. The optional *exception* parameter, if given, should be None or an exception that was caught by the parsing code and is being passed along as information.

This is the base class for the other SAX exception classes.

exception SAXParseException(msg, exception, locator)

Subclass of SAXException raised on parse errors. Instances of this class are passed to the methods of the SAX ErrorHandler interface to provide information about the parse error. This class supports the SAX Locator interface as well as the SAXException interface.

exception SAXNotRecognizedException(msg[, exception])

Subclass of SAXException raised when a SAX XMLReader is confronted with an unrecognized feature or property. SAX applications and extensions may use this class for similar purposes.

 $\textbf{exception SAXNotSupportedException} \ (\textit{msg} \big[, \textit{exception} \, \big])$

Subclass of SAXException raised when a SAX XMLReader is asked to enable a feature that is not supported, or to set a property to a value that the implementation does not support. SAX applications and extensions may use this class for similar purposes.

See Also:

SAX: The Simple API for XML

(http://www.saxproject.org/)

This site is the focal point for the definition of the SAX API. It provides a Java implementation and online documentation. Links to implementations and historical information are also available.

Module xml.sax.handler (section 13.10):

Definitions of the interfaces for application-provided objects.

Module xml.sax.saxutils (section 13.11):

Convenience functions for use in SAX applications.

Module xml.sax.xmlreader (section 13.12):

Definitions of the interfaces for parser-provided objects.

13.9.1 SAXException Objects

The SAXException exception class supports the following methods:

getMessage()

Return a human-readable message describing the error condition.

getException()

Return an encapsulated exception object, or None.

13.10 xml.sax.handler — Base classes for SAX handlers

New in version 2.0.

The SAX API defines four kinds of handlers: content handlers, DTD handlers, error handlers, and entity resolvers. Applications normally only need to implement those interfaces whose events they are interested in; they can implement the interfaces in a single object or in multiple objects. Handler implementations should inherit from the base classes provided in the module xml.sax, so that all methods get default implementations.

class ContentHandler

This is the main callback interface in SAX, and the one most important to applications. The order of events in this interface mirrors the order of the information in the document.

class DTDHandler

Handle DTD events.

This interface specifies only those DTD events required for basic parsing (unparsed entities and attributes).

class EntityResolver

Basic interface for resolving entities. If you create an object implementing this interface, then register the object with your Parser, the parser will call the method in your object to resolve all external entities.

class ErrorHandler

Interface used by the parser to present error and warning messages to the application. The methods of this object control whether errors are immediately converted to exceptions or are handled in some other way.

In addition to these classes, xml.sax.handler provides symbolic constants for the feature and property names.

feature_namespaces

Value: "http://xml.org/sax/features/namespaces"

true: Perform Namespace processing.

false: Optionally do not perform Namespace processing (implies namespace-prefixes; default).

access: (parsing) read-only; (not parsing) read/write

feature_namespace_prefixes

Value: "http://xml.org/sax/features/namespace-prefixes"

true: Report the original prefixed names and attributes used for Namespace declarations.

false: Do not report attributes used for Namespace declarations, and optionally do not report original pre-

fixed names (default).

access: (parsing) read-only; (not parsing) read/write

feature_string_interning

Value: "http://xml.org/sax/features/string-interning"

true: All element names, prefixes, attribute names, Namespace URIs, and local names are interned using the built-in intern function.

false: Names are not necessarily interned, although they may be (default).

access: (parsing) read-only; (not parsing) read/write

feature_validation

Value: "http://xml.org/sax/features/validation"

true: Report all validation errors (implies external-general-entities and external-parameter-entities).

false: Do not report validation errors.

access: (parsing) read-only; (not parsing) read/write

feature_external_ges

Value: "http://xml.org/sax/features/external-general-entities"

true: Include all external general (text) entities. false: Do not include external general entities. access: (parsing) read-only; (not parsing) read/write

feature_external_pes

Value: "http://xml.org/sax/features/external-parameter-entities"

true: Include all external parameter entities, including the external DTD subset.

false: Do not include any external parameter entities, even the external DTD subset.

access: (parsing) read-only; (not parsing) read/write

all_features

List of all features.

property_lexical_handler

Value: "http://xml.org/sax/properties/lexical-handler"

data type: xml.sax.sax2lib.LexicalHandler (not supported in Python 2)

description: An optional extension handler for lexical events like comments.

access: read/write

property_declaration_handler

Value: "http://xml.org/sax/properties/declaration-handler"

data type: xml.sax.sax2lib.DeclHandler (not supported in Python 2)

description: An optional extension handler for DTD-related events other than notations and unparsed enti-

ties.

access: read/write

property_dom_node

Value: "http://xml.org/sax/properties/dom-node"

data type: org.w3c.dom.Node (not supported in Python 2)

description: When parsing, the current DOM node being visited if this is a DOM iterator; when not parsing,

the root DOM node for iteration.

access: (parsing) read-only; (not parsing) read/write

property_xml_string

Value: "http://xml.org/sax/properties/xml-string"

data type: String

description: The literal string of characters that was the source for the current event.

access: read-only

all_properties

List of all known property names.

13.10.1 ContentHandler Objects

Users are expected to subclass ContentHandler to support their application. The following methods are called by the parser on the appropriate events in the input document:

setDocumentLocator(locator)

Called by the parser to give the application a locator for locating the origin of document events.

SAX parsers are strongly encouraged (though not absolutely required) to supply a locator: if it does so, it must supply the locator to the application by invoking this method before invoking any of the other methods in the DocumentHandler interface.

The locator allows the application to determine the end position of any document-related event, even if the parser is not reporting an error. Typically, the application will use this information for reporting its own errors (such as character content that does not match an application's business rules). The information returned by the locator is probably not sufficient for use with a search engine.

Note that the locator will return correct information only during the invocation of the events in this interface. The application should not attempt to use it at any other time.

startDocument()

Receive notification of the beginning of a document.

The SAX parser will invoke this method only once, before any other methods in this interface or in DTD-Handler (except for setDocumentLocator()).

endDocument()

Receive notification of the end of a document.

The SAX parser will invoke this method only once, and it will be the last method invoked during the parse. The parser shall not invoke this method until it has either abandoned parsing (because of an unrecoverable error) or reached the end of input.

startPrefixMapping(prefix, uri)

Begin the scope of a prefix-URI Namespace mapping.

The information from this event is not necessary for normal Namespace processing: the SAX XML reader will automatically replace prefixes for element and attribute names when the feature_namespaces feature is enabled (the default).

There are cases, however, when applications need to use prefixes in character data or in attribute values, where they cannot safely be expanded automatically; the startPrefixMapping() and endPrefixMapping() events supply the information to the application to expand prefixes in those contexts itself, if necessary.

Note that startPrefixMapping() and endPrefixMapping() events are not guaranteed to be properly nested relative to each-other: all startPrefixMapping() events will occur before the corresponding startElement() event, and all endPrefixMapping() events will occur after the corresponding endElement() event, but their order is not guaranteed.

endPrefixMapping(prefix)

End the scope of a prefix-URI mapping.

See startPrefixMapping() for details. This event will always occur after the corresponding endElement() event, but the order of endPrefixMapping() events is not otherwise guaranteed.

startElement(name, attrs)

Signals the start of an element in non-namespace mode.

The *name* parameter contains the raw XML 1.0 name of the element type as a string and the *attrs* parameter holds an object of the Attributes interface containing the attributes of the element. The object passed as *attrs* may be re-used by the parser; holding on to a reference to it is not a reliable way to keep a copy of the attributes. To keep a copy of the attributes, use the copy () method of the *attrs* object.

endElement(name)

Signals the end of an element in non-namespace mode.

The *name* parameter contains the name of the element type, just as with the startElement() event.

startElementNS(name, qname, attrs)

Signals the start of an element in namespace mode.

The *name* parameter contains the name of the element type as a (*uri*, *localname*) tuple, the *qname* parameter contains the raw XML 1.0 name used in the source document, and the *attrs* parameter holds an instance of the AttributesNS interface containing the attributes of the element. If no namespace is associated with the element, the *uri* component of *name* will be None. The object passed as *attrs* may be re-used by the parser; holding on to a reference to it is not a reliable way to keep a copy of the attributes. To keep a copy of the attributes, use the copy() method of the *attrs* object.

Parsers may set the *qname* parameter to None, unless the feature_namespace_prefixes feature is activated.

endElementNS(name, qname)

Signals the end of an element in namespace mode.

The *name* parameter contains the name of the element type, just as with the startElementNS() method, likewise the *qname* parameter.

characters(content)

Receive notification of character data.

The Parser will call this method to report each chunk of character data. SAX parsers may return all contiguous character data in a single chunk, or they may split it into several chunks; however, all of the characters in any single event must come from the same external entity so that the Locator provides useful information. *content* may be a Unicode string or a byte string; the expat reader module produces always Unicode strings.

Note: The earlier SAX 1 interface provided by the Python XML Special Interest Group used a more Javalike interface for this method. Since most parsers used from Python did not take advantage of the older interface, the simpler signature was chosen to replace it. To convert old code to the new interface, use *content* instead of slicing content with the old *offset* and *length* parameters.

ignorableWhitespace(whitespace)

Receive notification of ignorable whitespace in element content.

Validating Parsers must use this method to report each chunk of ignorable whitespace (see the W3C XML 1.0 recommendation, section 2.10): non-validating parsers may also use this method if they are capable of parsing and using content models.

SAX parsers may return all contiguous whitespace in a single chunk, or they may split it into several chunks; however, all of the characters in any single event must come from the same external entity, so that the Locator provides useful information.

processingInstruction(target, data)

Receive notification of a processing instruction.

The Parser will invoke this method once for each processing instruction found: note that processing instructions may occur before or after the main document element.

A SAX parser should never report an XML declaration (XML 1.0, section 2.8) or a text declaration (XML 1.0, section 4.3.1) using this method.

skippedEntity(name)

Receive notification of a skipped entity.

The Parser will invoke this method once for each entity skipped. Non-validating processors may skip entities if they have not seen the declarations (because, for example, the entity was declared in an external DTD subset). All processors may skip external entities, depending on the values of the feature_external_ges and the feature_external_pes properties.

13.10.2 DTDHandler Objects

DTDHandler instances provide the following methods:

notationDecl(name, publicId, systemId)

Handle a notation declaration event.

unparsedEntityDecl(name, publicId, systemId, ndata)

Handle an unparsed entity declaration event.

13.10.3 EntityResolver Objects

resolveEntity(publicId, systemId)

Resolve the system identifier of an entity and return either the system identifier to read from as a string, or an InputSource to read from. The default implementation returns *systemId*.

13.10.4 ErrorHandler Objects

Objects with this interface are used to receive error and warning information from the XMLReader. If you create an object that implements this interface, then register the object with your XMLReader, the parser will call the methods in your object to report all warnings and errors. There are three levels of errors available: warnings, (possibly) recoverable errors, and unrecoverable errors. All methods take a SAXParseException as the only parameter. Errors and warnings may be converted to an exception by raising the passed-in exception object.

error(exception)

Called when the parser encounters a recoverable error. If this method does not raise an exception, parsing may continue, but further document information should not be expected by the application. Allowing the parser to continue may allow additional errors to be discovered in the input document.

fatalError(exception)

Called when the parser encounters an error it cannot recover from; parsing is expected to terminate when this method returns.

warning(exception)

Called when the parser presents minor warning information to the application. Parsing is expected to continue when this method returns, and document information will continue to be passed to the application. Raising an exception in this method will cause parsing to end.

13.11 xml.sax.saxutils — SAX Utilities

New in version 2.0.

The module xml.sax.saxutils contains a number of classes and functions that are commonly useful when creating SAX applications, either in direct use, or as base classes.

escape(data[, entities])

Escape '&', '<', and '>' in a string of data.

You can escape other strings of data by passing a dictionary as the optional *entities* parameter. The keys and values must all be strings; each key will be replaced with its corresponding value.

unescape(data[, entities])

Unescape '&', '<', and '>' in a string of data.

You can unescape other strings of data by passing a dictionary as the optional *entities* parameter. The keys and values must all be strings; each key will be replaced with its corresponding value.

New in version 2.3.

quoteattr(data , entities)

Similar to escape(), but also prepares *data* to be used as an attribute value. The return value is a quoted version of *data* with any additional required replacements. quoteattr() will select a quote character based on the content of *data*, attempting to avoid encoding any quote characters in the string. If both single-and double-quote characters are already in *data*, the double-quote characters will be encoded and *data* will be wrapped in double-quotes. The resulting string can be used directly as an attribute value:

```
>>> print "<element attr=%s>" % quoteattr("ab ' cd \" ef")
<element attr="ab ' cd &quot; ef">
```

This function is useful when generating attribute values for HTML or any SGML using the reference concrete syntax. New in version 2.2.

class XMLGenerator([out[, encoding]])

This class implements the ContentHandler interface by writing SAX events back into an XML document. In other words, using an XMLGenerator as the content handler will reproduce the original document being parsed. *out* should be a file-like object which will default to *sys.stdout*. *encoding* is the encoding of the output stream which defaults to 'iso-8859-1'.

class XMLFilterBase(base)

This class is designed to sit between an XMLReader and the client application's event handlers. By default, it does nothing but pass requests up to the reader and events on to the handlers unmodified, but subclasses can override specific methods to modify the event stream or the configuration requests as they pass through.

prepare_input_source(source[, base])

This function takes an input source and an optional base URL and returns a fully resolved InputSource object ready for reading. The input source can be given as a string, a file-like object, or an InputSource object; parsers will use this function to implement the polymorphic *source* argument to their parse() method.

13.12 xml.sax.xmlreader — Interface for XML parsers

New in version 2.0.

SAX parsers implement the XMLReader interface. They are implemented in a Python module, which must provide a function <code>create_parser()</code>. This function is invoked by <code>xml.sax.make_parser()</code> with no arguments to create a new parser object.

class XMLReader()

Base class which can be inherited by SAX parsers.

class IncrementalParser()

In some cases, it is desirable not to parse an input source at once, but to feed chunks of the document as they get available. Note that the reader will normally not read the entire file, but read it in chunks as well; still parse() won't return until the entire document is processed. So these interfaces should be used if the blocking behaviour of parse() is not desirable.

When the parser is instantiated it is ready to begin accepting data from the feed method immediately. After parsing has been finished with a call to close the reset method must be called to make the parser ready to accept new data, either from feed or using the parse method.

Note that these methods must *not* be called during parsing, that is, after parse has been called and before it returns.

By default, the class also implements the parse method of the XMLReader interface using the feed, close and reset methods of the IncrementalParser interface as a convenience to SAX 2.0 driver writers.

class Locator()

Interface for associating a SAX event with a document location. A locator object will return valid results only during calls to DocumentHandler methods; at any other time, the results are unpredictable. If information is not available, methods may return None.

class InputSource([systemId])

Encapsulation of the information needed by the XMLReader to read entities.

This class may include information about the public identifier, system identifier, byte stream (possibly with character encoding information) and/or the character stream of an entity.

Applications will create objects of this class for use in the XMLReader.parse() method and for returning from EntityResolver.resolveEntity.

An InputSource belongs to the application, the XMLReader is not allowed to modify InputSource objects passed to it from the application, although it may make copies and modify those.

class AttributesImpl(attrs)

This is an implementation of the Attributes interface (see section 13.12.5). This is a dictionary-like object which represents the element attributes in a startElement() call. In addition to the most useful dictionary operations, it supports a number of other methods as described by the interface. Objects of this class should be instantiated by readers; *attrs* must be a dictionary-like object containing a mapping from attribute names to attribute values.

class AttributesNSImpl(attrs, qnames)

Namespace-aware variant of AttributesImpl, which will be passed to startElementNS(). It is derived from AttributesImpl, but understands attribute names as two-tuples of *namespaceURI* and *localname*. In addition, it provides a number of methods expecting qualified names as they appear in the original document. This class implements the AttributesNS interface (see section 13.12.6).

13.12.1 XMLReader Objects

The XMLReader interface supports the following methods:

parse(source)

Process an input source, producing SAX events. The *source* object can be a system identifier (a string identifying the input source – typically a file name or an URL), a file-like object, or an InputSource object. When parse() returns, the input is completely processed, and the parser object can be discarded or reset. As a limitation, the current implementation only accepts byte streams; processing of character streams is for further study.

getContentHandler()

Return the current ContentHandler.

setContentHandler(handler)

Set the current ContentHandler. If no ContentHandler is set, content events will be discarded.

getDTDHandler()

Return the current DTDHandler.

$\verb"setDTDH" and ler" (handler)$

Set the current DTDHandler. If no DTDHandler is set, DTD events will be discarded.

getEntityResolver()

Return the current EntityResolver.

setEntityResolver(handler)

Set the current EntityResolver. If no EntityResolver is set, attempts to resolve an external entity will result in opening the system identifier for the entity, and fail if it is not available.

getErrorHandler()

Return the current ErrorHandler.

setErrorHandler(handler)

Set the current error handler. If no ErrorHandler is set, errors will be raised as exceptions, and warnings will be printed.

setLocale(locale)

Allow an application to set the locale for errors and warnings.

SAX parsers are not required to provide localization for errors and warnings; if they cannot support the requested locale, however, they must throw a SAX exception. Applications may request a locale change in the middle of a parse.

getFeature(featurename)

Return the current setting for feature *featurename*. If the feature is not recognized, SAXNotRecognizedException is raised. The well-known featurenames are listed in the module xml.sax.handler.

setFeature(featurename, value)

Set the *featurename* to *value*. If the feature is not recognized, SAXNotRecognizedException is raised. If the feature or its setting is not supported by the parser, *SAXNotSupportedException* is raised.

getProperty(propertyname)

Return the current setting for property *propertyname*. If the property is not recognized, a SAXNotRecognizedException is raised. The well-known propertynames are listed in the module xml.sax.handler.

setProperty(propertyname, value)

Set the *propertyname* to *value*. If the property is not recognized, SAXNotRecognizedException is raised. If the property or its setting is not supported by the parser, *SAXNotSupportedException* is raised.

13.12.2 IncrementalParser Objects

Instances of IncrementalParser offer the following additional methods:

feed(data)

Process a chunk of data.

close()

Assume the end of the document. That will check well-formedness conditions that can be checked only at the end, invoke handlers, and may clean up resources allocated during parsing.

reset()

This method is called after close has been called to reset the parser so that it is ready to parse new documents. The results of calling parse or feed after close without calling reset are undefined.

13.12.3 Locator Objects

Instances of Locator provide these methods:

getColumnNumber()

Return the column number where the current event ends.

getLineNumber()

Return the line number where the current event ends.

getPublicId()

Return the public identifier for the current event.

getSystemId()

Return the system identifier for the current event.

13.12.4 InputSource Objects

setPublicId(id)

Sets the public identifier of this InputSource.

getPublicId()

Returns the public identifier of this InputSource.

setSystemId(id)

Sets the system identifier of this InputSource.

getSystemId()

Returns the system identifier of this InputSource.

setEncoding(encoding)

Sets the character encoding of this InputSource.

The encoding must be a string acceptable for an XML encoding declaration (see section 4.3.3 of the XML recommendation).

The encoding attribute of the InputSource is ignored if the InputSource also contains a character stream.

getEncoding()

Get the character encoding of this InputSource.

setByteStream(bytefile)

Set the byte stream (a Python file-like object which does not perform byte-to-character conversion) for this input source.

The SAX parser will ignore this if there is also a character stream specified, but it will use a byte stream in preference to opening a URI connection itself.

If the application knows the character encoding of the byte stream, it should set it with the setEncoding method.

getByteStream()

Get the byte stream for this input source.

The getEncoding method will return the character encoding for this byte stream, or None if unknown.

setCharacterStream(charfile)

Set the character stream for this input source. (The stream must be a Python 1.6 Unicode-wrapped file-like that performs conversion to Unicode strings.)

If there is a character stream specified, the SAX parser will ignore any byte stream and will not attempt to open a URI connection to the system identifier.

getCharacterStream()

Get the character stream for this input source.

13.12.5 The Attributes Interface

Attributes objects implement a portion of the mapping protocol, including the methods copy(), get(), has_key(), items(), keys(), and values(). The following methods are also provided:

getLength()

Return the number of attributes.

getNames()

Return the names of the attributes.

getType(name)

Returns the type of the attribute name, which is normally 'CDATA'.

getValue(name)

Return the value of attribute *name*.

13.12.6 The AttributesNS Interface

This interface is a subtype of the Attributes interface (see section 13.12.5). All methods supported by that interface are also available on AttributesNS objects.

The following methods are also available:

$\verb"getValueByQName" (name)$

Return the value for a qualified name.

${\tt getNameByQName}\,(\,name\,)$

Return the (namespace, localname) pair for a qualified name.

$\verb"getQNameByName" (name)$

Return the qualified name for a (namespace, localname) pair.

getQNames()

Return the qualified names of all attributes.

13.13 xmllib — A parser for XML documents

Deprecated since release 2.0. Use xml.sax instead. The newer XML package includes full support for XML 1.0

Changed in version 1.5.2: Added namespace support.

This module defines a class XMLParser which serves as the basis for parsing text files formatted in XML (Extensible Markup Language).

class XMLParser()

The XMLParser class must be instantiated without arguments.¹

This class provides the following interface methods and instance variables:

attributes

A mapping of element names to mappings. The latter mapping maps attribute names that are valid for the element to the default value of the attribute, or if there is no default to None. The default value is the empty dictionary. This variable is meant to be overridden, not extended since the default is shared by all instances of XMLParser.

elements

A mapping of element names to tuples. The tuples contain a function for handling the start and end tag respectively of the element, or None if the method unknown_starttag() or unknown_endtag() is to be called. The default value is the empty dictionary. This variable is meant to be overridden, not extended since the default is shared by all instances of XMLParser.

entitydefs

A mapping of entitynames to their values. The default value contains definitions for 'lt', 'gt', 'amp', 'quot', and 'apos'.

reset()

Reset the instance. Loses all unprocessed data. This is called implicitly at the instantiation time.

setnomoretags()

Stop processing tags. Treat all following input as literal input (CDATA).

setliteral()

Enter literal mode (CDATA mode). This mode is automatically exited when the close tag matching the last unclosed open tag is encountered.

feed(data)

Feed some text to the parser. It is processed insofar as it consists of complete tags; incomplete data is buffered until more data is fed or close() is called.

close()

Force processing of all buffered data as if it were followed by an end-of-file mark. This method may be redefined by a derived class to define additional processing at the end of the input, but the redefined version should always call close().

translate_references(data)

Translate all entity and character references in *data* and return the translated string.

getnamespace()

Return a mapping of namespace abbreviations to namespace URIs that are currently in effect.

handle_xml(encoding, standalone)

This method is called when the '<?xml ...?>' tag is processed. The arguments are the values of the encoding and standalone attributes in the tag. Both encoding and standalone are optional. The values passed to handle_xml() default to None and the string 'no' respectively.

¹Actually, a number of keyword arguments are recognized which influence the parser to accept certain non-standard constructs. The following keyword arguments are currently recognized. The defaults for all of these is 0 (false) except for the last one for which the default is 1 (true). accept_unquoted_attributes (accept certain attribute values without requiring quotes), accept_missing_endtag_name (accept end tags that look like </>), map_case (map upper case to lower case in tags and attributes), accept_utf8 (allow UTF-8 characters in input; this is required according to the XML standard, but Python does not as yet deal properly with these characters, so this is not the default), translate_attribute_references (don't attempt to translate character and entity references in attribute values).

handle_doctype(tag, pubid, syslit, data)

This method is called when the '<!DOCTYPE...>' declaration is processed. The arguments are the tag name of the root element, the Formal Public Identifier (or None if not specified), the system identifier, and the uninterpreted contents of the internal DTD subset as a string (or None if not present).

handle_starttag(tag, method, attributes)

This method is called to handle start tags for which a start tag handler is defined in the instance variable elements. The *tag* argument is the name of the tag, and the *method* argument is the function (method) which should be used to support semantic interpretation of the start tag. The *attributes* argument is a dictionary of attributes, the key being the *name* and the value being the *value* of the attribute found inside the tag's <> brackets. Character and entity references in the *value* have been interpreted. For instance, for the start tag , this method would be called as handle_starttag('A', self.elements['A'][0], {'HREF': 'http://www.cwi.nl/'}). The base implementation simply calls *method* with *attributes* as the only argument.

handle_endtag(tag, method)

This method is called to handle endtags for which an end tag handler is defined in the instance variable elements. The tag argument is the name of the tag, and the method argument is the function (method) which should be used to support semantic interpretation of the end tag. For instance, for the endtag , this method would be called as handle_endtag('A', self.elements['A'][1]). The base implementation simply calls method.

handle_data(data)

This method is called to process arbitrary data. It is intended to be overridden by a derived class; the base class implementation does nothing.

handle_charref(ref)

This method is called to process a character reference of the form '&#ref;'. ref can either be a decimal number, or a hexadecimal number when preceded by an 'x'. In the base implementation, ref must be a number in the range 0-255. It translates the character to ASCII and calls the method handle_data() with the character as argument. If ref is invalid or out of range, the method unknown_charref(ref) is called to handle the error. A subclass must override this method to provide support for character references outside of the ASCII range.

handle_comment(comment)

This method is called when a comment is encountered. The *comment* argument is a string containing the text between the '<!--' and '-->' delimiters, but not the delimiters themselves. For example, the comment '<!--text-->' will cause this method to be called with the argument 'text'. The default method does nothing.

handle_cdata(data)

This method is called when a CDATA element is encountered. The *data* argument is a string containing the text between the '<![CDATA[' and ']]>' delimiters, but not the delimiters themselves. For example, the entity '<![CDATA[text]]>' will cause this method to be called with the argument 'text'. The default method does nothing, and is intended to be overridden.

handle_proc(name, data)

This method is called when a processing instruction (PI) is encountered. The *name* is the PI target, and the *data* argument is a string containing the text between the PI target and the closing delimiter, but not the delimiter itself. For example, the instruction '<?XML text?>' will cause this method to be called with the arguments 'XML' and 'text'. The default method does nothing. Note that if a document starts with '<?xml ..?>', handle_xml() is called to handle it.

handle_special(data)

This method is called when a declaration is encountered. The *data* argument is a string containing the text between the '<!' and '>' delimiters, but not the delimiters themselves. For example, the entity declaration '<!ENTITY text>' will cause this method to be called with the argument 'ENTITY text'. The default method does nothing. Note that '<!DOCTYPE ...>' is handled separately if it is located at the start of the document.

syntax_error(message)

This method is called when a syntax error is encountered. The *message* is a description of what was wrong. The default method raises a RuntimeError exception. If this method is overridden, it is permissible for

it to return. This method is only called when the error can be recovered from. Unrecoverable errors raise a RuntimeError without first calling syntax_error().

unknown_starttag(tag, attributes)

This method is called to process an unknown start tag. It is intended to be overridden by a derived class; the base class implementation does nothing.

unknown_endtag(tag)

This method is called to process an unknown end tag. It is intended to be overridden by a derived class; the base class implementation does nothing.

unknown_charref(ref)

This method is called to process unresolvable numeric character references. It is intended to be overridden by a derived class; the base class implementation does nothing.

unknown_entityref(ref)

This method is called to process an unknown entity reference. It is intended to be overridden by a derived class; the base class implementation calls syntax_error() to signal an error.

See Also:

Extensible Markup Language (XML) 1.0

(http://www.w3.org/TR/REC-xml)

The XML specification, published by the World Wide Web Consortium (W3C), defines the syntax and processor requirements for XML. References to additional material on XML, including translations of the specification, are available at http://www.w3.org/XML/.

Python and XML Processing

(http://www.python.org/topics/xml/)

The Python XML Topic Guide provides a great deal of information on using XML from Python and links to other sources of information on XML.

SIG for XML Processing in Python

(http://www.python.org/sigs/xml-sig/)

The Python XML Special Interest Group is developing substantial support for processing XML from Python.

13.13.1 XML Namespaces

This module has support for XML namespaces as defined in the XML Namespaces proposed recommendation.

Tag and attribute names that are defined in an XML namespace are handled as if the name of the tag or element consisted of the namespace (the URL that defines the namespace) followed by a space and the name of the tag or attribute. For instance, the tag http://www.w3.org/TR/REC-html40">http://www.w3.org/TR/REC-html40 html:a href='http://frob.com'> inside the above mentioned element is treated as if the tag name were 'http://www.w3.org/TR/REC-html40 a' and the attribute name as if it were 'http://www.w3.org/TR/REC-html40 href'.

An older draft of the XML Namespaces proposal is also recognized, but triggers a warning.

See Also:

Namespaces in XML

(http://www.w3.org/TR/REC-xml-names/)

This World Wide Web Consortium recommendation describes the proper syntax and processing requirements for namespaces in XML.

Multimedia Services

The modules described in this chapter implement various algorithms or interfaces that are mainly useful for multimedia applications. They are available at the discretion of the installation. Here's an overview:

audioopimageopManipulate raw audio data.Manipulate raw image data.

Read and write audio files in AIFF or AIFC format.

Provide an interface to the Sun AU sound format.

Provide an interface to the WAV sound format.

chunk Module to read IFF chunks.

colorsys Conversion functions between RGB and other color systems.

rgbimg Read and write image files in "SGI RGB" format (the module is *not* SGI specific though!).

imghdr Determine the type of image contained in a file or byte stream.

sndhdr Determine type of a sound file.

ossaudiodev Access to OSS-compatible audio devices.

14.1 audioop — Manipulate raw audio data

The audioop module contains some useful operations on sound fragments. It operates on sound fragments consisting of signed integer samples 8, 16 or 32 bits wide, stored in Python strings. This is the same format as used by the al and sunaudiodev modules. All scalar items are integers, unless specified otherwise.

This module provides support for u-LAW and Intel/DVI ADPCM encodings.

A few of the more complicated operations only take 16-bit samples, otherwise the sample size (in bytes) is always a parameter of the operation.

The module defines the following variables and functions:

exception error

This exception is raised on all errors, such as unknown number of bytes per sample, etc.

add(fragment1, fragment2, width)

Return a fragment which is the addition of the two samples passed as parameters. *width* is the sample width in bytes, either 1, 2 or 4. Both fragments should have the same length.

adpcm2lin(adpcmfragment, width, state)

Decode an Intel/DVI ADPCM coded fragment to a linear fragment. See the description of lin2adpcm() for details on ADPCM coding. Return a tuple (*sample*, *newstate*) where the sample has the width specified in *width*.

adpcm32lin(adpcmfragment, width, state)

Decode an alternative 3-bit ADPCM code. See lin2adpcm3() for details.

avg(fragment, width)

Return the average over all samples in the fragment.

avgpp(fragment, width)

Return the average peak-peak value over all samples in the fragment. No filtering is done, so the usefulness

of this routine is questionable.

bias (fragment, width, bias)

Return a fragment that is the original fragment with a bias added to each sample.

cross (fragment, width)

Return the number of zero crossings in the fragment passed as an argument.

findfactor(fragment, reference)

Return a factor F such that rms(add(fragment, mul(reference, -F))) is minimal, i.e., return the factor with which you should multiply reference to make it match as well as possible to fragment. The fragments should both contain 2-byte samples.

The time taken by this routine is proportional to len(fragment).

findfit(fragment, reference)

Try to match *reference* as well as possible to a portion of *fragment* (which should be the longer fragment). This is (conceptually) done by taking slices out of *fragment*, using findfactor() to compute the best match, and minimizing the result. The fragments should both contain 2-byte samples. Return a tuple (*offset*, *factor*) where *offset* is the (integer) offset into *fragment* where the optimal match started and *factor* is the (floating-point) factor as per findfactor().

findmax(fragment, length)

Search fragment for a slice of length length samples (not bytes!) with maximum energy, i.e., return i for which rms (fragment[i*2:(i+length)*2]) is maximal. The fragments should both contain 2-byte samples.

The routine takes time proportional to len(fragment).

getsample(fragment, width, index)

Return the value of sample *index* from the fragment.

lin2lin(fragment, width, newwidth)

Convert samples between 1-, 2- and 4-byte formats.

lin2adpcm(fragment, width, state)

Convert samples to 4 bit Intel/DVI ADPCM encoding. ADPCM coding is an adaptive coding scheme, whereby each 4 bit number is the difference between one sample and the next, divided by a (varying) step. The Intel/DVI ADPCM algorithm has been selected for use by the IMA, so it may well become a standard. *state* is a tuple containing the state of the coder. The coder returns a tuple (*adpcmfrag*, *newstate*), and the

state is a tuple containing the state of the coder. The coder returns a tuple (adpcmfrag, newstate), and the newstate should be passed to the next call of lin2adpcm(). In the initial call, None can be passed as the state. adpcmfrag is the ADPCM coded fragment packed 2 4-bit values per byte.

lin2adpcm3(fragment, width, state)

This is an alternative ADPCM coder that uses only 3 bits per sample. It is not compatible with the Intel/DVI ADPCM coder and its output is not packed (due to laziness on the side of the author). Its use is discouraged.

lin2ulaw(fragment, width)

Convert samples in the audio fragment to u-LAW encoding and return this as a Python string. u-LAW is an audio encoding format whereby you get a dynamic range of about 14 bits using only 8 bit samples. It is used by the Sun audio hardware, among others.

minmax(fragment, width)

Return a tuple consisting of the minimum and maximum values of all samples in the sound fragment.

max(fragment, width)

Return the maximum of the absolute value of all samples in a fragment.

maxpp(fragment, width)

Return the maximum peak-peak value in the sound fragment.

$\mathbf{mul} \, (\mathit{fragment}, \, \mathit{width}, \, \mathit{factor} \,)$

Return a fragment that has all samples in the original fragment multiplied by the floating-point value *factor*. Overflow is silently ignored.

ratecv (fragment, width, nchannels, inrate, outrate, state[, weightA[, weightB]])

Convert the frame rate of the input fragment.

state is a tuple containing the state of the converter. The converter returns a tuple (newfragment, new-state), and newstate should be passed to the next call of ratecv(). The initial call should pass None as the state.

The weightA and weightB arguments are parameters for a simple digital filter and default to 1 and 0 respectively.

reverse(fragment, width)

Reverse the samples in a fragment and returns the modified fragment.

rms (fragment, width)

Return the root-mean-square of the fragment, i.e.

$$\sqrt{\frac{\sum S_i^2}{n}}$$

This is a measure of the power in an audio signal.

tomono (fragment, width, lfactor, rfactor)

Convert a stereo fragment to a mono fragment. The left channel is multiplied by *lfactor* and the right channel by *rfactor* before adding the two channels to give a mono signal.

tostereo(fragment, width, lfactor, rfactor)

Generate a stereo fragment from a mono fragment. Each pair of samples in the stereo fragment are computed from the mono sample, whereby left channel samples are multiplied by *lfactor* and right channel samples by *rfactor*.

ulaw2lin(fragment, width)

Convert sound fragments in u-LAW encoding to linearly encoded sound fragments. u-LAW encoding always uses 8 bits samples, so *width* refers only to the sample width of the output fragment here.

Note that operations such as mul() or max() make no distinction between mono and stereo fragments, i.e. all samples are treated equal. If this is a problem the stereo fragment should be split into two mono fragments first and recombined later. Here is an example of how to do that:

```
def mul_stereo(sample, width, lfactor, rfactor):
    lsample = audioop.tomono(sample, width, 1, 0)
    rsample = audioop.tomono(sample, width, 0, 1)
    lsample = audioop.mul(sample, width, lfactor)
    rsample = audioop.mul(sample, width, rfactor)
    lsample = audioop.tostereo(lsample, width, 1, 0)
    rsample = audioop.tostereo(rsample, width, 0, 1)
    return audioop.add(lsample, rsample, width)
```

If you use the ADPCM coder to build network packets and you want your protocol to be stateless (i.e. to be able to tolerate packet loss) you should not only transmit the data but also the state. Note that you should send the *initial* state (the one you passed to lin2adpcm()) along to the decoder, not the final state (as returned by the coder). If you want to use struct.struct() to store the state in binary you can code the first element (the predicted value) in 16 bits and the second (the delta index) in 8.

The ADPCM coders have never been tried against other ADPCM coders, only against themselves. It could well be that I misinterpreted the standards in which case they will not be interoperable with the respective standards.

The find*() routines might look a bit funny at first sight. They are primarily meant to do echo cancellation. A reasonably fast way to do this is to pick the most energetic piece of the output sample, locate that in the input sample and subtract the whole output sample from the input sample:

14.2 imageop — Manipulate raw image data

The imageop module contains some useful operations on images. It operates on images consisting of 8 or 32 bit pixels stored in Python strings. This is the same format as used by gl.lrectwrite() and the imgfile module.

The module defines the following variables and functions:

exception error

This exception is raised on all errors, such as unknown number of bits per pixel, etc.

```
crop(image, psize, width, height, x0, y0, x1, y1)
```

Return the selected part of *image*, which should by *width* by *height* in size and consist of pixels of *psize* bytes. x0, y0, x1 and y1 are like the gl.lrectread() parameters, i.e. the boundary is included in the new image. The new boundaries need not be inside the picture. Pixels that fall outside the old image will have their value set to zero. If x0 is bigger than x1 the new image is mirrored. The same holds for the y coordinates.

```
scale(image, psize, width, height, newwidth, newheight)
```

Return *image* scaled to size *newwidth* by *newheight*. No interpolation is done, scaling is done by simple-minded pixel duplication or removal. Therefore, computer-generated images or dithered images will not look nice after scaling.

```
tovideo(image, psize, width, height)
```

Run a vertical low-pass filter over an image. It does so by computing each destination pixel as the average of two vertically-aligned source pixels. The main use of this routine is to forestall excessive flicker if the image is displayed on a video device that uses interlacing, hence the name.

```
grey2mono(image, width, height, threshold)
```

Convert a 8-bit deep greyscale image to a 1-bit deep image by thresholding all the pixels. The resulting image is tightly packed and is probably only useful as an argument to mono2grey().

```
dither2mono(image, width, height)
```

Convert an 8-bit greyscale image to a 1-bit monochrome image using a (simple-minded) dithering algorithm.

```
mono2grey(image, width, height, p0, p1)
```

Convert a 1-bit monochrome image to an 8 bit greyscale or color image. All pixels that are zero-valued on input get value p0 on output and all one-value input pixels get value p1 on output. To convert a monochrome black-and-white image to greyscale pass the values 0 and 255 respectively.

```
grey2grey4(image, width, height)
```

Convert an 8-bit greyscale image to a 4-bit greyscale image without dithering.

```
grey2grey2(image, width, height)
```

Convert an 8-bit greyscale image to a 2-bit greyscale image without dithering.

```
dither2grey2(image, width, height)
```

Convert an 8-bit greyscale image to a 2-bit greyscale image with dithering. As for dither 2mono(), the dithering algorithm is currently very simple.

grey42grey(image, width, height)

Convert a 4-bit greyscale image to an 8-bit greyscale image.

grey22grey(image, width, height)

Convert a 2-bit greyscale image to an 8-bit greyscale image.

backward_compatible

If set to 0, the functions in this module use a non-backward compatible way of representing multi-byte pixels on little-endian systems. The SGI for which this module was originally written is a big-endian system, so setting this variable will have no effect. However, the code wasn't originally intended to run on anything else, so it made assumptions about byte order which are not universal. Setting this variable to 0 will cause the byte order to be reversed on little-endian systems, so that it then is the same as on big-endian systems.

14.3 aifc — Read and write AIFF and AIFC files

This module provides support for reading and writing AIFF and AIFF-C files. AIFF is Audio Interchange File Format, a format for storing digital audio samples in a file. AIFF-C is a newer version of the format that includes the ability to compress the audio data.

Caveat: Some operations may only work under IRIX; these will raise ImportError when attempting to import the cl module, which is only available on IRIX.

Audio files have a number of parameters that describe the audio data. The sampling rate or frame rate is the number of times per second the sound is sampled. The number of channels indicate if the audio is mono, stereo, or quadro. Each frame consists of one sample per channel. The sample size is the size in bytes of each sample. Thus a frame consists of *nchannels*samplesize* bytes, and a second's worth of audio consists of *nchannels*samplesize*framerate* bytes.

For example, CD quality audio has a sample size of two bytes (16 bits), uses two channels (stereo) and has a frame rate of 44,100 frames/second. This gives a frame size of 4 bytes (2*2), and a second's worth occupies 2*2*44100 bytes (176,400 bytes).

Module aifc defines the following function:

open(file, mode)

Open an AIFF or AIFF-C file and return an object instance with methods that are described below. The argument *file* is either a string naming a file or a file object. *mode* must be 'r' or 'rb' when the file must be opened for reading, or 'w' or 'wb' when the file must be opened for writing. If omitted, *file*. mode is used if it exists, otherwise 'rb' is used. When used for writing, the file object should be seekable, unless you know ahead of time how many samples you are going to write in total and use writeframesraw() and setnframes().

Objects returned by open () when a file is opened for reading have the following methods:

getnchannels()

Return the number of audio channels (1 for mono, 2 for stereo).

getsampwidth()

Return the size in bytes of individual samples.

getframerate()

Return the sampling rate (number of audio frames per second).

getnframes()

Return the number of audio frames in the file.

getcomptype()

Return a four-character string describing the type of compression used in the audio file. For AIFF files, the returned value is 'NONE'.

getcompname()

Return a human-readable description of the type of compression used in the audio file. For AIFF files, the returned value is 'not compressed'.

getparams()

Return a tuple consisting of all of the above values in the above order.

getmarkers()

Return a list of markers in the audio file. A marker consists of a tuple of three elements. The first is the mark ID (an integer), the second is the mark position in frames from the beginning of the data (an integer), the third is the name of the mark (a string).

getmark(id)

Return the tuple as described in getmarkers () for the mark with the given id.

readframes(nframes)

Read and return the next *nframes* frames from the audio file. The returned data is a string containing for each frame the uncompressed samples of all channels.

rewind()

Rewind the read pointer. The next readframes () will start from the beginning.

setpos(pos)

Seek to the specified frame number.

tell()

Return the current frame number.

close()

Close the AIFF file. After calling this method, the object can no longer be used.

Objects returned by open() when a file is opened for writing have all the above methods, except for readframes() and setpos(). In addition the following methods exist. The get*() methods can only be called after the corresponding set*() methods have been called. Before the first writeframes() or writeframesraw(), all parameters except for the number of frames must be filled in.

aiff()

Create an AIFF file. The default is that an AIFF-C file is created, unless the name of the file ends in '.aiff' in which case the default is an AIFF file.

aifc()

Create an AIFF-C file. The default is that an AIFF-C file is created, unless the name of the file ends in '.aiff' in which case the default is an AIFF file.

setnchannels(nchannels)

Specify the number of channels in the audio file.

setsampwidth(width)

Specify the size in bytes of audio samples.

setframerate(rate)

Specify the sampling frequency in frames per second.

setnframes(nframes)

Specify the number of frames that are to be written to the audio file. If this parameter is not set, or not set correctly, the file needs to support seeking.

setcomptype(type, name)

Specify the compression type. If not specified, the audio data will not be compressed. In AIFF files, compression is not possible. The name parameter should be a human-readable description of the compression type, the type parameter should be a four-character string. Currently the following compression types are supported: NONE, ULAW, ALAW, G722.

setparams (nchannels, sampwidth, framerate, comptype, compname)

Set all the above parameters at once. The argument is a tuple consisting of the various parameters. This means that it is possible to use the result of a getparams () call as argument to setparams ().

setmark(id, pos, name)

Add a mark with the given id (larger than 0), and the given name at the given position. This method can be

called at any time before close().

tell()

Return the current write position in the output file. Useful in combination with setmark().

writeframes(data)

Write data to the output file. This method can only be called after the audio file parameters have been set.

writeframesraw(data)

Like writeframes (), except that the header of the audio file is not updated.

close()

Close the AIFF file. The header of the file is updated to reflect the actual size of the audio data. After calling this method, the object can no longer be used.

14.4 sunau — Read and write Sun AU files

The sunau module provides a convenient interface to the Sun AU sound format. Note that this module is interface-compatible with the modules aifc and wave.

An audio file consists of a header followed by the data. The fields of the header are:

Field	Contents
magic word	The four bytes '.snd'.
header size	Size of the header, including info, in bytes.
data size	Physical size of the data, in bytes.
encoding	Indicates how the audio samples are encoded.
sample rate	The sampling rate.
# of channels	The number of channels in the samples.
info	ASCII string giving a description of the audio file (padded with null bytes).

Apart from the info field, all header fields are 4 bytes in size. They are all 32-bit unsigned integers encoded in big-endian byte order.

The sunau module defines the following functions:

open(file, mode)

If *file* is a string, open the file by that name, otherwise treat it as a seekable file-like object. *mode* can be any of

'r'Read only mode.

'w' Write only mode.

Note that it does not allow read/write files.

A mode of 'r' returns a AU_read object, while a mode of 'w' or 'wb' returns a AU_write object.

openfp(file, mode)

A synonym for open, maintained for backwards compatibility.

The sunau module defines the following exception:

exception Error

An error raised when something is impossible because of Sun AU specs or implementation deficiency.

The sunau module defines the following data items:

AUDIO_FILE_MAGIC

An integer every valid Sun AU file begins with, stored in big-endian form. This is the string '.snd' interpreted as an integer.

AUDIO_FILE_ENCODING_MULAW_8
AUDIO_FILE_ENCODING_LINEAR_8

AUDIO_FILE_ENCODING_LINEAR_16

```
AUDIO_FILE_ENCODING_LINEAR_24
```

AUDIO_FILE_ENCODING_LINEAR_32

AUDIO_FILE_ENCODING_ALAW_8

Values of the encoding field from the AU header which are supported by this module.

AUDIO_FILE_ENCODING_FLOAT

AUDIO_FILE_ENCODING_DOUBLE

AUDIO_FILE_ENCODING_ADPCM_G721

AUDIO_FILE_ENCODING_ADPCM_G722

AUDIO_FILE_ENCODING_ADPCM_G723_3

AUDIO_FILE_ENCODING_ADPCM_G723_5

Additional known values of the encoding field from the AU header, but which are not supported by this module.

14.4.1 AU_read Objects

AU_read objects, as returned by open() above, have the following methods:

close()

Close the stream, and make the instance unusable. (This is called automatically on deletion.)

getnchannels()

Returns number of audio channels (1 for mone, 2 for stereo).

getsampwidth()

Returns sample width in bytes.

getframerate()

Returns sampling frequency.

getnframes()

Returns number of audio frames.

getcomptype()

Returns compression type. Supported compression types are 'ULAW', 'ALAW' and 'NONE'.

getcompname()

Human-readable version of getcomptype(). The supported types have the respective names 'CCITT G.711 u-law', 'CCITT G.711 A-law' and 'not compressed'.

getparams()

Returns a tuple (nchannels, sampwidth, framerate, nframes, comptype, compname), equivalent to output of the get *() methods.

readframes(n)

Reads and returns at most n frames of audio, as a string of bytes. The data will be returned in linear format. If the original data is in u-LAW format, it will be converted.

rewind()

Rewind the file pointer to the beginning of the audio stream.

The following two methods define a term "position" which is compatible between them, and is otherwise implementation dependent.

setpos(pos)

Set the file pointer to the specified position. Only values returned from tell() should be used for pos.

tell()

Return current file pointer position. Note that the returned value has nothing to do with the actual position in the file.

The following two functions are defined for compatibility with the aifc, and don't do anything interesting.

getmarkers()

Returns None.

getmark(id)

Raise an error.

14.4.2 AU_write Objects

AU_write objects, as returned by open() above, have the following methods:

setnchannels(n)

Set the number of channels.

setsampwidth(n)

Set the sample width (in bytes.)

setframerate(n)

Set the frame rate.

setnframes(n)

Set the number of frames. This can be later changed, when and if more frames are written.

setcomptype(type, name)

Set the compression type and description. Only 'NONE' and 'ULAW' are supported on output.

setparams(tuple)

The tuple should be (nchannels, sampwidth, framerate, nframes, comptype, compname), with values valid for the set*() methods. Set all parameters.

tell()

Return current position in the file, with the same disclaimer for the AU_read.tell() and AU_read.setpos() methods.

writeframesraw(data)

Write audio frames, without correcting nframes.

writeframes(data)

Write audio frames and make sure *nframes* is correct.

close()

Make sure *nframes* is correct, and close the file.

This method is called upon deletion.

Note that it is invalid to set any parameters after calling writeframes() or writeframesraw().

14.5 wave — Read and write WAV files

The wave module provides a convenient interface to the WAV sound format. It does not support compression/decompression, but it does support mono/stereo.

The wave module defines the following function and exception:

```
open(file[, mode])
```

If file is a string, open the file by that name, other treat it as a seekable file-like object. mode can be any of

'r', 'rb' Read only mode.

'w', 'wb' Write only mode.

Note that it does not allow read/write WAV files.

A mode of 'r' or 'rb' returns a Wave_read object, while a mode of 'w' or 'wb' returns a Wave_write object. If mode is omitted and a file-like object is passed as file, file.mode is used as the default value for mode (the 'b' flag is still added if necessary).

openfp(file, mode)

A synonym for open (), maintained for backwards compatibility.

exception Error

An error raised when something is impossible because it violates the WAV specification or hits an implementation deficiency.

14.5.1 Wave_read Objects

Wave_read objects, as returned by open(), have the following methods:

close()

Close the stream, and make the instance unusable. This is called automatically on object collection.

getnchannels()

Returns number of audio channels (1 for mono, 2 for stereo).

getsampwidth()

Returns sample width in bytes.

getframerate()

Returns sampling frequency.

getnframes()

Returns number of audio frames.

getcomptype()

Returns compression type ('NONE' is the only supported type).

getcompname()

Human-readable version of getcomptype(). Usually 'not compressed' parallels 'NONE'.

getparams()

Returns a tuple (nchannels, sampwidth, framerate, nframes, comptype, compname), equivalent to output of the get*() methods.

readframes(n)

Reads and returns at most n frames of audio, as a string of bytes.

rewind()

Rewind the file pointer to the beginning of the audio stream.

The following two methods are defined for compatibility with the aifc module, and don't do anything interesting.

getmarkers()

Returns None.

$\mathtt{getmark}(\mathit{id})$

Raise an error.

The following two methods define a term "position" which is compatible between them, and is otherwise implementation dependent.

setpos(pos)

Set the file pointer to the specified position.

tell()

Return current file pointer position.

14.5.2 Wave_write Objects

Wave_write objects, as returned by open(), have the following methods:

close()

Make sure *nframes* is correct, and close the file. This method is called upon deletion.

setnchannels(n)

Set the number of channels.

setsampwidth(n)

Set the sample width to n bytes.

setframerate(n)

Set the frame rate to *n*.

setnframes(n)

Set the number of frames to *n*. This will be changed later if more frames are written.

setcomptype(type, name)

Set the compression type and description.

setparams(tuple)

The *tuple* should be (*nchannels*, *sampwidth*, *framerate*, *nframes*, *comptype*, *compname*), with values valid for the set*() methods. Sets all parameters.

tell()

Return current position in the file, with the same disclaimer for the Wave_read.tell() and Wave_read.setpos() methods.

writeframesraw(data)

Write audio frames, without correcting nframes.

writeframes(data)

Write audio frames and make sure nframes is correct.

Note that it is invalid to set any parameters after calling writeframes() or writeframesraw(), and any attempt to do so will raise wave. Error.

14.6 chunk — Read IFF chunked data

This module provides an interface for reading files that use EA IFF 85 chunks. This format is used in at least the Audio Interchange File Format (AIFF/AIFF-C) and the Real Media File Format (RMFF). The WAVE audio file format is closely related and can also be read using this module.

A chunk has the following structure:

Offset	Length	Contents
0	4	Chunk ID
4	4	Size of chunk in big-endian byte order, not including the header
8	n	Data bytes, where n is the size given in the preceding field
8 + n	0 or 1	Pad byte needed if <i>n</i> is odd and chunk alignment is used

The ID is a 4-byte string which identifies the type of chunk.

The size field (a 32-bit value, encoded using big-endian byte order) gives the size of the chunk data, not including the 8-byte header.

Usually an IFF-type file consists of one or more chunks. The proposed usage of the Chunk class defined here is to instantiate an instance at the start of each chunk and read from the instance until it reaches the end, after which a new instance can be instantiated. At the end of the file, creating a new instance will fail with a EOFError exception.

class Chunk (file, align, bigendian, inclheader)

Class which represents a chunk. The *file* argument is expected to be a file-like object. An instance of this class is specifically allowed. The only method that is needed is read(). If the methods seek() and tell() are present and don't raise an exception, they are also used. If these methods are present and raise an exception, they are expected to not have altered the object. If the optional argument *align* is true, chunks are assumed to be aligned on 2-byte boundaries. If *align* is false, no alignment is assumed. The default value is true. If the optional argument *bigendian* is false, the chunk size is assumed to be in little-endian order. This is needed for WAVE audio files. The default value is true. If the optional argument *inclheader* is true, the size given in the chunk header includes the size of the header. The default value is false.

¹"EA IFF 85" Standard for Interchange Format Files, Jerry Morrison, Electronic Arts, January 1985.

A Chunk object supports the following methods:

getname()

Returns the name (ID) of the chunk. This is the first 4 bytes of the chunk.

getsize()

Returns the size of the chunk.

close()

Close and skip to the end of the chunk. This does not close the underlying file.

The remaining methods will raise IOError if called after the close() method has been called.

isatty()

Returns False.

seek(pos[, whence])

Set the chunk's current position. The *whence* argument is optional and defaults to 0 (absolute file positioning); other values are 1 (seek relative to the current position) and 2 (seek relative to the file's end). There is no return value. If the underlying file does not allow seek, only forward seeks are allowed.

tell()

Return the current position into the chunk.

read([*size*])

Read at most *size* bytes from the chunk (less if the read hits the end of the chunk before obtaining *size* bytes). If the *size* argument is negative or omitted, read all data until the end of the chunk. The bytes are returned as a string object. An empty string is returned when the end of the chunk is encountered immediately.

skip()

Skip to the end of the chunk. All further calls to read() for the chunk will return ''. If you are not interested in the contents of the chunk, this method should be called so that the file points to the start of the next chunk.

14.7 colorsys — Conversions between color systems

The colorsys module defines bidirectional conversions of color values between colors expressed in the RGB (Red Green Blue) color space used in computer monitors and three other coordinate systems: YIQ, HLS (Hue Lightness Saturation) and HSV (Hue Saturation Value). Coordinates in all of these color spaces are floating point values. In the YIQ space, the Y coordinate is between 0 and 1, but the I and Q coordinates can be positive or negative. In all other spaces, the coordinates are all between 0 and 1.

More information about color spaces can be found at http://www.poynton.com/ColorFAQ.html.

The colorsys module defines the following functions:

$rgb_to_yiq(r, g, b)$

Convert the color from RGB coordinates to YIQ coordinates.

$yiq_to_rgb(y, i, q)$

Convert the color from YIQ coordinates to RGB coordinates.

rgb_to_hls(r, g, b)

Convert the color from RGB coordinates to HLS coordinates.

$hls_to_rgb(h, l, s)$

Convert the color from HLS coordinates to RGB coordinates.

$rgb_to_hsv(r, g, b)$

Convert the color from RGB coordinates to HSV coordinates.

$hsv_to_rgb(h, s, v)$

Convert the color from HSV coordinates to RGB coordinates.

Example:

```
>>> import colorsys
>>> colorsys.rgb_to_hsv(.3, .4, .2)
(0.25, 0.5, 0.4)
>>> colorsys.hsv_to_rgb(0.25, 0.5, 0.4)
(0.3, 0.4, 0.2)
```

14.8 rgbimg — Read and write "SGI RGB" files

The rgbimg module allows Python programs to access SGI imglib image files (also known as '.rgb' files). The module is far from complete, but is provided anyway since the functionality that there is enough in some cases. Currently, colormap files are not supported.

Note: This module is only built by default for 32-bit platforms; it is not expected to work properly on other systems.

The module defines the following variables and functions:

exception error

This exception is raised on all errors, such as unsupported file type, etc.

sizeofimage(file)

This function returns a tuple (x, y) where x and y are the size of the image in pixels. Only 4 byte RGBA pixels, 3 byte RGB pixels, and 1 byte greyscale pixels are currently supported.

longimagedata(file)

This function reads and decodes the image on the specified file, and returns it as a Python string. The string has 4 byte RGBA pixels. The bottom left pixel is the first in the string. This format is suitable to pass to gl.lrectwrite(), for instance.

longstoimage(data, x, y, z, file)

This function writes the RGBA data in *data* to image file *file*. x and y give the size of the image. z is 1 if the saved image should be 1 byte greyscale, 3 if the saved image should be 3 byte RGB data, or 4 if the saved images should be 4 byte RGBA data. The input data always contains 4 bytes per pixel. These are the formats returned by gl.lrectread().

ttob(flag)

This function sets a global flag which defines whether the scan lines of the image are read or written from bottom to top (flag is zero, compatible with SGI GL) or from top to bottom(flag is one, compatible with X). The default is zero.

14.9 imghdr — Determine the type of an image

The imghdr module determines the type of image contained in a file or byte stream.

The imghdr module defines the following function:

what (filename[, h])

Tests the image data contained in the file named by *filename*, and returns a string describing the image type. If optional *h* is provided, the *filename* is ignored and *h* is assumed to contain the byte stream to test.

The following image types are recognized, as listed below with the return value from what ():

Value	Image format
'rgb'	SGI ImgLib Files
'gif'	GIF 87a and 89a Files
'pbm'	Portable Bitmap Files
'pgm'	Portable Graymap Files
'ppm'	Portable Pixmap Files
'tiff'	TIFF Files
'rast'	Sun Raster Files
'xbm'	X Bitmap Files
'jpeg'	JPEG data in JFIF format
'bmp'	BMP files
'png'	Portable Network Graphics

You can extend the list of file types imghdr can recognize by appending to this variable:

tests

A list of functions performing the individual tests. Each function takes two arguments: the byte-stream and an open file-like object. When what () is called with a byte-stream, the file-like object will be None.

The test function should return a string describing the image type if the test succeeded, or None if it failed.

Example:

```
>>> import imghdr
>>> imghdr.what('/tmp/bass.gif')
'gif'
```

14.10 sndhdr — Determine type of sound file

The sndhdr provides utility functions which attempt to determine the type of sound data which is in a file. When these functions are able to determine what type of sound data is stored in a file, they return a tuple (type, sampling_rate, channels, frames, bits_per_sample). The value for type indicates the data type and will be one of the strings 'aifc', 'aiff', 'au', 'hcom', 'sndr', 'sndt', 'voc', 'wav', '8svx', 'sb', 'ub', or 'ul'. The sampling_rate will be either the actual value or 0 if unknown or difficult to decode. Similarly, channels will be either the number of channels or 0 if it cannot be determined or if the value is difficult to decode. The value for frames will be either the number of frames or -1. The last item in the tuple, bits_per_sample, will either be the sample size in bits or 'A' for A-LAW or 'U' for u-LAW.

what (filename)

Determines the type of sound data stored in the file *filename* using whathdr(). If it succeeds, returns a tuple as described above, otherwise None is returned.

whathdr(filename)

Determines the type of sound data stored in a file based on the file header. The name of the file is given by *filename*. This function returns a tuple as described above on success, or None.

14.11 ossaudiodev — Access to OSS-compatible audio devices

New in version 2.3.

This module allows you to access the OSS (Open Sound System) audio interface. OSS is available for a wide range of open-source and commercial Unices, and is the standard audio interface for Linux and recent versions of FreeBSD.

See Also:

Open Sound System Programmer's Guide

(http://www.opensound.com/pguide/oss.pdf)

the official documentation for the OSS C API

The module defines a large number of constants supplied by the OSS device driver; see <sys/soundcard.h> on either Linux or FreeBSD for a listing.

ossaudiodev defines the following variables and functions:

exception OSSAudioError

This exception is raised on certain errors. The argument is a string describing what went wrong.

(If ossaudiodev receives an error from a system call such as open(), write(), or ioctl(), it raises IOError. Errors detected directly by ossaudiodev result in OSSAudioError.)

(For backwards compatibility, the exception class is also available as ossaudiodev.error.)

open([device,]mode)

Open an audio device and return an OSS audio device object. This object supports many file-like methods, such as read(), write(), and fileno() (although there are subtle differences between conventional Unix read/write semantics and those of OSS audio devices). It also supports a number of audio-specific methods; see below for the complete list of methods.

device is the audio device filename to use. If it is not specified, this module first looks in the environment variable AUDIODEV for a device to use. If not found, it falls back to '/dev/dsp'.

mode is one of 'r' for read-only (record) access, 'w' for write-only (playback) access and 'rw' for both. Since many sound cards only allow one process to have the recorder or player open at a time, it is a good idea to open the device only for the activity needed. Further, some sound cards are half-duplex: they can be opened for reading or writing, but not both at once.

Note the unusual calling syntax: the *first* argument is optional, and the second is required. This is a historical artifact for compatibility with the older linuxaudiodev module which ossaudiodev supersedes.

openmixer([device])

Open a mixer device and return an OSS mixer device object. *device* is the mixer device filename to use. If it is not specified, this module first looks in the environment variable MIXERDEV for a device to use. If not found, it falls back to '/dev/mixer'.

14.11.1 Audio Device Objects

Before you can write to or read from an audio device, you must call three methods in the correct order:

- 1. setfmt() to set the output format
- 2. channels () to set the number of channels
- 3. speed() to set the sample rate

Alternately, you can use the setparameters () method to set all three audio parameters at once. This is more convenient, but may not be as flexible in all cases.

The audio device objects returned by open() define the following methods:

close()

Explicitly close the audio device. When you are done writing to or reading from an audio device, you should explicitly close it. A closed device cannot be used again.

fileno()

Return the file descriptor associated with the device.

read(size)

Read *size* bytes from the audio input and return them as a Python string. Unlike most UNIX device drivers, OSS audio devices in blocking mode (the default) will block read() until the entire requested amount of data is available.

write(data)

Write the Python string data to the audio device and return the number of bytes written. If the audio

device is in blocking mode (the default), the entire string is always written (again, this is different from usual UNIX device semantics). If the device is in non-blocking mode, some data may not be written—see writeall().

writeall(data)

Write the entire Python string *data* to the audio device: waits until the audio device is able to accept data, writes as much data as it will accept, and repeats until *data* has been completely written. If the device is in blocking mode (the default), this has the same effect as write(); writeall() is only useful in non-blocking mode. Has no return value, since the amount of data written is always equal to the amount of data supplied.

The following methods each map to exactly one <code>ioctl()</code> system call. The correspondence is obvious: for example, <code>setfmt()</code> corresponds to the <code>SNDCTL_DSP_SETFMT</code> ioctl, and <code>sync()</code> to <code>SNDCTL_DSP_SYNC</code> (this can be useful when consulting the OSS documentation). If the underlying <code>ioctl()</code> fails, they all raise <code>IOError</code>.

nonblock()

Put the device into non-blocking mode. Once in non-blocking mode, there is no way to return it to blocking mode.

getfmts()

Return a bitmask of the audio output formats supported by the soundcard. Some of the formats supported by OSS are:

Format	Description
AFMT_MU_LAW	a logarithmic encoding (used by Sun .au files and /dev/audio)
AFMT_A_LAW	a logarithmic encoding
AFMT_IMA_ADPCM	a 4:1 compressed format defined by the Interactive Multimedia Association
AFMT_U8	Unsigned, 8-bit audio
AFMT_S16_LE	Signed, 16-bit audio, little-endian byte order (as used by Intel processors)
AFMT_S16_BE	Signed, 16-bit audio, big-endian byte order (as used by 68k, PowerPC, Sparc)
AFMT_S8	Signed, 8 bit audio
AFMT_U16_LE	Unsigned, 16-bit little-endian audio
AFMT_U16_BE	Unsigned, 16-bit big-endian audio

Consult the OSS documentation for a full list of audio formats, and note that most devices support only a subset of these formats. Some older devices only support AFMT_U8; the most common format used today is AFMT_S16_LE.

setfmt(format)

Try to set the current audio format to *format*—see getfmts() for a list. Returns the audio format that the device was set to, which may not be the requested format. May also be used to return the current audio format—do this by passing an "audio format" of AFMT_QUERY.

channels(nchannels)

Set the number of output channels to *nchannels*. A value of 1 indicates monophonic sound, 2 stereophonic. Some devices may have more than 2 channels, and some high-end devices may not support mono. Returns the number of channels the device was set to.

speed(samplerate)

Try to set the audio sampling rate to *samplerate* samples per second. Returns the rate actually set. Most sound devices don't support arbitrary sampling rates. Common rates are:

Rate	Description	
8000	default rate for /dev/audio	
11025	speech recording	
22050		
44100	CD quality audio (at 16 bits/sample and 2 channels)	
96000	DVD quality audio (at 24 bits/sample)	

sync()

Wait until the sound device has played every byte in its buffer. (This happens implicitly when the device is closed.) The OSS documentation recommends closing and re-opening the device rather than using sync().

reset()

Immediately stop playing or recording and return the device to a state where it can accept commands. The OSS documentation recommends closing and re-opening the device after calling reset().

post()

Tell the driver that there is likely to be a pause in the output, making it possible for the device to handle the pause more intelligently. You might use this after playing a spot sound effect, before waiting for user input, or before doing disk I/O.

The following convenience methods combine several ioctls, or one ioctl and some simple calculations.

```
setparameters(format, nchannels, samplerate [, strict=False])
```

Set the key audio sampling parameters—sample format, number of channels, and sampling rate—in one method call. *format*, *nchannels*, and *samplerate* should be as specified in the setfmt(), channels(), and speed() methods. If *strict* is true, setparameters() checks to see if each parameter was actually set to the requested value, and raises OSSAudioError if not. Returns a tuple (*format*, *nchannels*, *samplerate*) indicating the parameter values that were actually set by the device driver (i.e., the same as the return values of setfmt(), channels(), and speed()).

For example,

```
(fmt, channels, rate) = dsp.setparameters(fmt, channels, rate)
is equivalent to

fmt = dsp.setfmt(fmt)
    channels = dsp.channels(channels)
    rate = dsp.rate(channels)
```

bufsize()

Returns the size of the hardware buffer, in samples.

obufcount()

Returns the number of samples that are in the hardware buffer yet to be played.

obuffree()

Returns the number of samples that could be queued into the hardware buffer to be played without blocking.

14.11.2 Mixer Device Objects

The mixer object provides two file-like methods:

close()

This method closes the open mixer device file. Any further attempts to use the mixer after this file is closed will raise an IOError.

fileno()

Returns the file handle number of the open mixer device file.

The remaining methods are specific to audio mixing:

controls()

This method returns a bitmask specifying the available mixer controls ("Control" being a specific mixable "channel", such as SOUND_MIXER_PCM or SOUND_MIXER_SYNTH). This bitmask indicates a subset of all available mixer controls—the SOUND_MIXER_* constants defined at module level. To determine if, for example, the current mixer object supports a PCM mixer, use the following Python code:

```
mixer=ossaudiodev.openmixer()
if mixer.controls() & (1 << ossaudiodev.SOUND_MIXER_PCM):
    # PCM is supported
    ... code ...</pre>
```

For most purposes, the SOUND_MIXER_VOLUME (master volume) and SOUND_MIXER_PCM controls should suffice—but code that uses the mixer should be flexible when it comes to choosing mixer controls.

On the Gravis Ultrasound, for example, SOUND_MIXER_VOLUME does not exist.

stereocontrols()

Returns a bitmask indicating stereo mixer controls. If a bit is set, the corresponding control is stereo; if it is unset, the control is either monophonic or not supported by the mixer (use in combination with controls() to determine which).

See the code example for the controls() function for an example of getting data from a bitmask.

reccontrols()

Returns a bitmask specifying the mixer controls that may be used to record. See the code example for controls() for an example of reading from a bitmask.

get(control)

Returns the volume of a given mixer control. The returned volume is a 2-tuple ($left_volume,right_volume$). Volumes are specified as numbers from 0 (silent) to 100 (full volume). If the control is monophonic, a 2-tuple is still returned, but both volumes are the same.

Raises OSSAudioError if an invalid control was is specified, or IOError if an unsupported control is specified.

set(control, (left, right))

Sets the volume for a given mixer control to (left,right). left and right must be ints and between 0 (silent) and 100 (full volume). On success, the new volume is returned as a 2-tuple. Note that this may not be exactly the same as the volume specified, because of the limited resolution of some soundcard's mixers.

Raises OSSAudioError if an invalid mixer control was specified, or if the specified volumes were out-of-range.

get_recsrc()

This method returns a bitmask indicating which control(s) are currently being used as a recording source.

set_recsrc(bitmask)

Call this function to specify a recording source. Returns a bitmask indicating the new recording source (or sources) if successful; raises IOError if an invalid source was specified. To set the current recording source to the microphone input:

mixer.setrecsrc (1 << ossaudiodev.SOUND_MIXER_MIC)</pre>

Cryptographic Services

The modules described in this chapter implement various algorithms of a cryptographic nature. They are available at the discretion of the installation. Here's an overview:

hmac Keyed-Hashing for Message Authentication (HMAC) implementation for Python.

md5 RSA's MD5 message digest algorithm.

sha NIST's secure hash algorithm, SHA.

Hardcore cypherpunks will probably find the cryptographic modules written by A.M. Kuchling of further interest; the package adds built-in modules for DES and IDEA encryption, provides a Python module for reading and decrypting PGP files, and then some. These modules are not distributed with Python but available separately. See the URL http://www.amk.ca/python/code/crypto.html for more information.

15.1 hmac — Keyed-Hashing for Message Authentication

New in version 2.2.

This module implements the HMAC algorithm as described by RFC 2104.

new(key[, msg[, digestmod]])

Return a new hmac object. If msg is present, the method call update (msg) is made. digest mod is the digest module for the HMAC object to use. It defaults to the md5 module.

An HMAC object has the following methods:

update (msg)

Update the hmac object with the string msg. Repeated calls are equivalent to a single call with the concatenation of all the arguments: m.update(a); m.update(b) is equivalent to m.update(a + b).

digest()

Return the digest of the strings passed to the update() method so far. This is a 16-byte string (for md5) or a 20-byte string (for sha) which may contain non-ASCII characters, including NUL bytes.

hexdigest()

Like digest() except the digest is returned as a string of length 32 for md5 (40 for sha), containing only hexadecimal digits. This may be used to exchange the value safely in email or other non-binary environments.

copy()

Return a copy ("clone") of the hmac object. This can be used to efficiently compute the digests of strings that share a common initial substring.

15.2 md5 — MD5 message digest algorithm

This module implements the interface to RSA's MD5 message digest algorithm (see also Internet RFC 1321). Its use is quite straightforward: use new() to create an md5 object. You can now feed this object with arbitrary strings using the update() method, and at any point you can ask it for the *digest* (a strong kind of 128-bit

checksum, a.k.a. "fingerprint") of the concatenation of the strings fed to it so far using the digest() method.

For example, to obtain the digest of the string 'Nobody inspects the spammish repetition':

```
>>> import md5
>>> m = md5.new()
>>> m.update("Nobody inspects")
>>> m.update(" the spammish repetition")
>>> m.digest()
'\xbbd\x9c\x83\xdd\x1e\xa5\xc9\xd9\xde\xc9\xa1\x8d\xf0\xff\xe9'
```

More condensed:

```
>>> md5.new("Nobody inspects the spammish repetition").digest()
'\xbbd\x9c\x83\xdd\x1e\xa5\xc9\xd9\xde\xc9\xa1\x8d\xf0\xff\xe9'
```

The following values are provided as constants in the module and as attributes of the md5 objects returned by new():

digest_size

The size of the resulting digest in bytes. This is always 16.

md5 objects support the following methods:

```
new([arg])
```

Return a new md5 object. If arg is present, the method call update (arg) is made.

md5([arg])

For backward compatibility reasons, this is an alternative name for the new() function.

An md5 object has the following methods:

update(arg)

Update the md5 object with the string *arg*. Repeated calls are equivalent to a single call with the concatenation of all the arguments: m.update(a); m.update(b) is equivalent to m.update(a+b).

digest()

Return the digest of the strings passed to the update() method so far. This is a 16-byte string which may contain non-ASCII characters, including null bytes.

hexdigest()

Like digest () except the digest is returned as a string of length 32, containing only hexadecimal digits. This may be used to exchange the value safely in email or other non-binary environments.

copy()

Return a copy ("clone") of the md5 object. This can be used to efficiently compute the digests of strings that share a common initial substring.

See Also:

```
Module sha (section 15.3):
```

Similar module implementing the Secure Hash Algorithm (SHA). The SHA algorithm is considered a more secure hash.

15.3 sha — SHA-1 message digest algorithm

This module implements the interface to NIST's secure hash algorithm, known as SHA-1. SHA-1 is an improved version of the original SHA hash algorithm. It is used in the same way as the md5 module: use new() to create an sha object, then feed this object with arbitrary strings using the update() method, and at any point you can ask it for the *digest* of the concatenation of the strings fed to it so far. SHA-1 digests are 160 bits instead of MD5's 128 bits.

new([string])

Return a new sha object. If string is present, the method call update (string) is made.

The following values are provided as constants in the module and as attributes of the sha objects returned by new():

blocksize

Size of the blocks fed into the hash function; this is always 1. This size is used to allow an arbitrary string to be hashed.

digest_size

The size of the resulting digest in bytes. This is always 20.

An sha object has the same methods as md5 objects:

update(arg)

Update the sha object with the string arg. Repeated calls are equivalent to a single call with the concatenation of all the arguments: m.update(a); m.update(b) is equivalent to m.update(a+b).

digest()

Return the digest of the strings passed to the update() method so far. This is a 20-byte string which may contain non-ASCII characters, including null bytes.

hexdigest()

Like digest () except the digest is returned as a string of length 40, containing only hexadecimal digits. This may be used to exchange the value safely in email or other non-binary environments.

copy()

Return a copy ("clone") of the sha object. This can be used to efficiently compute the digests of strings that share a common initial substring.

See Also:

Secure Hash Standard

(http://csrc.nist.gov/publications/fips/fips180-2/fips180-2withchangenotice.pdf)

The Secure Hash Algorithm is defined by NIST document FIPS PUB 180-2: *Secure Hash Standard*, published in August 2002.

Cryptographic Toolkit (Secure Hashing)

(http://csrc.nist.gov/encryption/tkhash.html)

Links from NIST to various information on secure hashing.

Graphical User Interfaces with Tk

Tk/Tcl has long been an integral part of Python. It provides a robust and platform independent windowing toolkit, that is available to Python programmers using the Tkinter module, and its extension, the Tix module.

The Tkinter module is a thin object-oriented layer on top of Tcl/Tk. To use Tkinter, you don't need to write Tcl code, but you will need to consult the Tk documentation, and occasionally the Tcl documentation. Tkinter is a set of wrappers that implement the Tk widgets as Python classes. In addition, the internal module _tkinter provides a threadsafe mechanism which allows Python and Tcl to interact.

Tk is not the only GUI for Python, but is however the most commonly used one; see section ??, "Other User Interface Modules and Packages," for more information on other GUI toolkits for Python.

Tkinter Interface to Tcl/Tk for graphical user interfaces

Tix Tk Extension Widgets for Tkinter

ScrolledText Text widget with a vertical scroll bar.

An environment for turtle graphics.

16.1 Tkinter — Python interface to Tcl/Tk

The Tkinter module ("Tk interface") is the standard Python interface to the Tk GUI toolkit. Both Tk and Tkinter are available on most UNIX platforms, as well as on Windows and Macintosh systems. (Tk itself is not part of Python; it is maintained at ActiveState.)

See Also:

Python Tkinter Resources

(http://www.python.org/topics/tkinter/)

The Python Tkinter Topic Guide provides a great deal of information on using Tk from Python and links to other sources of information on Tk.

An Introduction to Tkinter

(http://www.pythonware.com/library/an-introduction-to-tkinter.htm)

Fredrik Lundh's on-line reference material.

Tkinter reference: a GUI for Python

(http://www.nmt.edu/tcc/help/pubs/lang.html)

On-line reference material.

Tkinter for JPython

(http://jtkinter.sourceforge.net)

The Jython interface to Tkinter.

Python and Tkinter Programming

(http://www.amazon.com/exec/obidos/ASIN/1884777813)

The book by John Grayson (ISBN 1-884777-81-3).

16.1.1 Tkinter Modules

Most of the time, the Tkinter module is all you really need, but a number of additional modules are available as well. The Tk interface is located in a binary module named _tkinter. This module contains the low-level interface to Tk, and should never be used directly by application programmers. It is usually a shared library (or DLL), but might in some cases be statically linked with the Python interpreter.

In addition to the Tk interface module, Tkinter includes a number of Python modules. The two most important modules are the Tkinter module itself, and a module called Tkconstants. The former automatically imports the latter, so to use Tkinter, all you need to do is to import one module:

```
import Tkinter
```

Or, more often:

```
from Tkinter import *
```

class Tk (screenName=None, baseName=None, className='Tk', useTk=1)

The Tk class is instantiated without arguments. This creates a toplevel widget of Tk which usually is the main window of an application. Each instance has its own associated Tcl interpreter. Changed in version 2.4: The *useTk* parameter was added.

Tcl (screenName=None, baseName=None, className='Tk', useTk=0)

The Tcl function is a factory function which creates an object much like that created by the Tk class, except that it does not initialize the Tk subsystem. This is most often useful when driving the Tcl interpreter in an environment where one doesn't want to create extraneous toplevel windows, or where one cannot (i.e. Unix/Linux systems without an X server). An object created by the Tcl object can have a Toplevel window created (and the Tk subsystem initialized) by calling its loadtk method. New in version 2.4.

Other modules that provide Tk support include:

ScrolledText Text widget with a vertical scroll bar built in.

tkColorChooser Dialog to let the user choose a color.

tkCommonDialog Base class for the dialogs defined in the other modules listed here.

tkFileDialog Common dialogs to allow the user to specify a file to open or save.

tkFont Utilities to help work with fonts.

tkMessageBox Access to standard Tk dialog boxes.

tkSimpleDialog Basic dialogs and convenience functions.

Tkdnd Drag-and-drop support for **Tkinter**. This is experimental and should become deprecated when it is replaced with the Tk DND.

turtle Turtle graphics in a Tk window.

16.1.2 Tkinter Life Preserver

This section is not designed to be an exhaustive tutorial on either Tk or Tkinter. Rather, it is intended as a stop gap, providing some introductory orientation on the system.

Credits:

- Tkinter was written by Steen Lumholt and Guido van Rossum.
- Tk was written by John Ousterhout while at Berkeley.
- This Life Preserver was written by Matt Conway at the University of Virginia.

- The html rendering, and some liberal editing, was produced from a FrameMaker version by Ken Manheimer.
- Fredrik Lundh elaborated and revised the class interface descriptions, to get them current with Tk 4.2.
- Mike Clarkson converted the documentation to LaTeX, and compiled the User Interface chapter of the reference manual.

How To Use This Section

This section is designed in two parts: the first half (roughly) covers background material, while the second half can be taken to the keyboard as a handy reference.

When trying to answer questions of the form "how do I do blah", it is often best to find out how to do"blah" in straight Tk, and then convert this back into the corresponding Tkinter call. Python programmers can often guess at the correct Python command by looking at the Tk documentation. This means that in order to use Tkinter, you will have to know a little bit about Tk. This document can't fulfill that role, so the best we can do is point you to the best documentation that exists. Here are some hints:

- The authors strongly suggest getting a copy of the Tk man pages. Specifically, the man pages in the mann directory are most useful. The man3 man pages describe the C interface to the Tk library and thus are not especially helpful for script writers.
- Addison-Wesley publishes a book called *Tcl and the Tk Toolkit* by John Ousterhout (ISBN 0-201-63337-X) which is a good introduction to Tcl and Tk for the novice. The book is not exhaustive, and for many details it defers to the man pages.
- 'Tkinter.py' is a last resort for most, but can be a good place to go when nothing else makes sense.

See Also:

ActiveState Tcl Home Page (http://tcl.activestate.com/)

The Tk/Tcl development is largely taking place at ActiveState.

Tcl and the Tk Toolkit

(http://www.amazon.com/exec/obidos/ASIN/020163337X)

The book by John Ousterhout, the inventor of Tcl.

Practical Programming in Tcl and Tk

(http://www.amazon.com/exec/obidos/ASIN/0130220280)

Brent Welch's encyclopedic book.

A Simple Hello World Program

```
from Tkinter import *
class Application(Frame):
    def say_hi(self):
       print "hi there, everyone!"
    def createWidgets(self):
        self.QUIT = Button(self)
        self.QUIT["text"] = "QUIT"
        self.QUIT["fg"] = "red"
        self.QUIT["command"] = self.quit
        self.QUIT.pack({"side": "left"})
        self.hi_there = Button(self)
        self.hi_there["text"] = "Hello",
        self.hi_there["command"] = self.say_hi
        self.hi_there.pack({"side": "left"})
    def __init__(self, master=None):
        Frame.__init__(self, master)
        self.pack()
        self.createWidgets()
root = Tk()
app = Application(master=root)
app.mainloop()
root.destroy()
```

16.1.3 A (Very) Quick Look at Tcl/Tk

The class hierarchy looks complicated, but in actual practice, application programmers almost always refer to the classes at the very bottom of the hierarchy.

Notes:

- These classes are provided for the purposes of organizing certain functions under one namespace. They aren't meant to be instantiated independently.
- The Tk class is meant to be instantiated only once in an application. Application programmers need not instantiate one explicitly, the system creates one whenever any of the other classes are instantiated.
- The Widget class is not meant to be instantiated, it is meant only for subclassing to make "real" widgets (in C++, this is called an 'abstract class').

To make use of this reference material, there will be times when you will need to know how to read short passages of Tk and how to identify the various parts of a Tk command. (See section 16.1.4 for the Tkinter equivalents of what's below.)

Tk scripts are Tcl programs. Like all Tcl programs, Tk scripts are just lists of tokens separated by spaces. A Tk widget is just its *class*, the *options* that help configure it, and the *actions* that make it do useful things.

To make a widget in Tk, the command is always of the form:

classCommand newPathname options

classCommand denotes which kind of widget to make (a button, a label, a menu...)

newPathname is the new name for this widget. All names in Tk must be unique. To help enforce this, widgets in Tk are named with pathnames, just like files in a file system. The top level widget, the root, is called . (period) and children are delimited by more periods. For example, .myApp.controlPanel.okButton might be the name of a widget.

options configure the widget's appearance and in some cases, its behavior. The options come in the form of a list of flags and values. Flags are proceeded by a '-', like unix shell command flags, and values are put in quotes if they are more than one word.

For example:

Once created, the pathname to the widget becomes a new command. This new *widget command* is the programmer's handle for getting the new widget to perform some *action*. In C, you'd express this as someAction(fred, someOptions), in C++, you would express this as fred.someAction(someOptions), and in Tk, you say:

```
.fred someAction someOptions
```

Note that the object name, .fred, starts with a dot.

As you'd expect, the legal values for *someAction* will depend on the widget's class: .fred disable works if fred is a button (fred gets greyed out), but does not work if fred is a label (disabling of labels is not supported in Tk).

The legal values of *someOptions* is action dependent. Some actions, like disable, require no arguments, others, like a text-entry box's delete command, would need arguments to specify what range of text to delete.

16.1.4 Mapping Basic Tk into Tkinter

Class commands in Tk correspond to class constructors in Tkinter.

```
button .fred =====> fred = Button()
```

The master of an object is implicit in the new name given to it at creation time. In Tkinter, masters are specified explicitly.

```
button .panel.fred =====> fred = Button(panel)
```

The configuration options in Tk are given in lists of hyphened tags followed by values. In Tkinter, options are specified as keyword-arguments in the instance constructor, and keyword-args for configure calls or as instance indices, in dictionary style, for established instances. See section 16.1.6 on setting options.

In Tk, to perform an action on a widget, use the widget name as a command, and follow it with an action name, possibly with arguments (options). In Tkinter, you call methods on the class instance to invoke actions on the widget. The actions (methods) that a given widget can perform are listed in the Tkinter.py module.

```
.fred invoke ====> fred.invoke()
```

To give a widget to the packer (geometry manager), you call pack with optional arguments. In Tkinter, the Pack class holds all this functionality, and the various forms of the pack command are implemented as methods. All widgets in Tkinter are subclassed from the Packer, and so inherit all the packing methods. See the Tix module documentation for additional information on the Form geometry manager.

```
pack .fred -side left =====> fred.pack(side = "left")
```

16.1.5 How Tk and Tkinter are Related

Note: This was derived from a graphical image; the image will be used more directly in a subsequent version of this document.

From the top down:

Your App Here (Python) A Python application makes a Tkinter call.

Tkinter (**Python Module**) This call (say, for example, creating a button widget), is implemented in the *Tkinter* module, which is written in Python. This Python function will parse the commands and the arguments and convert them into a form that makes them look as if they had come from a Tk script instead of a Python script.

tkinter (**C**) These commands and their arguments will be passed to a C function in the *tkinter* - note the lowercase – extension module.

Tk Widgets (**C** and **Tcl**) This C function is able to make calls into other C modules, including the C functions that make up the Tk library. Tk is implemented in C and some Tcl. The Tcl part of the Tk widgets is used to bind certain default behaviors to widgets, and is executed once at the point where the Python **Tkinter** module is imported. (The user never sees this stage).

 $Tk_{\underline{\ }}(C)$ The Tk part of the Tk Widgets implement the final mapping to ...

Xlib (C) the Xlib library to draw graphics on the screen.

16.1.6 Handy Reference

Setting Options

Options control things like the color and border width of a widget. Options can be set in three ways:

At object creation time, using keyword arguments:

```
fred = Button(self, fg = "red", bg = "blue")
```

After object creation, treating the option name like a dictionary index :

```
fred["fg"] = "red"
fred["bg"] = "blue"
```

Use the config() method to update multiple attrs subsequent to object creation:

```
fred.config(fg = "red", bg = "blue")
```

For a complete explanation of a given option and its behavior, see the Tk man pages for the widget in question.

Note that the man pages list "STANDARD OPTIONS" and "WIDGET SPECIFIC OPTIONS" for each widget. The former is a list of options that are common to many widgets, the latter are the options that are ideosyncratic to that particular widget. The Standard Options are documented on the *options*(3) man page.

No distinction between standard and widget-specific options is made in this document. Some options don't apply to some kinds of widgets. Whether a given widget responds to a particular option depends on the class of the widget; buttons have a command option, labels do not.

The options supported by a given widget are listed in that widget's man page, or can be queried at runtime by calling the config() method without arguments, or by calling the keys() method on that widget. The return value of these calls is a dictionary whose key is the name of the option as a string (for example, 'relief') and whose values are 5-tuples.

Some options, like bg are synonyms for common options with long names (bg is shorthand for "background"). Passing the config() method the name of a shorthand option will return a 2-tuple, not 5-tuple. The 2-tuple passed back will contain the name of the synonym and the "real" option (such as ('bg', 'background')).

Index	Meaning	Example
0	option name	'relief'
1	option name for database lookup	'relief'
2	option class for database lookup	'Relief'
3	default value	'raised'
4	current value	'groove'

Example:

```
>>> print fred.config()
{'relief' : ('relief', 'relief', 'Relief', 'raised', 'groove')}
```

Of course, the dictionary printed will include all the options available and their values. This is meant only as an example.

The Packer

The packer is one of Tk's geometry-management mechanisms.

Geometry managers are used to specify the relative positioning of the positioning of widgets within their container - their mutual *master*. In contrast to the more cumbersome *placer* (which is used less commonly, and we do not cover here), the packer takes qualitative relationship specification - *above*, *to the left of, filling*, etc - and works everything out to determine the exact placement coordinates for you.

The size of any *master* widget is determined by the size of the "slave widgets" inside. The packer is used to control where slave widgets appear inside the master into which they are packed. You can pack widgets into frames, and frames into other frames, in order to achieve the kind of layout you desire. Additionally, the arrangement is dynamically adjusted to accommodate incremental changes to the configuration, once it is packed.

Note that widgets do not appear until they have had their geometry specified with a geometry manager. It's a common early mistake to leave out the geometry specification, and then be surprised when the widget is created but nothing appears. A widget will appear only after it has had, for example, the packer's pack() method applied to it.

The pack() method can be called with keyword-option/value pairs that control where the widget is to appear within its container, and how it is to behave when the main application window is resized. Here are some examples:

Packer Options

For more extensive information on the packer and the options that it can take, see the man pages and page 183 of John Ousterhout's book.

anchor Anchor type. Denotes where the packer is to place each slave in its parcel.

expand Boolean, 0 or 1.

```
fill Legal values: 'x', 'y', 'both', 'none'.
```

ipadx and ipady A distance - designating internal padding on each side of the slave widget.

padx and pady A distance - designating external padding on each side of the slave widget.

```
side Legal values are: 'left', 'right', 'top', 'bottom'.
```

Coupling Widget Variables

The current-value setting of some widgets (like text entry widgets) can be connected directly to application variables by using special options. These options are variable, textvariable, onvalue, offvalue, and value. This connection works both ways: if the variable changes for any reason, the widget it's connected to will be updated to reflect the new value.

Unfortunately, in the current implementation of Tkinter it is not possible to hand over an arbitrary Python variable to a widget through a variable or textvariable option. The only kinds of variables for which this works are variables that are subclassed from a class called Variable, defined in the Tkinter module.

There are many useful subclasses of Variable already defined: StringVar, IntVar, DoubleVar, and BooleanVar. To read the current value of such a variable, call the get() method on it, and to change its value you call the set() method. If you follow this protocol, the widget will always track the value of the variable, with no further intervention on your part.

For example:

```
class App(Frame):
   def __init__(self, master=None):
        Frame.__init__(self, master)
        self.pack()
        self.entrythingy = Entry()
        self.entrythingy.pack()
        # here is the application variable
        self.contents = StringVar()
        # set it to some value
        self.contents.set("this is a variable")
        # tell the entry widget to watch this variable
        self.entrythingy["textvariable"] = self.contents
        # and here we get a callback when the user hits return.
        # we will have the program print out the value of the
        # application variable when the user hits return
        self.entrythingy.bind('<Key-Return>',
                              self.print_contents)
   def print_contents(self, event):
        print "hi. contents of entry is now ---->", \
              self.contents.get()
```

The Window Manager

In Tk, there is a utility command, wm, for interacting with the window manager. Options to the wm command allow you to control things like titles, placement, icon bitmaps, and the like. In Tkinter, these commands have been implemented as methods on the Wm class. Toplevel widgets are subclassed from the Wm class, and so can call the Wm methods directly.

To get at the toplevel window that contains a given widget, you can often just refer to the widget's master. Of course if the widget has been packed inside of a frame, the master won't represent a toplevel window. To get at the toplevel window that contains an arbitrary widget, you can call the <code>_root()</code> method. This method begins with an underscore to denote the fact that this function is part of the implementation, and not an interface to Tk functionality.

Here are some examples of typical usage:

```
from Tkinter import *
class App(Frame):
    def __init__(self, master=None):
        Frame.__init__(self, master)
        self.pack()

# create the application
myapp = App()

# 
# here are method calls to the window manager class #
myapp.master.title("My Do-Nothing Application")
myapp.master.maxsize(1000, 400)

# start the program
myapp.mainloop()
```

Tk Option Data Types

- bitmap There are eight built-in, named bitmaps: 'error', 'gray25', 'gray50', 'hourglass', 'info', 'questhead', 'question', 'warning'. To specify an X bitmap filename, give the full path to the file, preceded with an @, as in "@/usr/contrib/bitmap/gumby.bit".

boolean You can pass integers 0 or 1 or the strings "yes" or "no".

callback This is any Python function that takes no arguments. For example:

- **color** Colors can be given as the names of X colors in the rgb.txt file, or as strings representing RGB values in 4 bit: "#RGB", 8 bit: "#RRGGBB", 12 bit' "#RRRGGGBBB", or 16 bit "#RRRGGGBBBB" ranges, where R,G,B here represent any legal hex digit. See page 160 of Ousterhout's book for details.
- **cursor** The standard X cursor names from 'cursorfont.h' can be used, without the XC_ prefix. For example to get a hand cursor (XC_hand2), use the string "hand2". You can also specify a bitmap and mask file of your own. See page 179 of Ousterhout's book.
- **distance** Screen distances can be specified in either pixels or absolute distances. Pixels are given as numbers and absolute distances as strings, with the trailing character denoting units: c for centimetres, i for inches, m for millimetres, p for printer's points. For example, 3.5 inches is expressed as "3.5i".
- font Tk uses a list font name format, such as {courier 10 bold}. Font sizes with positive numbers are measured in points; sizes with negative numbers are measured in pixels.
- **geometry** This is a string of the form 'widthxheight', where width and height are measured in pixels for most widgets (in characters for widgets displaying text). For example: fred["geometry"] = "200x100".
- justify Legal values are the strings: "left", "center", "right", and "fill".
- **region** This is a string with four space-delimited elements, each of which is a legal distance (see above). For example: "2 3 4 5" and "3i 2i 4.5i 2i" and "3c 2c 4c 10.43c" are all legal regions.
- **scrollcommand** This is almost always the set() method of some scrollbar widget, but can be any widget method that takes a single argument. Refer to the file 'Demo/tkinter/matt/canvas-with-scrollbars.py' in the Python source distribution for an example.

wrap: Must be one of: "none", "char", or "word".

Bindings and Events

The bind method from the widget command allows you to watch for certain events and to have a callback function trigger when that event type occurs. The form of the bind method is:

```
def bind(self, sequence, func, add=''):
```

where:

sequence is a string that denotes the target kind of event. (See the bind man page and page 201 of John Ousterhout's book for details).

func is a Python function, taking one argument, to be invoked when the event occurs. An Event instance will be passed as the argument. (Functions deployed this way are commonly known as *callbacks*.)

add is optional, either "or "+". Passing an empty string denotes that this binding is to replace any other bindings that this event is associated with. Preceeding with a "+" means that this function is to be added to the list of functions bound to this event type.

For example:

```
def turnRed(self, event):
    event.widget["activeforeground"] = "red"
self.button.bind("<Enter>", self.turnRed)
```

Notice how the widget field of the event is being accessed in the turnRed() callback. This field contains the widget that caught the X event. The following table lists the other event fields you can access, and how they are denoted in Tk, which can be useful when referring to the Tk man pages.

Tk	Tkinter Event Field	Tk	Tkinter Event Field
%f	focus	%A	char
%h	height	%E	send_event
%k	keycode	%K	keysym
%s	state	%N	keysym_num
%t	time	%T	type
%W	width	%W	widget
%x	x	%X	x_root
%y	У	%Y	y_root

The index Parameter

A number of widgets require "index" parameters to be passed. These are used to point at a specific place in a Text widget, or to particular characters in an Entry widget, or to particular menu items in a Menu widget.

Entry widget indexes (index, view index, etc.) Entry widgets have options that refer to character positions in the text being displayed. You can use these Tkinter functions to access these special points in text widgets:

AtEnd() refers to the last position in the text

AtInsert() refers to the point where the text cursor is

AtSelFirst() indicates the beginning point of the selected text

AtSelLast() denotes the last point of the selected text and finally

At(x[,y]) refers to the character at pixel location x, y (with y not used in the case of a text entry widget, which contains a single line of text).

Text widget indexes The index notation for Text widgets is very rich and is best described in the Tk man pages.

Menu indexes (menu.invoke(), menu.entryconfig(), etc.) Some options and methods for menus manipulate specific menu entries. Anytime a menu index is needed for an option or a parameter, you may pass in:

- an integer which refers to the numeric position of the entry in the widget, counted from the top, starting with 0;
- the string 'active', which refers to the menu position that is currently under the cursor;
- the string "last" which refers to the last menu item;
- An integer preceded by @, as in @6, where the integer is interpreted as a y pixel coordinate in the menu's coordinate system;

- the string "none", which indicates no menu entry at all, most often used with menu.activate() to deactivate all entries, and finally,
- a text string that is pattern matched against the label of the menu entry, as scanned from the top of the menu to the bottom. Note that this index type is considered after all the others, which means that matches for menu items labelled last, active, or none may be interpreted as the above literals, instead.

Images

Bitmap/Pixelmap images can be created through the subclasses of Tkinter.Image:

- BitmapImage can be used for X11 bitmap data.
- PhotoImage can be used for GIF and PPM/PGM color bitmaps.

Either type of image is created through either the file or the data option (other options are available as well).

The image object can then be used wherever an image option is supported by some widget (e.g. labels, buttons, menus). In these cases, Tk will not keep a reference to the image. When the last Python reference to the image object is deleted, the image data is deleted as well, and Tk will display an empty box wherever the image was used.

16.2 Tix — Extension widgets for Tk

The Tix (Tk Interface Extension) module provides an additional rich set of widgets. Although the standard Tk library has many useful widgets, they are far from complete. The Tix library provides most of the commonly needed widgets that are missing from standard Tk: HList, ComboBox, Control (a.k.a. SpinBox) and an assortment of scrollable widgets. Tix also includes many more widgets that are generally useful in a wide range of applications: NoteBook, FileEntry, PanedWindow, etc; there are more than 40 of them.

With all these new widgets, you can introduce new interaction techniques into applications, creating more useful and more intuitive user interfaces. You can design your application by choosing the most appropriate widgets to match the special needs of your application and users.

See Also:

Tix Homepage

(http://tix.sourceforge.net/)

The home page for Tix. This includes links to additional documentation and downloads.

Tix Man Pages

(http://tix.sourceforge.net/dist/current/man/)

On-line version of the man pages and reference material.

Tix Programming Guide

(http://tix.sourceforge.net/dist/current/docs/tix-book/tix.book.html)

On-line version of the programmer's reference material.

Tix Development Applications

(http://tix.sourceforge.net/Tide/)

Tix applications for development of Tix and Tkinter programs. Tide applications work under Tk or Tkinter, and include **TixInspect**, an inspector to remotely modify and debug Tix/Tk/Tkinter applications.

16.2.1 Using Tix

```
class Tix(screenName[, baseName[, className]])
```

Toplevel widget of Tix which represents mostly the main window of an application. It has an associated Tcl interpreter.

Classes in the Tix module subclasses the classes in the Tkinter module. The former imports the latter, so to use Tix with Tkinter, all you need to do is to import one module. In general, you can just import Tix, and replace the toplevel call to Tkinter. Tk with Tix. Tk:

```
import Tix
from Tkconstants import *
root = Tix.Tk()
```

To use Tix, you must have the Tix widgets installed, usually alongside your installation of the Tk widgets. To test your installation, try the following:

```
import Tix
root = Tix.Tk()
root.tk.eval('package require Tix')
```

If this fails, you have a Tk installation problem which must be resolved before proceeding. Use the environment variable TIX_LIBRARY to point to the installed <code>Tix</code> library directory, and make sure you have the dynamic object library ('tix8183.dll' or 'libtix8183.so') in the same directory that contains your Tk dynamic object library ('tk8183.dll' or 'libtk8183.so'). The directory with the dynamic object library should also have a file called 'pkgIndex.tcl' (case sensitive), which contains the line:

```
package ifneeded Tix 8.1 [list load "[file join $dir tix8183.dll]" Tix]
```

16.2.2 Tix Widgets

Tix introduces over 40 widget classes to the Tkinter repertoire. There is a demo of all the Tix widgets in the 'Demo/tix' directory of the standard distribution.

Basic Widgets

class Balloon()

A Balloon that pops up over a widget to provide help. When the user moves the cursor inside a widget to which a Balloon widget has been bound, a small pop-up window with a descriptive message will be shown on the screen.

class ButtonBox()

The ButtonBox widget creates a box of buttons, such as is commonly used for Ok Cancel.

class ComboBox()

The ComboBox widget is similar to the combo box control in MS Windows. The user can select a choice by either typing in the entry subwdget or selecting from the listbox subwidget.

class Control()

The Control widget is also known as the SpinBox widget. The user can adjust the value by pressing the two arrow buttons or by entering the value directly into the entry. The new value will be checked against the user-defined upper and lower limits.

class LabelEntry()

The LabelEntry widget packages an entry widget and a label into one mega widget. It can be used to simplify the creation of "entry-form" type of interface.

class LabelFrame()

The LabelFrame widget packages a frame widget and a label into one mega widget. To create widgets inside a LabelFrame widget, one creates the new widgets relative to the frame subwidget and manage them inside the frame subwidget.

class Meter()

The Meter widget can be used to show the progress of a background job which may take a long time to execute

class OptionMenu()

The OptionMenu creates a menu button of options.

class PopupMenu()

The PopupMenu widget can be used as a replacement of the tk_popup command. The advantage of the Tix PopupMenu widget is it requires less application code to manipulate.

class Select()

The Select widget is a container of button subwidgets. It can be used to provide radio-box or check-box style of selection options for the user.

class StdButtonBox()

The StdButtonBox widget is a group of standard buttons for Motif-like dialog boxes.

File Selectors

class DirList()

The DirList widget displays a list view of a directory, its previous directories and its sub-directories. The user can choose one of the directories displayed in the list or change to another directory.

class DirTree()

The DirTree widget displays a tree view of a directory, its previous directories and its sub-directories. The user can choose one of the directories displayed in the list or change to another directory.

class DirSelectDialog()

The DirSelectDialog widget presents the directories in the file system in a dialog window. The user can use this dialog window to navigate through the file system to select the desired directory.

class DirSelectBox()

The DirSelectBox is similar to the standard Motif(TM) directory-selection box. It is generally used for the user to choose a directory. DirSelectBox stores the directories mostly recently selected into a ComboBox widget so that they can be quickly selected again.

class ExFileSelectBox()

The ExFileSelectBox widget is usually embedded in a tixExFileSelectDialog widget. It provides an convenient method for the user to select files. The style of the ExFileSelectBox widget is very similar to the standard file dialog on MS Windows 3.1.

class FileSelectBox()

The FileSelectBox is similar to the standard Motif(TM) file-selection box. It is generally used for the user to choose a file. FileSelectBox stores the files mostly recently selected into a ComboBox widget so that they can be quickly selected again.

class FileEntry()

The FileEntry widget can be used to input a filename. The user can type in the filename manually. Alternatively, the user can press the button widget that sits next to the entry, which will bring up a file selection dialog.

Hierachical ListBox

class HList()

The HList widget can be used to display any data that have a hierarchical structure, for example, file system directory trees. The list entries are indented and connected by branch lines according to their places in the hierarchy.

class CheckList()

The CheckList widget displays a list of items to be selected by the user. CheckList acts similarly to the Tk checkbutton or radiobutton widgets, except it is capable of handling many more items than checkbuttons or radiobuttons.

class Tree()

The Tree widget can be used to display hierarchical data in a tree form. The user can adjust the view of the tree by opening or closing parts of the tree.

Tabular ListBox

class TList()

The TList widget can be used to display data in a tabular format. The list entries of a TList widget are similar to the entries in the Tk listbox widget. The main differences are (1) the TList widget can display the list entries in a two dimensional format and (2) you can use graphical images as well as multiple colors and fonts for the list entries.

Manager Widgets

class PanedWindow()

The PanedWindow widget allows the user to interactively manipulate the sizes of several panes. The panes can be arranged either vertically or horizontally. The user changes the sizes of the panes by dragging the resize handle between two panes.

class ListNoteBook()

The ListNoteBook widget is very similar to the TixNoteBook widget: it can be used to display many windows in a limited space using a notebook metaphor. The notebook is divided into a stack of pages (windows). At one time only one of these pages can be shown. The user can navigate through these pages by choosing the name of the desired page in the hlist subwidget.

class NoteBook()

The NoteBook widget can be used to display many windows in a limited space using a notebook metaphor. The notebook is divided into a stack of pages. At one time only one of these pages can be shown. The user can navigate through these pages by choosing the visual "tabs" at the top of the NoteBook widget.

Image Types

The Tix module adds:

- pixmap capabilities to all Tix and Tkinter widgets to create color images from XPM files.
- Compound image types can be used to create images that consists of multiple horizontal lines; each line is composed of a series of items (texts, bitmaps, images or spaces) arranged from left to right. For example, a compound image can be used to display a bitmap and a text string simultaneously in a Tk Button widget.

Miscellaneous Widgets

class InputOnly()

The InputOnly widgets are to accept inputs from the user, which can be done with the bind command (UNIX only).

Form Geometry Manager

In addition, Tix augments Tkinter by providing:

class Form()

The Form geometry manager based on attachment rules for all Tk widgets.

16.2.3 Tix Commands

class tixCommand()

The tix commands provide access to miscellaneous elements of Tix's internal state and the Tix application

context. Most of the information manipulated by these methods pertains to the application as a whole, or to a screen or display, rather than to a particular window.

To view the current settings, the common usage is:

```
import Tix
root = Tix.Tk()
print root.tix_configure()
```

tix_configure([cnf,] **kw)

Query or modify the configuration options of the Tix application context. If no option is specified, returns a dictionary all of the available options. If option is specified with no value, then the method returns a list describing the one named option (this list will be identical to the corresponding sublist of the value returned if no option is specified). If one or more option-value pairs are specified, then the method modifies the given option(s) to have the given value(s); in this case the method returns an empty string. Option may be any of the configuration options.

tix_cget(option)

Returns the current value of the configuration option given by *option*. Option may be any of the configuration options.

tix_getbitmap(name)

Locates a bitmap file of the name name.xpm or name in one of the bitmap directories (see the tix_addbitmapdir() method). By using tix_getbitmap(), you can avoid hard coding the pathnames of the bitmap files in your application. When successful, it returns the complete pathname of the bitmap file, prefixed with the character '@'. The returned value can be used to configure the bitmap option of the Tk and Tix widgets.

tix_addbitmapdir(directory)

Tix maintains a list of directories under which the tix_getimage() and tix_getbitmap() methods will search for image files. The standard bitmap directory is '\$TIX_LIBRARY/bitmaps'. The tix_addbitmapdir() method adds *directory* into this list. By using this method, the image files of an applications can also be located using the tix_getimage() or tix_getbitmap() method.

tix_filedialog([dlgclass])

Returns the file selection dialog that may be shared among different calls from this application. This method will create a file selection dialog widget when it is called the first time. This dialog will be returned by all subsequent calls to tix_filedialog(). An optional dlgclass parameter can be passed as a string to specified what type of file selection dialog widget is desired. Possible options are tix, FileSelectDialog or tixExFileSelectDialog.

tix_getimage(self, name)

Locates an image file of the name 'name.xpm', 'name.xbm' or 'name.ppm' in one of the bitmap directories (see the tix_addbitmapdir() method above). If more than one file with the same name (but different extensions) exist, then the image type is chosen according to the depth of the X display: xbm images are chosen on monochrome displays and color images are chosen on color displays. By using tix_getimage(), you can avoid hard coding the pathnames of the image files in your application. When successful, this method returns the name of the newly created image, which can be used to configure the image option of the Tk and Tix widgets.

tix_option_get(name)

Gets the options maintained by the Tix scheme mechanism.

tix_resetoptions(newScheme, newFontSet[, newScmPrio])

Resets the scheme and fontset of the Tix application to *newScheme* and *newFontSet*, respectively. This affects only those widgets created after this call. Therefore, it is best to call the resetoptions method before the creation of any widgets in a Tix application.

The optional parameter *newScmPrio* can be given to reset the priority level of the Tk options set by the Tix schemes.

Because of the way Tk handles the X option database, after Tix has been has imported and inited, it is not possible to reset the color schemes and font sets using the tix_config() method. Instead, the tix_resetoptions() method must be used.

16.3 ScrolledText — Scrolled Text Widget

The ScrolledText module provides a class of the same name which implements a basic text widget which has a vertical scroll bar configured to do the "right thing." Using the ScrolledText class is a lot easier than setting up a text widget and scroll bar directly. The constructor is the same as that of the Tkinter. Text class.

The text widget and scrollbar are packed together in a Frame, and the methods of the Grid and Pack geometry managers are acquired from the Frame object. This allows the ScrolledText widget to be used directly to achieve most normal geometry management behavior.

Should more specific control be necessary, the following attributes are available:

frame

The frame which surrounds the text and scroll bar widgets.

vbar

The scroll bar widget.

16.4 turtle — Turtle graphics for Tk

The turtle module provides turtle graphics primitives, in both an object-oriented and procedure-oriented ways. Because it uses Tkinter for the underlying graphics, it needs a version of python installed with Tk support.

The procedural interface uses a pen and a canvas which are automagically created when any of the functions are called.

The turtle module defines the following functions:

degrees()

Set angle measurement units to degrees.

radians()

Set angle measurement units to radians.

reset()

Clear the screen, re-center the pen, and set variables to the default values.

clear()

Clear the screen.

${\tt tracer}(\mathit{flag})$

Set tracing on/off (according to whether flag is true or not). Tracing means line are drawn more slowly, with an animation of an arrow along the line.

forward(distance)

Go forward distance steps.

backward(distance)

Go backward distance steps.

${\tt left} \, (\, angle \,)$

Turn left angle units. Units are by default degrees, but can be set via the degrees() and radians() functions.

right(angle)

Turn right *angle* units. Units are by default degrees, but can be set via the degrees () and radians () functions.

up()

Move the pen up — stop drawing.

down()

Move the pen down — draw when moving.

width(width)

Set the line width to width.

```
color(s)
color((r, g, b))
color(r, g, b)
```

Set the pen color. In the first form, the color is specified as a Tk color specification as a string. The second form specifies the color as a tuple of the RGB values, each in the range [0..1]. For the third form, the color is specified giving the RGB values as three separate parameters (each in the range [0..1]).

```
write(text[, move])
```

Write *text* at the current pen position. If *move* is true, the pen is moved to the bottom-right corner of the text. By default, *move* is false.

fill(flag)

The complete specifications are rather complex, but the recommended usage is: call fill(1) before drawing a path you want to fill, and call fill(0) when you finish to draw the path.

```
circle(radius[, extent])
```

Draw a circle with radius *radius* whose center-point is *radius* units left of the turtle. *extent* determines which part of a circle is drawn: if not given it defaults to a full circle.

If *extent* is not a full circle, one endpoint of the arc is the current pen position. The arc is drawn in a counter clockwise direction if *radius* is positive, otherwise in a clockwise direction. In the process, the direction of the turtle is changed by the amount of the *extent*.

```
goto(x, y)
goto((x, y))
```

Go to co-ordinates x, y. The co-ordinates may be specified either as two separate arguments or as a 2-tuple.

This module also does from math import *, so see the documentation for the math module for additional constants and functions useful for turtle graphics.

demo()

Exercise the module a bit.

exception Error

Exception raised on any error caught by this module.

For examples, see the code of the demo() function.

This module defines the following classes:

class Pen()

Define a pen. All above functions can be called as a methods on the given pen. The constructor automatically creates a canvas do be drawn on.

class RawPen (canvas)

Define a pen which draws on a canvas *canvas*. This is useful if you want to use the module to create graphics in a "real" program.

16.4.1 Pen and RawPen Objects

Pen and RawPen objects have all the global functions described above, except for demo() as methods, which manipulate the given pen.

The only method which is more powerful as a method is degrees ().

```
degrees ([fullcircle])
```

fullcircle is by default 360. This can cause the pen to have any angular units whatever: give fullcircle $2^*\pi$ for radians, or 400 for gradians.

16.5 Idle

Idle is the Python IDE built with the Tkinter GUI toolkit.

IDLE has the following features:

- coded in 100% pure Python, using the Tkinter GUI toolkit
- cross-platform: works on Windows and UNIX (on Mac OS, there are currently problems with Tcl/Tk)
- multi-window text editor with multiple undo, Python colorizing and many other features, e.g. smart indent and call tips
- Python shell window (a.k.a. interactive interpreter)
- debugger (not complete, but you can set breakpoints, view and step)

16.5.1 Menus

File menu

New window create a new editing window

Open... open an existing file

Open module... open an existing module (searches sys.path)

Class browser show classes and methods in current file

Path browser show sys.path directories, modules, classes and methods

Save save current window to the associated file (unsaved windows have a * before and after the window title)

Save As... save current window to new file, which becomes the associated file

Save Copy As... save current window to different file without changing the associated file

Close close current window (asks to save if unsaved)

Exit close all windows and quit IDLE (asks to save if unsaved)

Edit menu

Undo Undo last change to current window (max 1000 changes)

Redo Redo last undone change to current window

Cut Copy selection into system-wide clipboard; then delete selection

Copy Copy selection into system-wide clipboard

Paste Insert system-wide clipboard into window

Select All Select the entire contents of the edit buffer

Find... Open a search dialog box with many options

Find again Repeat last search

Find selection Search for the string in the selection

Find in Files... Open a search dialog box for searching files

Replace... Open a search-and-replace dialog box

Go to line Ask for a line number and show that line

Indent region Shift selected lines right 4 spaces

16.5. Idle 691

Dedent region Shift selected lines left 4 spaces

Comment out region Insert ## in front of selected lines

Uncomment region Remove leading # or ## from selected lines

Tabify region Turns leading stretches of spaces into tabs

Untabify region Turn all tabs into the right number of spaces

Expand word Expand the word you have typed to match another word in the same buffer; repeat to get a different expansion

Format Paragraph Reformat the current blank-line-separated paragraph

Import module Import or reload the current module

Run script Execute the current file in the __main__ namespace

Windows menu

Zoom Height toggles the window between normal size (24x80) and maximum height.

The rest of this menu lists the names of all open windows; select one to bring it to the foreground (deiconifying it if necessary).

Debug menu (in the Python Shell window only)

Go to file/line look around the insert point for a filename and linenumber, open the file, and show the line.

Open stack viewer show the stack traceback of the last exception

Debugger toggle Run commands in the shell under the debugger

JIT Stack viewer toggle Open stack viewer on traceback

16.5.2 Basic editing and navigation

- Backspace deletes to the left; Del deletes to the right
- Arrow keys and Page Up/Page Down to move around
- Home/End go to begin/end of line
- C-Home/C-End go to begin/end of file
- Some Emacs bindings may also work, including C-B, C-P, C-A, C-E, C-D, C-L

Automatic indentation

After a block-opening statement, the next line is indented by 4 spaces (in the Python Shell window by one tab). After certain keywords (break, return etc.) the next line is dedented. In leading indentation, Backspace deletes up to 4 spaces if they are there. Tab inserts 1-4 spaces (in the Python Shell window one tab). See also the indent/dedent region commands in the edit menu.

Python Shell window

- C-C interrupts executing command
- C-D sends end-of-file; closes window if typed at a '>>> ' prompt
- Alt-p retrieves previous command matching what you have typed
- Alt-n retrieves next
- Return while on any previous command retrieves that command
- Alt-/ (Expand word) is also useful here

16.5.3 Syntax colors

The coloring is applied in a background "thread," so you may occasionally see uncolorized text. To change the color scheme, edit the [Colors] section in 'config.txt'.

```
Python syntax colors: Keywords orange
```

```
Strings green
Comments red
Definitions blue
```

Shell colors: Console output brown

```
stdout blue
stderr dark green
stdin black
```

Command line usage

```
idle.py [-c command] [-d] [-e] [-s] [-t title] [arg] ...

-c command run this command
-d enable debugger
-e edit mode; arguments are files to be edited
-s run $IDLESTARTUP or $PYTHONSTARTUP first
-t title set title of shell window
```

If there are arguments:

- 1. If **-e** is used, arguments are files opened for editing and sys.argv reflects the arguments passed to IDLE itself.
- 2. Otherwise, if -c is used, all arguments are placed in sys.argv[1:...], with sys.argv[0] set to '-c'.
- 3. Otherwise, if neither -e nor -c is used, the first argument is a script which is executed with the remaining arguments in sys.argv[1:...] and sys.argv[0] set to the script name. If the script name is '-', no script is executed but an interactive Python session is started; the arguments are still available in sys.argv.

16.5. Idle 693

16.6 Other Graphical User Interface Packages

There are an number of extension widget sets to Tkinter.

Python megawidgets

(http://pmw.sourceforge.net/)

is a toolkit for building high-level compound widgets in Python using the Tkinter module. It consists of a set of base classes and a library of flexible and extensible megawidgets built on this foundation. These megawidgets include notebooks, comboboxes, selection widgets, paned widgets, scrolled widgets, dialog windows, etc. Also, with the Pmw.Blt interface to BLT, the busy, graph, stripchart, tabset and vector commands are be available.

The initial ideas for Pmw were taken from the Tk itcl extensions [incr Tk] by Michael McLennan and [incr Widgets] by Mark Ulferts. Several of the megawidgets are direct translations from the itcl to Python. It offers most of the range of widgets that [incr Widgets] does, and is almost as complete as Tix, lacking however Tix's fast HList widget for drawing trees.

Tkinter3000 Widget Construction Kit (WCK)

(http://tkinter.effbot.org/)

is a library that allows you to write new Tkinter widgets in pure Python. The WCK framework gives you full control over widget creation, configuration, screen appearance, and event handling. WCK widgets can be very fast and light-weight, since they can operate directly on Python data structures, without having to transfer data through the Tk/Tcl layer.

Tk is not the only GUI for Python, but is however the most commonly used one.

wxWindows

(http://www.wxwindows.org)

is a GUI toolkit that combines the most attractive attributes of Qt, Tk, Motif, and GTK+ in one powerful and efficient package. It is implemented in C++. wxWindows supports two flavors of UNIX implementation: GTK+ and Motif, and under Windows, it has a standard Microsoft Foundation Classes (MFC) appearance, because it uses Win32 widgets. There is a Python class wrapper, independent of Tkinter.

wxWindows is much richer in widgets than Tkinter, with its help system, sophisticated HTML and image viewers, and other specialized widgets, extensive documentation, and printing capabilities.

PyQt

PyQt is a **sip**-wrapped binding to the Qt toolkit. Qt is an extensive C++ GUI toolkit that is available for UNIX, Windows and Mac OS X. **sip** is a tool for generating bindings for C++ libraries as Python classes, and is specifically designed for Python. An online manual is available at http://www.opendocspublishing.com/pyqt/ (errata are located at http://www.valdyas.org/python/book.html).

PvKDE

(http://www.riverbankcomputing.co.uk/pykde/index.php)

PyKDE is a **sip**-wrapped interface to the KDE desktop libraries. KDE is a desktop environment for UNIX computers; the graphical components are based on Qt.

FXPy

(http://fxpy.sourceforge.net/)

is a Python extension module which provides an interface to the *FOX* GUI. FOX is a C++ based Toolkit for developing Graphical User Interfaces easily and effectively. It offers a wide, and growing, collection of Controls, and provides state of the art facilities such as drag and drop, selection, as well as OpenGL widgets for 3D graphical manipulation. FOX also implements icons, images, and user-convenience features such as status line help, and tooltips.

Even though FOX offers a large collection of controls already, FOX leverages C++ to allow programmers to easily build additional Controls and GUI elements, simply by taking existing controls, and creating a derived class which simply adds or redefines the desired behavior.

PyGTK

(http://www.daa.com.au/~james/software/pygtk/)

is a set of bindings for the GTK widget set. It provides an object oriented interface that is slightly higher level than the C one. It automatically does all the type casting and reference counting that you would have to do normally with the C API. There are also bindings to GNOME, and a tutorial is available.

Restricted Execution

Warning: In Python 2.3 these modules have been disabled due to various known and not readily fixable security holes. The modules are still documented here to help in reading old code that uses the rexec and Bastion modules.

Restricted execution is the basic framework in Python that allows for the segregation of trusted and untrusted code. The framework is based on the notion that trusted Python code (a *supervisor*) can create a "padded cell' (or environment) with limited permissions, and run the untrusted code within this cell. The untrusted code cannot break out of its cell, and can only interact with sensitive system resources through interfaces defined and managed by the trusted code. The term "restricted execution" is favored over "safe-Python" since true safety is hard to define, and is determined by the way the restricted environment is created. Note that the restricted environments can be nested, with inner cells creating subcells of lesser, but never greater, privilege.

An interesting aspect of Python's restricted execution model is that the interfaces presented to untrusted code usually have the same names as those presented to trusted code. Therefore no special interfaces need to be learned to write code designed to run in a restricted environment. And because the exact nature of the padded cell is determined by the supervisor, different restrictions can be imposed, depending on the application. For example, it might be deemed "safe" for untrusted code to read any file within a specified directory, but never to write a file. In this case, the supervisor may redefine the built-in open() function so that it raises an exception whenever the *mode* parameter is 'w'. It might also perform a chroot()-like operation on the *filename* parameter, such that root is always relative to some safe "sandbox" area of the filesystem. In this case, the untrusted code would still see an built-in open() function in its environment, with the same calling interface. The semantics would be identical too, with IOErrors being raised when the supervisor determined that an unallowable parameter is being used.

The Python run-time determines whether a particular code block is executing in restricted execution mode based on the identity of the __builtins__ object in its global variables: if this is (the dictionary of) the standard __builtin__ module, the code is deemed to be unrestricted, else it is deemed to be restricted.

Python code executing in restricted mode faces a number of limitations that are designed to prevent it from escaping from the padded cell. For instance, the function object attribute func_globals and the class and instance object attribute __dict__ are unavailable.

Two modules provide the framework for setting up restricted execution environments:

rexec Basic restricted execution framework. Bastion Providing restricted access to objects.

See Also:

Grail Home Page

(http://grail.sourceforge.net/)

Grail, an Internet browser written in Python, uses these modules to support Python applets. More information on the use of Python's restricted execution mode in Grail is available on the Web site.

17.1 rexec — Restricted execution framework

Warning: The documentation has been left in place to help in reading old code that uses the module.

This module contains the RExec class, which supports r_eval(), r_execfile(), r_exec(), and r_import() methods, which are restricted versions of the standard Python functions eval(), execfile() and the exec and import statements. Code executed in this restricted environment will only have access to modules and functions that are deemed safe; you can subclass RExec to add or remove capabilities as desired.

Warning: While the rexec module is designed to perform as described below, it does have a few known vulnerabilities which could be exploited by carefully written code. Thus it should not be relied upon in situations requiring "production ready" security. In such situations, execution via sub-processes or very careful "cleansing" of both code and data to be processed may be necessary. Alternatively, help in patching known rexec vulnerabilities would be welcomed.

Note: The RExec class can prevent code from performing unsafe operations like reading or writing disk files, or using TCP/IP sockets. However, it does not protect against code using extremely large amounts of memory or processor time.

```
class RExec ( [hooks[, verbose]])
```

Returns an instance of the RExec class.

hooks is an instance of the RHooks class or a subclass of it. If it is omitted or None, the default RHooks class is instantiated. Whenever the rexec module searches for a module (even a built-in one) or reads a module's code, it doesn't actually go out to the file system itself. Rather, it calls methods of an RHooks instance that was passed to or created by its constructor. (Actually, the RExec object doesn't make these calls — they are made by a module loader object that's part of the RExec object. This allows another level of flexibility, which can be useful when changing the mechanics of import within the restricted environment.)

By providing an alternate RHooks object, we can control the file system accesses made to import a module, without changing the actual algorithm that controls the order in which those accesses are made. For instance, we could substitute an RHooks object that passes all filesystem requests to a file server elsewhere, via some RPC mechanism such as ILU. Grail's applet loader uses this to support importing applets from a URL for a directory.

If verbose is true, additional debugging output may be sent to standard output.

It is important to be aware that code running in a restricted environment can still call the sys.exit() function. To disallow restricted code from exiting the interpreter, always protect calls that cause restricted code to run with a try/except statement that catches the SystemExit exception. Removing the sys.exit() function from the restricted environment is not sufficient — the restricted code could still use raise SystemExit. Removing SystemExit is not a reasonable option; some library code makes use of this and would break were it not available.

See Also:

Grail Home Page

(http://grail.sourceforge.net/)

Grail is a Web browser written entirely in Python. It uses the rexec module as a foundation for supporting Python applets, and can be used as an example usage of this module.

17.1.1 RExec Objects

RExec instances support the following methods:

```
r_eval(code)
```

code must either be a string containing a Python expression, or a compiled code object, which will be evaluated in the restricted environment's __main__ module. The value of the expression or code object will be returned.

r_exec(code)

code must either be a string containing one or more lines of Python code, or a compiled code object, which will be executed in the restricted environment's __main__ module.

r_execfile(filename)

Execute the Python code contained in the file *filename* in the restricted environment's __main__ module.

Methods whose names begin with ' s_{-} ' are similar to the functions beginning with ' r_{-} ', but the code will be granted access to restricted versions of the standard I/O streams sys.stdin, sys.stderr, and <math>sys.stdout.

s_eval(code)
code

```
is ('audioop', 'array', 'binascii', 'cmath', 'errno', 'imageop', 'marshal', 'math', 'md5', 'operator', 'parser', 'regex', 'select', 'sha', '_sre', 'strop', 'struct', 'time'). A similar remark about overriding this variable applies — use the value from the base class as a starting point.
```

ok_path

Contains the directories which will be searched when an import is performed in the restricted environment. The value for RExec is the same as sys.path (at the time the module is loaded) for unrestricted code

ok_posix_names

Contains the names of the functions in the os module which will be available to programs running in the restricted environment. The value for RExec is ('error', 'fstat', 'listdir', 'lstat', 'readlink', 'stat', 'times', 'uname', 'getpid', 'getppid', 'getcwd', 'getuid', 'getgid', 'geteuid', 'getegid').

ok_sys_names

Contains the names of the functions and variables in the sys module which will be available to programs running in the restricted environment. The value for RExec is ('ps1', 'ps2', 'copyright', 'version', 'platform', 'exit', 'maxint').

ok_file_types

Contains the file types from which modules are allowed to be loaded. Each file type is an integer constant defined in the imp module. The meaningful values are PY_SOURCE, PY_COMPILED, and C_EXTENSION. The value for RExec is (C_EXTENSION, PY_SOURCE). Adding PY_COMPILED in subclasses is not recommended; an attacker could exit the restricted execution mode by putting a forged byte-compiled file ('.pyc') anywhere in your file system, for example by writing it to '/tmp' or uploading it to the '/incoming' directory of your public FTP server.

17.1.3 An example

Let us say that we want a slightly more relaxed policy than the standard RExec class. For example, if we're willing to allow files in '/tmp' to be written, we can subclass the RExec class:

```
class TmpWriterRExec(rexec.RExec):
    def r_open(self, file, mode='r', buf=-1):
        if mode in ('r', 'rb'):
            pass
    elif mode in ('w', 'wb', 'a', 'ab'):
        # check filename : must begin with /tmp/
        if file[:5]!='/tmp/':
            raise IOError, "can't write outside /tmp"
        elif (string.find(file, '/../') >= 0 or
            file[:3] == '../' or file[-3:] == '/..'):
            raise IOError, "'..' in filename forbidden"
        else: raise IOError, "Illegal open() mode"
        return open(file, mode, buf)
```

Notice that the above code will occasionally forbid a perfectly valid filename; for example, code in the restricted environment won't be able to open a file called '/tmp/foo/../bar'. To fix this, the $r_open()$ method would have to simplify the filename to '/tmp/bar', which would require splitting apart the filename and performing various operations on it. In cases where security is at stake, it may be preferable to write simple code which is sometimes overly restrictive, instead of more general code that is also more complex and may harbor a subtle security hole.

17.2 Bastion — Restricting access to objects

Changed in version 2.3: Disabled module.

Warning: The documentation has been left in place to help in reading old code that uses the module.

According to the dictionary, a bastion is "a fortified area or position", or "something that is considered a stronghold." It's a suitable name for this module, which provides a way to forbid access to certain attributes of an object. It must always be used with the rexec module, in order to allow restricted-mode programs access to certain safe attributes of an object, while denying access to other, unsafe attributes.

Bastion(object[, filter[, name[, class]]])

Protect the object *object*, returning a bastion for the object. Any attempt to access one of the object's attributes will have to be approved by the *filter* function; if the access is denied an AttributeError exception will be raised.

If present, *filter* must be a function that accepts a string containing an attribute name, and returns true if access to that attribute will be permitted; if *filter* returns false, the access is denied. The default filter denies access to any function beginning with an underscore ('_'). The bastion's string representation will be '<Bastion for *name*>' if a value for *name* is provided; otherwise, 'repr(*object*)' will be used.

class, if present, should be a subclass of BastionClass; see the code in 'bastion.py' for the details. Overriding the default BastionClass will rarely be required.

${\bf class} \ {\bf BastionClass} \ (\ {\it getfunc}, \ name \)$

Class which actually implements bastion objects. This is the default class used by <code>Bastion()</code>. The <code>getfunc</code> parameter is a function which returns the value of an attribute which should be exposed to the restricted execution environment when called with the name of the attribute as the only parameter. <code>name</code> is used to construct the <code>repr()</code> of the <code>BastionClass</code> instance.

Python Language Services

Python provides a number of modules to assist in working with the Python language. These module support tokenizing, parsing, syntax analysis, bytecode disassembly, and various other facilities.

These modules include:

parser Access parse trees for Python source code.

symbol Constants representing internal nodes of the parse tree. **token** Constants representing terminal nodes of the parse tree.

keyword Test whether a string is a keyword in Python. **tokenize** Lexical scanner for Python source code.

Tool for detecting white space related problems in Python source files in a directory tree.

Supports information extraction for a Python class browser.

py_compile Compile Python source files to byte-code files.

compileal1 Tools for byte-compiling all Python source files in a directory tree.

dis Disassembler for Python byte code.

pickletools Contains extensive comments about the pickle protocols and pickle-machine opcodes, as well as some useful f

distutils Support for building and installing Python modules into an existing Python installation.

18.1 parser — Access Python parse trees

The parser module provides an interface to Python's internal parser and byte-code compiler. The primary purpose for this interface is to allow Python code to edit the parse tree of a Python expression and create executable code from this. This is better than trying to parse and modify an arbitrary Python code fragment as a string because parsing is performed in a manner identical to the code forming the application. It is also faster.

There are a few things to note about this module which are important to making use of the data structures created. This is not a tutorial on editing the parse trees for Python code, but some examples of using the parser module are presented.

Most importantly, a good understanding of the Python grammar processed by the internal parser is required. For full information on the language syntax, refer to the *Python Language Reference*. The parser itself is created from a grammar specification defined in the file 'Grammar/Grammar' in the standard Python distribution. The parse trees stored in the AST objects created by this module are the actual output from the internal parser when created by the <code>expr()</code> or <code>suite()</code> functions, described below. The AST objects created by <code>sequence2ast()</code> faithfully simulate those structures. Be aware that the values of the sequences which are considered "correct" will vary from one version of Python to another as the formal grammar for the language is revised. However, transporting code from one Python version to another as source text will always allow correct parse trees to be created in the target version, with the only restriction being that migrating to an older version of the interpreter will not support more recent language constructs. The parse trees are not typically compatible from one version to another, whereas source code has always been forward-compatible.

Each element of the sequences returned by ast2list() or ast2tuple() has a simple form. Sequences representing non-terminal elements in the grammar always have a length greater than one. The first element is an integer which identifies a production in the grammar. These integers are given symbolic names in the C header file 'Include/graminit.h' and the Python module symbol. Each additional element of the sequence represents a

component of the production as recognized in the input string: these are always sequences which have the same form as the parent. An important aspect of this structure which should be noted is that keywords used to identify the parent node type, such as the keyword if in an if_stmt , are included in the node tree without any special treatment. For example, the if keyword is represented by the tuple (1, 'if'), where 1 is the numeric value associated with all NAME tokens, including variable and function names defined by the user. In an alternate form returned when line number information is requested, the same token might be represented as (1, 'if', 12), where the 12 represents the line number at which the terminal symbol was found.

Terminal elements are represented in much the same way, but without any child elements and the addition of the source text which was identified. The example of the if keyword above is representative. The various types of terminal symbols are defined in the C header file 'Include/token.h' and the Python module token.

The AST objects are not required to support the functionality of this module, but are provided for three purposes: to allow an application to amortize the cost of processing complex parse trees, to provide a parse tree representation which conserves memory space when compared to the Python list or tuple representation, and to ease the creation of additional modules in C which manipulate parse trees. A simple "wrapper" class may be created in Python to hide the use of AST objects.

The parser module defines functions for a few distinct purposes. The most important purposes are to create AST objects and to convert AST objects to other representations such as parse trees and compiled code objects, but there are also functions which serve to query the type of parse tree represented by an AST object.

See Also:

Module symbol (section 18.2):

Useful constants representing internal nodes of the parse tree.

Module token (section 18.3):

Useful constants representing leaf nodes of the parse tree and functions for testing node values.

18.1.1 Creating AST Objects

AST objects may be created from source code or from a parse tree. When creating an AST object from source, different functions are used to create the 'eval' and 'exec' forms.

expr(source)

The expr() function parses the parameter *source* as if it were an input to 'compile(*source*, 'file.py', 'eval')'. If the parse succeeds, an AST object is created to hold the internal parse tree representation, otherwise an appropriate exception is thrown.

suite(source)

The suite() function parses the parameter *source* as if it were an input to 'compile(*source*, 'file.py', 'exec')'. If the parse succeeds, an AST object is created to hold the internal parse tree representation, otherwise an appropriate exception is thrown.

sequence2ast(sequence)

This function accepts a parse tree represented as a sequence and builds an internal representation if possible. If it can validate that the tree conforms to the Python grammar and all nodes are valid node types in the host version of Python, an AST object is created from the internal representation and returned to the called. If there is a problem creating the internal representation, or if the tree cannot be validated, a ParserError exception is thrown. An AST object created this way should not be assumed to compile correctly; normal exceptions thrown by compilation may still be initiated when the AST object is passed to compileast(). This may indicate problems not related to syntax (such as a MemoryError exception), but may also be due to constructs such as the result of parsing del f(0), which escapes the Python parser but is checked by the bytecode compiler.

Sequences representing terminal tokens may be represented as either two-element lists of the form (1, 'name') or as three-element lists of the form (1, 'name', 56). If the third element is present, it is assumed to be a valid line number. The line number may be specified for any subset of the terminal symbols in the input tree.

$\verb"tuple2ast" (sequence")$

This is the same function as sequence2ast(). This entry point is maintained for backward compatibil-

18.1.2 Converting AST Objects

AST objects, regardless of the input used to create them, may be converted to parse trees represented as list- or tuple- trees, or may be compiled into executable code objects. Parse trees may be extracted with or without line numbering information.

ast2list(ast[, line_info])

This function accepts an AST object from the caller in *ast* and returns a Python list representing the equivalent parse tree. The resulting list representation can be used for inspection or the creation of a new parse tree in list form. This function does not fail so long as memory is available to build the list representation. If the parse tree will only be used for inspection, ast2tuple() should be used instead to reduce memory consumption and fragmentation. When the list representation is required, this function is significantly faster than retrieving a tuple representation and converting that to nested lists.

If *line_info* is true, line number information will be included for all terminal tokens as a third element of the list representing the token. Note that the line number provided specifies the line on which the token *ends*. This information is omitted if the flag is false or omitted.

$ast2tuple(ast[, line_info])$

This function accepts an AST object from the caller in *ast* and returns a Python tuple representing the equivalent parse tree. Other than returning a tuple instead of a list, this function is identical to ast2list().

If *line_info* is true, line number information will be included for all terminal tokens as a third element of the list representing the token. This information is omitted if the flag is false or omitted.

compileast(ast[, filename = '<ast>'])

The Python byte compiler can be invoked on an AST object to produce code objects which can be used as part of an exec statement or a call to the built-in eval() function. This function provides the interface to the compiler, passing the internal parse tree from *ast* to the parser, using the source file name specified by the *filename* parameter. The default value supplied for *filename* indicates that the source was an AST object.

Compiling an AST object may result in exceptions related to compilation; an example would be a SyntaxError caused by the parse tree for del f(0): this statement is considered legal within the formal grammar for Python but is not a legal language construct. The SyntaxError raised for this condition is actually generated by the Python byte-compiler normally, which is why it can be raised at this point by the parser module. Most causes of compilation failure can be diagnosed programmatically by inspection of the parse tree.

18.1.3 Queries on AST Objects

Two functions are provided which allow an application to determine if an AST was created as an expression or a suite. Neither of these functions can be used to determine if an AST was created from source code via expr() or suite() or from a parse tree via sequence2ast().

isexpr(ast)

When *ast* represents an 'eval' form, this function returns true, otherwise it returns false. This is useful, since code objects normally cannot be queried for this information using existing built-in functions. Note that the code objects created by compileast() cannot be queried like this either, and are identical to those created by the built-in compile() function.

issuite(ast)

This function mirrors <code>isexpr()</code> in that it reports whether an AST object represents an 'exec' form, commonly known as a "suite." It is not safe to assume that this function is equivalent to 'not <code>isexpr(ast)</code>', as additional syntactic fragments may be supported in the future.

18.1.4 Exceptions and Error Handling

The parser module defines a single exception, but may also pass other built-in exceptions from other portions of the Python runtime environment. See each function for information about the exceptions it can raise.

exception ParserError

Exception raised when a failure occurs within the parser module. This is generally produced for validation failures rather than the built in SyntaxError thrown during normal parsing. The exception argument is either a string describing the reason of the failure or a tuple containing a sequence causing the failure from a parse tree passed to sequence2ast() and an explanatory string. Calls to sequence2ast() need to be able to handle either type of exception, while calls to other functions in the module will only need to be aware of the simple string values.

Note that the functions compileast(), expr(), and suite() may throw exceptions which are normally thrown by the parsing and compilation process. These include the built in exceptions MemoryError, OverflowError, SyntaxError, and SystemError. In these cases, these exceptions carry all the meaning normally associated with them. Refer to the descriptions of each function for detailed information.

18.1.5 AST Objects

Ordered and equality comparisons are supported between AST objects. Pickling of AST objects (using the pickle module) is also supported.

```
ASTType
```

```
The type of the objects returned by expr(), suite() and sequence2ast().
```

```
AST objects have the following methods:

compile([filename])
    Same as compileast(ast, filename).

isexpr()
    Same as isexpr(ast).

issuite()
    Same as issuite(ast).

tolist([line_info])
    Same as ast2list(ast, line_info).

totuple([line_info])
    Same as ast2tuple(ast, line_info).
```

18.1.6 Examples

The parser modules allows operations to be performed on the parse tree of Python source code before the bytecode is generated, and provides for inspection of the parse tree for information gathering purposes. Two examples are presented. The simple example demonstrates emulation of the <code>compile()</code> built-in function and the complex example shows the use of a parse tree for information discovery.

```
Emulation of compile()
```

While many useful operations may take place between parsing and bytecode generation, the simplest operation is to do nothing. For this purpose, using the parser module to produce an intermediate data structure is equivalent to the code

```
>>> code = compile('a + 5', 'file.py', 'eval')
>>> a = 5
>>> eval(code)
10
```

The equivalent operation using the parser module is somewhat longer, and allows the intermediate internal parse tree to be retained as an AST object:

```
>>> import parser
>>> ast = parser.expr('a + 5')
>>> code = ast.compile('file.py')
>>> a = 5
>>> eval(code)
10
```

An application which needs both AST and code objects can package this code into readily available functions:

```
import parser

def load_suite(source_string):
    ast = parser.suite(source_string)
    return ast, ast.compile()

def load_expression(source_string):
    ast = parser.expr(source_string)
    return ast, ast.compile()
```

Information Discovery

Some applications benefit from direct access to the parse tree. The remainder of this section demonstrates how the parse tree provides access to module documentation defined in docstrings without requiring that the code being examined be loaded into a running interpreter via import. This can be very useful for performing analyses of untrusted code.

Generally, the example will demonstrate how the parse tree may be traversed to distill interesting information. Two functions and a set of classes are developed which provide programmatic access to high level function and class definitions provided by a module. The classes extract information from the parse tree and provide access to the information at a useful semantic level, one function provides a simple low-level pattern matching capability, and the other function defines a high-level interface to the classes by handling file operations on behalf of the caller. All source files mentioned here which are not part of the Python installation are located in the 'Demo/parser/' directory of the distribution.

The dynamic nature of Python allows the programmer a great deal of flexibility, but most modules need only a limited measure of this when defining classes, functions, and methods. In this example, the only definitions that will be considered are those which are defined in the top level of their context, e.g., a function defined by a def statement at column zero of a module, but not a function defined within a branch of an if ... else construct, though there are some good reasons for doing so in some situations. Nesting of definitions will be handled by the code developed in the example.

To construct the upper-level extraction methods, we need to know what the parse tree structure looks like and how much of it we actually need to be concerned about. Python uses a moderately deep parse tree so there are a large number of intermediate nodes. It is important to read and understand the formal grammar used by Python. This is specified in the file 'Grammar/Grammar' in the distribution. Consider the simplest case of interest when searching for docstrings: a module consisting of a docstring and nothing else. (See file 'docstring.py'.)

```
"""Some documentation.
```

Using the interpreter to take a look at the parse tree, we find a bewildering mass of numbers and parentheses, with the documentation buried deep in nested tuples.

```
>>> import parser
>>> import pprint
>>> ast = parser.suite(open('docstring.py').read())
>>> tup = ast.totuple()
>>> pprint.pprint(tup)
(257,
 (264,
  (265,
   (266,
    (267)
     (307,
      (287,
       (288,
        (289.
         (290,
           (292,
            (293,
             (294,
              (295,
               (296,
                (297,
                 (298,
                  (299.
                   (300, (3, '"""Some documentation.\n"""')))))))))))))))),
   (4, ''))),
 (4, ''),
 (0, ''))
```

The numbers at the first element of each node in the tree are the node types; they map directly to terminal and non-terminal symbols in the grammar. Unfortunately, they are represented as integers in the internal representation, and the Python structures generated do not change that. However, the symbol and token modules provide symbolic names for the node types and dictionaries which map from the integers to the symbolic names for the node types.

In the output presented above, the outermost tuple contains four elements: the integer 257 and three additional tuples. Node type 257 has the symbolic name file_input. Each of these inner tuples contains an integer as the first element; these integers, 264, 4, and 0, represent the node types stmt, NEWLINE, and ENDMARKER, respectively. Note that these values may change depending on the version of Python you are using; consult 'symbol.py' and 'token.py' for details of the mapping. It should be fairly clear that the outermost node is related primarily to the input source rather than the contents of the file, and may be disregarded for the moment. The stmt node is much more interesting. In particular, all docstrings are found in subtrees which are formed exactly as this node is formed, with the only difference being the string itself. The association between the docstring in a similar tree and the defined entity (class, function, or module) which it describes is given by the position of the docstring subtree within the tree defining the described structure.

By replacing the actual docstring with something to signify a variable component of the tree, we allow a simple pattern matching approach to check any given subtree for equivalence to the general pattern for docstrings. Since the example demonstrates information extraction, we can safely require that the tree be in tuple form rather than list form, allowing a simple variable representation to be ['variable_name']. A simple recursive function can implement the pattern matching, returning a Boolean and a dictionary of variable name to value mappings. (See file 'example.py'.)

```
from types import ListType, TupleType
def match(pattern, data, vars=None):
    if vars is None:
        vars = { }
    if type(pattern) is ListType:
        vars[pattern[0]] = data
        return 1, vars
    if type(pattern) is not TupleType:
        return (pattern == data), vars
    if len(data) != len(pattern):
       return 0, vars
    for pattern, data in map(None, pattern, data):
        same, vars = match(pattern, data, vars)
        if not same:
            break
    return same, vars
```

Using this simple representation for syntactic variables and the symbolic node types, the pattern for the candidate docstring subtrees becomes fairly readable. (See file 'example.py'.)

```
import symbol
import token
DOCSTRING STMT PATTERN = (
    symbol.stmt,
    (symbol.simple_stmt,
     (symbol.small_stmt,
      (symbol.expr_stmt,
       (symbol.testlist,
        (symbol.test,
         (symbol.and_test,
          (symbol.not_test,
           (symbol.comparison,
            (symbol.expr,
             (symbol.xor_expr,
              (symbol.and_expr,
               (symbol.shift_expr,
                (symbol.arith_expr,
                  (symbol.term,
                   (symbol.factor,
                    (symbol.power,
                     (symbol.atom,
                      (token.STRING, ['docstring'])
                      )))))))))))))),
     (token.NEWLINE, '')
     ))
```

Using the match() function with this pattern, extracting the module docstring from the parse tree created previously is easy:

```
>>> found, vars = match(DOCSTRING_STMT_PATTERN, tup[1])
>>> found
1
>>> vars
{'docstring': '"""Some documentation.\n"""'}
```

Once specific data can be extracted from a location where it is expected, the question of where information can be expected needs to be answered. When dealing with docstrings, the answer is fairly simple: the docstring

is the first stmt node in a code block (file_input or suite node types). A module consists of a single file_input node, and class and function definitions each contain exactly one suite node. Classes and functions are readily identified as subtrees of code block nodes which start with (stmt, (compound_stmt, (classdef, ... Note that these subtrees cannot be matched by match() since it does not support multiple sibling nodes to match without regard to number. A more elaborate matching function could be used to overcome this limitation, but this is sufficient for the example.

Given the ability to determine whether a statement might be a docstring and extract the actual string from the statement, some work needs to be performed to walk the parse tree for an entire module and extract information about the names defined in each context of the module and associate any docstrings with the names. The code to perform this work is not complicated, but bears some explanation.

The public interface to the classes is straightforward and should probably be somewhat more flexible. Each "major" block of the module is described by an object providing several methods for inquiry and a constructor which accepts at least the subtree of the complete parse tree which it represents. The ModuleInfo constructor accepts an optional *name* parameter since it cannot otherwise determine the name of the module.

The public classes include ClassInfo, FunctionInfo, and ModuleInfo. All objects provide the methods get_name(), get_docstring(), get_class_names(), and get_class_info(). The ClassInfo objects support get_method_names() and get_method_info() while the other classes provide get_function_names() and get_function_info().

Within each of the forms of code block that the public classes represent, most of the required information is in the same form and is accessed in the same way, with classes having the distinction that functions defined at the top level are referred to as "methods." Since the difference in nomenclature reflects a real semantic distinction from functions defined outside of a class, the implementation needs to maintain the distinction. Hence, most of the functionality of the public classes can be implemented in a common base class, SuiteInfoBase, with the accessors for function and method information provided elsewhere. Note that there is only one class which represents function and method information; this parallels the use of the def statement to define both types of elements.

Most of the accessor functions are declared in SuiteInfoBase and do not need to be overridden by subclasses. More importantly, the extraction of most information from a parse tree is handled through a method called by the SuiteInfoBase constructor. The example code for most of the classes is clear when read alongside the formal grammar, but the method which recursively creates new information objects requires further examination. Here is the relevant part of the SuiteInfoBase definition from 'example.py':

```
class SuiteInfoBase:
    _docstring = ''
    _name = ''
    def __init__(self, tree = None):
        self._class_info = {}
        self._function_info = {}
        if tree:
            self._extract_info(tree)
    def _extract_info(self, tree):
        # extract docstring
        if len(tree) == 2:
            found, vars = match(DOCSTRING_STMT_PATTERN[1], tree[1])
        else:
            found, vars = match(DOCSTRING_STMT_PATTERN, tree[3])
        if found:
            self._docstring = eval(vars['docstring'])
        # discover inner definitions
        for node in tree[1:]:
            found, vars = match(COMPOUND_STMT_PATTERN, node)
            if found:
                cstmt = vars['compound']
                if cstmt[0] == symbol.funcdef:
                    name = cstmt[2][1]
                    self._function_info[name] = FunctionInfo(cstmt)
                elif cstmt[0] == symbol.classdef:
                    name = cstmt[2][1]
                    self._class_info[name] = ClassInfo(cstmt)
```

After initializing some internal state, the constructor calls the <code>_extract_info()</code> method. This method performs the bulk of the information extraction which takes place in the entire example. The extraction has two distinct phases: the location of the docstring for the parse tree passed in, and the discovery of additional definitions within the code block represented by the parse tree.

The initial if test determines whether the nested suite is of the "short form" or the "long form." The short form is used when the code block is on the same line as the definition of the code block, as in

```
def square(x): "Square an argument."; return x ** 2
```

while the long form uses an indented block and allows nested definitions:

```
def make_power(exp):
    "Make a function that raises an argument to the exponent 'exp'."
    def raiser(x, y=exp):
        return x ** y
    return raiser
```

When the short form is used, the code block may contain a docstring as the first, and possibly only, small_stmt element. The extraction of such a docstring is slightly different and requires only a portion of the complete pattern used in the more common case. As implemented, the docstring will only be found if there is only one small_stmt node in the simple_stmt node. Since most functions and methods which use the short form do not provide a docstring, this may be considered sufficient. The extraction of the docstring proceeds using the match() function as described above, and the value of the docstring is stored as an attribute of the SuiteInfoBase object.

After docstring extraction, a simple definition discovery algorithm operates on the stmt nodes of the suite

node. The special case of the short form is not tested; since there are no stmt nodes in the short form, the algorithm will silently skip the single simple_stmt node and correctly not discover any nested definitions.

Each statement in the code block is categorized as a class definition, function or method definition, or something else. For the definition statements, the name of the element defined is extracted and a representation object appropriate to the definition is created with the defining subtree passed as an argument to the constructor. The representation objects are stored in instance variables and may be retrieved by name using the appropriate accessor methods.

The public classes provide any accessors required which are more specific than those provided by the SuiteInfoBase class, but the real extraction algorithm remains common to all forms of code blocks. A high-level function can be used to extract the complete set of information from a source file. (See file 'example.py'.)

```
def get_docs(fileName):
    import os
    import parser

source = open(fileName).read()
    basename = os.path.basename(os.path.splitext(fileName)[0])
    ast = parser.suite(source)
    return ModuleInfo(ast.totuple(), basename)
```

This provides an easy-to-use interface to the documentation of a module. If information is required which is not extracted by the code of this example, the code may be extended at clearly defined points to provide additional capabilities.

18.2 symbol — Constants used with Python parse trees

This module provides constants which represent the numeric values of internal nodes of the parse tree. Unlike most Python constants, these use lower-case names. Refer to the file 'Grammar/Grammar' in the Python distribution for the definitions of the names in the context of the language grammar. The specific numeric values which the names map to may change between Python versions.

This module also provides one additional data object:

sym_name

Dictionary mapping the numeric values of the constants defined in this module back to name strings, allowing more human-readable representation of parse trees to be generated.

See Also:

Module parser (section 18.1):

The second example for the parser module shows how to use the symbol module.

18.3 token — Constants used with Python parse trees

This module provides constants which represent the numeric values of leaf nodes of the parse tree (terminal tokens). Refer to the file 'Grammar/Grammar' in the Python distribution for the definitions of the names in the context of the language grammar. The specific numeric values which the names map to may change between Python versions.

This module also provides one data object and some functions. The functions mirror definitions in the Python C header files.

tok_name

Dictionary mapping the numeric values of the constants defined in this module back to name strings, allowing more human-readable representation of parse trees to be generated.

 ${\tt ISTERMINAL}(x)$

Return true for terminal token values.

ISNONTERMINAL(X)

Return true for non-terminal token values.

ISEOF(x)

Return true if *x* is the marker indicating the end of input.

See Also:

Module parser (section 18.1):

The second example for the parser module shows how to use the symbol module.

18.4 keyword — Testing for Python keywords

This module allows a Python program to determine if a string is a keyword.

iskeyword(s)

Return true if *s* is a Python keyword.

kwlist

Sequence containing all the keywords defined for the interpreter. If any keywords are defined to only be active when particular __future__ statements are in effect, these will be included as well.

18.5 tokenize — Tokenizer for Python source

The tokenize module provides a lexical scanner for Python source code, implemented in Python. The scanner in this module returns comments as tokens as well, making it useful for implementing "pretty-printers," including colorizers for on-screen displays.

The primary entry point is a generator:

generate_tokens(readline)

The generate_tokens() generator requires one argment, *readline*, which must be a callable object which provides the same interface as the readline() method of built-in file objects (see section 2.3.9). Each call to the function should return one line of input as a string.

The generator produces 5-tuples with these members: the token type; the token string; a 2-tuple (*srow*, *scol*) of ints specifying the row and column where the token begins in the source; a 2-tuple (*erow*, *ecol*) of ints specifying the row and column where the token ends in the source; and the line on which the token was found. The line passed is the *logical* line; continuation lines are included. New in version 2.2.

An older entry point is retained for backward compatibility:

tokenize(readline[, tokeneater])

The tokenize() function accepts two parameters: one representing the input stream, and one providing an output mechanism for tokenize().

The first parameter, *readline*, must be a callable object which provides the same interface as the readline() method of built-in file objects (see section 2.3.9). Each call to the function should return one line of input as a string.

The second parameter, *tokeneater*, must also be a callable object. It is called once for each token, with five arguments, corresponding to the tuples generated by generate_tokens().

All constants from the token module are also exported from tokenize, as are two additional token type values that might be passed to the *tokeneater* function by tokenize():

COMMENT

Token value used to indicate a comment.

NL

Token value used to indicate a non-terminating newline. The NEWLINE token indicates the end of a logical

line of Python code; NL tokens are generated when a logical line of code is continued over multiple physical lines.

18.6 tabnanny — Detection of ambiguous indentation

For the time being this module is intended to be called as a script. However it is possible to import it into an IDE and use the function <code>check()</code> described below.

Warning: The API provided by this module is likely to change in future releases; such changes may not be backward compatible.

check(file_or_dir)

If file_or_dir is a directory and not a symbolic link, then recursively descend the directory tree named by file_or_dir, checking all '.py' files along the way. If file_or_dir is an ordinary Python source file, it is checked for whitespace related problems. The diagnostic messages are written to standard output using the print statement.

verbose

Flag indicating whether to print verbose messages. This is incremented by the -v option if called as a script.

filename_only

Flag indicating whether to print only the filenames of files containing whitespace related problems. This is set to true by the -q option if called as a script.

exception NannyNag

Raised by tokeneater() if detecting an ambiguous indent. Captured and handled in check().

tokeneater (type, token, start, end, line)

This function is used by check() as a callback parameter to the function tokenize.tokenize().

See Also:

Module tokenize (section 18.5):

Lexical scanner for Python source code.

18.7 pyclbr — Python class browser support

The pyclbr can be used to determine some limited information about the classes, methods and top-level functions defined in a module. The information provided is sufficient to implement a traditional three-pane class browser. The information is extracted from the source code rather than by importing the module, so this module is safe to use with untrusted source code. This restriction makes it impossible to use this module with modules not implemented in Python, including many standard and optional extension modules.

readmodule(module[, path])

Read a module and return a dictionary mapping class names to class descriptor objects. The parameter *module* should be the name of a module as a string; it may be the name of a module within a package. The *path* parameter should be a sequence, and is used to augment the value of sys.path, which is used to locate module source code.

readmodule_ex(module[, path])

Like readmodule(), but the returned dictionary, in addition to mapping class names to class descriptor objects, also maps top-level function names to function descriptor objects. Moreover, if the module being read is a package, the key '__path__' in the returned dictionary has as its value a list which contains the package search path.

18.7.1 Class Descriptor Objects

The class descriptor objects used as values in the dictionary returned by readmodule() and readmodule_ex() provide the following data members:

module

The name of the module defining the class described by the class descriptor.

name

The name of the class.

super

A list of class descriptors which describe the immediate base classes of the class being described. Classes which are named as superclasses but which are not discoverable by readmodule() are listed as a string with the class name instead of class descriptors.

methods

A dictionary mapping method names to line numbers.

file

Name of the file containing the class statement defining the class.

lineno

The line number of the class statement within the file named by file.

18.7.2 Function Descriptor Objects

The function descriptor objects used as values in the dictionary returned by readmodule_ex() provide the following data members:

module

The name of the module defining the function described by the function descriptor.

name

The name of the function.

file

Name of the file containing the def statement defining the function.

lineno

The line number of the def statement within the file named by file.

18.8 py_compile — Compile Python source files

The py_compile module provides a function to generate a byte-code file from a source file, and another function used when the module source file is invoked as a script.

Though not often needed, this function can be useful when installing modules for shared use, especially if some of the users may not have permission to write the byte-code cache files in the directory containing the source code.

exception PyCompileError

Exception raised when an error occurs while attempting to compile the file.

compile(file[, cfile[, dfile[, doraise]]])

Compile a source file to byte-code and write out the byte-code cache file. The source code is loaded from the file name *file*. The byte-code is written to *cfile*, which defaults to *file* + 'c' ('o' if optimization is enabled in the current interpreter). If *dfile* is specified, it is used as the name of the source file in error messages instead of *file*. If *doraise* = True, a PyCompileError is raised when an error is encountered while compiling *file*. If *doraise* = False (the default), an error string is written to sys.stderr, but no exception is raised.

main([args])

Compile several source files. The files named in *args* (or on the command line, if *args* is not specified) are compiled and the resulting bytecode is cached in the normal manner. This function does not search a directory structure to locate source files; it only compiles files named explicitly.

When this module is run as a script, the main() is used to compile all the files named on the command line.

See Also:

Module compileall (section 18.9):

Utilities to compile all Python source files in a directory tree.

18.9 compileall — Byte-compile Python libraries

This module provides some utility functions to support installing Python libraries. These functions compile Python source files in a directory tree, allowing users without permission to write to the libraries to take advantage of cached byte-code files.

The source file for this module may also be used as a script to compile Python sources in directories named on the command line or in sys.path.

```
compile_dir(dir[, maxlevels[, ddir[, force[, rx[, quiet]]]]])
```

Recursively descend the directory tree named by *dir*, compiling all '.py' files along the way. The *maxlevels* parameter is used to limit the depth of the recursion; it defaults to 10. If *ddir* is given, it is used as the base path from which the filenames used in error messages will be generated. If *force* is true, modules are re-compiled even if the timestamps are up to date.

If rx is given, it specifies a regular expression of file names to exclude from the search; that expression is searched for in the full path.

If quiet is true, nothing is printed to the standard output in normal operation.

```
compile_path([skip_curdir[, maxlevels[, force]]])
```

Byte-compile all the '.py' files found along sys.path. If $skip_curdir$ is true (the default), the current directory is not included in the search. The maxlevels and force parameters default to 0 and are passed to the $compile_dir()$ function.

See Also:

```
Module py_compile (section 18.8):
```

Byte-compile a single source file.

18.10 dis — Disassembler for Python byte code

The dis module supports the analysis of Python byte code by disassembling it. Since there is no Python assembler, this module defines the Python assembly language. The Python byte code which this module takes as an input is defined in the file 'Include/opcode.h' and used by the compiler and the interpreter.

Example: Given the function myfunc:

```
def myfunc(alist):
    return len(alist)
```

the following command can be used to get the disassembly of myfunc():

(The "2" is a line number).

The dis module defines the following functions and constants:

dis([bytesource])

Disassemble the *bytesource* object. *bytesource* can denote either a module, a class, a method, a function, or a code object. For a module, it disassembles all functions. For a class, it disassembles all methods. For a single code sequence, it prints one line per byte code instruction. If no object is provided, it disassembles the last traceback.

distb([tb])

Disassembles the top-of-stack function of a traceback, using the last traceback if none was passed. The instruction causing the exception is indicated.

disassemble(code[, lasti])

Disassembles a code object, indicating the last instruction if *lasti* was provided. The output is divided in the following columns:

- 1.the line number, for the first instruction of each line
- 2.the current instruction, indicated as '-->',
- 3.a labelled instruction, indicated with '>>',
- 4.the address of the instruction,
- 5.the operation code name,
- 6.operation parameters, and
- 7.interpretation of the parameters in parentheses.

The parameter interpretation recognizes local and global variable names, constant values, branch targets, and compare operators.

disco(code[, lasti])

A synonym for disassemble. It is more convenient to type, and kept for compatibility with earlier Python releases.

opname

Sequence of operation names, indexable using the byte code.

cmp_op

Sequence of all compare operation names.

hasconst

Sequence of byte codes that have a constant parameter.

hasfree

Sequence of byte codes that access a free variable.

hasname

Sequence of byte codes that access an attribute by name.

hasjrel

Sequence of byte codes that have a relative jump target.

hasjabs

Sequence of byte codes that have an absolute jump target.

haslocal

Sequence of byte codes that access a local variable.

hascompare

Sequence of byte codes of Boolean operations.

18.10.1 Python Byte Code Instructions

The Python compiler currently generates the following byte code instructions.

STOP CODE

Indicates end-of-code to the compiler, not used by the interpreter.

NOP

Do nothing code. Used as a placeholder by the bytecode optimizer.

POP_TOP

Removes the top-of-stack (TOS) item.

ROT_TWO

Swaps the two top-most stack items.

ROT_THREE

Lifts second and third stack item one position up, moves top down to position three.

ROT_FOUR

Lifts second, third and forth stack item one position up, moves top down to position four.

DUP_TOP

Duplicates the reference on top of the stack.

Unary Operations take the top of the stack, apply the operation, and push the result back on the stack.

UNARY_POSITIVE

Implements TOS = +TOS.

UNARY_NEGATIVE

Implements TOS = -TOS.

UNARY_NOT

Implements TOS = not TOS.

UNARY_CONVERT

Implements TOS = `TOS`.

UNARY_INVERT

Implements $TOS = ^TOS$.

GET_ITER

Implements TOS = iter(TOS).

Binary operations remove the top of the stack (TOS) and the second top-most stack item (TOS1) from the stack. They perform the operation, and put the result back on the stack.

BINARY_POWER

Implements TOS = TOS1 ** TOS.

BINARY_MULTIPLY

Implements TOS = TOS1 * TOS.

BINARY_DIVIDE

Implements TOS = TOS1 / TOS when from __future__ import division is not in effect.

BINARY_FLOOR_DIVIDE

Implements TOS = TOS1 // TOS.

BINARY_TRUE_DIVIDE

Implements TOS = TOS1 / TOS when from __future__ import division is in effect.

BINARY_MODULO

Implements TOS = TOS1 % TOS.

BINARY_ADD

Implements TOS = TOS1 + TOS.

BINARY_SUBTRACT

Implements TOS = TOS1 - TOS.

BINARY_SUBSCR

Implements TOS = TOS1[TOS].

BINARY_LSHIFT

Implements TOS = TOS1 << TOS.

BINARY_RSHIFT

Implements TOS = TOS1 >> TOS.

BINARY_AND

Implements TOS = TOS1 & TOS.

BINARY_XOR

Implements TOS = TOS1 ^ TOS.

BINARY_OR

Implements TOS = TOS1 | TOS.

In-place operations are like binary operations, in that they remove TOS and TOS1, and push the result back on the stack, but the operation is done in-place when TOS1 supports it, and the resulting TOS may be (but does not have to be) the original TOS1.

INPLACE_POWER

Implements in-place TOS = TOS1 ** TOS.

INPLACE_MULTIPLY

Implements in-place TOS = TOS1 * TOS.

INPLACE_DIVIDE

Implements in-place TOS = TOS1 / TOS when from __future__ import division is not in
effect.

INPLACE_FLOOR_DIVIDE

Implements in-place TOS = TOS1 // TOS.

INPLACE_TRUE_DIVIDE

Implements in-place TOS = TOS1 / TOS when from __future__ import division is in effect.

INPLACE_MODULO

Implements in-place TOS = TOS1 % TOS.

INPLACE_ADD

Implements in-place TOS = TOS1 + TOS.

INPLACE_SUBTRACT

Implements in-place TOS = TOS1 - TOS.

INPLACE_LSHIFT

Implements in-place TOS = TOS1 << TOS.

INPLACE_RSHIFT

Implements in-place TOS = TOS1 >> TOS.

INPLACE_AND

Implements in-place TOS = TOS1 & TOS.

INPLACE_XOR

Implements in-place $TOS = TOS1 ^ TOS$.

INPLACE_OR

Implements in-place TOS = TOS1 | TOS.

The slice opcodes take up to three parameters.

SLICE+0

Implements TOS = TOS[:].

SLICE+1

Implements TOS = TOS1[TOS:].

SLICE+2

Implements TOS = TOS1[:TOS].

SLICE+3

Implements TOS = TOS2[TOS1:TOS].

Slice assignment needs even an additional parameter. As any statement, they put nothing on the stack.

STORE_SLICE+0

Implements TOS[:] = TOS1.

STORE_SLICE+1

Implements TOS1[TOS:] = TOS2.

STORE_SLICE+2

Implements TOS1[:TOS] = TOS2.

STORE_SLICE+3

Implements TOS2[TOS1:TOS] = TOS3.

DELETE_SLICE+0

Implements del TOS[:].

DELETE_SLICE+1

Implements del TOS1[TOS:].

DELETE_SLICE+2

Implements del TOS1[:TOS].

DELETE_SLICE+3

Implements del TOS2[TOS1:TOS].

STORE_SUBSCR

Implements TOS1[TOS] = TOS2.

DELETE_SUBSCR

Implements del TOS1[TOS].

Miscellaneous opcodes.

PRINT_EXPR

Implements the expression statement for the interactive mode. TOS is removed from the stack and printed. In non-interactive mode, an expression statement is terminated with POP_STACK.

PRINT_ITEM

Prints TOS to the file-like object bound to sys.stdout. There is one such instruction for each item in the print statement.

PRINT_ITEM_TO

Like PRINT_ITEM, but prints the item second from TOS to the file-like object at TOS. This is used by the extended print statement.

PRINT_NEWLINE

Prints a new line on sys.stdout. This is generated as the last operation of a print statement, unless the statement ends with a comma.

PRINT_NEWLINE_TO

Like PRINT_NEWLINE, but prints the new line on the file-like object on the TOS. This is used by the extended print statement.

BREAK_LOOP

Terminates a loop due to a break statement.

CONTINUE_LOOP target

Continues a loop due to a continue statement. *target* is the address to jump to (which should be a FOR_ITER instruction).

LIST_APPEND

Calls list.append(TOS1, TOS). Used to implement list comprehensions.

LOAD_LOCALS

Pushes a reference to the locals of the current scope on the stack. This is used in the code for a class definition: After the class body is evaluated, the locals are passed to the class definition.

RETURN_VALUE

Returns with TOS to the caller of the function.

YIELD_VALUE

Pops TOS and yields it from a generator.

IMPORT_STAR

Loads all symbols not starting with '_' directly from the module TOS to the local namespace. The module is popped after loading all names. This opcode implements from module import *.

EXEC_STMT

Implements exec TOS2, TOS1, TOS. The compiler fills missing optional parameters with None.

POP_BLOCK

Removes one block from the block stack. Per frame, there is a stack of blocks, denoting nested loops, try statements, and such.

END_FINALLY

Terminates a finally clause. The interpreter recalls whether the exception has to be re-raised, or whether the function returns, and continues with the outer-next block.

BUILD_CLASS

Creates a new class object. TOS is the methods dictionary, TOS1 the tuple of the names of the base classes, and TOS2 the class name.

All of the following opcodes expect arguments. An argument is two bytes, with the more significant byte last.

STORE_NAME namei

Implements name = TOS. *namei* is the index of *name* in the attribute co_names of the code object. The compiler tries to use STORE_LOCAL or STORE_GLOBAL if possible.

DELETE_NAME namei

Implements del name, where namei is the index into co_names attribute of the code object.

UNPACK_SEQUENCE count

Unpacks TOS into *count* individual values, which are put onto the stack right-to-left.

DUP_TOPX count

Duplicate *count* items, keeping them in the same order. Due to implementation limits, *count* should be between 1 and 5 inclusive.

STORE_ATTR namei

Implements TOS. name = TOS1, where namei is the index of name in co_names.

DELETE_ATTR namei

Implements del TOS.name, using *namei* as index into co_names.

STORE_GLOBAL namei

Works as STORE_NAME, but stores the name as a global.

DELETE_GLOBAL namei

Works as DELETE_NAME, but deletes a global name.

LOAD_CONST consti

Pushes 'co_consts[consti]' onto the stack.

LOAD_NAME namei

Pushes the value associated with 'co_names [namei]' onto the stack.

BUILD_TUPLE count

Creates a tuple consuming *count* items from the stack, and pushes the resulting tuple onto the stack.

BUILD_LIST count

Works as BUILD_TUPLE, but creates a list.

BUILD_MAP zero

Pushes a new empty dictionary object onto the stack. The argument is ignored and set to zero by the compiler.

LOAD_ATTR namei

Replaces TOS with getattr(TOS, co_names[namei]).

COMPARE_OP opname

Performs a Boolean operation. The operation name can be found in cmp_op[opname].

IMPORT_NAME namei

Imports the module co_names [namei]. The module object is pushed onto the stack. The current namespace is not affected: for a proper import statement, a subsequent STORE_FAST instruction modifies the namespace.

IMPORT_FROM namei

Loads the attribute co_names [namei] from the module found in TOS. The resulting object is pushed onto the stack, to be subsequently stored by a STORE_FAST instruction.

JUMP_FORWARD delta

Increments byte code counter by delta.

JUMP_IF_TRUE delta

If TOS is true, increment the byte code counter by delta. TOS is left on the stack.

JUMP_IF_FALSE delta

If TOS is false, increment the byte code counter by delta. TOS is not changed.

JUMP_ABSOLUTE target

Set byte code counter to target.

FOR_ITER delta

TOS is an iterator. Call its next() method. If this yields a new value, push it on the stack (leaving the iterator below it). If the iterator indicates it is exhausted TOS is popped, and the byte code counter is incremented by *delta*.

LOAD_GLOBAL namei

Loads the global named co_names [namei] onto the stack.

SETUP_LOOP delta

Pushes a block for a loop onto the block stack. The block spans from the current instruction with a size of *delta* bytes.

SETUP_EXCEPT delta

Pushes a try block from a try-except clause onto the block stack. delta points to the first except block.

SETUP_FINALLY delta

Pushes a try block from a try-except clause onto the block stack. delta points to the finally block.

LOAD_FAST var_num

Pushes a reference to the local co_varnames[var_num] onto the stack.

STORE_FAST var_num

Stores TOS into the local co_varnames[var_num].

DELETE_FAST var_num

Deletes local co_varnames[var_num].

LOAD_CLOSURE i

Pushes a reference to the cell contained in slot i of the cell and free variable storage. The name of the variable is co_cellvars[i] if i is less than the length of $co_cellvars$. Otherwise it is co_freevars[i - len(co_cellvars)].

LOAD_DEREF i

Loads the cell contained in slot i of the cell and free variable storage. Pushes a reference to the object the cell contains on the stack.

STORE_DEREF i

Stores TOS into the cell contained in slot i of the cell and free variable storage.

SET_LINENO lineno

This opcode is obsolete.

RAISE_VARARGS argc

Raises an exception. *argc* indicates the number of parameters to the raise statement, ranging from 0 to 3. The handler will find the traceback as TOS2, the parameter as TOS1, and the exception as TOS.

CALL_FUNCTION argc

Calls a function. The low byte of *argc* indicates the number of positional parameters, the high byte the number of keyword parameters. On the stack, the opcode finds the keyword parameters first. For each keyword argument, the value is on top of the key. Below the keyword parameters, the positional parameters are on the stack, with the right-most parameter on top. Below the parameters, the function object to call is on the stack.

MAKE_FUNCTION argc

Pushes a new function object on the stack. TOS is the code associated with the function. The function object is defined to have *argc* default parameters, which are found below TOS.

MAKE_CLOSURE argc

Creates a new function object, sets its *func_closure* slot, and pushes it on the stack. TOS is the code associated with the function. If the code object has N free variables, the next N items on the stack are the cells for these variables. The function also has *argc* default parameters, where are found before the cells.

BUILD_SLICE argc

Pushes a slice object on the stack. *argc* must be 2 or 3. If it is 2, slice(TOS1, TOS) is pushed; if it is 3, slice(TOS2, TOS1, TOS) is pushed. See the slice() built-in function for more information.

EXTENDED_ARG ext

Prefixes any opcode which has an argument too big to fit into the default two bytes. *ext* holds two additional bytes which, taken together with the subsequent opcode's argument, comprise a four-byte argument, *ext* being the two most-significant bytes.

CALL_FUNCTION_VAR argc

Calls a function. *argc* is interpreted as in CALL_FUNCTION. The top element on the stack contains the variable argument list, followed by keyword and positional arguments.

CALL_FUNCTION_KW argc

Calls a function. *argc* is interpreted as in CALL_FUNCTION. The top element on the stack contains the keyword arguments dictionary, followed by explicit keyword and positional arguments.

CALL_FUNCTION_VAR_KW argc

Calls a function. *argc* is interpreted as in CALL_FUNCTION. The top element on the stack contains the keyword arguments dictionary, followed by the variable-arguments tuple, followed by explicit keyword and positional arguments.

18.11 pickletools — Tools for pickle developers.

This module contains various constants relating to the intimate details of the pickle module, some lengthy comments about the implementation, and a few useful functions for analyzing pickled data. The contents of this module are useful for Python core developers who are working on the pickle and cpickle implementations; ordinary users of the pickle module probably won't find the pickletools module relevant.

dis(pickle[, out=None, memo=None, indentlevel=4])

Outputs a symbolic disassembly of the pickle to the file-like object *out*, defaulting to sys.stdout. *pickle* can be a string or a file-like object. *memo* can be a Python dictionary that will be used as the pickle's memo; it can be used to perform disassemblies across multiple pickles created by the same pickler. Successive levels, indicated by MARK opcodes in the stream, are indented by *indentlevel* spaces.

genops (pickle)

Provides an iterator over all of the opcodes in a pickle, returning a sequence of (*opcode*, *arg*, *pos*) triples. *opcode* is an instance of an OpcodeInfo class; *arg* is the decoded value, as a Python object, of the opcode's argument; *pos* is the position at which this opcode is located. *pickle* can be a string or a file-like object.

18.12 distutils — Building and installing Python modules

The distutils package provides support for building and installing additional modules into a Python installation. The new modules may be either 100%-pure Python, or may be extension modules written in C, or may be collections of Python packages which include modules coded in both Python and C.

This package is discussed in two separate documents which are included in the Python documentation package. To learn about distributing new modules using the distutils facilities, read *Distributing Python Modules*; this includes documentation needed to extend distutils. To learn about installing Python modules, whether or not the author made use of the distutils package, read *Installing Python Modules*.

See Also:

Distributing Python Modules

(../dist/dist.html)

The manual for developers and packagers of Python modules. This describes how to prepare distutils-based packages so that they may be easily installed into an existing Python installation.

Installing Python Modules

(../inst/inst.html)

An "administrators" manual which includes information on installing modules into an existing Python installation. You do not need to be a Python programmer to read this manual.

Python compiler package

The Python compiler package is a tool for analyzing Python source code and generating Python bytecode. The compiler contains libraries to generate an abstract syntax tree from Python source code and to generate Python bytecode from the tree.

The compiler package is a Python source to bytecode translator written in Python. It uses the built-in parser and standard parser module to generated a concrete syntax tree. This tree is used to generate an abstract syntax tree (AST) and then Python bytecode.

The full functionality of the package duplicates the builtin compiler provided with the Python interpreter. It is intended to match its behavior almost exactly. Why implement another compiler that does the same thing? The package is useful for a variety of purposes. It can be modified more easily than the builtin compiler. The AST it generates is useful for analyzing Python source code.

This chapter explains how the various components of the compiler package work. It blends reference material with a tutorial.

The following modules are part of the compiler package:

19.1 The basic interface

The top-level of the package defines four functions. If you import compiler, you will get these functions and a collection of modules contained in the package.

parse(buf)

Returns an abstract syntax tree for the Python source code in *buf*. The function raises SyntaxError if there is an error in the source code. The return value is a compiler.ast.Module instance that contains the tree.

parseFile(path)

Return an abstract syntax tree for the Python source code in the file specified by path. It is equivalent to parse(open(path).read()).

walk(ast, visitor[, verbose])

Do a pre-order walk over the abstract syntax tree *ast*. Call the appropriate method on the *visitor* instance for each node encountered.

compile(source, filename, mode, flags=None, dont_inherit=None)

Compile the string *source*, a Python module, statement or expression, into a code object that can be executed by the exec statement or eval(). This function is a replacement for the built-in compile() function.

The *filename* will be used for run-time error messages.

The *mode* must be 'exec' to compile a module, 'single' to compile a single (interactive) statement, or 'eval' to compile an expression.

The *flags* and *dont_inherit* arguments affect future-related statements, but are not supported yet.

compileFile(source)

Compiles the file source and generates a .pyc file.

The compiler package contains the following modules: ast, consts, future, misc, pyassem, pycodegen, symbols, transformer, and visitor.

19.2 Limitations

There are some problems with the error checking of the compiler package. The interpreter detects syntax errors in two distinct phases. One set of errors is detected by the interpreter's parser, the other set by the compiler. The compiler package relies on the interpreter's parser, so it get the first phases of error checking for free. It implements the second phase itself, and that implementation is incomplete. For example, the compiler package does not raise an error if a name appears more than once in an argument list: def f(x, x): ...

A future version of the compiler should fix these problems.

19.3 Python Abstract Syntax

The compiler.ast module defines an abstract syntax for Python. In the abstract syntax tree, each node represents a syntactic construct. The root of the tree is Module object.

The abstract syntax offers a higher level interface to parsed Python source code. The parser module and the compiler written in C for the Python interpreter use a concrete syntax tree. The concrete syntax is tied closely to the grammar description used for the Python parser. Instead of a single node for a construct, there are often several levels of nested nodes that are introduced by Python's precedence rules.

The abstract syntax tree is created by the compiler.transformer module. The transformer relies on the builtin Python parser to generate a concrete syntax tree. It generates an abstract syntax tree from the concrete tree.

The transformer module was created by Greg Stein and Bill Tutt for an experimental Python-to-C compiler. The current version contains a number of modifications and improvements, but the basic form of the abstract syntax and of the transformer are due to Stein and Tutt.

19.3.1 AST Nodes

The compiler.ast module is generated from a text file that describes each node type and its elements. Each node type is represented as a class that inherits from the abstract base class compiler.ast.Node and defines a set of named attributes for child nodes.

class Node()

The Node instances are created automatically by the parser generator. The recommended interface for specific Node instances is to use the public attributes to access child nodes. A public attribute may be bound to a single node or to a sequence of nodes, depending on the Node type. For example, the bases attribute of the Class node, is bound to a list of base class nodes, and the doc attribute is bound to a single node.

Each Node instance has a lineno attribute which may be None. XXX Not sure what the rules are for which nodes will have a useful lineno.

All Node objects offer the following methods:

getChildren()

Returns a flattened list of the child nodes and objects in the order they occur. Specifically, the order of the nodes is the order in which they appear in the Python grammar. Not all of the children are Node instances. The names of functions and classes, for example, are plain strings.

getChildNodes()

Returns a flattened list of the child nodes in the order they occur. This method is like getChildren(), except that it only returns those children that are Node instances.

Two examples illustrate the general structure of Node classes. The while statement is defined by the following grammar production:

```
while_stmt: "while" expression ":" suite
["else" ":" suite]
```

The While node has three attributes: test, body, and else. (If the natural name for an attribute is also a Python reserved word, it can't be used as an attribute name. An underscore is appended to the word to make it a legal identifier, hence else_instead of else.)

The if statement is more complicated because it can include several tests.

```
if_stmt: 'if' test ':' suite ('elif' test ':' suite)* ['else' ':' suite]
```

The If node only defines two attributes: tests and else.. The tests attribute is a sequence of test expression, consequent body pairs. There is one pair for each if/elif clause. The first element of the pair is the test expression. The second elements is a Stmt node that contains the code to execute if the test is true.

The getChildren() method of If returns a flat list of child nodes. If there are three if/elif clauses and no else clause, then getChildren() will return a list of six elements: the first test expression, the first Stmt, the second text expression, etc.

The following table lists each of the Node subclasses defined in compiler.ast and each of the public attributes available on their instances. The values of most of the attributes are themselves Node instances or sequences of instances. When the value is something other than an instance, the type is noted in the comment. The attributes are listed in the order in which they are returned by getChildren() and getChildNodes().

Node type	Attribute	Value
Add	left	left operand
	right	right operand
And	nodes	list of operands
AssAttr		attribute as target of assignment
	expr	expression on the left-hand side of the dot
	attrname	the attribute name, a string
	flags	XXX
AssList	nodes	list of list elements being assigned to
AssName	name	name being assigned to
	flags	XXX
AssTuple	nodes	list of tuple elements being assigned to
Assert	test	the expression to be tested
	fail	the value of the AssertionError
Assign	nodes	a list of assignment targets, one per equal sign
	expr	the value being assigned
AugAssign	node	
	op	
	expr	
Backquote	expr	
Bitand	nodes	
Bitor	nodes	
Bitxor	nodes	
Break		
CallFunc	node	expression for the callee
	args	a list of arguments
	${\sf star_args}$	the extended *-arg value
	dstar_args	the extended **-arg value
Class	name	the name of the class, a string

Node type	Attribute	Value
	bases	a list of base classes
	doc	doc string, a string or None
	code	the body of the class statement
Compare	expr	
	ops	
Const	value	
Continue		
Decorators	nodes	List of function decorator expressions
Dict	items	
Discard	expr	
Div	left	
	right	
Ellipsis		
Exec	expr	
	locals	
	globals	
For	assign	
	list	
	body	
	else_	
From	modname	
	names	
Function	decorators	Decorators or None
	name	name used in def, a string
	argnames	list of argument names, as strings
	defaults	list of default values
	flags	XXX
	doc	doc string, a string or None
	code	the body of the function
Getattr	expr	
	attrname	
Global	names	
If	tests	
	else_	
Import	names	
Invert	expr	
Keyword	name	
	expr	
Lambda	argnames	
	defaults	
	flags	
	code	
LeftShift	left	
	right	
List	nodes	
ListComp	expr	
	quals	
ListCompFor	assign	
	list	
	ifs	
ListCompIf	test	
Mod	left	
	right	
Module	doc	doc string, a string or None
	node	body of the module, a Stmt
Mul	left	

Node type	Attribute	Value	
	right		
Name	name		

When an expression contains several attribute references, an assignment or delete statement will contain only one AssAttr node – for the final attribute reference. The other attribute references will be represented as Getattr nodes in the expr attribute of the AssAttr instance.

19.3.3 Examples

This section shows several simple examples of ASTs for Python source code. The examples demonstrate how to use the parse() function, what the repr of an AST looks like, and how to access attributes of an AST node.

The first module defines a single function. Assume it is stored in '/tmp/doublelib.py'.

```
"""This is an example module.
This is the docstring.
"""

def double(x):
    "Return twice the argument"
    return x * 2
```

In the interactive interpreter session below, I have reformatted the long AST reprs for readability. The AST reprs use unqualified class names. If you want to create an instance from a repr, you must import the class names from the compiler.ast module.

```
>>> import compiler
>>> mod = compiler.parseFile("/tmp/doublelib.py")
>>> mod
Module('This is an example module.\n\nThis is the docstring.\n',
       Stmt([Function(None, 'double', ['x'], [], 0,
                      'Return twice the argument',
                      Stmt([Return(Mul((Name('x'), Const(2))))])))
>>> from compiler.ast import *
>>> Module('This is an example module.\n\nThis is the docstring.\n',
       Stmt([Function(None, 'double', ['x'], [], 0,
                      'Return twice the argument',
. . .
                      Stmt([Return(Mul((Name('x'), Const(2))))])))
Module('This is an example module.\n\nThis is the docstring.\n',
       Stmt([Function(None, 'double', ['x'], [], 0,
                      'Return twice the argument',
                      Stmt([Return(Mul((Name('x'), Const(2))))])))
>>> mod.doc
'This is an example module.\n\nThis is the docstring.\n'
>>> for node in mod.node.nodes:
       print node
Function(None, 'double', ['x'], [], 0, 'Return twice the argument',
         Stmt([Return(Mul((Name('x'), Const(2))))]))
>>> func = mod.node.nodes[0]
>>> func.code
Stmt([Return(Mul((Name('x'), Const(2))))])
```

19.4 Using Visitors to Walk ASTs

The visitor pattern is ... The compiler package uses a variant on the visitor pattern that takes advantage of Python's introspection features to eliminate the need for much of the visitor's infrastructure.

The classes being visited do not need to be programmed to accept visitors. The visitor need only define visit methods for classes it is specifically interested in; a default visit method can handle the rest.

XXX The magic visit() method for visitors.

```
walk(tree, visitor[, verbose])
class ASTVisitor()
```

The ASTVisitor is responsible for walking over the tree in the correct order. A walk begins with a call to preorder(). For each node, it checks the *visitor* argument to preorder() for a method named 'visitNodeType,' where NodeType is the name of the node's class, e.g. for a While node a visitWhile() would be called. If the method exists, it is called with the node as its first argument.

The visitor method for a particular node type can control how child nodes are visited during the walk. The ASTVisitor modifies the visitor argument by adding a visit method to the visitor; this method can be used to visit a particular child node. If no visitor is found for a particular node type, the default() method is called.

ASTVisitor objects have the following methods:

XXX describe extra arguments

```
default(node[, ...])
dispatch(node[, ...])
preorder(tree, visitor)
```

19.5 Bytecode Generation

The code generator is a visitor that emits bytecodes. Each visit method can call the <code>emit()</code> method to emit a new bytecode. The basic code generator is specialized for modules, classes, and functions. An assembler converts that emitted instructions to the low-level bytecode format. It handles things like generator of constant lists of code objects and calculation of jump offsets.

SGI IRIX Specific Services

The modules described in this chapter provide interfaces to features that are unique to SGI's IRIX operating system (versions 4 and 5).

al	Audio functions on the SGI.
AL	Constants used with the al module.
cd	Interface to the CD-ROM on Silicon Graphics systems.
fl	FORMS library for applications with graphical user interfaces
FL	Constants used with the fl module.
flp	Functions for loading stored FORMS designs.
fm	Font Manager interface for SGI workstations.
gl	Functions from the Silicon Graphics Graphics Library.
DEVICE	Constants used with the gl module.
GL	Constants used with the gl module.
imgfile	Support for SGI imglib files.
jpeg	Read and write image files in compressed JPEG format.

20.1 al — Audio functions on the SGI

This module provides access to the audio facilities of the SGI Indy and Indigo workstations. See section 3A of the IRIX man pages for details. You'll need to read those man pages to understand what these functions do! Some of the functions are not available in IRIX releases before 4.0.5. Again, see the manual to check whether a specific function is available on your platform.

All functions and methods defined in this module are equivalent to the C functions with 'AL' prefixed to their name.

Symbolic constants from the C header file <audio.h> are defined in the standard module AL, see below.

Warning: The current version of the audio library may dump core when bad argument values are passed rather than returning an error status. Unfortunately, since the precise circumstances under which this may happen are undocumented and hard to check, the Python interface can provide no protection against this kind of problems. (One example is specifying an excessive queue size — there is no documented upper limit.)

The module defines the following functions:

```
openport(name, direction[, config])
```

The name and direction arguments are strings. The optional *config* argument is a configuration object as returned by newconfig(). The return value is an *audio port object*; methods of audio port objects are described below.

newconfig()

The return value is a new *audio configuration object*; methods of audio configuration objects are described below.

queryparams (device)

The device argument is an integer. The return value is a list of integers containing the data returned by ALqueryparams ().

```
getparams(device, list)
```

The *device* argument is an integer. The list argument is a list such as returned by queryparams (); it is modified in place (!).

setparams(device, list)

The *device* argument is an integer. The *list* argument is a list such as returned by queryparams ().

20.1.1 Configuration Objects

Configuration objects returned by newconfig() have the following methods:

getqueuesize()

Return the queue size.

setqueuesize(size)

Set the queue size.

getwidth()

Get the sample width.

setwidth(width)

Set the sample width.

getchannels()

Get the channel count.

setchannels(nchannels)

Set the channel count.

getsampfmt()

Get the sample format.

setsampfmt(sampfmt)

Set the sample format.

getfloatmax()

Get the maximum value for floating sample formats.

setfloatmax(floatmax)

Set the maximum value for floating sample formats.

20.1.2 Port Objects

Port objects, as returned by openport (), have the following methods:

closeport()

Close the port.

getfd()

Return the file descriptor as an int.

getfilled()

Return the number of filled samples.

getfillable()

Return the number of fillable samples.

readsamps (nsamples)

Read a number of samples from the queue, blocking if necessary. Return the data as a string containing the raw data, (e.g., 2 bytes per sample in big-endian byte order (high byte, low byte) if you have set the sample width to 2 bytes).

writesamps(samples)

Write samples into the queue, blocking if necessary. The samples are encoded as described for the readsamps() return value.

The module defines the following variables:

exception error

Exception raised on various errors.

DATASIZE

The size of one frame's worth of audio data. This is the size of the audio data as passed to the callback of type audio.

BLOCKSIZE

The size of one uninterpreted frame of audio data.

The following variables are states as returned by getstatus():

READY

The drive is ready for operation loaded with an audio CD.

NODISC

The drive does not have a CD loaded.

CDROM

The drive is loaded with a CD-ROM. Subsequent play or read operations will return I/O errors.

ERROR

An error occurred while trying to read the disc or its table of contents.

PLAYING

The drive is in CD player mode playing an audio CD through its audio jacks.

PAUSED

The drive is in CD layer mode with play paused.

STILL

The equivalent of PAUSED on older (non 3301) model Toshiba CD-ROM drives. Such drives have never been shipped by SGI.

audio

pnum

index

ptime

atime

catalog

ident

control

Integer constants describing the various types of parser callbacks that can be set by the addcallback() method of CD parser objects (see below).

20.3.1 Player Objects

Player objects (returned by open ()) have the following methods:

allowremoval()

Unlocks the eject button on the CD-ROM drive permitting the user to eject the caddy if desired.

bestreadsize()

Returns the best value to use for the *num_frames* parameter of the readda() method. Best is defined as the value that permits a continuous flow of data from the CD-ROM drive.

close()

Frees the resources associated with the player object. After calling close(), the methods of the object should no longer be used.

eject()

Ejects the caddy from the CD-ROM drive.

getstatus()

Returns information pertaining to the current state of the CD-ROM drive. The returned information is a tuple with the following values: *state*, *track*, *rtime*, *atime*, *ttime*, *first*, *last*, *scsi_audio*, *cur_block*. *rtime* is the time relative to the start of the current track; *atime* is the time relative to the beginning of the disc; *ttime* is the total time on the disc. For more information on the meaning of the values, see the man page *CDgetstatus*(3dm). The value of *state* is one of the following: ERROR, NODISC, READY, PLAYING, PAUSED, STILL, or CDROM.

gettrackinfo(track)

Returns information about the specified track. The returned information is a tuple consisting of two elements, the start time of the track and the duration of the track.

msftoblock(min, sec, frame)

Converts a minutes, seconds, frames triple representing a time in absolute time code into the corresponding logical block number for the given CD-ROM drive. You should use msftoframe() rather than msftoblock() for comparing times. The logical block number differs from the frame number by an offset required by certain CD-ROM drives.

play(start, play)

Starts playback of an audio CD in the CD-ROM drive at the specified track. The audio output appears on the CD-ROM drive's headphone and audio jacks (if fitted). Play stops at the end of the disc. *start* is the number of the track at which to start playing the CD; if *play* is 0, the CD will be set to an initial paused state. The method togglepause() can then be used to commence play.

playabs (minutes, seconds, frames, play)

Like play(), except that the start is given in minutes, seconds, and frames instead of a track number.

playtrack(start, play)

Like play(), except that playing stops at the end of the track.

playtrackabs(track, minutes, seconds, frames, play)

Like play(), except that playing begins at the specified absolute time and ends at the end of the specified track.

preventremoval()

Locks the eject button on the CD-ROM drive thus preventing the user from arbitrarily ejecting the caddy.

readda(num_frames)

Reads the specified number of frames from an audio CD mounted in the CD-ROM drive. The return value is a string representing the audio frames. This string can be passed unaltered to the parseframe() method of the parser object.

seek(minutes, seconds, frames)

Sets the pointer that indicates the starting point of the next read of digital audio data from a CD-ROM. The pointer is set to an absolute time code location specified in *minutes*, *seconds*, and *frames*. The return value is the logical block number to which the pointer has been set.

seekblock(block)

Sets the pointer that indicates the starting point of the next read of digital audio data from a CD-ROM. The pointer is set to the specified logical block number. The return value is the logical block number to which the pointer has been set.

seektrack(track)

Sets the pointer that indicates the starting point of the next read of digital audio data from a CD-ROM. The pointer is set to the specified track. The return value is the logical block number to which the pointer has been set.

stop()

Stops the current playing operation.

togglepause()

Pauses the CD if it is playing, and makes it play if it is paused.

20.3.2 Parser Objects

Parser objects (returned by createparser()) have the following methods:

addcallback(type, func, arg)

Adds a callback for the parser. The parser has callbacks for eight different types of data in the digital audio data stream. Constants for these types are defined at the cd module level (see above). The callback is called as follows: func(arg, type, data), where arg is the user supplied argument, type is the particular type of callback, and data is the data returned for this type of callback. The type of the data depends on the type of callback as follows:

Type	Value
audio	String which can be passed unmodified to al.writesamps().
pnum	Integer giving the program (track) number.
index	Integer giving the index number.
ptime	Tuple consisting of the program time in minutes, seconds, and frames.
atime	Tuple consisting of the absolute time in minutes, seconds, and frames.
catalog	String of 13 characters, giving the catalog number of the CD.
ident	String of 12 characters, giving the ISRC identification number of the
	recording. The string consists of two characters country code, three char-
	acters owner code, two characters giving the year, and five characters
	giving a serial number.
control	Integer giving the control bits from the CD subcode data

deleteparser()

Deletes the parser and frees the memory it was using. The object should not be used after this call. This call is done automatically when the last reference to the object is removed.

parseframe(frame)

Parses one or more frames of digital audio data from a CD such as returned by readda(). It determines which subcodes are present in the data. If these subcodes have changed since the last frame, then parseframe() executes a callback of the appropriate type passing to it the subcode data found in the frame. Unlike the C function, more than one frame of digital audio data can be passed to this method.

removecallback(type)

Removes the callback for the given type.

resetparser()

Resets the fields of the parser used for tracking subcodes to an initial state. resetparser() should be called after the disc has been changed.

20.4 fl — FORMS library for graphical user interfaces

This module provides an interface to the FORMS Library by Mark Overmars. The source for the library can be retrieved by anonymous ftp from host 'ftp.cs.ruu.nl', directory 'SGI/FORMS'. It was last tested with version 2.0b.

Most functions are literal translations of their C equivalents, dropping the initial 'fl_' from their name. Constants used by the library are defined in module FL described below.

The creation of objects is a little different in Python than in C: instead of the 'current form' maintained by the library to which new FORMS objects are added, all functions that add a FORMS object to a form are methods of the Python object representing the form. Consequently, there are no Python equivalents for the C functions fl_addto_form() and fl_end_form(), and the equivalent of fl_bgn_form() is called fl.make_form().

Watch out for the somewhat confusing terminology: FORMS uses the word *object* for the buttons, sliders etc. that you can place in a form. In Python, 'object' means any value. The Python interface to FORMS introduces two new Python object types: form objects (representing an entire form) and FORMS objects (representing one button, slider etc.). Hopefully this isn't too confusing.

There are no 'free objects' in the Python interface to FORMS, nor is there an easy way to add object classes written in Python. The FORMS interface to GL event handling is available, though, so you can mix FORMS with pure GL windows.

Please note: importing fl implies a call to the GL function foreground() and to the FORMS routine fl_init().

20.4.1 Functions Defined in Module fl

Module fl defines the following functions. For more information about what they do, see the description of the equivalent C function in the FORMS documentation:

make_form(type, width, height)

Create a form with given type, width and height. This returns a *form* object, whose methods are described below.

do_forms()

The standard FORMS main loop. Returns a Python object representing the FORMS object needing interaction, or the special value FL. EVENT.

check_forms()

Check for FORMS events. Returns what do_forms() above returns, or None if there is no event that immediately needs interaction.

set_event_call_back(function)

Set the event callback function.

set_graphics_mode(rgbmode, doublebuffering)

Set the graphics modes.

get_rgbmode()

Return the current rgb mode. This is the value of the C global variable fl_rgbmode.

show_rmfi8.928

show

dle some GL events yourself when using fl.do_events(). When a GL event is detected that FORMS cannot handle, fl.do_forms() returns the special value FL.EVENT and you should call fl.qread() to read the event from the queue. Don't use the equivalent GL functions!

```
color()
mapcolor()
getmcolor()
    See the description in the FORMS documentation of fl_color(), fl_mapcolor() and
    fl_getmcolor().
```

20.4.2 Form Objects

Form objects (returned by make_form() above) have the following methods. Each method corresponds to a C function whose name is prefixed with 'fl_'; and whose first argument is a form pointer; please refer to the official FORMS documentation for descriptions.

All the add_* () methods return a Python object representing the FORMS object. Methods of FORMS objects are described below. Most kinds of FORMS object also have some methods specific to that kind; these methods are listed here.

```
show_form(placement, bordertype, name)
     Show the form.
hide_form()
     Hide the form.
redraw_form()
     Redraw the form.
set_form_position(x, y)
     Set the form's position.
freeze_form()
     Freeze the form.
unfreeze_form()
     Unfreeze the form.
activate_form()
     Activate the form.
deactivate_form()
     Deactivate the form.
bgn_group()
     Begin a new group of objects; return a group object.
end_group()
     End the current group of objects.
find_first()
     Find the first object in the form.
find_last()
     Find the last object in the form.
add_box(type, x, y, w, h, name)
     Add a box object to the form. No extra methods.
add_text(type, x, y, w, h, name)
     Add a text object to the form. No extra methods.
add_clock(type, x, y, w, h, name)
     Add a clock object to the form.
     Method: get_clock().
```

```
add_button(type, x, y, w, h, name)
    Add a button object to the form.
    Methods: get_button(), set_button().
add_lightbutton(type, x, y, w, h, name)
     Add a lightbutton object to the form.
    Methods: get_button(), set_button().
add_roundbutton(type, x, y, w, h, name)
     Add a roundbutton object to the form.
    Methods: get_button(), set_button().
add_slider(type, x, y, w, h, name)
    Add a slider object to the form.
    Methods: set_slider_value(), get_slider_value(), set_slider_bounds(),
    get_slider_bounds(), set_slider_return(), set_slider_size(),
    set_slider_precision(), set_slider_step().
add_valslider(type, x, y, w, h, name)
    Add a valslider object to the form.
    Methods: set_slider_value(), get_slider_value(), set_slider_bounds(),
    get_slider_bounds(), set_slider_return(), set_slider_size(),
    set_slider_precision(), set_slider_step().
add_dial(type, x, y, w, h, name)
    Add a dial object to the form.
    Methods: set_dial_value(), get_dial_value(), set_dial_bounds(),
    get_dial_bounds().
add_positioner(type, x, y, w, h, name)
    Add a positioner object to the form.
    Methods: set_positioner_xvalue(), set_positioner_yvalue(),
    set_positioner_xbounds(), set_positioner_ybounds(),
    get_positioner_xvalue(), get_positioner_yvalue(),
    get_positioner_xbounds(), get_positioner_ybounds().
add_counter(type, x, y, w, h, name)
    Add a counter object to the form.
    Methods: set_counter_value(), get_counter_value(), set_counter_bounds(),
    set_counter_step(), set_counter_precision(), set_counter_return().
add_input(type, x, y, w, h, name)
    Add a input object to the form.
    Methods: set_input(), get_input(), set_input_color(), set_input_return().
add_menu(type, x, y, w, h, name)
    Add a menu object to the form.
    Methods: set_menu(), get_menu(), addto_menu().
add_choice(type, x, y, w, h, name)
    Add a choice object to the form.
    Methods: set_choice(), get_choice(), clear_choice(), addto_choice(),
    replace_choice(), delete_choice(), get_choice_text(),
    set_choice_fontsize(), set_choice_fontstyle().
add_browser(type, x, y, w, h, name)
    Add a browser object to the form.
    Methods: set_browser_topline(), clear_browser(), add_browser_line(),
    addto_browser(), insert_browser_line(), delete_browser_line(),
    replace_browser_line(), get_browser_line(), load_browser(),
    get_browser_maxline(), select_browser_line(), deselect_browser_line(),
    deselect_browser(), isselected_browser_line(), get_browser(),
    set_browser_fontsize(), set_browser_fontstyle(), set_browser_specialkey().
```

add_timer(type, x, y, w, h, name) Add a timer object to the form. Methods: set_timer(), get_timer().

Form objects have the following data attributes; see the FORMS documentation:

Name	C Type	Meaning
window	int (read-only)	GL window id
W	float	form width
h	float	form height
X	float	form x origin
У	float	form y origin
deactivated	int	nonzero if form is deactivated
visible	int	nonzero if form is visible
frozen	int	nonzero if form is frozen
doublebuf	int	nonzero if double buffering on

20.4.3 FORMS Objects

Besides methods specific to particular kinds of FORMS objects, all FORMS objects also have the following methods:

set_call_back(function, argument)

Set the object's callback function and argument. When the object needs interaction, the callback function will be called with two arguments: the object, and the callback argument. (FORMS objects without a callback function are returned by fl.do_forms() or fl.check_forms() when they need interaction.) Call this method without arguments to remove the callback function.

delete_object()

Delete the object.

show_object()

Show the object.

hide_object()

Hide the object.

redraw_object()

Redraw the object.

freeze_object()

Freeze the object.

unfreeze_object()

Unfreeze the object.

FORMS objects have these data attributes; see the FORMS documentation:

Name	C Type	Meaning
objclass	int (read-only)	object class
type	int (read-only)	object type
boxtype	int	box type
X	float	x origin
У	float	y origin
W	float	width
h	float	height
col1	int	primary color
col2	int	secondary color
align	int	alignment
lcol	int	label color
lsize	float	label font size
label	string	label string
lstyle	int	label style
pushed	int (read-only)	(see FORMS docs)
focus	int (read-only)	(see FORMS docs)
belowmouse	int (read-only)	(see FORMS docs)
frozen	int (read-only)	(see FORMS docs)
active	int (read-only)	(see FORMS docs)
input	int (read-only)	(see FORMS docs)
visible	int (read-only)	(see FORMS docs)
radio	int (read-only)	(see FORMS docs)
automatic	int (read-only)	(see FORMS docs)

20.5 FL — Constants used with the fl module

This module defines symbolic constants needed to use the built-in module fl (see above); they are equivalent to those defined in the C header file <forms.h> except that the name prefix 'FL_' is omitted. Read the module source for a complete list of the defined names. Suggested use:

```
import fl
from FL import *
```

20.6 flp — Functions for loading stored FORMS designs

This module defines functions that can read form definitions created by the 'form designer' (**fdesign**) program that comes with the FORMS library (see module £1 above).

For now, see the file 'flp.doc' in the Python library source directory for a description.

XXX A complete description should be inserted here!

20.7 fm — Font Manager interface

This module provides access to the IRIS *Font Manager* library. It is available only on Silicon Graphics machines. See also: *4Sight User's Guide*, section 1, chapter 5: "Using the IRIS Font Manager."

This is not yet a full interface to the IRIS Font Manager. Among the unsupported features are: matrix operations; cache operations; character operations (use string operations instead); some details of font info; individual glyph metrics; and printer matching.

It supports the following operations:

init()

Initialization function. Calls fminit(). It is normally not necessary to call this function, since it is called automatically the first time the fm module is imported.

findfont(fontname)

Return a font handle object. Calls fmfindfont (fontname).

enumerate()

Returns a list of available font names. This is an interface to fmenumerate().

prstr(string)

Render a string using the current font (see the setfont() font handle method below). Calls fmprstr(string).

setpath(string)

Sets the font search path. Calls fmsetpath(string). (XXX Does not work!?!)

fontpath()

Returns the current font search path.

Font handle objects support the following operations:

scalefont(factor)

Returns a handle for a scaled version of this font. Calls fmscalefont (fh, factor).

setfont()

Makes this font the current font. Note: the effect is undone silently when the font handle object is deleted. Calls fmsetfont(fh).

getfontname()

Returns this font's name. Calls fmgetfontname(fh).

getcomment()

Returns the comment string associated with this font. Raises an exception if there is none. Calls figetcomment(fh).

getfontinfo()

Returns a tuple giving some pertinent data about this font. This is an interface to fmgetfontinfo(). The returned tuple contains the following numbers: (printermatched, fixed_width, xorig, yorig, xsize, ysize, height, nglyphs).

getstrwidth(string)

Returns the width, in pixels, of *string* when drawn in this font. Calls fmgetstrwidth(*fh*, *string*).

20.8 gl — Graphics Library interface

This module provides access to the Silicon Graphics *Graphics Library*. It is available only on Silicon Graphics machines.

Warning: Some illegal calls to the GL library cause the Python interpreter to dump core. In particular, the use of most GL calls is unsafe before the first window is opened.

The module is too large to document here in its entirety, but the following should help you to get started. The parameter conventions for the C functions are translated to Python as follows:

- All (short, long, unsigned) int values are represented by Python integers.
- All float and double values are represented by Python floating point numbers. In most cases, Python integers are also allowed.
- All arrays are represented by one-dimensional Python lists. In most cases, tuples are also allowed.
- All string and character arguments are represented by Python strings, for instance, winopen('Hi There!') and rotate(900, 'z').

• All (short, long, unsigned) integer arguments or return values that are only used to specify the length of an array argument are omitted. For example, the C call

```
lmdef(deftype, index, np, props)
is translated to Python as
lmdef(deftype, index, props)
```

• Output arguments are omitted from the argument list; they are transmitted as function return values instead. If more than one value must be returned, the return value is a tuple. If the C function has both a regular return value (that is not omitted because of the previous rule) and an output argument, the return value comes first in the tuple. Examples: the C call

```
getmcolor(i, &red, &green, &blue)
is translated to Python as

red, green, blue = getmcolor(i)
```

The following functions are non-standard or have special argument conventions:

```
varray(argument)
```

Equivalent to but faster than a number of v3d() calls. The *argument* is a list (or tuple) of points. Each point must be a tuple of coordinates (x, y, z) or (x, y). The points may be 2- or 3-dimensional but must all have the same dimension. Float and int values may be mixed however. The points are always converted to 3D double precision points by assuming z = 0.0 if necessary (as indicated in the man page), and for each point v3d() is called.

nvarray()

Equivalent to but faster than a number of n3f and v3f calls. The argument is an array (list or tuple) of pairs of normals and points. Each pair is a tuple of a point and a normal for that point. Each point or normal must be a tuple of coordinates (x, y, z). Three coordinates must be given. Float and int values may be mixed. For each pair, n3f() is called for the normal, and then v3f() is called for the point.

vnarray()

Similar to nvarray() but the pairs have the point first and the normal second.

```
nurbssurface(s_k, t_k, ctl, s_ord, t_ord, type)
```

```
Defines a nurbs surface. The dimensions of ctl[][] are computed as follows: [len(s\_k) - s\_ord], [len(t\_k) - t\_ord].
```

nurbscurve(knots, ctlpoints, order, type)

Defines a nurbs curve. The length of ctlpoints is len(knots) - order.

```
pwlcurve(points, type)
```

Defines a piecewise-linear curve. points is a list of points. type must be N_ST.

```
pick(n)
select(n)
```

The only argument to these functions specifies the desired size of the pick or select buffer.

```
endpick()
endselect()
```

These functions have no arguments. They return a list of integers representing the used part of the pick/select buffer. No method is provided to detect buffer overrun.

Here is a tiny but complete example GL program in Python:

```
import gl, GL, time
def main():
    gl.foreground()
    gl.prefposition(500, 900, 500, 900)
    w = gl.winopen('CrissCross')
    gl.ortho2(0.0, 400.0, 0.0, 400.0)
    gl.color(GL.WHITE)
    gl.clear()
    gl.color(GL.RED)
    gl.bgnline()
    gl.v2f(0.0, 0.0)
    gl.v2f(400.0, 400.0)
    gl.endline()
    gl.bgnline()
    gl.v2f(400.0, 0.0)
    gl.v2f(0.0, 400.0)
    gl.endline()
    time.sleep(5)
main()
```

See Also:

PyOpenGL: The Python OpenGL Binding (http://pyopengl.sourceforge.net/)

An interface to OpenGL is also available; see information about the **PyOpenGL** project online at http://pyopengl.sourceforge.net/. This may be a better option if support for SGI hardware from before about 1996 is not required.

20.9 DEVICE — Constants used with the gl module

This modules defines the constants used by the Silicon Graphics *Graphics Library* that C programmers find in the header file <ql/>1/device.h>. Read the module source file for details.

20.10 GL — Constants used with the gl module

This module contains constants used by the Silicon Graphics *Graphics Library* from the C header file <gl/>| file .h>. Read the module source file for details.

20.11 imgfile — Support for SGI imglib files

The imgfile module allows Python programs to access SGI imglib image files (also known as '.rgb' files). The module is far from complete, but is provided anyway since the functionality that there is enough in some cases. Currently, colormap files are not supported.

The module defines the following variables and functions:

exception error

This exception is raised on all errors, such as unsupported file type, etc.

```
getsizes(file)
```

This function returns a tuple (x, y, z) where x and y are the size of the image in pixels and z is the number of bytes per pixel. Only 3 byte RGB pixels and 1 byte greyscale pixels are currently supported.

read(file)

This function reads and decodes the image on the specified file, and returns it as a Python string. The string has either 1 byte greyscale pixels or 4 byte RGBA pixels. The bottom left pixel is the first in the string. This format is suitable to pass to gl.lrectwrite(), for instance.

readscaled(file, x, y, filter[, blur])

This function is identical to read but it returns an image that is scaled to the given x and y sizes. If the *filter* and *blur* parameters are omitted scaling is done by simply dropping or duplicating pixels, so the result will be less than perfect, especially for computer-generated images.

Alternatively, you can specify a filter to use to smooth the image after scaling. The filter forms supported are 'impulse', 'box', 'triangle', 'quadratic' and 'gaussian'. If a filter is specified *blur* is an optional parameter specifying the blurriness of the filter. It defaults to 1.0.

readscaled() makes no attempt to keep the aspect ratio correct, so that is the users' responsibility.

ttob(flag)

This function sets a global flag which defines whether the scan lines of the image are read or written from bottom to top (flag is zero, compatible with SGI GL) or from top to bottom(flag is one, compatible with X). The default is zero.

write(file, data, x, y, z)

This function writes the RGB or greyscale data in *data* to image file *file*. *x* and *y* give the size of the image, *z* is 1 for 1 byte greyscale images or 3 for RGB images (which are stored as 4 byte values of which only the lower three bytes are used). These are the formats returned by gl.lrectread().

20.12 jpeg — Read and write JPEG files

The module jpeg provides access to the jpeg compressor and decompressor written by the Independent JPEG Group (IJG). JPEG is a standard for compressing pictures; it is defined in ISO 10918. For details on JPEG or the Independent JPEG Group software refer to the JPEG standard or the documentation provided with the software.

A portable interface to JPEG image files is available with the Python Imaging Library (PIL) by Fredrik Lundh. Information on PIL is available at http://www.pythonware.com/products/pil/.

The jpeg module defines an exception and some functions.

exception error

Exception raised by compress() and decompress() in case of errors.

compress(data, w, h, b)

Treat data as a pixmap of width w and height h, with b bytes per pixel. The data is in SGI GL order, so the first pixel is in the lower-left corner. This means that gl.lrectread() return data can immediately be passed to compress(). Currently only 1 byte and 4 byte pixels are allowed, the former being treated as greyscale and the latter as RGB color. compress() returns a string that contains the compressed picture, in JFIF format.

decompress(data)

Data is a string containing a picture in JFIF format. It returns a tuple (data, width, height, bytesper-pixel). Again, the data is suitable to pass to gl.lrectwrite().

setoption(name, value)

Set various options. Subsequent compress() and decompress() calls will use these options. The following options are available:

Option	Effect	
'forcegray'	Force output to be grayscale, even if input is RGB.	
'quality'	Set the quality of the compressed image to a value be-	
	tween 0 and 100 (default is 75). This only affects compression.	
'optimize'	Perform Huffman table optimization. Takes longer,	
	but results in smaller compressed image. This only	
	affects compression.	
'smooth'	Perform inter-block smoothing on uncompressed im-	
	age. Only useful for low-quality images. This only	
	affects decompression.	

See Also:

JPEG Still Image Data Compression Standard

The canonical reference for the JPEG image format, by Pennebaker and Mitchell.

Information Technology - Digital Compression and Coding of Continuous-tone Still Images - Requirements and Guidelines (http://www.w3.org/Graphics/JPEG/itu-t81.pdf)

The ISO standard for JPEG is also published as ITU T.81. This is available online in PDF form.

SunOS Specific Services

The modules described in this chapter provide interfaces to features that are unique to SunOS 5 (also known as Solaris version 2).

21.1 sunaudiodev — Access to Sun audio hardware

This module allows you to access the Sun audio interface. The Sun audio hardware is capable of recording and playing back audio data in u-LAW format with a sample rate of 8K per second. A full description can be found in the *audio*(7I) manual page.

The module SUNAUDIODEV defines constants which may be used with this module.

This module defines the following variables and functions:

exception error

This exception is raised on all errors. The argument is a string describing what went wrong.

open(mode)

This function opens the audio device and returns a Sun audio device object. This object can then be used to do I/O on. The *mode* parameter is one of 'r' for record-only access, 'w' for play-only access, 'rw' for both and 'control' for access to the control device. Since only one process is allowed to have the recorder or player open at the same time it is a good idea to open the device only for the activity needed. See *audio*(7I) for details.

As per the manpage, this module first looks in the environment variable AUDIODEV for the base audio device filename. If not found, it falls back to '/dev/audio'. The control device is calculated by appending "ctl" to the base audio device.

21.1.1 Audio Device Objects

The audio device objects are returned by open() define the following methods (except control objects which only provide getinfo(), setinfo(), fileno(), and drain()):

close()

This method explicitly closes the device. It is useful in situations where deleting the object does not immediately close it since there are other references to it. A closed device should not be used again.

fileno()

Returns the file descriptor associated with the device. This can be used to set up SIGPOLL notification, as described below.

drain()

This method waits until all pending output is processed and then returns. Calling this method is often not necessary: destroying the object will automatically close the audio device and this will do an implicit drain.

flush()

This method discards all pending output. It can be used avoid the slow response to a user's stop request (due to buffering of up to one second of sound).

getinfo()

This method retrieves status information like input and output volume, etc. and returns it in the form of an audio status object. This object has no methods but it contains a number of attributes describing the current device status. The names and meanings of the attributes are described in <sun/audioio.h> and in the *audio*(7I) manual page. Member names are slightly different from their C counterparts: a status object is only a single structure. Members of the play substructure have 'o_' prepended to their name and members of the record structure have 'i_'. So, the C member play.sample_rate is accessed as o_sample_rate, record.gain as i_gain and monitor_gain plainly as monitor_gain.

ibufcount()

This method returns the number of samples that are buffered on the recording side, i.e. the program will not block on a read() call of so many samples.

obufcount()

This method returns the number of samples buffered on the playback side. Unfortunately, this number cannot be used to determine a number of samples that can be written without blocking since the kernel output queue length seems to be variable.

read(size)

This method reads *size* samples from the audio input and returns them as a Python string. The function blocks until enough data is available.

setinfo(status)

This method sets the audio device status parameters. The *status* parameter is an device status object as returned by getinfo() and possibly modified by the program.

write(samples)

Write is passed a Python string containing audio samples to be played. If there is enough buffer space free it will immediately return, otherwise it will block.

The audio device supports asynchronous notification of various events, through the SIGPOLL signal. Here's an example of how you might enable this in Python:

```
def handle_sigpoll(signum, frame):
    print 'I got a SIGPOLL update'

import fcntl, signal, STROPTS

signal.signal(signal.SIGPOLL, handle_sigpoll)
fcntl.ioctl(audio_obj.fileno(), STROPTS.I_SETSIG, STROPTS.S_MSG)
```

21.2 SUNAUDIODEV — Constants used with sunaudiodev

This is a companion module to sunaudiodev which defines useful symbolic constants like MIN_GAIN, MAX_GAIN, SPEAKER, etc. The names of the constants are the same names as used in the C include file <sun/audioio.h>, with the leading string 'AUDIO_' stripped.

MS Windows Specific Services

This chapter describes modules that are only available on MS Windows platforms.

msvcrt Miscellaneous useful routines from the MS VC++ runtime.

winreg Routines and objects for manipulating the Windows registry.

Access to the sound-playing machinery for Windows.

22.1 msvcrt - Useful routines from the MS VC++ runtime

These functions provide access to some useful capabilities on Windows platforms. Some higher-level modules use these functions to build the Windows implementations of their services. For example, the getpass module uses this in the implementation of the getpass() function.

Further documentation on these functions can be found in the Platform API documentation.

22.1.1 File Operations

locking(fd, mode, nbytes)

Lock part of a file based on file descriptor *fd* from the C runtime. Raises IOError on failure. The locked region of the file extends from the current file position for *nbytes* bytes, and may continue beyond the end of the file. *mode* must be one of the LK_* constants listed below. Multiple regions in a file may be locked at the same time, but may not overlap. Adjacent regions are not merged; they must be unlocked individually.

LK_LOCK

LK_RLCK

Locks the specified bytes. If the bytes cannot be locked, the program immediately tries again after 1 second. If, after 10 attempts, the bytes cannot be locked, IOError is raised.

LK_NBLCK

LK_NBRLCK

Locks the specified bytes. If the bytes cannot be locked, IOError is raised.

LK_UNLCK

Unlocks the specified bytes, which must have been previously locked.

setmode (fd, flags)

Set the line-end translation mode for the file descriptor fd. To set it to text mode, flags should be os.O_TEXT; for binary, it should be os.O_BINARY.

open_osfhandle(handle, flags)

Create a C runtime file descriptor from the file handle *handle*. The *flags* parameter should be a bit-wise OR of os.O_APPEND, os.O_RDONLY, and os.O_TEXT. The returned file descriptor may be used as a parameter to os.fdopen() to create a file object.

$get_osfhandle(fd)$

Return the file handle for the file descriptor fd. Raises IOError if fd is not recognized.

22.1.2 Console I/O

kbhit()

Return true if a keypress is waiting to be read.

getch()

Read a keypress and return the resulting character. Nothing is echoed to the console. This call will block if a keypress is not already available, but will not wait for Enter to be pressed. If the pressed key was a special function key, this will return '\000' or '\xe0'; the next call will return the keycode. The Control-C keypress cannot be read with this function.

getche()

Similar to getch(), but the keypress will be echoed if it represents a printable character.

putch(char)

Print the character *char* to the console without buffering.

ungetch(char)

Cause the character *char* to be "pushed back" into the console buffer; it will be the next character read by getch() or getche().

22.1.3 Other Functions

heapmin()

Force the malloc() heap to clean itself up and return unused blocks to the operating system. This only works on Windows NT. On failure, this raises IOError.

22.2 _winreg - Windows registry access

New in version 2.0.

These functions expose the Windows registry API to Python. Instead of using an integer as the registry handle, a handle object is used to ensure that the handles are closed correctly, even if the programmer neglects to explicitly close them.

This module exposes a very low-level interface to the Windows registry; it is expected that in the future a new winreg module will be created offering a higher-level interface to the registry API.

This module offers the following functions:

CloseKey(hkey)

Closes a previously opened registry key. The hkey argument specifies a previously opened key.

Note that if hkey is not closed using this method, (or the handle.Close() closed when the hkey object is destroyed by Python.

ConnectRegistry(computer_name, key)

Establishes a connection to a predefined registry handle on another computer, and returns a *handle object computer_name* is the name of the remote computer, of the form r"\\computername". If None, the local computer is used.

key is the predefined handle to connect to.

The return value is the handle of the opened key. If the function fails, an EnvironmentError exception is raised.

CreateKey(key, sub_key)

Creates or opens the specified key, returning a handle object

key is an already open key, or one of the predefined HKEY_* constants.

sub_key is a string that names the key this method opens or creates.

If key is one of the predefined keys, sub_key may be None. In that case, the handle returned is the same key handle passed in to the function.

If the key already exists, this function opens the existing key

The return value is the handle of the opened key. If the function fails, an EnvironmentError exception is raised.

DeleteKey(key, sub_key)

Deletes the specified key.

key is an already open key, or any one of the predefined HKEY_* constants.

sub_key is a string that must be a subkey of the key identified by the *key* parameter. This value must not be None, and the key may not have subkeys.

This method can not delete keys with subkeys.

If the method succeeds, the entire key, including all of its values, is removed. If the method fails, an EnvironmentError exception is raised.

DeleteValue(key, value)

Removes a named value from a registry key.

key is an already open key, or one of the predefined HKEY_* constants.

value is a string that identifies the value to remove.

EnumKey(key, index)

Enumerates subkeys of an open registry key, returning a string.

key is an already open key, or any one of the predefined HKEY_* constants.

index is an integer that identifies the index of the key to retrieve.

The function retrieves the name of one subkey each time it is called. It is typically called repeatedly until an EnvironmentError exception is raised, indicating, no more values are available.

EnumValue(key, index)

Enumerates values of an open registry key, returning a tuple.

key is an already open key, or any one of the predefined HKEY_* constants.

index is an integer that identifies the index of the value to retrieve.

The function retrieves the name of one subkey each time it is called. It is typically called repeatedly, until an EnvironmentError exception is raised, indicating no more values.

The result is a tuple of 3 items:

Index	Meaning
0	A string that identifies the value name
1	An object that holds the value data, and whose type
	depends on the underlying registry type
2	An integer that identifies the type of the value data

FlushKey(key)

Writes all the attributes of a key to the registry.

key is an already open key, or one of the predefined HKEY_* constants.

It is not necessary to call RegFlushKey to change a key. Registry changes are flushed to disk by the registry using its lazy flusher. Registry changes are also flushed to disk at system shutdown. Unlike CloseKey(), the FlushKey() method returns only when all the data has been written to the registry. An application should only call FlushKey() if it requires absolute certainty that registry changes are on disk.

If you don't know whether a FlushKey() call is required, it probably isn't.

RegLoadKey(key, sub_key, file_name)

Creates a subkey under the specified key and stores registration information from a specified file into that subkey.

key is an already open key, or any of the predefined HKEY_* constants.

sub_key is a string that identifies the sub_key to load

file_name is the name of the file to load registry data from. This file must have been created with the SaveKey() function. Under the file allocation table (FAT) file system, the filename may not have an extension.

A call to LoadKey() fails if the calling process does not have the SE_RESTORE_PRIVILEGE privilege. Note that privileges are different than permissions - see the Win32 documentation for more details.

If key is a handle returned by ConnectRegistry(), then the path specified in *fileName* is relative to the remote computer.

The Win32 documentation implies *key* must be in the HKEY_USER or HKEY_LOCAL_MACHINE tree. This may or may not be true.

OpenKey (key,
$$sub_key[$$
, $res = 0][$, $sam = KEY_READ])$

Opens the specified key, returning a handle object

key is an already open key, or any one of the predefined HKEY_* constants.

sub_key is a string that identifies the sub_key to open

res is a reserved integer, and must be zero. The default is zero.

sam is an integer that specifies an access mask that describes the desired security access for the key. Default is KEY_READ

The result is a new handle to the specified key

If the function fails, EnvironmentError is raised.

OpenKeyEx()

The functionality of OpenKeyEx() is provided via OpenKey(), by the use of default arguments.

QueryInfoKey(key)

Returns information about a key, as a tuple.

key is an already open key, or one of the predefined HKEY_* constants.

The result is a tuple of 3 items:

Index	Meaning
0	An integer giving the number of sub keys this key has.
1	An integer giving the number of values this key has.
2	A long integer giving when the key was last modi-
	fied (if available) as 100's of nanoseconds since Jan
	1, 1600.

${\tt QueryValue}\,(\,\textit{key},\,\textit{sub_key}\,)$

Retrieves the unnamed value for a key, as a string

key is an already open key, or one of the predefined HKEY_* constants.

<code>sub_key</code> is a string that holds the name of the subkey with which the value is associated. If this parameter is None or empty, the function retrieves the value set by the <code>SetValue()</code> method for the key identified by <code>key</code>.

Values in the registry have name, type, and data components. This method retrieves the data for a key's first value that has a NULL name. But the underlying API call doesn't return the type, Lame Lame Lame, DO NOT USE THIS!!!

QueryValueEx(key, value_name)

Retrieves the type and data for a specified value name associated with an open registry key.

key is an already open key, or one of the predefined HKEY_* constants.

value_name is a string indicating the value to query.

The result is a tuple of 2 items:

Index	Meaning
0	The value of the registry item.
1	An integer giving the registry type for this value.

SaveKey(key, file_name)

Saves the specified key, and all its subkeys to the specified file.

key is an already open key, or one of the predefined HKEY_* constants.

file_name is the name of the file to save registry data to. This file cannot already exist. If this filename includes an extension, it cannot be used on file allocation table (FAT) file systems by the LoadKey(), ReplaceKey() or RestoreKey() methods.

If *key* represents a key on a remote computer, the path described by *file_name* is relative to the remote computer. The caller of this method must possess the SeBackupPrivilege security privilege. Note that privileges are different than permissions - see the Win32 documentation for more details.

This function passes NULL for security_attributes to the API.

SetValue(key, sub_key, type, value)

Associates a value with a specified key.

key is an already open key, or one of the predefined HKEY_* constants.

sub_key is a string that names the subkey with which the value is associated.

type is an integer that specifies the type of the data. Currently this must be REG_SZ, meaning only strings are supported. Use the SetValueEx() function for support for other data types.

value is a string that specifies the new value.

If the key specified by the *sub_key* parameter does not exist, the SetValue function creates it.

Value lengths are limited by available memory. Long values (more than 2048 bytes) should be stored as files with the filenames stored in the configuration registry. This helps the registry perform efficiently.

The key identified by the key parameter must have been opened with KEY_SET_VALUE access.

SetValueEx(key, value_name, reserved, type, value)

Stores data in the value field of an open registry key.

key is an already open key, or one of the predefined HKEY_* constants.

sub_key is a string that names the subkey with which the value is associated.

type is an integer that specifies the type of the data. This should be one of the following constants defined in this module:

Constant	Meaning
REG_BINARY	Binary data in any form.
REG_DWORD	A 32-bit number.
REG_DWORD_LITTLE_ENDIAN	A 32-bit number in little-endian format.
REG_DWORD_BIG_ENDIAN	A 32-bit number in big-endian format.
REG_EXPAND_SZ	Null-terminated string containing references to envi-
	ronment variables ('%PATH%').
REG_LINK	A Unicode symbolic link.
REG_MULTI_SZ	A sequence of null-terminated strings, terminated by
	two null characters. (Python handles this termination
	automatically.)
REG_NONE	No defined value type.
REG_RESOURCE_LIST	A device-driver resource list.
REG_SZ	A null-terminated string.

reserved can be anything - zero is always passed to the API.

value is a string that specifies the new value.

This method can also set additional value and type information for the specified key. The key identified by the key parameter must have been opened with KEY_SET_VALUE access.

To open the key, use the CreateKeyEx() or OpenKey() methods.

Value lengths are limited by available memory. Long values (more than 2048 bytes) should be stored as files with the filenames stored in the configuration registry. This helps the registry perform efficiently.

22.2.1 Registry Handle Objects

This object wraps a Windows HKEY object, automatically closing it when the object is destroyed. To guarantee cleanup, you can call either the Close() method on the object, or the CloseKey() function.

All registry functions in this module return one of these objects.

All registry functions in this module which accept a handle object also accept an integer, however, use of the handle object is encouraged.

Handle objects provide semantics for __nonzero__() - thus

```
if handle:
    print "Yes"
```

will print Yes if the handle is currently valid (has not been closed or detached).

The object also support comparison semantics, so handle objects will compare true if they both reference the same underlying Windows handle value.

Handle objects can be converted to an integer (eg, using the builtin int() function, in which case the underlying Windows handle value is returned. You can also use the Detach() method to return the integer handle, and also disconnect the Windows handle from the handle object.

Close()

Closes the underlying Windows handle.

If the handle is already closed, no error is raised.

Detach()

Detaches the Windows handle from the handle object.

The result is an integer (or long on 64 bit Windows) that holds the value of the handle before it is detached. If the handle is already detached or closed, this will return zero.

After calling this function, the handle is effectively invalidated, but the handle is not closed. You would call this function when you need the underlying Win32 handle to exist beyond the lifetime of the handle object.

22.3 winsound — Sound-playing interface for Windows

New in version 1.5.2.

The winsound module provides access to the basic sound-playing machinery provided by Windows platforms. It includes functions and several constants.

Beep(frequency, duration)

Beep the PC's speaker. The *frequency* parameter specifies frequency, in hertz, of the sound, and must be in the range 37 through 32,767. The *duration* parameter specifies the number of milliseconds the sound should last. If the system is not able to beep the speaker, RuntimeError is raised. **Note:** Under Windows 95 and 98, the Windows Beep() function exists but is useless (it ignores its arguments). In that case Python simulates it via direct port manipulation (added in version 2.1). It's unknown whether that will work on all systems. New in version 1.6.

PlaySound(sound, flags)

Call the underlying PlaySound() function from the Platform API. The *sound* parameter may be a filename, audio data as a string, or None. Its interpretation depends on the value of *flags*, which can be a bitwise ORed combination of the constants described below. If the system indicates an error, RuntimeError is raised.

$\texttt{MessageBeep}([type=MB_OK])$

Call the underlying MessageBeep() function from the Platform API. This plays a sound as specified in the registry. The *type* argument specifies which sound to play; possible values are -1, MB_ICONASTERISK, MB_ICONEXCLAMATION, MB_ICONHAND, MB_ICONQUESTION, and MB_OK, all described below. The value -1 produces a "simple beep"; this is the final fallback if a sound cannot be played otherwise. New in version 2.3.

SND_FILENAME

The *sound* parameter is the name of a WAV file. Do not use with SND_ALIAS.

SND ALIAS

The *sound* parameter is a sound association name from the registry. If the registry contains no such name, play the system default sound unless SND_NODEFAULT is also specified. If no default sound is registered, raise RuntimeError. Do not use with SND_FILENAME.

All Win32 systems support at least the following; most systems support many more:

PlaySound() name	Corresponding Control Panel Sound name
'SystemAsterisk'	Asterisk
'SystemExclamation'	Exclamation
'SystemExit'	Exit Windows
'SystemHand'	Critical Stop
'SystemQuestion'	Question

For example:

```
import winsound
# Play Windows exit sound.
winsound.PlaySound("SystemExit", winsound.SND_ALIAS)

# Probably play Windows default sound, if any is registered (because
# "*" probably isn't the registered name of any sound).
winsound.PlaySound("*", winsound.SND_ALIAS)
```

SND_LOOP

Play the sound repeatedly. The SND_ASYNC flag must also be used to avoid blocking. Cannot be used with SND_MEMORY.

SND_MEMORY

The sound parameter to PlaySound() is a memory image of a WAV file, as a string.

Note: This module does not support playing from a memory image asynchronously, so a combination of this flag and SND_ASYNC will raise RuntimeError.

SND_PURGE

Stop playing all instances of the specified sound.

SND_ASYNC

Return immediately, allowing sounds to play asynchronously.

SND_NODEFAULT

If the specified sound cannot be found, do not play the system default sound.

${\tt SND_NOSTOP}$

Do not interrupt sounds currently playing.

SND_NOWAIT

Return immediately if the sound driver is busy.

${\tt MB_ICONASTERISK}$

Play the SystemDefault sound.

MB_ICONEXCLAMATION

Play the SystemExclamation sound.

MB_ICONHAND

Play the SystemHand sound.

MB_ICONQUESTION

Play the SystemQuestion sound.

MB_OK

Play the SystemDefault sound.

Α

Undocumented Modules

Here's a quick listing of modules that are currently undocumented, but that should be documented. Feel free to contribute documentation for them! (Send via email to docs@python.org.)

The idea and original contents for this chapter were taken from a posting by Fredrik Lundh; the specific contents of this chapter have been substantially revised.

A.1 Frameworks

Frameworks tend to be harder to document, but are well worth the effort spent.

None at this time.

A.2 Miscellaneous useful utilities

Some of these are very old and/or not very robust; marked with "hmm."

bdb — A generic Python debugger base class (used by pdb).

ihooks — Import hook support (for rexec; may become obsolete).

A.3 Platform specific modules

These modules are used to implement the os.path module, and are not documented beyond this mention. There's little need to document these.

ntpath — Implementation of os.path on Win32, Win64, WinCE, and OS/2 platforms.

posixpath — Implementation of os.path on POSIX.

bsddb185 — Backwards compatibility module for systems which still use the Berkeley DB 1.85 module. It is normally only available on certain BSD Unix-based systems. It should never be used directly.

A.4 Multimedia

audiodev — Platform-independent API for playing audio data.

linuxaudiodev — Play audio data on the Linux audio device. Replaced in Python 2.3 by the ossaudiodev module.

sunaudio — Interpret Sun audio headers (may become obsolete or a tool/demo).

toaiff — Convert "arbitrary" sound files to AIFF files; should probably become a tool or demo. Requires the external program **sox**.

A.5 Obsolete

These modules are not normally available for import; additional work must be done to make them available.

Those which are written in Python will be installed into the directory 'lib-old' installed as part of the standard library. To use these, the directory must be added to sys.path, possibly using PYTHONPATH.

Obsolete extension modules written in C are not built by default. Under UNIX, these must be enabled by uncommenting the appropriate lines in 'Modules/Setup' in the build tree and either rebuilding Python if the modules are statically linked, or building and installing the shared object if using dynamically-loaded extensions.

addpack — Alternate approach to packages. Use the built-in package support instead.

cmp — File comparison function. Use the newer filecmp instead.

cmpcache — Caching version of the obsolete cmp module. Use the newer filecmp instead.

codehack — Extract function name or line number from a function code object (these are now accessible as attributes: co.co_name, func.func_name, co.co_firstlineno).

dircmp — Class to build directory diff tools on (may become a demo or tool). Deprecated since release 2.0.
The filecmp module replaces dircmp.

dump — Print python code that reconstructs a variable.

fmt — Text formatting abstractions (too slow).

lockfile — Wrapper around FCNTL file locking (use fcntl.lockf()/flock() instead; see fcntl).

newdir — New dir() function (the standard dir() is now just as good).

Para — Helper for fmt.

poly — Polynomials.

regex — Emacs-style regular expression support; may still be used in some old code (extension module). Refer to the *Python 1.6 Documentation* for documentation.

regsub — Regular expression based string replacement utilities, for use with regex (extension module). Refer to the *Python 1.6 Documentation* for documentation.

tb — Print tracebacks, with a dump of local variables (use pdb.pm() or traceback instead).

timing — Measure time intervals to high resolution (use time.clock() instead). (This is an extension module.)

tzparse — Parse a timezone specification (unfinished; may disappear in the future, and does not work when the TZ environment variable is not set).

util — Useful functions that don't fit elsewhere.

whatsound — Recognize sound files; use sndhdr instead.

zmod — Compute properties of mathematical "fields."

The following modules are obsolete, but are likely to re-surface as tools or scripts:

find — Find files matching pattern in directory tree.

grep — **grep** implementation in Python.

packmail — Create a self-unpacking UNIX shell archive.

The following modules were documented in previous versions of this manual, but are now considered obsolete. The source for the documentation is still available as part of the documentation source archive.

- **ni** Import modules in "packages." Basic package support is now built in. The built-in support is very similar to what is provided in this module.
- **rand** Old interface to the random number generator.
- **soundex** Algorithm for collapsing names which sound similar to a shared key. The specific algorithm doesn't seem to match any published algorithm. (This is an extension module.)

A.6 SGI-specific Extension modules

The following are SGI specific, and may be out of touch with the current version of reality.

- **c1** Interface to the SGI compression library.
- **sv** Interface to the "simple video" board on SGI Indigo (obsolete hardware).

В

Reporting Bugs

Python is a mature programming language which has established a reputation for stability. In order to maintain this reputation, the developers would like to know of any deficiencies you find in Python or its documentation.

Before submitting a report, you will be required to log into SourceForge; this will make it possible for the developers to contact you for additional information if needed. It is not possible to submit a bug report anonymously.

All bug reports should be submitted via the Python Bug Tracker on SourceForge (http://sourceforge.net/bugs/?group_id=5470). The bug tracker offers a Web form which allows pertinent information to be entered and submitted to the developers.

The first step in filing a report is to determine whether the problem has already been reported. The advantage in doing so, aside from saving the developers time, is that you learn what has been done to fix it; it may be that the problem has already been fixed for the next release, or additional information is needed (in which case you are welcome to provide it if you can!). To do this, search the bug database using the search box on the left side of the page.

If the problem you're reporting is not already in the bug tracker, go back to the Python Bug Tracker (http://sourceforge.net/bugs/?group_id=5470). Select the "Submit a Bug" link at the top of the page to open the bug reporting form.

The submission form has a number of fields. The only fields that are required are the "Summary" and "Details" fields. For the summary, enter a *very* short description of the problem; less than ten words is good. In the Details field, describe the problem in detail, including what you expected to happen and what did happen. Be sure to include the version of Python you used, whether any extension modules were involved, and what hardware and software platform you were using (including version information as appropriate).

The only other field that you may want to set is the "Category" field, which allows you to place the bug report into a broad category (such as "Documentation" or "Library").

Each bug report will be assigned to a developer who will determine what needs to be done to correct the problem. You will receive an update each time action is taken on the bug.

See Also:

How to Report Bugs Effectively

(http://www-mice.cs.ucl.ac.uk/multimedia/software/documentation/ReportingBugs.html)

Article which goes into some detail about how to create a useful bug report. This describes what kind of information is useful and why it is useful.

Bug Writing Guidelines

(http://www.mozilla.org/quality/bug-writing-guidelines.html)

Information about writing a good bug report. Some of this is specific to the Mozilla project, but describes general good practices.

C

History and License

C.1 History of the software

Python was created in the early 1990s by Guido van Rossum at Stichting Mathematisch Centrum (CWI, see http://www.cwi.nl/) in the Netherlands as a successor of a language called ABC. Guido remains Python's principal author, although it includes many contributions from others.

In 1995, Guido continued his work on Python at the Corporation for National Research Initiatives (CNRI, see http://www.cnri.reston.va.us/) in Reston, Virginia where he released several versions of the software.

In May 2000, Guido and the Python core development team moved to BeOpen.com to form the BeOpen Python-Labs team. In October of the same year, the PythonLabs team moved to Digital Creations (now Zope Corporation; see http://www.zope.com/). In 2001, the Python Software Foundation (PSF, see http://www.python.org/psf/) was formed, a non-profit organization created specifically to own Python-related Intellectual Property. Zope Corporation is a sponsoring member of the PSF.

All Python releases are Open Source (see http://www.opensource.org/ for the Open Source Definition). Historically, most, but not all, Python releases have also been GPL-compatible; the table below summarizes the various releases.

Release	Derived from	Year	Owner	GPL compatible?
0.9.0 thru 1.2	n/a	1991-1995	CWI	yes
1.3 thru 1.5.2	1.2	1995-1999	CNRI	yes
1.6	1.5.2	2000	CNRI	no
2.0	1.6	2000	BeOpen.com	no
1.6.1	1.6	2001	CNRI	no
2.1	2.0+1.6.1	2001	PSF	no
2.0.1	2.0+1.6.1	2001	PSF	yes
2.1.1	2.1+2.0.1	2001	PSF	yes
2.2	2.1.1	2001	PSF	yes
2.1.2	2.1.1	2002	PSF	yes
2.1.3	2.1.2	2002	PSF	yes
2.2.1	2.2	2002	PSF	yes
2.2.2	2.2.1	2002	PSF	yes
2.2.3	2.2.2	2002-2003	PSF	yes
2.3	2.2.2	2002-2003	PSF	yes
2.3.1	2.3	2002-2003	PSF	yes
2.3.2	2.3.1	2003	PSF	yes
2.3.3	2.3.2	2003	PSF	yes
2.3.4	2.3.3	2004	PSF	yes
2.3.5	2.3.4	2005	PSF	yes
2.4	2.3	2004	PSF	yes
2.4.1	2.4	2005	PSF	yes
2.4.2	2.4.1	2005	PSF	yes

Note: GPL-compatible doesn't mean that we're distributing Python under the GPL. All Python licenses, unlike

the GPL, let you distribute a modified version without making your changes open source. The GPL-compatible licenses make it possible to combine Python with other software that is released under the GPL; the others don't.

Thanks to the many outside volunteers who have worked under Guido's direction to make these releases possible.

C.2 Terms and conditions for accessing or otherwise using Python

PSF LICENSE AGREEMENT FOR PYTHON 2.4.2

- 1. This LICENSE AGREEMENT is between the Python Software Foundation ("PSF"), and the Individual or Organization ("Licensee") accessing and otherwise using Python 2.4.2 software in source or binary form and its associated documentation.
- 2. Subject to the terms and conditions of this License Agreement, PSF hereby grants Licensee a nonexclusive, royalty-free, world-wide license to reproduce, analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use Python 2.4.2 alone or in any derivative version, provided, however, that PSF's License Agreement and PSF's notice of copyright, i.e., "Copyright © 2001-2004 Python Software Foundation; All Rights Reserved" are retained in Python 2.4.2 alone or in any derivative version prepared by Licensee.
- 3. In the event Licensee prepares a derivative work that is based on or incorporates Python 2.4.2 or any part thereof, and wants to make the derivative work available to others as provided herein, then Licensee hereby agrees to include in any such work a brief summary of the changes made to Python 2.4.2.
- 4. PSF is making Python 2.4.2 available to Licensee on an "AS IS" basis. PSF MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF EXAMPLE, BUT NOT LIMITATION, PSF MAKES NO AND DISCLAIMS ANY REPRESENTATION OR WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE USE OF PYTHON 2.4.2 WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.
- 5. PSF SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF PYTHON 2.4.2 FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF MODIFYING, DISTRIBUTING, OR OTHERWISE USING PYTHON 2.4.2, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
- 6. This License Agreement will automatically terminate upon a material breach of its terms and conditions.
- 7. Nothing in this License Agreement shall be deemed to create any relationship of agency, partnership, or joint venture between PSF and Licensee. This License Agreement does not grant permission to use PSF trademarks or trade name in a trademark sense to endorse or promote products or services of Licensee, or any third party.
- 8. By copying, installing or otherwise using Python 2.4.2, Licensee agrees to be bound by the terms and conditions of this License Agreement.

BEOPEN.COM LICENSE AGREEMENT FOR PYTHON 2.0 BEOPEN PYTHON OPEN SOURCE LICENSE AGREEMENT VERSION 1

- 1. This LICENSE AGREEMENT is between BeOpen.com ("BeOpen"), having an office at 160 Saratoga Avenue, Santa Clara, CA 95051, and the Individual or Organization ("Licensee") accessing and otherwise using this software in source or binary form and its associated documentation ("the Software").
- 2. Subject to the terms and conditions of this BeOpen Python License Agreement, BeOpen hereby grants Licensee a non-exclusive, royalty-free, world-wide license to reproduce, analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use the Software alone or in any derivative version, provided, however, that the BeOpen Python License is retained in the Software, alone or in any derivative version prepared by Licensee.
- 3. BeOpen is making the Software available to Licensee on an "AS IS" basis. BEOPEN MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF EXAMPLE, BUT NOT LIMITATION, BEOPEN MAKES NO AND DISCLAIMS ANY REPRESENTATION OR WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE USE OF THE SOFTWARE WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.

- 4. BEOPEN SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF THE SOFTWARE FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF USING, MODIFYING OR DISTRIBUTING THE SOFTWARE, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
- 5. This License Agreement will automatically terminate upon a material breach of its terms and conditions.
- 6. This License Agreement shall be governed by and interpreted in all respects by the law of the State of California, excluding conflict of law provisions. Nothing in this License Agreement shall be deemed to create any relationship of agency, partnership, or joint venture between BeOpen and Licensee. This License Agreement does not grant permission to use BeOpen trademarks or trade names in a trademark sense to endorse or promote products or services of Licensee, or any third party. As an exception, the "BeOpen Python" logos available at http://www.pythonlabs.com/logos.html may be used according to the permissions granted on that web page.
- 7. By copying, installing or otherwise using the software, Licensee agrees to be bound by the terms and conditions of this License Agreement.

CNRI LICENSE AGREEMENT FOR PYTHON 1.6.1

- 1. This LICENSE AGREEMENT is between the Corporation for National Research Initiatives, having an office at 1895 Preston White Drive, Reston, VA 20191 ("CNRI"), and the Individual or Organization ("Licensee") accessing and otherwise using Python 1.6.1 software in source or binary form and its associated documentation.
- 2. Subject to the terms and conditions of this License Agreement, CNRI hereby grants Licensee a nonexclusive, royalty-free, world-wide license to reproduce, analyze, test, perform and/or display publicly, prepare derivative works, distribute, and otherwise use Python 1.6.1 alone or in any derivative version, provided, however, that CNRI's License Agreement and CNRI's notice of copyright, i.e., "Copyright © 1995-2001 Corporation for National Research Initiatives; All Rights Reserved" are retained in Python 1.6.1 alone or in any derivative version prepared by Licensee. Alternately, in lieu of CNRI's License Agreement, Licensee may substitute the following text (omitting the quotes): "Python 1.6.1 is made available subject to the terms and conditions in CNRI's License Agreement. This Agreement together with Python 1.6.1 may be located on the Internet using the following unique, persistent identifier (known as a handle): 1895.22/1013. This Agreement may also be obtained from a proxy server on the Internet using the following URL: http://hdl.handle.net/1895.22/1013."
- 3. In the event Licensee prepares a derivative work that is based on or incorporates Python 1.6.1 or any part thereof, and wants to make the derivative work available to others as provided herein, then Licensee hereby agrees to include in any such work a brief summary of the changes made to Python 1.6.1.
- 4. CNRI is making Python 1.6.1 available to Licensee on an "AS IS" basis. CNRI MAKES NO REPRESENTATIONS OR WARRANTIES, EXPRESS OR IMPLIED. BY WAY OF EXAMPLE, BUT NOT LIMITATION, CNRI MAKES NO AND DISCLAIMS ANY REPRESENTATION OR WARRANTY OF MERCHANTABILITY OR FITNESS FOR ANY PARTICULAR PURPOSE OR THAT THE USE OF PYTHON 1.6.1 WILL NOT INFRINGE ANY THIRD PARTY RIGHTS.
- 5. CNRI SHALL NOT BE LIABLE TO LICENSEE OR ANY OTHER USERS OF PYTHON 1.6.1 FOR ANY INCIDENTAL, SPECIAL, OR CONSEQUENTIAL DAMAGES OR LOSS AS A RESULT OF MODIFYING, DISTRIBUTING, OR OTHERWISE USING PYTHON 1.6.1, OR ANY DERIVATIVE THEREOF, EVEN IF ADVISED OF THE POSSIBILITY THEREOF.
- 6. This License Agreement will automatically terminate upon a material breach of its terms and conditions.
- 7. This License Agreement shall be governed by the federal intellectual property law of the United States, including without limitation the federal copyright law, and, to the extent such U.S. federal law does not apply, by the law of the Commonwealth of Virginia, excluding Virginia's conflict of law provisions. Notwithstanding the foregoing, with regard to derivative works based on Python 1.6.1 that incorporate non-separable material that was previously distributed under the GNU General Public License (GPL), the law of the Commonwealth of Virginia shall govern this License Agreement only as to issues arising under or with respect to Paragraphs 4, 5, and 7 of this License Agreement. Nothing in this License Agreement shall be deemed to

create any relationship of agency, partnership, or joint venture between CNRI and Licensee. This License Agreement does not grant permission to use CNRI trademarks or trade name in a trademark sense to endorse or promote products or services of Licensee, or any third party.

8. By clicking on the "ACCEPT" button where indicated, or by copying, installing or otherwise using Python 1.6.1, Licensee agrees to be bound by the terms and conditions of this License Agreement.

ACCEPT CWI LICENSE AGREEMENT FOR PYTHON 0.9.0 THROUGH 1.2

Copyright © 1991 - 1995, Stichting Mathematisch Centrum Amsterdam, The Netherlands. All rights reserved.

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Stichting Mathematisch Centrum or CWI not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

STICHTING MATHEMATISCH CENTRUM DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL STICHTING MATHEMATISCH CENTRUM BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

C.3 Licenses and Acknowledgements for Incorporated Software

This section is an incomplete, but growing list of licenses and acknowledgements for third-party software incorporated in the Python distribution.

C.3.1 Mersenne Twister

The _random module includes code based on a download from http://www.math.keio.ac.jp/ matu-moto/MT2002/emt19937ar.html. The following are the verbatim comments from the original code:

A C-program for MT19937, with initialization improved 2002/1/26. Coded by Takuji Nishimura and Makoto Matsumoto.

Before using, initialize the state by using init_genrand(seed) or init_by_array(init_key, key_length).

Copyright (C) 1997 - 2002, Makoto Matsumoto and Takuji Nishimura, All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3. The names of its contributors may not be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS
"AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT
LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR
A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR
CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL,
EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO,
PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR
PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF
LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING
NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS
SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Any feedback is very welcome. http://www.math.keio.ac.jp/matumoto/emt.html email: matumoto@math.keio.ac.jp

C.3.2 Sockets

The socket module uses the functions, getaddrinfo, and getnameinfo, which are coded in separate source files from the WIDE Project, http://www.wide.ad.jp/about/index.html.

Copyright (C) 1995, 1996, 1997, and 1998 WIDE Project. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.
- 3. Neither the name of the project nor the names of its contributors may be used to endorse or promote products derived from this software without specific prior written permission.

THIS SOFTWARE IS PROVIDED BY THE PROJECT AND CONTRIBUTORS 'AS IS' AND GAI_ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE PROJECT OR CONTRIBUTORS BE LIABLE FOR GAI_ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON GAI_ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN GAI_ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

C.3.3 Floating point exception control

The source for the fpectl module includes the following notice:

Copyright (c) 1996.

The Regents of the University of California.

All rights reserved.

Permission to use, copy, modify, and distribute this software for any purpose without fee is hereby granted, provided that this entire notice is included in all copies of any software which is or includes a copy or modification of this software and in all copies of the supporting documentation for such software.

This work was produced at the University of California, Lawrence Livermore National Laboratory under contract no. W-7405-ENG-48 between the U.S. Department of Energy and The Regents of the University of California for the operation of UC LLNL.

DISCLAIMER

This software was prepared as an account of work sponsored by an agency of the United States Government. Neither the United States Government nor the University of California nor any of their employees, makes any warranty, express or implied, or assumes any liability or responsibility for the accuracy, completeness, or usefulness of any information, apparatus, product, or process disclosed, or represents that its use would not infringe privately-owned rights. Reference herein to any specific commercial products, process, or service by trade name, trademark, manufacturer, or otherwise, does not necessarily constitute or imply its endorsement, recommendation, or favoring by the United States Government or the University of California. The views and opinions of authors expressed herein do not necessarily state or reflect those of the United States Government or the University of California, and shall not be used for advertising or product endorsement purposes.

.3.4 MD5 message digest algorithm

The source code for the md5 module contains the following notice:

Copyright (C) 1991-2, RSA Data Security, Inc. Created 1991. All rights reserved.

License to copy and use this software is granted provided that it is identified as the "RSA Data Security, Inc. MD5 Message-Digest Algorithm" in all material mentioning or referencing this software or this function.

License is also granted to make and use derivative works provided that such works are identified as "derived from the RSA Data Security, Inc. MD5 Message-Digest Algorithm" in all material mentioning or referencing the derived work.

RSA Data Security, Inc. makes no representations concerning either the merchantability of this software or the suitability of this software for any particular purpose. It is provided "as is" without express or implied warranty of any kind.

These notices must be retained in any copies of any part of this documentation and/or software.

C.3.5 Asynchronous socket services

The asynchat and asyncore modules contain the following notice:

Copyright 1996 by Sam Rushing

All Rights Reserved

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Sam Rushing not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

SAM RUSHING DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL SAM RUSHING BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

C.3.6 Cookie management

The Cookie module contains the following notice:

Copyright 2000 by Timothy O'Malley <timo@alum.mit.edu>

All Rights Reserved

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Timothy O'Malley not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

Timothy O'Malley DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL Timothy O'Malley BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

C.3.7 Profiling

The profile and pstats modules contain the following notice:

Copyright 1994, by InfoSeek Corporation, all rights reserved. Written by James Roskind

Permission to use, copy, modify, and distribute this Python software and its associated documentation for any purpose (subject to the restriction in the following sentence) without fee is hereby granted, provided that the above copyright notice appears in all copies, and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of InfoSeek not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission. This permission is explicitly restricted to the copying and modification of the software to remain in Python, compiled Python, or other languages (such as C) wherein the modified or derived code is exclusively imported into a Python module.

INFOSEEK CORPORATION DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS. IN NO EVENT SHALL INFOSEEK CORPORATION BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

C.3.8 Execution tracing

The trace module contains the following notice:

portions copyright 2001, Autonomous Zones Industries, Inc., all rights... err... reserved and offered to the public under the terms of the

Python 2.2 license.

Author: Zooko O'Whielacronx

http://zooko.com/ mailto:zooko@zooko.com

Copyright 2000, Mojam Media, Inc., all rights reserved.

Author: Skip Montanaro

Copyright 1999, Bioreason, Inc., all rights reserved.

Author: Andrew Dalke

Copyright 1995-1997, Automatrix, Inc., all rights reserved.

Author: Skip Montanaro

Copyright 1991-1995, Stichting Mathematisch Centrum, all rights reserved.

Permission to use, copy, modify, and distribute this Python software and its associated documentation for any purpose without fee is hereby granted, provided that the above copyright notice appears in all copies, and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of neither Automatrix, Bioreason or Mojam Media be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

C.3.9 UUencode and UUdecode functions

The uu module contains the following notice:

Copyright 1994 by Lance Ellinghouse Cathedral City, California Republic, United States of America. All Rights Reserved

Permission to use, copy, modify, and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Lance Ellinghouse not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

LANCE ELLINGHOUSE DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS, IN NO EVENT SHALL LANCE ELLINGHOUSE CENTRUM BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

Modified by Jack Jansen, CWI, July 1995:

- Use binascii module to do the actual line-by-line conversion between ascii and binary. This results in a 1000-fold speedup. The C version is still 5 times faster, though.
- Arguments more compliant with python standard

C.3.10 XML Remote Procedure Calls

The xmlrpclib module contains the following notice:

The XML-RPC client interface is

Copyright (c) 1999-2002 by Secret Labs AB Copyright (c) 1999-2002 by Fredrik Lundh

By obtaining, using, and/or copying this software and/or its associated documentation, you agree that you have read, understood, and will comply with the following terms and conditions:

Permission to use, copy, modify, and distribute this software and its associated documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appears in all copies, and that both that copyright notice and this permission notice appear in supporting documentation, and that the name of Secret Labs AB or the author not be used in advertising or publicity pertaining to distribution of the software without specific, written prior permission.

SECRET LABS AB AND THE AUTHOR DISCLAIMS ALL WARRANTIES WITH REGARD TO THIS SOFTWARE, INCLUDING ALL IMPLIED WARRANTIES OF MERCHANT-ABILITY AND FITNESS. IN NO EVENT SHALL SECRET LABS AB OR THE AUTHOR BE LIABLE FOR ANY SPECIAL, INDIRECT OR CONSEQUENTIAL DAMAGES OR ANY DAMAGES WHATSOEVER RESULTING FROM LOSS OF USE, DATA OR PROFITS, WHETHER IN AN ACTION OF CONTRACT, NEGLIGENCE OR OTHER TORTIOUS ACTION, ARISING OUT OF OR IN CONNECTION WITH THE USE OR PERFORMANCE OF THIS SOFTWARE.

MODULE INDEX

compiler.visitor,728

ConfigParser, 226 __builtin__, 102 Cookie, 532 __future__, 103 cookielib, 524 __main__, 103 сору, 84 _winreg,750 copy_reg,81 Α cPickle, 81 crypt, 433 aifc, 655 cStringIO, 131 AL, 733 csv, 604 al, 731 curses, 293 anydbm, 409 curses.ascii, 309 array, 212 curses.panel,311 asynchat, 545 curses.textpad, 307 asyncore, 542 curses.wrapper, 308 atexit,55 audioop, 651 D В datetime, 270 dbhash, 409 base64.595 dbm, 435 BaseHTTPServer, 521 decimal. 183 Bastion, 698 DEVICE, 744 binascii, 596 difflib, 122 binhex, 598 dircache, 258 bisect, 206 dis, 714 bsddb, 410 distutils, 722 bz2,416 d1,434 C doctest, 146 DocXMLRPCServer, 541 calendar, 230 dumbdbm, 413 cd, 733 dummy_thread, 405 cgi, 471 ${\tt dummy_threading}, 406$ CGIHTTPServer, 524 cgitb, 478 Ε chunk, 661 email, 553 cmath, 201 email.Charset,566 cmd, 231 email. Encoders, 568 code, 94 email.Errors, 569 codecs, 133 email.Generator,561 codeop, 95 email.Header, 564 collections, 206 email.Iterators, 572 colorsys, 662 email.Message, 553 commands, 447 email.Parser,559 compileall, 714 email.Utils,570 compiler, 723 encodings.idna, 141 compiler.ast, 724 errno, 340

Symbols

exceptions, 33	M
F	mailbox, 580
	mailcap,579
fcnt1, 439	marshal,85
filecmp, 261	math, 199
fileinput, 229	md5,669
FL, 741	mhlib, 582
f1,736	mimetools, 584
flp, 741	mimetypes, 585
fm, 741 fnmatch, 346	MimeWriter, 587
formatter, 549	mimify, 588
fpectl, 54	mmap,407 modulefinder,93
fpformat, 130	msvcrt,749
ftplib,496	multifile, 589
_	mutex, 292
G	N
gc, 47	
gdbm, 436	netrc, 602
getopt, 312	new, 100
getpass, 293	nis,446
gettext, 353 GL, 744	nntplib, 506
gl, 744 gl, 742	O
glob, 346	
gopherlib, 499	operator, 60
grp, 433	optparse, 314 os, 237
gzip, 415	os.path, 255
	ossaudiodev, 664
Н	
heapq, 210	Р
hmac, 669	parser, 701
hotshot, 462	pdb, 449
hotshot.stats, 463	pickle,72
htmlentitydefs, 615	pickletools,721
htmllib, 613	pipes, 441
HTMLParser, 609	pkgutil,93
httplib,492	platform, 382
I	popen2, 268
·	poplib, 499
imageop,654 imaplib,501	posix, 431
imgfile,744	posixfile,442 pprint,97
imghdr, 663	pprint, 97 profile, 458
imp, 89	profife, 456 pstats, 459
inspect, 64	pty, 438
itertools, 217	pwd, 432
	py_compile,713
J	pyclbr, 712
jpeg,745	pydoc, 145
K	Q
keyword,711	Queue, 406
L	quopri,598
	R
linecache,71	• •
locale, 348	random, 202 re. 110
+UMM+11M, JUZ	

776 Module Index

readline, 426	token, 710
repr, 99	tokenize,711
resource, 443	traceback,69
rexec, 695	tty, 438
rfc822,591	turtle,689
rgbimg, 663	types, 56
rlcompleter, 428	
robotparser, 603	U
	unicodedata, 142
S	unittest, 170
sched, 291	urllib, 478
ScrolledText, 689	urllib2,483
select, 396	urlparse, 516
sets, 214	user, 102
sgmllib, 611	UserDict, 58
sha, 670	UserList, 59
shelve, 82	UserString, 59
shlex, 233	uu, 599
shutil, 347	
signal, 385	W
SimpleHTTPServer, 523	warnings, 86
SimpleXMLRPCServer, 539	wave, 659
site, 101	weakref, 49
smtpd, 513	webbrowser, 469
smtplib, 510	whichdb, 410
sndhdr, 664	whrandom, 205
	winsound, 754
socket, 387	willsoulid, 734
SocketServer, 518	X
a+a+ 250	\wedge
stat, 258	
statcache, 260	xdrlib,600
statcache, 260 statvfs, 261	xdrlib,600 xml.dom,623
statcache, 260 statvfs, 261 string, 105	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633
statcache, 260 statvfs, 261 string, 105 StringIO, 131	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143	xdrlib,600 xml.dom,623 xml.dom.minidom,633 xml.dom.pulldom,637 xml.parsers.expat,615
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710 sys, 41	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536 Z
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710 sys, 41 syslog, 446	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536 Z zipfile, 418
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710 sys, 41 syslog, 446 T	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536 Z zipfile, 418 zipimport, 91
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710 sys, 41 syslog, 446 T tabnanny, 712	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536 Z zipfile, 418
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710 sys, 41 syslog, 446 T tabnanny, 712 tarfile, 421	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536 Z zipfile, 418 zipimport, 91
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710 sys, 41 syslog, 446 T tabnanny, 712 tarfile, 421 telnetlib, 514	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536 Z zipfile, 418 zipimport, 91
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710 sys, 41 syslog, 446 T tabnanny, 712 tarfile, 421 telnetlib, 514 tempfile, 338	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536 Z zipfile, 418 zipimport, 91
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710 sys, 41 syslog, 446 T tabnanny, 712 tarfile, 421 telnetlib, 514 tempfile, 338 termios, 437	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536 Z zipfile, 418 zipimport, 91
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710 sys, 41 syslog, 446 T tabnanny, 712 tarfile, 421 telnetlib, 514 tempfile, 338 termios, 437 test, 180	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536 Z zipfile, 418 zipimport, 91
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710 sys, 41 syslog, 446 T tabnanny, 712 tarfile, 421 telnetlib, 514 tempfile, 338 termios, 437 test, 180 test.test_support, 182	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536 Z zipfile, 418 zipimport, 91
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710 sys, 41 syslog, 446 T tabnanny, 712 tarfile, 421 telnetlib, 514 tempfile, 338 termios, 437 test, 180 test.test_support, 182 textwrap, 131	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536 Z zipfile, 418 zipimport, 91
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710 sys, 41 syslog, 446 T tabnanny, 712 tarfile, 421 telnetlib, 514 tempfile, 338 termios, 437 test, 180 test.test_support, 182 textwrap, 131 thread, 397	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536 Z zipfile, 418 zipimport, 91
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710 sys, 41 syslog, 446 T tabnanny, 712 tarfile, 421 telnetlib, 514 tempfile, 338 termios, 437 test, 180 test.test_support, 182 textwrap, 131 thread, 397 threading, 398	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536 Z zipfile, 418 zipimport, 91
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710 sys, 41 syslog, 446 T tabnanny, 712 tarfile, 421 telnetlib, 514 tempfile, 338 termios, 437 test, 180 test.test_support, 182 textwrap, 131 thread, 397 threading, 398 time, 286	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536 Z zipfile, 418 zipimport, 91
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710 sys, 41 syslog, 446 T tabnanny, 712 tarfile, 421 telnetlib, 514 tempfile, 338 termios, 437 test, 180 test.test_support, 182 textwrap, 131 thread, 397 threading, 398 time, 286 timeit, 464	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536 Z zipfile, 418 zipimport, 91
statcache, 260 statvfs, 261 string, 105 StringIO, 131 stringprep, 143 struct, 120 subprocess, 263 sunau, 657 SUNAUDIODEV, 748 sunaudiodev, 747 symbol, 710 sys, 41 syslog, 446 T tabnanny, 712 tarfile, 421 telnetlib, 514 tempfile, 338 termios, 437 test, 180 test.test_support, 182 textwrap, 131 thread, 397 threading, 398 time, 286	xdrlib, 600 xml.dom, 623 xml.dom.minidom, 633 xml.dom.pulldom, 637 xml.parsers.expat, 615 xml.sax, 638 xml.sax.handler, 639 xml.sax.saxutils, 643 xml.sax.xmlreader, 644 xmllib, 648 xmlrpclib, 536 Z zipfile, 418 zipimport, 91

Module Index 777

INDEX

Symbols	iadd() (AddressList method), 594
.ini	import() (in module), 3
file, 226	init() (NullTranslations method), 356
.pdbrc	init() (method), 372
file, 451	init() (in module difflib), 123
.pythonrc.py	init() (instance constructor), 76
file, 102	inv() (in module operator), 61
;protocol;_proxy, 484	invert() (in module operator), 61
==	isub() (AddressList method), 594
operator, 16	iter() (container method), 18
abs() (in module operator), 61	iter() (iterator method), 18
add() (AddressList method), 594	le() (in module operator), 60
add() (in module operator), 61	len() (AddressList method), 594
and() (in module operator), 61	len() (Message method), 555
bases (class attribute), 33	lshift() (in module operator), 61
builtin (built-in module), 102	lt() (in module operator), 60
call() (Generator method), 563	main (built-in module), 103
class (instance attribute), 33	members (object attribute), 33
cmp() (instance method), 16	methods (object attribute), 33
concat() (in module operator), 62	mod() (in module operator), 61
contains() (Message method), 555	mul() (in module operator), 61
contains() (in module operator), 62	name (class attribute), 33
copy() (copy protocol), 85	ne() (Header method), 566, 568
deepcopy() (copy protocol), 85	ne() (in module operator), 60
delitem() (Message method), 555	neg() (in module operator), 61
delitem() (in module operator), 62	not() (in module operator), 60
delslice() (in module operator), 62	or() (in module operator), 61
dict (instance attribute), 76	pos() (in module operator), 61
dict (object attribute), 33	pow() (in module operator), 61
displayhook (data in sys), 42	repeat() (in module operator), 62
div() (in module operator), 61	repr() (netrc method), 603
eq() (Charset method), 568	rshift() (in module operator), 61
eq() (Header method), 566	setitem() (Message method), 555
eq() (in module operator), 60	setitem() (in module operator), 62
excepthook (data in sys), 42	setslice() (in module operator), 62
floordiv() (in module operator), 61	setstate() (copy protocol), 76
future (standard module), 103	stderr (data in sys), 46
ge() (in module operator), 60	stdin (data in sys), 46
getinitargs() (copy protocol), 76	stdout (data in sys), 46
getitem() (Message method), 555	str() (AddressList method), 594
getitem() (in module operator), 62	str() (Charset method), 568
getnewargs() (copy protocol), 76	str() (Header method), 566
getslice() (in module operator), 62	str() (Message method), 554
getstate() (copy protocol), 76	str() (date method), 274
gt() (in module operator), 60	str() (datetime method), 279
	str() (time method), 280

sub() (AddressList method), 594	activeCount() (in module threading), 398
sub() (in module operator), 61	add()
truediv() (in module operator), 62	Context method, 191
unicode() (Header method), 566	in module audioop, 651
xor() (in module operator), 62	in module operator, 61
_exit() (in module os), 249	Stats method, 459
_getframe() (in module sys), 44	TarFile method, 423
_locale (built-in module), 348	add_alias() (in module email.Charset), 568
_parse() (NullTranslations method), 356	add_box() (form method), 738
_structure() (in module email.Iterators), 572	add_browser() (form method), 739
_urlopener (data in urllib), 480	add_button() (form method), 739
_winreg (extension module), 750	add_charset() (in module email.Charset), 568
% formatting, 23	add_choice() (form method), 739
% interpolation, 23	add_clock() (form method), 738
•	add_codec() (in module email.Charset), 568
A	<pre>add_cookie_header() (CookieJar method),</pre>
A-LAW, 656, 664	526
a2b_base64() (in module binascii), 596	add_counter() (form method), 739
a2b_hex() (in module binascii), 597	add_data() (Request method), 485
a2b_hqx() (in module binascii), 597	add_dial() (form method), 739
a2b_qp() (in module binascii), 596	<pre>add_fallback() (NullTranslations method),</pre>
a2b_uu() (in module binascii), 596	356
ABDAY_1 ABDAY_7 (data in locale), 351	add_flowing_data() (formatter method), 550
ABMON_1 ABMON_12 (data in locale), 351	add_handler() (OpenerDirector method), 486
abort()	add_header()
FTP method, 497	Message method, 556
in module os, 249	Request method, 486
above() (method), 311	add_history() (in module readline), 427
abs()	add_hor_rule() (formatter method), 550
Context method, 191	add_input() (form method), 739
in module, 4	add_label_data() (formatter method), 550
in module operator, 61	add_lightbutton() (form method), 739
abspath() (in module os.path), 255	add_line_break() (formatter method), 550
AbstractBasicAuthHandler (class in url-	add_literal_data() (formatter method), 550
lib2), 485	add_menu() (form method), 739
AbstractDigestAuthHandler (class in url-	add_parent() (BaseHandler method), 487
lib2), 485	add_password() (HTTPPasswordMgr method),
AbstractFormatter (class in formatter), 551	489
AbstractWriter (class in formatter), 552	add_positioner() (form method), 739
ac_in_buffer_size (data in asyncore), 543	add_roundbutton() (form method), 739
ac_out_buffer_size (data in asyncore), 543	add_section() (SafeConfigParser method), 227
accept()	<pre>add_slider() (form method), 739 add_text() (form method), 738</pre>
dispatcher method, 544	add_text() (form method), 738 add_timer() (form method), 739
socket method, 392	· · · · · · · · · · · · · · · · · · ·
accept 2dyear (data in time), 287	add_type() (in module mimetypes), 586
access() (in module os), 243	add_unredirected_header() (Request method), 486
acos()	add_valslider() (form method), 739
in module cmath, 201	addcallback() (CD parser method), 736
in module math, 200	addch() (window method), 299
acosh() (in module cmath), 201	addError() (TestResult method), 179
acquire()	addFailure() (TestResult method), 179
method, 372	addfile() (TarFile method), 423
Condition method, 401	addFilter() (method), 366, 372
lock method, 398 Semaphore method, 402	addHandler() (method), 366
Timer method, 400	addheader() (MimeWriter method), 587
acquire_lock() (in module imp), 90	addinfo() (Profile method), 463
activate_form() (form method), 738	addLevelName() (in module logging), 364

780 Index

addnstr() (window method), 299	appendChild() (Node method), 627
AddPackagePath() (in module modulefinder),	appendleft() (method), 207
93	apply() (in module), 14
address_family (data in SocketServer), 519	architecture() (in module platform), 382
address_string() (BaseHTTPRequestHand- ler method), 523	aRepr (data in repr), 99
<i>"</i>	argy (data in sys), 41
AddressList (class in rfc822), 592	arithmetic, 17
addresslist (AddressList attribute), 594	ArithmeticError (exception in exceptions), 34
addstr() (window method), 299	array() (in module array), 212
addSuccess() (TestResult method), 179	array (built-in module), 212
addTest() (TestSuite method), 178	arrays, 212
addTests() (TestSuite method), 178	ArrayType (data in array), 212
adjusted() (Decimal method), 188	article() (NNTPDataError method), 509
adler32() (in module zlib), 414	AS_IS (data in formatter), 550
ADPCM, Intel/DVI, 651	as_string() (Message method), 554
adpcm2lin() (in module audioop), 651	as_tuple() (Decimal method), 188
adpcm32lin() (in module audioop), 651	ascii() (in module curses.ascii), 310
AF_INET (data in socket), 388	ascii_letters (data in string), 105
AF_INET6 (data in socket), 388	ascii_lowercase (data in string), 105
AF_UNIX (data in socket), 388	ascii_uppercase (data in string), 105
AI_* (data in socket), 389	asctime() (in module time), 287
aifc() (aifc method), 656	asin()
aifc (standard module), 655	in module cmath, 201
AIFF, 655, 661	in module math, 200
aiff() (aifc method), 656	asinh() (in module cmath), 201
AIFF-C, 655, 661	assert
AL (standard module), 731, 733	statement, 34
al (built-in module), 731	assert_() (TestCase method), 177
alarm() (in module signal), 386	assert_line_data() (formatter method), 551
all_errors (data in ftplib), 497	assertAlmostEqual() (TestCase method)
all_features (data in xml.sax.handler), 640	177
all_properties (data in xml.sax.handler), 640	assertEqual() (TestCase method), 177
allocate_lock() (in module thread), 397	AssertionError (exception in exceptions), 34
allow_reuse_address (data in SocketServer),	assertNotAlmostEqual() (TestCase
519	method), 177
allowed_domains() (DefaultCookiePolicy	assertNotEqual() (TestCase method), 177
method), 529	assertRaises() (TestCase method), 177
allowremoval() (CD player method), 734	assignment
alt() (in module curses.ascii), 310	extended slice, 25
ALT_DIGITS (data in locale), 352	slice, 25
altsep (data in os), 254	subscript, 25
altzone (data in time), 287	ast2list() (in module parser), 703
anchor_bgn() (HTML Parser method), 614	ast2tuple() (in module parser), 703
anchor_end() (HTMLParser method), 615	astimezone() (datetime method), 277
and	ASTType (data in parser), 704
operator, 15, 16	ASTVisitor (class in compiler visitor), 729
and_() (in module operator), 61	async_chat (class in asynchat), 545
annotate() (in module direache), 258	asynchat (standard module), 545
anydbm (standard module), 409	asyncore (built-in module), 542
api_version (data in sys), 47	atan()
apop() (POP3_SSL method), 500	in module cmath, 201
append()	in module math, 200
method, 207	atan2() (in module math), 200
array method, 213	atanh() (in module cmath), 201
Header method, 565	atexit (standard module), 55
IMAP4_stream method, 503	atime (data in cd), 734
list method, 25	atof()
Template method, 441	in module locale, 350

Index 781

in module string, 108	b2a_hex() (in module binascii), 597
atoi()	b2a_hqx() (in module binascii), 597
in module locale, 350	b2a_qp() (in module binascii), 597
in module string, 108	b2a_uu() (in module binascii), 596
atol() (in module string), 108	b32decode() (in module base64), 595
attach() (Message method), 554	b32encode() (in module base64), 595
AttlistDeclHandler() (xmlparser method),	b64decode() (in module base64), 595
618	b64encode() (in module base64), 595
attrgetter() (in module operator), 63	BabylMailbox (class in mailbox), 581
AttributeError (exception in exceptions), 34	backslashreplace_errors_errors() (in
attributes	module codecs), 135
Node attribute, 626	backward() (in module turtle), 689
XMLParser attribute, 648	backward_compatible (data in imageop), 655
AttributesImpl (class in xml.sax.xmlreader),	BadStatusLine (exception in httplib), 493
645	Balloon (class in Tix), 685
AttributesNSImpl (class in	base64
xml.sax.xmlreader), 645	encoding, 595
attroff() (window method), 299	base64 (standard module), 595
attron() (window method), 299	BaseCookie (class in Cookie), 532
attrset() (window method), 299	BaseHandler (class in urllib2), 484
audio (data in cd), 734	BaseHTTPRequestHandler (class in Base-
Audio Interchange File Format, 655, 661	HTTPServer), 521
AUDIO_FILE_ENCODING_ADPCM_G721 (data	BaseHTTPServer (standard module), 521
in sunau), 658	basename() (in module os.path), 255
AUDIO_FILE_ENCODING_ADPCM_G722 (data	basestring() (in module), 4
in sunau), 658	basicConfig() (in module logging), 365
AUDIO_FILE_ENCODING_ADPCM_G723_3	BasicContext (class in decimal), 189
(data in sunau), 658	Bastion() (in module Bastion), 699
AUDIO_FILE_ENCODING_ADPCM_G723_5	Bastion (standard module), 698
(data in sunau), 658	BastionClass (class in Bastion), 699
AUDIO_FILE_ENCODING_ALAW_8 (data in	baudrate() (in module curses), 294
sunau), 658	bdb (standard module), 449
AUDIO_FILE_ENCODING_DOUBLE (data in	Beep() (in module winsound), 754
sunau), 658	beep() (in module curses), 294
AUDIO_FILE_ENCODING_FLOAT (data in	below() (method), 311
sunau), 658	Benchmarking, 464
AUDIO_FILE_ENCODING_LINEAR_16 (data in	benchmarking, 288
sunau), 657	bestreadsize() (CD player method), 734
AUDIO_FILE_ENCODING_LINEAR_24 (data in	betavariate() (in module random), 204
sunau), 658	bgn_group() (form method), 738
AUDIO_FILE_ENCODING_LINEAR_32 (data in	bias() (in module audioop), 652
sunau), 658	bidirectional() (in module unicodedata), 142
AUDIO_FILE_ENCODING_LINEAR_8 (data in	binary
sunau), 657	data, packing, 120
AUDIO_FILE_ENCODING_MULAW_8 (data in	binary() (in module xmlrpclib), 539
sunau), 657	binary semaphores, 397
AUDIO_FILE_MAGIC (data in sunau), 657	binascii (built-in module), 596
AUDIODEV, 665	bind()
audioop (built-in module), 651	dispatcher method, 544
authenticate() (IMAP4_stream method), 503	socket method, 392
authenticators() (netrc method), 603	bind (widgets), 682
avg() (in module audioop), 651	bind_textdomain_codeset() (in module
avgpp() (in module audioop), 651	gettext), 353
SEE (/ (m mount audioop), out	bindtextdomain() (in module gettext), 353
В	binhex() (in module binhex), 598
b16decode() (in module base64), 596	binhex (standard module), 596, 598
b16encode() (in module base64), 595	bisect() (in module bisect), 206
b2a_base64() (in module binascii), 596	bisect (standard module), 206
DAG_DGGCUT(/ VIII HIUUUIE UHIASCH), J70	

782 Index

bisect_left() (in module bisect), 206	BufferingHandler (class in logging), 376
bisect_right() (in module bisect), 206	BufferType (data in types), 58
bit-string	bufsize() (audio device method), 667
operations, 18	build_opener() (in module urllib2), 483
bkgd() (window method), 299	built-in
bkgdset() (window method), 299	constants, 3
blocked_domains() (DefaultCookiePolicy	exceptions, 3
method), 529	functions, 3
BLOCKSIZE (data in cd), 734	types, 3, 15
blocksize (data in sha), 671	builtin_module_names (data in sys), 42
body() (NNTPDataError method), 509	BuiltinFunctionType (data in types), 57
body_encode() (Charset method), 568	BuiltinMethodType (data in types), 58
body_encoding (data in email.Charset), 567	ButtonBox (class in Tix), 685
body_line_iterator() (in module	byte-code
email.Iterators), 572	file, 89, 90, 713
BOM (data in codecs), 135	byteorder (data in sys), 42
BOM_BE (data in codecs), 135	byteswap() (array method), 213
BOM_LE (data in codecs), 135	bz2 (built-in module), 416
BOM_UTF16 (data in codecs), 135	BZ2Compressor (class in bz2), 417
BOM_UTF16_BE (data in codecs), 135	BZ2Decompressor (class in bz2), 417
BOM_UTF16_LE (data in codecs), 135	BZ2File (class in bz2), 416
BOM_UTF32 (data in codecs), 135	_
BOM_UTF32_BE (data in codecs), 135	C
BOM_UTF32_LE (data in codecs), 135	С
BOM_UTF8 (data in codecs), 135	language, 17
bool() (in module), 4	structures, 120
Boolean	C_BUILTIN (data in imp), 90
object, 17	C_EXTENSION (data in imp), 90
operations, 15, 16	CacheFTPHandler (class in urllib2), 485
type, 4	calcsize() (in module struct), 120
values, 33	calendar() (in module calendar), 231
boolean() (in module xmlrpclib), 539	calendar (standard module), 230
BooleanType (data in types), 57	call()
border() (window method), 299	method, 435
bottom() (method), 311	in module subprocess, 264
bottom_panel() (in module curses.panel), 311	callable() (in module), 4
BoundaryError (exception in email.Errors), 569	CallableProxyType (data in weakref), 51
BoundedSemaphore() (in module threading),	can_change_color() (in module curses), 294
399	can_fetch() (RobotFileParser method), 603
box() (window method), 300	cancel()
break_long_words (TextWrapper attribute),	scheduler method, 292
133	Timer method, 405
BROWSER, 469, 470	Cannot SendHeader (exception in httplib), 493
bsddb	Cannot Send Request (exception in httplib), 493
built-in module, 82, 409	capitalize()
extension module, 410	in module string, 108
BsdDbShelf (class in shelve), 83	string method, 20
btopen() (in module bsddb), 411	capwords () (in module string), 108
buffer	cat() (in module nis), 446
object, 19	catalog (data in cd), 734
buffer()	category() (in module unicodedata), 142
built-in function, 19, 58	cbreak() (in module curses), 294
in module, 14	cd (built-in module), 733
buffer size, I/O, 7	CDROM (data in cd), 734
buffer_info() (array method), 213	ceil()
buffer_size (xmlparser attribute), 617	in module math, 17
buffer_text (xmlparser attribute), 617	in module math, 199
buffer_used (xmlparser attribute), 617	
	center()

in module string, 110	Clamped (class in decimal), 192
string method, 20	Class browser, 691
CGI	classmethod() (in module),4
debugging, 476	classobj() (in module new), 101
exceptions, 478	ClassType (data in types), 57
protocol, 471	clear()
security, 475	method, 207
tracebacks, 478	CookieJar method, 526
cgi (standard module), 471	dictionary method, 28
cgi_directories (CGIHTTPRequestHandler	Event method, 403
attribute), 524	in module turtle, 689
CGIHTTPRequestHandler (class in CGI-	window method, 300
HTTPServer), 524	<pre>clear_flags() (Context method), 190</pre>
CGIHTTPServer (standard module), 521, 524	clear_history() (in module readline), 426
cgitb (standard module), 478	clear_memo() (Pickler method), 74
CGIXMLRPCRequestHandler (class in Sim-	clear_session_cookies() (CookieJan
pleXMLRPCServer), 540	method), 527
chain() (in module itertools), 218	clearcache() (in module linecache), 71
chaining	clearok() (window method), 300
comparisons, 16	client_address (BaseHTTPRequestHandle
channels() (audio device method), 666	attribute), 521
CHAR_MAX (data in locale), 351	clock() (in module time), 288
character, 142	clone()
CharacterDataHandler() (xmlparser	Generator method, 562
method), 619	Template method, 441
characters() (ContentHandler method), 642	cloneNode() (Node method), 627, 635
CHARSET (data in mimify), 589	Close() (method), 754
Charset (class in email.Charset), 566	close()
charset() (NullTranslations method), 356	method, 372, 408, 411, 435
chdir() (in module os), 244	aifc method, 656, 657
check()	AU_read method, 658
IMAP4_stream method, 503	AU_write method, 659
in module tabnanny, 712	audio device method, 665, 747
check_forms() (in module fl), 737	BaseHandler method, 487
check_output() (OutputChecker method), 166	BZ2File method, 416
checkcache() (in module linecache), 71	CD player method, 734
CheckList (class in Tix), 686	Chunk method, 662
checksum	dispatcher method, 544
Cyclic Redundancy Check, 414	FeedParser method, 560
MD5, 670	file method, 29
SHA, 670	FileHandler method, 373
childerr (Popen4 attribute), 269	FTP method, 499
childNodes (Node attribute), 626	HTMLParser method, 610
chmod() (in module os), 244	HTTPResponse method, 495
choice()	IMAP4_stream method, 503
in module random, 203	in module fileinput, 230
in module whrandom, 205	in module os, 241
choose_boundary() (in module mimetools),	IncrementalParser method, 646
584	MemoryHandler method, 377
chown () (in module os), 244	mixer device method, 667
chr() (in module), 4	NTEventLogHandler method, 376
chroot() (in module os), 244	Profile method, 463
Chunk (class in chunk), 661	SGMLParser method, 612
chunk (standard module), 661	socket method, 392
cipher	SocketHandler method, 374
DES, 433, 669	StringIO method, 131
IDEA, 669	SysLogHandler method, 375
circle() (in module turtle), 690	TarFile method, 423

T-1	GOLDATIVE (1-4-1-4-1-4-1-7-1-7-1-7-1-7-1-7-1-7-1-7-
Telnet method, 515	COMMENT (data in tokenize), 711
Wave_read method, 660	comment
Wave_write method, 660	Cookie attribute, 531
XMLParser method, 648	ZipInfo attribute, 420
ZipFile method, 419	comment_url (Cookie attribute), 531
close_when_done() (async_chat method), 545	commenters (shlex attribute), 235
closed (file attribute), 30	CommentHandler() (xmlparser method), 619
CloseKey() (in module _winreg), 750	common (dircmp attribute), 262
closelog() (in module syslog), 446	Common Gateway Interface, 471
closeport() (audio port method), 732	common_dirs (dircmp attribute), 262
clrtobot() (window method), 300	common_files (dircmp attribute), 262
clrtoeol() (window method), 300	common_funny (dircmp attribute), 262
cmath (built-in module), 201	common_types (data in mimetypes), 586, 587
Cmd (class in cmd), 231	commonprefix() (in module os.path), 255
cmd (standard module), 231, 449	communicate() (Popen method), 265
cmdloop() (Cmd method), 232	compare()
cmp()	Context method, 191
built-in function, 350	Decimal method, 188
in module , 4	Differ method, 129
in module filecmp, 261	comparing
cmp_op (data in dis), 715	objects, 16
cmpfiles() (in module filecmp), 261	comparison
code	operator, 16
object, 32, 86	COMPARISON_FLAGS (data in doctest), 155
code () (in module new), 101	comparisons
code	chaining, 16
ExpatError attribute, 620	Compile (class in codeop), 96
standard module, 94	compile()
Codecs, 133	AST method, 704
decode, 133	built-in function, 32, 57, 703, 704
encode, 133	in module, 4
codecs (standard module), 133	in module compiler, 723
coded_value (Morsel attribute), 533	in module py_compile, 713
codeop (standard module), 95	in module re, 114
codepoint2name (data in htmlentitydefs), 615	compile_command()
CODESET (data in locale), 351	in module code, 94
CodeType (data in types), 57	in module codeop, 96
coerce() (in module), 15	compile_dir() (in module compileall), 714
collapse_rfc2231_value() (in module	compile_path() (in module compileall), 714
email.Utils), 571	compileall (standard module), 714
collect() (in module gc), 47	compileast() (in module parser), 703
collect_incoming_data() (async_chat	compileFile() (in module compiler), 723
method), 546	compiler (module), 723
collections (standard module), 206	compiler.ast (module), 724
color()	compiler.visitor(module),728
in module fl, 738	complete() (Completer method), 429
in module turtle, 690	completedefault() (Cmd method), 232
color_content() (in module curses), 294	complex()
color_pair() (in module curses), 294	built-in function, 17
colorsys (standard module), 662	in module, 5
COLUMNS, 299	complex number
combine() (datetime method), 276	literals, 17
combining() (in module unicodedata), 142	object, 17
ComboBox (class in Tix), 685	ComplexType (data in types), 57
command (BaseHTTPRequestHandler attribute),	compress()
521	BZ2Compressor method, 417
CommandCompiler (class in codeop), 96	Compress method, 414
commands (standard module), 447	in module bz2, 418

in module jpeg, 745	Coordinated Universal Time, 287
in module zlib, 414	copy()
compress_size (ZipInfo attribute), 421	Context method, 190
compress_type (ZipInfo attribute), 420	hmac method, 669
CompressionError (exception in tarfile), 422	IMAP4_stream method, 503
compressobj() (in module zlib), 414	in module shutil, 347
COMSPEC, 252	md5 method, 670
concat() (in module operator), 62	sha method, 671
concatenation	Template method, 441
operation, 19	copy (standard module), 82, 84
Condition() (in module threading), 398	copy()
Condition (class in threading), 401	dictionary method, 28
ConfigParser	in copy, 84
class in ConfigParser, 226	copy2() (in module shutil), 347
standard module, 226	copy_reg (standard module), 81
configuration	copybinary() (in module mimetools), 584
file, 226	copyfile() (in module shutil), 347
file, debugger, 451	copyfileobj() (in module shutil), 347
file, path, 101	copying files, 347
file, user, 102	copyliteral() (in module mimetools), 584
confstr() (in module os), 254	copymessage() (Folder method), 584
confstr_names (data in os), 254	copymode() (in module shutil), 347
conjugate() (complex number method), 17	copyright (data in sys), 42
connect()	copystat() (in module shutil), 347
dispatcher method, 544	copytree() (in module shutil), 347
FTP method, 497	cos()
HTTPResponse method, 495	in module cmath, 201
SMTP method, 511	in module math, 200
socket method, 392	cosh()
connect_ex() (socket method), 392	in module cmath, 201
ConnectRegistry() (in module _winreg), 750	in module math, 200
constants	count()
built-in, 3	array method, 213
constructor() (in module copy_reg), 82	in module itertools, 218
container	in module string, 109
iteration over, 18	list method, 25
contains() (in module operator), 62	string method, 20
content type	countOf() (in module operator), 62
MIME, 585	countTestCases() (TestCase method), 178
ContentHandler (class in xml.sax.handler), 639	cPickle (built-in module), 81, 82
Context (class in decimal), 190	CPU time, 288
context_diff() (in module difflib), 124	CRC (ZipInfo attribute), 421
Control (class in Tix), 685	crc32()
control (data in cd), 734	in module binascii, 597
controlnames (data in curses.ascii), 311	in module zlib, 414
controls() (mixer device method), 667	crc_hqx() (in module binascii), 597
ConversionError (exception in xdrlib), 602	create() (IMAP4_stream method), 503
conversions	create_decimal() (Context method), 190
numeric, 17	create_socket() (dispatcher method), 544
convert() (Charset method), 567	create_system (ZipInfo attribute), 420
Cookie	create_version (ZipInfo attribute), 420
class in cookielib, 525	createAttribute() (Document method), 628
standard module, 532	<pre>createAttributeNS() (Document method),</pre>
CookieError (exception in Cookie), 532	628
CookieJar (class in cookielib), 525	createComment() (Document method), 628
cookiejar (UnknownHandler attribute), 489	createDocument() (DOMImplementation
cookielib (standard module), 524	method), 625
CookiePolicy (class in cookielib), 525	

createDocumentType() (DOMImplementation method), 625	ProcessingInstruction attribute, 630 Text attribute, 630
createElement() (Document method), 628	UserList attribute, 59
createElementNS() (Document method), 628	database
CreateKey() (in module _winreg), 750	Unicode, 142
createLock() (method), 372	databases, 413
createparser() (in module cd), 733	DatagramHandler (class in logging), 375
createProcessingInstruction() (Docu-	DATASIZE (data in cd), 734
ment method), 628	date()
createTextNode() (Document method), 628	datetime method, 277
critical()	NNTPDataError method, 509
method, 366	date (class in datetime), 270, 273
in module logging, 364	date_time (ZipInfo attribute), 420
CRNCYSTR (data in locale), 351	date_time_string() (BaseHTTPRequest
crop() (in module imageop), 654	Handler method), 523
cross() (in module audioop), 652	datetime
crypt() (in module crypt), 433	built-in module, 270
crypt (built-in module), 432, 433	class in datetime, 270, 275
crypt(3), 433, 434	day
cryptography, 669	date attribute, 273
cStringIO (built-in module), 131	date attribute, 273
_ ,	
csv, 604	DAY_1 DAY_7 (data in locale), 351
csv (standard module), 604 ctermid() (in module os), 238	daylight (data in time), 288
	Daylight Saving Time, 287
ctime()	DbfilenameShelf (class in shelve), 83
date method, 274	dbhash (standard module), 409, 409
datetime method, 279	dbm (built-in module), 82, 409, 435 , 436
in module time, 288	deactivate_form() (form method), 738
ctrl() (in module curses.ascii), 310	debug()
curdir (data in os), 254	method, 366
CurrentByteIndex (xmlparser attribute), 618	in module doctest, 168
CurrentColumnNumber (xmlparser attribute),	in module logging, 364
618	Template method, 441
currentframe() (in module inspect), 69	TestCase method, 177
CurrentLineNumber (xmlparser attribute), 618	debug
currentThread() (in module threading), 398	IMAP4_stream attribute, 506
curs_set() (in module curses), 294	shlex attribute, 235
curses (standard module), 293	ZipFile attribute, 419
curses.ascii (standard module), 309	debug=0 (TarFile attribute), 424
curses.panel (standard module), 311	DEBUG_COLLECTABLE (data in gc), 49
curses.textpad (standard module), 307	DEBUG_INSTANCES (data in gc), 49
curses.wrapper (standard module), 308	DEBUG_LEAK (data in gc), 49
cursyncup() (window method), 300	DEBUG_OBJECTS (data in gc), 49
cwd() (FTP method), 499	DEBUG_SAVEALL (data in gc), 49
cycle() (in module itertools), 218	debug_src() (in module doctest), 168
Cyclic Redundancy Check, 414	DEBUG_STATS (data in gc), 49
D	DEBUG_UNCOLLECTABLE (data in gc), 49
D	debugger, 46, 692
D_FMT (data in locale), 351	configuration file, 451
D_T_FMT (data in locale), 351	debugging, 449
data	CGI, 476
packing binary, 120	DebuggingServer (class in smtpd), 514
tabular, 604	DebugRunner (class in doctest), 168
data	Decimal (class in decimal), 187
Binary attribute, 538	decimal() (in module unicodedata), 142
Comment attribute, 630	decimal (standard module), 183
IterableUserDict attribute, 58	DecimalException (class in decimal), 192
MutableString attribute, 60	decode

Codecs, 133	delay_output() (in module curses), 295
decode()	delayload (Cookie attribute), 527
method, 136	delch() (window method), 300
Binary method, 538	dele() (POP3_SSL method), 501
in module base64, 596	delete()
in module mimetools, 584	FTP method, 499
in module quopri, 598	IMAP4_stream method, 503
in module uu, 599	delete_object() (FORMS object method),
ServerProxy method, 537	740
string method, 20	deleteacl() (IMAP4_stream method), 503
decode_header() (in module email.Header),	deletefolder() (MH method), 583
566	DeleteKey() (in module _winreg), 751
decode_params() (in module email.Utils), 571	deleteln() (window method), 300
decode_rfc2231() (in module email.Utils),	deleteparser() (CD parser method), 736
571	DeleteValue() (in module _winreg), 751
DecodedGenerator (class in email.Generator),	delimiter (Dialect attribute), 606
562	delitem() (in module operator), 62
decodestring()	delslice() (in module operator), 62
in module base64, 596	demo() (in module turtle), 690
in module quopri, 599	DeprecationWarning (exception in excep-
decomposition() (in module unicodedata), 143	tions), 37
decompress()	deque() (in module collections), 207
BZ2Decompressor method, 417	dereference (TarFile attribute), 423
Decompress method, 415	derwin() (window method), 300
in module bz2, 418	DES
in module jpeg, 745	cipher, 433, 669
in module zlib, 414	description() (NNTPDataError method), 508
decompressobj() (in module zlib), 414	descriptions() (NNTPDataError method),
dedent() (in module textwrap), 132	508
deepcopy() (in copy), 84	descriptor, file, 29
def_prog_mode() (in module curses), 294	Detach() (method), 754
def_shell_mode() (in module curses), 294	deterministic profiling, 455
default()	DEVICE (standard module), 744
ASTVisitor method, 729	devnull (data in os), 255
Cmd method, 232	dgettext() (in module gettext), 354
default_bufsize (data in xml.dom.pulldom),	Dialect (class in csv), 605
637	dict() (in module), 5
default_open() (BaseHandler method), 487	dictionary
DefaultContext (class in decimal), 189	object, 28
DefaultCookiePolicy (class in cookielib),	type, operations on, 28
525	DictionaryType (data in types), 57
DefaultHandler() (xmlparser method), 619	DictMixin (class in UserDict), 58
DefaultHandlerExpand() (xmlparser	DictReader (class in csv), 605
method), 619	DictType (data in types), 57
defaults() (SafeConfigParser method), 227	DictWriter (class in csv), 605
defaultTestLoader (data in unittest), 176	diff_files (dircmp attribute), 263
<pre>defaultTestResult() (TestCase method),</pre>	Differ (class in difflib), 123, 129
178	difflib (standard module), 122
defects (data in email.Message), 559	digest()
defpath (data in os), 255	hmac method, 669
<pre>degrees()</pre>	md5 method, 670
in module math, 200	sha method, 671
in module turtle, 689	digest_size
RawPen method, 690	data in md5, 670
del	data in sha, 671
statement, 25, 28	digit() (in module unicodedata), 142
del_param() (Message method), 557	digits (data in string), 105
delattr() (in module), 5	dir()

FTP method, 498	DocCGIXMLRPCRequestHandler (class in
in module, 5	DocXMLRPCServer), 541
dircache (standard module), 258	DocFileSuite() (in module doctest), 160
dircmp (class in filecmp), 262	docmd() (SMTP method), 511
directory	docstring (DocTest attribute), 162
changing, 244	docstrings, 705
creating, 245	DocTest (class in doctest), 162
deleting, 246, 347	doctest (standard module), 146
site-packages, 101	DocTestFailure (exception in doctest), 169
site-python, 101	DocTestFinder (class in doctest), 163
traversal, 248	DocTestParser (class in doctest), 164
walking, 248	DocTestRunner (class in doctest), 164
DirList (class in Tix), 686	DocTestSuite() (in module doctest), 160
dirname() (in module os.path), 255	DOCTYPE declaration, 649
DirSelectBox (class in Tix), 686	documentation
DirSelectDialog (class in Tix), 686	generation, 145
DirTree (class in Tix), 686	online, 145
dis()	documentElement (Document attribute), 628
in module dis, 715	DocXMLRPCRequestHandler (class in
in module pickletools, 721	DocXMLRPCServer), 541
dis (standard module), 714	DocXMLRPCServer
<pre>disable()</pre>	class in DocXMLRPCServer, 541
in module gc, 47	standard module, 541
in module logging, 364	domain_initial_dot (Cookie attribute), 531
disassemble() (in module dis), 715	<pre>domain_return_ok() (CookiePolicy method),</pre>
discard (Cookie attribute), 530	528
discard_buffers() (async_chat method), 546	domain_specified (Cookie attribute), 531
disco() (in module dis), 715	DomainLiberal (LWPCookieJar attribute), 530
dispatch() (ASTVisitor method), 729	DomainRFC2965Match (LWPCookieJar at-
dispatcher (class in asyncore), 543	tribute), 530
displayhook() (in module sys), 42	DomainStrict (LWPCookieJar attribute), 530
dist() (in module platform), 384	DomainStrictNoDots (LWPCookieJar at-
distb() (in module dis), 715	tribute), 530
distutils (standard module), 722	DomainStrictNonDomain (LWPCookieJar at-
dither2grey2() (in module imageop), 654	tribute), 530
dither2mono() (in module imageop), 654	DOMEventStream (class in xml.dom.pulldom),
div() (in module operator), 61	637
divide() (Context method), 191	DOMException (exception in xml.dom), 631
division	DomstringSizeErr (exception in xml.dom),
integer, 17	631
long integer, 17	done() (Unpacker method), 601
DivisionByZero (class in decimal), 192	DONT_ACCEPT_BLANKLINE (data in doctest),
divmod()	154
Context method, 191	DONT_ACCEPT_TRUE_FOR_1 (data in doctest),
in module, 6	154
dl (extension module), 434	<pre>doRollover()</pre>
dllhandle (data in sys), 42	RotatingFileHandler method, 373
dngettext() (in module gettext), 354	TimedRotatingFileHandler method, 374
do_command() (Textbox method), 308	DOTALL (data in re), 115
do_forms() (in module fl), 737	doublequote (Dialect attribute), 606
do_GET() (SimpleHTTPRequestHandler method),	doupdate() (in module curses), 295
523	down() (in module turtle), 689
do_HEAD() (SimpleHTTPRequestHandler	drain() (audio device method), 747
method), 523	dropwhile() (in module itertools), 219
<pre>do_POST() (CGIHTTPRequestHandler method),</pre>	dst()
524	datetime method, 278
doc_header (Cmd attribute), 233	time method, 280, 281
	DTDHandler (class in xml.sax.handler), 639

dumbdbm (standard module), 409, 413	EDESTADDRREQ (data in errno), 344
DumbWriter (class in formatter), 552	edit() (Textbox method), 308
dummy_thread (standard module), 405	EDOM (data in errno), 342
dummy_threading (standard module), 406	EDOTDOT (data in errno), 343
dump()	EDQUOT (data in errno), 345
in module marshal, 86	EEXIST (data in errno), 341
in module pickle, 73	EFAULT (data in errno), 341
Pickler method, 74	EFBIG (data in errno), 341
<pre>dump_address_pair() (in module rfc822),</pre>	ehlo() (SMTP method), 511
592	EHOSTDOWN (data in errno), 345
dump_stats() (Stats method), 459	EHOSTUNREACH (data in errno), 345
dumps()	EIDRM (data in errno), 342
in module marshal, 86	EILSEQ (data in errno), 344
in module pickle, 74	EINPROGRESS (data in errno), 345
in module xmlrpclib, 539	EINTR (data in errno), 340
dup()	EINVAL (data in errno), 341
in module os, 241	EIO (data in errno), 340
in module posixfile, 442	EISCONN (data in errno), 345
dup2()	EISDIR (data in errno), 341
in module os, 241	EISNAM (data in errno), 345
in module posixfile, 442	eject() (CD player method), 734
DuplicateSectionError (exception in Con-	EL2HLT (data in errno), 342
figParser), 226	EL2NSYNC (data in errno), 342
_	EL3HLT (data in errno), 342
E	EL3RST (data in errno), 342
е	<pre>ElementDeclHandler() (xmlparser method),</pre>
data in cmath, 202	618
data in math, 200	elements (XMLParser attribute), 648
E2BIG (data in errno), 341	ELIBACC (data in errno), 344
EACCES (data in errno), 341	ELIBBAD (data in errno), 344
EADDRINUSE (data in errno), 344	ELIBEXEC (data in errno), 344
EADDRNOTAVAIL (data in errno), 344	ELIBMAX (data in errno), 344
EADV (data in errno), 343	ELIBSCN (data in errno), 344
EAFNOSUPPORT (data in errno), 344	Ellinghouse, Lance, 599
EAGAIN (data in errno), 341	ELLIPSIS (data in doctest), 154
EAI_* (data in socket), 389	Ellipsis (data in), 39
EALREADY (data in errno), 345	EllipsisType (data in types), 58
east_asian_width() (in module unicode-	ELNRNG (data in errno), 342
data), 142	ELOOP (data in errno), 342
EBADE (data in errno), 342	email (standard module), 553
EBADF (data in errno), 341	email.Charset (standard module), 566
EBADFD (data in errno), 344	email.Encoders (standard module), 568
EBADMSG (data in errno), 343	email.Errors (standard module), 569
EBADR (data in errno), 342	email.Generator (standard module), 561
EBADRQC (data in errno), 343	email.Header (standard module), 564
EBADSLT (data in errno), 343	email.Iterators (standard module), 572
EBFONT (data in errno), 343	email.Message (standard module), 553
EBUSY (data in errno), 341	email.Parser (standard module), 559
ECHILD (data in errno), 341	email.Utils (standard module), 570
echo() (in module curses), 295	EMFILE (data in errno), 341
echochar() (window method), 300	emit()
ECHRNG (data in errno), 342	method, 373
ECOMM (data in errno), 343	BufferingHandler method, 376
ECONNABORTED (data in errno), 345	DatagramHandler method, 375
ECONNREFUSED (data in errno), 345	FileHandler method, 373
ECONNRESET (data in errno), 345	HTTPHandler method, 377
EDEADLK (data in errno), 342	NTEventLogHandler method, 376
EDEADLOCK (data in errno), 343	RotatingFileHandler method, 374

SMTPHandler method, 376	end_headers() (BaseHTTPRequestHandler
SocketHandler method, 374	method), 522
StreamHandler method, 373	end_marker() (MultiFile method), 590
SysLogHandler method, 375	end_paragraph() (formatter method), 550
TimedRotatingFileHandler method, 374	<pre>EndCdataSectionHandler() (xmlparser</pre>
EMLINK (data in errno), 342	method), 619
Empty (exception in Queue), 406	EndDoctypeDeclHandler() (xmlparser
empty()	method), 618
Queue method, 406	endDocument() (ContentHandler method), 641
scheduler method, 292	endElement() (ContentHandler method), 641
EMPTY_NAMESPACE (data in xml.dom), 624	<pre>EndElementHandler() (xmlparser method),</pre>
emptyline()(Cmd method), 232	618
EMSGSIZE (data in errno), 344	endElementNS() (ContentHandler method), 642
EMULTIHOP (data in errno), 343	endheaders() (HTTPResponse method), 495
enable()	EndNamespaceDeclHandler() (xmlparser
in module cgitb, 478	method), 619
in module gc, 47	endpick() (in module gl), 743
ENAMETOOLONG (data in errno), 342	endpos (MatchObject attribute), 118
ENAVAIL (data in errno), 345	endPrefixMapping() (ContentHandler
enclose() (window method), 300	method), 641
encode	endselect() (in module gl), 743
Codecs, 133	endswith() (string method), 21
encode()	endwin() (in module curses), 295
method, 136	ENETDOWN (data in errno), 344
Binary method, 538	ENETRESET (data in errno), 345
Header method, 565	ENETUNREACH (data in errno), 345
in module base64, 596	ENFILE (data in errno), 341
in module mimetools, 584	ENOANO (data in errno), 343
in module quopri, 599	ENOBUFS (data in errno), 345
in module uu, 599	ENOCSI (data in errno), 342
ServerProxy method, 537	ENODATA (data in errno), 343
string method, 20	ENODEV (data in errno), 341
encode_7or8bit() (in module	ENOENT (data in errno), 340
email.Encoders), 569	ENOEXEC (data in errno), 341
encode_base64() (in module email.Encoders),	ENOLCK (data in errno), 342
569	ENOLINK (data in errno), 343
encode_noop() (in module email.Encoders),	ENOMEM (data in errno), 341
569	ENOMSG (data in errno), 342
encode_quopri() (in module email.Encoders),	ENONET (data in errno), 343
569	ENOPKG (data in errno), 343
encode_rfc2231() (in module email.Utils),	ENOPROTOOPT (data in errno), 344
571	ENOSPC (data in errno), 341
encoded_header_len() (Charset method),	ENOSR (data in errno), 343
567	ENOSTR (data in errno), 343
EncodedFile() (in module codecs), 135	ENOSYS (data in errno), 342
encodePriority() (SysLogHandler method),	ENOTBLK (data in errno), 341
375	ENOTCONN (data in errno), 345
encodestring()	ENOTDIR (data in errno), 341
in module base64, 596	ENOTEMPTY (data in errno), 342
in module quopri, 599	ENOTNAM (data in errno), 345
encoding	ENOTSOCK (data in errno), 344
base64, 595	ENOTTY (data in errno), 341
quoted-printable, 598	ENOTUNIQ (data in errno), 343
encoding (file attribute), 30	enter() (scheduler method), 292
encodings.idna (standard module), 141	enterabs() (scheduler method), 292
encodings_map (data in mimetypes), 586, 587	entities (DocumentType attribute), 628
end () (MatchObject method), 118	ENTITY declaration, 649
end_group() (form method), 738	

<pre>EntityDeclHandler() (xmlparser method),</pre>	EOPNOTSUPP (data in errno), 344
619	EOVERFLOW (data in errno), 343
entitydefs	EPERM (data in errno), 340
data in htmlentitydefs, 615	EPFNOSUPPORT (data in errno), 344
XMLParser attribute, 648	epilogue (data in email.Message), 558
EntityResolver (class in xml.sax.handler), 639	EPIPE (data in errno), 342
enumerate()	epoch, 286
in module, 6	EPROTO (data in errno), 343
in module fm, 742	EPROTONOSUPPORT (data in errno), 344
in module threading, 398	EPROTOTYPE (data in errno), 344
EnumKey() (in module _winreg), 751	eq() (in module operator), 60
EnumValue() (in module _winreg), 751	ERA (data in locale), 351
environ	ERA_D_FMT (data in locale), 352
data in os, 238	ERA_D_T_FMT (data in locale), 352
data in posix, 432	ERA_YEAR (data in locale), 352
environment variables	ERANGE (data in errno), 342
;protocol;_proxy, 484	erase() (window method), 300
AUDIODEV, 665	erasechar() (in module curses), 295
BROWSER, 469, 470	EREMCHG (data in errno), 344
COLUMNS, 299	EREMOTE (data in errno), 343
COMSPEC, 252	EREMOTE (data in errno), 345
HOMEDRIVE, 256	
	ERESTART (data in errno), 344
HOMEPATH, 256	EROFS (data in errno), 342
HOME, 102, 256	ERR (data in curses), 304
KDEDIR, 470	errcode (ServerProxy attribute), 538
LANGUAGE, 353, 355	errmsg (ServerProxy attribute), 538
LANG, 349, 353, 355	errno
LC_ALL, 353, 355	built-in module, 238, 388
LC_MESSAGES, 353, 355	standard module, 340
LINES, 299	ERROR (data in cd), 734
LNAME, 293	Error
LOGNAME, 239, 293	exception in binascii, 597
MIXERDEV, 665	exception in binhex, 598
PAGER, 451	exception in csv, 606
PATH, 249, 251, 255, 476, 477	exception in locale, 348
PYTHONDOCS, 146	exception in shutil, 348
PYTHONPATH, 45, 476, 758	exception in sunau, 657
PYTHONSTARTUP, 102, 427, 429	exception in turtle, 690
PYTHONY2K, 286, 287	exception in uu, 599
PYTHON_DOM, 624	exception in wave, 660
TEMP, 340	exception in webbrowser, 470
TIX_LIBRARY, 685	exception in xdrlib, 602
TMPDIR, 247, 340	error()
TMP, 247, 340	method, 366
TZ, 290, 291, 758	ErrorHandler method, 643
USERNAME, 293	Folder method, 583
USER, 293	in module logging, 364
Wimp\$ScrapDir, 340	MH method, 582
ftp_proxy, 479	OpenerDirector method, 486
gopher_proxy, 479	•
http_proxy, 479, 491	error
	exception in anydbm, 409
deleting, 240	exception in audioop, 651
setting, 239	exception in cd, 734
EnvironmentError (exception in exceptions),	exception in curses, 294
34	exception in dbhash, 409
ENXIO (data in errno), 341	exception in dbm, 435
eof (shlex attribute), 235	exception in dl, 434
EOFError (exception in exceptions), 35	exception in dumbdbm, 413

exception in gdbm, 436	ETXTBSY (data in errno), 341
exception in getopt, 312	EUCLEAN (data in errno), 345
exception in imageop, 654	EUNATCH (data in errno), 342
exception in imageop, 0.54 exception in imgfile, 744	
	EUSERS (data in errno), 344
exception in jpeg, 745	eval()
exception in nis, 446	built-in function, 32, 98, 108, 703
exception in os, 238	in module, 6
exception in re, 117	Event () (in module threading), 399
exception in resource, 444	Event (class in threading), 403
exception in rgbimg, 663	event scheduling, 291
exception in select, 396	events (widgets), 682
exception in socket, 388	EWOULDBLOCK (data in errno), 342
exception in struct, 120	EX_CANTCREAT (data in os), 250
exception in sunaudiodev, 747	EX_CONFIG (data in os), 251
exception in thread, 397	EX_DATAERR (data in os), 250
exception in xml.parsers.expat, 615	EX_IOERR (data in os), 250
exception in zipfile, 418	EX_NOHOST (data in os), 250
exception in zlib, 414	EX_NOINPUT (data in os), 250
error_leader() (shlex method), 234	EX_NOPERM (data in os), 250
error_message_format (BaseHTTPRequest-	EX_NOTFOUND (data in os), 251
Handler attribute), 522	EX_NOUSER (data in os), 250
error_perm (exception in ftplib), 497	EX_OK (data in os), 250
error_proto	EX_OSERR (data in os), 250
exception in ftplib, 497	EX_OSFILE (data in os), 250
exception in poplib, 500	EX_PROTOCOL (data in os), 250
error_reply (exception in ftplib), 497	EX_SOFTWARE (data in os), 250
error_temp (exception in ftplib), 497	EX_TEMPFAIL (data in os), 250
ErrorByteIndex (xmlparser attribute), 617	EX_UNAVAILABLE (data in os), 250
ErrorCode (xmlparser attribute), 618	EX_USAGE (data in os), 250
errorcode (data in errno), 340	Example (class in doctest), 163
ErrorColumnNumber (xmlparser attribute), 618	example
ErrorHandler (class in xml.sax.handler), 639	DocTestFailure attribute, 169
errorlevel (TarFile attribute), 424	UnexpectedException attribute, 169
ErrorLineNumber (xmlparser attribute), 618	examples (DocTest attribute), 162
Errors	exc_clear() (in module sys), 43
logging, 362	exc_info() (in module sys), 42
errors (TestResult attribute), 179	exc_info (UnexpectedException attribute), 169
<pre>ErrorString() (in module xml.parsers.expat),</pre>	exc_msg (Example attribute), 163
616	exc_traceback (data in sys), 43
escape()	exc_type (data in sys), 43
in module cgi, 475	exc_value (data in sys), 43
in module re, 117	except
in module xml.sax.saxutils, 643	statement, 34
escape (shlex attribute), 235	excepthook()
escapechar (Dialect attribute), 606	in module sys, 42
escapedquotes (shlex attribute), 235	in module sys, 478
ESHUTDOWN (data in errno), 345	Exception (exception in exceptions), 34
ESOCKTNOSUPPORT (data in errno), 344	exception()
ESPIPE (data in errno), 341	method, 366
ESRCH (data in errno), 340	in module logging, 364
ESRMNT (data in errno), 343	exceptions
ESTALE (data in errno), 345	built-in, 3
ESTRPIPE (data in errno), 344	in CGI scripts, 478
ETIME (data in errno), 343	exceptions (standard module), 33
ETIME (data in errno), 345 ETIMEDOUT (data in errno), 345	EXDEV (data in errno), 341
Etiny() (Context method), 190	exec
ETOOMANYREFS (data in errno), 345	statement, 32
Etop() (Context method), 191	exec_prefix (data in sys), 43
Ecop (/ (Context memou), 191	CACC-PLELIA (data III sys), 43

<pre>execfile()</pre>	extra (ZipInfo attribute), 420
built-in function, 102	extract() (TarFile method), 423
in module, 6	extract_cookies() (CookieJar method), 526
execl() (in module os), 249	extract_stack() (in module traceback), 70
execle() (in module os), 249	extract_tb() (in module traceback), 70
execlp() (in module os), 249	extract_version (ZipInfo attribute), 420
execlpe() (in module os), 249	ExtractError (exception in tarfile), 422
executable (data in sys), 43	extractfile() (TarFile method), 423
execv() (in module os), 249	extsep (data in os), 255
execve() (in module os), 249	F
execvp() (in module os), 249	F
execvpe() (in module os), 249	F_BAVAIL (data in statvfs), 261
ExFileSelectBox (class in Tix), 686	F_BFREE (data in statvfs), 261
EXFULL (data in errno), 343	F_BLOCKS (data in statvfs), 261
exists() (in module os.path), 255	F_BSIZE (data in statvfs), 261
exit()	F_FAVAIL (data in statvfs), 261
in module sys, 43	F_FFREE (data in statvfs), 261
in module thread, 397	F_FILES (data in statvfs), 261
exitfunc	F_FLAG (data in statvfs), 261
data in sys, 43	F_FRSIZE (data in statvfs), 261
in sys, 55	F_NAMEMAX (data in statvfs), 261
exp()	F_OK (data in os), 243
in module cmath, 201	fabs() (in module math), 199
in module math, 199	fail() (TestCase method), 178
expand() (MatchObject method), 118	failIf() (TestCase method), 178
expand_tabs (TextWrapper attribute), 133	<pre>failIfAlmostEqual() (TestCase method)</pre>
expandNode() (DOMEventStream method), 637	177
expandtabs()	failIfEqual() (TestCase method), 177
in module string, 108	failUnless() (TestCase method), 177
string method, 21	failUnlessAlmostEqual() (TestCase
expanduser() (in module os.path), 256	method), 177
expandvars() (in module os.path), 256	failUnlessEqual() (TestCase method), 177
Expat, 615	failUnlessRaises() (TestCase method), 177
ExpatError (exception in xml.parsers.expat), 615	failureException (TestCase attribute), 178
expect() (Telnet method), 515	failures (TestResult attribute), 179
expires (Cookie attribute), 530	False, 15, 33
expovariate() (in module random), 204	False
expr() (in module parser), 702	Built-in object, 15
expunge() (IMAP4_stream method), 503	data in, 38
extend()	false, 15
method, 207	FancyURLopener (class in urllib), 481
array method, 213 list method, 25	fatalError() (ErrorHandler method), 643
extend_path() (in module pkgutil), 93	faultCode (ServerProxy attribute), 538
extended slice	faultString (ServerProxy attribute), 538
assignment, 25	fchdir() (in module os), 244
operation, 19	fcntl() (in module fcntl), 439
ExtendedContext (class in decimal), 189	fcntl (built-in module), 29, 439
extendedtontext (class in decimal), 189	fcntl() (in module fcntl), 442
Extensible Markup Language, 648	fdatasync() (in module os), 241
extensions_map (SimpleHTTPRequestHandler	fdopen() (in module os), 240
attribute), 523	Faatuus sutamaal saa (doto ir
External Data Representation, 73, 600	feature_external_ges (data in
	xml.sax.handler), 640
external attr (ZinInfo attribute) 420	xml.sax.handler), 640 feature_external_pes (data in
external_attr (ZipInfo attribute), 420 ExternalEntityParserCreate() (xml-	xml.sax.handler), 640 feature_external_pes (data ir xml.sax.handler), 640
ExternalEntityParserCreate() (xml-	xml.sax.handler), 640 feature_external_pes (data in xml.sax.handler), 640 feature_namespace_prefixes (data in
ExternalEntityParserCreate() (xml-parser method), 617	xml.sax.handler), 640 feature_external_pes (data ir xml.sax.handler), 640 feature_namespace_prefixes (data ir xml.sax.handler), 640
ExternalEntityParserCreate() (xml-	xml.sax.handler), 640 feature_external_pes (data in xml.sax.handler), 640 feature_namespace_prefixes (data in

feature_string_interning (data	in	ZipInfo attribute, 420
xml.sax.handler), 640		filename_only (data in tabnanny), 712
feature_validation (data	in	filenames
xml.sax.handler), 640		pathname expansion, 346
feed()		wildcard expansion, 346
FeedParser method, 560		fileno()
HTMLParser method, 610		audio device method, 665, 747
IncrementalParser method, 646		file method, 29
SGMLParser method, 612		in module SocketServer, 519
XMLParser method, 648		mixer device method, 667
FeedParser (class in email.Parser), 560		Profile method, 463
fetch() (IMAP4_stream method), 503		socket method, 392
fifo (class in asynchat), 547		Telnet method, 515
file		fileopen() (in module posixfile), 442
.ini, 226		FileSelectBox (class in Tix), 686
.pdbrc, 451		FileType (data in types), 58
.pythonrc.py, 102		fill()
byte-code, 89, 90, 713		in module textwrap, 132
configuration, 226		in module turtle, 690
copying, 347		TextWrapper method, 133
debugger configuration, 451		Filter (class in logging), 378
large files, 431		filter()
mime.types, 586		method, 366, 372
object, 29		Filter method, 378
path configuration, 101		in module, 7
temporary, 338		in module curses, 295
user configuration, 102		in module fnmatch, 346
file()		filterwarnings() (in module warnings), 88
built-in function, 29		find()
in module, 7		method, 408
in module posixfile, 442		DocTestFinder method, 163
file		in module gettext, 355
class descriptor attribute, 713		in module string, 108
function descriptor attribute, 713		string method, 21
file control		find_first() (form method), 738
Unix, 439		<pre>find_last() (form method), 738</pre>
file descriptor, 29		<pre>find_longest_match() (SequenceMatcher</pre>
file name		method), 126
temporary, 338		find_module()
file object		in module imp, 89
POSIX, 442		zipimporter method, 92
file_offset (ZipInfo attribute), 421		<pre>find_prefix_at_end() (in module asynchat),</pre>
file_open() (FileHandler method), 490		547
file_size (ZipInfo attribute), 421		<pre>find_user_password() (HTTPPasswordMgr</pre>
filecmp (standard module), 261		method), 489
fileConfig() (in module logging), 379		findall()
FileCookieJar (class in cookielib), 525		in module re, 116
FileEntry (class in Tix), 686		RegexObject method, 117
FileHandler		findCaller() (method), 366
class in logging, 373		findfactor() (in module audioop), 652
class in urllib2, 485		findfile() (in module test.test_support), 183
FileInput (class in fileinput), 230		findfit() (in module audioop), 652
fileinput (standard module), 229		findfont() (in module fm), 742
filelineno() (in module fileinput), 229		finditer()
filename() (in module fileinput), 229		in module re, 116
filename		RegexObject method, 117
Cookie attribute, 527		findmatch() (in module mailcap), 580
DocTest attribute, 162		findmax() (in module audioop), 652

finish() (in module SocketServer), 520	Folder (class in mhlib), 582
<pre>finish_request() (in module SocketServer),</pre>	Font Manager, IRIS, 741
520	fontpath() (in module fm), 742
<pre>first()</pre>	forget()
method, 412	in module statcache, 260
dbhash method, 410	in module test.test_support, 183
fifo method, 547	forget_dir() (in module statcache), 260
firstChild (Node attribute), 626	<pre>forget_except_prefix() (in module stat-</pre>
firstkey() (in module gdbm), 436	cache), 260
firstweekday() (in module calendar), 230	<pre>forget_prefix() (in module statcache), 260</pre>
fix() (in module fpformat), 130	fork()
fix_sentence_endings (TextWrapper at-	in module os, 251
tribute), 133	in module pty, 438
FL (standard module), 741	forkpty() (in module os), 251
fl (built-in module), 736	Form (class in Tix), 687
flag_bits (ZipInfo attribute), 420	Formal Public Identifier, 649
flags() (in module posixfile), 442	format()
flags (RegexObject attribute), 117	method, 373
flash() (in module curses), 295	Formatter method, 378
flatten() (Generator method), 562	in module locale, 350
flattening	PrettyPrinter method, 99
objects, 72	<pre>format_exc() (in module traceback), 70</pre>
float()	<pre>format_exception() (in module traceback),</pre>
built-in function, 17, 108	70
in module, 7	<pre>format_exception_only() (in module trace-</pre>
floating point	back), 70
literals, 17	<pre>format_list() (in module traceback), 70</pre>
object, 17	format_stack() (in module traceback), 70
FloatingPointError	<pre>format_tb() (in module traceback), 70</pre>
exception in exceptions, 35	formataddr() (in module email. Utils), 570
exception in fpectl, 54	formatargspec() (in module inspect), 68
FloatType (data in types), 57	formatargvalues() (in module inspect), 68
flock() (in module fcntl), 440	formatdate() (in module email. Utils), 571
floor()	formatException() (Formatter method), 378
in module math, 17	Formatter (class in logging), 377
in module math, 199	formatter
floordiv() (in module operator), 61	HTMLParser attribute, 614
flp (standard module), 741	standard module, 549 , 613
flush()	formatTime() (Formatter method), 378
method, 372, 408	formatting, string (%), 23
audio device method, 747	formatwarning() (in module warnings), 88
BufferingHandler method, 376	FORMS Library, 736
BZ2Compressor method, 417	forward() (in module turtle), 689
Compress method, 414	<pre>found_terminator() (async_chat method),</pre>
Decompress method, 415	546
file method, 29	fp (AddressList attribute), 594
MemoryHandler method, 377	fpathconf() (in module os), 241
StreamHandler method, 373	fpectl (extension module), 54
writer method, 551	fpformat (standard module), 130
flush_softspace() (formatter method), 550	frame (ScrolledText attribute), 689
flushheaders () (MimeWriter method), 587	FrameType (data in types), 58
flushinp() (in module curses), 295	freeze_form() (form method), 738
FlushKey() (in module _winreg), 751	<pre>freeze_object() (FORMS object method),</pre>
fm (built-in module), 741	740
fmod() (in module math), 199	frexp() (in module math), 199
fnmatch() (in module fnmatch), 346	from_splittable() (Charset method), 567
fnmatch (standard module), 346	frombuf() (TarInfo method), 424
fnmatchcase() (in module fnmatch), 346	fromchild (Popen4 attribute), 269

fromfd() (in module socket), 390	Queue method, 407
fromfile() (array method), 213	SafeConfigParser method, 228
fromkeys() (dictionary method), 28	<pre>get_all() (Message method), 555</pre>
fromlist() (array method), 213	<pre>get_begidx() (in module readline), 427</pre>
<pre>fromordinal()</pre>	<pre>get_body_encoding() (Charset method), 567</pre>
date method, 273	<pre>get_boundary() (Message method), 557</pre>
datetime method, 276	get_buffer()
fromstring() (array method), 213	Packer method, 600
<pre>fromtimestamp()</pre>	Unpacker method, 601
date method, 273	<pre>get_charset() (Message method), 555</pre>
datetime method, 275	<pre>get_charsets() (Message method), 558</pre>
fromunicode() (array method), 213	get_close_matches() (in module difflib), 124
fromutc() (time method), 282	<pre>get_code() (zipimporter method), 92</pre>
frozenset() (in module),7	get_completer() (in module readline), 427
fstat() (in module os), 242	<pre>get_completer_delims() (in module read-</pre>
fstatvfs() (in module os), 242	line), 427
fsync() (in module os), 242	<pre>get_content_charset() (Message method),</pre>
FTP, 481	558
ftplib (standard module), 496	<pre>get_content_maintype() (Message</pre>
protocol, 481, 496	method), 556
FTP (class in ftplib), 497	<pre>get_content_subtype() (Message method),</pre>
ftp_open() (FTPHandler method), 490	556
ftp_proxy, 479	<pre>get_content_type() (Message method), 556</pre>
FTPHandler (class in urllib2), 485	<pre>get_current_history_length() (in mod-</pre>
ftplib (standard module), 496	ule readline), 426
ftpmirror.py, 497	get_data()
ftruncate() (in module os), 242	Request method, 485
Full (exception in Queue), 406	zipimporter method, 92
full() (Queue method), 406	get_debug() (in module gc), 48
func_code (function object attribute), 32	<pre>get_default_type() (Message method), 556</pre>
function() (in module new), 100	<pre>get_dialect() (in module csv), 605</pre>
functions	<pre>get_directory() (in module fl), 737</pre>
built-in, 3	<pre>get_doctest() (DocTestParser method), 164</pre>
FunctionTestCase (class in unittest), 176	get_endidx() (in module readline), 427
FunctionType (data in types), 57	<pre>get_examples() (DocTestParser method), 164</pre>
funny_files (dircmp attribute), 263	$get_filename()$
FutureWarning (exception in exceptions), 37	in module fl, 737
	Message method, 557
G	get_full_url() (Request method), 486
G.722, 656	<pre>get_grouped_opcodes() (SequenceMatcher</pre>
gaierror (exception in socket), 388	method), 127
gammavariate() (in module random), 204	<pre>get_history_item() (in module readline),</pre>
garbage (data in gc), 48	427
gather() (Textbox method), 308	<pre>get_history_length() (in module readline),</pre>
gauss () (in module random), 204	426
gc (extension module), 47	get_host() (Request method), 486
gdbm (built-in module), 82, 409, 436	get_ident() (in module thread), 397
ge() (in module operator), 60	get_line_buffer() (in module readline), 426
generate_tokens() (in module tokenize), 711	get_magic() (in module imp), 89
Generator (class in email.Generator), 562	get_main_type() (Message method), 559
GeneratorType (data in types), 57	get_matching_blocks() (SequenceMatcher
genops() (in module pickletools), 721	method), 127
get()	get_method() (Request method), 485
AddressList method, 593	<pre>get_mouse() (in module fl), 737</pre>
dictionary method, 28	<pre>get_nonstandard_attr() (Cookie method),</pre>
in module webbrowser, 470	531
Message method, 555	get_nowait() (Queue method), 407
mixer device method, 668	get_objects() (in module gc), 48

<pre>get_opcodes() (SequenceMatcher method 127</pre>	od), getCharacterStream() (InputSource method), 647
<pre>get_origin_req_host() (Request method</pre>	od), getche() (in module msvcrt), 750
486 get_osfhandle() (in module msvcrt), 749	<pre>getcheckinterval() (in module sys), 43 getChildNodes() (Node method), 724</pre>
get_ostrianate() (in module insvert), 749 get_output_charset() (Charset metho	
567	getclasstree() (in module inspect), 68
get_param() (Message method), 557	getColumnNumber() (Locator method), 646
get_params() (Message method), 556	getcomment() (in module fm), 742
get_pattern() (in module fl), 737	getcomments() (in module inspect), 67
<pre>get_payload() (Message method), 554</pre>	getcompname()
<pre>get_position() (Unpacker method), 601</pre>	aifc method, 655
<pre>get_recsrc() (mixer device method), 668</pre>	AU_read method, 658
get_referents() (in module gc), 48	Wave_read method, 660
<pre>get_referrers() (in module gc), 48</pre>	<pre>getcomptype()</pre>
${\tt get_request()} \ (in \ module \ SocketServer), 52$	
<pre>get_rgbmode() (in module fl), 737</pre>	AU_read method, 658
get_selector() (Request method), 486	Wave_read method, 660
get_socket() (Telnet method), 515	getconfig() (audio port method), 733
get_source() (zipimporter method), 92	getContentHandler() (XMLReader method),
<pre>get_starttag_text()</pre>	645
HTMLParser method, 610	getcontext()
SGMLParser method, 612	in module decimal, 189
get_subtype() (Message method), 559	MH method, 583
get_suffixes() (in module imp), 89	getctime() (in module os.path), 256
get_terminator() (async_chat method), 54	
get_threshold() (in module gc), 48	getcwd() (in module os), 244
get_token() (shlex method), 234	getcwdu() (in module os), 244 getdate() (AddressList method), 593
get_type() Message method, 559	getdate() (AddressList method), 593 getdate_tz() (AddressList method), 594
Request method, 486	getdecoder() (in module codecs), 134
get_unixfrom() (Message method), 554	getdefoder() (in module codecs), 134 getdefaultencoding() (in module sys), 43
getacl() (IMAP4_stream method), 503	getdefaultlocale() (in module locale), 349
getaddr() (AddressList method), 593	getdefaulttimeout() (in module socket),
getaddresses() (in module email.Utils), 570	
getaddrinfo() (in module socket), 389	getdlopenflags() (in module sys), 43
getaddrlist() (AddressList method), 593	getdoc() (in module inspect), 67
getallmatchingheaders() (AddressI	
method), 593	xml.dom), 624
getargspec() (in module inspect), 68	getDTDHandler() (XMLReader method), 645
getargvalues() (in module inspect), 68	<pre>getEffectiveLevel() (method), 365</pre>
getatime() (in module os.path), 256	getegid() (in module os), 238
getattr() (in module), 7	<pre>getElementsByTagName()</pre>
getAttribute() (Element method), 629	Document method, 628
<pre>getAttributeNode() (Element method), 62</pre>	
<pre>getAttributeNodeNS() (Element method</pre>	
629	Document method, 628
getAttributeNS() (Element method), 629	Element method, 629
GetBase() (xmlparser method), 616	getencoder() (in module codecs), 134
getbegyx() (window method), 300	getEncoding() (InputSource method), 647
getboolean() (SafeConfigParser method), 22	
getByteStream() (InputSource method), 64	
getcaps() (in module mailcap), 580	645
getch()	getenv() (in module os), 239
in module msvcrt, 750	getErrorHandler() (XMLReader method),
window method, 300	645
getchannels() (audio configuration method 732	od), geteuid() (in module os), 239 getEvent() (DOMEventStream method), 637
1 34	gccivciic() (Dominutanii incuidu), 03/

getEventCategory() (NTEventLogHandler	getLineNumber() (Locator method), 646
method), 376	getlist() (FieldStorage method), 474
getEventType() (NTEventLogHandler	getloadavg() (in module os), 254
method), 376	getlocale() (in module locale), 349
getException() (SAXException method), 639	getLogger() (in module logging), 364
getfd() (audio port method), 732	getLoggerClass() (in module logging), 364
getFeature() (XMLReader method), 645	getlogin() (in module os), 239
getfile() (in module inspect), 68	getmaintype() (Message method), 585
getfilesystemencoding() (in module sys),	getmark()
44	aifc method, 656
getfillable() (audio port method), 732	AU_read method, 659
getfilled() (audio port method), 732	Wave_read method, 660
getfillpoint() (audio port method), 733	getmarkers()
getfirst() (FieldStorage method), 474	aifc method, 656
getfirstmatchingheader() (AddressList	AU_read method, 658
method), 593	Wave_read method, 660
getfloat() (SafeConfigParser method), 228	getmaxyx() (window method), 300
getfloatmax() (audio configuration method),	getmcolor() (in module fl), 738
732	getmember () (TarFile method), 423
getfmts() (audio device method), 666	getmembers()
getfontinfo() (in module fm), 742	in module inspect, 66
getfontname() (in module fm), 742	TarFile method, 423
getfqdn() (in module socket), 389	getMessage()
getframeinfo() (in module inspect), 69	LogRecord method, 378
getframerate()	SAXException method, 639
aifc method, 655	getmessagefilename() (Folder method), 583
AU_read method, 658	getMessageID() (NTEventLogHandler
Wave_read method, 660	method), 376
getfullname() (Folder method), 583	getmodule() (in module inspect), 68
getgid() (in module os), 239	getmoduleinfo() (in module inspect), 66
getgrall() (in module grp), 433	getmodulename() (in module inspect), 67
getgrgid() (in module grp), 433	getmouse() (in module curses), 295
getgrnam() (in module grp), 433	getmro() (in module inspect), 68
getgroups() (in module os), 239	getmtime() (in module os.path), 256
getheader()	getName() (Thread method), 404
AddressList method, 593	getname() (Chunk method), 662
HTTPResponse method, 495	getNameByQName() (AttributesNS method), 647
getheaders () (HTTPResponse method), 495	getnameinfo() (in module socket), 390
gethostbyaddr()	getNames () (Attributes method), 647
in module socket, 240 in module socket, 389	getnames() (TarFile method), 423 getnamespace() (XMLParser method), 648
	- '
gethostbyname() (in module socket), 389 gethostbyname_ex() (in module socket), 389	getnchannels()
gethostname()	aifc method, 655 AU_read method, 658
in module socket, 240	
in module socket, 389	Wave_read method, 660 getnframes()
	aifc method, 655
getinfo() audio device method, 748	AU_read method, 658
ZipFile method, 419	Wave_read method, 660
getinnerframes() (in module inspect), 69	getopt() (in module getopt), 312
GetInputContext() (xmlparser method), 616	getopt (standard module), 312
getint() (SafeConfigParser method), 228	GetoptError (exception in getopt), 312
getitem() (in module operator), 62	getouterframes () (in module inspect), 69
getkey() (window method), 300	getouterrames () (in module inspect), 69 getoutput () (in module commands), 447
getlast() (Folder method), 583	getpagesize() (in module resource), 445
getLength() (Attributes method), 647	getpages12e() (Minodule resource), 445 getparam() (Message method), 585
getLevelName() (in module logging), 364	getparams()
getline() (in module linecache), 71	aifc method, 656
jee-ine () (in module infection), / i	and moniou, 000

AU_read method, 658	getsockname() (socket method), 392
in module al, 732	getsockopt() (socket method), 392
Wave_read method, 660	getsource() (in module inspect), 68
getparyx() (window method), 301	getsourcefile() (in module inspect), 68
getpass() (in module getpass), 293	getsourcelines() (in module inspect), 68
getpass (standard module), 293	getstate() (in module random), 203
getpath() (MH method), 583	getstatus()
getpeername() (socket method), 392	audio port method, 733
getpgid() (in module os), 239	CD player method, 734
getpgrp() (in module os), 239	in module commands, 447
getpid() (in module os), 239	getstatusoutput() (in module commands)
getplist() (Message method), 585	447
getpos() (HTMLParser method), 610	getstr() (window method), 301
getppid() (in module os), 239	getstrwidth() (in module fm), 742
getpreferredencoding() (in module locale),	getSubject() (SMTPHandler method), 376
350	getsubtype() (Message method), 585
getprofile()(MH method),582	getSystemId()
getProperty() (XMLReader method), 646	InputSource method, 646
getprotobyname() (in module socket), 390	Locator method, 646
getPublicId()	getsyx() (in module curses), 295
InputSource method, 646	gettarinfo() (TarFile method), 423
Locator method, 646	gettempdir() (in module tempfile), 340
getpwall() (in module pwd), 433	gettempprefix() (in module tempfile), 340
getpwnam() (in module pwd), 433	getTestCaseNames() (TestLoader method)
getpwuid() (in module pwd), 433	180
getQNameByName() (AttributesNS method), 647	gettext()
getQNames() (AttributesNS method), 647	GNUTranslations method, 357
getqueuesize() (audio configuration method),	in module gettext, 354
732	NullTranslations method, 356
getquota() (IMAP4_stream method), 503	gettext (standard module), 353
getquotaroot() (IMAP4_stream method), 503 getrandbits() (in module random), 203	gettimeout() (socket method), 393 gettrackinfo() (CD player method), 735
getrawheader() (AddressList method), 593	getType() (Attributes method), 647
getrawheader() (AddressEss method), 393 getreader() (in module codecs), 134	gettype() (Message method), 585
getrecursionlimit() (in module sys), 44	gettype() (Message method), 363 getuid() (in module os), 239
getrefcount() (in module sys), 44	getuser() (in module getpass), 293
getresponse() (HTTPResponse method), 495	getValue() (Attributes method), 647
getrlimit() (in module resource), 444	getvalue() (StringIO method), 131
getrusage() (in module resource), 445	getValueByQName() (AttributesNS method)
getsampfmt() (audio configuration method),	647
732	getweakrefcount() (in module weakref), 50
getsample() (in module audioop), 652	getweakrefs() (in module weakref), 50
getsampwidth()	getwelcome()
aifc method, 655	FTP method, 497
AU_read method, 658	NNTPDataError method, 508
Wave_read method, 660	POP3_SSL method, 500
getsequences() (Folder method), 583	getwidth() (audio configuration method), 732
getsequencesfilename() (Folder method),	getwin() (in module curses), 295
583	getwindowsversion() (in module sys), 44
getservbyname() (in module socket), 390	getwriter() (in module codecs), 134
getservbyport() (in module socket), 390	getyx() (window method), 301
getsid() (in module os), 240	gid (TarInfo attribute), 424
getsignal() (in module signal), 386	GL (standard module), 744
getsize()	gl (built-in module), 742
Chunk method, 662	glob() (in module glob), 346
in module os.path, 256	glob (standard module), 346, 346
getsizes() (in module imgfile), 744	globals() (in module), 8
getslice() (in module operator), 62	globs (DocTest attribute), 162

gmtime() (in module time), 288	async_chat method, 546
gname (TarInfo attribute), 424	dispatcher method, 544
GNOME, 358	handle_comment()
<pre>gnu_getopt() (in module getopt), 312</pre>	HTMLParser method, 610
Gopher	SGMLParser method, 612
protocol, 481, 499	XMLParser method, 649
<pre>gopher_open() (GopherHandler method), 490</pre>	handle_connect() (dispatcher method), 544
gopher_proxy, 479	handle_data()
GopherError (exception in urllib2), 484	HTMLParser method, 610
GopherHandler (class in urllib2), 485	SGMLParser method, 612
gopherlib (standard module), 499	XMLParser method, 649
got (DocTestFailure attribute), 169	handle_decl()
goto() (in module turtle), 690	HTMLParser method, 611
Graphical User Interface, 673	SGMLParser method, 613
Greenwich Mean Time, 287	handle_doctype() (XMLParser method), 649
grey22grey() (in module imageop), 655	handle_endtag()
grey2grey2() (in module imageop), 654	HTMLParser method, 610
grey2grey4() (in module imageop), 654	SGMLParser method, 612
grey2mono() (in module imageop), 654	XMLParser method, 649
grey42grey() (in module imageop), 655	handle_entityref()
group()	HTMLParser method, 610
MatchObject method, 118	SGMLParser method, 612
NNTPDataError method, 509	handle_error()
groupby() (in module itertools), 219	dispatcher method, 544
groupdict() (MatchObject method), 118	in module SocketServer, 520
groupindex (RegexObject attribute), 117	handle_expt() (dispatcher method), 543
groups () (MatchObject method), 118	handle_image() (HTMLParser method), 615
grp (built-in module), 433	handle_one_request() (BaseHTTPRequest-
gt() (in module operator), 60	Handler method), 522
guess_all_extensions() (in module mime-	handle_pi() (HTMLParser method), 611
types), 586	handle_proc() (XMLParser method), 649
<pre>guess_extension()</pre>	handle_read()
in module mimetypes, 586	async_chat method, 546
MimeTypes method, 587	dispatcher method, 543
guess_type()	handle_request()
in module mimetypes, 585	in module SocketServer, 519
MimeTypes method, 587	SimpleXMLRPCRequestHandler method, 541
GUI, 673	handle_special() (XMLParser method), 649
gzip (standard module), 415	handle_startendtag() (HTMLParser
GzipFile (class in gzip), 415	method), 610
	handle_starttag()
H	HTMLParser method, 610
halfdelay() (in module curses), 296	SGMLParser method, 612
handle()	XMLParser method, 649
method, 366, 372	handle_write()
BaseHTTPRequestHandler method, 522	async_chat method, 546
in module SocketServer, 520	dispatcher method, 543
handle_accept() (dispatcher method), 544	handle_xml() (XMLParser method), 648
handle_authentication_request() (Ab-	handleError()
stractBasicAuthHandler method), 489	method, 372
handle_authentication_request() (Ab-	SocketHandler method, 374
stractDigestAuthHandler method), 489	handler() (in module cgitb), 478
handle_cdata() (XMLParser method), 649	has_colors() (in module curses), 295
handle_charref()	has_data() (Request method), 485
HTMLParser method, 610	has_extn() (SMTP method), 511
SGMLParser method, 612	has_header()
	Request method, 486
XMLParser method, 649	Sniffer method, 605
handle_close()	Similar manage, 000

has_ic() (in module curses), 295	hexbin() (in module binhex), 598
has_il() (in module curses), 295	hexdigest()
has_ipv6 (data in socket), 389	hmac method, 669
has_key()	md5 method, 670
method, 411	sha method, 671
dictionary method, 28	hexdigits (data in string), 105
in module curses, 296	hexlify() (in module binascii), 597
Message method, 555	hexversion (data in sys), 44
has_nonstandard_attr() (Cookie method),	hidden() (method), 311
531	hide() (method), 311
has_option() (SafeConfigParser method), 227	hide_cookie2 (LWPCookieJar attribute), 528
has_section()(SafeConfigParser method), 227	hide_form() (form method), 738
hasattr() (in module), 8	hide_object() (FORMS object method), 740
hasAttribute() (Element method), 629	HierarchyRequestErr (exception in
hasAttributeNS() (Element method), 629	xml.dom), 631
hasAttributes() (Node method), 626	HIGHEST_PROTOCOL (data in pickle), 73
hasChildNodes() (Node method), 626	hline() (window method), 301
hascompare (data in dis), 715	HList (class in Tix), 686
hasconst (data in dis), 715	hls_to_rgb() (in module colorsys), 662
hasFeature() (DOMImplementation method),	hmac (standard module), 669
625	HOME, 102, 256
hasfree (data in dis), 715	HOMEDRIVE, 256
hash() (in module), 8	HOMEPATH, 256
hashopen() (in module bsddb), 411	hosts (netrc attribute), 603
has jabs (data in dis), 715	hotshot (standard module), 462
hasjrel (data in dis), 715	hotshot.stats (standard module), 463
haslocal (data in dis), 715	hour
hasname (data in dis), 715	datetime attribute, 276
have_unicode (data in test.test_support), 183	time attribute, 280
head() (NNTPDataError method), 509	hsv_to_rgb() (in module colorsys), 662
Header (class in email. Header), 565	HTML, 481, 609, 613
header_encode() (Charset method), 568	HtmlDiff (class in difflib), 123
header_encoding (data in email.Charset), 567	htmlentitydefs (standard module), 615
header_offset (ZipInfo attribute), 421	htmllib (standard module), 481, 613
HeaderParseError (exception in email.Errors),	HTMLParseError
569	exception in htmllib, 614
headers	exception in HTMLParser, 610
MIME, 471, 585	HTMLParser
headers	class in htmllib, 549, 614
AddressList attribute, 594	class in HTMLParser, 609
BaseHTTPRequestHandler attribute, 521	standard module, 609
ServerProxy attribute, 538	htonl() (in module socket), 390
heapify() (in module heapq), 210	htons() (in module socket), 390
heapmin() (in module msvcrt), 750	HTTP
heappop() (in module heapq), 210	httplib (standard module), 492
heappush() (in module heapq), 210	protocol, 471, 481, 492, 521
heapq (standard module), 210	http_error_301() (HTTPRedirectHandler
heapreplace() (in module heapq), 210	method), 488
helo() (SMTP method), 511	http_error_302() (HTTPRedirectHandler
help	method), 488
online, 145	http_error_303() (HTTPRedirectHandler
help()	method), 488
in module, 8	http_error_307() (HTTPRedirectHandler
NNTPDataError method, 509	method), 488
herror (exception in socket), 388	http_error_401() (HTTPBasicAuthHandler
hex() (in module), 8	method), 489
hexadecimal	http_error_401() (HTTPDigestAuthHandler
literals, 17	method), 490

http_error_407() (ProxyBasicAuthHandler method), 489	ifilterfalse() (in module itertools), 220 ignorableWhitespace() (ContentHandler
http_error_407() (ProxyDigestAuthHandler	method), 642
method), 490	ignore() (Stats method), 461
http_error_default() (BaseHandler	ignore_errors() (in module codecs), 135
method), 488	IGNORE_EXCEPTION_DETAIL (data in doctest),
http_open() (HTTPHandler method), 490	154
HTTP_PORT (data in httplib), 493	ignore_zeros (TarFile attribute), 424
http_proxy, 479, 491	IGNORECASE (data in re), 115
HTTPBasicAuthHandler (class in urllib2), 485	ihave() (NNTPDataError method), 509
HTTPConnection (class in httplib), 492	ihooks (standard module), 3
HTTPCookieProcessor (class in urllib2), 484	imageop (built-in module), 654
httpd, 521	imap() (in module itertools), 220
HTTPDefaultErrorHandler (class in urllib2),	IMAP4
484	protocol, 501
HTTPDigestAuthHandler (class in urllib2),	IMAP4 (class in imaplib), 502
485	IMAP4. abort (exception in imaplib), 502
HTTPError (exception in urllib2), 484	IMAP4.error (exception in imaplib), 502
HTTPException (exception in httplib), 493	IMAP4. error (exception in maphs), 502 IMAP4. readonly (exception in imaplib), 502
HTTPHandler	IMAP4.1 eadoffly (exception in imapho), 302
class in logging, 377	protocol, 501
class in urllib2, 485	IMAP4_SSL (class in imaplib), 502
httplib (standard module), 492	IMAP4_55L (class in mapho), 302 IMAP4_stream
HTTPPasswordMgr (class in urllib2), 484	protocol, 501
HTTPPasswordMgrWithDefaultRealm	
(class in urllib2), 484	<pre>IMAP4_stream (class in imaplib), 502 imaplib (standard module), 501</pre>
HTTPRedirectHandler (class in urllib2), 484	imgfile (built-in module), 744
HTTPResponse (class in httplib), 492	imghdr (standard module), 663
https_open() (HTTPSHandler method), 490	immedok() (window method), 301
HTTPS_PORT (data in httplib), 493	ImmutableSet (class in sets), 215
HTTPSConnection (class in httplib), 492	imp (built-in module), 3, 89
HTTPServer (class in BaseHTTPServer), 521	import
HTTPSHandler (class in urllib2), 485	statement, 3, 89
hypertext, 613	Import module, 692
hypot() (in module math), 200	ImportError (exception in exceptions), 35
I	ImproperConnectionState (exception in httplib), 493
I (data in re), 115	in
I/O control	operator, 16, 19
buffering, 7, 240, 392	in_table_a1() (Td[(a1())]TJ/222ingprep), 143
POSIX, 437	in_table_b1() (Td[(a1())]TJ/222ingprep), 143
tty, 437	in_table_c11() (Td[(a1())]TJ/222ingprep), 144
UNIX, 439	in_table_c11_c12() (in
ibufcount() (audio device method), 748	144
id()	in_table_c12() (Td[(a1())]TJ/222ingprep), 144
in module, 8	in_table_c21() (Td[(a1())]TJ/222ingprep), 144
TestCase method, 178	in_table_c21_c22() (in
idcok() (window method), 301	144
IDEA	in_table_c22() (Td[(a1())]TJ/222ingprep), 144
cipher, 669	in_table_c3() (Td[(a1())]TJ/222ingprep), 144
ident (data in cd), 734	in_table_c4() (Td[(a1())]TJ/222ingprep), 144
identchars (Cmd attribute), 233	in_table_c5() (Td[(a1())]TJ/222ingprep), 144
Idle, 690	in_table_c6() (Td[(a1())]TJ/222ingprep), 144
idlok() (window method), 301	in_table_c7()(Td[(a1())]TJ/222ingprep), 144
IEEE-754, 54	in_table_c8() (Td[(a1())]TJ/222ingprep), 144
if	in_table_c9()(Td[(a1())]TJ/222ingprep), 144
statement, 15	in_table_d1()(Td[(a1())]TJ/222ingprep), 144
ifilter() (in module itertools), 220	in_table_d2() (Td[(a1())]TJ/222ingprep), 144
, (iii iiioddie iteitooib), 220	., \ L\ \ \/, \ \ \ \ \ \ \ \ \ \ \ \ \ \ \ \

INADDR_* (data in socket), 389	insertln() (window method), 301
inch() (window method), 301	insnstr() (window method), 301
Incomplete (exception in binascii), 597	insort() (in module bisect), 206
IncompleteRead (exception in httplib), 493	<pre>insort_left() (in module bisect), 206</pre>
IncrementalParser (class in	<pre>insort_right() (in module bisect), 206</pre>
xml.sax.xmlreader), 644	inspect (standard module), 64
indent (Example attribute), 163	insstr() (window method), 301
indentation, 693	install()
Independent JPEG Group, 745	in module gettext, 355
index()	NullTranslations method, 356
array method, 213	<pre>install_opener() (in module urllib2), 483</pre>
in module string, 108	instance() (in module new), 100
string method, 21	instancemethod() (in module new), 100
index (data in cd), 734	InstanceType (data in types), 57
index() (list method), 25	instr() (window method), 301
IndexError (exception in exceptions), 35	instream (shlex attribute), 235
indexOf() (in module operator), 62	int()
IndexSizeErr (exception in xml.dom), 631	built-in function, 17
inet_aton() (in module socket), 391	in module, 8
inet_ntoa() (in module socket), 391	Int2AP() (in module imaplib), 502
inet_ntop() (in module socket), 391	integer
inet_pton() (in module socket), 391	division, 17
Inexact (class in decimal), 193	division, long, 17
infile (shlex attribute), 235	literals, 17
Infinity, 7, 108	literals, long, 17
info()	object, 17
method, 366	types, operations on, 18
in module logging, 364	Integrated Development Environment, 690
	-
NullTranslations method, 356	Intel/DVI ADPCM, 651
infolist() (ZipFile method), 419	interact()
InfoSeek Corporation, 455	in module code, 94
ini file, 226	InteractiveConsole method, 95
init()	Telnet method, 515
in module fm, 742	InteractiveConsole (class in code), 94
in module mimetypes, 586	InteractiveInterpreter (class in code), 94
init_builtin() (in module imp), 90	intern() (in module), 15
init_color() (in module curses), 296	internal_attr (ZipInfo attribute), 420
init_frozen() (in module imp), 90	Internaldate2tuple() (in module imaplib),
init_pair() (in module curses), 296	502
inited (data in mimetypes), 586	internalSubset (DocumentType attribute), 628
initial_indent (TextWrapper attribute), 133	Internet, 469
initscr() (in module curses), 296	Internet Config, 479
input()	interpolation, string (%), 23
built-in function, 46	InterpolationDepthError (exception in
in module, 8	ConfigParser), 226
in module fileinput, 229	InterpolationError (exception in Config-
input_charset (data in email.Charset), 567	Parser), 226
input_codec (data in email.Charset), 567	<pre>InterpolationMissingOptionError (ex-</pre>
InputOnly (class in Tix), 687	ception in ConfigParser), 227
InputSource (class in xml.sax.xmlreader), 644	InterpolationSyntaxError (exception in
InputType (data in cStringIO), 131	ConfigParser), 227
insch() (window method), 301	interpreter prompts, 45
insdelln() (window method), 301	<pre>interrupt_main() (in module thread), 397</pre>
<pre>insert()</pre>	intro (Cmd attribute), 233
array method, 213	IntType (data in types), 57
list method, 25	InuseAttributeErr (exception in xml.dom),
insert_text() (in module readline), 426	631
insertBefore() (Node method), 627	inv() (in module operator), 61
, , (· · · · · · · · · · · · · · · · · · ·

Investidance agence (execution in vml dom)	in modulo os 242
InvalidAccessErr (exception in xml.dom), 631	in module os, 242 isblank() (in module curses.ascii), 310
InvalidCharacterErr (exception in	isblk() (TarInfo method), 425
xml.dom), 631	isbuiltin() (in module inspect), 67
InvalidModificationErr (exception in	isCallable() (in module operator), 63
xml.dom), 631	ischr() (TarInfo method), 425
InvalidOperation (class in decimal), 193	isclass() (in module inspect), 67
InvalidStateErr (exception in xml.dom), 631	iscntrl() (in module curses.ascii), 310
Invalidurl (exception in httplib), 493	iscode() (in module inspect), 67
invert() (in module operator), 61	iscomment() (AddressList method), 593
ioctl() (in module fcntl), 439	isctrl() (in module curses.ascii), 310
IOError (exception in exceptions), 35	isDaemon() (Thread method), 405
IP_* (data in socket), 389	isdatadescriptor() (in module inspect), 67
IPPORT_* (data in socket), 389	isdev() (TarInfo method), 425
IPPROTO_* (data in socket), 388	isdigit()
IPV6_* (data in socket), 389	in module curses.ascii, 310
IRIS Font Manager, 741	string method, 21
IRIX	isdir()
threads, 398	in module os.path, 256
is	TarInfo method, 425
operator, 16	isenabled() (in module gc), 47
is not	isEnabledFor() (method), 365
operator, 16	isendwin() (in module curses), 296
is_() (in module operator), 60	ISEOF() (in module token), 711
<pre>is_blocked() (DefaultCookiePolicy method),</pre>	isexpr()
529	AST method, 704
is_builtin() (in module imp), 90	in module parser, 703
IS_CHARACTER_JUNK() (in module difflib), 125	isfifo() (TarInfo method), 425
is_data() (MultiFile method), 590	isfile()
is_empty() (fifo method), 547	in module os.path, 256
is_expired() (Cookie method), 531	TarInfo method, 425
is_frozen() (in module imp), 90	isfirstline() (in module fileinput), 229
is_jython (data in test.test_support), 183	isframe() (in module inspect), 67
IS_LINE_JUNK() (in module difflib), 125	isfunction() (in module inspect), 67
is_linetouched() (window method), 301	isgraph() (in module curses.ascii), 310
<pre>is_multipart() (Message method), 554</pre>	isheader() (AddressList method), 593
is_not() (in module operator), 61	isinstance() (in module), 8
is_not_allowed() (DefaultCookiePolicy	iskeyword() (in module keyword), 711
method), 529	islast() (AddressList method), 593
is_package() (zipimporter method), 92	isleap() (in module calendar), 230
is_resource_enabled() (in module	islice() (in module itertools), 221
test.test_support), 183	islink() (in module os.path), 256
is_tarfile() (in module tarfile), 422	islnk() (TarInfo method), 425
is_unverifiable() (Request method), 486	islower()
is_wintouched() (window method), 301	in module curses.ascii, 310
is_zipfile() (in module zipfile), 418	string method, 21
isabs() (in module os.path), 256	isMappingType() (in module operator), 63
isAlive() (Thread method), 405	ismeta() (in module curses.ascii), 310
isalnum()	ismethod() (in module inspect), 67
in module curses.ascii, 309	ismethoddescriptor() (in module inspect)
string method, 21	67
isalpha()	ismodule() (in module inspect), 67
in module curses.ascii, 310	ismount() (in module os.path), 256
string method, 21	ISNONTERMINAL() (in module token), 711
isascii() (in module curses.ascii), 310	isNumberType() (in module operator), 63
isatty()	isocalendar()
Chunk method, 662	date method, 274
file method, 29	datetime method, 278

isoformat()	java_ver() (in module platform), 383
date method, 274	JFIF, 745
datetime method, 279	<pre>join()</pre>
time method, 280	in module os.path, 256
<pre>isoweekday()</pre>	in module string, 109
date method, 274	string method, 21
datetime method, 278	Thread method, 404
isprint() (in module curses.ascii), 310	joinfields() (in module string), 109
ispunct() (in module curses.ascii), 310	jpeg (built-in module), 745
isqueued() (in module fl), 737	js_output()
<pre>isreadable()</pre>	BaseCookie method, 533
in module pprint, 98	Morsel method, 534
PrettyPrinter method, 98	jumpahead() (in module random), 203
<pre>isrecursive()</pre>	
in module pprint, 98	K
PrettyPrinter method, 98	kbhit() (in module msvcrt), 750
isreg() (TarInfo method), 425	KDEDIR, 470
isReservedKey() (Morsel method), 533	key (Morsel attribute), 533
isroutine() (in module inspect), 67	KeyboardInterrupt (exception in exceptions).
isSameNode() (Node method), 626	35
isSequenceType() (in module operator), 63	KeyError (exception in exceptions), 35
isSet() (Event method), 403	keyname() (in module curses), 296
isspace()	
in module curses.ascii, 310	keypad() (window method), 302
string method, 21	keys()
isstdin() (in module fileinput), 230	method, 411
•	dictionary method, 28
issubclass() (in module), 8	Message method, 555
issuite()	keyword (standard module), 711
AST method, 704	kill() (in module os), 251
in module parser, 703	killchar() (in module curses), 296
issym() (TarInfo method), 425	killpg() (in module os), 251
ISTERMINAL() (in module token), 710	knee (module), 91
istitle() (string method), 21	knownfiles (data in mimetypes), 586
istraceback() (in module inspect), 67	Kuchling, Andrew, 669
isupper()	kwlist (data in keyword), 711
in module curses.ascii, 310	
string method, 21	L
isxdigit() (in module curses.ascii), 310	L (data in re), 115
item()	LabelEntry (class in Tix), 685
NamedNodeMap method, 630	LabelFrame (class in Tix), 685
NodeList method, 627	LambdaType (data in types), 57
itemgetter() (in module operator), 63	LANG, 349, 353, 355
items()	LANGUAGE, 353, 355
dictionary method, 28	language
Message method, 555	C, 17
SafeConfigParser method, 228, 229	large files, 431
itemsize (array attribute), 213	last()
iter() (in module), 9	
IterableUserDict (class in UserDict), 58	method, 412
iterator protocol, 18	dbhash method, 410
iteritems() (dictionary method), 28	NNTPDataError method, 509
iterkeys() (dictionary method), 28	last (MultiFile attribute), 590
itertools (standard module), 217	last_traceback (data in sys), 45
itervalues() (dictionary method), 28	last_type (data in sys), 45
izip() (in module itertools), 221	last_value (data in sys), 45
121P() (III IIIOdule Retwols), 221	lastChild (Node attribute), 626
J	lastcmd (Cmd attribute), 233
	lastgroup (MatchObject attribute), 119
Jansen, Jack, 599	lastindex (MatchObject attribute), 118

lastpart() (MimeWriter method), 588	list()
LC_ALL, 353, 355	IMAP4_stream method, 504
LC_ALL (data in locale), 351	in module, 9
LC_COLLATE (data in locale), 350	NNTPDataError method, 508
LC_CTYPE (data in locale), 350	POP3_SSL method, 500
LC_MESSAGES, 353, 355	TarFile method, 423
LC_MESSAGES (data in locale), 350	list_dialects() (in module csv), 605
LC_MONETARY (data in locale), 350	listallfolders() (MH method), 583
LC_NUMERIC (data in locale), 351	listallsubfolders() (MH method), 583
LC_TIME (data in locale), 350	listdir()
lchown() (in module os), 244	in module dircache, 258
ldexp() (in module math), 199	in module os, 245
ldgettext() (in module gettext), 354	listen()
ldngettext() (in module gettext), 354	dispatcher method, 544
le() (in module operator), 60	in module logging, 379
leapdays() (in module calendar), 230	socket method, 392
leaveok() (window method), 302	listfolders() (MH method), 583
left() (in module turtle), 689	listmessages() (Folder method), 583
left_list (dircmp attribute), 262	ListNoteBook (class in Tix), 687
left_only (dircmp attribute), 262	listsubfolders() (MH method), 583
len()	ListType (data in types), 57
built-in function, 19, 28	literals
in module, 9	complex number, 17
length	floating point, 17
NamedNodeMap attribute, 630	hexadecimal, 17
NodeList attribute, 627	integer, 17
letters (data in string), 105	long integer, 17
level (MultiFile attribute), 590	numeric, 17
lexists() (in module os.path), 255	octal, 17
<pre>lgettext()</pre>	ljust()
GNUTranslations method, 357	in module string, 110
in module gettext, 354	string method, 21
NullTranslations method, 356	LK_LOCK (data in msvcrt), 749
libc_ver() (in module platform), 384	LK_NBLCK (data in msvcrt), 749
library (data in dbm), 435	LK_NBRLCK (data in msvcrt), 749
light-weight processes, 397	LK_RLCK (data in msvcrt), 749
lin2adpcm() (in module audioop), 652	LK_UNLCK (data in msvcrt), 749
lin2adpcm3() (in module audioop), 652	LNAME, 293
lin2lin() (in module audioop), 652	<pre>lngettext()</pre>
lin2ulaw() (in module audioop), 652	GNUTranslations method, 357
line-buffered I/O, 7	in module gettext, 354
linecache (standard module), 71	NullTranslations method, 356
lineno() (in module fileinput), 229	load()
lineno	BaseCookie method, 533
class descriptor attribute, 713	FileCookieJar method, 527
DocTest attribute, 162	in module hotshot.stats, 463
Example attribute, 163	in module marshal, 86
ExpatError attribute, 620	in module pickle, 73
function descriptor attribute, 713	Unpickler method, 75
shlex attribute, 235	load_compiled() (in module imp), 90
LINES, 299	load_dynamic() (in module imp), 90
linesep (data in os), 255	<pre>load_module()</pre>
lineterminator (Dialect attribute), 606	in module imp, 89
link() (in module os), 245	zipimporter method, 92
linkname (TarInfo attribute), 424	<pre>load_source() (in module imp), 91</pre>
list	LoadError (exception in cookielib), 525
object, 19, 25	loads()
type, operations on, 25	in module marshal, 86

in module pickle, 74	logout() (IMAP4_stream method), 504
in module xmlrpclib, 539	LogRecord (class in logging), 378
loadTestsFromModule() (TestLoader	long
method), 179	integer division, 17
loadTestsFromName() (TestLoader method),	integer literals, 17
180	long()
loadTestsFromNames() (TestLoader method),	built-in function, 17, 108
180	in module, 9
loadTestsFromTestCase() (TestLoader	long integer
method), 179	object, 17
local (class in threading), 399	longimagedata() (in module rgbimg), 663
LOCALE (data in re), 115	longname() (in module curses), 296
locale (standard module), 348	longstoimage() (in module rgbimg), 663
localeconv() (in module locale), 349	LongType (data in types), 57
localName	lookup()
Attr attribute, 630	in module codecs, 134
Node attribute, 626	in module unicodedata, 142
locals() (in module), 9	lookup_error() (in module codecs), 134
localtime() (in module time), 288	LookupError (exception in exceptions), 34
Locator (class in xml.sax.xmlreader), 644	loop() (in module asyncore), 543
Lock () (in module threading), 399	lower()
lock()	in module string, 109
in module posixfile, 442	string method, 21
mutex method, 293	lowercase (data in string), 106
lock_held() (in module imp), 89	lseek() (in module os), 242
locked() (lock method), 398	lshift() (in module operator), 61
lockf()	lstat() (in module os), 245
in module fcntl, 440	lstrip()
in module fcntl, 442	in module string, 109
locking() (in module msvcrt), 749	string method, 22
LockType (data in thread), 397	lsub() (IMAP4_stream method), 504
log()	lt() (in module operator), 60
method, 366	Lundh, Fredrik, 745
in module cmath, 201	LWPCookieJar (class in cookielib), 527
in module logging, 364	
in module math, 200	M
log10()	M (data in re), 115
in module cmath, 201	mac_ver() (in module platform), 383
in module math, 200	machine() (in module platform), 382
log_data_time_string() (BaseHTTPRe-	macros (netrc attribute), 603
questHandler method), 523	mailbox (standard module), 580 , 591
log_error() (BaseHTTPRequestHandler	mailcap (standard module), 579
method), 522	Maildir (class in mailbox), 581
log_message() (BaseHTTPRequestHandler	MailmanProxy (class in smtpd), 514
method), 522	<pre>main()</pre>
log_request() (BaseHTTPRequestHandler	in module py_compile, 713
method), 522	in module unittest, 176
logging	major() (in module os), 245
Errors, 362	make_cookies() (CookieJar method), 526
logging (standard module), 362	<pre>make_file() (in module difflib), 123</pre>
login()	make_form() (in module fl), 737
FTP method, 497	make_header() (in module email.Header), 566
IMAP4_stream method, 504	make_msgid() (in module email.Utils), 571
SMTP method, 512	make_parser() (in module xml.sax), 638
login_cram_md5() (IMAP4_stream method),	<pre>make_table() (in module difflib), 123</pre>
504	makedev() (in module os), 245
LOGNAME, 239, 293	makedirs() (in module os), 245
lognormvariate() (in module random), 204	makefile() (socket method), 392

makefolder() (MH method), 583	MB_ICONQUESTION (data in winsound), 755
makeLogRecord() (in module logging), 365	MB_OK (data in winsound), 755
makePickle() (SocketHandler method), 374	md5() (in module md5), 670
makeRecord() (method), 366	md5 (built-in module), 669
makeSocket()	MemoryError (exception in exceptions), 35
DatagramHandler method, 375	MemoryHandler (class in logging), 376
SocketHandler method, 374	Message
maketrans() (in module string), 108	class in email.Message, 553
map() (in module), 9	class in mhlib, 582
<pre>map_table_b2() (in module stringprep), 144</pre>	class in mimetools, 584
map_table_b3() (in module stringprep), 144	class in rfc822, 591
mapcolor() (in module fl), 738	in module mimetools, 522
mapping	message digest, MD5, 669
object, 28	message_from_file() (in module
types, operations on, 28	email.Parser), 561
maps () (in module nis), 446	<pre>message_from_string() (in module</pre>
marshal (built-in module), 85	email.Parser), 561
marshalling	MessageBeep() (in module winsound), 754
objects, 72	MessageClass (BaseHTTPRequestHandler at-
masking	tribute), 522
operations, 18	MessageError (exception in email.Errors), 569
match()	MessageParseError (exception in
in module nis, 446	email.Errors), 569
in module re, 115	meta() (in module curses), 296
RegexObject method, 117	Meter (class in Tix), 686
math (built-in module), 17, 199, 202	method
max()	object, 32
built-in function, 19	methods (class descriptor attribute), 713
Context method, 191	MethodType (data in types), 57
Decimal method, 188	MH (class in mhlib), 582
in module, 9	mhlib (standard module), 582
in module audioop, 652	MHMailbox (class in mailbox), 581
max	microsecond
date attribute, 273	datetime attribute, 276
datetime attribute, 276	time attribute, 280
time attribute, 279	MIME
timedelta attribute, 272	base64 encoding, 595
MAX_INTERPOLATION_DEPTH (data in Config-	content type, 585
Parser), 227	headers, 471, 585
maxarray (Repr attribute), 99	quoted-printable encoding, 598
maxdeque (Repr attribute), 99	<pre>mime_decode_header() (in module mimify),</pre>
maxdict (Repr attribute), 99	588
maxfrozenset (Reprattribute), 99	<pre>mime_encode_header() (in module mimify),</pre>
maxint (data in sys), 45	588
MAXLEN (data in mimify), 588	MIMEAudio (class in email.Generator), 564
maxlevel (Repr attribute), 99	MIMEBase (class in email.Generator), 563
maxlist (Reprattribute), 99	MIMEImage (class in email.Generator), 564
maxlong (Repr attribute), 99	MIMEMessage (class in email.Generator), 564
maxother (Repr attribute), 100	MIMEMultipart (class in email.Generator), 563
maxpp() (in module audioop), 652	MIMENonMultipart (class in email.Generator),
maxset (Repr attribute), 99	563
maxstring (Repr attribute), 99	MIMEText (class in email.Generator), 564
maxtuple (Repr attribute), 99	mimetools (standard module), 479, 584
maxunicode (data in sys), 45	MimeTypes (class in mimetypes), 586
MAXYEAR (data in datetime), 270	mimetypes (standard module), 585
MB_ICONASTERISK (data in winsound), 755	MimeWriter
MB_ICONEXCLAMATION (data in winsound), 755	class in MimeWriter, 587
MB_ICONHAND (data in winsound), 755	standard module, 587

mimify() (in module mimify), 588	date attribute, 273
mimify (standard module), 588	datetime attribute, 276
min()	monthcalendar() (in module calendar), 231
built-in function, 19	monthrange() (in module calendar), 231
Context method, 191	more() (simple_producer method), 547
Decimal method, 188	Morsel (class in Cookie), 533
in module, 9	mouseinterval() (in module curses), 296
min	mousemask() (in module curses), 296
date attribute, 273	move()
datetime attribute, 276	method, 311, 408
time attribute, 279	in module shutil, 347
timedelta attribute, 271	window method, 302
minmax() (in module audioop), 652	movemessage() (Folder method), 584
minor() (in module os), 245	MozillaCookieJar (class in cookielib), 527
minus() (Context method), 191	msftoblock() (CD player method), 735
minute	msftoframe() (in module cd), 733
datetime attribute, 276	msg() (Telnet method), 515
time attribute, 280	msg (data in httplib), 495
MINYEAR (data in datetime), 270	MSG_* (data in socket), 388
mirrored() (in module unicodedata), 142	msvcrt (built-in module), 749
misc_header (Cmd attribute), 233	<pre>mt_interact() (Telnet method), 515</pre>
MissingSectionHeaderError (exception in	mtime() (RobotFileParser method), 603
ConfigParser), 227	mtime (TarInfo attribute), 424
MIXERDEV, 665	mul()
mkd() (FTP method), 499	in module audioop, 652
mkdir() (in module os), 245	in module operator, 61
mkdtemp() (in module tempfile), 339	MultiCall (class in xmlrpclib), 538
mkfifo() (in module os), 245	MultiFile (class in multifile), 589
mknod() (in module os), 245	multifile (standard module), 589
mkstemp() (in module tempfile), 339	MULTILINE (data in re), 115
mktemp() (in module tempfile), 339	MultipartConversionError (exception in
mktime() (in module time), 288	email.Errors), 569
<pre>mktime_tz()</pre>	multiply() (Context method), 191
in module email. Utils, 571	mutable
in module rfc822, 592	sequence types, 25
mmap() (in module mmap), 407	sequence types, operations on, 25
mmap (built-in module), 407	MutableString (class in UserString), 60
MmdfMailbox (class in mailbox), 581	mutex
mod() (in module operator), 61	class in mutex, 293
mode	standard module, 292
file attribute, 31	mvderwin() (window method), 302
TarInfo attribute, 424	mvwin() (window method), 302
modf () (in module math), 199	myrights() (IMAP4_stream method), 504
modified() (RobotFileParser method), 603	N1
module	N
search path, 45, 71, 101	name() (in module unicodedata), 142
module() (in module new), 101	name
module	Attr attribute, 630
class descriptor attribute, 713	class descriptor attribute, 713
function descriptor attribute, 713	Cookie attribute, 530
ModuleFinder (class in modulefinder), 94	data in os, 238
modulefinder (standard module), 93	DocTest attribute, 162
modules (data in sys), 45	DocumentType attribute, 628
ModuleType (data in types), 58	file attribute, 31
MON_1 MON_12 (data in locale), 351	function descriptor attribute, 713
mono2grey() (in module imageop), 654	TarInfo attribute, 424
month() (in module calendar), 231	name2codepoint (data in htmlentitydefs), 615
INCHEST.	

NamedTemporaryFile() (in module tempfile),	NI_* (data in socket), 389
339	nice() (in module os), 251
NameError (exception in exceptions), 35	nis (extension module), 446
namelist() (ZipFile method), 419	NIST, 670
nameprep() (in module encodings.idna), 142	NL (data in tokenize), 711
namespace() (IMAP4_stream method), 504	nl() (in module curses), 297
NamespaceErr (exception in xml.dom), 631	nl_langinfo() (in module locale), 349
namespaces	nlargest() (in module heapq), 211
XML, 650	nlst() (FTP method), 498
namespaceURI (Node attribute), 626	NNTP
NaN, 7, 108	protocol, 506
NannyNag (exception in tabnanny), 712	NNTP (class in nntplib), 507
napms () (in module curses), 296	NNTPDataError (class in nntplib), 508
ndiff() (in module difflib), 124	NNTPError (class in nntplib), 507
ne() (in module operator), 60	nntplib (standard module), 506
neg() (in module operator), 61	NNTPPermanentError (class in nntplib), 507
netrc	NNTPProtocolError (class in nntplib), 507
class in netrc, 602	NNTPReplyError (class in nntplib), 507
standard module, 602	NNTPTemporaryError (class in nntplib), 507
NetrcParseError (exception in netrc), 602	nocbreak() (in module curses), 297
netscape (LWPCookieJar attribute), 528	NoDataAllowedErr (exception in xml.dom),
Network News Transfer Protocol, 506	631
new()	Node (class in compiler.ast), 724
in module hmac, 669	node() (in module platform), 382
in module md5, 670	nodelay() (window method), 302
in module sha, 671	nodeName (Node attribute), 626
new (built-in module), 100	nodeType (Node attribute), 626
<pre>new_alignment() (writer method), 551</pre>	nodeValue (Node attribute), 626
new_font() (writer method), 551	NODISC (data in cd), 734
new_margin() (writer method), 552	noecho() (in module curses), 297
new_module() (in module imp), 89	NOEXPR (data in locale), 351
new_panel() (in module curses.panel), 311	nofill (HTMLParser attribute), 614
new_spacing() (writer method), 552	nok_builtin_names (RExec attribute), 697
<pre>new_styles() (writer method), 552</pre>	noload() (Unpickler method), 75
newconfig() (in module al), 731	NoModificationAllowedErr (exception in
newgroups() (NNTPDataError method), 508	xml.dom), 631
newlines (file attribute), 31	nonblock() (audio device method), 666
newnews() (NNTPDataError method), 508	None
newpad() (in module curses), 296	Built-in object, 15
newwin() (in module curses), 297	data in, 38
next()	NoneType (data in types), 57
method, 412	nonl() (in module curses), 297
csv reader method, 606	noop()
dbhash method, 410	IMAP4_stream method, 504
file method, 29	POP3_SSL method, 501
iterator method, 18	NoOptionError (exception in ConfigParser), 226
mailbox method, 582	noqiflush() (in module curses), 297
MultiFile method, 590	noraw() (in module curses), 297
NNTPDataError method, 509	normalize()
TarFile method, 423	Context method, 191
nextfile() (in module fileinput), 230	Decimal method, 188
nextkey() (in module gdbm), 436	in module locale, 350
nextpart() (MimeWriter method), 588	in module unicodedata, 143
nextSibling (Node attribute), 626	Node method, 627
ngettext()	NORMALIZE_WHITESPACE (data in doctest), 154
GNUTranslations method, 357	normalvariate() (in module random), 204
in module gettext, 354	normcase() (in module os.path), 257
NullTranslations method, 356	normpath() (in module os.path), 257

NoSectionError (exception in ConfigParser),	O_RSYNC (data in os), 243
226	O_SEQUENTIAL (data in os), 243
not	O_SHORT_LIVED (data in os), 243
operator, 16	O_SYNC (data in os), 243
not in	O_TEMPORARY (data in os), 243
operator, 16, 19	O_TEXT (data in os), 243
not_() (in module operator), 60	O_TRUNC (data in os), 243
NotANumber (exception in fpformat), 130	O_WRONLY (data in os), 243
notationDecl() (DTDHandler method), 642	object
NotationDeclHandler()(xmlparser method),	Boolean, 17
619	buffer, 19
notations (DocumentType attribute), 628	code, 32, 86
NotConnected (exception in httplib), 493	complex number, 17
NoteBook (class in Tix), 687	dictionary, 28
NotFoundErr (exception in xml.dom), 631	file, 29
notify() (Condition method), 402	floating point, 17
notifyAll() (Condition method), 402	integer, 17
notimeout() (window method), 302	list, 19, 25
NotImplemented (data in), 39	long integer, 17
NotImplementedError (exception in excep-	mapping, 28
tions), 35	method, 32
NotStandaloneHandler() (xmlparser	numeric, 16, 17
method), 619	sequence, 19
NotSupportedErr (exception in xml.dom), 631	set, 26
noutrefresh() (window method), 302	socket, 387
now() (datetime method), 275	string, 19
NSIG (data in signal), 386	traceback, 42, 69
nsmallest() (in module heapq), 211	tuple, 19
NTEventLogHandler (class in logging), 375	type, 13
ntohl() (in module socket), 390	Unicode, 19
ntohs() (in module socket), 390	xrange, 19, 25
ntransfercmd() (FTP method), 498	object() (in module), 9
NullFormatter (class in formatter), 551	objects
NullWriter (class in formatter), 552	comparing, 16
numeric (class in formatter), 332	flattening, 72
conversions, 17	marshalling, 72
	•
literals, 17	persistent, 72
object, 16, 17	pickling, 72
types, operations on, 17	serializing, 72
numeric() (in module unicodedata), 142	obufcount () (audio device method), 667, 748
Numerical Python, 12	obuffree() (audio device method), 667
nurbscurve() (in module gl), 743	oct() (in module), 9
nurbssurface() (in module gl), 743	octal
nvarray() (in module gl), 743	literals, 17
^	octdigits (data in string), 106
O	offset (ExpatError attribute), 620
O_APPEND (data in os), 243	OK (data in curses), 304
O_BINARY (data in os), 243	ok_builtin_modules (RExec attribute), 697
O_CREAT (data in os), 243	ok_file_types (RExec attribute), 698
O_DSYNC (data in os), 243	ok_path (RExec attribute), 698
O_EXCL (data in os), 243	ok_posix_names (RExec attribute), 698
O_NDELAY (data in os), 243	ok_sys_names (RExec attribute), 698
O_NOCTTY (data in os), 243	onecmd() (Cmd method), 232
O_NOINHERIT (data in os), 243	open()
O_NONBLOCK (data in os), 243	IMAP4_stream method, 504
O_RANDOM (data in os), 243	in module, 9
O_RDONLY (data in os), 243	in module aifc, 655
O_RDWR (data in os), 243	in module anydbm, 409
5 - 12 (and ii 65), 2 15	•

in module cd, 733	numeric types, 17
in module codecs, 135	sequence types, 19, 25
in module dbhash, 409	operator
in module dbm, 435	==, 16
in module dl, 434	and, 15, 16
in module dumbdbm, 413	comparison, 16
in module gdbm, 436	in, 16, 19
in module gzip, 416	is, 16
in module os, 242	is not, 16
in module ossaudiodev, 665	not, 16
in module posixfile, 442	not in, 16, 19
in module shelve, 82	or, 15, 16
in module sunau, 657	operator (built-in module), 60
in module sunaudiodev, 747	opname (data in dis), 715
in module tarfile, 421	OptionMenu (class in Tix), 686
in module wave, 659	options() (SafeConfigParser method), 227
in module webbrowser, 470, 471	options (Example attribute), 163
OpenerDirector method, 486	optionxform() (SafeConfigParser method), 228
TarFile method, 423	optparse (standard module), 314
Telnet method, 515	or
Template method, 441	operator, 15, 16
URLopener method, 482	or_() (in module operator), 61
open_new() (in module webbrowser), 470, 471	ord() (in module), 10
open_osfhandle() (in module msvcrt), 749	ordered_attributes (xmlparser attribute),
open_unknown() (URLopener method), 482	617
opendir() (in module direache), 258	os (standard module), 29, 237 , 431
OpenerDirector (class in urllib2), 484	os.path (standard module), 255
openfolder() (MH method), 583	OSError (exception in exceptions), 35
openfp()	ossaudiodev (built-in module), 664
in module sunau, 657	OSSAudioError (exception in ossaudiodev), 665
in module wave, 659	output()
OpenGL, 744	BaseCookie method, 533
OpenKey() (in module _winreg), 752	
	Morsel method, 534
OpenKeyEx() (in module _winreg), 752	output_charset() (NullTranslations method), 356
openlog() (in module syslog), 446	
openmessage() (Message method), 584	output_charset (data in email.Charset), 567
openmixer() (in module ossaudiodev), 665	output_codec (data in email.Charset), 567
openport() (in module al), 731	output_difference() (OutputChecker
openpty()	method), 166
in module os, 242	OutputChecker (class in doctest), 165
in module pty, 438	OutputString() (Morsel method), 534
operation	OutputType (data in cStringIO), 131
concatenation, 19	Overflow (class in decimal), 193
extended slice, 19	OverflowError (exception in exceptions), 35
repetition, 19	overlay() (window method), 302
slice, 19	Overmars, Mark, 736
subscript, 19	overwrite() (window method), 302
operations	Р
bit-string, 18	P
Boolean, 15, 16	P_DETACH (data in os), 252
masking, 18	P_NOWAIT (data in os), 252
shifting, 18	P_NOWAITO (data in os), 252
operations on	P_OVERLAY (data in os), 252
dictionary type, 28	P_WAIT (data in os), 252
integer types, 18	pack() (in module struct), 120
list type, 25	pack_array() (Packer method), 601
mapping types, 28	pack_bytes() (Packer method), 600
mutable sequence types, 25	pack_double() (Packer method), 600
- -	

pack_farray() (Packer method), 601 pack_float() (Packer method), 600	in module xml.dom.pulldom, 637 in module xml.sax, 638
pack_fopaque() (Packer method), 600 pack_fstring() (Packer method), 600	parsing Python source code, 701 URL, 516
pack_list() (Packer method), 600	
<pre>pack_opaque() (Packer method), 600 pack_string() (Packer method), 600</pre>	ParsingError (exception in ConfigParser), 227 partial() (IMAP4_stream method), 504
package, 101	pass_() (POP3_SSL method), 500
Packer (class in xdrlib), 600	PATH, 249, 251, 255, 476, 477
packing	path
binary data, 120	configuration file, 101
packing (widgets), 679	module search, 45, 71, 101
PAGER, 451	operations, 255
pair_content() (in module curses), 297	path
pair_number() (in module curses), 297	BaseHTTPRequestHandler attribute, 521
PanedWindow (class in Tix), 687	Cookie attribute, 530
pardir (data in os), 254	data in os, 238
parent (BaseHandler attribute), 487	data in sys, 45
parentNode (Node attribute), 626	Path browser, 691
paretovariate() (in module random), 204	<pre>path_return_ok() (CookiePolicy method),</pre>
Parse() (xmlparser method), 616	528
parse()	pathconf() (in module os), 245
DocTestParser method, 164	pathconf_names (data in os), 245
in module cgi, 474	pathname2url() (in module urllib), 480
in module compiler, 723	pathsep (data in os), 255
in module xml.dom.minidom, 633	pattern (RegexObject attribute), 117
in module xml.dom.pulldom, 637	pause() (in module signal), 386
in module xml.sax, 638	PAUSED (data in cd), 734
Parser method, 560	Pdb (class in pdb), 449
RobotFileParser method, 603	pdb (standard module), 449
XMLReader method, 645	Pen (class in turtle), 690
parse_and_bind() (in module readline), 426	PendingDeprecationWarning (exception in
parse_header() (in module cgi), 475 parse_multipart() (in module cgi), 475	exceptions), 37 Performance, 464
parse_qs() (in module cgi), 473	persistence, 72
parse_qs() (in module cgi), 474 parse_qsl() (in module cgi), 475	persistent
parseaddr()	objects, 72
in module email.Utils, 570	pformat()
in module rfc822, 592	in module pprint, 97
parsedate()	PrettyPrinter method, 98
in module email. Utils, 570	PGP, 669
in module rfc822, 592	pi
parsedate_tz()	data in cmath, 202
in module email. Utils, 571	data in math, 200
in module rfc822, 592	pick() (in module gl), 743
ParseFile() (xmlparser method), 616	pickle() (in module copy_reg), 82
parseFile() (in module compiler), 723	pickle (standard module), 72 , 81, 82, 85, 86
ParseFlags() (in module imaplib), 502	PickleError (exception in pickle), 74
parseframe() (CD parser method), 736	Pickler (class in pickle), 74
Parser (class in email.Parser), 560	pickletools (standard module), 721
parser (built-in module), 701	pickling
ParserCreate() (in module xml.parsers.expat),	objects, 72
616	PicklingError (exception in pickle), 74
ParserError (exception in parser), 704	pid
parsesequence() (Folder method), 583	Popen4 attribute, 269
parsestr() (Parser method), 560	Popen attribute, 265
<pre>parseString()</pre>	PIL (the Python Imaging Library), 745
in module xml.dom.minidom, 633	pipe() (in module os), 242

pipes (standard module), 441	PopupMenu (class in Tix), 686
PKG_DIRECTORY (data in imp), 90	port (Cookie attribute), 530
pkgutil (standard module), 93	port_specified (Cookie attribute), 531
platform() (in module platform), 382	PortableUnixMailbox (class in mailbox), 581
platform	pos() (in module operator), 61
data in sys, 45	pos (MatchObject attribute), 118
standard module, 382	POSIX
play() (CD player method), 735	file object, 442
playabs() (CD player method), 735	I/O control, 437
PLAYING (data in cd), 734	threads, 397
PlaySound() (in module winsound), 754	posix
playtrack() (CD player method), 735	built-in module, 431
playtrackabs() (CD player method), 735	TarFile attribute, 423
plock() (in module os), 251	posixfile (built-in module), 442
plus() (Context method), 191	post()
pm() (in module pdb), 450	audio device method, 667
pnum (data in cd), 734	NNTPDataError method, 509
poll()	<pre>post_mortem() (in module pdb), 450</pre>
method, 397	postcmd() (Cmd method), 232
in module select, 396	postloop() (Cmd method), 233
Popen4 method, 268	pow()
Popen method, 264	in module, 10
pop()	in module math, 200
method, 207	in module operator, 61
array method, 213	power() (Context method), 191
dictionary method, 28	<pre>pprint()</pre>
fifo method, 547	in module pprint, 97
list method, 25	PrettyPrinter method, 98
MultiFile method, 590	pprint (standard module), 97
POP3	prcal() (in module calendar), 231
protocol, 499	preamble (data in email.Message), 558
POP3 (class in poplib), 500	precmd() (Cmd method), 232
POP3_SSL (class in poplib), 500	prefix
pop_alignment() (formatter method), 550	Attr attribute, 630
pop_font() (formatter method), 551	data in sys, 45
pop_margin() (formatter method), 551	Node attribute, 626
pop_source() (shlex method), 234	preloop() (Cmd method), 232
pop_style() (formatter method), 551	preorder() (ASTVisitor method), 729
Popen (class in subprocess), 263	<pre>prepare_input_source() (in module</pre>
popen()	xml.sax.saxutils), 644
in module os, 240	prepend() (Template method), 441
in module os, 396	Pretty Good Privacy, 669
in module platform, 383	PrettyPrinter (class in pprint), 97
popen2()	preventremoval() (CD player method), 735
in module os, 241	<pre>previous()</pre>
in module popen2, 268	method, 412
popen2 (standard module), 268	dbhash method, 410
Popen3 (class in popen2), 268	previousSibling (Node attribute), 626
popen3()	print
in module os, 241	statement, 15
in module popen2, 268	<pre>print_callees() (Stats method), 460</pre>
Popen4 (class in popen2), 268	<pre>print_callers() (Stats method), 460</pre>
popen4()	<pre>print_directory() (in module cgi), 475</pre>
in module os, 241	print_environ() (in module cgi), 475
in module popen2, 268	<pre>print_environ_usage() (in module cgi), 475</pre>
popitem() (dictionary method), 28	<pre>print_exc()</pre>
popleft() (method), 207	in module traceback, 70
poplib (standard module), 499	Timer method, 464

print_exception() (in module traceback), 70	Telnet, 514
<pre>print_form() (in module cgi), 475 print_last() (in module traceback), 70</pre>	PROTOCOL_VERSION (IMAP4_stream attribute), 506
print_stack() (in module traceback), 70	protocol_version (BaseHTTPRequestHand-
print_stats() (Stats method), 460	ler attribute), 522
print_tb() (in module traceback), 70	proxy() (in module weakref), 50
printable (data in string), 106	proxyauth() (IMAP4_stream method), 504
printdir() (ZipFile method), 419	ProxyBasicAuthHandler (class in urllib2),
printf-style formatting, 23	485
prmonth() (in module calendar), 231	ProxyDigestAuthHandler (class in urllib2),
process	485
group, 239	ProxyHandler (class in urllib2), 484
id, 239	ProxyType (data in weakref), 51
id of parent, 239	ProxyType (data in weaker), 51 ProxyTypes (data in weaker), 51
killing, 251	prstr() (in module fm), 742
signalling, 251	ps1 (data in sys), 45
process_message() (SMTPServer method),	ps2 (data in sys), 45 ps2 (data in sys), 45
513	pstats (standard module), 459
process_request() (in module SocketServer),	pthreads, 397
520	ptime (data in cd), 734
processes, light-weight, 397	pty (standard module), 242, 438
processingInstruction() (ContentHandler	publicId (DocumentType attribute), 627
method), 642	PullDOM (class in xml.dom.pulldom), 637
ProcessingInstructionHandler() (xml-	punctuation (data in string), 106
	PureProxy (class in smtpd), 514
parser method), 618 processor() (in module platform), 382	push()
processor () (in module platform), 382	async_chat method, 546
•	
Profile (class in hotshot), 462	fifo method, 547 InteractiveConsole method, 95
profile (standard module), 458	
profile function, 46, 399	MultiFile method, 590
profiler, 46	push_alignment() (formatter method), 550
profiling, deterministic, 455	push_font() (formatter method), 551
prompt (Cmd attribute), 233	push_margin() (formatter method), 551
prompt_user_passwd() (FancyURLopener	push_source() (shlex method), 234
method), 482	<pre>push_style() (formatter method), 551 push_token() (shlex method), 234</pre>
prompts, interpreter, 45	push_with_producer() (async_chat method),
propagate (data in logging), 365 property() (in module), 10	546
property_declaration_handler (data in	put () (Queue method), 407
xml.sax.handler), 640	put_nowait() (Queue method), 407
property_dom_node (data in xml.sax.handler), 640	<pre>putch() (in module msvcrt), 750 putenv() (in module os), 239</pre>
property_lexical_handler (data in	putheader() (HTTPResponse method), 495
xml.sax.handler), 640	putp() (in module curses), 297
property_xml_string (data in	putrequest() (HTTPResponse method), 495
xml.sax.handler), 640	putsequences() (Folder method), 584
	putwin() (window method), 302
protocol CGI, 471	pwd() (FTP method), 499
FTP, 481, 496	pwd () (111 method), 439 pwd (built-in module), 256, 432
Gopher, 481, 499	pwlcurve() (in module gl), 743
HTTP, 471, 481, 492, 521	py_compile (standard module), 713
IMAP4, 501	PY_COMPILED (data in imp), 90
IMAP4_SSL, 501	PY_FROZEN (data in imp), 90
IMAP4_SSL, 301 IMAP4_stream, 501	PY_RESOURCE (data in imp), 90
iterator, 18	PY_SOURCE (data in imp), 90 PY_SOURCE (data in imp), 90
NNTP, 506	pyclbr (standard module), 712
POP3, 499	PyCompileError (exception in py_compile),
SMTP, 510	713
517111, 510	/13

pydoc (standard module), 145 pyexpat (built-in module), 615 PyOpenGL, 744 Python Editor, 690 Python Enhancement Proposals PEP 0205, 51 PEP 0273, 92 PEP 0302, 92 PEP 236, 4	QUOTE_NONNUMERIC (data in csv), 605 quote_plus() (in module urllib), 480 quoteattr() (in module xml.sax.saxutils), 643 quotechar (Dialect attribute), 606 quoted-printable encoding, 598 quotes (shlex attribute), 235 quoting (Dialect attribute), 606
PEP 282, 365	R
PEP 292, 106	r_eval() (RExec method), 696
PEP 305, 604	r_exec() (RExec method), 696
Python Imaging Library, 745	r_execfile() (RExec method), 697
python_build() (in module platform), 382	r_import() (RExec method), 697
python_compiler() (in module platform), 382	R_OK (data in os), 243
PYTHON_DOM, 624	r_open() (RExec method), 697
python_version() (in module platform), 382	r_reload() (RExec method), 697
python_version_tuple() (in module platform), 382	r_unload() (RExec method), 697
PYTHONDOCS, 146	radians()
PYTHONPATH, 45, 476, 758	in module math, 200 in module turtle, 689
PYTHONSTARTUP, 102, 427, 429	RADIXCHAR (data in locale), 351
PYTHONY2K, 286, 287	raise
PyZipFile (class in zipfile), 418	statement, 34
	randint()
Q	in module random, 203
qdevice() (in module fl), 737	in module whrandom, 205
qenter() (in module fl), 737	random()
qiflush() (in module curses), 297	in module random, 204
qread() (in module fl), 737	in module whrandom, 205
qreset() (in module fl), 737	random (standard module), 202
qsize() (Queue method), 406	randrange() (in module random), 203
qtest() (in module fl), 737	range() (in module), 10 ratecv() (in module audioop), 652
quantize() Context method, 192	ratio() (SequenceMatcher method), 127
Decimal method, 189	raw() (in module curses), 297
QueryInfoKey() (in module _winreg), 752	raw_input()
queryparams() (in module al), 731	built-in function, 46
QueryValue() (in module _winreg), 752	in module, 10
QueryValueEx() (in module _winreg), 752	InteractiveConsole method, 95
Queue	RawConfigParser (class in ConfigParser), 226
class in Queue, 406	RawPen (class in turtle), 690
standard module, 406	re
<pre>quick_ratio() (SequenceMatcher method),</pre>	MatchObject attribute, 119
127	standard module, 25, 105, 110 , 346
quit()	read()
FTP method, 499	method, 394, 408
NNTPDataError method, 510	array method, 213 audio device method, 665, 748
POP3_SSL method, 501 SMTP method, 512	BZ2File method, 417
quopri (standard module), 598	Chunk method, 662
quote()	file method, 29
in module email. Utils, 570	HTTPResponse method, 495
in module rfc822, 592	IMAP4_stream method, 504
in module urllib, 480	in module imgfile, 745
QUOTE_ALL (data in csv), 605	in module os, 242
QUOTE_MINIMAL (data in csv), 605	MimeTypes method, 587
QUOTE_NONE (data in csv), 605	MultiFile method, 590

RobotFileParser method, 603	rectangle() (in module curses.textpad), 307
SafeConfigParser method, 227	recv()
StreamReader method, 138	dispatcher method, 544
ZipFile method, 419	socket method, 392
read_all() (Telnet method), 514	recvfrom() (socket method), 393
read_byte() (method), 408	redirect_request() (HTTPRedirectHandler
read_eager() (Telnet method), 515	method), 488
read_history_file() (in module readline),	redisplay() (in module readline), 427
426	redraw_form() (form method), 738
read_init_file() (in module readline), 426	redraw_object() (FORMS object method),
read_lazy() (Telnet method), 515	740
read_mime_types() (in module mimetypes),	redrawln() (window method), 302
586	redrawwin() (window method), 302
read_sb_data() (Telnet method), 515	reduce() (in module), 11
read_some() (Telnet method), 515	ref (class in weakref), 50
read_token() (shlex method), 234	ReferenceError
read_until() (Telnet method), 514	exception in exceptions, 35
read_very_eager() (Telnet method), 515	exception in weakref, 51
read_very_lazy() (Telnet method), 515	ReferenceType (data in weakref), 51
readable()	refilemessages() (Folder method), 584
async_chat method, 546	refill_buffer() (async_chat method), 546
dispatcher method, 544	refresh() (window method), 302
readda() (CD player method), 735	register()
reader() (in module csv), 604	method, 396
ReadError (exception in tarfile), 422	in module atexit, 55
readfp()	in module codecs, 133
MimeTypes method, 587	in module webbrowser, 470
SafeConfigParser method, 228	register_dialect() (in module csv), 604
readframes()	register_error() (in module codecs), 134
aifc method, 656	register_function()
AU_read method, 658	SimpleXMLRPCRequestHandler method, 541
Wave_read method, 660	SimpleXMLRPCServer method, 540
readline()	register_instance()
method, 408	SimpleXMLRPCRequestHandler method, 541
BZ2File method, 417	SimpleXMLRPCServer method, 540
file method, 30	register_introspection_functions()
IMAP4_stream method, 504	(SimpleXMLRPCRequestHandler
MultiFile method, 589	
	method), 540, 541
StreamReader method, 138	register_multicall_functions() (Sim-
readline (built-in module), 426	pleXMLRPCRequestHandler method),
readlines()	540, 541
BZ2File method, 417	register_optionflag() (in module doctest), 156
file method, 30	
MultiFile method, 589	registerDOMImplementation() (in module
StreamReader method, 138	xml.dom), 624
readlink() (in module os), 246	RegLoadKey() (in module _winreg), 751
readmodule() (in module pyclbr), 712	relative
readmodule_ex() (in module pyclbr), 712	URL, 516
readsamps() (audio port method), 732	release()
readscaled() (in module imgfile), 745	method, 372
READY (data in cd), 734	Condition method, 401
Real Media File Format, 661	in module platform, 383
real_quick_ratio() (SequenceMatcher	lock method, 398
method), 127	Semaphore method, 402
realpath() (in module os.path), 257	Timer method, 400, 401
reason (data in httplib), 495	release_lock() (in module imp), 90
reccontrols() (mixer device method), 668	reload()
recent () (IMAP4_stream method), 504	built-in function, 45, 89, 91

```
in module, 11
remainder() (Context method), 192
remainder_near()
    Context method, 192
    Decimal method, 189
remove()
    array method, 214
    in module os, 246
    list method, 25
remove_history_item() (in module read-
        line), 427
remove_option() (SafeConfigParser method),
        228
remove_section()(SafeConfigParser method),
        228
removeAttribute() (Element method), 629
removeAttributeNode() (Element method),
removeAttributeNS() (Element method), 629
removecallback() (CD parser method), 736
removeChild() (Node method), 627
removedirs() (in module os), 246
removeFilter() (method), 366, 372
removeHandler() (method), 366
removemessages() (Folder method), 584
rename()
    FTP method, 499
    IMAP4_stream method, 504
    in module os, 246
renames () (in module os), 246
reorganize() (in module gdbm), 436
repeat()
    in module itertools, 221
    in module operator, 62
    Timer method, 464
repetition
    operation, 19
replace()
    method, 311
    date method, 274
    datetime method, 277
    in module string, 110
    string method, 22
    time method, 280
replace_errors() (in module codecs), 135
replace_header() (Message method), 556
replace_history_item() (in module read-
        line), 427
replace_whitespace (TextWrapper attribute),
replaceChild() (Node method), 627
ReplacePackage() (in module modulefinder),
        94
report()
    dircmp method, 262
    ModuleFinder method, 94
REPORT_CDIFF (data in doctest), 155
```

```
report_failure() (DocTestRunner method),
        165
report_full_closure() (dircmp method),
        262
REPORT_NDIFF (data in doctest), 155
REPORT_ONLY_FIRST_FAILURE
                                 (data
                                        in
        doctest), 155
report_partial_closure()
                                   (dircmp
        method), 262
report_start() (DocTestRunner method), 165
report_success() (DocTestRunner method),
REPORT_UDIFF (data in doctest), 155
report_unbalanced()
                              (SGMLParser
        method), 613
report_
```

datetime attribute, 276
time attribute, 279
timedelta attribute, 272
resolveEntity() (EntityResolver method), 643
resource (built-in module), 443
ResourceDenied (exception in
test.test_support), 183
response() (IMAP4_stream method), 504
ResponseNotReady (exception in httplib), 493
responses (BaseHTTPRequestHandler attribute), 522
restore() (in module difflib), 125
retr() (POP3_SSL method), 501
retrbinary() (FTP method), 498
retrieve() (URLopener method), 482
retrlines() (FTP method), 498
return_ok() (CookiePolicy method), 528
returncode (Popen attribute), 265
returns_unicode (xmlparser attribute), 617
reverse()
array method, 214
in module audioop, 653
-
list method, 25
reverse_order() (Stats method), 460
reversed() (in module), 12
revert() (FileCookieJar method), 527
rewind()
aifc method, 656
AU_read method, 658
Wave_read method, 660
rewindbody() (AddressList method), 593
RExec (class in rexec), 696
rexec (standard module), 3, 695
RFC
RFC 1014, 600
RFC 1321, 669
RFC 1521, 596, 598, 599
RFC 1522, 599
RFC 1522, 599 RFC 1524, 580
RFC 1725, 499
RFC 1730, 501
RFC 1738, 517
RFC 1766, 349, 350
RFC 1808, 517
RFC 1832, 600
RFC 1866, 613
RFC 1869, 510, 511
RFC 1894, 574
RFC 2045, 553, 556, 557, 564
RFC 2046, 553, 564
RFC 2047, 553, 564, 565
RFC 2060, 501, 505
RFC 2068, 532
RFC 2104, 669
RFC 2109, 524, 526, 532, 533
RFC 2231, 553, 557, 564, 571
RFC 2396, 517

```
RFC 2553, 387
    RFC 2616, 481, 488
    RFC 2774, 494
    RFC 2817, 494
    RFC 2821, 553
    RFC 2822, 289, 513, 553, 555, 560, 562, 564,
         565, 569–571, 591–593
    RFC 2964, 526
    RFC 2965, 484, 486, 524, 526
    RFC 3229, 494
    RFC 3454, 143
    RFC 3490, 141, 142
    RFC 3492, 141
    RFC 3548, 595
    RFC 821, 510, 511
    RFC 822, 226, 289, 357, 495, 512, 513, 564,
        591
    RFC 854, 514
    RFC 959, 496
    RFC 977, 506
rfc2965 (LWPCookieJar attribute), 528
rfc822 (standard module), 584, rexec (RaseHTTPRequest249eJar
                                lintmmdsh32950,6488
```

rms() (in module audioop), 653	S_IFMT() (in module stat), 259
rmtree() (in module shutil), 347	S_IMODE() (in module stat), 259
rnopen() (in module bsddb), 411	s_import() (RExec method), 697
RobotFileParser (class in robotparser), 603	S_ISBLK() (in module stat), 258
robotparser (standard module), 603	S_ISCHR() (in module stat), 258
robots.txt, 603	S_ISDIR() (in module stat), 258
rotate() (method), 207	S_ISFIFO() (in module stat), 258
RotatingFileHandler (class in logging), 373	S_ISLNK() (in module stat), 258
round() (in module), 12	S_ISREG() (in module stat), 258
Rounded (class in decimal), 193	
	S_ISSOCK() (in module stat), 259
rpop() (POP3_SSL method), 500	s_reload() (RExec method), 697
rset() (POP3_SSL method), 501	s_unload() (RExec method), 697
rshift() (in module operator), 61	safe_substitute() (Template method), 106
rsplit()	SafeConfigParser (class in ConfigParser), 226
in module string, 109	saferepr() (in module pprint), 98
string method, 22	same_files (dircmp attribute), 263
rstrip()	same_quantum()
in module string, 109	Context method, 192
string method, 22	Decimal method, 189
RTLD_LAZY (data in dl), 434	<pre>samefile() (in module os.path), 257</pre>
RTLD_NOW (data in dl), 434	sameopenfile() (in module os.path), 257
ruler (Cmd attribute), 233	samestat() (in module os.path), 257
run()	sample() (in module random), 203
DocTestRunner method, 165	save() (FileCookieJar method), 527
in module pdb, 450	<pre>save_bgn() (HTMLParser method), 615</pre>
in module profile, 458	<pre>save_end() (HTMLParser method), 615</pre>
Profile method, 463	SaveKey() (in module _winreg), 752
scheduler method, 292	SAX2DOM (class in xml.dom.pulldom), 637
TestCase method, 177	SAXException (exception in xml.sax), 638
TestSuite method, 178	SAXNotRecognizedException (exception in
Thread method, 404	xml.sax), 638
Run script, 692	SAXNotSupportedException (exception in
run_docstring_examples() (in module	xml.sax), 638
doctest), 159	SAXParseException (exception in xml.sax),
run_script() (ModuleFinder method), 94	638
run_suite() (in module test.test_support), 183	scale() (in module imageop), 654
run_unittest() (in module test.test_support),	scalefont() (in module fm), 742
183	scanf() (in module re), 119
runcall()	sched (standard module), 291
in module pdb, 450	scheduler (class in sched), 291
Profile method, 463	sci() (in module fpformat), 130
runcode () (InteractiveConsole method), 95	script_from_examples() (in module
runctx()	doctest), 167
in module profile, 459	scroll() (window method), 303
Profile method, 463	ScrolledText (standard module), 689
runeval() (in module pdb), 450	scrollok() (window method), 303
runsource() (InteractiveConsole method), 94	search
	path, module, 45, 71, 101
RuntimeError (exception in exceptions), 36	± 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1 1
RuntimeWarning (exception in exceptions), 37	search()
RUSAGE_BOTH (data in resource), 446	IMAP4_stream method, 504
RUSAGE_CHILDREN (data in resource), 446	in module re, 115
RUSAGE_SELF (data in resource), 445	RegexObject method, 117
S	SEARCH_ERROR (data in imp), 90
S	second
S (data in re), 115	datetime attribute, 276
s_eval() (RExec method), 697	time attribute, 280
s_exec() (RExec method), 697	section_divider() (MultiFile method), 590
s_execfile() (RExec method), 697	sections() (SafeConfigParser method), 227

secure (Cookie attribute), 530	types, mutable, 25
Secure Hash Algorithm, 670	types, operations on, 19, 25
security	types, operations on mutable, 25
CGI, 475	sequence2ast() (in module parser), 702
seed()	sequenceIncludes() (in module operator), 62
in module random, 203	SequenceMatcher (class in difflib), 122, 126
in module whrandom, 205	SerialCookie (class in Cookie), 532
whrandom method, 205	serializing
seek()	objects, 72
method, 408	<pre>serve_forever() (in module SocketServer),</pre>
BZ2File method, 417	519
CD player method, 735	server
Chunk method, 662	WWW, 471, 521
file method, 30	<pre>server_activate() (in module SocketServer),</pre>
MultiFile method, 590	520
SEEK_CUR (data in posixfile), 442	server_address (data in SocketServer), 519
SEEK_END (data in posixfile), 442	server_bind() (in module SocketServer), 520
SEEK_SET (data in posixfile), 442	server_version
seekblock() (CD player method), 735	BaseHTTPRequestHandler attribute, 521
seektrack() (CD player method), 735	SimpleHTTPRequestHandler attribute, 523
Select (class in Tix), 686	ServerProxy (class in xmlrpclib), 536
select()	Set (class in sets), 215
IMAP4_stream method, 504	set
in module gl, 743	object, 26
in module select, 396	set()
select (built-in module), 396	Event method, 403
Semaphore() (in module threading), 399	in module , 12
Semaphore (class in threading), 402	mixer device method, 668
	Morsel method, 533
semaphores, binary, 397	
send()	SafeConfigParser method, 228, 229
DatagramHandler method, 375	set_allowed_domains() (DefaultCookiePol-
dispatcher method, 544	icy method), 529
HTTPResponse method, 495	set_blocked_domains() (DefaultCookiePol-
IMAP4_stream method, 505	icy method), 529
socket method, 393	set_boundary() (Message method), 558
SocketHandler method, 375	<pre>set_call_back() (FORMS object method),</pre>
send_error() (BaseHTTPRequestHandler	740
method), 522	set_charset() (Message method), 554
send_flowing_data() (writer method), 552	set_completer() (in module readline), 427
send_header() (BaseHTTPRequestHandler	<pre>set_completer_delims() (in module read-</pre>
method), 522	line), 427
send_hor_rule() (writer method), 552	set_cookie() (CookieJar method), 526
send_label_data() (writer method), 552	<pre>set_cookie_if_ok() (CookieJar method), 526</pre>
send_line_break() (writer method), 552	set_debug() (in module gc), 47
send_literal_data() (writer method), 552	set_debuglevel()
send_paragraph() (writer method), 552	FTP method, 497
send_query() (in module gopherlib), 499	HTTPResponse method, 495
send_response() (BaseHTTPRequestHandler	NNTPDataError method, 508
method), 522	POP3_SSL method, 500
send_selector() (in module gopherlib), 499	SMTP method, 511
sendall() (socket method), 393	Telnet method, 515
sendcmd() (FTP method), 498	<pre>set_default_type() (Message method), 556</pre>
sendmail()(SMTP method), 512	<pre>set_event_call_back() (in module fl), 737</pre>
sendto() (socket method), 393	<pre>set_form_position() (form method), 738</pre>
sep (data in os), 254	<pre>set_graphics_mode() (in module fl), 737</pre>
sequence	<pre>set_history_length() (in module readline),</pre>
iteration, 18	426
object, 19	<pre>set_location() (method), 411</pre>

<pre>set_nonstandard_attr() (Cookie method), 531</pre>	setContentHandler() (XMLReader method), 645
set_ok() (CookiePolicy method), 528	setcontext()
<pre>set_option_negotiation_callback()</pre>	in module decimal, 189
(Telnet method), 516	MH method, 583
set_output_charset() (NullTranslations	setcurrent() (Folder method), 583
method), 356	setDaemon() (Thread method), 405
<pre>set_param() (Message method), 557</pre>	setdefault() (dictionary method), 28
set_pasv() (FTP method), 498	setdefaultencoding() (in module sys), 45
<pre>set_payload() (Message method), 554</pre>	setdefaulttimeout() (in module socket),
set_policy() (CookieJar method), 526	391
set_position() (Unpacker method), 601	setdlopenflags() (in module sys), 46
set_pre_input_hook() (in module readline),	setDocumentLocator() (ContentHandler
427	method), 641
set_proxy() (Request method), 486	setDTDHandler() (XMLReader method), 645
set_recsrc() (mixer device method), 668	setegid() (in module os), 239
set_seq1() (SequenceMatcher method), 126	setEncoding() (InputSource method), 646
set_seq2() (SequenceMatcher method), 126	setEntityResolver() (XMLReader method),
set_seqs() (SequenceMatcher method), 126	645
set_server_documentation() (DocXML-	setErrorHandler() (XMLReader method),
RPCRequestHandler method), 542	645
set_server_name() (DocXMLRPCRe-	seteuid() (in module os), 239
questHandler method), 542	setFeature() (XMLReader method), 646
set_server_title() (DocXMLRPCRe-	setfillpoint() (audio port method), 733
questHandler method), 542	setfirstweekday() (in module calendar), 230
set_spacing() (formatter method), 551	setfloatmax() (audio configuration method),
set_spacing() (in module readline),	732
427	setfmt() (audio device method), 666
set_terminator() (async_chat method), 546	setfont() (in module fm), 742
set_threshold() (in module gc), 48	setFormatter() (method), 372
set_trace() (in module pdb), 450	setframerate()
	aifc method, 656
<pre>set_type() (Message method), 557 set_unittest_reportflags() (in module</pre>	AU_write method, 659
doctest), 161	Wave_write method, 661
set_unixfrom() (Message method), 554	setgid() (in module os), 239
set_url() (RobotFileParser method), 603	setgroups() (in module os), 239
set_userptr() (method), 311	setinfo() (audio device method), 748
setacl() (IMAP4_stream method), 505	setitem() (in module operator), 62
setattr() (in module), 12	setlast() (Folder method), 583
setAttribute() (Element method), 629	setLevel() (method), 365, 372
setAttributeNode() (Element method), 629	setliteral()
setAttributeNodeNS() (Element method),	SGMLParser method, 612
629	XMLParser method, 648
setAttributeNS() (Element method), 629	setLocale() (XMLReader method), 645
SetBase() (xmlparser method), 616	setlocale() (in module locale), 348
setblocking() (socket method), 393	setLoggerClass() (in module logging), 365
setByteStream() (InputSource method), 647	setlogmask() (in module syslog), 446
setcbreak() (in module tty), 438	setmark() (aifc method), 656
setchannels() (audio configuration method), 732	setMaxConns() (CacheFTPHandler method), 490
setCharacterStream() (InputSource	setmode() (in module msvcrt), 749
method), 647	setName() (Thread method), 405
setcheckinterval() (in module sys), 45	setnchannels()
setcomptype()	aifc method, 656
aifc method, 656	AU_write method, 659
AU_write method, 659	Wave_write method, 660
Wave_write method, 661	setnframes()
setconfig() (audio port method), 733	aifc method, 656

AU_write method, 659	SetValueEx() (in module _winreg), 753
Wave_write method, 661	setwidth() (audio configuration method), 732
setnomoretags()	SGML, 611
SGMLParser method, 612	sgmllib (standard module), 611, 613
XMLParser method, 648	SGMLParseError (exception in sgmllib), 611
setoption() (in module jpeg), 745	SGMLParser
setparameters() (audio device method), 667	class in sgmllib, 611
setparams()	in module sgmllib, 613
aifc method, 656	sha (built-in module), 670
AU_write method, 659	Shelf (class in shelve), 83
in module al, 732	shelve (standard module), 82, 86
Wave_write method, 661	shifting
setpath() (in module fm), 742	operations, 18
setpgid() (in module os), 239	shlex
setpgrp() (in module os), 239	class in shlex, 233
setpos()	standard module, 233
aifc method, 656	shortDescription() (TestCase method), 178
AU_read method, 658	shouldFlush()
Wave_read method, 660	BufferingHandler method, 376
setprofile()	MemoryHandler method, 377
in module sys, 46	show() (method), 312
in module threading, 399	show_choice() (in module fl), 737
setProperty() (XMLReader method), 646	show_file_selector() (in module fl), 737
setPublicId() (InputSource method), 646	show_form() (form method), 738
setqueuesize() (audio configuration method),	show_input() (in module fl), 737
732	show_message() (in module fl), 737
setquota() (IMAP4_stream method), 505	show_object() (FORMS object method), 740
setraw() (in module tty), 438	show_question() (in module fl), 737
setrecursionlimit() (in module sys), 46	showsyntaxerror() (InteractiveConsole
setregid() (in module os), 240	method), 95
setreuid() (in module os), 240	showtraceback() (InteractiveConsole method),
setrlimit() (in module resource), 444	95
sets (standard module), 214	showwarning() (in module warnings), 88
setsampfmt() (audio configuration method),	shuffle() (in module random), 203
732	shutdown()
setsampwidth()	IMAP4_stream method, 505
aifc method, 656	in module logging, 365
AU_write method, 659	socket method, 393
Wave_write method, 661	shutil (standard module), 347
setscrreg() (window method), 303	SIG* (data in signal), 386
setsid() (in module os), 240	SIG_DFL (data in signal), 386
setslice() (in module operator), 62	SIG_IGN (data in signal), 386
setsockopt() (socket method), 393	signal() (in module signal), 386
setstate() (in module random), 203	signal (built-in module), 385, 398
setSystemId() (InputSource method), 646	Simple Mail Transfer Protocol, 510
setsyx() (in module curses), 298	simple_producer (class in asynchat), 547
setTarget() (MemoryHandler method), 377	SimpleCookie (class in Cookie), 532
setTimeout() (CacheFTPHandler method), 490	SimpleHTTPRequestHandler (class in Sim-
settimeout() (socket method), 393	pleHTTPServer), 523
settrace()	SimpleHTTPServer (standard module), 521,
in module sys, 46	523
in module threading, 399	SimpleXMLRPCRequestHandler (class in
settscdump() (in module sys), 46	SimpleXMLRPCServer), 540
setuid() (in module os), 240	SimpleXMLRPCServer
setUp() (TestCase method), 177	class in SimpleXMLRPCServer, 539
setup() (in module SocketServer), 520	standard module, 539
setupterm() (in module curses), 298	sin()
SetValue() (in module _winreg), 753	in module cmath, 202

in module math, 200	sniff() (Sniffer method), 605
sinh()	Sniffer (class in csv), 605
in module cmath, 202	SO_* (data in socket), 388
in module math, 200	SOCK_DGRAM (data in socket), 388
site (standard module), 101	SOCK_RAW (data in socket), 388
site-packages	SOCK_RDM (data in socket), 388
directory, 101	SOCK_SEQPACKET (data in socket), 388
site-python	SOCK_STREAM (data in socket), 388
directory, 101	socket
sitecustomize (module), 102	object, 387
size()	socket()
method, 408	IMAP4_stream method, 505
FTP method, 499	in module socket, 390
size (TarInfo attribute), 424	socket
sizeofimage() (in module rgbimg), 663	built-in module, 29, 387 , 469
skip() (Chunk method), 662	data in SocketServer, 519
skipinitialspace (Dialect attribute), 606	socket() (in module socket), 396
skippedEntity() (ContentHandler method),	socket_type (data in SocketServer), 520
642	SocketHandler (class in logging), 374
slave() (NNTPDataError method), 509	socketpair() (in module socket), 390
sleep() (in module time), 288	SocketServer (standard module), 518
slice	SocketType (data in socket), 391
assignment, 25	softspace (file attribute), 31
operation, 19	SOL_* (data in socket), 388
slice()	SOMAXCONN (data in socket), 388
built-in function, 58, 721	sort()
in module , 12	IMAP4_stream method, 505
SliceType (data in types), 58	list method, 25
SmartCookie (class in Cookie), 532	sort_stats() (Stats method), 459
SMTP	sorted() (in module), 12
protocol, 510	sortTestMethodsUsing (TestLoader at-
SMTP (class in smtplib), 510	tribute), 180
SMTPConnectError (exception in smtplib), 511	Source Every least ribute 162
smtpd (standard module), 513 SMTPDataError (exception in smtplib), 511	Example attribute, 163
SMTPException (exception in smtplib), 510	shlex attribute, 235 sourcehook() (shlex method), 234
SMTPHAndler (class in logging), 376	span() (MatchObject method), 118
SMTPHeloError (exception in smtplib), 511	spam() (Matchobject method), 118 spawn() (in module pty), 439
smtplib (standard module), 510	spawn () (in module os), 439
SMTPRecipientsRefused (exception in smt-	spawnle() (in module os), 251
plib), 510	spawnlp() (in module os), 251
SMTPResponseException (exception in smt-	spawnlpe() (in module os), 251
plib), 510	spawnv() (in module os), 251
SMTPSenderRefused (exception in smtplib),	spawnve() (in module os), 251
510	spawnvp() (in module os), 251
SMTPServer (class in smtpd), 513	spawnvpe() (in module os), 251
SMTPServerDisconnected (exception in smt-	specified_attributes (xmlparser attribute),
plib), 510	617
SND_ALIAS (data in winsound), 754	speed () (audio device method), 666
SND_ASYNC (data in winsound), 755	split()
SND_FILENAME (data in winsound), 754	in module os.path, 257
SND_LOOP (data in winsound), 755	in module re, 115
SND_MEMORY (data in winsound), 755	in module shlex, 233
SND_NODEFAULT (data in winsound), 755	in module string, 109
SND_NOSTOP (data in winsound), 755	RegexObject method, 117
SND_NOWAIT (data in winsound), 755	string method, 22
SND_PURGE (data in winsound), 755	splitdrive() (in module os.path), 257
sndhdr (standard module), 664	splitext() (in module os.path), 257

splitfields() (in module string), 109 splitlines() (string method), 22	startPrefixMapping() (ContentHandler method), 641
splitunc() (in module os.path), 257	startswith() (string method), 23
sprintf-style formatting, 23	startTest() (TestResult method), 179
sqrt()	starttls()(SMTP method), 512
Context method, 192	stat()
Decimal method, 189	in module os, 246
in module cmath, 202	in module statcache, 260
in module math, 200	NNTPDataError method, 509
ssl()	POP3_SSL method, 500
IMAP4_stream method, 506	stat (standard module), 247, 258
in module socket, 390	stat_float_times() (in module os), 247
ST_ATIME (data in stat), 259	statcache (standard module), 260
ST_CTIME (data in stat), 259	statement
ST_DEV (data in stat), 259	assert,34
ST_GID (data in stat), 259	del, 25, 28
ST_INO (data in stat), 259	except, 34
ST_MODE (data in stat), 259	exec, 32
ST_MTIME (data in stat), 259	if,15
ST_NLINK (data in stat), 259	import, 3, 89
ST_SIZE (data in stat), 259	print, 15
ST_UID (data in stat), 259	raise,34
stack() (in module inspect), 69	try, 34
stack viewer, 692	while, 15
stackable	staticmethod() (in module), 12
streams, 133	Stats (class in pstats), 459
standard_b64decode() (in module base64),	status() (IMAP4_stream method), 505
595	status (data in httplib), 495
standard_b64encode() (in module base64),	statvfs() (in module os), 247
595	statvfs (standard module), 247, 261
StandardError (exception in exceptions), 34	StdButtonBox (class in Tix), 686
standend() (window method), 303	stderr
standout() (window method), 303	data in sys, 46
starmap() (in module itertools), 221	Popen attribute, 265
start()	stdin
MatchObject method, 118	data in sys, 46
Profile method, 463	Popen attribute, 265
Thread method, 404	stdout
start_color() (in module curses), 298	data in sys, 46
start_new_thread() (in module thread), 397	Popen attribute, 265
startbody() (MimeWriter method), 588	Stein, Greg, 724
StartCdataSectionHandler() (xmlparser	stereocontrols() (mixer device method), 668
method), 619	STILL (data in cd), 734
StartDoctypeDeclHandler() (xmlparser	stop()
method), 618	CD player method, 735
startDocument() (ContentHandler method),	Profile method, 463
641	TestResult method, 179
startElement() (ContentHandler method), 641	StopIteration (exception in exceptions), 36
StartElementHandler()(xmlparser method),	stopListening() (in module logging), 379
618	stopTest() (TestResult method), 179
startElementNS() (ContentHandler method),	storbinary() (FTP method), 498
642	store() (IMAP4_stream method), 505
startfile() (in module os), 252	storlines() (FTP method), 498
startmultipartbody() (MimeWriter	str()
method), 588	in module, 12
StartNamespaceDeclHandler() (xmlparser	in module locale, 350
method), 619	strcoll() (in module locale), 350
	StreamError (exception in tarfile), 422

StreamHandler (class in logging), 373 StreamReader (class in codecs), 137	Subnormal (class in decimal), 193 subpad() (window method), 303
StreamReaderWriter (class in codecs), 138	subprocess (standard module), 263
StreamRecoder (class in codecs), 139	<pre>subscribe() (IMAP4_stream method), 505</pre>
streams, 133	subscript
stackable, 133	assignment, 25
StreamWriter (class in codecs), 136	operation, 19
strerror() (in module os), 240	subsequent_indent (TextWrapper attribute),
strftime()	133
date method, 274	substitute() (Template method), 106
datetime method, 279	subtract() (Context method), 192
in module time, 288	subwin() (window method), 303
time method, 280	suffix_map (data in mimetypes), 586, 587
strict_domain (LWPCookieJar attribute), 529	suite() (in module parser), 702
strict_errors() (in module codecs), 135	suiteClass (TestLoader attribute), 180
strict_ns_domain (LWPCookieJar attribute),	sum() (in module), 13
530	summarize() (DocTestRunner method), 165
strict_ns_set_initial_dollar (LWP-	sunau (standard module), 657
CookieJar attribute), 530	SUNAUDIODEV (standard module), 747, 748
strict_ns_set_path (LWPCookieJar at-	sunaudiodev (built-in module), 747 , 748
tribute), 530	super() (in module), 13
strict_ns_unverifiable (LWPCookieJar	super (class descriptor attribute), 713
attribute), 529	supports_unicode_filenames (data in
strict_rfc2965_unverifiable (LWP-	os.path), 257
CookieJar attribute), 529	swapcase()
string	in module string, 109
documentation, 705	string method, 23
formatting, 23	sym() (method), 435
-	
interpolation, 23	sym_name (data in symbol), 710
object, 19	symbol (standard module), 710
string	symbol table, 3
MatchObject attribute, 119	symlink() (in module os), 247
standard module, 25, 105 , 350, 352	sync()
StringIO	method, 412, 413
class in StringIO, 131	audio device method, 666
standard module, 131	dbhash method, 410
stringprep (standard module), 143	in module gdbm, 437
StringType (data in types), 57	Shelf method, 82
StringTypes (data in types), 58	syncdown() (window method), 303
strip()	syncok() (window method), 303
in module string, 109	syncup() (window method), 303
string method, 23	<pre>syntax_error() (XMLParser method), 649</pre>
strip_dirs() (Stats method), 459	SyntaxErr (exception in xml.dom), 631
stripspaces (Textbox attribute), 308	SyntaxError (exception in exceptions), 36
strptime() (in module time), 289	SyntaxWarning (exception in exceptions), 37
struct (built-in module), 120, 393	sys (built-in module), 41
struct_time (data in time), 290	sys_version (BaseHTTPRequestHandler
structures	attribute), 522
C, 120	sysconf() (in module os), 254
strxfrm() (in module locale), 350	sysconf_names (data in os), 254
sub()	syslog() (in module syslog), 446
in module operator, 61	syslog (built-in module), 446
in module re, 116	SysLogHandler (class in logging), 375
RegexObject method, 117	system()
subdirs (dircmp attribute), 263	in module os, 252
subn()	in module platform, 383
in module re, 116	system.listMethods() (ServerProxy
RegexObject method, 117	method), 537
regeroojeet memoa, 117	memou, sor

<pre>system.methodHelp() (ServerProxy method),</pre>	TEMP, 340
537	tempdir (data in tempfile), 340
system.methodSignature() (ServerProxy	tempfile (standard module), 338
method), 537	Template
system_alias() (in module platform), 383	class in pipes, 441
SystemError (exception in exceptions), 36	class in string, 106
SystemExit (exception in exceptions), 36	template
systemId (DocumentType attribute), 628	data in tempfile, 340
SystemRandom (class in random), 204	string attribute, 107
Т	temporary
	temporary file, 338
T_FMT (data in locale), 351	file name, 338
T_FMT_AMPM (data in locale), 351	TemporaryFile() (in module tempfile), 339
tabnanny (standard module), 712	termattrs() (in module curses), 298
tabular	termios (built-in module), 437
data, 604 tagName (Element attribute), 629	termname() (in module curses), 298
takewhile() (in module itertools), 222	test()
tan()	in module cgi, 475
in module cmath, 202	mutex method, 293
in module math, 200	test
tanh()	DocTestFailure attribute, 169
in module cmath, 202	standard module, 180
in module math, 200	UnexpectedException attribute, 169
TAR_GZIPPED (data in tarfile), 422	test.test_support (standard module), 182
TAR_PLAIN (data in tarfile), 422	testandset() (mutex method), 293
TarError (exception in tarfile), 422	TestCase (class in unittest), 176
TarFile (class in tarfile), 422	TestFailed (exception in test.test_support), 182
tarfile (standard module), 421	testfile() (in module doctest), 158
TarFileCompat (class in tarfile), 422	TESTFN (data in test.test_support), 183
target (ProcessingInstruction attribute), 630	TestLoader (class in unittest), 176
TarInfo (class in tarfile), 424	testMethodPrefix (TestLoader attribute), 180
tb_lineno() (in module traceback), 71	testmod() (in module doctest), 158
tcdrain() (in module termios), 437	tests (data in imghdr), 664
tcflow() (in module termios), 437	TestSkipped (exception in test.test_support)
tcflush() (in module termios), 437	183
tcgetattr() (in module termios), 437	testsource() (in module doctest), 168
tcgetpgrp() (in module os), 242	testsRun (TestResult attribute), 179
Tcl() (in module Tkinter), 674	TestSuite (class in unittest), 176
TCP_* (data in socket), 389	testzip() (ZipFile method), 419
tcsendbreak() (in module termios), 437	Textbox (class in curses.textpad), 307
tcsetattr() (in module termios), 437	textdomain() (in module gettext), 354
tcsetpgrp() (in module os), 242	TextTestRunner (class in unittest), 176
tearDown() (TestCase method), 177	textwrap (standard module), 131
tee() (in module itertools), 222	TextWrapper (class in textwrap), 132
tell()	THOUSEP (data in locale), 351
method, 408	Thread (class in threading), 399, 404 thread() (IMAP4_stream method), 505
aifc method, 656, 657	· · · · · · · · · · · · · · · · · · ·
AU_read method, 658	thread (built-in module), 397 threading (standard module), 398
AU_write method, 659	threads
BZ2File method, 417	IRIX, 398
Chunk method, 662	POSIX, 397
file method, 30	tie() (in module fl), 737
MultiFile method, 590	tigetflag() (in module curses), 298
Wave_read method, 660 Wave_write method, 661	tigetnum() (in module curses), 298
Telnet (class in telnetlib), 514	tigetstr() (in module curses), 298
telnet lib (standard module) 514	time()

datetime method, 277	to_sci_string() (Context method), 192
in module time, 290	to_splittable() (Charset method), 567
time	ToASCII() (in module encodings.idna), 142
built-in module, 286	tobuf () (TarInfo method), 424
class in datetime, 270, 279	tochild (Popen4 attribute), 269
Time2Internaldate() (in module imaplib),	today()
502	date method, 273
timedelta (class in datetime), 270, 271	datetime method, 275
TimedRotatingFileHandler (class in log-	tofile() (array method), 214
ging), 374	togglepause() (CD player method), 735
timegm() (in module calendar), 231	tok_name (data in token), 710
timeit()(Timer method), 465	token
timeit (standard module), 464	shlex attribute, 235
timeout() (window method), 303	standard module, 710
timeout (exception in socket), 388	tokeneater() (in module tabnanny), 712
Timer	tokenize() (in module tokenize), 711
class in threading, 399, 405	tokenize (standard module), 711
class in timeit, 464	tolist()
times() (in module os), 253	array method, 214
timetuple()	AST method, 704
date method, 274 datetime method, 278	tomono() (in module audioop), 653 toordinal()
timetz() (datetime method), 277	date method, 274
timezone (data in time), 290	date inclind, 274 datetime method, 278
title() (string method), 23	top()
Tix, 684	method, 312
Tix	POP3_SSL method, 501
class in Tix, 684	top_panel() (in module curses.panel), 311
standard module, 684	toprettyxml() (Node method), 635
tix_addbitmapdir() (tixCommand method),	tostereo() (in module audioop), 653
688	tostring() (array method), 214
tix_cget() (tixCommand method), 688	totuple()(AST method),704
tix_configure() (tixCommand method), 688	touchline() (window method), 303
tix_filedialog() (tixCommand method), 688	touchwin() (window method), 303
tix_getbitmap() (tixCommand method), 688	ToUnicode() (in module encodings.idna), 142
tix_getimage() (tixCommand method), 688	tounicode() (array method), 214
TIX_LIBRARY, 685	tovideo() (in module imageop), 654
tix_option_get() (tixCommand method), 688	toxml() (Node method), 635
<pre>tix_resetoptions() (tixCommand method),</pre>	tparm() (in module curses), 298
688	trace() (in module inspect), 69
tixCommand (class in Tix), 687	trace function, 46, 399
Tk, 673	traceback
Tk (class in Tkinter), 674	object, 42, 69
Tk Option Data Types, 682	traceback (standard module), 69
Tkinter, 673	tracebacklimit (data in sys), 46
Tkinter (standard module), 673	tracebacks
TList (class in Tix), 687	in CGI scripts, 478
TMP, 247, 340	TracebackType (data in types), 58
TMP_MAX (data in os), 248	tracer() (in module turtle), 689
TMPDIR, 247, 340	transfercmd() (FTP method), 498
tmpfile() (in module os), 240	translate()
tmpnam() (in module os), 247	in module string, 109
to_eng_string()	string method, 23
Context method, 192	translate_references() (XMLParser
Decimal method, 189	method), 648
to_integral()	translation() (in module gettext), 355
Context method, 192	Tree (class in Tix), 687
Decimal method, 189	True, 15, 33

True (data in), 38	tzname (data in time), 290
true, 15	tzset() (in module time), 290
truediv() (in module operator), 62	1.1
truncate() (file method), 30	U
truth	U (data in re), 115
value, 15	u-LAW, 651, 656, 664, 747
truth() (in module operator), 60	ugettext()
try	GNUTranslations method, 357
statement, 34	NullTranslations method, 356
ttob()	uid() (IMAP4_stream method), 505
in module imgfile, 745	uid (TarInfo attribute), 424
in module rgbimg, 663	uidl() (POP3_SSL method), 501
tty	ulaw2lin() (in module audioop), 653
I/O control, 437	umask() (in module os), 240
tty (standard module), 438	uname()
ttyname() (in module os), 242	in module os, 240
tuple	in module platform, 383
object, 19	uname (TarInfo attribute), 424
tuple() (in module), 13	UnboundLocalError (exception in exceptions),
tuple2ast() (in module parser), 702	36
TupleType (data in types), 57	UnboundMethodType (data in types), 57
turnoff_sigfpe() (in module fpectl), 54	unbuffered I/O, 7
turnon_sigfpe() (in module fpectl), 54	UNC paths
turtle (standard module), 689	and os.makedirs(), 245
Tutt, Bill, 724	unconsumed_tail(attribute), 415
type	unctrl()
Boolean, 4	in module curses, 298
object, 13	in module curses.ascii, 310
operations on dictionary, 28	Underflow (class in decimal), 193
operations on list, 25	undoc_header (Cmd attribute), 233
type()	unescape() (in module xml.sax.saxutils), 643
built-in function, 32, 57	UnexpectedException (exception in doctest),
in module, 13	169
type (TarInfo attribute), 424	unfreeze_form() (form method), 738
typeahead() (in module curses), 298	unfreeze_object() (FORMS object method),
typecode (array attribute), 213	740
typed_subpart_iterator() (in module	ungetch()
email.Iterators), 572	in module curses, 298
TypeError (exception in exceptions), 36	in module msvcrt, 750
types	ungetmouse() (in module curses), 298
built-in, 3, 15	ungettext()
mutable sequence, 25	GNUTranslations method, 358
operations on integer, 18	NullTranslations method, 356
operations on mapping, 28	unhexlify() (in module binascii), 597
operations on mutable sequence, 25	unichr() (in module), 13
operations on numeric, 17	UNICODE (data in re), 115
operations on sequence, 19, 25	Unicode, 133, 142
types (standard module), 32, 56	database, 142
types_map (data in mimetypes), 586, 587	object, 19
TypeType (data in types), 57	•
TZ, 290, 291, 758	unicode() (in module), 13
tzinfo	unicodedata (standard module), 142
class in datetime, 270	UnicodeDecodeError (exception in exceptions) 36
datetime attribute, 276	tions), 36
time attribute, 280	UnicodeEncodeError (exception in excep-
tzname()	tions), 36
datetime method, 278	UnicodeError (exception in exceptions), 36
time method, 280, 282	UnicodeTranslateError (exception in excep-
unic method, 200, 202	tions), 36

UnicodeType (data in types), 57	unquote()
unidata_version (data in unicodedata), 143	in module email.Utils, 570
unified_diff() (in module difflib), 125	in module rfc822, 592
uniform()	in module urllib, 480
in module random, 204	unquote_plus() (in module urllib), 480
in module whrandom, 205	unregister() (method), 397
UnimplementedFileMode (exception in	unregister_dialect() (in module csv), 605
httplib), 493	unsetenv() (in module os), 240
unittest (standard module), 170	unsubscribe() (IMAP4_stream method), 506
UNIX	untouchwin() (window method), 303
file control, 439	unused_data (attribute), 414
I/O control, 439	up () (in module turtle), 689
unixfrom (AddressList attribute), 594	update()
UnixMailbox (class in mailbox), 580	dictionary method, 28
unknown_charref()	hmac method, 669
SGMLParser method, 613	md5 method, 670
XMLParser method, 650	sha method, 671
unknown_endtag()	update_panels() (in module curses.panel), 311
SGMLParser method, 613	upper()
XMLParser method, 650	in module string, 110
unknown_entityref()	string method, 23
SGMLParser method, 613	uppercase (data in string), 106
XMLParser method, 650	urandom() (in module os), 255
unknown_open()	URL, 471, 478, 516, 521, 603
BaseHandler method, 487	parsing, 516
HTTPErrorProcessor method, 491	relative, 516
UnknownHandler method, 490	url (ServerProxy attribute), 538
unknown_starttag()	url2pathname() (in module urllib), 481
SGMLParser method, 613	urlcleanup() (in module urllib), 480
XMLParser method, 650	urldefrag() (in module urlparse), 517
UnknownHandler (class in urllib2), 485	urlencode() (in module urllib), 480
UnknownProtocol (exception in httplib), 493	URLError (exception in urllib2), 484
UnknownTransferEncoding (exception in	urljoin() (in module urlparse), 517
httplib), 493	urllib (standard module), 478, 492
unlink()	urllib2 (standard module), 483
in module os, 248	urlopen()
Node method, 634	in module urllib, 478
unlock() (mutex method), 293	in module urllib2, 483
unmimify() (in module mimify), 588	URLopener (class in urllib), 481
unpack() (in module struct), 120	urlparse() (in module urlparse), 516
unpack_array() (Unpacker method), 602	urlparse (standard module), 482, 516
unpack_bytes() (Unpacker method), 602	urlretrieve() (in module urllib), 479
unpack_double() (Unpacker method), 601	urlsafe_b64decode() (in module base64),
unpack_farray() (Unpacker method), 602	595
unpack_float() (Unpacker method), 601	<pre>urlsafe_b64encode() (in module base64),</pre>
unpack_fopaque() (Unpacker method), 601	595
unpack_fstring() (Unpacker method), 601	urlsplit() (in module urlparse), 517
unpack_list() (Unpacker method), 602	urlunparse() (in module urlparse), 517
unpack_opaque() (Unpacker method), 601	urlunsplit() (in module urlparse), 517
unpack_string() (Unpacker method), 601	<pre>use_default_colors() (in module curses),</pre>
Unpacker (class in xdrlib), 600	299
unparsedEntityDecl() (DTDHandler	use_env() (in module curses), 298
method), 643	use_rawinput (Cmd attribute), 233
UnparsedEntityDeclHandler() (xmlparser	UseForeignDTD() (xmlparser method), 617
method), 619	USER, 293
Unpickler (class in pickle), 75	user
UnpicklingError (exception in pickle), 74	configuration file, 102
unqdevice() (in module fl), 737	effective id, 239

id, 239	version_info (data in sys), 47
id, setting, 240	version_string() (BaseHTTPRequestHand-
user() (POP3_SSL method), 500	ler method), 523
user (standard module), 102	vline() (window method), 303
UserDict	vnarray() (in module gl), 743
class in UserDict, 58	voidcmd() (FTP method), 498
standard module, 58	volume (ZipInfo attribute), 420
UserList	vonmisesvariate() (in module random), 204
class in UserList, 59	,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,
standard module, 59	W
USERNAME, 293	W_OK (data in os), 243
userptr() (method), 312	wait()
UserString	Condition method, 402
class in UserString, 59	Event method, 403
standard module, 59	in module os, 253
UserWarning (exception in exceptions), 37	Popen4 method, 269
UTC, 287	Popen method, 265
utcfromtimestamp() (datetime method), 276	waitpid() (in module os), 253
utcnow() (datetime method), 275	walk()
utcoffset()	in module compiler, 723
datetime method, 278	in module compiler.visitor, 729
time method, 280, 281	in module os, 248
utctimetuple() (datetime method), 278	in module os, 240
utime() (in module os), 248	Message method, 558
uu (standard module), 596, 599	want (Example attribute), 163
(warn () (in module warnings), 88
V	warn_explicit() (in module warnings), 88
value	Warning (exception in exceptions), 37
truth, 15	warning()
value	method, 366
Cookie attribute, 530	ErrorHandler method, 643
Morsel attribute, 533	in module logging, 364
value_decode() (BaseCookie method), 533	warnings, 86
value_encode() (BaseCookie method), 533	warnings, 60 warnings (standard module), 86
ValueError (exception in exceptions), 37	warnoptions (data in sys), 47
values	wasSuccessful() (TestResult method), 179
Boolean, 33	wave (standard module), 659
values()	WCONTINUED (data in os), 253
dictionary method, 28	WCOREDUMP () (in module os), 253
Message method, 555	WeakKeyDictionary (class in weakref), 50
varray() (in module gl), 743	weakref (extension module), 49
vars() (in module), 14	WeakValueDictionary (class in weakref), 50
vbar (ScrolledText attribute), 689	webbrowser (standard module), 469
VERBOSE (data in re), 115	weekday()
verbose	date method, 274
data in tabnanny, 712	datetime method, 278
data in test.test_support, 183	in module calendar, 230
verify() (SMTP method), 512	weekheader () (in module calendar), 231
verify_request() (in module SocketServer),	weibullvariate() (in module random), 204
520	WEXITSTATUS() (in module os), 253
version() (in module platform), 383	wfile (BaseHTTPRequestHandler attribute), 521
version	what()
Cookie attribute, 530	in module imghdr, 663
data in curses, 304	in module sndhdr, 664
data in httplib, 495	whathdr() (in module sndhdr), 664
data in marshal, 86	whichdb() (in module whichdb), 410
data in sys, 47	whichdb (standard module), 410
URLopener attribute, 482	while
CILIOPONOI MINIOMO, 102	,,

statement, 15	AU_write method, 659
whitespace	Wave_write method, 661
data in string, 106	<pre>writelines()</pre>
shlex attribute, 235	BZ2File method, 417
whitespace_split (shlex attribute), 235	file method, 30
whrandom (standard module), 205	StreamWriter method, 137
whseed() (in module random), 204	writepy() (PyZipFile method), 419
WichmannHill (class in random), 204	writer() (in module csv), 604
width() (in module turtle), 689	writer (formatter attribute), 550
width (TextWrapper attribute), 132	writerow() (csv writer method), 606
WIFCONTINUED() (in module os), 253	writerows() (csv writer method), 607
WIFEXITED() (in module os), 253	writesamps() (audio port method), 732
WIFSIGNALED() (in module os), 253	writestr() (ZipFile method), 419
WIFSTOPPED() (in module os), 253	writexml() (Node method), 634
Wimp\$ScrapDir, 340	WrongDocumentErr (exception in xml.dom)
win32_ver() (in module platform), 383	631
window() (method), 312	WSTOPSIG() (in module os), 254
window manager (widgets), 681	WTERMSIG() (in module os), 254
Windows ini file, 226	WUNTRACED (data in os), 253
WindowsError (exception in exceptions), 37	WWW, 469, 478, 516, 603
WinSock, 396	server, 471, 521
winsound (built-in module), 754	
winver (data in sys), 47	X
WNOHANG (data in os), 253	X (data in re), 115
wordchars (shlex attribute), 235	X_OK (data in os), 244
World Wide Web, 469, 478, 516, 603	xatom() (IMAP4_stream method), 506
wrap()	XDR, 73, 600
in module textwrap, 132	xdrlib (standard module), 600
TextWrapper method, 133	xgtitle() (NNTPDataError method), 509
wrapper() (in module curses.wrapper), 308	xhdr() (NNTPDataError method), 509
writable()	XHTML, 609
async_chat method, 546	XHTML_NAMESPACE (data in xml.dom), 625
dispatcher method, 544	XML, 648
write()	namespaces, 650
method, 394, 408	xml.dom (standard module), 623
array method, 214	xml.dom.minidom (standard module), 633
audio device method, 665, 748	xml.dom.pulldom (standard module), 637
BZ2File method, 417	xml.parsers.expat (standard module), 615
file method, 30	xml.sax (standard module), 638
Generator method, 562	xml.sax.handler (standard module), 639
in module imgfile, 745	xml.sax.saxutils (standard module), 643
in module os, 243	xml.sax.xmlreader (standard module), 644
in module turtle, 690	XML_NAMESPACE (data in xml.dom), 624
InteractiveConsole method, 95	<pre>xmlcharrefreplace_errors_errors()</pre>
SafeConfigParser method, 228	(in module codecs), 135
StreamWriter method, 137	XmlDeclHandler() (xmlparser method), 618
Telnet method, 515	XMLFilterBase (class in xml.sax.saxutils), 644
ZipFile method, 419	XMLGenerator (class in xml.sax.saxutils), 644
<pre>write_byte() (method), 408</pre>	xmllib (standard module), 648
<pre>write_history_file() (in module readline),</pre>	XMLNS_NAMESPACE (data in xml.dom), 625
426	XMLParser (class in xmllib), 648
writeall() (audio device method), 666	XMLParserType (data in xml.parsers.expat), 615
<pre>writeframes()</pre>	XMLReader (class in xml.sax.xmlreader), 644
aifc method, 657	xmlrpclib (standard module), 536
AU_write method, 659	xor() (in module operator), 62
Wave_write method, 661	xover() (NNTPDataError method), 510
<pre>writeframesraw()</pre>	xpath() (NNTPDataError method), 510
aifc method, 657	xrange

```
object, 19, 25
xrange()
    built-in function, 19, 58
    in module, 14
XRangeType (data in types), 58
xreadlines()
    BZ2File method, 417
    file method, 30
Υ
Y2K, 286
year
    date attribute, 273
    datetime attribute, 276
Year 2000, 286
Year 2038, 286
YESEXPR (data in locale), 351
yiq_to_rgb() (in module colorsys), 662
Ζ
ZeroDivisionError (exception in exceptions),
         37
zfill()
    in module string, 110
    string method, 23
zip() (in module), 14
ZIP_DEFLATED (data in zipfile), 418
ZIP_STORED (data in zipfile), 418
ZipFile (class in zipfile), 418, 419
zipfile (standard module), 418
zipimport (standard module), 91
zipimporter (class in zipimport), 92
ZipImporterError (exception in zipimport), 92
ZipInfo (class in zipfile), 418
zlib (built-in module), 413
```