

Astra Control Center documentation

Astra Control Center

NetApp September 23, 2022

This PDF was generated from https://docs.netapp.com/us-en/astra-control-center/index.html on September 23, 2022. Always check docs.netapp.com for the latest.

Table of Contents

Astra Control Center documentation	1
Release notes	2
What's new in this release of Astra Control Center	2
Known issues	4
Known limitations	8
Concepts	12
Learn about Astra Control	12
Architecture and components	15
Data protection	16
Licensing	19
Understanding app management	20
Storage classes and persistent volume size	22
User roles and namespaces	23
Get started	24
Astra Control Center requirements	24
Quick start for Astra Control Center	30
Installation overview	31
Set up Astra Control Center	85
Frequently asked questions for Astra Control Center	104
Use Astra	106
Start managing apps	106
Protect apps	110
Monitor app and cluster health	141
Manage your account	143
Manage buckets	154
Manage the storage backend	156
Monitor infrastructure with Cloud Insights and Fluentd connections	162
Unmanage apps and clusters	169
Upgrade Astra Control Center	170
Uninstall Astra Control Center	182
Automate with REST API	186
Automation using the Astra Control REST API	186
Knowledge and support	187
Troubleshooting	187
Get help	187
Earlier versions of Astra Control Center documentation	190
Legal notices	191
Copyright	191
Trademarks	191
Patents	191
Privacy policy	191
Open source	191
Astra Control API license	191

Astra Control Center documentation

Release notes

We're pleased to announce the latest release of Astra Control Center.

- · What's in this release of Astra Control Center
- Known issues
- · Known issues with Astra Data Store and this Astra Control Center release
- Known limitations

Follow us on Twitter @NetAppDoc. Send feedback about documentation by becoming a GitHub contributor or sending an email to doccomments@netapp.com.

What's new in this release of Astra Control Center

We're pleased to announce the latest release of Astra Control Center.

8 September 2022 (22.08.1)

This patch release (22.08.1) for Astra Control Center (22.08.0) fixes minor bugs in app replication using NetApp SnapMirror.

10 August 2022 (22.08.0)

New features and support

- App replication using NetApp SnapMirror technology
- Improved app management workflow
- Enhanced provide-your-own execution hooks functionality



The NetApp provided default pre- and post-snapshot execution hooks for specific applications have been removed in this release. If you upgrade to this release and do not provide your own execution hooks for snapshots, Astra Control will take crash-consistent snapshots only. Visit the NetApp Verda GitHub repository for sample execution hook scripts that you can modify to fit your environment.

- Support for VMware Tanzu Kubernetes Grid Integrated Edition (TKGI)
- · Support for Google Anthos
- LDAP configuration (via Astra Control API)

Known issues and limitations

- · Known issues for this release
- Known issues with Astra Data Store and this Astra Control Center release
- · Known limitations for this release

26 April 2022 (22.04.0)

Details

New features and support

- Astra Data Store deployment from Astra Control Center
- Namespace role-based access control (RBAC)
- Support for Cloud Volumes ONTAP
- Generic ingress enablement for Astra Control Center
- Bucket removal from Astra Control
- · Support for VMware Tanzu Portfolio

Known issues and limitations

- · Known issues for this release
- · Known issues with Astra Data Store and this Astra Control Center release
- · Known limitations for this release

14 December 2021 (21.12)

Details

New features and support

- Application restore
- Execution hooks
- Support for applications deployed with namespace-scoped operators
- · Additional support for upstream Kubernetes and Rancher
- Astra Data Store preview backend management and monitoring
- · Astra Control Center upgrades
- Red Hat OperatorHub option for installation

Resolved issues

· Resolved issues for this release

Known issues and limitations

- · Known issues for this release
- · Known issues with Astra Data Store preview and this Astra Control Center release
- · Known limitations for this release

5 August 2021 (21.08)

Details

Initial release of Astra Control Center.

- · What it is
- · Understand architecture and components
- · What it takes to get started
- · Install and setup
- · Manage and protect apps
- Manage buckets and storage backends
- · Manage accounts
- Automate with API

Find more information

- · Known issues for this release
- · Known limitations for this release
- Astra Data Store documentation
- Earlier versions of Astra Control Center documentation

Known issues

Known issues identify problems that might prevent you from using this release of the product successfully.

The following known issues affect the current release:

Apps

- Restore of an app results in PV size larger than original PV
- App clones fail using a specific version of PostgreSQL
- App clones fail when using Service Account level OCP Security Context Constraints (SCC)
- · App clones fail after an application is deployed with a set storage class
- App backups and snapshots fail if the volumesnapshotclass is added after a cluster is managed

Clusters

 Managing a cluster with Astra Control Center fails when default kubeconfig file contains more than one context

Other issues

- App data management operations fail with Internal Service Error (500) when Astra Trident is offline
- Snapshots might fail with snapshot controller version 4.2.0

Restore of an app results in PV size larger than original PV

If you resize a persistent volume after creating a backup and then restore from that backup, the persistent volume size will match the new size of the PV instead of using the size of the backup.

App clones fail using a specific version of PostgreSQL

App clones within the same cluster consistently fail with the Bitnami PostgreSQL 11.5.0 chart. To clone successfully, use an earlier or later version of the chart.

App clones fail when using Service Account level OCP Security Context Constraints (SCC)

An application clone might fail if the original security context constraints are configured at the service account level within the namespace on the OpenShift Container Platform cluster. When the application clone fails, it appears in the Managed Applications area in Astra Control Center with status Removed. See the knowledgebase article for more information.

App backups and snapshots fail if the volumesnapshotclass is added after a cluster is managed

Backups and snapshots fail with a UI 500 error in this scenario. As a workaround, refresh the app list.

App clones fail after an application is deployed with a set storage class

After an application is deployed with a storage class explicitly set (for example, helm install ...-set global.storageClass=netapp-cvs-perf-extreme), subsequent attempts to clone the application require that the target cluster have the originally specified storage class.

Cloning an application with an explicitly set storage class to a cluster that does not have the same storage class will fail. There are no recovery steps in this scenario.

Managing a cluster with Astra Control Center fails when default kubeconfig file contains more than one context

You cannot use a kubeconfig with more than one cluster and context in it. See the knowledgebase article for more information.

App data management operations fail with Internal Service Error (500) when Astra Trident is offline

If Astra Trident on an app cluster goes offline (and is brought back online) and 500 internal service errors are encountered when attempting app data management, restart all of the Kubernetes nodes in the app cluster to restore functionality.

Snapshots might fail with snapshot controller version 4.2.0

When you use Kubernetes snapshot-controller (also known as external-snapshotter) version 4.2.0 with Kubernetes 1.20 or 1.21, snapshots can eventually begin to fail. To prevent this, use a different supported version of external-snapshotter, such as version 4.2.1, with Kubernetes versions 1.20 or 1.21.

- 1. Run a POST call to add an updated kubeconfig file to the /credentials endpoint and retrieve the assigned id from the response body.
- 2. Run a PUT call from the /clusters endpoint using the appropriate cluster ID and set the credentialID to the id value from the previous step.

After you complete these steps, the credential associated with the cluster is updated and the cluster should reconnect and update its state to available.

Find more information

- Known issues with Astra Data Store preview and this Astra Control Center release
- Known limitations

Known issues with Astra Data Store and this Astra Control Center release

Known issues identify problems that might prevent you from using this release of the product successfully.

See these additional Astra Data Store known issues that might affect the management of Astra Data Store with the current release of the Astra Control Center.

Astra Data Store volume details do not appear in Storage Backends page of the Astra Control Center UI

Details such as capacity and throughput do not appear in the UI. When this issue occurs, unmanage the storage backend and add it back again.

Unmanaging a cluster with Astra Data Store requires first removing a managed system app

If you added a cluster that contains Astra Data Store to an Astra Control Center cluster, the astrads-system app is managed by default as a hidden application. To unmanage the cluster, you must first unmanage the astrads-system app. You cannot unmanage this type of app using the Astra Control Center UI. Instead, use an Astra Control API request to manually remove the app:

Steps

1. Get the ID for the managed cluster using this API:

```
/accounts/{account_id}/topology/v1/managedClusters
```

Response:

```
"items": [
{
  "type": "application/astra-managedCluster",
  "version": "1.1",
  "id": "123ab987-0bc0-00d0-a00a-1234567abd8d",
  "name": "astrads-cluster-1234567",
  ...
```

2. Get the managed astrads-system app ID:

```
/accounts/{account_id}/topology/v2/managedClusters/{managedCluster_i
d}/apps
```

Response:

3. Delete the astrads-system app using the app ID you acquired in the previous step (1b011d11-bb88-40c7-a1a1-ab1234c123d3).

```
/accounts/{account_id}/k8s/v2/apps/{astrads-system_app_id}
```

Find more information

- Known issues
- Known limitations

Known limitations

Known limitations identify platforms, devices, or functions that are not supported by this release of the product, or that do not interoperate correctly with it. Review these limitations carefully.

Cluster management limitations

- The same cluster cannot be managed by two Astra Control Center instances
- · Astra Control Center cannot manage two identically named clusters

Role-based Access Control (RBAC) limitations

- · A user with namespace RBAC constraints can add and unmanage a cluster
- A member with namespace constraints cannot access the cloned or restored apps until admin adds the namespace to the constraint

App management limitations

- · Clones of apps installed using pass-by-reference operators can fail
- In-place restore operations of apps that use a certificate manager are not supported
- OLM-enabled and cluster-scoped operator deployed apps not supported
- · Apps deployed with Helm 2 are not supported

General limitations

- · S3 buckets in Astra Control Center do not report available capacity
- · Astra Control Center does not validate the details you enter for your proxy server
- Existing connections to a Postgres pod causes failures
- · Backups and snapshots might not be retained during removal of an Astra Control Center instance

The same cluster cannot be managed by two Astra Control Center instances

If you want to manage a cluster on another Astra Control Center instance, you should first unmanage the cluster from the instance on which it is managed before you manage it on another instance. After you remove the cluster from management, verify that the cluster is unmanaged by executing this command:

```
oc get pods n -netapp-monitoring
```

There should be no pods running in that namespace or the namespace should not exist. If either of those are true, the cluster is unmanaged.

Astra Control Center cannot manage two identically named clusters

If you try to add a cluster with the same name of a cluster that already exists, the operation will fail. This issue most often occurs in a standard Kubernetes environment if you have not changed the cluster name default in Kubernetes configuration files.

As a workaround, do the following:

1. Edit your kubeadm-config ConfigMap:

```
kubectl edit configmaps -n kube-system kubeadm-config
```

- 2. Change the clusterName field value from kubernetes (the Kubernetes default name) to a unique custom name.
- 3. Edit kubeconfig (.kube/config).
- 4. Update cluster name from kubernetes to a unique custom name (xyz-cluster is used in the examples below). Make the update in both clusters and contexts sections as shown in this example:

```
apiVersion: v1
clusters:
    cluster:
    certificate-authority-data:
ExAmpLERb2tCcjZ5K3E2Njk4eQotLExAMpLEORCBDRVJUSUZJQ0FURS0txxxxXX==
    server: https://x.x.x.x:6443
    name: xyz-cluster
contexts:
    context:
    cluster: xyz-cluster
    namespace: default
    user: kubernetes-admin
    name: kubernetes-admin@kubernetes
```

A user with namespace RBAC constraints can add and unmanage a cluster

A user with namespace RBAC constraints should not be allowed to add or unmanage clusters. Due to a current limitation, Astra does not prevent such users from unmanaging clusters.

A member with namespace constraints cannot access the cloned or restored apps until admin adds the namespace to the constraint

Any member user with RBAC constraints by namespace name/ID can clone or restore an app to a new namespace on the same cluster or to any other cluster in their organization's account. However, the same user cannot access the cloned or restored app in the new namespace. After a new namespace is created by a clone or restore operation, the account admin/owner can edit the member user account and update role constraints for the affected user to grant access to the new namespace.

Clones of apps installed using pass-by-reference operators can fail

Astra Control supports apps installed with namespace-scoped operators. These operators are generally designed with a "pass-by-value" rather than "pass-by-reference" architecture. The following are some operator apps that follow these patterns:

Apache K8ssandra



For K8ssandra, in-place restore operations are supported. A restore operation to a new namespace or cluster requires that the original instance of the application to be taken down. This is to ensure that the peer group information carried over does not lead to cross-instance communication. Cloning of the app is not supported.

- Jenkins CI
- Percona XtraDB Cluster

Astra Control might not be able to clone an operator that is designed with a "pass-by-reference" architecture (for example, the CockroachDB operator). During these types of cloning operations, the cloned operator attempts to reference Kubernetes secrets from the source operator despite having its own new secret as part of the cloning process. The clone operation might fail because Astra Control is unaware of the Kubernetes secrets in the source operator.

In-place restore operations of apps that use a certificate manager are not supported

This release of Astra Control Center does not support in-place restore of apps with certificate managers. Restore operations to a different namespace and clone operations are supported.

OLM-enabled and cluster-scoped operator deployed apps not supported

Astra Control Center does not support application management activities with cluster-scoped operators.

Apps deployed with Helm 2 are not supported

If you use Helm to deploy apps, Astra Control Center requires Helm version 3. Managing and cloning apps deployed with Helm 3 (or upgraded from Helm 2 to Helm 3) is fully supported. For more information, see Astra Control Center requirements.

S3 buckets in Astra Control Center do not report available capacity

Before backing up or cloning apps managed by Astra Control Center, check bucket information in the ONTAP or StorageGRID management system.

Astra Control Center does not validate the details you enter for your proxy server

Ensure that you enter the correct values when establishing a connection.

Existing connections to a Postgres pod causes failures

When you perform operations on Postgres pods, you shouldn't connect directly within the pod to use the psql command. Astra Control requires psql access to freeze and thaw the databases. If there is a pre-existing connection, the snapshot, backup, or clone will fail.

Backups and snapshots might not be retained during removal of an Astra Control Center instance

If you have an evaluation license, be sure you store your account ID to avoid data loss in the event of Astra Control Center failure if you are not sending ASUPs.

Find more information

- Known issues
- Known issues with Astra Data Store and this Astra Control Center release

Concepts

Learn about Astra Control

Astra Control is a Kubernetes application data lifecycle management solution that simplifies operations for stateful applications. Easily protect, back up, replicate, and migrate Kubernetes workloads, and instantly create working application clones.

Features

Astra Control offers critical capabilities for Kubernetes application data lifecycle management:

- · Automatically manage persistent storage
- · Create application-aware, on-demand snapshots and backups
- Automate policy-driven snapshot and backup operations
- Replicate application to a remote system using NetApp SnapMirror technology
- · Migrate applications and data from one Kubernetes cluster to another
- · Easily clone an application from production to staging
- Visualize application health and protection status
- · Use a user interface or an API to implement your backup and migration workflows

Astra Control continually watches your compute for state changes, so it's aware of any new apps that you add along the way.

Deployment models

Astra Control is available in two deployment models:

- Astra Control Service: A NetApp-managed service that provides application-aware data management of Kubernetes clusters in Google Kubernetes Engine (GKE) and Azure Kubernetes Service (AKS).
- Astra Control Center: Self-managed software that provides application-aware data management of Kubernetes clusters running in your on-premises environment.

	Astra Control Service	Astra Control Center	
How is it offered?	As a fully managed cloud service from NetApp	As software that you download, install, and manage	
Where is it hosted?	On a public cloud of NetApp's choice	On your provided Kubernetes cluster	
How is it updated?	Managed by NetApp	You manage any updates	
What are the app data management capabilities?	Same capabilities on both platforms with exceptions to storage backend or to external services	Same capabilities on both platforms with exceptions to storage backend or to external services	

	Astra Control Service	Astra Control Center
What is the storage backend support?	NetApp cloud service offerings	 NetApp ONTAP AFF and FAS systems Astra Data Store as storage backend Cloud Volumes ONTAP storage backend

How Astra Control Service works

Astra Control Service is a NetApp-managed cloud service that is always on and updated with the latest capabilities. It utilizes several components to enable application data lifecycle management.

At a high level, Astra Control Service works like this:

- You get started with Astra Control Service by setting up your cloud provider and by registering for an Astra account.
 - For GKE clusters, Astra Control Service uses NetApp Cloud Volumes Service for Google Cloud or Google Persistent Disks as the storage backend for your persistent volumes.
 - For AKS clusters, Astra Control Service uses Azure NetApp Files or Azure Disk Storage as the storage backend for your persistent volumes.
 - For Amazon EKS clusters, Astra Control Service uses Amazon Elastic Block Store or Amazon FSx for NetApp ONTAP as the storage backend for your persistent volumes.
- You add your first Kubernetes compute to Astra Control Service. Astra Control Service then does the following:
 - Creates an object store in your cloud provider account, which is where backup copies are stored.

In Azure, Astra Control Service also creates a resource group, a storage account, and keys for the Blob container.

- Creates a new admin role and Kubernetes service account on the cluster.
- Uses that new admin role to install Astra Trident on the cluster and to create one or more storage classes.
- If you use Azure NetApp Files or NetApp Cloud Volumes Service for Google Cloud as your storage backend, Astra Control Service uses Astra Trident to provision persistent volumes for your apps.
- At this point, you can add apps to your cluster. Persistent volumes will be provisioned on the new default storage class.
- You then use Astra Control Service to manage these apps, and start creating snapshots, backups, and clones.

Astra Control's Free Plan enables you to manage up to 10 apps in your account. If you want to manage more than 10 apps, then you'll need to set up billing by upgrading from the Free Plan to the Premium Plan.

How Astra Control Center works

Astra Control Center runs locally in your own private cloud.

Astra Control Center supports Kubernetes clusters with:

- Trident storage backends with ONTAP 9.5 and above
- · Astra Data Store storage backends

In a cloud connected environment Astra Control Center uses Cloud Insights to provide advanced monitoring and telemetry. In the absence of a Cloud Insights connection, limited (7-days of metrics) monitoring and telemetry is available in Astra Control Center and also exported to Kubernetes native monitoring tools (such as Prometheus and Grafana) through open metrics end points.

Astra Control Center is fully integrated into the AutoSupport and Active IQ ecosystem to provide users and NetApp Support with troubleshooting and usage information.

You can try Astra Control Center out using a 90-day evaluation license. The evaluation version is supported through email and community (Slack channel) options. Additionally, you have access to Knowledgebase articles and documentation from the in-product support dashboard.

To install and use Astra Control Center, you'll need to meet certain requirements.

At a high level, Astra Control Center works like this:

- You install Astra Control Center in your local environment. Learn more about how to install Astra Control Center.
- · You complete some setup tasks such as these:
 - · Set up licensing.
 - · Add your first cluster.
 - Add storage backend that is discovered when you added the cluster.
 - Add an object store bucket that will store your app backups.

Learn more about how to set up Astra Control Center.

Astra Control Center does this:

- Discovers details about the cluster including namespaces and enables you to define and protect the apps.
- Discovers your Astra Trident or Astra Data Store configuration on the clusters that you choose to manage and lets you monitor the storage backends.


You can add apps to your cluster. Or, if you have some apps already in the cluster being managed, you can use Astra Control Center to manage them. Then, use Astra Control Center to create snapshots, backups, clones and replication relationships.

For more information

- Astra Control Service documentation
- Astra Control Center documentation
- Astra Data Store documentation
- Astra Trident documentation
- Use the Astra Control API
- Cloud Insights documentation
- ONTAP documentation

Architecture and components

Here is an overview of the various components of the Astra Control environment.



Astra Control components

- **Kubernetes clusters**: Kubernetes is a portable, extensible, open-source platform for managing containerized workloads and services, that facilitates both declarative configuration and automation. Astra provides management services for applications hosted in a Kubernetes cluster.
- Astra Trident: As a fully supported open source storage provisioner and orchestrator maintained by NetApp, Trident enables you to create storage volumes for containerized applications managed by Docker and Kubernetes. When deployed with Astra Control Center, Trident includes a configured ONTAP storage backend.
- · Storage backend:
 - Astra Control Service uses the following storage backends:
 - NetApp Cloud Volumes Service for Google Cloud or Google Persistent Disk as the storage backend for GKE clusters
 - Azure NetApp Files or Azure Managed Disks as the storage backend for AKS clusters.
 - Amazon Elastic Block Store (EBS) or Amazon FSx for NetApp ONTAP as backend storage options for EKS clusters.

- Astra Control Center uses the following storage backends:
 - ONTAP AFF and FAS. As a storage software and hardware platform, ONTAP provides core storage services, support for multiple storage access protocols, and storage management functionality, such as snapshots and mirroring.
 - Cloud Volumes ONTAP
- Cloud Insights: A NetApp cloud infrastructure monitoring tool, Cloud Insights enables you to monitor performance and utilization for your Kubernetes clusters managed by Astra Control Center. Cloud Insights correlates storage usage to workloads. When you enable the Cloud Insights connection in Astra Control Center, telemetry information shows in Astra Control Center UI pages.

Astra Control interfaces

You can complete tasks using different interfaces:

- Web user interface (UI): Both Astra Control Service and Astra Control Center use the same web-based UI
 where you can manage, migrate and protect apps. Use the UI also to manage user accounts and
 configuration settings.
- **API**: Both Astra Control Service and Astra Control Center use the same Astra Control API. Using the API, you can perform the same tasks that you would using the UI.

Astra Control Center also enables you to manage, migrate, and protect Kubernetes clusters running within VM environments.

For more information

- Astra Control Service documentation
- Astra Control Center documentation
- Astra Trident documentation
- Use the Astra Control API
- Cloud Insights documentation
- ONTAP documentation

Data protection

Learn about the available types of data protection in Astra Control Center, and how best to use them to protect your apps.

Snapshots, backups, and protection policies

A *snapshot* is a point-in-time copy of an app that's stored on the same provisioned volume as the app. They are usually fast. You can use local snapshots to restore the application to an earlier point in time. Snapshots are useful for fast clones; snapshots include all of the Kubernetes objects for the app, including configuration files.

A *backup* is stored in the external object store, and can be slower to take compared to local snapshots. You can restore an app backup to the same cluster, or you can migrate an app by restoring its backup to a different cluster. You can also choose a longer retention period for backups. Because they are stored in the external object store, backups generally offer you better protection than snapshots in cases of server failure or data loss.

A *protection policy* is a way to protect an app by automatically creating snapshots, backups, or both according to a schedule that you define for that app. A protection policy also enables you to choose how many snapshots and backups to retain in the schedule. Automating your backups and snapshots with a protection policy is the best way to ensure each app is protected according to the needs of your organization.



You can't be fully protected until you have a recent backup. This is important because backups are stored in an object store away from the persistent volumes. If a failure or accident wipes out the cluster and its associated persistent storage, then you need a backup to recover. A snapshot would not enable you to recover.

Clones

A *clone* is an exact duplicate of an app, its configuration, and its persistent storage. You can manually create a clone on either the same Kubernetes cluster or on another cluster. Cloning an app can be useful if you need to move applications and storage from one Kubernetes cluster to another.

Replication to a remote cluster

Using Astra Control, you can build business continuity for your applications with a low-RPO (Recovery Point Objective) and low-RTO (Recovery Time Objective) using asynchronous replication capabilities of NetApp SnapMirror technology. Once configured, this enables your applications to replicate data and application changes from one cluster to another.

Astra Control asynchronously replicates app Snapshot copies to a remote cluster. The replication process includes data in the persistent volumes replicated by SnapMirror and the app metadata protected by Astra Control.

App replication is different from app backup and restore in the following ways:

- App replication: Astra Control requires the source and destination Kubernetes clusters to be available and
 managed with their respective ONTAP storage backends configured to enable NetApp SnapMirror.
 Astra Control takes the policy-driven application Snapshot and replicates it to the remote cluster.
 NetApp SnapMirror technology is used to replicate the persistent volume data. To fail over, Astra Control
 can bring the replicated app online by recreating the app objects on the destination Kubernetes cluster with
 the replicated volumes on the destination ONTAP cluster. Since the persistent volume data is already
 present on the destination ONTAP cluster, Astra Control can offer quick recovery times for failover.
- App backup and restore: When backing up applications, Astra Control creates a Snapshot of the app data and stores it in an object storage bucket. When a restore is needed, the data in the bucket must be copied to a persistent volume on the ONTAP cluster. The backup/restore operation does not require the secondary Kubernetes/ONTAP cluster to be available and managed, but the additional data copy can result in longer restore times.

To learn how to replicate apps, see Replicate apps to a remote system using SnapMirror technology.

The following images show the scheduled backup and restore process compared to the replication process.

The backup process copies data to S3 buckets and restores from S3 buckets:


Scheduled Backup





On the other hand, replication is done by replicating to ONTAP and then a fail over creates the Kubernetes resources:

Replication Relationship





Licensing

Astra Control Center requires a license to be installed for the full app data management functionality to be enabled. When you deploy Astra Control Center without a license, a banner is displayed in the web UI, warning that system functionality is limited.

The following operations require a valid license:

- · Managing new applications
- · Creating snapshots or backups
- · Configuring a protection policy to schedule snapshots or backups
- · Restoring from a snapshot or backup
- · Cloning from a snapshot or current state
- · Replicating applications to a remote system



You can add a cluster, add a bucket, and manage an Astra Data Store storage backend without a license. However, you need a valid Astra Control Center license to manage apps using Astra Data Store as a storage backend.

How license consumption is calculated

When you add a new cluster to Astra Control Center, it doesn't count toward consumed licenses until at least one application running on the cluster is managed by Astra Control Center. You can also add an Astra Data Store storage backend to Astra Control Center without affecting license consumption. This enables you to manage an Astra Data Store backend from an unlicensed Astra Control Center system.

When you start managing an app on a cluster, all of that cluster's CPU units are included in the Astra Control Center license consumption. If the cluster has a licensed deployment of Astra Data Store, those CPU units are excluded from the Astra Control Center license consumption calculation.



CPU units from Evaluation Deployments of Astra Data Store are not excluded from the Astra Control Center license consumption.

Find more information

· Update an existing license

Understanding app management

When Astra Control discovers your clusters, the apps on those clusters are unmanaged until you choose how you want to manage them. A managed application in Astra Control can be any of the following:

A namespace, including all resources in that namespace



• An individual application deployed within a namespace (helm3 is used in this example)



• A group of resources that are identified by a Kubernetes label within a namespace



Storage classes and persistent volume size

Astra Control Center supports ONTAP or Astra Data Store as the storage backend.

Overview

Astra Control Center supports the following:

• Trident storage classes backed by Astra Data Store storage: If you installed one or more Astra Data Store clusters manually, Astra Control Center offers the ability to import these and retrieve their topology (nodes, disks) as well as various statuses.

Astra Control Center displays the underlying Kubernetes cluster from the Astra Data Store configuration, the cloud that the Kubernetes cluster belongs to, any persistent volumes provisioned by Astra Data Store, the name of the corresponding internal volume, the application using the persistent volume, and the cluster containing the app.

• **Trident storage classes backed by ONTAP storage**: If you are using an ONTAP backend, Astra Control Center offers the ability to import the ONTAP backend to report various monitoring information.



Trident storage classes should be preconfigured outside of Astra Control Center.

Storage classes

When you add a cluster to Astra Control Center, you're prompted to select one previously configured storage class on that cluster as the default storage class. This storage class will be used when no storage class is specified in a persistent volume claim (PVC). The default storage class can be changed at any time within Astra Control Center and any storage class can be used at any time by specifying the name of the storage class within the PVC or Helm chart. Ensure that you have only a single default storage class defined for your Kubernetes cluster.

When you use Astra Control Center integrated with an Astra Data Store storage backend, after the installation, no storage classes are defined. You will need to create the Trident default storage class and apply it to the storage backend. See Astra Data Store getting started to create a default Astra Data Store storage class.

For more information

Astra Trident documentation

User roles and namespaces

Learn about user roles and namespaces in Astra Control, and how you can use them to control access to resources in your organization.

User roles

You can use roles to control the access users have to resources or capabilities of Astra Control. The following are the user roles in Astra Control:

- · A Viewer can view resources.
- A Member has Viewer role permissions and can manage apps and clusters, unmanage apps, and delete snapshots and backups.
- An **Admin** has Member role permissions and can add and remove any other users except the Owner.
- An **Owner** has Admin role permissions and can add and remove any user accounts.

You can add constraints to a Member or Viewer user to restrict the user to one or more Namespaces.

Namespaces

A namespace is a scope you can assign to specific resources within a cluster that is managed by Astra Control. Astra Control discovers a cluster's namespaces when you add the cluster to Astra Control. Once discovered, the namespaces are available to assign as constraints to users. Only members that have access to that namespace are able to use that resource. You can use namespaces to control access to resources using a paradigm that makes sense for your organization; for example, by physical regions or divisions within a company. When you add constraints to a user, you can configure that user to have access to all namespaces or only a specific set of namespaces. You can also assign namespace constraints using namespace labels.

Find more information

Manage roles

Get started

Astra Control Center requirements

Get started by verifying the readiness of your operational environment, application clusters, applications, licenses, and web browser.

- Operational environment requirements
- · Supported storage backends
- Application cluster requirements
- · Application management requirements
- · Replication prerequisites
- · Access to the internet
- License
- Ingress for on-premises Kubernetes clusters
- Networking requirements
- · Supported web browsers

Operational environment requirements

Astra Control Center has been validated on the following types of operational environments:

- · Google Anthos 1.10 or 1.11
- Kubernetes 1.22 to 1.24
- Rancher Kubernetes Engine (RKE):
 - RKE 1.2.16 w/ Rancher 2.5.12 and RKE 1.3.3 w/ 2.6.3
 - RKE 2 (v1.23.6+rke2r2) w/ Rancher 2.6.3
- Red Hat OpenShift Container Platform 4.8, 4.9, or 4.10
- VMware Tanzu Kubernetes Grid 1.4 or 1.5
- VMware Tanzu Kubernetes Grid Integrated Edition 1.12.2 or 1.13

Ensure that the operating environment you choose to host Astra Control Center meets the basic resource requirements outlined in the environment's official documentation. Astra Control Center requires the following resources in addition to the environment's resource requirements:

Component	Requirement
Storage backend capacity	At least 500GB available
Worker nodes	At least 3 worker nodes total, with 4 CPU cores and 12GB RAM each
FQDN address	An FQDN address for Astra Control Center

Component	Requirement
Astra Trident	Astra Trident 21.10.1 or newer installed and configured Astra Trident 22.07 or newer for SnapMirror-based application replication



These requirements assume that Astra Control Center is the only application running in the operational environment. If the environment is running additional applications, adjust these minimum requirements accordingly.

- Image registry: You must have an existing private Docker image registry to which you can push Astra Control Center build images. You need to provide the URL of the image registry where you will upload the images.
- Astra Trident / ONTAP configuration: Astra Control Center requires that a storage class be created and set as the default storage class. Astra Control Center supports the following ONTAP drivers provided by Astra Trident:
 - ontap-nas
 - ontap-nas-flexgroup
 - ∘ ontap-san
 - ontap-san-economy

During app cloning in OpenShift environments, Astra Control Center needs to allow OpenShift to mount volumes and change the ownership of files. Because of this, you need to configure an ONTAP volume export policy to allow these operations. You can do so with the following commands:



- 1. export-policy rule modify -vserver <storage virtual machine name>
 -policyname <policy name> -ruleindex 1 -superuser sys
- 2. export-policy rule modify -vserver <storage virtual machine name>
 -policyname <policy name> -ruleindex 1 -anon 65534



If you plan to add a second OpenShift operational environment as a managed compute resource, you need to ensure that the Astra Trident Volume Snapshot feature is enabled. To enable and test volume snapshots with Astra Trident, see the official Astra Trident instructions.

VMware Tanzu Kubernetes Grid cluster requirements

When hosting Astra Control Center on a VMware Tanzu Kubernetes Grid (TKG) or Tanzu Kubernetes Grid Integrated Edition (TKGi) cluster, keep in mind the following considerations.

- Disable the TKG or TKGi default storage class enforcement on any application clusters intended to be managed by Astra Control. You can do this by editing the TanzuKubernetesCluster resource on the namespace cluster.
- As part of Astra Control Center installation, the following resources are created in a pod security policy (PSP) restricted environment:
 - pod security policy

- RBAC Role
- RBAC RoleBinding
 The RBAC Role and RoleBinding resources are created in the netapp-acc namespace.
- Be aware of specific requirements for Astra Trident when you deploy Astra Control Center in a TKG or TKGi environment. For more information, see the Astra Trident documentation.



The default VMware TKG and TKGi configuration file token expires ten hours after deployment. If you use Tanzu portfolio products, you must generate a Tanzu Kubernetes Cluster configuration file with a non-expiring token to prevent connection issues between Astra Control Center and managed application clusters. For instructions, visit the VMware NSX-T Data Center Product Documentation.

Google Anthos cluster requirements

When hosting Astra Control Center on a Google Anthos cluster, note that Google Anthos includes the MetalLB load balancer and the Istio ingress gateway service by default, enabling you to simply use the generic ingress capabilities of Astra Control Center during installation. See Configure Astra Control Center for details.

Supported storage backends

Astra Control Center supports the following storage backends.

- NetApp ONTAP 9.5 or newer AFF and FAS systems
- NetApp ONTAP 9.8 or newer AFF and FAS systems for SnapMirror-based application replication
- NetApp Cloud Volumes ONTAP

Application cluster requirements

Astra Control Center has the following requirements for clusters that you plan to manage from Astra Control Center. These requirements also apply if the cluster you plan to manage is the operational environment cluster that hosts Astra Control Center.

- The most recent version of the Kubernetes snapshot-controller component is installed
- An Astra Trident volumesnapshotclass object has been defined by an administrator
- A default Kubernetes storage class exists on the cluster
- At least one storage class is configured to use Astra Trident



Your application cluster should have a kubeconfig.yaml file that defines only one context element. Visit the Kubernetes documentation for information about creating kubeconfig files.



When managing application clusters in a Rancher environment, modify the application cluster's default context in the kubeconfig file provided by Rancher to use a control plane context instead of the Rancher API server context. This reduces load on the Rancher API server and improves performance.

Application management requirements

Astra Control has the following application management requirements:

- Licensing: To manage applications using Astra Control Center, you need an Astra Control Center license.
- **Namespaces**: Astra Control requires that an app not span more than a single namespace, but a namespace can contain more than one app.
- StorageClass: If you install an application with a StorageClass explicitly set and you need to clone the app, the target cluster for the clone operation must have the originally specified StorageClass. Cloning an application with an explicitly set StorageClass to a cluster that does not have the same StorageClass will fail.
- **Kubernetes resources**: Applications that use Kubernetes resources not collected by Astra Control might not have full app data management capabilities. Astra Control collects the following Kubernetes resources:

ClusterRole	ClusterRoleBinding	ConfigMap
CronJob	CustomResourceDefinition	CustomResource
DaemonSet	DeploymentConfig	HorizontalPodAutoscaler
Ingress	MutatingWebhook	NetworkPolicy
PersistentVolumeClaim	Pod	PodDisruptionBudget
PodTemplate	ReplicaSet	Role
RoleBinding	Route	Secret
Service	ServiceAccount	StatefulSet
ValidatingWebhook		

Replication prerequisites

Astra Control application replication requires that the following prerequisites must be met before you begin:

- To achieve seamless disaster recovery, we recommend that you deploy Astra Control Center in a third fault domain or secondary site.
- The app's host Kubernetes cluster and a destination Kubernetes cluster must be available and connected to two ONTAP clusters, ideally at different failure domains or sites.
- ONTAP clusters and the host SVM must be paired. See Cluster and SVM peering overview.
- The paired remote SVM must be available to Trident on the destination cluster.
- Trident version 22.07 or greater must exist on both the source and destination ONTAP clusters.
- ONTAP SnapMirror asynchronous licenses using the Data Protection bundle must be enabled on both the source and destination ONTAP clusters. See SnapMirror licensing overview in ONTAP.
- When you add an ONTAP storage backend to Astra Control Center, apply user credentials with the "admin" role, which has access methods http and ontapi enabled on both ONTAP clusters. See Manage User Accounts for more information.
- Both source and destination Kubernetes clusters and ONTAP clusters must be managed by Astra Control.



You can simultaneously replicate a different app (running on the other cluster or site) in the opposite direction. For example, Apps A, B, C can be replicated from Datacenter 1 to Datacenter 2; and Apps X, Y, Z can be replicated from Datacenter 2 to Datacenter 1.

Learn how to replicate apps to a remote system using SnapMirror technology.

Supported application installation methods

Astra Control supports the following application installation methods:

Manifest file: Astra Control supports apps installed from a manifest file using kubectl. For example:

```
kubectl apply -f myapp.yaml
```

- **Helm 3**: If you use Helm to install apps, Astra Control requires Helm version 3. Managing and cloning apps installed with Helm 3 (or upgraded from Helm 2 to Helm 3) is fully supported. Managing apps installed with Helm 2 is not supported.
- **Operator-deployed apps**: Astra Control supports apps installed with namespace-scoped operators. The following are some apps that have been validated for this installation model:
 - Apache K8ssandra
 - Jenkins CI
 - Percona XtraDB Cluster



An operator and the app it installs must use the same namespace; you might need to modify the deployment .yaml file for the operator to ensure this is the case.

Access to the internet

You should determine whether you have outside access to the internet. If you do not, some functionality might be limited, such as receiving monitoring and metrics data from NetApp Cloud Insights, or sending support bundles to the NetApp Support Site.

License

Astra Control Center requires an Astra Control Center license for full functionality. Obtain an evaluation license or full license from NetApp. Without a license, you can't do any of the following:

- · Define apps
- · Create snapshots or clones of existing apps
- · Configure data protection policies

If you want to try Astra Control Center, you can use a 90-day evaluation license.

To learn more about how licenses work, see Licensing.

Ingress for on-premises Kubernetes clusters

You can choose the type of network ingress Astra Control Center uses. By default, Astra Control Center deploys the Astra Control Center gateway (service/traefik) as a cluster-wide resource. Astra Control Center also supports using a service load balancer, if they are permitted in your environment. If you would rather use a service load balancer and you don't already have one configured, you can use the MetalLB load balancer to automatically assign an external IP address to the service. In the internal DNS server configuration, you should point the chosen DNS name for Astra Control Center to the load-balanced IP address.



If you are hosting Astra Control Center on a Tanzu Kubernetes Grid cluster, use the kubectl get nsxlbmonitors -A command to see if you already have a service monitor configured to accept ingress traffic. If one exists, you should not install MetalLB, because the existing service monitor will override any new load balancer configuration.

For more information, see Set up ingress for load balancing.

Networking requirements

The operational environment that hosts Astra Control Center communicates using the following TCP ports. You should ensure that these ports are allowed through any firewalls, and configure firewalls to allow any HTTPS egress traffic originating from the Astra network. Some ports require connectivity both ways between the environment hosting Astra Control Center and each managed cluster (noted where applicable).



You can deploy Astra Control Center in a dual-stack Kubernetes cluster, and Astra Control Center can manage applications and storage backends that have been configured for dual-stack operation. For more information about dual-stack cluster requirements, see the Kubernetes documentation.

Source	Destination	Port	Protocol	Purpose
Client PC	Astra Control Center	443	HTTPS	UI / API access - Ensure this port is open both ways between the cluster hosting Astra Control Center and each managed cluster
Metrics consumer	Astra Control Center worker node	9090	HTTPS	Metrics data communication - ensure each managed cluster can access this port on the cluster hosting Astra Control Center (two-way communication required)
Astra Control Center	Hosted Cloud Insights service (https://cloudinsights .netapp.com)	443	HTTPS	Cloud Insights communication
Astra Control Center	Amazon S3 storage bucket provider (https://my- bucket.s3.us-west- 2.amazonaws.com/)	443	HTTPS	Amazon S3 storage communication
Astra Control Center	NetApp AutoSupport (https://support.neta pp.com)	443	HTTPS	NetApp AutoSupport communication

Supported web browsers

Astra Control Center supports recent versions of Firefox, Safari, and Chrome with a minimum resolution of 1280 x 720.

What's next

View the quick start overview.

Quick start for Astra Control Center

This page provides a high-level overview of the steps needed to get started with Astra Control Center. The links within each step take you to a page that provides more details.

Try it out! If you want to try Astra Control Center, you can use a 90-day evaluation license. See licensing information for details.



Review Kubernetes cluster requirements

- Astra works with Kubernetes clusters with a Trident-configured ONTAP storage backend or an Astra Data Store storage backend.
- Clusters must be running in a healthy state, with at least three online worker nodes.
- The cluster must be running Kubernetes.

Learn more about the Astra Control Center requirements.



Download and install Astra Control Center

- Download Astra Control Center from the NetApp Support Site Astra Control Center Downloads page.
- · Install Astra Control Center in your local environment.

Optionally, install Astra Control Center using Red Hat OperatorHub.

Learn more about installing Astra Control Center.



Complete some initial setup tasks

- · Add a license.
- · Add a Kubernetes cluster and Astra Control Center discovers details.
- Add an ONTAP or Astra Data Store storage backend.
- Optionally, add an object store bucket that will store your app backups.

Learn more about the initial setup process.



Use Astra Control Center

After you finish setting up Astra Control Center, here's what you might do next:

- Manage an app. Learn more about how to manage apps.
- Optionally, connect to NetApp Cloud Insights to display metrics on the health of your system, capacity, and throughput inside the Astra Control Center UI. Learn more about connecting to Cloud Insights.



Continue from this Quick Start

Install Astra Control Center.

Find more information

Use the Astra Control API

Installation overview

Choose and complete one of the following Astra Control Center installation procedures:

- Install Astra Control Center using the standard process
- (If you use Red Hat OpenShift) Install Astra Control Center using OpenShift OperatorHub
- · Install Astra Control Center with a Cloud Volumes ONTAP storage backend

Install Astra Control Center using the standard process

To install Astra Control Center, download the installation bundle from the NetApp Support Site and perform the following steps to install Astra Control Center Operator and Astra Control Center in your environment. You can use this procedure to install Astra Control Center in internet-connected or air-gapped environments.

For Red Hat OpenShift environments, you can use an alternative procedure to install Astra Control Center using OpenShift OperatorHub.

What you'll need

- Before you begin installation, prepare your environment for Astra Control Center deployment.
- If you have configured or want to configure pod security policies in your environment, familiarize yourself
 with pod security policies and how they affect Astra Control Center installation. See Understand pod
 security policy restrictions.
- Ensure all cluster operators are in a healthy state and available.

```
kubectl get clusteroperators
```

• Ensure all API services are in a healthy state and available:

```
kubectl get apiservices
```

- Ensure the Astra FQDN you plan to use is routable to this cluster. This means that you either have a DNS entry in your internal DNS server or you are using a core URL route that is already registered.
- If a cert-manager already exists in the cluster, you need to perform some prerequisite steps so that Astra Control Center does not install its own cert-manager.

About this task

The Astra Control Center installation process does the following:

- Installs the Astra components into the netapp-acc (or custom-named) namespace.
- · Creates a default account.
- Establishes a default administrative user email address and default one-time password. This user is assigned the Owner role in the system that is needed for first time login to the UI.
- Helps you determine that all Astra Control Center pods are running.
- Installs the Astra UI.



(Applies to the Astra Data Store Early Access Program (EAP) release only) If you intend to manage Astra Data Store using Astra Control Center and enable VMware workflows, deploy Astra Control Center only on the pcloud namespace and not on the netapp-acc namespace or a custom namespace described in the steps of this procedure.



Do not execute the following command during the entirety of the installation process to avoid deleting all Astra Control Center pods: kubectl delete -f astra_control_center_operator_deploy.yaml



If you are using Red Hat's Podman instead of Docker Engine, Podman commands can be used in place of Docker commands.

Steps

To install Astra Control Center, do the following steps:

- Download and unpack the Astra Control Center bundle
- Install the NetApp Astra kubectl plugin
- · Add the images to your local registry
- Set up namespace and secret for registries with auth requirements
- · Install the Astra Control Center operator
- · Configure Astra Control Center
- Complete Astra Control Center and operator installation
- · Verify system status
- Set up ingress for load balancing
- Log in to the Astra Control Center UI

Download and unpack the Astra Control Center bundle

- 1. Download the Astra Control Center bundle (astra-control-center-[version].tar.gz) from the NetApp Support Site.
- 2. Download the zip of Astra Control Center certificates and keys from the NetApp Support Site.
- 3. (Optional) Use the following command to verify the signature of the bundle:

```
openssl dgst -sha256 -verify AstraControlCenter-public.pub -signature astra-control-center-[version].tar.gz.sig astra-control-center-[version].tar.gz
```

4. Extract the images:

```
tar -vxzf astra-control-center-[version].tar.gz
```

Install the NetApp Astra kubectl plugin

The NetApp Astra kubectl command line plugin saves time when performing common tasks associated with deploying and upgrading Astra Control Center.

What you'll need

NetApp provides binaries for the plugin for different CPU architectures and operating systems. You need to know which CPU and operating system you have before you perform this task. On Linux and Mac operating systems, you can use the uname -a command to gather this information.

Steps

1. List the available NetApp Astra kubectl plugin binaries, and note the name of the file you need for your operating system and CPU architecture:

```
ls kubectl-astra/
```

2. Copy the file to the same location as the standard kubectl utility. In this example, the kubectl utility is located in the /usr/local/bin directory. Replace <binary-name> with the name of the file you need:

```
cp kubectl-astra/<binary-name> /usr/local/bin/kubectl-astra
```

Add the images to your local registry

1. Complete the appropriate step sequence for your container engine:

Docker

1. Change to the Astra directory:

```
cd acc
```

- 2. Push the package images in the Astra Control Center image directory to your local registry. Make the following substitutions before running the command:
 - Replace BUNDLE_FILE with the name of the Astra Control bundle file (for example, acc.manifest.yaml).
 - Replace MY REGISTRY with the URL of the Docker repository.
 - Replace MY REGISTRY USER with the user name.
 - Replace MY_REGISTRY_TOKEN with an authorized token for the registry.

```
kubectl astra packages push-images -m BUNDLE_FILE -r MY_REGISTRY
-u MY_REGISTRY_USER -p MY_REGISTRY_TOKEN
```

Podman

1. Log in to your registry:

```
podman login [your_registry_path]
```

2. Run the following script, making the <YOUR_REGISTRY> substitution as noted in the comments:

```
# You need to be at the root of the tarball.
# You should see these files to confirm correct location:
  acc.manifest.yaml
   acc/
# Replace <YOUR REGISTRY> with your own registry (e.g.
registry.customer.com or registry.customer.com/testing, etc..)
export REGISTRY=<YOUR REGISTRY>
export PACKAGENAME=acc
export PACKAGEVERSION=22.08.1-26
export DIRECTORYNAME=acc
for astraImageFile in $(ls ${DIRECTORYNAME}/images/*.tar); do
  # Load to local cache
 astraImage=$(podman load --input ${astraImageFile} | sed 's/Loaded
image: //')
  # Remove path and keep imageName.
  astraImageNoPath=$(echo ${astraImage} | sed 's:.*/::')
  # Tag with local image repo.
  podman tag ${astraImage} ${REGISTRY}/netapp/astra/${PACKAGENAME}
/${PACKAGEVERSION}/${astraImageNoPath}
  # Push to the local repo.
  podman push ${REGISTRY}/netapp/astra/${PACKAGENAME}/
${PACKAGEVERSION}/${astraImageNoPath}
done
```

Set up namespace and secret for registries with auth requirements

1. Export the KUBECONFIG for the Astra Control Center host cluster:

```
export KUBECONFIG=[file path]
```

- 2. If you use a registry that requires authentication, you need to do the following:
 - a. Create the netapp-acc-operator namespace:

```
kubectl create ns netapp-acc-operator
```

Response:

```
namespace/netapp-acc-operator created
```

b. Create a secret for the netapp-acc-operator namespace. Add Docker information and run the following command:



The placeholder your_registry_path should match the location of the images that you uploaded earlier (for example,

[Registry_URL]/netapp/astra/astracc/22.08.1-26).

kubectl create secret docker-registry astra-registry-cred -n netappacc-operator --docker-server=[your_registry_path] --docker
-username=[username] --docker-password=[token]

Sample response:

secret/astra-registry-cred created



If you delete the namespace after the secret is generated, you need to regenerate the secret for the namespace after the namespace is recreated.

c. Create the netapp-acc (or custom named) namespace.

kubectl create ns [netapp-acc or custom namespace]

Sample response:

namespace/netapp-acc created

d. Create a secret for the netapp-acc (or custom named) namespace. Add Docker information and run the following command:

kubectl create secret docker-registry astra-registry-cred -n [netappacc or custom namespace] --docker-server=[your_registry_path]
--docker-username=[username] --docker-password=[token]

Response

secret/astra-registry-cred created

e. (Optional) If you want the cluster to be automatically managed by Astra Control Center after

installation, make sure that you provide the kubeconfig as a secret within the Astra Control Center namespace you intend to deploy into using this command:

kubectl create secret generic [acc-kubeconfig-cred or custom secret
name] --from-file=<path-to-your-kubeconfig> -n [netapp-acc or custom
namespace]

Install the Astra Control Center operator

1. Change the directory:

cd manifests

2. Edit the Astra Control Center operator deployment YAML

(astra_control_center_operator_deploy.yaml) to refer to your local registry and secret.

```
vim astra control center operator deploy.yaml
```



An annotated sample YAML follows these steps.

a. If you use a registry that requires authentication, replace the default line of imagePullSecrets: [] with the following:

```
imagePullSecrets:
- name: <astra-registry-cred>
```

- b. Change [your_registry_path] for the kube-rbac-proxy image to the registry path where you pushed the images in a previous step.
- c. Change [your_registry_path] for the acc-operator-controller-manager image to the registry path where you pushed the images in a previous step.
- d. (For installations using Astra Data Store preview) See this known issue regarding storage class provisioners and additional changes you will need to make to the YAML.

```
apiVersion: apps/v1
kind: Deployment
metadata:
  labels:
    control-plane: controller-manager
  name: acc-operator-controller-manager
 namespace: netapp-acc-operator
spec:
 replicas: 1
  selector:
    matchLabels:
      control-plane: controller-manager
  template:
   metadata:
      labels:
        control-plane: controller-manager
    spec:
      containers:
      - args:
        - --secure-listen-address=0.0.0.0:8443
        - --upstream=http://127.0.0.1:8080/
        - --logtostderr=true
        - -v=10
        image: [your registry path]/kube-rbac-proxy:v4.8.0
        name: kube-rbac-proxy
        ports:
        - containerPort: 8443
         name: https
      - args:
        - --health-probe-bind-address=:8081
        - --metrics-bind-address=127.0.0.1:8080
        - --leader-elect
        command:
        - /manager
        env:
        - name: ACCOP LOG LEVEL
          value: "2"
        image: [your registry path]/acc-operator:[version x.y.z]
        imagePullPolicy: IfNotPresent
      imagePullSecrets: []
```

3. Install the Astra Control Center operator:

```
kubectl apply -f astra_control_center_operator_deploy.yaml
```

Sample response:

```
namespace/netapp-acc-operator created
customresourcedefinition.apiextensions.k8s.io/astracontrolcenters.astra.
netapp.io created
role.rbac.authorization.k8s.io/acc-operator-leader-election-role created
clusterrole.rbac.authorization.k8s.io/acc-operator-manager-role created
clusterrole.rbac.authorization.k8s.io/acc-operator-metrics-reader
created
clusterrole.rbac.authorization.k8s.io/acc-operator-proxy-role created
rolebinding.rbac.authorization.k8s.io/acc-operator-leader-election-
rolebinding created
clusterrolebinding.rbac.authorization.k8s.io/acc-operator-manager-
rolebinding created
clusterrolebinding.rbac.authorization.k8s.io/acc-operator-proxy-
rolebinding created
configmap/acc-operator-manager-config created
service/acc-operator-controller-manager-metrics-service created
deployment.apps/acc-operator-controller-manager created
```

4. Verify pods are running:

```
kubectl get pods -n netapp-acc-operator
```

Configure Astra Control Center

1. Edit the Astra Control Center custom resource (CR) file (astra_control_center_min.yaml) to make account, autoSupport, registry, and other necessary configurations:



astra_control_center_min.yaml is the default CR and is suitable for most installations. Familiarize yourself with all CR options and their potential values to ensure you deploy Astra Control Center correctly for your environment. If additional customizations are required for your environment, you can use astra_control_center.yaml as an alternative CR.

vim astra control center min.yaml



If you are using a registry that does not require authorization, you must delete the secret line within imageRegistry or the installation will fail.

- a. Change [your_registry_path] to the registry path where you pushed the images in the previous step.
- b. Change the accountName string to the name you want to associate with the account.

- c. Change the astraAddress string to the FQDN you want to use in your browser to access Astra. Do not use http://orhttps://in the address. Copy this FQDN for use in a later step.
- d. Change the email string to the default initial administrator address. Copy this email address for use in a later step.
- e. Change enrolled for AutoSupport to false for sites without internet connectivity or retain true for connected sites.
- f. If you use an external cert-manager, add the following lines to spec:

```
spec:
   crds:
   externalCertManager: true
```

- g. (Optional) Add a first name firstName and last name lastName of the user associated with the account. You can perform this step now or later within the UI.
- h. (Optional) Change the storageClass value to another Trident storageClass resource if required by your installation.
- i. (Optional) If you want the cluster to be automatically managed by Astra Control Center after installation and you have already created the secret containing the kubeconfig for this cluster, provide the name of the secret by adding a new field to this YAML file called astraKubeConfigSecret: "acckubeconfig-cred or custom secret name"
- j. Complete one of the following steps:
 - Other ingress controller (ingressType:Generic): This is the default action with Astra Control Center. After Astra Control Center is deployed, you will need to configure the ingress controller to expose Astra Control Center with a URL.

The default Astra Control Center installation sets up its gateway (service/traefik) to be of the type ClusterIP. This default installation requires you to additionally set up a Kubernetes IngressController/Ingress to route traffic to it. If you want to use an ingress, see Set up ingress for load balancing.

• Service load balancer (ingressType:AccTraefik): If you don't want to install an IngressController or create an Ingress resource, set ingressType to AccTraefik.

This deploys the Astra Control Center traefik gateway as a Kubernetes LoadBalancer type service.

Astra Control Center uses a service of the type "LoadBalancer" (svc/traefik in the Astra Control Center namespace), and requires that it be assigned an accessible external IP address. If load balancers are permitted in your environment and you don't already have one configured, you can use MetalLB or another external service load balancer to assign an external IP address to the service. In the internal DNS server configuration, you should point the chosen DNS name for Astra Control Center to the load-balanced IP address.



For details about the service type of "LoadBalancer" and ingress, see Requirements.

```
apiVersion: astra.netapp.io/v1
kind: AstraControlCenter
metadata:
  name: astra
spec:
  accountName: "Example"
  astraVersion: "ASTRA VERSION"
  astraAddress: "astra.example.com"
  astraKubeConfigSecret: "acc-kubeconfig-cred or custom secret name"
  ingressType: "Generic"
  autoSupport:
    enrolled: true
  email: "[admin@example.com]"
  firstName: "SRE"
  lastName: "Admin"
  imageRegistry:
   name: "[your registry path]"
    secret: "astra-registry-cred"
  storageClass: "ontap-gold"
```

Complete Astra Control Center and operator installation

1. If you didn't already do so in a previous step, create the netapp-acc (or custom) namespace:

```
kubectl create ns [netapp-acc or custom namespace]
```

Sample response:

```
namespace/netapp-acc created
```

2. Install Astra Control Center in the netapp-acc (or your custom) namespace:

```
kubectl apply -f astra_control_center_min.yaml -n [netapp-acc or custom
namespace]
```

Sample response:

```
astracontrolcenter.astra.netapp.io/astra created
```

Verify system status



If you prefer to use OpenShift, you can use comparable oc commands for verification steps.

1. Verify that all system components installed successfully.

```
kubectl get pods -n [netapp-acc or custom namespace]
```

Each pod should have a status of Running. It may take several minutes before the system pods are deployed.

Sample response

NAME	READY	STATUS	RESTARTS
AGE			
acc-helm-repo-6b44d68d94-d8m55 13m	1/1	Running	0
activity-78f99ddf8-hltct	1/1	Running	0
10m			
api-token-authentication-457nl 9m28s	1/1	Running	0
api-token-authentication-dgwsz 9m28s	1/1	Running	0
api-token-authentication-hmqqc 9m28s	1/1	Running	0
asup-75fd554dc6-m6qzh	1/1	Running	0
9m38s authentication-6779b4c85d-92gds	1/1	Running	0
8m11s bucketservice-7cc767f8f8-lqwr8	1/1	Running	0
9m31s certificates-549fd5d6cb-5kmd6	1/1	Running	0
9m56s		_	
certificates-549fd5d6cb-bkjh9 9m56s	1/1	Running	0
cloud-extension-7bcb7948b-hn8h2	1/1	Running	0
10m			
cloud-insights-service-56ccf86647-fgg69 9m46s	1/1	Running	0
composite-compute-677685b9bb-7vgsf 10m	1/1	Running	0
composite-volume-657d6c5585-dnq79 9m49s	1/1	Running	0
credentials-755fd867c8-vrlmt	1/1	Running	0
11m entitlement-86495cdf5b-nwhh2	1/1	Running	2
10m			
features-5684fb8b56-8d6s8 10m	1/1	Running	0
fluent-bit-ds-rhx7v	1/1	Running	0
7m48s fluent-bit-ds-rjms4	1/1	Running	0
7m48s	, <u>-</u>		
fluent-bit-ds-zf5ph 7m48s	1/1	Running	0
graphql-server-66d895f544-w6hjd 3m29s	1/1	Running	0

identity-744df448d5-rlcmm	1/1	Running	0
influxdb2-0	1/1	Running	0
13m			
keycloak-operator-75c965cc54-z7csw	1/1	Running	0
8m16s krakend-798d6df96f-9z2sk	1 /1	D	0
3m26s	1/1	Running	0
license-5fb7d75765-f8mjg 9m50s	1/1	Running	0
login-ui-7d5b7df85d-12s7s	1/1	Running	0
3m20s		-	
loki-0	1/1	Running	0
13m			
metrics-facade-599b9d7fcc-gtmgl 9m40s	1/1	Running	0
monitoring-operator-67cc74f844-cdplp	2/2	Running	0
8m11s			
nats-0	1/1	Running	0
13m			
nats-1	1/1	Running	0
13m	1 /1		0
nats-2	1/1	Running	0
12m nautilus-769f5b74cd-k5jxm	1/1	Running	0
9m42s	1/1	Railiting	O
nautilus-769f5b74cd-kd9gd	1/1	Running	0
8m59s		-	
openapi-84f6ccd8ff-76kvp	1/1	Running	0
9m34s			
packages-6f59fc67dc-4g2f5	1/1	Running	0
9m52s	1 /1	D	0
polaris-consul-consul-server-0 13m	1/1	Running	0
polaris-consul-consul-server-1	1/1	Running	0
13m	,	. ,	
polaris-consul-consul-server-2	1/1	Running	0
13m			
polaris-keycloak-0	1/1	Running	0
8m7s			
polaris-keycloak-1	1/1	Running	0
5m49s	1 /1		0
polaris-keycloak-2	1/1	Running	0
5m15s polaris-keycloak-db-0	1/1	Running	0
8m6s	1 / 1	ramming	J

polaris-keycloak-db-1	1/1	Running	0
5m49s			
polaris-keycloak-db-2 4m57s	1/1	Running	0
polaris-mongodb-0 13m	2/2	Running	0
polaris-mongodb-1 12m	2/2	Running	0
polaris-mongodb-2 12m	2/2	Running	0
polaris-ui-565f56bf7b-zwr8b 3m19s	1/1	Running	0
polaris-vault-0 13m	1/1	Running	0
polaris-vault-1 13m	1/1	Running	0
polaris-vault-2 13m	1/1	Running	0
public-metrics-6d86d66444-2wbzl 9m30s	1/1	Running	0
storage-backend-metrics-77c5d98dcd-dbhg5	1/1	Running	0
9m44s storage-provider-78c885f57c-6zcv4	1/1	Running	0
9m36s telegraf-ds-212m9	1/1	Running	0
7m48s telegraf-ds-qfzgh	1/1	Running	0
7m48s telegraf-ds-shrms	1/1	Running	0
7m48s telegraf-rs-bjpkt	1/1	Running	0
7m48s telemetry-service-6684696c64-qzfdf	1/1	Running	0
10m tenancy-6596b6c54d-vmpsm	1/1	Running	0
10m traefik-7489dc59f9-6mnst	1/1	Running	0
3m19s traefik-7489dc59f9-xrkgg	1/1	Running	0
3m4s trident-svc-6c8dc458f5-jswcl	1/1	Running	0
10m vault-controller-6b954f9b76-gz9nm	1/1	Running	0
11m	•	9	

2. (Optional) To ensure the installation is completed, you can watch the acc-operator logs using the following command.

```
kubectl logs deploy/acc-operator-controller-manager -n netapp-acc-operator -c manager -f
```



accHost cluster registration is one of the last operations, and if it fails it will not cause deployment to fail. In the event of a cluster registration failure indicated in the logs, you can attempt registration again through the add cluster workflow in the UI or API.

3. When all the pods are running, verify that the installation was successful (READY is True) and get the one-time password you will use when you log in to Astra Control Center:

```
kubectl get AstraControlCenter -n netapp-acc
```

Response:

```
NAME UUID

READY
astra ACC-9aa5fdae-4214-4cb7-9976-5d8b4c0ce27f 22.08.1-26
10.111.111 True
```



Copy the UUID value. The password is ACC- followed by the UUID value (ACC-[UUID] or, in this example, ACC-9aa5fdae-4214-4cb7-9976-5d8b4c0ce27f).

Set up ingress for load balancing

You can set up a Kubernetes ingress controller that manages external access to services, such as load balancing in a cluster.

This procedure explains how to set up an ingress controller (ingressType:Generic). This is the default action with Astra Control Center. After Astra Control Center is deployed, you will need to configure the ingress controller to expose Astra Control Center with a URL.



If you don't want to set up an ingress controller, you can set ingressType:AccTraefik). Astra Control Center uses a service of the type "LoadBalancer" (svc/traefik in the Astra Control Center namespace), and requires that it be assigned an accessible external IP address. If load balancers are permitted in your environment and you don't already have one configured, you can use MetalLB or another external service load balancer to assign an external IP address to the service. In the internal DNS server configuration, you should point the chosen DNS name for Astra Control Center to the load-balanced IP address. For details about the service type of "LoadBalancer" and ingress, see Requirements.

The steps differ depending on the type of ingress controller you use:

· Istio ingress

- Nginx ingress controller
- · OpenShift ingress controller

What you'll need

- The required ingress controller should already be deployed.
- The ingress class corresponding to the ingress controller should already be created.
- You are using Kubernetes versions between and including v1.19 and v1.22.

Steps for Istio ingress

1. Configure Istio ingress.



This procedure assumes that Istio is deployed using the "default" configuration profile.

2. Gather or create the desired certificate and private key file for the Ingress Gateway.

You can use a CA-signed or self-signed certificate. The common name must be the Astra address (FQDN).

Sample command:

```
openssl req -x509 -nodes -days365-newkey rsa:2048 -keyout tls.key -out tls.crt
```

3. Create a secret tls secret name of type kubernetes.io/tls for a TLS private key and certificate in the istio-system namespace as described in TLS secrets.

Sample command:

```
kubectl create secret tls [tls secret name]
--key="tls.key"
--cert="tls.crt" -n istio-system
```



The name of the secret should match the spec.tls.secretName provided in istio-ingress.yaml file.

4. Deploy an ingress resource in netapp-acc (or custom-named) namespace using either the v1beta1 (deprecated in Kubernetes version less than or 1.22) or v1 resource type for either a deprecated or a new schema:

Output:

```
apiVersion: networking.k8s.io/v1beta1
kind: IngressClass
metadata:
  name: istio
spec:
  controller: istio.io/ingress-controller
apiVersion: networking.k8s.io/v1beta1
kind: Ingress
metadata:
  name: ingress
  namespace: istio-system
spec:
 ingressClassName: istio
 tls:
 - hosts:
   - <ACC addess>
    secretName: [tls secret name]
  rules:
  - host: [ACC addess]
   http:
      paths:
      - path: /
        pathType: Prefix
        backend:
          serviceName: traefik
          servicePort: 80
```

For the v1 new schema, follow this sample:

```
kubectl apply -f istio-Ingress.yaml
```

Output:

```
apiVersion: networking.k8s.io/v1
kind: IngressClass
metadata:
  name: istio
spec:
  controller: istio.io/ingress-controller
apiVersion: networking.k8s.io/v1
kind: Ingress
metadata:
  name: ingress
  namespace: istio-system
spec:
  ingressClassName: istio
  tls:
  - hosts:
    - <ACC addess>
    secretName: [tls secret name]
  rules:
  - host: [ACC addess]
    http:
      paths:
      - path: /
        pathType: Prefix
        backend:
          service:
            name: traefik
            port:
              number: 80
```

- 5. Deploy Astra Control Center as usual.
- 6. Check the status of the ingress:

```
kubectl get ingress -n netapp-acc

NAME CLASS HOSTS ADDRESS PORTS AGE
ingress istio astra.example.com 172.16.103.248 80, 443 1h
```

Steps for Nginx ingress controller

- 1. Create a secret of type kubernetes.io/tls for a TLS private key and certificate in netapp-acc (or custom-named) namespace as described in TLS secrets.
- 2. Deploy an ingress resource in netapp-acc (or custom-named) namespace using either the v1beta1 (deprecated in Kubernetes version less than or 1.22) or v1 resource type for either a deprecated or a new schema:

a. For a v1beta1 deprecated schema, follow this sample:

```
apiVersion: extensions/v1beta1
Kind: IngressClass
metadata:
 name: ingress-acc
 namespace: [netapp-acc or custom namespace]
 annotations:
    kubernetes.io/ingress.class: [class name for nginx controller]
spec:
 tls:
  - hosts:
   - <ACC address>
    secretName: [tls secret name]
 rules:
  - host: [ACC address]
   http:
      paths:
      - backend:
        serviceName: traefik
        servicePort: 80
        pathType: ImplementationSpecific
```

b. For the v1 new schema, follow this sample:

```
apiVersion: networking.k8s.io/v1
kind: Ingress
metadata:
  name: netapp-acc-ingress
  namespace: [netapp-acc or custom namespace]
spec:
  ingressClassName: [class name for nginx controller]
  - hosts:
    - <ACC address>
    secretName: [tls secret name]
  rules:
  - host: <ACC addess>
    http:
      paths:
        - path:
          backend:
            service:
              name: traefik
              port:
                number: 80
          pathType: ImplementationSpecific
```

Steps for OpenShift ingress controller

- 1. Procure your certificate and get the key, certificate, and CA files ready for use by the OpenShift route.
- 2. Create the OpenShift route:

```
oc create route edge --service=traefik
--port=web -n [netapp-acc or custom namespace]
--insecure-policy=Redirect --hostname=<ACC address>
--cert=cert.pem --key=key.pem
```

Log in to the Astra Control Center UI

After installing Astra Control Center, you will change the password for the default administrator and log in to the Astra Control Center UI dashboard.

Steps

- In a browser, enter the FQDN you used in the astraAddress in the astra_control_center_min.yaml CR when you installed Astra Control Center.
- 2. Accept the self-signed certificates when prompted.



You can create a custom certificate after login.

 At the Astra Control Center login page, enter the value you used for email in astra_control_center_min.yaml CR when you installed Astra Control Center, followed by the onetime password (ACC-[UUID]).



If you enter an incorrect password three times, the admin account will be locked for 15 minutes.

- 4. Select Login.
- 5. Change the password when prompted.



If this is your first login and you forget the password and no other administrative user accounts have yet been created, contact NetApp Support for password recovery assistance.

6. (Optional) Remove the existing self-signed TLS certificate and replace it with a custom TLS certificate signed by a Certificate Authority (CA).

Troubleshoot the installation

If any of the services are in Error status, you can inspect the logs. Look for API response codes in the 400 to 500 range. Those indicate the place where a failure happened.

Steps

1. To inspect the Astra Control Center operator logs, enter the following:

```
kubectl logs --follow -n netapp-acc-operator $(kubectl get pods -n
netapp-acc-operator -o name) -c manager
```

What's next

Complete the deployment by performing setup tasks.

Understand Astra Control Center cluster CR options

You can use the following Astra Control Center cluster CR options to create custom configurations during deployment.

Setting	Туре	Use	Value Example	Description
astraVersion	string	Required	1.5.2	Version of AstraControlCenter to deploy. You are provided a Helm repository with a corresponding version.

Setting	Туре	Use	Value Example	Description
astraAddress	string	Required	astra.example.com	Defines how Astra will be found in the data center. This IP address and/or DNS A record must be created prior to provisioning Astra Control Center.
accountName	string	Required	Example	Astra Control Center account name. There can be only one.
email	string	Required	admin@example.co m	The username of the administrator to be added as the first user of Astra. This email address will be notified by Astra Control as events warrant.
firstName	string	Required	SRE	The first name of the administrator supporting Astra.
lastName	string	Required	Admin	The last name of the administrator supporting Astra.
storageClass	string	Optional (this is the default value)	ontap-gold	The storage class to be used for PVCs. If not set, the default storage class will be used.
volumeReclaimPolic y	Undefined	Optional	Retain	Reclaim policy to be set for persistent volumes.
astraResourcesScal er	string	Required	Default	Scaling options for AstraControlCenter Resource limits. See setting complexities to understand how this settings affects others settings.

Setting	Туре	Use	Value Example	Description
astraKubeConfigSec ret	string	Required	acc-kubeconfig-cred	If this value is present and a secret exists, the operator will attempt to add that KubeConfig to become the first managed cluster.
ingressType	string	Optional	Generic (this is the default value)	The type of ingress Astra Control Center should be configured for. Valid values are Generic and AccTraefik. See setting complexities to understand how this settings affects others settings.
avpDeploy	Boolean	Optional	true (this is the default value)	Option that allows a user to disable deployment of Astra Plugin for VMware vSphere operator.
imageRegistry	Undefined	Optional		The container image registry that is hosting the Astra application images, Astra Control Center Operator, and Astra Control Center Helm Repository.
imageRegistry.name	string	Required if you are using imageRegistry	example.registry.co m/astra	The name of the image registry. Do not prefix with protocol.
imageRegistry.secret	string	Required if you are using imageRegistry	astra-registry-cred	The name of the Kubernetes secret used to authenticate with the image registry.
autoSupport	Undefined	Required		Indicates participation status in NetApp's pro- active support application, NetApp Active IQ. An internet connection is required (port 442) and all support data is anonymized.

Setting	Туре	Use	Value Example	Description
autoSupport.enrolled	Boolean	Optional, but either enrolled or url fields must be selected	false (this value is the default)	Enrolled determines if you want to send anonymous data to NetApp for support purposes. The default election is false and indicates no support data will be sent to NetApp.
autoSupport.url	string	Optional, but either enrolled or url fields must be selected	https://support.netap p.com/asupprod/ post/1.0/postAsup	URL determines where the anonymous data will be sent.
crds	Undefined	Undefined		Options for how Astra Control Center should handle CRDs.
crds.externalTraefik	Boolean	Optional	True (this value is the default)	By default, Astra Control Center will install the required Traefik CRDs. CRDs are cluster-wide objects and installing them may have an impact on other parts of the cluster. You can use this flag to signal to Astra Control Center that these CRDs will be installed and managed by the cluster administrator outside of Astra Control Center.

Setting	Туре	Use	Value Example	Description
crds.externalCertMa nager	Boolean	Optional	True (this value is the default)	By default, Astra Control Center will install the required cert-manager CRDs. CRDs are cluster- wide objects and installing them may have an impact on other parts of the cluster. You can use this flag to signal to Astra Control Center that these CRDs will be installed and managed by the cluster administrator outside of Astra Control Center.
crds.shouldUpgrade	Boolean	Optional	Undefined	Determines if CRDs should be upgraded when Astra Control Center is upgraded.
mtls				Options for how Astra Control Center should implement service to service mTLS in the cluster. See setting complexities to understand how this settings affects others settings
mtls.enabled	Boolean	Optional	true (this value is the default)	By default, Astra Control Center uses mTLS for service-to- service communication. This option should be disabled when using a service mesh to encrypt service-to- service communication instead.

Setting	Туре	Use	Value Example	Description
mtls.certDuration	string	Optional	2140h (this value is the default duration)	The duration of time in hours to use as a certificate lifespan when issuing service TLS certificates. This setting only works when mtls.enabled is set to true.

Configuration combinations and incompatibilities

Some Astra Control Center cluster CR configuration settings greatly affect the way Astra Control Center is installed and could conflict with other settings. The content that follows describes important configuration settings and how to avoid incompatible combinations.

astraResourcesScaler

By default, Astra Control Center deploys with resource requests set for most of the components within Astra. This configuration allows the Astra Control Center software stack to perform better in environments under increased application load and scale.

However, in scenarios using smaller development or test clusters, the CR field AstraResourcesScalar may be set to Off. This disables resource requests and allows for deployment on smaller clusters.

ingressType

There are two valid values for ingressType:

- Generic
- AccTraefik

Generic (default)

When ingressType is set to Generic, Astra Control does not install any ingress resources. The assumption is that the user has a common way of securing and routing traffic through their network to applications running on Kubernetes clusters and they want to use the same mechanisms here. When the user creates an ingress to route traffic to Astra Control, the ingress needs to point to the internal traefik service on port 80. Here is an example of an Nginx ingress resource that works with the Generic ingressType setting.

```
apiVersion: networking.k8s.io/v1
kind: Ingress
metadata:
  name: netapp-acc-ingress
  namespace: [netapp-acc or custom namespace]
spec:
  ingressClassName: [class name for nginx controller]
  - hosts:
    - <ACC address>
    secretName: [tls secret name]
  rules:
  - host: <ACC addess>
    http:
      paths:
        - path:
          backend:
            service:
              name: traefik
              port:
                number: 80
          pathType: ImplementationSpecific
```



When mTLS is disabled using the mtls.enabled setting in the CR, you must use ingressType: Generic.

AccTraefik

When ingressType is set to AccTraefik, Astra Control Center deploys its Traefik gateway as a Kubernetes LoadBalancer type service. Users need to provide an external Load Balancer (like MetalLB) for Astra Control Center to get an external IP.

mtls

The settings used in the CR determine how intra-application communication is secured. It is very important for the user to know ahead of time whether they will be using a service mesh or not.

• enabled=true: When this setting is enabled, Astra will deploy an internal service-to-service communication network that secures all traffic within the application.



Do not cover Astra Control Center in a service mesh while this setting is true.

enabled=false: When this setting is disabled, Astra Control Center will not secure internal traffic and you
must secure Astra namespaces independently with a service mesh.



When mTLS is disabled using the mtls.enabled setting in the CR, you must use ingressType: Generic.



Understand pod security policy restrictions

Astra Control Center supports privilege limitation through pod security policies (PSPs). Pod security policies enable you to limit what users or groups are able to run containers and what privileges those containers can have.

Some Kubernetes distributions, such as RKE2, have a default pod security policy that is too restrictive, and causes problems when installing Astra Control Center.

You can use the information and examples included here to understand the pod security policies that Astra Control Center creates, and configure pod security policies that provide the protection you need without interfering with Astra Control Center functions.

PSPs installed by Astra Control Center

Astra Control Center creates several pod security policies during installation. Some of these are permanent, and some of them are created during certain operations and are removed once the operation is complete.

PSPs created during installation

During Astra Control Center installation, the Astra Control Center operator installs a custom pod security policy, a Role object, and a RoleBinding object to support the deployment of Astra Control Center services in the Astra Control Center namespace.

The new policy and objects have the following attributes:

NAME			PRIV	CAPS	SELINUX	RUNASUSER
FSGROUP	SUPGROUP	READON	LYROOTFS	VOLUMES		
avp-psp			false		RunAsAny	RunAsAny
RunAsAny	RunAsAny	false		*		
netapp-ast	ra-deployment	t-psp	false		RunAsAny	RunAsAny
RunAsAny	RunAsAny	false		*		
<pre>\$ kubectl</pre>	get role					
NAME	get role ra-deployment	t-role		CREATED <i>F</i> 2022-06-2	AT 27T19:34:58Z	
NAME netapp-ast	ra-deployment					
NAME netapp-ast						
NAME netapp-ast \$ kubectl	ra-deployment			2022-06-2		
NAME netapp-ast \$ kubectl NAME AGE	ra-deployment	ing		2022-06-2		loyment-role

PSPs created during backup operations

During backup operations, Astra Control Center creates a dynamic pod security policy, a ClusterRole object,

and a RoleBinding object. These support the backup process, which happens in a separate namespace.

The new policy and objects have the following attributes:

\$ kubectl get psp NAME PRIV CAPS SELINUX RUNASUSER READONLYROOTFS FSGROUP SUPGROUP VOLUMES netapp-astra-backup false DAC READ SEARCH RunAsAny RunAsAny RunAsAny RunAsAny false \$ kubectl get role CREATED AT NAME 2022-07-21T00:00:00Z netapp-astra-backup \$ kubectl get rolebinding NAME AGE ROLE Role/netapp-astra-backup netapp-astra-backup 62s

PSPs created during cluster management

When you manage a cluster, Astra Control Center installs the netapp-monitoring operator in the managed cluster. This operator creates a pod security policy, a ClusterRole object, and a RoleBinding object to deploy telemetry services in the Astra Control Center namespace.

The new policy and objects have the following attributes:

\$ kubectl get psp NAME PRIV CAPS SELINUX READONLYROOTFS RUNASUSER FSGROUP SUPGROUP VOLUMES netapp-monitoring-psp-nkmo AUDIT WRITE, NET ADMIN, NET RAW true RunAsAny RunAsAny RunAsAny RunAsAny false \$ kubectl get role NAME CREATED AT netapp-monitoring-role-privileged 2022-07-21T00:00:00Z \$ kubectl get rolebinding NAME ROLE AGE netapp-monitoring-role-binding-privileged Role/netappmonitoring-role-privileged 2m5s

Enable network communication between namespaces

Some environments use NetworkPolicy constructs to restrict traffic between namespaces. The Astra Control Center operator, Astra Control Center, and the Astra Plugin for VMware vSphere are all in different namespaces. The services in these different namespaces need to be able to communicate with one another. To enable this communication, follow these steps.

Steps

1. Delete any NetworkPolicy resources that exist in the Astra Control Center namespace:

```
$kubectl get networkpolicy -n netapp-acc
```

2. For each NetworkPolicy object that is returned by the preceding command, use the following command to delete it. Replace <OBJECT_NAME> with the name of the returned object:

```
$kubectl delete networkpolicy <OBJECT_NAME> -n netapp-acc
```

3. Apply the following resource file to configure the acc-avp-network-policy object to allow Astra Plugin for VMware vSphere services to make requests to Astra Control Center services. Replace the information in brackets <> with information from your environment:

```
apiVersion: networking.k8s.io/v1
kind: NetworkPolicy
metadata:
  name: acc-avp-network-policy
  namespace: <ACC NAMESPACE NAME> # REPLACE THIS WITH THE ASTRA CONTROL
CENTER NAMESPACE NAME
spec:
 podSelector: {}
  policyTypes:
    - Ingress
  ingress:
    - from:
        - namespaceSelector:
            matchLabels:
              kubernetes.io/metadata.name: <PLUGIN NAMESPACE NAME> #
REPLACE THIS WITH THE ASTRA PLUGIN FOR VMWARE VSPHERE NAMESPACE NAME
```

4. Apply the following resource file to configure the acc-operator-network-policy object to allow the Astra Control Center operator to communicate with Astra Control Center services. Replace the information in brackets <> with information from your environment:

```
apiVersion: networking.k8s.io/v1
kind: NetworkPolicy
metadata:
  name: acc-operator-network-policy
  namespace: <ACC NAMESPACE NAME> # REPLACE THIS WITH THE ASTRA CONTROL
CENTER NAMESPACE NAME
spec:
  podSelector: {}
  policyTypes:
    - Ingress
  ingress:
    - from:
        - namespaceSelector:
            matchLabels:
              kubernetes.io/metadata.name: <NETAPP-ACC-OPERATOR> #
REPLACE THIS WITH THE OPERATOR NAMESPACE NAME
```

Remove resource limitations

Some environments use the ResourceQuotas and LimitRanges objects to prevent the resources in a namespace from consuming all available CPU and memory on the cluster. Astra Control Center does not set maximum limits, so it will not be in compliance with those resources. You need to remove them from the namespaces where you plan to install Astra Control Center.

You can use the following steps to retrieve and remove these quotas and limits. In these examples, the command output is shown immediately after the command.

Steps

1. Get the resource quotas in the netapp-acc namespace:

2. Delete all of the resource quotas by name:

```
$ kubectl delete resourcequota pods-high -n netapp-acc
resourcequota "pods-high" deleted

$ kubectl delete resourcequota pods-low -n netapp-acc
resourcequota "pods-low" deleted

$ kubectl delete resourcequota pods-medium -n netapp-acc
resourcequota "pods-medium" deleted
```

3. Get the limit ranges in the netapp-acc namespace:

4. Delete the limit ranges by name:

```
$kubectl delete limitrange cpu-limit-range -n netapp-acc
```

Configure an external cert-manager

If a cert-manager already exists in your Kubernetes cluster, you need to perform some prerequisite steps so that Astra Control Center does not install its own cert-manager.

Steps

1. Confirm that you have a cert-manager installed:

```
kubectl get pods -A | grep 'cert-manager'
```

Sample response:

```
cert-manager essential-cert-manager-84446f49d5-sf2zd 1/1
Running 0 6d5h
cert-manager essential-cert-manager-cainjector-66dc99cc56-9ldmt 1/1
Running 0 6d5h
cert-manager essential-cert-manager-webhook-56b76db9cc-fjqrq 1/1
Running 0 6d5h
```

2. Create a certificate/key pair for the astraAddress FQDN:

```
openssl req -x509 -nodes -days 365 -newkey rsa:2048 -keyout tls.key -out tls.crt
```

Sample response:

```
Generating a 2048 bit RSA private key
.....+++
writing new private key to 'tls.key'
```

3. Create a secret with previously generated files:

```
kubectl create secret tls selfsigned-tls --key tls.key --cert tls.crt -n
<cert-manager-namespace>
```

Sample response:

```
secret/selfsigned-tls created
```

4. Create a ClusterIssuer file that is **exactly** the following but includes the namespace location where your cert-manager pods are installed:

```
apiVersion: cert-manager.io/v1
kind: ClusterIssuer
metadata:
   name: astra-ca-clusterissuer
   namespace: <cert-manager-namespace>
spec:
   ca:
    secretName: selfsigned-tls
```

```
kubectl apply -f ClusterIssuer.yaml
```

Sample response:

```
clusterissuer.cert-manager.io/astra-ca-clusterissuer created
```

5. Verify that the ClusterIssuer has come up correctly. Ready must be True before you can proceed:

```
kubectl get ClusterIssuer
```

Sample response:

```
NAME READY AGE astra-ca-clusterissuer True 9s
```

6. Complete the Astra Control Center installation process. There is a required configuration step for the Astra Control Center cluster YAML in which you change the CRD value to indicate that the cert-manager is externally installed. You must complete this step during installation so that Astra Control Center recognizes the external cert-manager.

Install Astra Control Center using OpenShift OperatorHub

If you use Red Hat OpenShift, you can install Astra Control Center using the Red Hat certified operator. Use this procedure to install Astra Control Center from the Red Hat Ecosystem Catalog or using the Red Hat OpenShift Container Platform.

After you complete this procedure, you must return to the installation procedure to complete the remaining steps to verify installation success and log on.

What you'll need

- · Before you begin installation, prepare your environment for Astra Control Center deployment.
- From your OpenShift cluster, ensure all cluster operators are in a healthy state (available is true):

```
oc get clusteroperators
```

From your OpenShift cluster, ensure all API services are in a healthy state (available is true):

```
oc get apiservices
```

- Create an FQDN address for Astra Control Center in your data center.
- Obtain the necessary permissions and access to the Red Hat OpenShift Container Platform to perform the installation steps described.
- If a cert-manager already exists in the cluster, you need to perform some prerequisite steps so that Astra Control Center does not install its own cert-manager.

Steps

- Download and unpack the Astra Control Center bundle
- Install the NetApp Astra kubectl plugin
- · Add the images to your local registry
- Find the operator install page
- Install the operator

Install Astra Control Center

Download and unpack the Astra Control Center bundle

- 1. Download the Astra Control Center bundle (astra-control-center-[version].tar.gz) from the NetApp Support Site.
- 2. Download the zip of Astra Control Center certificates and keys from the NetApp Support Site.
- 3. (Optional) Use the following command to verify the signature of the bundle:

```
openssl dgst -sha256 -verify AstraControlCenter-public.pub -signature astra-control-center-[version].tar.gz.sig astra-control-center-[version].tar.gz
```

4. Extract the images:

```
tar -vxzf astra-control-center-[version].tar.gz
```

Install the NetApp Astra kubectl plugin

The NetApp Astra kubectl command line plugin saves time when performing common tasks associated with deploying and upgrading Astra Control Center.

What you'll need

NetApp provides binaries for the plugin for different CPU architectures and operating systems. You need to know which CPU and operating system you have before you perform this task. On Linux and Mac operating systems, you can use the uname -a command to gather this information.

Steps

1. List the available NetApp Astra kubectl plugin binaries, and note the name of the file you need for your operating system and CPU architecture:

```
ls kubectl-astra/
```

2. Copy the file to the same location as the standard kubectl utility. In this example, the kubectl utility is located in the /usr/local/bin directory. Replace <binary-name> with the name of the file you need:

```
cp kubectl-astra/<binary-name> /usr/local/bin/kubectl-astra
```

Add the images to your local registry

1. Complete the appropriate step sequence for your container engine:

Docker

1. Change to the Astra directory:

```
cd acc
```

- 2. Push the package images in the Astra Control Center image directory to your local registry. Make the following substitutions before running the command:
 - Replace BUNDLE_FILE with the name of the Astra Control bundle file (for example, acc.manifest.yaml).
 - Replace MY REGISTRY with the URL of the Docker repository.
 - Replace MY REGISTRY USER with the user name.
 - Replace MY_REGISTRY_TOKEN with an authorized token for the registry.

```
kubectl astra packages push-images -m BUNDLE_FILE -r MY_REGISTRY
-u MY_REGISTRY_USER -p MY_REGISTRY_TOKEN
```

Podman

1. Log in to your registry:

```
podman login [your_registry_path]
```

2. Run the following script, making the <YOUR_REGISTRY> substitution as noted in the comments:


```
# You need to be at the root of the tarball.
# You should see these files to confirm correct location:
  acc.manifest.yaml
   acc/
# Replace <YOUR REGISTRY> with your own registry (e.g.
registry.customer.com or registry.customer.com/testing, etc..)
export REGISTRY=<YOUR REGISTRY>
export PACKAGENAME=acc
export PACKAGEVERSION=22.08.1-26
export DIRECTORYNAME=acc
for astraImageFile in $(ls ${DIRECTORYNAME}/images/*.tar); do
  # Load to local cache
 astraImage=$(podman load --input ${astraImageFile} | sed 's/Loaded
image: //')
  # Remove path and keep imageName.
  astraImageNoPath=$(echo ${astraImage} | sed 's:.*/::')
  # Tag with local image repo.
  podman tag ${astraImage} ${REGISTRY}/netapp/astra/${PACKAGENAME}
/${PACKAGEVERSION}/${astraImageNoPath}
  # Push to the local repo.
  podman push ${REGISTRY}/netapp/astra/${PACKAGENAME}/
${PACKAGEVERSION}/${astraImageNoPath}
done
```

Find the operator install page

- 1. Complete one of the following procedures to access the operator install page:
 - ° From Red Hat Openshift web console:



- a. Log in to the OpenShift Container Platform UI.
- b. From the side menu, select **Operators > OperatorHub**.
- c. Select the NetApp Astra Control Center operator.
- d. Select Install.
- ° From Red Hat Ecosystem Catalog:



- a. Select the NetApp Astra Control Center operator.
- b. Select **Deploy and Use**.

Install the operator

1. Complete the **Install Operator** page and install the operator:



The operator will be available in all cluster namespaces.

- a. Select the operator namespace or netapp-acc-operator namespace will be created automatically as part of the operator installation.
- b. Select a manual or automatic approval strategy.



Manual approval is recommended. You should only have a single operator instance running per cluster.

c. Select Install.



If you selected a manual approval strategy, you will be prompted to approve the manual install plan for this operator.

2. From the console, go to the OperatorHub menu and confirm that the operator installed successfully.

Install Astra Control Center

- 1. From the console within the details view of the Astra Control Center operator, select Create instance in the Provided APIs section.
- Complete the Create AstraControlCenter form field:
 - a. Keep or adjust the Astra Control Center name.
 - b. (Optional) Enable or disable Auto Support. Retaining Auto Support functionality is recommended.
 - c. Enter the Astra Control Center address. Do not enter http://orhttps://in the address.

- d. Enter the Astra Control Center version; for example, 21.12.60.
- e. Enter an account name, email address, and admin last name.
- f. Retain the default volume reclaim policy.
- g. In Image Registry, enter your local container image registry path. Do not enter http://orhttps:// in the address.
- h. If you use a registry that requires authentication, enter the secret.
- i. Enter the admin first name.
- j. Configure resources scaling.
- k. Retain the default storage class.
- I. Define CRD handling preferences.
- 3. Select Create.

What's next

Verify the successful installation of Astra Control Center and complete the remaining steps to log in. Additionally, you will complete the deployment by also performing setup tasks.

Install Astra Control Center with a Cloud Volumes ONTAP storage backend

With Astra Control Center, you can manage your apps in a hybrid cloud environment with self-managed Kubernetes clusters and Cloud Volumes ONTAP instances. You can deploy Astra Control Center in your onpremise Kubernetes clusters or in one of the self-managed Kubernetes clusters in the cloud environment.

With one of these deployments, you can perform app data management operations using Cloud Volumes ONTAP as a storage backend. You can also configure an S3 bucket as the backup target.

To install Astra Control Center in Amazon Web Services (AWS), Google Cloud Platform (GCP) and Microsoft Azure with a Cloud Volumes ONTAP storage backend, perform the following steps depending on your cloud environment.

- Deploy Astra Control Center in Amazon Web Services
- Deploy Astra Control Center in Google Cloud Platform
- Deploy Astra Control Center in Microsoft Azure

You can manage your apps in distributions with self-managed Kubernetes clusters, such with OpenShift Container Platform (OCP). Only self-managed OCP clusters are validated for deploying Astra Control Center.

Deploy Astra Control Center in Amazon Web Services

You can deploy Astra Control Center on a self-managed Kubernetes cluster hosted on an Amazon Web Services (AWS) public cloud.

What you'll need for AWS

Before you deploy Astra Control Center in AWS, you will need the following items:

- Astra Control Center license. See Astra Control Center licensing requirements.
- Meet Astra Control Center requirements.

- NetApp Cloud Central account
- If using OCP, Red Hat OpenShift Container Platform (OCP) permissions (on namespace level to create pods)
- AWS credentials, Access ID and Secret Key with permissions that enable you to create buckets and connectors
- AWS account Elastic Container Registry (ECR) access and login
- AWS hosted zone and Route 53 entry required to access the Astra Control UI

Operational environment requirements for AWS

Astra Control Center requires the following operational environment for AWS:

• Red Hat OpenShift Container Platform 4.8



Ensure that the operating environment you choose to host Astra Control Center meets the basic resource requirements outlined in the environment's official documentation.

Astra Control Center requires the following resources in addition to the environment's resource requirements:

Component	Requirement
Backend NetApp Cloud Volumes ONTAP storage capacity	At least 300GB available
Worker nodes (AWS EC2 requirement)	At least 3 worker nodes total, with 4 vCPU cores and 12GB RAM each
Load balancer	Service type "LoadBalancer" available for ingress traffic to be sent to services in the operational environment cluster
FQDN	A method for pointing the FQDN of Astra Control Center to the load balanced IP address
	Astra Trident 21.04 or newer installed and configured and NetApp ONTAP version 9.5 or newer as a storage backend
Image registry	You must have an existing private registry, such as AWS Elastic Container Registry, to which you can push Astra Control Center build images. You need to provide the URL of the image registry where you will upload the images. The Astra Control Center hosted cluster and the managed cluster must have access to the same image registry to be able to back up and restore apps using the Resticbased image.

Component	Requirement
Astra Trident / ONTAP configuration	Astra Control Center requires that a storage class be created and set as the default storage class. Astra Control Center supports the following ONTAP Kubernetes storage classes that are created when you import your Kubernetes cluster into NetApp Cloud Manager. These are provided by Astra Trident:
	<pre>• vsaworkingenvironment-<>-ha-nas csi.trident.netapp.io</pre>
	<pre>• vsaworkingenvironment-<>-ha-san csi.trident.netapp.io</pre>
	 vsaworkingenvironment-<>-single-nas csi.trident.netapp.io
	<pre>• vsaworkingenvironment-<>-single-san csi.trident.netapp.io</pre>



These requirements assume that Astra Control Center is the only application running in the operational environment. If the environment is running additional applications, adjust these minimum requirements accordingly.



The AWS registry token expires in 12 hours, after which you will have to renew the Docker image registry secret.

Overview of deployment for AWS

Here is an overview of the process to install Astra Control Center for AWS with Cloud Volumes ONTAP as a storage backend.

Each of these steps is explained in more detail below.

- 1. Ensure that you have sufficient IAM permissions.
- 2. Install a RedHat OpenShift cluster on AWS.
- 3. Configure AWS.
- 4. Configure NetApp Cloud Manager.
- 5. Install Astra Control Center.

Ensure that you have sufficient IAM permissions

Ensure that you have sufficient IAM roles and permissions that enable you to install a RedHat OpenShift cluster and a NetApp Cloud Manager Connector.

See Initial AWS credentials.

Install a RedHat OpenShift cluster on AWS

Install a RedHat OpenShift Container Platform cluster on AWS.

For installation instructions, see Installing a cluster on AWS in OpenShift Container Platform.

Configure AWS

Next, configure AWS to create a virtual network, set up EC2 compute instances, create an AWS S3 bucket, create an Elastic Container Register (ECR) to host the Astra Control Center images, and push the images to this registry.

Follow the AWS documentation to complete the following steps. See AWS installation documentation.

- 1. Create an AWS virtual network.
- 2. Review the EC2 compute instances. This can be a bare metal server or VMs in AWS.
- If the instance type does not already match the Astra minimum resource requirements for master and worker nodes, change the instance type in AWS to meet the Astra requirements. See Astra Control Center requirements.
- 4. Create at least one AWS S3 bucket to store your backups.
- 5. Create an AWS Elastic Container Registry (ECR) to host all the ACC images.



If you do not create the ECR, Astra Control Center cannot access monitoring data from a cluster containing Cloud Volumes ONTAP with an AWS backend. The issue is caused when the cluster you try to discover and manage using Astra Control Center does not have AWS ECR access.

6. Push the ACC images to your defined registry.



The AWS Elastic Container Registry (ECR) token expires after 12 hours and causes cross-cluster clone operations to fail. This issue occurs when managing a storage backend from Cloud Volumes ONTAP configured for AWS. To correct this issue, authenticate with the ECR again and generate a new secret for clone operations to resume successfully.

Here's an example of an AWS deployment:



Configure NetApp Cloud Manager

Using Cloud Manager, create a workspace, add a connector to AWS, create a working environment, and import the cluster.

Follow the Cloud Manager documentation to complete the following steps. See the following:

- Getting started with Cloud Volumes ONTAP in AWS.
- Create a connector in AWS using Cloud Manager

Steps

- 1. Add your credentials to Cloud Manager.
- 2. Create a workspace.
- 3. Add a connector for AWS. Choose AWS as the Provider.
- 4. Create a working environment for your cloud environment.
 - a. Location: "Amazon Web Services (AWS)"
 - b. Type: "Cloud Volumes ONTAP HA"
- 5. Import the OpenShift cluster. The cluster will connect to the working environment you just created.
 - a. View the NetApp cluster details by selecting K8s > Cluster list > Cluster Details.

- b. In the upper right corner, note the Trident version.
- c. Note the Cloud Volumes ONTAP cluster storage classes showing NetApp as the provisioner.

This imports your Red Hat OpenShift cluster and assigns it a default storage class. You select the storage class.

Trident is automatically installed as part of the import and discovery process.

6. Note all the persistent volumes and volumes in this Cloud Volumes ONTAP deployment.



Cloud Volumes ONTAP can operate as a single node or in High Availability. If HA is enabled, note the HA status and node deployment status running in AWS.

Install Astra Control Center

Follow the standard Astra Control Center installation instructions.



AWS uses the Generic S3 bucket type.

Deploy Astra Control Center in Google Cloud Platform

You can deploy Astra Control Center on a self-managed Kubernetes cluster hosted on a Google Cloud Platform (GCP) public cloud.

What you'll need for GCP

Before you deploy Astra Control Center in GCP, you will need the following items:

- Astra Control Center license. See Astra Control Center licensing requirements.
- Meet Astra Control Center requirements.
- NetApp Cloud Central account
- If using OCP, Red Hat OpenShift Container Platform (OCP) 4.10
- If using OCP, Red Hat OpenShift Container Platform (OCP) permissions (on namespace level to create pods)
- · GCP Service Account with permissions that enable you to create buckets and connectors

Operational environment requirements for GCP



Ensure that the operating environment you choose to host Astra Control Center meets the basic resource requirements outlined in the environment's official documentation.

Astra Control Center requires the following resources in addition to the environment's resource requirements:

Component	Requirement
Backend NetApp Cloud Volumes ONTAP storage capacity	At least 300GB available
Worker nodes (GCP compute requirement)	At least 3 worker nodes total, with 4 vCPU cores and 12GB RAM each

Component	Requirement
Load balancer	Service type "LoadBalancer" available for ingress traffic to be sent to services in the operational environment cluster
FQDN (GCP DNS zone)	A method for pointing the FQDN of Astra Control Center to the load balanced IP address
Astra Trident (installed as part of the Kubernetes cluster discovery in NetApp Cloud Manager)	Astra Trident 21.04 or newer installed and configured and NetApp ONTAP version 9.5 or newer as a storage backend
Image registry	You must have an existing private registry, such as Google Container Registry, to which you can push Astra Control Center build images. You need to provide the URL of the image registry where you will upload the images. You need to enable anonymous access to pull Restic images for backups.
Astra Trident / ONTAP configuration	Astra Control Center requires that a storage class be created and set as the default storage class. Astra Control Center supports the following ONTAP Kubernetes storage classes that are created when you import your Kubernetes cluster into NetApp Cloud Manager. These are provided by Astra Trident: • vsaworkingenvironment-<>-ha-nas csi.trident.netapp.io • vsaworkingenvironment-<>-ha-san csi.trident.netapp.io • vsaworkingenvironment-<>-single-nas csi.trident.netapp.io • vsaworkingenvironment-<>-single-san csi.trident.netapp.io



These requirements assume that Astra Control Center is the only application running in the operational environment. If the environment is running additional applications, adjust these minimum requirements accordingly.

Overview of deployment for GCP

Here is an overview of the process to install Astra Control Center on a self-managed OCP cluster in GCP with Cloud Volumes ONTAP as a storage backend.

Each of these steps is explained in more detail below.

- 1. Install a RedHat OpenShift cluster on GCP.
- 2. Create a GCP Project and Virtual Private Cloud.

- 3. Ensure that you have sufficient IAM permissions.
- 4. Configure GCP.
- 5. Configure NetApp Cloud Manager.
- 6. Install and configure Astra Control Center.

Install a RedHat OpenShift cluster on GCP

The first step is to install a RedHat OpenShift cluster on GCP.

For installation instructions, see the following:

- · Installing an OpenShift cluster in GCP
- Creating a GCP Service Account

Create a GCP Project and Virtual Private Cloud

Create at least one GCP Project and Virtual Private Cloud (VPC).



OpenShift might create its own resource groups. In addition to these, you should also define a GCP VPC. Refer to OpenShift documentation.

You might want to create a platform cluster resource group and a target app OpenShift cluster resource group.

Ensure that you have sufficient IAM permissions

Ensure that you have sufficient IAM roles and permissions that enable you to install a RedHat OpenShift cluster and a NetApp Cloud Manager Connector.

See Initial GCP credentials and permissions.

Configure GCP

Next, configure GCP to create a VPC, set up compute instances, create a Google Cloud Object Storage, create an Google Container Register to host the Astra Control Center images, and push the images to this registry.

Follow the GCP documentation to complete the following steps. See Installing OpenShift cluster in GCP.

- 1. Create a GCP Project and VPC in the GCP that you plan on using for the OCP cluster with CVO backend.
- 2. Review the compute instances. This can be a bare metal server or VMs in GCP.
- If the instance type does not already match the Astra minimum resource requirements for master and worker nodes, change the instance type in GCP to meet the Astra requirements. See Astra Control Center requirements.
- 4. Create at least one GCP Cloud Storage Bucket to store your backups.
- 5. Create a secret, which is required for bucket access.
- Create a Google Container Registry to host all the Astra Control Center images.
- 7. Set up Google Container Registry access for Docker push/pull for all the Astra Control Center images.

Example: ACC images can be pushed to this registry by entering the following script:

```
gcloud auth activate-service-account <service account email address>
--key-file=<GCP Service Account JSON file>
```

This script requires an Astra Control Center manifest file and your Google Image Registry location.

Example:

```
manifestfile=astra-control-center-<version>.manifest
GCP_CR_REGISTRY=<target image repository>
ASTRA_REGISTRY=<source ACC image repository>

while IFS= read -r image; do
    echo "image: $ASTRA_REGISTRY/$image $GCP_CR_REGISTRY/$image"
    root_image=${image*:*}
    echo $root_image
    docker pull $ASTRA_REGISTRY/$image
    docker tag $ASTRA_REGISTRY/$image $GCP_CR_REGISTRY/$image
    docker push $GCP_CR_REGISTRY/$image
    docker push $GCP_CR_REGISTRY/$image
docker control-center-22.04.41.manifest
```

8. Set up DNS zones.

Configure NetApp Cloud Manager

Using Cloud Manager, create a workspace, add a connector to GCP, create a working environment, and import the cluster.

Follow the Cloud Manager documentation to complete the following steps. See Getting started with Cloud Volumes ONTAP in GCP.

What you'll need

Access to the GCP Service Account with the required IAM permissions and roles

Steps

- 1. Add your credentials to Cloud Manager. See Adding GCP accounts.
- 2. Add a connector for GCP.
 - a. Choose "GCP" as the Provider.
 - b. Enter GCP credentials. See Creating a connector in GCP from Cloud Manager.
 - c. Ensure that the connector is running and switch to that connector.
- 3. Create a working environment for your cloud environment.
 - a. Location: "GCP"
 - b. Type: "Cloud Volumes ONTAP HA"
- 4. Import the OpenShift cluster. The cluster will connect to the working environment you just created.
 - a. View the NetApp cluster details by selecting K8s > Cluster list > Cluster Details.

- b. In the upper right corner, note the Trident version.
- c. Note the Cloud Volumes ONTAP cluster storage classes showing "NetApp" as the provisioner.

This imports your Red Hat OpenShift cluster and assigns it a default storage class. You select the storage class.

Trident is automatically installed as part of the import and discovery process.

5. Note all the persistent volumes and volumes in this Cloud Volumes ONTAP deployment.



Cloud Volumes ONTAP can operate as a single node or in High Availability (HA). If HA is enabled, note the HA status and node deployment status running in GCP.

Install Astra Control Center

Follow the standard Astra Control Center installation instructions.



GCP uses the Generic S3 bucket type.

1. Generate the Docker Secret to pull images for the Astra Control Center installation:

```
kubectl create secret docker-registry <secret name>
--docker-server=<Registry location>
--docker-username=_json_key
--docker-password="$(cat <GCP Service Account JSON file>)"
--namespace=pcloud
```

Deploy Astra Control Center in Microsoft Azure

You can deploy Astra Control Center on a self-managed Kubernetes cluster hosted on a Microsoft Azure public cloud.

What you'll need for Azure

Before you deploy Astra Control Center in Azure, you will need the following items:

- Astra Control Center license. See Astra Control Center licensing requirements.
- · Meet Astra Control Center requirements.
- NetApp Cloud Central account
- If using OCP, Red Hat OpenShift Container Platform (OCP) 4.8
- If using OCP, Red Hat OpenShift Container Platform (OCP) permissions (on namespace level to create pods)
- · Azure credentials with permissions that enable you to create buckets and connectors

Operational environment requirements for Azure

Ensure that the operating environment you choose to host Astra Control Center meets the basic resource requirements outlined in the environment's official documentation.

Astra Control Center requires the following resources in addition to the environment's resource requirements:

See Astra Control Center operational environment requirements.

Component	Requirement
Backend NetApp Cloud Volumes ONTAP storage capacity	At least 300GB available
Worker nodes (Azure compute requirement)	At least 3 worker nodes total, with 4 vCPU cores and 12GB RAM each
Load balancer	Service type "LoadBalancer" available for ingress traffic to be sent to services in the operational environment cluster
FQDN (Azure DNS zone)	A method for pointing the FQDN of Astra Control Center to the load balanced IP address
Astra Trident (installed as part of the Kubernetes cluster discovery in NetApp Cloud Manager)	Astra Trident 21.04 or newer installed and configured and NetApp ONTAP version 9.5 or newer will be used as a storage backend
Image registry	You must have an existing private registry, such as Azure Container Registry (ACR), to which you can push Astra Control Center build images. You need to provide the URL of the image registry where you will upload the images. You need to enable anonymous access to pull Restic images for backups.
Astra Trident / ONTAP configuration	Astra Control Center requires that a storage class be created and set as the default storage class. Astra Control Center supports the following ONTAP Kubernetes storage classes that are created when you import your Kubernetes cluster into NetApp Cloud Manager. These are provided by Astra Trident: • vsaworkingenvironment-<>-ha-nas csi.trident.netapp.io • vsaworkingenvironment-<>-ha-san csi.trident.netapp.io • vsaworkingenvironment-<>-single-nas csi.trident.netapp.io • vsaworkingenvironment-<>-single-san csi.trident.netapp.io



These requirements assume that Astra Control Center is the only application running in the operational environment. If the environment is running additional applications, adjust these minimum requirements accordingly.

Overview of deployment for Azure

Here is an overview of the process to install Astra Control Center for Azure.

Each of these steps is explained in more detail below.

- 1. Install a RedHat OpenShift cluster on Azure.
- 2. Create Azure resource groups.
- 3. Ensure that you have sufficient IAM permissions.
- 4. Configure Azure.
- 5. Configure NetApp Cloud Manager.
- 6. Install and configure Astra Control Center.

Install a RedHat OpenShift cluster on Azure

The first step is to install a RedHat OpenShift cluster on Azure.

For installation instructions, see the following:

- · Installing OpenShift cluster on Azure.
- · Installing an Azure account.

Create Azure resource groups

Create at least one Azure resource group.



OpenShift might create its own resource groups. In addition to these, you should also define Azure resource groups. Refer to OpenShift documentation.

You might want to create a platform cluster resource group and a target app OpenShift cluster resource group.

Ensure that you have sufficient IAM permissions

Ensure that you have sufficient IAM roles and permissions that enable you to install a RedHat OpenShift cluster and a NetApp Cloud Manager Connector.

See Azure credentials and permissions.

Configure Azure

Next, configure Azure to create a virtual network, set up compute instances, create an Azure Blob container, create an Azure Container Register (ACR) to host the Astra Control Center images, and push the images to this registry.

Follow the Azure documentation to complete the following steps. See Installing OpenShift cluster on Azure.

- 1. Create an Azure virtual network.
- 2. Review the compute instances. This can be a bare metal server or VMs in Azure.
- If the instance type does not already match the Astra minimum resource requirements for master and worker nodes, change the instance type in Azure to meet the Astra requirements. See Astra Control Center requirements.

- 4. Create at least one Azure Blob container to store your backups.
- 5. Create a storage account. You will need a storage account to create a container to be used as a bucket in Astra Control Center.
- 6. Create a secret, which is required for bucket access.
- 7. Create an Azure Container Registry (ACR) to host all the Astra Control Center images.
- 8. Set up ACR access for Docker push/pull all the Astra Control Center images.
- 9. Push the ACC images to this registry by entering the following script:

```
az acr login -n <AZ ACR URL/Location>
This script requires ACC manifest file and your Azure ACR location.
```

Example:

```
manifestfile=astra-control-center-<version>.manifest
AZ_ACR_REGISTRY=<target image repository>
ASTRA_REGISTRY=<source ACC image repository>

while IFS= read -r image; do
    echo "image: $ASTRA_REGISTRY/$image $AZ_ACR_REGISTRY/$image"
    root_image=${image*:*}
    echo $root_image
    docker pull $ASTRA_REGISTRY/$image
    docker tag $ASTRA_REGISTRY/$image $AZ_ACR_REGISTRYY/$image
    docker push $AZ_ACR_REGISTRY/$image
    docker push $AZ_ACR_REGISTRY/$image
    docker satra-control-center-22.04.41.manifest
```

10. Set up DNS zones.

Configure NetApp Cloud Manager

Using Cloud Manager, create a workspace, add a connector to Azure, create a working environment, and import the cluster.

Follow the Cloud Manager documentation to complete the following steps. See Getting started with Cloud Manager in Azure.

What you'll need


Access to the Azure account with the required IAM permissions and roles

Steps


- 1. Add your credentials to Cloud Manager.
- 2. Add a connector for Azure. See Cloud Manager policies.
 - a. Choose Azure as the Provider.
 - b. Enter Azure credentials, including the application ID, client secret, and directory (tenant) ID.

See Creating a connector in Azure from Cloud Manager.


3. Ensure that the connector is running and switch to that connector.



- 4. Create a working environment for your cloud environment.
 - a. Location: "Microsoft Azure".
 - b. Type: "Cloud Volumes ONTAP HA".



- 5. Import the OpenShift cluster. The cluster will connect to the working environment you just created.
 - a. View the NetApp cluster details by selecting K8s > Cluster list > Cluster Details.



- b. In the upper right corner, note the Trident version.
- c. Note the Cloud Volumes ONTAP cluster storage classes showing NetApp as the provisioner.

This imports your Red Hat OpenShift cluster and assigns a default storage class. You select the storage class.

Trident is automatically installed as part of the import and discovery process.

- 6. Note all the persistent volumes and volumes in this Cloud Volumes ONTAP deployment.
- 7. Cloud Volumes ONTAP can operate as a single node or in High Availability. If HA is enabled, note the HA status and node deployment status running in Azure.

Install and configure Astra Control Center

Install Astra Control Center with the standard installation instructions.

Using Astra Control Center, add an Azure bucket. See Set up Astra Control Center and add buckets.

Set up Astra Control Center

Astra Control Center supports and monitors ONTAP and Astra Data Store as the storage backend. After you install Astra Control Center, log in to the UI, and change your password, you'll want to set up a license, add clusters, manage storage, and add buckets.

Tasks

- Add a license for Astra Control Center
- Add cluster

- Add a storage backend
- · Add a bucket

Add a license for Astra Control Center

You can add a new license using the UI or API to gain full Astra Control Center functionality. Without a license, your usage of Astra Control Center is limited to managing users and adding new clusters.

For more information on how licenses are calculated, see Licensing.



To update an existing evaluation or full license, see Update an existing license.

Astra Control Center licenses measure CPU resources using Kubernetes CPU units. The license needs to account for the CPU resources assigned to the worker nodes of all the managed Kubernetes clusters. Before you add a license, you need to obtain the license file (NLF) from the NetApp Support Site.

You can also try Astra Control Center with an evaluation license, which lets you use Astra Control Center for 90 days from the date you download the license. You can sign up for a free trial by registering here.



If your installation grows to exceed the licensed number of CPU units, Astra Control Center prevents you from managing new applications. An alert is displayed when capacity is exceeded.

What you'll need

When you downloaded Astra Control Center from the NetApp Support Site, you also downloaded the NetApp license file (NLF). Ensure you have access to this license file.

Steps

- 1. Log in to the Astra Control Center UI.
- 2. Select Account > License.
- 3. Select Add License.
- 4. Browse to the license file (NLF) that you downloaded.
- Select Add License.

The **Account > License** page displays the license information, expiration date, license serial number, account ID, and CPU units used.



If you have an evaluation license, be sure you store your account ID to avoid data loss in the event of Astra Control Center failure if you are not sending ASUPs.

Add cluster

To begin managing your apps, add a Kubernetes cluster and manage it as a compute resource. You have to add a cluster for Astra Control Center to discover your Kubernetes applications. For Astra Data Store, you want to add the Kubernetes app cluster that contains applications that are using volumes provisioned by Astra Data Store.



We recommend that Astra Control Center manage the cluster it is deployed on first before you add other clusters to Astra Control Center to manage. Having the initial cluster under management is necessary to send Kubemetrics data and cluster-associated data for metrics and troubleshooting. You can use the **Add Cluster** feature to manage a cluster with Astra Control Center.

When Astra Control manages a cluster, it keeps track of the cluster's default storage class. If you change the storage class using kubectl commands, Astra Control reverts the change. To change the default storage class in a cluster managed by Astra Control, use one of the following methods:



- Use the Astra Control API PUT /managedClusters endpoint, and assign a different default storage class with the DefaultStorageClass parameter.
- Use the Astra Control web UI to assign a different default storage class. See Change the default storage class.

What you'll need


• Before you add a cluster, review and perform the necessary prerequisite tasks.

Steps

- 1. From the **Dashboard** in the Astra Control Center UI, select **Add** in the Clusters section.
- 2. In the Add Cluster window that opens, upload a kubeconfig.yaml file or paste the contents of a kubeconfig.yaml file.



The kubeconfig.yaml file should include only the cluster credential for one cluster.






If you create your own kubeconfig file, you should define only **one** context element in it. See Kubernetes documentation for information about creating kubeconfig files.

- 3. Provide a credential name. By default, the credential name is auto-populated as the name of the cluster.
- Select Configure storage.
- 5. Select the storage class to be used for this Kubernetes cluster, and select Review.



You should select a Trident storage class backed by ONTAP storage or Astra Data Store.



6. Review the information, and if everything looks good, select **Add cluster**.

Result

The cluster enters the **Discovering** status and then changes to **Running**. You have successfully added a Kubernetes cluster and are now managing it in Astra Control Center.



After you add a cluster to be managed in Astra Control Center, it might take a few minutes to deploy the monitoring operator. Until then, the Notification icon turns red and logs a **Monitoring Agent Status Check Failed** event. You can ignore this, because the issue resolves when Astra Control Center obtains the correct status. If the issue does not resolve in a few minutes, go to the cluster, and run oc get pods -n netapp-monitoring as the starting point. You will need to look into the monitoring operator logs to debug the problem.

Add a storage backend

You can add a storage backend so that Astra Control can manage its resources. You can deploy a storage backend on a managed cluster or use an existing storage backend.

Managing storage clusters in Astra Control as a storage backend enables you to get linkages between persistent volumes (PVs) and the storage backend as well as additional storage metrics.

What you'll need for existing Astra Data Store deployments

You have added your Kubernetes app cluster and the underlying compute cluster.



After you add your Kubernetes app cluster for Astra Data Store and it is managed by Astra Control, the cluster appears as unmanaged in the list of discovered backends. You must next add the compute cluster that contains Astra Data Store and underlies the Kubernetes app cluster. You can do this from **Backends** in the UI. Select the Actions menu for the cluster, select Manage, and add the cluster. After the cluster state of unmanaged changes to the name of the Kubernetes cluster, you can proceed with adding a backend.

What you'll need for new Astra Data Store deployments

- You have uploaded the version of the installation bundle you intend to deploy to a location that is accessible to Astra Control.
- You have added the Kubernetes cluster that you intend to use for deployment.
- You have uploaded the Astra Data Store license for your deployment to a location that is accessible to Astra Control.

Options

- · Deploy storage resources
- Use an existing storage backend

Deploy storage resources

You can deploy a new Astra Data Store and manage the associated storage backend.

Steps

- 1. Navigate from the Dashboard or the Backends menu:
 - From Dashboard: From the Resource Summary, select a link from the Storage Backends pane and select Add from the Backends section.
 - From Backends:
 - a. In the left navigation area, select **Backends**.
 - b. Select Add.
- 2. Select the Astra Data Store deployment option within the Deploy tab.
- 3. Select the Astra Data Store package to deploy:
 - a. Enter a name for the Astra Data Store application.
 - b. Choose the version of Astra Data Store you want to deploy.



If you have not yet uploaded the version you intend to deploy, you can use the **Add package** option or exit the wizard and use package management to upload the installation bundle.

4. Select an Astra Data Store license that you have previously uploaded or use the **Add license** option to upload a license to use with the application.



Astra Data Store licenses with full permissions are associated with your Kubernetes cluster, and these associated clusters should appear automatically. If there is no managed cluster, you can select the **Add a Cluster** option to add one to Astra Control management. For Astra Data Store licenses, if no association has been made between the license and cluster, you can define this association on the next page of the wizard.

- 5. If you have not added a Kubernetes cluster to Astra Control management, you need to do so from the Kubernetes cluster page. Select an existing cluster from the list or select add the underlying cluster to add a cluster to Astra Control management.
- 6. Select a template size for the Kubernetes cluster that will provide resources for Astra Data Store. You can choose one of the following:
 - ° If you choose Recommended Kubernetes worker node requirements, select a template from large to small based on what your license allows.
 - o If you choose Custom Kubernetes worker node requirements, select the number of cores and total memory you want for each cluster node. You can also show the eligible number of nodes in the cluster that meet your selection criteria for cores and memory.



When picking a template, select larger nodes with more memory and cores for larger workloads or a greater number of nodes for smaller workloads. You should select a template based on what your license allows. Each recommended template option suggests the number of eligible nodes that satisfy the template pattern for memory and cores and capacity for each node.

7. Configure the nodes:

a. Add a node label to identify the pool of worker nodes that supports this Astra Data Store cluster.



The label must be added to each individual node in the cluster that will be used for Astra Data Store deployment prior to the start of deployment or deployment will fail.

- b. Configure the capacity (GiB) per node manually or select the maximum node capacity allowed.
- c. Configure a maximum number of nodes allowed in the cluster or allow the maximum number of nodes on the cluster.
- 8. (Astra Data Store full licenses only) Enter the key of the label you want to use for Protection Domains.



Create at least three unique labels for the key for each node. For example, if your key is astra.datastore.protection.domain, you might create the following labels: astra.datastore.protection.domain=domain1,astra.datastore.protection.domain=domain3.

- 9. Configure the management network:
 - a. Enter a management IP address for Astra Data Store internal management that is on the same subnet as worker node IP addresses.
 - b. Choose to use the same NIC for both management and data networks or configure them separately.
 - c. Enter data network IP address pool, subnet mask and gateway for storage access.
- 10. Review the configuration and select **Deploy** to begin installation.

Result

After a successful installation, the backend appears in available state in the backends list along with active performance information.



You might need to refresh the page for the backend to appear.

Use an existing storage backend

You can bring a discovered ONTAP or Astra Data Store storage backend into Astra Control Center management.

Steps

- 1. Navigate from the Dashboard or the Backends menu:
 - From Dashboard: From the Resource Summary, select a link from the Storage Backends pane and select Add from the Backends section.
 - From Backends:
 - a. In the left navigation area, select **Backends**.

- b. Select **Manage** on a discovered backend from the managed cluster or select **Add** to manage an additional existing backend.
- 2. Select the **Use existing** tab.
- 3. Do one of the following depending on your backend type:
 - Astra Data Store:
 - a. Select Astra Data Store.
 - b. Select the managed compute cluster and select Next.
 - c. Confirm the backend details and select Add storage backend.
 - ONTAP:
 - Select ONTAP and select Next.
 - b. Enter the ONTAP cluster management IP address and admin credentials.



The user whose credentials you enter here must have the <code>ontapi</code> user login access method enabled within ONTAP System Manager on the ONTAP cluster. If you plan to use SnapMirror replication, enable the access methods <code>ontapi</code> and <code>http</code> for the user on both ONTAP clusters. See Manage User Accounts for more information.

- c. Select Review.
- d. Confirm the backend details and select **Add storage backend**.

Result

The backend appears in available state in the list with summary information.



You might need to refresh the page for the backend to appear.

Add a bucket

Adding object store bucket providers is essential if you want to back up your applications and persistent storage or if you want to clone applications across clusters. Astra Control stores those backups or clones in the object store buckets that you define.

When you add a bucket, Astra Control marks one bucket as the default bucket indicator. The first bucket that you create becomes the default bucket.

You don't need a bucket if you are cloning your application configuration and persistent storage to the same cluster.

Use any of the following bucket types:

- NetApp ONTAP S3
- NetApp StorageGRID S3
- Generic S3



Amazon Web Services (AWS) and Google Cloud Platform (GCP) use the Generic S3 bucket type.

· Microsoft Azure



Although Astra Control Center supports Amazon S3 as a Generic S3 bucket provider, Astra Control Center might not support all object store vendors that claim Amazon's S3 support.

· Microsoft Azure

For instructions on how to add buckets using the Astra Control API, see Astra Automation and API information.

Steps

- 1. In the left navigation area, select **Buckets**.
 - a. Select Add.
 - b. Select the bucket type.



When you add a bucket, select the correct bucket provider and provide the right credentials for that provider. For example, the UI accepts NetApp ONTAP S3 as the type and accepts StorageGRID credentials; however, this will cause all future app backups and restores using this bucket to fail.

c. Create a new bucket name or enter an existing bucket name and optional description.



The bucket name and description appear as a backup location that you can choose later when you're creating a backup. The name also appears during protection policy configuration.

- d. Enter the name or IP address of the S3 endpoint.
- e. If you want this bucket to be the default bucket for all backups, check the Make this bucket the default bucket for this private cloud option.
 - (i)

This option does not appear for the first bucket you create.

f. Continue by adding credential information.

Add S3 access credentials

Add S3 access credentials at any time.

Steps

- 1. From the Buckets dialog, select either the Add or Use existing tab.
 - a. Enter a name for the credential that distinguishes it from other credentials in Astra Control.
 - b. Enter the access ID and secret key by pasting the contents from your clipboard.

Change the default storage class

You can change the default storage class for a cluster.

Steps

- 1. In the Astra Control Center web UI, select Clusters.
- 2. On the Clusters page, select the cluster that you want to change.
- Select the Storage tab.

- Select the Storage classes category.
- 5. Select the **Actions** menu for the storage class that you want to set as default.
- Select Set as default.

What's next?

Now that you've logged in and added clusters to Astra Control Center, you're ready to start using Astra Control Center's application data management features.

- Manage users
- · Start managing apps
- Protect apps
- Clone apps
- · Manage notifications
- · Connect to Cloud Insights
- · Add a custom TLS certificate

Find more information

- Use the Astra Control API
- Known issues

Prerequisites for adding a cluster

You should ensure that the prerequisite conditions are met before you add a cluster. You should also run the eligibility checks to ensure that your cluster is ready to be added to Astra Control Center.

What you'll need before you add a cluster

Ensure that your cluster meets the requirements outlined in Application cluster requirements.



If you plan to add a second OpenShift 4.6, 4.7, or 4.8 cluster as a managed compute resource, you should ensure that the Astra Trident Volume Snapshot feature is enabled. See the official Astra Trident instructions to enable and test Volume Snapshots with Astra Trident.

- Astra Trident StorageClasses configured with a supported storage backend (required for any type of cluster)
- The superuser and user ID set on the backing ONTAP system to back up and restore apps with Astra Control Center. Run the following command in the ONTAP command line:

 export-policy rule modify -vserver <storage virtual machine name> -policyname <policy name> -ruleindex 1 -superuser sysm --anon 65534
- An Astra Trident volumesnapshotclass object that has been defined by an administrator. See the Astra
 Trident instructions to enable and test Volume Snapshots with Astra Trident.
- Ensure that you have only a single default storage class defined for your Kubernetes cluster.

Run eligibility checks

Run the following eligibility checks to ensure that your cluster is ready to be added to Astra Control Center.

Steps

1. Check the Trident version.

```
kubectl get tridentversions -n trident
```

If Trident exists, you see output similar to the following:

```
NAME VERSION
trident 21.04.0
```

If Trident does not exist, you see output similar to the following:

```
error: the server doesn't have a resource type "tridentversions"
```



If Trident is not installed or the installed version is not the latest, you need to install the latest version of Trident before proceeding. See the Trident documentation for instructions.

2. Check if the storage classes are using the supported Trident drivers. The provisioner name should be csi.trident.netapp.io. See the following example:

```
kubectl get sc
NAME
                       PROVISIONER
                                                      RECLAIMPOLICY
VOLUMEBINDINGMODE
                    ALLOWVOLUMEEXPANSION
                                           AGE
ontap-gold (default)
                      csi.trident.netapp.io
                                                      Delete
Immediate
                    true
                                           5d23h
thin
                       kubernetes.io/vsphere-volume
                                                      Delete
Immediate
                    false
                                           6d
```

Create an admin-role kubeconfig

Ensure that you have the following on your machine before you do the steps:

- kubectl v1.19 or later installed
- · An active kubeconfig with cluster admin rights for the active context

Steps

- 1. Create a service account as follows:
 - a. Create a service account file called astracontrol-service-account.yaml.

Adjust the name and namespace as needed. If changes are made here, you should apply the same

changes in the following steps.

```
<strong>astracontrol-service-account.yaml</strong>
```

```
apiVersion: v1
kind: ServiceAccount
metadata:
   name: astracontrol-service-account
   namespace: default
```

b. Apply the service account:

```
kubectl apply -f astracontrol-service-account.yaml
```

- 2. (Optional) If your cluster uses a restrictive pod security policy that doesn't allow privileged pod creation or allow processes within the pod containers to run as the root user, create a custom pod security policy for the cluster that enables Astra Control to create and manage pods. For instructions, see Create a custom pod security policy.
- 3. Grant cluster admin permissions as follows:
 - a. Create a ClusterRoleBinding file called astracontrol-clusterrolebinding.yaml.

Adjust any names and namespaces modified when creating the service account as needed.

```
<strong>astracontrol-clusterrolebinding.yaml</strong>
```

```
apiVersion: rbac.authorization.k8s.io/v1
kind: ClusterRoleBinding
metadata:
   name: astracontrol-admin
roleRef:
   apiGroup: rbac.authorization.k8s.io
   kind: ClusterRole
   name: cluster-admin
subjects:
   - kind: ServiceAccount
   name: astracontrol-service-account
   namespace: default
```

b. Apply the cluster role binding:

```
kubectl apply -f astracontrol-clusterrolebinding.yaml
```

4. List the service account secrets, replacing <context> with the correct context for your installation:

```
kubectl get serviceaccount astracontrol-service-account --context
<context> --namespace default -o json
```

The end of the output should look similar to the following:

```
"secrets": [
{ "name": "astracontrol-service-account-dockercfg-vhz87"},
{ "name": "astracontrol-service-account-token-r59kr"}
]
```

The indices for each element in the secrets array begin with 0. In the above example, the index for astracontrol-service-account-dockercfg-vhz87 would be 0 and the index for astracontrol-service-account-token-r59kr would be 1. In your output, make note of the index for the service account name that has the word "token" in it.

- 5. Generate the kubeconfig as follows:
 - a. Create a create-kubeconfig.sh file. Replace TOKEN_INDEX in the beginning of the following script with the correct value.

```
<strong>create-kubeconfig.sh</strong>
```

```
TOKEN DATA=$(kubectl get secret ${SECRET NAME} \
  --context ${CONTEXT} \
 --namespace ${NAMESPACE} \
  -o jsonpath='{.data.token}')
TOKEN=$ (echo ${TOKEN DATA} | base64 -d)
# Create dedicated kubeconfig
# Create a full copy
kubectl config view --raw > ${KUBECONFIG FILE}.full.tmp
# Switch working context to correct context
kubectl --kubeconfig ${KUBECONFIG FILE}.full.tmp config use-context
${CONTEXT}
# Minify
kubectl --kubeconfig ${KUBECONFIG FILE}.full.tmp \
  config view --flatten --minify > ${KUBECONFIG FILE}.tmp
# Rename context
kubectl config --kubeconfig ${KUBECONFIG FILE}.tmp \
 rename-context ${CONTEXT} ${NEW CONTEXT}
# Create token user
kubectl config --kubeconfig ${KUBECONFIG FILE}.tmp \
 set-credentials ${CONTEXT}-${NAMESPACE}-token-user \
 --token ${TOKEN}
# Set context to use token user
kubectl config --kubeconfig ${KUBECONFIG FILE}.tmp \
 set-context ${NEW CONTEXT} --user ${CONTEXT}-${NAMESPACE}-token
-user
# Set context to correct namespace
kubectl config --kubeconfig ${KUBECONFIG FILE}.tmp \
  set-context ${NEW CONTEXT} --namespace ${NAMESPACE}
# Flatten/minify kubeconfig
kubectl config --kubeconfig ${KUBECONFIG FILE}.tmp \
 view --flatten --minify > ${KUBECONFIG FILE}
# Remove tmp
rm ${KUBECONFIG FILE}.full.tmp
rm ${KUBECONFIG FILE}.tmp
```

b. Source the commands to apply them to your Kubernetes cluster.

```
source create-kubeconfig.sh
```

6. (Optional) Rename the kubeconfig to a meaningful name for your cluster. Protect your cluster credential.

```
chmod 700 create-kubeconfig.sh
mv kubeconfig-sa.txt YOUR_CLUSTER_NAME_kubeconfig
```

What's next?

Now that you've verified that the prerequisites are met, you're ready to add a cluster.

Find more information

- Trident documentation
- Use the Astra Control API

Add a custom TLS certificate

You can remove the existing self-signed TLS certificate and replace it with a TLS certificate signed by a Certificate Authority (CA).

What you'll need

- Kubernetes cluster with Astra Control Center installed
- Administrative access to a command shell on the cluster to run kubectl commands
- · Private key and certificate files from the CA

Remove the self-signed certificate

Remove the existing self-signed TLS certificate.

- 1. Using SSH, log in to the Kubernetes cluster that hosts Astra Control Center as an administrative user.
- Find the TLS secret associated with the current certificate using the following command, replacing <ACC-deployment-namespace> with the Astra Control Center deployment namespace:

```
kubectl get certificate -n <ACC-deployment-namespace>
```

3. Delete the currently installed secret and certificate using the following commands:

```
kubectl delete cert cert-manager-certificates -n <ACC-deployment-
namespace>
kubectl delete secret secure-testing-cert -n <ACC-deployment-namespace>
```

Add a new certificate

Add a new TLS certificate that is signed by a CA.

1. Use the following command to create the new TLS secret with the private key and certificate files from the CA, replacing the arguments in brackets <> with the appropriate information:

```
kubectl create secret tls <secret-name> --key <private-key-filename>
--cert <certificate-filename> -n <ACC-deployment-namespace>
```

2. Use the following command and example to edit the cluster Custom Resource Definition (CRD) file and change the spec.selfSigned value to spec.ca.secretName to refer to the TLS secret you created earlier:

```
kubectl edit clusterissuers.cert-manager.io/cert-manager-certificates -n
<ACC-deployment-namespace>
....
#spec:
# selfSigned: {}

spec:
ca:
    secretName: <secret-name>
```

3. Use the following command and example output to validate that the changes are correct and the cluster is ready to validate certificates, replacing <acheeologyment-namespace> with the Astra Control Center deployment namespace:

```
kubectl describe clusterissuers.cert-manager.io/cert-manager-
certificates -n <ACC-deployment-namespace>
....

Status:
   Conditions:
    Last Transition Time: 2021-07-01T23:50:27Z
    Message: Signing CA verified
    Reason: KeyPairVerified
    Status: True
    Type: Ready
Events: <none>
```

4. Create the certificate.yaml file using the following example, replacing the placeholder values in brackets <> with appropriate information:

```
apiVersion: cert-manager.io/v1
kind: Certificate
metadata:
   name: <certificate-name>
   namespace: <ACC-deployment-namespace>
spec:
   secretName: <certificate-secret-name>
   duration: 2160h # 90d
   renewBefore: 360h # 15d
   dnsNames:
   - <astra.dnsname.example.com> #Replace with the correct Astra Control
Center DNS address
   issuerRef:
     kind: ClusterIssuer
     name: cert-manager-certificates
```

5. Create the certificate using the following command:

```
kubectl apply -f certificate.yaml
```

6. Using the following command and example output, validate that the certificate has been created correctly and with the arguments you specified during creation (such as name, duration, renewal deadline, and DNS names).

```
kubectl describe certificate -n <ACC-deployment-namespace>
. . . .
Spec:
  Dns Names:
    astra.example.com
  Duration: 125h0m0s
  Issuer Ref:
    Kind:
                ClusterIssuer
               cert-manager-certificates
    Name:
  Renew Before: 61h0m0s
  Secret Name: <certificate-secret-name>
Status:
  Conditions:
    Last Transition Time: 2021-07-02T00:45:41Z
                           Certificate is up to date and has not expired
    Message:
    Reason:
                           Ready
    Status:
                           True
    Type:
                           Ready
  Not After:
                           2021-07-07T05:45:41Z
  Not Before:
                           2021-07-02T00:45:41Z
  Renewal Time:
                           2021-07-04T16:45:41Z
  Revision:
Events:
                           <none>
```

7. Edit the ingress CRD TLS option to point to your new certificate secret using the following command and example, replacing the placeholder values in brackets <> with appropriate information:

```
kubectl edit ingressroutes.traefik.containo.us -n <ACC-deployment-
namespace>
. . . .
# tls:
     options:
#
       name: default
#
     secretName: secure-testing-cert
#
     store:
#
       name: default
 tls:
    options:
      name: default
    secretName: <certificate-secret-name>
    store:
      name: default
```

- 8. Using a web browser, browse to the deployment IP address of Astra Control Center.
- 9. Verify that the certificate details match the details of the certificate you installed.
- 10. Export the certificate and import the result into the certificate manager in your web browser.

Create a custom pod security policy

Astra Control needs to create and manage Kubernetes pods on the clusters it manages. If your cluster uses a restrictive pod security policy that doesn't allow privileged pod creation or allow processes within the pod containers to run as the root user, you need to create a less restrictive pod security policy to enable Astra Control to create and manage these pods.

Steps

1. Create a pod security policy for the cluster that is less restrictive than the default, and save it in a file. For example:

```
apiVersion: policy/v1beta1
kind: PodSecurityPolicy
metadata:
  name: astracontrol
  annotations:
    seccomp.security.alpha.kubernetes.io/allowedProfileNames: '*'
spec:
  privileged: true
  allowPrivilegeEscalation: true
  allowedCapabilities:
  _ ! * !
  volumes:
  _ | | | | |
  hostNetwork: true
  hostPorts:
  - min: 0
   max: 65535
  hostIPC: true
  hostPID: true
  runAsUser:
   rule: 'RunAsAny'
  seLinux:
   rule: 'RunAsAny'
  supplementalGroups:
   rule: 'RunAsAny'
  fsGroup:
    rule: 'RunAsAny'
```

2. Create a new role for the pod security policy.

```
kubectl-admin create role psp:astracontrol \
    --verb=use \
    --resource=podsecuritypolicy \
    --resource-name=astracontrol
```

3. Bind the new role to the service account.

```
kubectl-admin create rolebinding default:psp:astracontrol \
    --role=psp:astracontrol \
    --serviceaccount=astracontrol-service-account:default
```

Frequently asked questions for Astra Control Center

This FAQ can help if you're just looking for a quick answer to a question.

Overview

The following sections provide answers to some additional questions that you might come across as you use Astra Control Center. For additional clarifications, please reach out to astra.feedback@netapp.com

Access to Astra Control Center

What's the Astra Control URL?

Astra Control Center uses local authentication and a URL specific to each environment.

For the URL, in a browser, enter the Fully Qualified Domain Name (FQDN) you set in the spec.astraAddress field in the astra_control_center_min.yaml custom resource definition (CRD) file when you installed Astra Control Center. The email is the value that you set in the spec.email field in the astra_control_center_min.yaml CRD.

Licensing

I am using the Evaluation license. How to I change to the full license?

You can easily change to a full license by obtaining the NetApp license file (NLF).

Steps

- From the left navigation, select **Account > License**.
- · Select Add license.
- · Browse to the license file you downloaded and select Add.

I am using the Evaluation license. Can I still manage apps?

Yes, you can test out the managing apps functionality with the Evaluation license.

Registering Kubernetes clusters

I need to add worker nodes to my Kubernetes cluster after adding to Astra Control. What should I do?

New worker nodes can be added to existing pools. These will be automatically discovered by Astra Control. If the new nodes are not visible in Astra Control, check if the new worker nodes are running the supported image type. You can also verify the health of the new worker nodes by using the kubectl get nodes command.

How do I properly unmanage a cluster?

- 1. Unmanage the applications from Astra Control.
- 2. Unmanage the cluster from Astra Control.

What happens to my applications and data after removing the Kubernetes cluster from Astra Control?

Removing a cluster from Astra Control will not make any changes to the cluster's configuration (applications

and persistent storage). Any Astra Control snapshots or backups taken of applications on that cluster will be unavailable to restore. Persistent storage backups created by Astra Control remain within Astra Control, but they are unavailable for restore.



Always remove a cluster from Astra Control before you delete it through any other methods. Deleting a cluster using another tool while it's still being managed by Astra Control can cause problems for your Astra Control account.

Is NetApp Trident automatically uninstalled from a cluster when I unmanage it?

When you unmanage a cluster from Astra Control Center, Trident isn't automatically uninstalled from the cluster. To uninstall Trident, you'll need to follow these steps in the Trident documentation.

Managing applications

Can Astra Control deploy an application?

Astra Control doesn't deploy applications. Applications must be deployed outside of Astra Control.

What happens to applications after I stop managing them from Astra Control?

Any existing backups or snapshots will be deleted. Applications and data remain available. Data management operations will not be available for unmanaged applications or any backups or snapshots that belong to it.

Can Astra Control manage an application that is on non-NetApp storage?

No. While Astra Control can discover applications that are using non-NetApp storage, it can't manage an application that's using non-NetApp storage.

Should I manage Astra Control itself?

No, you should not manage Astra Control itself because it is a "system app."

Do unhealthy pods affect app management?

If a managed app has pods in an unhealthy state, Astra Control can't create new backups and clones.

Data management operations

There are snapshots in my account that I didn't create. Where did they come from?

In some situations, Astra Control will automatically create a snapshot as part of a backup, clone or restore process.

My application uses several PVs. Will Astra Control take snapshots and backups of all these PVCs?

Yes. A snapshot operation on an application by Astra Control includes snapshot of all the PVs that are bound to the application's PVCs.

Can I manage snapshots taken by Astra Control directly through a different interface or object storage?

No. Snapshots and backups taken by Astra Control can only be managed with Astra Control.

Use Astra

Start managing apps

After you add a cluster to Astra Control management, you can install apps on the cluster (outside of Astra Control) and then go to the Applications page in Astra Control to start managing the apps and their resources.

For more information, see App management requirements.

Supported app installation methods

Astra Control supports the following application installation methods:

Manifest file: Astra Control supports apps installed from a manifest file using kubectl. For example:

```
kubectl apply -f myapp.yaml
```

- **Helm 3**: If you use Helm to install apps, Astra Control requires Helm version 3. Managing and cloning apps installed with Helm 3 (or upgraded from Helm 2 to Helm 3) are fully supported. Managing apps installed with Helm 2 is not supported.
- Operator-deployed apps: Astra Control supports apps installed with namespace-scoped operators that are, in general, designed with a "pass-by-value" rather than "pass-by-reference" architecture. An operator and the app it installs must use the same namespace; you might need to modify the deployment .yaml file for the operator to ensure this is the case.

The following are some operator apps that follow these patterns:

Apache K8ssandra



For K8ssandra, in-place restore operations are supported. A restore operation to a new namespace or cluster requires that the original instance of the application to be taken down. This is to ensure that the peer group information carried over does not lead to cross-instance communication. Cloning of the app is not supported.

- Jenkins CI
- Percona XtraDB Cluster

Astra Control might not be able to clone an operator that is designed with a "pass-by-reference" architecture (for example, the CockroachDB operator). During these types of cloning operations, the cloned operator attempts to reference Kubernetes secrets from the source operator despite having its own new secret as part of the cloning process. The clone operation might fail because Astra Control is unaware of the Kubernetes secrets in the source operator.

Install apps on your cluster

After you've added your cluster to Astra Control, you can install apps or manage existing apps on the cluster. Any app that is scoped to a single namespace can be managed.

Manage apps

After Astra Control discovers namespaces on your clusters, you can define applications that you want to manage. You can choose to manage an entire namespace as a single application or manage one or more apps in the namespace individually. It all comes down to the level of granularity that you need for data protection operations.

Although Astra Control enables you to separately manage both levels of the hierarchy (the namespace and the apps in that namespace), the best practice is to choose one or the other. Actions that you take in Astra Control can fail if the actions take place at the same time at both the namespace and app level.



As an example, you might want to set a backup policy for "maria" that has a weekly cadence, but you might need to back up "mariadb" (which is in the same namespace) more frequently than that. Based on those needs, you would need to manage the apps separately and not as a single-namespace app.

What you'll need

- · A Kubernetes cluster added to Astra Control.
- One or more installed apps on the cluster. Read more about supported app installation methods.
- · One or more active pods.
- Namespaces specified on the Kubernetes cluster that you added to Astra Control.
- (Optional) Kubernetes label on any supported Kubernetes resources.



A label is a key/value pair you can assign to Kubernetes objects for identification. Labels make it easier to sort, organize, and find your Kubernetes objects. To learn more about Kubernetes labels, see the official Kubernetes documentation.

Before you begin, you should also understand managing standard and system namespaces.

For instructions on how to manage apps using the Astra Control API, see the Astra Automation and API information.

App management options

- Define resources to manage as an app
- Define a namespace to manage as an app

Additional app management options

Unmanage apps

Define resources to manage as an app

You can specify the Kubernetes resources that make up an app that you want to manage with Astra Control. Defining an app enables you to group elements of your Kubernetes cluster into a single app. This collection of Kubernetes resources is organized by namespace and label selector criteria.

Defining an app gives you more granular control over what to include in an Astra Control operation, including clone, snapshot, and backups.



When defining apps, ensure that you do not include a Kubernetes resource in multiple apps with protection policies. Overlapping protection policies on a Kubernetes resources can cause data conflicts. Read more about best practices.

Steps

- 1. From the Applications page, select **Define**.
- 2. In the **Define application** window, enter the app name.
- 3. Choose the cluster on which your application is running in the Cluster drop-down list.
- 4. Choose the namespace of your application from the Namespace drop-down list.
 - Apps can be defined only within a specified namespace on a single cluster. Astra Control does not support the ability for apps to span multiple namespaces or clusters.
- 5. Enter a label for the app and namespace. You can specify a single label or label selector criteria (query).
 - To learn more about Kubernetes labels, see the official Kubernetes documentation.
- 6. After you select **Define**, repeat the process for other apps, as needed.

After you finish defining an app, the app appears in the list of apps on the Applications page. You are now able to clone it and create backups and snapshots.

- \bigcirc
- The app you just added might have a warning icon under the Protected column, indicating that it is not backed up and not scheduled for backups yet.
- To see details of a particular app, select the app name.

Define a namespace to manage as an app

You can add all Kubernetes resources in a namespace to Astra Control management by defining the resources of that namespace as an application. This method is preferable to defining apps individually if you intend to manage and protect all resources in a particular namespace in a similar way and at common intervals.

Steps

- 1. From the Clusters page, select a cluster.
- 2. Select the **Namespaces** tab.
- 3. Select the Actions menu for the namespace that contains the app resources you want to manage and select **Define as application**.
 - If you want to manage multiple namespaces, select the namespaces and select the **Actions** button in the upper-left corner and select **manage**.
 - Select the **Show system namespaces** checkbox to reveal system namespaces that are usually not used in app management by default. Show system namespaces Read more.

After the process completes, the applications that are associated with the namespace appear in the Associated applications column.

Unmanage apps

When you no longer want to back up, snapshot, or clone an app, you can stop managing it.



If you unmanage an app, any backups or snapshots that were created earlier will be lost.


Steps

- 1. From the left navigation bar, select **Applications**.
- 2. Select the app.
- 3. From the menu in the **Actions** column, select **Unmanage**.
- Review the information.
- 5. Type "unmanage" to confirm.
- Select Yes, Unmanage Application.

What about system namespaces?

Astra Control also discovers system namespaces on a Kubernetes cluster. We don't show you these system namespaces by default because it's rare that you'd need to back up system app resources.

You can display system namespaces from the Namespaces tab for a selected cluster by selecting the **Show system namespaces** check box.





Astra Control itself is not a standard app; it is a "system app." You should not try to manage Astra Control itself. Astra Control itself isn't shown by default for management.

Example: Separate Protection Policy for different releases

In this example, the devops team is managing a "canary" release deployment. The team's cluster has three pods running NginX. Two of the pods are dedicated to the stable release. The third pod is for the canary release.

The devops team's Kubernetes admin adds the label deployment=stable to the stable release pods. The team adds the label deployment=canary to the canary release pod.

The team's stable release includes a requirement for hourly snapshots and daily backups. The canary release is more ephemeral, so they want to create a less aggressive, short-term Protection Policy for anything labeled deployment=canary.

In order to avoid possible data conflicts, the admin will create two apps: one for the "canary" release, and one for the "stable" release. This keeps the backups, snapshots, and clone operations separate for the two groups of Kubernetes objects.

Find more information

Use the Astra Control API

Protect apps

Protection overview

You can create backups, clones, snapshots, and protection policies for your apps using Astra Control Center. Backing up your apps helps your services and associated data be as available as possible; during a disaster scenario, restoring from backup can ensure full recovery of an app and its associated data with minimal disruption. Backups, clones, and snapshots can help protect against common threats such as ransomware, accidental data loss, and environmental disasters. Learn about the available types of data protection in Astra Control Center, and when to use them.

Additionally, you can replicate applications to a remote cluster in preparation for disaster recovery.

App protection workflow

You can use the following example workflow to get started protecting your apps.

[One] Protect all apps

To make sure that your apps are immediately protected, create a manual backup of all apps.

[Two] Configure a protection policy for each app

To automate future backups and snapshots, configure a protection policy for each app. As an example, you can start with weekly backups and daily snapshots, with one month retention for both. Automating backups and snapshots with a protection policy is strongly recommended over manual backups and snapshots.

[Three] Adjust the protection policies

As apps and their usage patterns change, adjust the protection policies as needed to provide the best protection.

[Four] Replicate apps to a remote cluster

Replicate applications to a remote cluster by using NetApp SnapMirror technology. Astra Control replicates Snapshots to a remote cluster, providing asynchronous, disaster recovery capability.

[Five] In case of a disaster, restore your apps with the latest backup or replication to remote system

If data loss occurs, you can recover by restoring the latest backup first for each app. You can then restore the latest snapshot (if available). Or, you can use the replication to a remote system.

Protect apps with snapshots and backups

Protect all apps by taking snapshots and backups using an automated protection policy or on an ad-hoc basis. You can use the Astra UI or the Astra Control API to protect apps.

If you use Helm to deploy apps, Astra Control Center requires Helm version 3. Managing and cloning apps deployed with Helm 3 (or upgraded from Helm 2 to Helm 3) are fully supported. Apps deployed with Helm 2 are not supported.

When you create a project for hosting an app on an OpenShift cluster, the project (or Kubernetes namespace) is assigned a SecurityContext UID. To enable Astra Control Center to protect your app and move the app to another cluster or project in OpenShift, you need to add policies that enable the app to run as any UID. As an

example, the following OpenShift CLI commands grant the appropriate policies to a WordPress app.

```
oc new-project wordpress oc adm policy add-scc-to-group anyuid system:serviceaccounts:wordpress oc adm policy add-scc-to-user privileged -z default -n wordpress
```

You can do the following tasks related to protecting your app data:

- Configure a protection policy
- · Create a snapshot
- · Create a backup
- · View snapshots and backups
- · Delete snapshots
- · Cancel backups
- · Delete backups

Configure a protection policy

A protection policy protects an app by creating snapshots, backups, or both at a defined schedule. You can choose to create snapshots and backups hourly, daily, weekly, and monthly, and you can specify the number of copies to retain. As an example, a protection policy might create weekly backups and daily snapshots, and retain the backups and snapshots for one month. How often you create snapshots and backups and how long you retain them depends on the needs of your organization.

Steps

- 1. Select **Applications** and then select the name of an app.
- 2. Select Data Protection.
- 3. Select Configure Protection Policy.
- Define a protection schedule by choosing the number of snapshots and backups to keep hourly, daily, weekly, and monthly.

You can define the hourly, daily, weekly, and monthly schedules concurrently. A schedule won't turn active until you set a retention level.

The following example sets four protection schedules: hourly, daily, weekly, and monthly for snapshots and backups.

- Select Review.
- 6. Select Set Protection Policy.

Result

Astra Control Center implements the data protection policy by creating and retaining snapshots and backups using the schedule and retention policy that you defined.

Create a snapshot

You can create an on-demand snapshot at any time.

Steps

- 1. Select Applications.
- 2. From the Options menu in the **Actions** column for the desired app, select **Snapshot**.
- 3. Customize the name of the snapshot and then select Review.
- Review the snapshot summary and select Snapshot.

Result

The snapshot process begins. A snapshot is successful when the status is **Available** in the **Actions** column on the **Data protection** > **Snapshots** page.

Create a backup

You can also back up an app at any time.



S3 buckets in Astra Control Center do not report available capacity. Before backing up or cloning apps managed by Astra Control Center, check bucket information in the ONTAP or StorageGRID management system.

Steps

- 1. Select Applications.
- From the Options menu in the Actions column for the desired app, select Backup.
- 3. Customize the name of the backup.
- Choose whether to back up the app from an existing snapshot. If you select this option, you can choose from a list of existing snapshots.
- 5. Choose a destination for the backup by selecting from the list of storage buckets.
- 6. Select **Review**.
- 7. Review the backup summary and select **Backup**.

Result

Astra Control Center creates a backup of the app.



If your network has an outage or is abnormally slow, a backup operation might time out. This causes the backup to fail.



There is no way to stop a running backup. If you need to delete the backup, wait until it has completed and then use the instructions in Delete backups. To delete a failed backup, use the Astra Control API.



After a data protection operation (clone, backup, restore) and subsequent persistent volume resize, there is up to a twenty-minute delay before the new volume size is shown in the UI. The data protection operation is successful within minutes, and you can use the management software for the storage backend to confirm the change in volume size.

View snapshots and backups

You can view the snapshots and backups of an app from the Data Protection tab.

Steps

- 1. Select **Applications** and then select the name of an app.
- 2. Select Data Protection.

The snapshots display by default.

Select Backups to see the list of backups.

Delete snapshots

Delete the scheduled or on-demand snapshots that you no longer need.



You cannot delete a Snapshot copy that is currently being replicated.

Steps

- 1. Select **Applications** and then select the name of an app.
- 2. Select Data Protection.
- 3. From the Options menu in the **Actions** column for the desired snapshot, select **Delete snapshot**.
- 4. Type the word "delete" to confirm deletion and then select Yes, Delete snapshot.

Result

Astra Control Center deletes the snapshot.

Cancel backups

You can cancel a backup that is in progress.



To cancel a backup, the backup must be in a Running state. You cannot cancel a backup that is in a Pending state.

Steps

- 1. Select **Applications** and then select the name of an app.
- 2. Select Data Protection.
- 3. Select Backups.
- 4. From the Options menu in the **Actions** column for the desired backup, select **Cancel**.
- 5. Type the word "cancel" to confirm deletion and then select **Yes, cancel backup**.

Delete backups

Delete the scheduled or on-demand backups that you no longer need.



There is no way to stop a running backup. If you need to delete the backup, wait until it has completed and then use these instructions. To delete a failed backup, use the Astra Control API.

Steps

- 1. Select **Applications** and then select the name of an app.
- 2. Select Data Protection.

- 3. Select Backups.
- 4. From the Options menu in the **Actions** column for the desired backup, select **Delete backup**.
- 5. Type the word "delete" to confirm deletion and then select **Yes, Delete backup**.

Result

Astra Control Center deletes the backup.

Restore apps

Astra Control can restore your application from a snapshot or backup. Restoring from an existing snapshot will be faster when restoring the application to the same cluster. You can use the Astra Control UI or the Astra Control API to restore apps.

About this task

- It is strongly recommended to take a snapshot of or back up your application before restoring it. This will enable you to clone from the snapshot or backup in the event that the restore is unsuccessful.
- If you use Helm to deploy apps, Astra Control Center requires Helm version 3. Managing and cloning apps deployed with Helm 3 (or upgraded from Helm 2 to Helm 3) are fully supported. Apps deployed with Helm 2 are not supported.
- If you restore to a different cluster, ensure that the cluster is using the same persistent volume access mode (for example, ReadWriteMany). The restore operation will fail if the destination persistent volume access mode is different.
- Any member user with namespace constraints by namespace name/ID or by namespace labels can clone
 or restore an app to a new namespace on the same cluster or to any other cluster in their organization's
 account. However, the same user cannot access the cloned or restored app in the new namespace. After a
 new namespace is created by a clone or restore operation, the account admin/owner can edit the member
 user account and update role constraints for the affected user to grant access to the new namespace.
- When you create a project for hosting an app on an OpenShift cluster, the project (or Kubernetes namespace) is assigned a SecurityContext UID. To enable Astra Control Center to protect your app and move the app to another cluster or project in OpenShift, you need to add policies that enable the app to run as any UID. As an example, the following OpenShift CLI commands grant the appropriate policies to a WordPress app.

```
oc new-project wordpress
oc adm policy add-scc-to-group anyuid system:serviceaccounts:wordpress
oc adm policy add-scc-to-user privileged -z default -n wordpress
```

Steps

- 1. Select **Applications** and then select the name of an app.
- 2. Select Data protection.
- 3. If you want to restore from a snapshot, keep the **Snapshots** icon selected. Otherwise, select the **Backups** icon to restore from a backup.
- 4. From the Options menu in the **Actions** column for the snapshot or backup from which you want to restore, select **Restore application**.
- 5. Restore details: Specify details for the restored app. By default, the current cluster and namespace appear. Leave these values intact to restore an app in-place, which reverts the app to an earlier version of itself. Change these values if you want to restore to a different cluster or namespace.

- Enter a name and namespace for the app.
- Choose the destination cluster for the app.
- Select Review.



If you restore to a namespace that was previously deleted, a new namespace with the same name is created as part of the restore process. Any users that had rights to manage apps in the previously deleted namespace need to manually restore rights to the newly re-created namespace.

6. **Restore Summary**: Review details about the restore action, type "restore", and select **Restore**.

Result

Astra Control Center restores the app based on the information that you provided. If you restored the app inplace, the contents of any existing persistent volumes are replaced with the contents of persistent volumes from the restored app.



After a data protection operation (clone, backup, restore) and subsequent persistent volume resize, there is a delay of up to twenty minutes before the new volume size is shown in the web UI. The data protection operation is successful within minutes, and you can use the management software for the storage backend to confirm the change in volume size.

Replicate apps to a remote system using SnapMirror technology

Using Astra Control, you can build business continuity for your applications with a low-RPO (Recovery Point Objective) and low-RTO (Recovery Time Objective) using asynchronous replication capabilities of NetApp SnapMirror technology. Once configured, this enables your applications to replicate data and application changes from one cluster to another.

For a comparison between backups/restores and replication, see Data protection concepts.

You can replicate apps in different scenarios, such as the following on-premises only, hybrid, and multi-cloud scenarios:

- On-premise site A to on-premise site B
- · On-premise to cloud with Cloud Volumes ONTAP
- Cloud with Cloud Volumes ONTAP to on-premise
- Cloud with Cloud Volumes ONTAP to cloud (between different regions in the same cloud provider or to different cloud providers)

Astra Control can replicate apps across on-premises clusters, on-premises to cloud (using Cloud Volumes ONTAP) or between clouds (Cloud Volumes ONTAP to Cloud Volumes ONTAP).



You can simultaneously replicate a different app (running on the other cluster or site) in the opposite direction. For example, Apps A, B, C can be replicated from Datacenter 1 to Datacenter 2; and Apps X, Y, Z can be replicated from Datacenter 2 to Datacenter 1.

Using Astra Control, you can do the following tasks related to replicating applications:

- · Set up a replication relationship
- Bring a replicated app online on the destination cluster (fail over)
- Resync a failed over replication
- · Reverse application replication
- Fail back applications to the original source cluster
- · Delete an application replication relationship

Replication prerequisites

See the replication prerequisites before you begin.

Set up a replication relationship

Setting up a replication relationship involves the following that make up the replication policy;

- Choosing how frequently you want Astra Control to take an app Snapshot (which includes the app's Kubernetes resources as well as the volume Snapshots for each of the app's volumes)
- Choosing the replication schedule (included Kubernetes resources as well as persistent volume data)
- Setting the time for the Snapshot to be taken

Steps

- 1. From the Astra Control left navigation, select **Applications**.
- 2. In the Application page, select the **Data Protection > Replication** tab.
- 3. In the Data Protection > Replication tab, select **Configure replication policy**. Or, from the Application Protection box, select the Actions option and select **Configure replication policy**.
- 4. Enter or select the following information:
 - Destination cluster
 - Destination storage class: Select or enter the storage class that uses the paired SVM on the destination ONTAP cluster.
 - **Replication type**: "Asynchronous" is currently the only replication type available.
 - Destination namespace: Enter a new or existing destination namespace for the destination cluster.



Any conflicting resources in the selected namespace will be overwritten.

- Replication frequency: Set how often you want Astra Control to take a Snapshot and replicate it to its
 destination.
- Offset: Set the number of minutes from the top of the hour that you want Astra Control to take a
 Snapshot. You might want to use an offset so that it doesn't coincide with other scheduled operations.
 For example, if you want to take the Snapshot every 5 minutes starting at 10:02, enter "02" as the
 offset minutes. The result would be 10:02, 10:07, 10:12, etc.
- 5. Select **Next**, review the summary, and select **Save**.



At first, the status displays "app-mirror" before the first schedule occurs.

Astra Control creates an application Snapshot used for replication.

To see the application Snapshot status, select the Applications > Snapshots tab.

The Snapshot name uses the format of "replication-schedule-<string>". Astra Control retains the last Snapshot that was used for replication. Any older replication Snapshots are deleted after successful completion of replication.

Result

This creates the replication relationship.

Astra Control completes the following actions as a result of establishing the relationship:

- Creates a namespace on the destination (if it doesn't exist)
- Creates a PVC on the destination namespace corresponding to the source app's PVCs.
- · Takes an initial app-consistent Snapshot.
- Establishes the SnapMirror relationship for persistent volumes using the initial Snapshot.

The Data Protection page shows the replication relationship state and status: <Health status> | <Relationship life cycle state>

For example: Normal | Established

Learn more about replication states and status below.

Bring a replicated app online on the destination cluster (fail over)

Using Astra Control, you can "fail over" replicated applications to a destination cluster. This procedure stops the replication relationship and brings the app online on the destination cluster. This procedure does not stop the app on the source cluster if it was operational.

Steps

- 1. From the Astra Control left navigation, select **Applications**.
- In the Application page, select the Data Protection > Replication tab.
- 3. In the Data Protection > Replication tab, from the Actions menu, select **Fail over**.
- 4. In the Fail over page, review the information and select **Fail over**.

Result

The following actions occur as a result of the fail over procedure:

- On the destination cluster, the app is started based on the latest replicated Snapshot.
- The source cluster and app (if operational) are not stopped and will continue to run.
- The replication state changes to "Failing over" and then to "Failed over" when it has completed.
- The source app's protection policy is copied to the destination app based on the schedules present on the source app at the time of the fail over.
- Astra Control shows the app both on the source and destination clusters and its respective health.

Resync a failed over replication

The resync operation re-establishes the replication relationship. You can choose the source of the relationship to retain the data on the source or destination cluster. This operation re-establishes the SnapMirror relationships to start the volume replication in the direction of choice.

The process stops the app on the new destination cluster before re-establishing replication.



During the resync process, the life cycle state shows as "Establishing."

Steps

- 1. From the Astra Control left navigation, select **Applications**.
- 2. In the Application page, select the **Data Protection > Replication** tab.
- 3. In the Data Protection > Replication tab, from the Actions menu, select **Resync**.
- 4. In the Resync page, select either the source or destination app instance containing the data that you want to preserve.



Choose the resync source carefully, as the data on the destination will be overwritten.

- 5. Select **Resync** to continue.
- 6. Type "resync" to confirm.
- 7. Select Yes, resync to finish.

Result

- The Replication page shows "Establishing" as the replication status.
- Astra Control stops the application on the new destination cluster.
- Astra Control re-establishes the persistent volume replication in the selected direction using SnapMirror resync.
- The Replication page shows the updated relationship.

Reverse application replication

This is the planned operation to move the application to the destination cluster while continuing to replicate back to the original source cluster. Astra Control stops the application on the source cluster and replicates the data to the destination before failing over the app to the destination cluster.

In this situation, you are swapping the source and destination. The original source cluster becomes the new destination cluster, and the original destination cluster becomes the new source cluster.

Steps

- 1. From the Astra Control left navigation, select **Applications**.
- 2. In the Application page, select the **Data Protection** > **Replication** tab.
- 3. In the Data Protection > Replication tab, from the Actions menu, select **Reverse replication**.
- 4. In the Reverse Replication page, review the information and select **Reverse replication** to continue.

Result

The following actions occur as a result of the reverse replication:

- A Snapshot is taken of the original source app's Kubernetes resources.
- The original source app's pods are gracefully stopped by deleting the app's Kubernetes resources (leaving PVCs and PVs in place).
- · After the pods are shut down, Snapshots of the app's volumes are taken and replicated.
- The SnapMirror relationships are broken, making the destination volumes ready for read/write.
- The app's Kubernetes resources are restored from the pre-shutdown Snapshot, using the volume data replicated after the original source app was shut down.
- · Replication is re-established in the reverse direction.

Fail back applications to the original source cluster

Using Astra Control, you can achieve "fail back" after a "fail over" operation by using the following sequence of operations. In this workflow to restore the original replication direction, Astra Control replicates (resyncs) any application changes back to the original source cluster before reversing the replication direction.

This process starts from a relationship that has completed a fail over to a destination and involves the following steps:

- · Start with a failed over state.
- · Resync the relationship.
- · Reverse the replication.

Steps

- 1. From the Astra Control left navigation, select **Applications**.
- 2. In the Application page, select the **Data Protection > Replication** tab.
- In the Data Protection > Replication tab, from the Actions menu, select Resync.
- 4. For a fail back operation, choose the failed over app as the source of the resync operation (preserving any data written post fail over).
- 5. Type "resync" to confirm.
- 6. Select **Yes, resync** to finish.
- 7. After the resync is complete, in the Data Protection > Replication tab, from the Actions menu, select **Reverse replication**.
- 8. In the Reverse Replication page, review the information and select **Reverse replication**.

Result

This combines the results from the "resync" and "reverse relationship" operations to bring the application online on the original source cluster with replication resumed to the original destination cluster.

Delete an application replication relationship

Deleting the relationship results in two separate apps with no relationship between them.

Steps

- 1. From the Astra Control left navigation, select **Applications**.
- 2. In the Application page, select the **Data Protection** > **Replication** tab.
- 3. In the Data Protection > Replication tab, from the Application Protection box or in the relationship diagram,

select Delete replication relationship.

Result

The following actions occur as a result of deleting a replication relationship:

- If the relationship is established but the app has not yet been brought online on the destination cluster (failed over), Astra Control retains PVCs created during initialization, leaves an "empty" managed app on the destination cluster, and retains the destination app to keep any backups that might have been created.
- If the app has been brought online on the destination cluster (failed over), Astra Control retains PVCs and destination apps. Source and destination apps are now treated as independent apps. The backup schedules remain on both apps but are not associated with each other.

Replication relationship health status and relationship life cycle states

Astra Control displays the health of the relationship and the states of the life cycle of the replication relationship.

Replication relationship health statuses

The following statuses indicate the health of the replication relationship:

- **Normal**: The relationship is either establishing or has established, and the most recent Snapshot transferred successfully.
- **Warning**: The relationship is either failing over or has failed over (and therefore is no longer protecting the source app).
- Critical
 - The relationship is establishing or failed over, and the last reconcile attempt failed.
 - The relationship is established, and the last attempt to reconcile the addition of a new PVC is failing.
 - The relationship is established (so a successful Snapshot has replicated, and failover is possible), but the most recent Snapshot failed or failed to replicate.

Replication life cycle states

The following states states reflect the different stages of the replication life cycle:

- **Establishing**: A new replication relationship is being created. Astra Control creates a namespace if needed, creates persistent volume claims (PVCs) on new volumes on the destination cluster, and creates SnapMirror relationships. This status can also indicate that the replication is resyncing or reversing replication.
- **Established**: A replication relationship exists. Astra Control periodically checks that the PVCs are available, checks the replication relationship, periodically creates Snapshots of the app, and identifies any new source PVCs in the app. If so, Astra Control creates the resources to include them in the replication.
- **Failing over**: Astra Control breaks the SnapMirror relationships and restores the app's Kubernetes resources from the last successfully replicated app Snapshot.
- **Failed over**: Astra Control stops replicating from the source cluster, uses the most recent (successful) replicated app Snapshot on the destination, and restores the Kubernetes resources.
- Resyncing: Astra Control resyncs the new data on the resync source to the resync destination by using SnapMirror resync. This operation might overwrite some of the data on the destination based on the direction of the sync. Astra Control stops the app running on the destination namespace and removes the Kubernetes app. During the resyncing process, the status shows as "Establishing."

Reversing: The is the planned operation to move the application to the destination cluster while continuing
to replicate back to the original source cluster. Astra Control stops the application on the source cluster,
replicates the data to the destination before failing over the app to the destination cluster. During the
reverse replication, the status shows as "Establishing."

· Deleting:

- If the replication relationship was established but not failed over yet, Astra Control removes PVCs that were created during replication and deletes the destination managed app.
- If the replication failed over already, Astra Control retains the PVCs and destination app.

Clone and migrate apps

Clone an existing app to create a duplicate app on the same Kubernetes cluster or on another cluster. When Astra Control Center clones an app, it creates a clone of your application configuration and persistent storage.

Cloning can help if you need to move applications and storage from one Kubernetes cluster to another. For example, you might want to move workloads through a CI/CD pipeline and across Kubernetes namespaces. You can use the Astra UI or the Astra Control API to clone and migrate apps.

What you'll need

To clone apps to a different cluster, you need a default bucket. When you add your first bucket, it becomes the default bucket.

About this task

- If you deploy an app with a StorageClass explicitly set and you need to clone the app, the target cluster must have the originally specified StorageClass. Cloning an application with an explicitly set StorageClass to a cluster that does not have the same StorageClass will fail.
- If you clone an operator-deployed instance of Jenkins CI, you need to manually restore the persistent data. This is a limitation of the app's deployment model.
- S3 buckets in Astra Control Center do not report available capacity. Before backing up or cloning apps managed by Astra Control Center, check bucket information in the ONTAP or StorageGRID management system.
- During an app backup or app restore, you can optionally specify a bucket ID. An app clone operation, however, always uses the default bucket that has been defined. There is no option to change buckets for a clone. If you want control over which bucket is used, you can either change the bucket default or do a backup followed by a restore separately.
- Any member user with namespace constraints by namespace name/ID or by namespace labels can clone
 or restore an app to a new namespace on the same cluster or to any other cluster in their organization's
 account. However, the same user cannot access the cloned or restored app in the new namespace. After a
 new namespace is created by a clone or restore operation, the account admin/owner can edit the member
 user account and update role constraints for the affected user to grant access to the new namespace.

OpenShift considerations

- If you clone an app between clusters, the source and destination clusters must be the same distribution of OpenShift. For example, if you clone an app from an OpenShift 4.7 cluster, use a destination cluster that is also OpenShift 4.7.
- When you create a project for hosting an app on an OpenShift cluster, the project (or Kubernetes namespace) is assigned a SecurityContext UID. To enable Astra Control Center to protect your app and move the app to another cluster or project in OpenShift, you need to add policies that enable the app to run

as any UID. As an example, the following OpenShift CLI commands grant the appropriate policies to a WordPress app.

```
oc new-project wordpress oc adm policy add-scc-to-group anyuid system:serviceaccounts:wordpress oc adm policy add-scc-to-user privileged -z default -n wordpress
```

Steps

- 1. Select Applications.
- Do one of the following:
 - Select the Options menu in the Actions column for the desired app.
 - Select the name of the desired app, and select the status drop-down list at the top right of the page.
- Select Clone.
- 4. Clone details: Specify details for the clone:
 - Enter a name.
 - Enter a namespace for the clone.
 - Choose a destination cluster for the clone.
 - Choose whether you want to create the clone from an existing snapshot or backup. If you don't select
 this option, Astra Control Center creates the clone from the app's current state.
- 5. **Source**: If you chose to clone from an existing snapshot or backup, choose the snapshot or backup that you'd like to use.
- Select Review.
- 7. Clone Summary: Review the details about the clone and select Clone.

Result

Astra Control Center clones that app based on the information that you provided. The clone operation is successful when the new app clone is in the Available state on the **Applications** page.



After a data protection operation (clone, backup, restore) and subsequent persistent volume resize, there is up to a twenty-minute delay before the new volume size is shown in the UI. The data protection operation is successful within minutes, and you can use the management software for the storage backend to confirm the change in volume size.

Manage app execution hooks

An execution hook is a custom action that you can configure to run in conjunction with a data protection operation of a managed app. For example, if you have a database app, you can use execution hooks to pause all database transactions before a snapshot, and resume transactions after the snapshot is complete. This ensures application-consistent snapshots.

Types of execution hooks

Astra Control supports the following types of execution hooks, based on when they can be run:

· Pre-snapshot

- Post-snapshot
- · Pre-backup
- · Post-backup
- Post-restore

Important notes about custom execution hooks

Consider the following when planning execution hooks for your apps.

- An execution hook must use a script to perform actions. Many execution hooks can reference the same script.
- Astra Control requires the scripts that execution hooks use to be written in the format of executable shell scripts.
- Script size is limited to 96KB.
- Astra Control uses execution hook settings and any matching criteria to determine which hooks are applicable to a snapshot, backup, or restore operation.
- All execution hook failures are soft failures; other hooks and the data protection operation are still
 attempted even if a hook fails. However, when a hook fails, a warning event is recorded in the **Activity**page event log.
- To create, edit, or delete execution hooks, you must be a user with Owner, Admin, or Member permissions.
- If an execution hook takes longer than 25 minutes to run, the hook will fail, creating an event log entry with a return code of "N/A". Any affected snapshot will time out and be marked as failed, with a resulting event log entry noting the timeout.
- For adhoc data protection operations, all hook events are generated and saved in the **Activity** page event log. However, for scheduled data protection operations, only hook failure events are recorded in the event log (events generated by the scheduled data protection operations themselves are still recorded).



Since execution hooks often reduce or completely disable the functionality of the application they are running against, you should always try to minimize the time your custom execution hooks take to run.

If you start a backup or snapshot operation with associated execution hooks but then cancel it, the hooks are still allowed to run if the backup or snapshot operation has already begun. This means that a post-backup execution hook cannot assume that the backup was completed.

Order of execution

When a data protection operation is run, execution hook events take place in the following order:

- 1. Any applicable custom pre-operation execution hooks are run on the appropriate containers. You can create and run as many custom pre-operation hooks as you need, but the order of execution of these hooks before the operation is neither guaranteed nor configurable.
- 2. The data protection operation is performed.
- Any applicable custom post-operation execution hooks are run on the appropriate containers. You can create and run as many custom post-operation hooks as you need, but the order of execution of these hooks after the operation is neither guaranteed nor configurable.

If you create multiple execution hooks of the same type (for example, pre-snapshot), the order of execution of those hooks is not guaranteed. However, the order of execution of hooks of different types is guaranteed. For example, the order of execution of a configuration that has all five different types of hooks would look like this:

- 1. Pre-backup hooks executed
- 2. Pre-snapshot hooks executed
- 3. Post-snapshot hooks executed
- 4. Post-backup hooks executed
- 5. Post-restore hooks executed

You can see an example of this configuration in scenario number 2 from the table in Determine whether a hook will run.



You should always test your execution hook scripts before enabling them in a production environment. You can use the 'kubectl exec' command to conveniently test the scripts. After you enable the execution hooks in a production environment, test the resulting snapshots and backups to ensure they are consistent. You can do this by cloning the app to a temporary namespace, restoring the snapshot or backup, and then testing the app.

Determine whether a hook will run

Use the following table to help determine if a custom execution hook will run for your app.

Note that all high-level app operations consist of running one of the basic operations of snapshot, backup, or restore. Depending on the scenario, a clone operation can consists of various combinations of these operations, so what execution hooks a clone operation runs will vary.

In-place restore operations require an existing snapshot or backup, so these operations don't run snapshot or backup hooks.

If you start but then cancel a backup that includes a snapshot and there are associated execution hooks, some hooks might run, and others might not. This means that a post-backup execution hook cannot assume that the backup was completed. Keep in mind the following points for cancelled backups with associated execution hooks:



- The pre-backup and post-backup hooks are always run.
- If the backup includes a new snapshot and the snapshot has started, the pre-snapshot and post-snapshot hooks are run.
- If the backup is cancelled prior to the snapshot starting, the pre-snapshot and post-snapshot hooks are not run.

Scenario	Operation	Existing snapshot	Existing backup	Namespa ce	Cluster	Snapshot hooks run	Backup hooks run	Restore hooks run
1	Clone	N	N	New	Same	Υ	N	Υ
2	Clone	N	N	New	Different	Υ	Υ	Υ
3	Clone or restore	Υ	N	New	Same	N	N	Υ
4	Clone or restore	N	Υ	New	Same	N	N	Υ
5	Clone or restore	Υ	N	New	Different	N	Υ	Υ

Scenario	Operation	Existing snapshot	Existing backup	Namespa ce	Cluster	Snapshot hooks run	Backup hooks run	Restore hooks run
6	Clone or restore	N	Υ	New	Different	N	N	Υ
7	Restore	Υ	N	Existing	Same	N	N	Υ
8	Restore	N	Υ	Existing	Same	N	N	Υ
9	Snapshot	N/A	N/A	N/A	N/A	Υ	N/A	N/A
10	Backup	N	N/A	N/A	N/A	Υ	Υ	N/A
11	Backup	Υ	N/A	N/A	N/A	N	Υ	N/A

View existing execution hooks

You can view existing custom execution hooks for an app.

Steps

- 1. Go to **Applications** and then select the name of a managed app.
- 2. Select the **Execution hooks** tab.

You can view all enabled or disabled execution hooks in the resulting list. You can see a hook's status, source, and when it runs (pre- or post-operation). To view event logs surrounding execution hooks, go to the **Activity** page in the left-side navigation area.

View existing scripts

You can view the existing uploaded scripts. You can also see which scripts are in use, and what hooks are using them, on this page.

Steps

- 1. Go to Account.
- Select the Scripts tab.

You can see a list of existing uploaded scripts on this page. The **Used by** column shows which execution hooks are using each script.

Add a script

You can add one or more scripts that execution hooks can reference. Many execution hooks can reference the same script; this enables you to update many execution hooks by only changing one script.

Steps

- 1. Go to Account.
- 2. Select the Scripts tab.
- 3. Select Add.
- 4. Do one of the following:
 - Upload a custom script.

- a. Select the Upload file option.
- b. Browse to a file and upload it.
- c. Give the script a unique name.
- d. (Optional) Enter any notes other administrators should know about the script.
- e. Select Save script.
- Paste in a custom script from the clipboard.
 - a. Select the **Paste or type** option.
 - b. Select the text field and paste the script text into the field.
 - c. Give the script a unique name.
 - d. (Optional) Enter any notes other administrators should know about the script.
- 5. Select Save script.

Result

The new script appears in the list on the **Scripts** tab.

Delete a script

You can remove a script from the system if it is no longer needed and not used by any execution hooks.

Steps

- 1. Go to Account.
- 2. Select the Scripts tab.
- 3. Choose a script you want to remove, and select the menu in the Actions column.
- 4. Select Delete.



If the script is associated with one or more execution hooks, the **Delete** action is unavailable. To delete the script, first edit the associated execution hooks and associate them with a different script.

Create a custom execution hook

You can create a custom execution hook for an app. See Execution hook examples for hook examples. You need to have Owner, Admin, or Member permissions to create execution hooks.



When you create a custom shell script to use as an execution hook, remember to specify the appropriate shell at the beginning of the file, unless you are running specific commands or providing the full path to an executable.

Steps

- 1. Select **Applications** and then select the name of a managed app.
- Select the Execution hooks tab.
- 3. Select Add.
- 4. In the **Hook Details** area, determine when the hook should run by selecting an operation type from the **Operation** drop-down menu.

- 5. Enter a unique name for the hook.
- 6. (Optional) Enter any arguments to pass to the hook during execution, pressing the Enter key after each argument you enter to record each one.
- 7. In the **Container Images** area, if the hook should run against all container images contained within the application, enable the **Apply to all container images** check box. If instead the hook should act only on one or more specified container images, enter the container image names in the **Container image names** to match field.
- 8. In the **Script** area, do one of the following:
 - Add a new script.
 - a. Select Add.
 - b. Do one of the following:
 - Upload a custom script.
 - i. Select the **Upload file** option.
 - ii. Browse to a file and upload it.
 - iii. Give the script a unique name.
 - iv. (Optional) Enter any notes other administrators should know about the script.
 - v. Select Save script.
 - Paste in a custom script from the clipboard.
 - i. Select the **Paste or type** option.
 - ii. Select the text field and paste the script text into the field.
 - iii. Give the script a unique name.
 - iv. (Optional) Enter any notes other administrators should know about the script.
 - · Select an existing script from the list.

This instructs the execution hook to use this script.

9. Select Add hook.

Check the state of an execution hook

After a snapshot, backup, or restore operation finishes running, you can check the state of execution hooks that ran as part of the operation. You can use this status information to determine if you want to keep the execution hook, modify it, or delete it.

Steps

- 1. Select **Applications** and then select the name of a managed app.
- 2. Select the **Data protection** tab.
- Select Snapshots to see running snapshots, or Backups to see running backups.

The **Hook state** shows the status of the execution hook run after the operation is complete. You can hover over the state for more details. For example, if there are execution hook failures during a snapshot, hovering over the hook state for that snapshot gives a list of failed execution hooks. To see reasons for each failure, you can check the **Activity** page in the left-side navigation area.

View script usage

You can see which execution hooks use a particular script in the Astra Control web UI.

Steps

- Select Account.
- 2. Select the Scripts tab.

The **Used by** column in the list of scripts contains details on which hooks are using each script in the list.

3. Select the information in the **Used by** column for a script you are interested in.

A more detailed list appears, with the names of hooks that are using the script and the type of operation they are configured to run with.

Disable an execution hook

You can disable an execution hook if you want to temporarily prevent it from running before or after a snapshot of an app. You need to have Owner, Admin, or Member permissions to disable execution hooks.

Steps

- 1. Select **Applications** and then select the name of a managed app.
- Select the Execution hooks tab.
- 3. Select the Options menu in the Actions column for a hook that you wish to disable.
- 4. Select Disable.

Delete an execution hook

You can remove an execution hook entirely if you no longer need it. You need to have Owner, Admin, or Member permissions to delete execution hooks.

Steps

- 1. Select **Applications** and then select the name of a managed app.
- 2. Select the Execution hooks tab.
- 3. Select the Options menu in the **Actions** column for a hook that you wish to delete.
- 4. Select **Delete**.

Execution hook examples

Use the following examples to get an idea of how to structure your execution hooks. You can use these hooks as templates, or as test scripts.

Simple success example

This is an example of a simple hook that succeeds and writes a message to standard output and standard error.

#!/bin/sh

```
# success_sample.sh
# A simple noop success hook script for testing purposes.
# args: None
# Writes the given message to standard output
# $* - The message to write
msg() {
   echo "$*"
}
# Writes the given information message to standard output
# $* - The message to write
info() {
  msg "INFO: $*"
}
# Writes the given error message to standard error
# $* - The message to write
error() {
   msg "ERROR: $*" 1>&2
}
# main
# log something to stdout
info "running success sample.sh"
# exit with 0 to indicate success
info "exit 0"
```

Simple success example (bash version)

This is an example of a simple hook that succeeds and writes a message to standard output and standard error, written for bash.

```
#!/bin/bash
# success sample.bash
#
# A simple noop success hook script for testing purposes.
# args: None
# Writes the given message to standard output
\# $* - The message to write
msq() {
    echo "$*"
}
# Writes the given information message to standard output
# $* - The message to write
info() {
   msg "INFO: $*"
}
# Writes the given error message to standard error
# $* - The message to write
error() {
    msg "ERROR: $*" 1>&2
}
```

```
# main
#

# log something to stdout
info "running success_sample.bash"

# exit with 0 to indicate success
info "exit 0"
exit 0
```

Simple success example (zsh version)

This is an example of a simple hook that succeeds and writes a message to standard output and standard error, written for Z shell.

```
#!/bin/zsh
# success sample.zsh
# A simple noop success hook script for testing purposes.
# args: None
# Writes the given message to standard output
# $* - The message to write
msg() {
   echo "$*"
}
# Writes the given information message to standard output
# $* - The message to write
info() {
   msg "INFO: $*"
}
# Writes the given error message to standard error
```

```
#
# $* - The message to write
#
error() {
    msg "ERROR: $*" 1>&2
}

#
# main
#
# log something to stdout
info "running success_sample.zsh"
# exit with 0 to indicate success
info "exit 0"
exit 0
```

Success with arguments example

The following example demonstrates how you can use args in a hook.

```
#!/bin/sh

# success_sample_args.sh

# A simple success hook script with args for testing purposes.

# args: Up to two optional args that are echoed to stdout

# Writes the given message to standard output

# s* - The message to write

# msg() {
   echo "$*"
}

# Writes the given information message to standard output

# info() {
```

```
msg "INFO: $*"
}
# Writes the given error message to standard error
# $* - The message to write
error() {
   msg "ERROR: $*" 1>&2
}
# main
# log something to stdout
info "running success sample args.sh"
# collect args
arg1=$1
arg2=$2
# output args and arg count to stdout
info "number of args: $#"
info "arg1 ${arg1}"
info "arg2 ${arg2}"
# exit with 0 to indicate success
info "exit 0"
exit 0
```

Pre-snapshot / post-snapshot hook example

The following example demonstrates how the same script can be used for both a pre-snapshot and a post-snapshot hook.

```
#!/bin/sh

# success_sample_pre_post.sh

#

# A simple success hook script example with an arg for testing purposes
# to demonstrate how the same script can be used for both a prehook and
posthook
```

```
# args: [pre|post]
# unique error codes for every error case
ebase=100
eusage=$((ebase+1))
ebadstage=$((ebase+2))
epre=$((ebase+3))
epost=$((ebase+4))
# Writes the given message to standard output
# $* - The message to write
msg() {
   echo "$*"
}
# Writes the given information message to standard output
# $* - The message to write
info() {
   msg "INFO: $*"
}
\# Writes the given error message to standard error
# $* - The message to write
error() {
   msg "ERROR: $*" 1>&2
}
# Would run prehook steps here
prehook() {
   info "Running noop prehook"
    return 0
```

```
# Would run posthook steps here
posthook() {
   info "Running noop posthook"
   return 0
}
# main
# check arg
stage=$1
if [ -z "${stage}" ]; then
   echo "Usage: $0 <pre|post>"
   exit ${eusage}
fi
if [ "${stage}" != "pre" ] && [ "${stage}" != "post" ]; then
   echo "Invalid arg: ${stage}"
   exit ${ebadstage}
fi
# log something to stdout
info "running success sample pre post.sh"
if [ "${stage}" = "pre" ]; then
   prehook
   rc=$?
   if [ ${rc} -ne 0 ]; then
       error "Error during prehook"
    fi
fi
if [ "${stage}" = "post" ]; then
   posthook
   rc=$?
   if [ ${rc} -ne 0 ]; then
       error "Error during posthook"
    fi
fi
```

Failure example

The following example demonstrates how you can handle failures in a hook.

```
#!/bin/sh
# failure sample arg exit code.sh
# A simple failure hook script for testing purposes.
# args: [the exit code to return]
# Writes the given message to standard output
# $* - The message to write
msg() {
   echo "$*"
}
# Writes the given information message to standard output
# $* - The message to write
info() {
   msg "INFO: $*"
}
# Writes the given error message to standard error
# $* - The message to write
error() {
    msg "ERROR: $*" 1>&2
}
```

```
# main
#

# log something to stdout
info "running failure_sample_arg_exit_code.sh"

argexitcode=$1

# log to stderr
error "script failed, returning exit code ${argexitcode}"

# exit with specified exit code
exit ${argexitcode}
```

Verbose failure example

The following example demonstrates how you can handle failures in a hook, with more verbose logging.

```
#!/bin/sh
# failure sample verbose.sh
# A simple failure hook script with args for testing purposes.
# args: [The number of lines to output to stdout]
# Writes the given message to standard output
# $* - The message to write
msq() {
    echo "$*"
}
# Writes the given information message to standard output
\# $* - The message to write
info() {
   msg "INFO: $*"
}
```

```
# Writes the given error message to standard error
#
# $* - The message to write
error() {
   msg "ERROR: $*" 1>&2
}
# main
# log something to stdout
info "running failure sample verbose.sh"
# output arg value to stdout
linecount=$1
info "line count ${linecount}"
# write out a line to stdout based on line count arg
i=1
while [ "$i" -le ${linecount} ]; do
   info "This is line ${i} from failure sample verbose.sh"
    i=\$((i+1))
done
error "exiting with error code 8"
exit 8
```

Failure with an exit code example

The following example demonstrates a hook failing with an exit code.

```
#!/bin/sh

# failure_sample_arg_exit_code.sh
#
# A simple failure hook script for testing purposes.
#
# args: [the exit code to return]
#
```

```
# Writes the given message to standard output
# $* - The message to write
msg() {
  echo "$*"
}
# Writes the given information message to standard output
# $* - The message to write
info() {
   msg "INFO: $*"
}
# Writes the given error message to standard error
# $* - The message to write
error() {
   msg "ERROR: $*" 1>&2
}
# main
# log something to stdout
info "running failure sample arg exit code.sh"
argexitcode=$1
# log to stderr
error "script failed, returning exit code ${argexitcode}"
# exit with specified exit code
exit ${argexitcode}
```

Success after failure example

The following example demonstrates a hook failing the first time it is run, but succeeding after the second run.

```
#!/bin/sh
# failure_then_success_sample.sh
# A hook script that fails on initial run but succeeds on second run for
testing purposes.
# Helpful for testing retry logic for post hooks.
# args: None
#
# Writes the given message to standard output
# $* - The message to write
msg() {
   echo "$*"
}
# Writes the given information message to standard output
# $* - The message to write
info() {
   msg "INFO: $*"
}
# Writes the given error message to standard error
# $* - The message to write
error() {
   msg "ERROR: $*" 1>&2
}
# main
```

```
#
# log something to stdout
info "running failure_success sample.sh"

if [ -e /tmp/hook-test.junk ] ; then
    info "File does exist. Removing /tmp/hook-test.junk"
    rm /tmp/hook-test.junk
    info "Second run so returning exit code 0"
    exit 0

else
    info "File does not exist. Creating /tmp/hook-test.junk"
    echo "test" > /tmp/hook-test.junk
    error "Failed first run, returning exit code 5"
    exit 5
fi
```

Monitor app and cluster health

View a summary of app and cluster health

Select the **Dashboard** to see a high-level view of your apps, clusters, storage backends, and their health.

These aren't just static numbers or statuses—you can drill down from each. For example, if apps aren't fully protected, you can hover over the icon to identify which apps aren't fully protected, which includes a reason why.

Applications tile

The **Applications** tile helps you identify the following:

- How many apps you're currently managing with Astra.
- · Whether those managed apps are healthy.
- Whether the apps are fully protected (they're protected if recent backups are available).
- The number of apps that were discovered, but are not yet managed.

Ideally, this number would be zero because you would either manage or ignore apps after they're discovered. And then you would monitor the number of discovered apps on the Dashboard to identify when developers add new apps to a cluster.

Clusters tile

The **Clusters** tile provides similar details about the health of the clusters that you are managing by using Astra Control Center, and you can drill down to get more details just like you can with an app.

Storage backends tile

The **Storage backends** tile provides information to help you identify the health of storage backends including:

- · How many storage backends are managed
- Whether these managed backends are healthy
- · Whether the backends are fully protected
- The number of backends that are discovered, but are not yet managed.

View the health and details of clusters

After you add clusters to be managed by Astra Control Center, you can view details about the cluster, such as its location, the worker nodes, persistent volumes, and storage classes.

Steps

- 1. In the Astra Control Center UI, select Clusters.
- 2. On the Clusters page, select the cluster whose details you want to view.



If a cluster is in removed state yet cluster and network connectivity appears healthy (external attempts to access the cluster using Kubernetes APIs are successful), the kubeconfig you provided to Astra Control might no longer be valid. This can be due to certificate rotation or expiration on the cluster. To correct this issue, update the credentials associated with the cluster in Astra Control using the Astra Control API.

- 3. View the information on the **Overview**, **Storage**, and **Activity** tabs to find the information that you're looking for.
 - Overview: Details about the worker nodes, including their state.
 - Storage: The persistent volumes associated with the compute, including the storage class and state.
 - Activity: Shows the activities related to the cluster.



You can also view cluster information starting from the Astra Control Center **Dashboard**. On the **Clusters** tab under **Resource summary**, you can select the managed clusters, which takes you to the **Clusters** page. After you get to the **Clusters** page, follow the steps outlined above.

View the health and details of an app

After you start managing an app, Astra provides details about the app that enables you to identify its status (whether it's healthy), its protection status (whether it's fully protected in case of failure), the pods, persistent storage, and more.

Steps

- 1. In the Astra Control Center UI, select **Applications** and then select the name of an app.
- 2. Find the information that you're looking for:

App Status

Provides a status that reflects the app's state in Kubernetes. For example, are pods and persistent

volumes online? If an app is unhealthy, you'll need to go and troubleshoot the issue on the cluster by looking at Kubernetes logs. Astra doesn't provide information to help you fix a broken app.

App Protection Status

Provides a status of how well the app is protected:

- Fully protected: The app has an active backup schedule and a successful backup that's less than a week old
- Partially protected: The app has an active backup schedule, an active snapshot schedule, or a successful backup or snapshot
- **Unprotected**: Apps that are neither fully protected or partially protected.

You can't be fully protected until you have a recent backup. This is important because backups are stored in an object store away from the persistent volumes. If a failure or accident wipes out the cluster and it's persistent storage, then you need a backup to recover. A snapshot wouldn't enable you to recover.

Overview

Information about the state of the pods that are associated with the app.

Data protection

Enables you to configure a data protection policy and to view the existing snapshots and backups.

Storage

Shows you the app-level persistent volumes. The state of a persistent volume is from the perspective of the Kubernetes cluster.

Resources

Enables you to verify which resources are being backed up and managed.

Activity

Shows the activities related to the app.



You can also view app information starting from the Astra Control Center **Dashboard**. On the **Applications** tab under **Resource summary**, you can select the managed apps, which takes you to the **Applications** page. After you get to the **Applications** page, follow the steps outlined above.

Manage your account

Manage users

You can invite, add, remove, and edit users of your Astra Control Center installation using the Astra Control UI. You can use the Astra Control UI or the Astra Control API to manage users.

You can also use LDAP to perform authentication for selected users.

Use LDAP

LDAP is an industry standard protocol for accessing distributed directory information and a popular choice for

enterprise authentication. You can connect Astra Control Center to an LDAP server to perform authentication for selected Astra users. At a high level, the configuration involves integrating Astra with LDAP and defining the Astra users and groups corresponding to the LDAP definitions. See LDAP authentication for more information.

Invite users

Account Owners and Admins can invite new users to Astra Control Center.

Steps

- 1. In the Manage Your Account navigation area, select Account.
- 2. Select the Users tab.
- Select Invite User.
- 4. Enter the user's name and email address.
- 5. Select a user role with the appropriate system permissions.

Each role provides the following permissions:

- A Viewer can view resources.
- A Member has Viewer role permissions and can manage apps and clusters, unmanage apps, and delete snapshots and backups.
- An **Admin** has Member role permissions and can add and remove any other users except the Owner.
- An Owner has Admin role permissions and can add and remove any user accounts.
- To add constraints to a user with a Member or Viewer role, enable the Restrict role to constraints check box.

For more information on adding constraints, see Manage roles.

7. Select Invite users.

The user receives an email informing them that they've been invited to Astra Control Center. The email includes temporary password, which they'll need to change upon first login.

Add users

Account Owners and Admins can add more users to the Astra Control Center installation.

Steps

- 1. In the Manage Your Account navigation area, select Account.
- 2. Select the Users tab.
- Select Add User.
- 4. Enter the user's name, email address, and a temporary password.

The user will need to change the password upon first login.

5. Select a user role with the appropriate system permissions.

Each role provides the following permissions:

· A Viewer can view resources.

- A Member has Viewer role permissions and can manage apps and clusters, unmanage apps, and delete snapshots and backups.
- · An Admin has Member role permissions and can add and remove any other users except the Owner.
- An **Owner** has Admin role permissions and can add and remove any user accounts.
- To add constraints to a user with a Member or Viewer role, enable the Restrict role to constraints check box.

For more information on adding constraints, see Manage roles.

Select Add.

Manage passwords

You can manage passwords for user accounts in Astra Control Center.

Change your password

You can change the password of your user account at any time.

Steps

- 1. Select the User icon at the top right of the screen.
- 2. Select Profile.
- 3. From the Options menu in the **Actions** column, and select **Change Password**.
- 4. Enter a password that conforms to the password requirements.
- 5. Enter the password again to confirm.
- 6. Select Change password.

Reset another user's password

If your account has Admin or Owner role permissions, you can reset passwords for other user accounts as well as your own. When you reset a password, you assign a temporary password that the user will have to change upon logging in.

Steps

- 1. In the Manage Your Account navigation area, select Account.
- 2. Select the **Actions** drop-down list.
- 3. Select Reset Password.
- 4. Enter a temporary password that conforms to the password requirements.
- 5. Enter the password again to confirm.
 - The next time the user logs in, the user will be prompted to change the password.
- 6. Select Reset password.

Change a user's role

Users with the Owner role can change the role of all users, while users with the Admin role can change the role of users who have the Admin, Member, or Viewer role.

Steps

- 1. In the Manage Your Account navigation area, select Account.
- 2. Select the Actions drop-down list.
- Select Edit role.
- 4. Select a new role.
- To apply constraints to the role, enable the **Restrict role to constraints** check box and select a constraint from the list.

If there are no constraints, you can add a constraint. For more information, see Manage roles.

6. Select Confirm.

Result

Astra Control Center updates the user's permissions based on the new role that you selected.

Remove users

Users with the Owner or Admin role can remove other users from the account at any time.

Steps

- 1. In the Manage Your Account navigation area, select Account.
- 2. In the **Users** tab, select the check box in the row of each user that you want to remove.
- 3. From the Options menu in the **Actions** column, select **Remove user/s**.
- 4. When you're prompted, confirm deletion by typing the word "remove" and then select **Yes, Remove User**.

Result

Astra Control Center removes the user from the account.

Manage roles

You can manage roles by adding namespace constraints and restricting user roles to those constraints. This enables you to control access to resources within your organization. You can use the Astra Control UI or the Astra Control API to manage roles.

Add a namespace constraint to a role

An Admin or Owner user can add namespace constraints.

Steps

- 1. In the Manage Your Account navigation area, select Account.
- Select the Users tab.
- 3. In the **Actions** column, select the menu button for a user with the Member or Viewer role.
- 4. Select Edit role.
- 5. Enable the **Restrict role to constraints** check box.

The check box is only available for Member or Viewer roles. You can select a different role from the **Role** drop-down list.

Select Add constraint.

You can view the list of available constraints by namespace or by namespace label.

- 7. In the **Constraint type** drop-down list, select either **Kubernetes namespace** or **Kubernetes namespace** label depending on how your namespaces are configured.
- 8. Select one or more namespaces or labels from the list to compose a constraint that restricts roles to those namespaces.
- 9. Select Confirm.

The **Edit role** page displays the list of constraints you've chosen for this role.

10. Select Confirm.

On the Account page, you can view the constraints for any Member or Viewer role in the Role column.



If you enable constraints for a role and select **Confirm** without adding any constraints, the role is considered to have full restrictions (the role is denied access to any resources that are assigned to namespaces).

Remove a namespace constraint from a role

An Admin or Owner user can remove a namespace constraint from a role.

Steps

- 1. In the Manage Your Account navigation area, select Account.
- 2. Select the Users tab.
- In the Actions column, select the menu button for a user with the Member or Viewer role that has active constraints.
- 4. Select Edit role.

The **Edit role** dialog displays the active constraints for the role.

- 5. Select the **X** to the right of the constraint you need to remove.
- Select Confirm.

For more information

User roles and namespaces

View and manage notifications

Astra notifies you when actions have completed or failed. For example, you'll see a notification if a backup of an app completed successfully.

You can manage these notifications from the top right of the interface:



Steps

- 1. Select the number of unread notifications in the top right.
- 2. Review the notifications and then select Mark as read or Show all notifications.

If you selected **Show all notifications**, the Notifications page loads.

3. On the **Notifications** page, view the notifications, select the ones that you want to mark as read, select **Action** and select **Mark as read**.

Add and remove credentials

Add and remove credentials for local private cloud providers such as ONTAP S3, Kubernetes clusters managed with OpenShift, or unmanaged Kubernetes clusters from your account at any time. Astra Control Center uses these credentials to discover Kubernetes clusters and the apps on the clusters, and to provision resources on your behalf.

Note that all users in Astra Control Center share the same sets of credentials.

Add credentials

You can add credentials to Astra Control Center when you manage clusters. To add credentials by adding a new cluster, see Add a Kubernetes cluster.



If you create your own kubeconfig file, you should define only **one** context element in it. See Kubernetes documentation for information about creating kubeconfig files.

Remove credentials

Remove credentials from an account at any time. You should only remove credentials after unmanaging all associated clusters.



The first set of credentials that you add to Astra Control Center is always in use because Astra Control Center uses the credentials to authenticate to the backup bucket. It's best not to remove these credentials.

Steps

- Select Account.
- 2. Select the Credentials tab.
- Select the Options menu in the State column for the credentials that you want to remove.
- 4. Select Remove.
- 5. Type the word "remove" to confirm deletion and then select Yes, Remove Credential.

Result

Astra Control Center removes the credentials from the account.

Monitor account activity

You can view details about the activities in your Astra Control account. For example, when new users were invited, when a cluster was added, or when a snapshot was taken.

You also have the ability to export your account activity to a CSV file.



If you manage Kubernetes clusters from Astra Control and Astra Control is connected to Cloud Insights, Astra Control sends event logs to Cloud Insights. The log information, including information about pod deployment and PVC attachments, appears in the Astra Control Activity log. Use this information to identify any issues on the Kubernetes clusters you are managing.

View all account activity in Astra Control

- Select Activity.
- Use the filters to narrow down the list of activities or use the search box to find exactly what you're looking for.
- 3. Select **Export to CSV** to download your account activity to a CSV file.

View account activity for a specific app

- 1. Select **Applications** and then select the name of an app.
- Select Activity.

View account activity for clusters

- 1. Select Clusters and then select the name of the cluster.
- 2. Select Activity.

Take action to resolve events that require attention

- 1. Select Activity.
- 2. Select an event that requires attention.
- 3. Select the **Take action** drop-down option.

From this list, you can view possible corrective actions that you can take, view documentation related to the issue, and get support to help resolve the issue.

Update an existing license

You can convert an evaluation license to a full license, or you can update an existing evaluation or full license with a new license. If you don't have a full license, work with your NetApp sales contact to obtain a full license and serial number. You can use the Astra UI or the Astra Control API to update an existing license.

Steps

- 1. Log in to the NetApp Support Site.
- 2. Access the Astra Control Center Download page, enter the serial number, and download the full NetApp license file (NLF).
- 3. Log in to the Astra Control Center UI.
- 4. From the left navigation, select **Account > License**.
- In the Account > License page, select the status drop-down menu for the existing license and select Replace.
- 6. Browse to the license file that you downloaded.
- 7. Select Add.

The **Account > Licenses** page displays the license information, expiration date, license serial number,

account ID, and CPU units used.

For more information

Astra Control Center licensing

Manage repository connections

You can connect repositories to Astra Control to use as a reference for software package installation images and artifacts. When you import software packages, Astra Control references installation images in the image repository and binaries and other artifacts in the artifact repository.

What you'll need

- · Kubernetes cluster with Astra Control Center installed
- · A running Docker repository that you can access
- · A running artifact repository (such as Artifactory) that you can access

Connect a Docker image repository

You can connect a Docker image repository to hold package installation images, such as those for Astra Data Store. When you install packages, Astra Control imports the package image files from the image repository.

Steps

- 1. In the Manage Your Account navigation area, select Account.
- Select the Connections tab.
- In the Docker Image Repository section, select the menu at the top right.
- 4. Select Connect.
- 5. Add the URL and port for the repository.
- 6. Enter the credentials for the repository.
- Select Connect.

Result

The repository is connected. In the **Docker Image Repository** section, the repository should show a connected status.

Disconnect a Docker image repository

You can remove the connection to a Docker image repository if it is no longer needed.

Steps

- 1. In the Manage Your Account navigation area, select Account.
- Select the Connections tab.
- 3. In the Docker Image Repository section, select the menu at the top right.
- Select Disconnect.
- 5. Select Yes, disconnect Docker image repository.

Result

The repository is disconnected. In the Docker Image Repository section, the repository should show a

disconnected status.

Connect an artifact repository

You can connect an artifact repository to host artifacts such as software package binaries. When you install packages, Astra Control imports the artifacts for the software packages from the image repository.

Steps

- 1. In the **Manage Your Account** navigation area, select **Account**.
- 2. Select the Connections tab.
- 3. In the Artifact Repository section, select the menu at the top right.
- 4. Select Connect.
- 5. Add the URL and port for the repository.
- 6. If authentication is required, enable the **Use authentication** check box and enter the credentials for the repository.
- Select Connect.

Result

The repository is connected. In the **Artifact Repository** section, the repository should show a connected status.

Disconnect an artifact repository

You can remove the connection to an artifact repository if it is no longer needed.

Steps

- 1. In the **Manage Your Account** navigation area, select **Account**.
- Select the Connections tab.
- 3. In the Artifact Repository section, select the menu at the top right.
- 4. Select **Disconnect**.
- 5. Select Yes, disconnect artifact repository.

Result

The repository is disconnected. In the **Artifact Repository** section, the repository should show a connected status.

Find more information

Manage software packages

Manage software packages

NetApp delivers additional capabilities for Astra Control Center with software packages that you can download from the NetApp Support Site. After you connect Docker and artifact repositories, you can upload and import packages to add this functionality to Astra Control Center. You can use the CLI or the Astra Control Center web UI to manage software packages.

What you'll need

- Kubernetes cluster with Astra Control Center installed
- A connected Docker image repository to hold software package images. For more information, see Manage repository connections.
- A connected artifact repository to hold software package binaries and artifacts. For more information, see Manage repository connections.
- · A software package from the NetApp Support Site

Upload software package images to the repositories

Astra Control Center references package images and artifacts in connected repositories. You can upload images and artifacts to the repositories using the CLI.

Steps

- 1. Download the software package from the NetApp Support Site, and save it on a machine that has the kubectl utility installed.
- 2. Extract the compressed package file, and change directory to the location of the Astra Control bundle file (for example, acc.manifest.yaml).
- 3. Push the package images to the Docker repository. Make the following substitutions:
 - Replace BUNDLE_FILE with the name of the Astra Control bundle file (for example, acc.manifest.yaml).
 - Replace MY_REGISTRY with the URL of the Docker repository.
 - Replace MY REGISTRY USER with the user name.
 - Replace MY REGISTRY TOKEN with an authorized token for the registry.

```
kubectl astra packages push-images -m BUNDLE_FILE -r MY_REGISTRY -u
MY_REGISTRY_USER -p MY_REGISTRY_TOKEN
```

4. If the package has artifacts, copy the artifacts to the artifact repository. Replace BUNDLE_FILE with the name of the Astra Control bundle file, and NETWORK_LOCATION with the network location to copy the artifact files to:

```
kubectl astra packages copy-artifacts -m BUNDLE_FILE -n NETWORK_LOCATION
```

Add a software package

You can import software packages using an Astra Control Center bundle file. Doing this installs the package and makes the software available for Astra Control Center to use.

Add a software package using the Astra Control web UI

You can use the Astra Control Center web UI to add a software package that has been uploaded to the connected repositories.

Steps

1. In the Manage Your Account navigation area, select Account.

- Select the Packages tab.
- 3. Select the Add button.
- 4. In the file selection dialog, select the upload icon.
- 5. Choose an Astra Control bundle file, in .yaml format, to upload.
- 6. Select Add.

Result

If the bundle file is valid and the package images and artifacts are located in your connected repositories, the package is added to Astra Control Center. When the status in the **Status** column changes to **Available**, you can use the package. You can hover over the status for a package to get more information.



If one or more images or artifacts for a package are not found in your repository, an error message appears for that package.

Add a software package using the CLI

You can use the CLI to import a software package that you have uploaded to the connected repositories. To do this, you first need to record your Astra Control Center account ID and an API token.

Steps

- 1. Using a web browser, log in to the Astra Control Center web UI.
- 2. From the Dashboard, select the user icon at the top right.
- Select API access.
- 4. Note the Account ID near the top of the screen.
- 5. Select Generate API token.
- 6. In the resulting dialog, select Generate API token.
- 7. Note the resulting token, and select **Close**.

 In the CLI, change directories to the location of the .yaml bundle file in the extracted package contents.
- 8. Import the package using the bundle file, making the following substitutions:
 - Replace BUNDLE FILE with the name of the Astra Control bundle file.
 - Replace SERVER with the DNS name of the Astra Control instance.
 - Replace ACCOUNT ID and TOKEN with the account ID and API token you recorded earlier.

kubectl astra packages import -m BUNDLE_FILE -u SERVER -a ACCOUNT_ID
-k TOKEN

Result

If the bundle file is valid and the package images and artifacts are located in your connected repositories, the package is added to Astra Control Center.



If one or more images or artifacts for a package are not found in your repository, an error message appears for that package.

Remove a software package

You can use the Astra Control Center web UI to remove a software package that you previously imported in Astra Control Center.

Steps

- 1. In the Manage Your Account navigation area, select Account.
- 2. Select the Packages tab.

You can see the list of installed packages and their statuses on this page.

- 3. In the **Actions** column for the package, open the actions menu.
- 4. Select **Delete**.

Result

The package is deleted from Astra Control Center, but the images and artifacts for the package remain in your repositories.

Find more information

· Manage repository connections

Manage buckets

An object store bucket provider is essential if you want to back up your applications and persistent storage or if you want to clone applications across clusters. Using Astra Control Center, add an object store provider as your off-cluster, backup destination for your apps.

You don't need a bucket if you are cloning your application configuration and persistent storage to the same cluster.

Use one of the following Amazon Simple Storage Service (S3) bucket providers:

- NetApp ONTAP S3
- NetApp StorageGRID S3
- Microsoft Azure
- · Generic S3



Amazon Web Services (AWS) and Google Cloud Platform (GCP) use the Generic S3 bucket type.



Although Astra Control Center supports Amazon S3 as a Generic S3 bucket provider, Astra Control Center might not support all object store vendors that claim Amazon's S3 support.

A bucket can be in one of these states:

- pending: The bucket is scheduled for discovery.
- available: The bucket is available for use.
- removed: The bucket is not currently accessible.

For instructions on how to manage buckets using the Astra Control API, see the Astra Automation and API information.

You can do these tasks related to managing buckets:

- Add a bucket
- Edit a bucket
- · Rotate or remove bucket credentials
- · Remove a bucket



S3 buckets in Astra Control Center do not report available capacity. Before backing up or cloning apps managed by Astra Control Center, check bucket information in the ONTAP or StorageGRID management system.

Edit a bucket

You can change the access credential information for a bucket and change whether a selected bucket is the default bucket.



When you add a bucket, select the correct bucket provider and provide the right credentials for that provider. For example, the UI accepts NetApp ONTAP S3 as the type and accepts StorageGRID credentials; however, this will cause all future app backups and restores using this bucket to fail. See the Release Notes.

Steps

- 1. From the left navigation, select **Buckets**.
- 2. From the Options menu in the **Actions** column, select **Edit**.
- 3. Change any information other than the bucket type.



You can't modify the bucket type.

4. Select Update.

Rotate or remove bucket credentials

Astra Control uses bucket credentials to gain access and provide secret keys for an S3 bucket so that Astra Control Center can communicate with the bucket.

Rotate bucket credentials

If you rotate credentials, rotate them during a maintenance window when no backups are in progress (scheduled or on-demand).

Steps to edit and rotate credentials

- 1. From the left navigation, select **Buckets**.
- 2. From the Options menu in the Actions column, select Edit.
- 3. Create the new credential.
- 4. Select Update.

Remove bucket credentials

You should remove bucket credentials only if new credentials have been applied to a bucket, or if the bucket is no longer actively used.



The first set of credentials that you add to Astra Control is always in use because Astra Control uses the credentials to authenticate the backup bucket. Do not remove these credentials if the bucket is in active use as this will lead to backup failures and backup unavailability.



If you do remove active bucket credentials, see troubleshooting bucket credential removal.

For instructions on how to remove S3 credentials using the Astra Control API, see the Astra Automation and API information.

Remove a bucket

You can remove a bucket that is no longer in use or is not healthy. You might want to do this to keep your object store configuration simple and up-to-date.



You cannot remove a default bucket. If you want to remove that bucket, first select another bucket as the default.

What you'll need

- You should check to ensure that there are no running or completed backups for this bucket before you begin.
- You should check to ensure that the bucket is not being used in any active protection policy.

If there are, you will not be able to continue.

Steps

- 1. From left navigation, select Buckets.
- 2. From the **Actions** menu, select **Remove**.



Astra Control ensures first that there are no schedule policies using the bucket for backups and that there are no active backups in the bucket you are about to remove.

- 3. Type "remove" to confirm the action.
- 4. Select Yes, remove bucket.

Find more information

Use the Astra Control API

Manage the storage backend

Managing storage clusters in Astra Control as a storage backend enables you to get linkages between persistent volumes (PVs) and the storage backend as well as additional storage metrics. You can monitor storage capacity and health details, including performance if Astra Control Center is connected to Cloud Insights.

For instructions on how to manage storage backends using the Astra Control API, see the Astra Automation and API information.

You can complete the following tasks related to managing a storage backend:

- · Add a storage backend
- View storage backend details
- · Unmanage a storage backend
- · Update an Astra Data Store storage backend license
- Upgrade an Astra Data Store storage backend
- · Remove a storage backend
- · Add nodes to a storage backend cluster
- · Remove nodes from a storage backend cluster

View storage backend details

You can view storage backend information from the Dashboard or from the Backends option.

In the Storage Backend Details page, for Astra Data Store, you can see the following information:

- Astra Data Store cluster
 - Throughput, IOPS, and latency
 - Used capacity compared to total capacity
- · For each Astra Data Store cluster volume
 - Used capacity compared to total capacity
 - Throughput

View storage backend details from the Dashboard

Steps

- 1. From the left navigation, select **Dashboard**.
- 2. Review the Storage backend section that shows the state:
 - Unhealthy: The storage is not in an optimal state. This could be due to a latency issue or an app is degraded due to a container issue, for example.
 - All healthy: The storage has been managed and is in an optimal state.
 - Discovered: The storage has been discovered, but not managed by Astra Control.

View storage backend details from the Backends option

View information about the backend health, capacity, and performance (IOPS throughput and/or latency).

You can see the volumes that the Kubernetes apps are using, which are stored on a selected storage backend. With Cloud Insights, you can see additional information. See Cloud Insights documentation.


Steps

1. In the left navigation area, select Backends.

Select the storage backend.



If you connected to NetApp Cloud Insights, excerpts of data from Cloud Insights appear on the Backends page.



3. To go directly to Cloud Insights, select the Cloud Insights icon next to the metrics image.

Unmanage a storage backend

You can unmanage the backend.

Steps

- 1. From the left navigation, select **Backends**.
- 2. Select the storage backend.
- 3. From the Options menu in the **Actions** column, select **Unmanage**.
- 4. Type "unmanage" to confirm the action.
- 5. Select Yes, unmanage storage backend.

Remove a storage backend

You can remove a storage backend that is no longer in use. You might want to do this to keep your configuration simple and up-to-date.



If you are removing an Astra Data Store backend, it must not have been created by vCenter.

What you'll need

- · Ensure that the storage backend is unmanaged.
- Ensure that the storage backend does not have any volumes associated with the Astra Data Store cluster.

Steps

- 1. From left navigation, select Backends.
- 2. If the backend is managed, unmanage it.
 - a. Select Managed.
 - b. Select the storage backend.
 - c. From the **Actions** option, select **Unmanage**.
 - d. Type "unmanage" to confirm the action.
 - e. Select Yes, unmanage storage backend.
- 3. Select **Discovered**.
 - a. Select the storage backend.
 - b. From the **Actions** option, select **Remove**.
 - c. Type "remove" to confirm the action.
 - d. Select Yes, remove storage backend.

Update an Astra Data Store storage backend license

You can update the license for an Astra Data Store storage backend to support a larger deployment or enhanced features.

What you'll need

- · A deployed and managed Astra Data Store storage backend
- An Astra Data Store license file (contact your NetApp sales representative to purchase an Astra Data Store license)

Steps

- 1. From the left navigation, select **Backends**.
- 2. Select the name of a storage backend.
- 3. Under **Basic Information**, you can see the type of license installed.

If you hover over the license information, a popup appears with more information, such as expiration and entitlement information.

- 4. Under **License**, select the edit icon next to the license name.
- 5. In the **Update license** page, do one of the following:

License status	Action
At least one license has been added to Astra Data Store.	Select a license from the list.

License status	Action
No licenses have been added to Astra Data Store.	a. Select the Add button.
	b. Select a license file to upload.
	c. Select Add to upload the license file.

6. Select Update.

Upgrade an Astra Data Store storage backend

You can upgrade your Astra Data Store backend from within Astra Control Center. To do so, you must first upload an upgrade package; Astra Control Center will use this upgrade package to upgrade Astra Data Store.

What you'll need

- · A managed Astra Data Store storage backend
- An uploaded Astra Data Store upgrade package (see Manage software packages)

Steps

- 1. Select Backends.
- Choose an Astra Data Store storage backend from the list, and select the corresponding menu in the Actions column.
- 3. Select Upgrade.
- Select an upgrade version from the list.

If you have several upgrade packages in your repository that are different versions, you can open the drop-down list to select the version you need.

- 5. Select Next.
- 6. Select Start Upgrade.

Result

The **Backends** page displays an **Upgrading** status in the **Status** column until the upgrade is complete.

Add nodes to a storage backend cluster

You can add nodes to an Astra Data Store cluster, up to the number of nodes supported by the type of license installed for Astra Data Store.

What you'll need

- A deployed and licensed Astra Data Store storage backend
- · You have added the Astra Data Store software package in Astra Control Center
- · One or more new nodes to add to the cluster

Steps

- 1. From the left navigation, select **Backends**.
- 2. Select the name of a storage backend.
- 3. Under Basic Information, you can see the number of nodes in this storage backend cluster.

- Under Nodes, select the edit icon next to the number of nodes.
- 5. In the **Add nodes** page, enter information about the new node or nodes:
 - a. Assign a node label for each node.
 - b. Do one of the following:
 - If you want Astra Data Store to always use the maximum available number of nodes according to your license, enable the **Always use up to maximum number of nodes allowed** check box.
 - If you don't want Astra Data Store to always use the maximum available number of nodes, select the desired number of total nodes to use.
 - c. If you deployed Astra Data Store with Protection Domains enabled, assign the new node or nodes to Protection Domains.
- Select Next.
- 7. Enter IP address and network information for each new node. Enter a single IP address for a single new node, or an IP address pool for multiple new nodes.

If Astra Data Store can use the IP addresses configured during deployment, you don't need to enter any IP address information.

- 8. Select Next.
- 9. Review the configuration for the new node or nodes.
- 10. Select Add nodes.

Remove nodes from a storage backend cluster

You can remove nodes from an Astra Data Store cluster. These nodes can be healthy or failed nodes.

Removing a node from an Astra Data Store cluster moves its data to other nodes in the cluster and removes the node from Astra Data Store.

The process requires the following conditions:

- There must be enough free space in the other nodes to receive the data.
- There must be 4 or more nodes in the cluster.

Steps

- 1. From the left navigation, select **Backends**.
- 2. Select the name of a storage backend.
- Select the Nodes tab.
- 4. From the Actions menu, select Remove.
- 5. Confirm the deletion by entering "remove".
- 6. Select Yes, remove node.

Find more information

Use the Astra Control API

Monitor infrastructure with Cloud Insights and Fluentd connections

You can configure several optional settings to enhance your Astra Control Center experience. To monitor and gain insight into your complete infrastructure, create a connection to NetApp Cloud Insights. To collect Kubernetes events from systems monitored by Astra Control Center, add a Fluentd connection.

If the network where you're running Astra Control Center requires a proxy for connecting to the Internet (to upload support bundles to NetApp Support Site or establish a connection to Cloud Insights), you should configure a proxy server in Astra Control Center.

You can also monitor Astra Data Store storage backend throughput, IOPS, and capacity from the Astra Control Center Storage Backends page. See Manage storage backends.

Add a proxy server for connections to Cloud Insight or to NetApp Support Site

If the network where you're running Astra Control Center requires a proxy for connecting to the Internet (to upload support bundles to NetApp Support Site or establish a connection to Cloud Insights), you should configure a proxy server in Astra Control Center.



Astra Control Center does not validate the details you enter for your proxy server. Ensure that you enter the correct values.

Steps

- 1. Log in to Astra Control Center using an account with admin/owner privilege.
- 2. Select Account > Connections.
- 3. Select **Connect** from the drop-down list to add a proxy server.



- 4. Enter the proxy server name or IP address and the proxy port number.
- 5. If your proxy server requires authentication, select the check box, and enter the username and password.
- 6. Select Connect.

Result

If the proxy information you entered was saved, the **HTTP Proxy** section of the **Account > Connections** page indicates that it is connected, and displays the server name.





HTTP PROXY ?

FROXI

Server: proxy.example.com:8888

Authentication: Enabled

Edit proxy server settings

You can edit the proxy server settings.

Steps

- 1. Log in to Astra Control Center using an account with admin/owner privilege.
- 2. Select Account > Connections.
- 3. Select **Edit** from the drop-down list to edit the connection.
- 4. Edit the server details and authentication information.
- Select Save.

Disable proxy server connection

You can disable the proxy server connection. You will be warned before you disable that potential disruption to other connections might occur.

Steps

- Log in to Astra Control Center using an account with admin/owner privilege.
- 2. Select Account > Connections.
- 3. Select **Disconnect** from the drop-down list to disable the connection.
- 4. In the dialog box that opens, confirm the operation.

Connect to Cloud Insights

To monitor and gain insight into your complete infrastructure, connect NetApp Cloud Insights with your Astra Control Center instance. Cloud Insights is included in your Astra Control Center license.

Cloud Insights should be accessible from the network that Astra Control Center uses, or indirectly via a proxy server.

When Astra Control Center is connected to Cloud Insights, an Acquisition Unit pod gets created. This pod collects data from the storage backends that are managed by Astra Control Center and pushes it to Cloud Insights. This pod requires 8 GB RAM and 2 CPU cores.

Additionally, if you manage Astra Data Store clusters on Astra Control (that is connected to Cloud Insights), an Acquisition Unit pod is created on Astra Data Store for each Astra Data Store cluster and the metrics are sent from Astra Data Store to the paired Cloud Insights system. Each pod requires 8 GB RAM and 2 CPU cores.



After you enable the Cloud Insights connection, you can view throughput information on the **Backends** page as well as connect to Cloud Insights from here after selecting a storage backend. You can also find the information on the **Dashboard** in the Cluster section, and also connect to Cloud Insights from there.

What you'll need


- An Astra Control Center account with admin/owner privileges.
- · A valid Astra Control Center license.
- A proxy server if the network where you're running Astra Control Center requires a proxy for connecting to the Internet.



If you are new to Cloud Insights, familiarize yourself with the features and capabilities. See Cloud Insights documentation.

Steps

- 1. Log in to Astra Control Center using an account with **admin/owner** privilege.
- 2. Select Account > Connections.
- 3. Select Connect where it shows Disconnected in the drop-down list to add the connection.



4. Enter the Cloud Insights API tokens and the tenant URL. The tenant URL has the following format, as an example:

```
https://<environment-name>.c01.cloudinsights.netapp.com/
```

You get the tenant URL when you get the Cloud Insights license. If you do not have the tenant URL, see the Cloud Insights documentation.

- a. To get the API token, log in to your Cloud Insights tenant URL.
- b. In Cloud Insights, generate both a **Read/Write** and a **Read only** API Access token by clicking **Admin** > **API Access**.



- c. Copy the **Read only** key. You will need to paste it into the Astra Control Center window for enabling the Cloud Insights connection. For the Read API Access Token key permissions, select: Assets, Alerts, Acquisition Unit, and Data Collection.
- d. Copy the **Read/Write** key. You will need to paste it into the Astra Control Center **Connect Cloud Insights** window. For the Read/Write API Access Token key permissions, select: Assets, Data Ingestion, Log Ingestion, Acquisition Unit, and Data Collection.



We recommend that you generate a **Read only** key and a **Read/Write** key, and not use the same key for both purposes. By default, the token expiry period is set to one year. We recommend that you keep the default selection to give the token the maximum duration before it expires. If your token expires, the telemetry will stop.

e. Paste the keys that you copied from Cloud Insights into Astra Control Center.

5. Select Connect.



After you select **Connect**, the status of the connection changes to **Pending** in the **Cloud Insights** section of the **Account** > **Connections** page. It can a few minutes for the connection to be enabled and the status to change to **Connected**.




To go back and forth easily between the Astra Control Center and Cloud Insights UIs, ensure that you are logged into both.

View data in Cloud Insights

If the connection was successful, the **Cloud Insights** section of the **Account > Connections** page indicates that it is connected, and displays the tenant URL. You can visit Cloud Insights to see data being successfully received and displayed.






If the connection failed for some reason, the status shows **Failed**. You can find the reason for failure under **Notifications** at the top-right side of the UI.




You can also find the same information under **Account > Notifications**.

From Astra Control Center, you can view throughput information on the **Backends** page as well as connect to Cloud Insights from here after selecting a storage backend.



To go directly to Cloud Insights, select the Cloud Insights icon next to the metrics image.

You can also find the information on the **Dashboard**.





After enabling the Cloud Insights connection, if you remove the backends that you added in Astra Control Center, the backends stop reporting to Cloud Insights.

Edit Cloud Insights connection

You can edit the Cloud Insights connection.



You can only edit the API keys. To change the Cloud Insights tenant URL, we recommended that you disconnect the Cloud Insights connection, and connect with the new URL.

Steps

- 1. Log in to Astra Control Center using an account with admin/owner privilege.
- 2. Select Account > Connections.
- 3. Select **Edit** from the drop-down list to edit the connection.
- Edit the Cloud Insights connection settings.
- Select Save.

Disable Cloud Insights connection


You can disable the Cloud Insights connection for a Kubernetes cluster managed by Astra Control Center. Disabling the Cloud Insights connection does not delete the telemetry data already uploaded to Cloud Insights.

Steps

- 1. Log in to Astra Control Center using an account with admin/owner privilege.
- 2. Select Account > Connections.
- 3. Select **Disconnect** from the drop-down list to disable the connection.
- 4. In the dialog box that opens, confirm the operation. After you confirm the operation, on the **Account > Connections** page, the Cloud Insights status changes to **Pending**. It take a few minutes for the status to change to **Disconnected**.

Connect to Fluentd

You can send logs (Kubernetes events) from Astra Control Center to your Fluentd endpoint. The Fluentd connection is disabled by default.





Only the event logs from managed clusters are forwarded to Fluentd.

What you'll need

- An Astra Control Center account with admin/owner privileges.
- Astra Control Center installed and running on a Kubernetes cluster.



Astra Control Center does not validate the details you enter for your Fluentd server. Ensure that you enter the correct values.

Steps

- 1. Log in to Astra Control Center using an account with admin/owner privilege.
- Select Account > Connections.
- 3. Select **Connect** from the drop-down list where it shows **Disconnected** to add the connection.



FLUENTD

Connect Astra Control logs to Fluentd for use by your log analysis software.

- 4. Enter the host IP address, the port number, and shared key for your Fluentd server.
- 5. Select Connect.

Result

If the details you entered for your Fluentd server were saved, the **Fluentd** section of the **Account > Connections** page indicates that it is connected. Now you can visit the Fluentd server that you connected and view the event logs.

If the connection failed for some reason, the status shows **Failed**. You can find the reason for failure under **Notifications** at the top-right side of the UI.

You can also find the same information under **Account > Notifications**.



If you are having trouble with log collection, you should log in to your worker node and ensure that your logs are available in /var/log/containers/.

Edit the Fluentd connection

You can edit the Fluentd connection to your Astra Control Center instance.

Steps

- Log in to Astra Control Center using an account with admin/owner privilege.
- Select Account > Connections.
- 3. Select **Edit** from the drop-down list to edit the connection.
- Change the Fluentd endpoint settings.
- Select Save.

Disable the Fluentd connection

You can disable the Fluentd connection to your Astra Control Center instance.

Steps

- 1. Log in to Astra Control Center using an account with admin/owner privilege.
- 2. Select Account > Connections.
- 3. Select **Disconnect** from the drop-down list to disable the connection.
- 4. In the dialog box that opens, confirm the operation.

Unmanage apps and clusters

Remove any apps or clusters that you no longer want to manage from Astra Control Center.

Unmanage an app

Stop managing apps that you no longer want to back up, snapshot, or clone from Astra Control Center.

- Any existing backups and snapshots will be deleted.
- Applications and data remain available.

Steps

- 1. From the left navigation bar, select **Applications**.
- 2. Select the check box for the apps that you no longer want to manage.
- 3. From the **Action** menu, select **Unmanage**.
- 4. Type "unmanage" to confirm.
- 5. Confirm that you want to unmanage the apps and then select Yes, unmanage Application.

Result

Astra Control Center stops managing the app.

Unmanage a cluster

Unmanage the cluster that you no longer want to manage from Astra Control Center.

- This action stops your cluster from being managed by Astra Control Center. It doesn't make any changes
 to the cluster's configuration and it doesn't delete the cluster.
- Trident won't be uninstalled from the cluster. Learn how to uninstall Trident.



Before you unmanage the cluster, you should unmanage the apps associated with the cluster.

Steps

- 1. From the left navigation bar, select **Clusters**.
- 2. Select the check box for the cluster that you no longer want to manage in Astra Control Center.
- 3. From the Options menu in the Actions column, select Unmanage.
- 4. Confirm that you want to unmanage the cluster and then select Yes, unmanage cluster.

Result

The status of the cluster changes to **Removing** and after that the cluster will be removed from the **Clusters** page, and it is no longer managed by Astra Control Center.



If Astra Control Center and Cloud Insights are not connected, unmanaging the cluster removes all the resources that were installed for sending telemetry data. If Astra Control Center and Cloud Insights are connected, unmanaging the cluster deletes only the fluentbit and event-exporter pods.

Upgrade Astra Control Center

To upgrade Astra Control Center, download the installation bundle from the NetApp Support Site and complete these instructions to upgrade the Astra Control Center components in your environment. You can use this procedure to upgrade Astra Control Center in internet-connected or air-gapped environments.

What you'll need

- Before you begin upgrade, ensure your environment still meets the minimum requirements for Astra Control Center deployment.
- Ensure all cluster operators are in a healthy state and available.

```
kubectl get clusteroperators
```

• Ensure all API services are in a healthy state and available.

```
kubectl get apiservices
```

Log out of your Astra Control Center.

About this task

The Astra Control Center upgrade process guides you through the following high-level steps:

- Download the Astra Control Center bundle
- Unpack the bundle and change directory
- Add the images to your local registry
- Install the updated Astra Control Center operator
- Upgrade Astra Control Center
- Upgrade third-party services (Optional)
- · Verify system status
- · Set up ingress for load balancing



Do not execute the following command during the entirety of the upgrade process to avoid deleting all Astra Control Center pods: kubectl delete -f astra control center operator deploy.yaml



Perform upgrades in a maintenance window when schedules, backups, and snapshots are not running.



Podman commands can be used in place of Docker commands if you are using Red Hat's Podman instead of Docker Engine.

Download the Astra Control Center bundle

- Download the Astra Control Center upgrade bundle (astra-control-center-[version].tar.gz) from the https://mysupport.netapp.com/site/products/all/details/astra-control-center/downloads-tab[NetApp Support Site^].
- 2. (Optional) Use the following command to verify the signature of the bundle:

```
openssl dgst -sha256 -verify AstraControlCenter-public.pub -signature astra-control-center-[version].tar.gz.sig astra-control-center-[version].tar.gz
```

Unpack the bundle and change directory

1. Extract the images:

```
tar -vxzf astra-control-center-[version].tar.gz
```

Add the images to your local registry

1. Complete the appropriate step sequence for your container engine:

Docker

1. Change to the Astra directory:

```
cd acc
```

- 2. Push the package images in the Astra Control Center image directory to your local registry. Make the following substitutions before running the command:
 - Replace BUNDLE_FILE with the name of the Astra Control bundle file (for example, acc.manifest.yaml).
 - Replace MY REGISTRY with the URL of the Docker repository.
 - Replace MY REGISTRY USER with the user name.
 - Replace MY_REGISTRY_TOKEN with an authorized token for the registry.

```
kubectl astra packages push-images -m BUNDLE_FILE -r MY_REGISTRY
-u MY_REGISTRY_USER -p MY_REGISTRY_TOKEN
```

Podman

1. Log in to your registry:

```
podman login [your_registry_path]
```

2. Run the following script, making the <YOUR_REGISTRY> substitution as noted in the comments:

```
# You need to be at the root of the tarball.
# You should see these files to confirm correct location:
  acc.manifest.vaml
   acc/
# Replace <YOUR REGISTRY> with your own registry (e.g.
registry.customer.com or registry.customer.com/testing, etc..)
export REGISTRY=<YOUR REGISTRY>
export PACKAGENAME=acc
export PACKAGEVERSION=22.08.1-26
export DIRECTORYNAME=acc
for astraImageFile in $(ls ${DIRECTORYNAME}/images/*.tar) ; do
  # Load to local cache
 astraImage=$(podman load --input ${astraImageFile} | sed 's/Loaded
image: //')
  # Remove path and keep imageName.
  astraImageNoPath=$(echo ${astraImage} | sed 's:.*/::')
  # Tag with local image repo.
  podman tag ${astraImage} ${REGISTRY}/netapp/astra/${PACKAGENAME}
/${PACKAGEVERSION}/${astraImageNoPath}
  # Push to the local repo.
  podman push ${REGISTRY}/netapp/astra/${PACKAGENAME}/
${PACKAGEVERSION}/${astraImageNoPath}
done
```

Install the updated Astra Control Center operator

1. Change the directory:

```
cd manifests
```

 Edit the Astra Control Center operator deployment yaml (astra_control_center_operator_deploy.yaml) to refer to your local registry and secret.

```
vim astra_control_center_operator_deploy.yaml
```

a. If you use a registry that requires authentication, replace the default line of imagePullSecrets: [] with the following:

```
imagePullSecrets:
    name: <name_of_secret_with_creds_to_local_registry>
```

- b. Change [your_registry_path] for the kube-rbac-proxy image to the registry path where you pushed the images in a previous step.
- c. Change [your_registry_path] for the acc-operator-controller-manager image to the registry path where you pushed the images in a previous step.
- d. Add the following values to the env section:

- name: ACCOP_HELM_UPGRADETIMEOUT value: 300m

```
apiVersion: apps/v1
kind: Deployment
metadata:
  labels:
    control-plane: controller-manager
  name: acc-operator-controller-manager
 namespace: netapp-acc-operator
spec:
 replicas: 1
  selector:
    matchLabels:
      control-plane: controller-manager
  template:
    metadata:
      labels:
        control-plane: controller-manager
    spec:
      containers:
      - args:
        - --secure-listen-address=0.0.0.0:8443
        - --upstream=http://127.0.0.1:8080/
        - --logtostderr=true
        - -v=10
        image: [your registry path]/kube-rbac-proxy:v4.8.0
        name: kube-rbac-proxy
        ports:
        - containerPort: 8443
         name: https
      - args:
        - --health-probe-bind-address=:8081
        - --metrics-bind-address=127.0.0.1:8080
        - --leader-elect
        command:
        - /manager
        env:
        - name: ACCOP LOG LEVEL
          value: "2"
        - name: ACCOP HELM UPGRADETIMEOUT
          value: 300m
        image: [your_registry_path]/acc-operator:[version x.y.z]
        imagePullPolicy: IfNotPresent
      imagePullSecrets: []
```

3. Install the updated Astra Control Center operator:

```
kubectl apply -f astra control center operator deploy.yaml
```

Sample response:

```
namespace/netapp-acc-operator unchanged
customresourcedefinition.apiextensions.k8s.io/astracontrolcenters.astra.
netapp.io configured
role.rbac.authorization.k8s.io/acc-operator-leader-election-role
unchanged
clusterrole.rbac.authorization.k8s.io/acc-operator-manager-role
configured
clusterrole.rbac.authorization.k8s.io/acc-operator-metrics-reader
unchanged
clusterrole.rbac.authorization.k8s.io/acc-operator-proxy-role unchanged
rolebinding.rbac.authorization.k8s.io/acc-operator-leader-election-
rolebinding unchanged
clusterrolebinding.rbac.authorization.k8s.io/acc-operator-manager-
rolebinding configured
clusterrolebinding.rbac.authorization.k8s.io/acc-operator-proxy-
rolebinding unchanged
configmap/acc-operator-manager-config unchanged
service/acc-operator-controller-manager-metrics-service unchanged
deployment.apps/acc-operator-controller-manager configured
```

4. Verify pods are running:

```
kubectl get pods -n netapp-acc-operator
```

Upgrade Astra Control Center

1. Edit the Astra Control Center custom resource (CR) (astra_control_center_min.yaml) and change the Astra version (astraVersion inside of Spec) number to the latest:

kubectl edit acc -n [netapp-acc or custom namespace]



Your registry path must match the registry path where you pushed the images in a previous step.

Add the following lines within additional Values inside of Spec in the Astra Control Center CR:

```
additionalValues:
    nautilus:
    startupProbe:
    periodSeconds: 30
    failureThreshold: 600
```

- 3. Do one of the following:
 - a. If you don't have your own IngressController or ingress and have been using the Astra Control Center with its Traefik gateway as a LoadBalancer type service and would like to continue with that setup, specify another field ingressType (if not already present) and set it to AccTraefik.

```
ingressType: AccTraefik
```

b. If you want to switch to the default Astra Control Center generic ingress deployment, provide your own IngressController/Ingress setup (with TLS termination, etc.), open up a route to Astra Control Center, and set ingressType to Generic.

```
ingressType: Generic
```



If you omit the field, the process becomes the generic deployment. If you don't want the generic deployment, be sure to add the field.

4. (Optional) Verify that the pods terminate and become available again:

```
watch kubectl get po -n [netapp-acc or custom namespace]
```

5. Wait for the Astra status conditions to indicate that the upgrade is complete and ready:

```
kubectl get -o yaml -n [netapp-acc or custom namespace]
astracontrolcenters.astra.netapp.io astra
```

Response:

```
conditions:
    - lastTransitionTime: "2021-10-25T18:49:26Z"
    message: Astra is deployed
    reason: Complete
    status: "True"
    type: Ready
    - lastTransitionTime: "2021-10-25T18:49:26Z"
    message: Upgrading succeeded.
    reason: Complete
    status: "False"
    type: Upgrading
```

- 6. Log back in and verify that all managed clusters and apps are still present and protected.
- 7. If the operator did not update the Cert-manager, upgrade third-party services, next.

Upgrade third-party services (Optional)

The third-party services Traefik and Cert-manager are not upgraded during earlier upgrade steps. You can optionally upgrade them using the procedure described here or retain existing service versions if your system requires it.

• Traefik: By default, Astra Control Center manages the lifecycle of the Traefik deployment. Setting externalTraefik to false (default) indicates that no external Traefik exists in the system and and Traefik is being installed and managed by Astra Control Center. In this case, externalTraefik is set to false.

On the other hand, if you have your own Traefik deployment, set externalTraefik to true. In this case, you maintain the deployment and Astra Control Center will not upgrade the CRDs, unless shouldUpgrade is set to true.

• Cert-manager: By default, Astra Control Center installs the cert-manager (and CRDs) unless you set externalCertManager to true. Set shouldUpgrade to true to have Astra Control Center upgrade the CRDs.

Traefik is upgraded if any of the following conditions are met:

- · externalTraefik: false
- externalTraefik: true AND shouldUpgrade: true.

Steps

1. Edit the acc CR:

```
kubectl edit acc -n [netapp-acc or custom namespace]
```

2. Change the externalTraefik field and the shouldUpgrade field to either true or false as needed.

crds:

externalTraefik: false
externalCertManager: false

shouldUpgrade: false

Verify system status

1. Log in to Astra Control Center.

2. Verify that all your managed clusters and apps are still present and protected.

Set up ingress for load balancing

You can set up a Kubernetes ingress object that manages external access to the services, such as load balancing in a cluster.

- Default upgrade uses the generic ingress deployment. In this case, you will also need to set up an ingress controller or ingress resource.
- If you don't want an ingress controller and want to retain what you already have, set ingressType to AccTraefik.



For additional details about the service type of "LoadBalancer" and ingress, see Requirements.

The steps differ depending on the type of ingress controller you use:

- · Nginx ingress controller
- · OpenShift ingress controller

What you'll need

- · In the CR spec,
 - If crd.externalTraefik is present, it should be set to false OR
 - old crd.externalTraefik is true, crd.shouldUpgrade should also be true.
- The required ingress controller should already be deployed.
- The ingress class corresponding to the ingress controller should already be created.
- You are using Kubernetes versions between and including v1.19 and v1.21.

Steps for Nginx ingress controller

- Use the existing secret secure-testing-cert or create a secret of type kubernetes.io/tls for a TLS private key and certificate in netapp-acc (or custom-named) namespace as described in TLS secrets.
- 2. Deploy an ingress resource in netapp-acc (or custom-named) namespace for either a deprecated or a new schema:
 - a. For a deprecated schema, follow this sample:

```
apiVersion: extensions/v1beta1
kind: IngressClass
metadata:
  name: ingress-acc
 namespace: [netapp-acc or custom namespace]
  annotations:
   kubernetes.io/ingress.class: nginx
spec:
 tls:
  - hosts:
    - <ACC address>
    secretName: [tls secret name]
 rules:
  - host: [ACC address]
   http:
     paths:
      - backend:
        serviceName: traefik
        servicePort: 80
        pathType: ImplementationSpecific
```

b. For a new schema, follow this example:

```
apiVersion: networking.k8s.io/v1
kind: Ingress
metadata:
  name: netapp-acc-ingress
  namespace: [netapp-acc or custom namespace]
spec:
  ingressClassName: [class name for nginx controller]
  - hosts:
    - <ACC address>
    secretName: [tls secret name]
  rules:
  - host: <ACC address>
    http:
      paths:
        - path:
          backend:
            service:
              name: traefik
              port:
                number: 80
          pathType: ImplementationSpecific
```

Steps for OpenShift ingress controller

- 1. Procure your certificate and get the key, certificate, and CA files ready for use by the OpenShift route.
- 2. Create the OpenShift route:

```
oc create route edge --service=traefik
--port=web -n [netapp-acc or custom namespace]
--insecure-policy=Redirect --hostname=<ACC address>
--cert=cert.pem --key=key.pem
```

Verify ingress set up

You can verify the ingress set up before you continue.

1. Ensure that Traefik has changed to clusterIP from Loadbalancer:

```
kubectl get service traefik -n [netapp-acc or custom namespace]
```

2. Verify routes in Traefik:

```
Kubectl get ingressroute ingressroutetls -n [netapp-acc or custom
namespace]
-o yaml | grep "Host("
```



The result should be empty.

Uninstall Astra Control Center

You might need to remove Astra Control Center components if you are upgrading from a trial to a full version of the product. To remove Astra Control Center and the Astra Control Center Operator, run the commands described in this procedure in sequence.

If you have any issues with the uninstall, see Troubleshooting uninstall issues.

What you'll need

Use Astra Control Center UI to unmanage all clusters.

Steps

1. Delete Astra Control Center. The following sample command is based upon a default installation. Modify the command if you made custom configurations.

```
kubectl delete -f astra_control_center_min.yaml -n netapp-acc
```

Result:

```
astracontrolcenter.astra.netapp.io "astra" deleted
```

2. Use the following command to delete the netapp-acc namespace:

```
kubectl delete ns netapp-acc
```

Result:

```
namespace "netapp-acc" deleted
```

3. Use the following command to delete Astra Control Center operator system components:

```
kubectl delete -f astra_control_center_operator_deploy.yaml
```

Result:

```
namespace/netapp-acc-operator deleted
customresourcedefinition.apiextensions.k8s.io/astracontrolcenters.astra.
netapp.io deleted
role.rbac.authorization.k8s.io/acc-operator-leader-election-role deleted
clusterrole.rbac.authorization.k8s.io/acc-operator-manager-role deleted
clusterrole.rbac.authorization.k8s.io/acc-operator-metrics-reader
deleted
clusterrole.rbac.authorization.k8s.io/acc-operator-proxy-role deleted
rolebinding.rbac.authorization.k8s.io/acc-operator-leader-election-
rolebinding deleted
clusterrolebinding.rbac.authorization.k8s.io/acc-operator-manager-
rolebinding deleted
clusterrolebinding.rbac.authorization.k8s.io/acc-operator-proxy-
rolebinding deleted
configmap/acc-operator-manager-config deleted
service/acc-operator-controller-manager-metrics-service deleted
deployment.apps/acc-operator-controller-manager deleted
```

Troubleshooting uninstall issues

Use the following workarounds to address any problems you have with uninstalling Astra Control Center.

Uninstall of Astra Control Center fails to clean up the monitoring-operator pod on the managed cluster

If you did not unmanage your clusters before you uninstalled Astra Control Center, you can manually delete the pods in the netapp-monitoring namespace and the namespace with the following commands:

Steps

1. Delete acc-monitoring agent:

```
kubectl delete agents acc-monitoring -n netapp-monitoring
```

Result:

```
agent.monitoring.netapp.com "acc-monitoring" deleted
```

2. Delete the namespace:

```
kubectl delete ns netapp-monitoring
```

Result:

namespace "netapp-monitoring" deleted

3. Confirm resources removed:

kubectl get pods -n netapp-monitoring

Result:

No resources found in netapp-monitoring namespace.

4. Confirm monitoring agent removed:

kubectl get crd|grep agent

Sample result:

agents.monitoring.netapp.com

2021-07-21T06:08:13Z

5. Delete custom resource definition (CRD) information:

kubectl delete crds agents.monitoring.netapp.com

Result:

customresourcedefinition.apiextensions.k8s.io
"agents.monitoring.netapp.com" deleted

Uninstall of Astra Control Center fails to clean up Traefik CRDs

You can manually delete the Traefik CRDs. CRDs are global resources, and deleting them might impact other applications on the cluster.

Steps

1. List Traefik CRDs installed on the cluster:

kubectl get crds |grep -E 'traefik'

Response

ingressroutes.traefik.containo.us	2021-06-23T23:29:11Z
ingressroutetcps.traefik.containo.us	2021-06-23T23:29:11Z
ingressrouteudps.traefik.containo.us	2021-06-23T23:29:12Z
middlewares.traefik.containo.us	2021-06-23T23:29:12Z
middlewaretcps.traefik.containo.us	2021-06-23T23:29:12Z
serverstransports.traefik.containo.us	2021-06-23T23:29:13Z
tlsoptions.traefik.containo.us	2021-06-23T23:29:13Z
tlsstores.traefik.containo.us	2021-06-23T23:29:14Z
traefikservices.traefik.containo.us	2021-06-23T23:29:15Z

2. Delete the CRDs:

```
kubectl delete crd ingressroutes.traefik.containo.us
ingressroutetcps.traefik.containo.us
ingressrouteudps.traefik.containo.us middlewares.traefik.containo.us
serverstransports.traefik.containo.us tlsoptions.traefik.containo.us
tlsstores.traefik.containo.us traefikservices.traefik.containo.us
middlewaretcps.traefik.containo.us
```

Find more information

Known issues for uninstall

Automate with REST API

Automation using the Astra Control REST API

Astra Control has a REST API that enables you to directly access the Astra Control functionality using a programming language or utility such as Curl. You can also manage Astra Control deployments using Ansible and other automation technologies.

To set up and manage your Kubernetes apps, you can use either the Astra UI or the Astra Control API.

To learn more, go to the Astra automation docs.

Knowledge and support

Troubleshooting

Learn how to work around some common problems you might encounter.

NetApp Knowledge Base for Astra

Find more information

- How to upload a file to NetApp (login required)
- How to manually upload a file to NetApp (login required)

Get help

NetApp provides support for Astra Control in a variety of ways. Extensive free self-support options are available 24x7, such as knowledgebase (KB) articles and a Discord channel. Your Astra Control account includes remote technical support via web ticketing.



If you have an evaluation license for Astra Control Center, you can get technical support. However, case creation via NetApp Support Site (NSS) is not available. You can get in touch with Support via the feedback option or use the Discord channel for self service.

You must first activate support for your NetApp serial number in order to use these non self-service support options. A NetApp Support Site (NSS) SSO account is required for chat and web ticketing along with case management.

Self-support options

You can access support options from the Astra Control Center UI by selecting the **Support** tab from the main menu.

These options are available for free, 24x7:

- Knowledge base (login required): Search for articles, FAQs, or Break Fix information related to Astra Control.
- Documentation center: This is the doc site that you're currently viewing.
- Get help via Discord: Go to Astra in The Pub category to connect with peers and experts.
- Create a support case: Generate support bundles to provide to NetApp Support for troubleshooting.
- Give feedback about Astra Control: Send an email to astra.feedback@netapp.com to let us know your thoughts, ideas, or concerns.

Enable daily scheduled support bundle upload to NetApp Support

During Astra Control Center installation, if you specify enrolled: true for autoSupport in the Astra Control Center Custom Resource Definition (CRD) file (astra_control_center_min.yaml), daily support bundles are automatically uploaded to the NetApp Support Site.

Generate support bundle to provide to NetApp Support

Astra Control Center enables the admin user to generate bundles, which include information useful to NetApp Support, including logs, events for all the components of the Astra deployment, metrics, and topology information about the clusters and apps under management. If you are connected to the Internet, you can upload support bundles to NetApp Support Site (NSS) directly from the Astra Control Center UI.



The time taken by Astra Control Center to generate the bundle depends on the size of your Astra Control Center installation as well as the parameters of the requested support bundle. The time duration that you specified when requesting a support bundle dictates the time it takes for the bundle to be generated (for example, a shorter time period results in faster bundle generation).

Before you begin

Determine whether a proxy connection will be required to upload bundles to NSS. If a proxy connection is needed, verify that Astra Control Center has been configured to use a proxy server.

- 1. Select Accounts > Connections.
- 2. Check the proxy settings in Connection settings.

Steps

- 1. Create a case on the NSS portal using the license serial number listed on the **Support** page of the Astra Control Center UI.
- 2. Perform the following steps for generating the support bundle by using the Astra Control Center UI:
 - a. On the **Support** page, in the Support bundle tile, select **Generate**.
 - b. In the **Generate a Support Bundle** window, select the timeframe.

You can choose between quick or custom timeframes.



You can choose a custom date range as well as specify a custom time period during the date range.

- c. After you make the selections, select Confirm.
- d. Select the **Upload the bundle to the NetApp Support Site when generated** check box.
- e. Select Generate Bundle.

When the support bundle is ready, a notification appears on the **Accounts > Notification** page in the Alerts area, on the **Activity** page, and also in the notifications list (accessible by selecting the icon in the top-right side of the UI).

If the generation failed, an icon appears on the Generate Bundle page. Select the icon to see the message.



The notifications icon at the top-right side of the UI provides information about events related to the support bundle, such as when the bundle is successfully created, when the bundle creation fails, when the bundle could not be uploaded, when the bundle could not be downloaded, and so on.

If you have an air-gapped installation

If you have an air-gapped installation, perform the following steps after the Support bundle is generated. When the bundle is available for download, the Download icon appears next to **Generate** in the **Support Bundles** section of the **Support** page.

Steps

- 1. Select the Download icon to download the bundle locally.
- 2. Manually upload the bundle to NSS.

You can use one of the following methods to do this:

- Use NetApp Authenticated File Upload (login required).
- · Attach the bundle to the case directly on NSS.
- · Use NetApp Active IQ.

Find more information

- How to upload a file to NetApp (login required)
- How to manually upload a file to NetApp (login required)

Earlier versions of Astra Control Center documentation

Documentation for previous releases is available.

- Astra Control Center 22.04 documentation
- Astra Control Center 21.12 documentation
- Astra Control Center 21.08 documentation

Legal notices

Legal notices provide access to copyright statements, trademarks, patents, and more.

Copyright

http://www.netapp.com/us/legal/copyright.aspx

Trademarks

NETAPP, the NETAPP logo, and the marks listed on the NetApp Trademarks page are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.

http://www.netapp.com/us/legal/netapptmlist.aspx

Patents

A current list of NetApp owned patents can be found at:

https://www.netapp.com/us/media/patents-page.pdf

Privacy policy

https://www.netapp.com/us/legal/privacypolicy/index.aspx

Open source

Notice files provide information about third-party copyright and licenses used in NetApp software.

- Notice for Astra Control Center
- · Notice for Astra Data Store

Astra Control API license

https://docs.netapp.com/us-en/astra-automation/media/astra-api-license.pdf

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.