



### Topic 10: IPv6 Addressing

Introduction to Networks v7.0 (ITN)



### Module Objectives

Module Title: IPv6 Addressing

**Module Objective**: Implement an IPv6 Addressing scheme.

Topic Title	Topic Objective
IPv4 Issues	Explain the need for IPv6 addressing.
IPv6 Address Representation	Explain how IPv6 addresses are represented.
IPv6 Address Types	Compare types of IPv6 network addresses.
GUA and LLA Static Configuration	Explain how to Configure static global unicast and link-local IPv6 network addresses.
Dynamic Addressing for IPv6 GUAs	Explain how to configure global unicast addresses dynamically.



### Module Objectives (Cont.)

Module Title: IPv6 Addressing

**Module Objective**: Implement an IPv6 Addressing scheme.

Topic Title	Topic Objective
Dynamic Addressing for IPv6 LLAs	Configure link-local addresses dynamically.
IPv6 Multicast Addresses	Identify IPv6 addresses.
Subnet an IPv6 Network	Implement a subnetted IPv6 addressing scheme.



### IPv4 Issues

## official (Open) IPv4 Issues Need for IPv6

- IPv4 is running out of addresses. IPv6 is the successor to IPv4. IPv6 has a much larger 128-bit address space.
- The development of IPv6 also included fixes for IPv4 limitations and other enhancements.
- With an increasing internet population, a limited IPv4 address space, issues with NAT and the IoT, the time has come to begin the transition to IPv6.



### official (Open) IPv4 Issues IPv4 and IPv6 Coexistence

Both IPv4 and IPv6 will coexist in the near future and the transition will take several years.

The IETF has created various protocols and tools to help network administrators migrate their networks to IPv6. These migration techniques can be divided into three categories:

- Dual stack -The devices run both IPv4 and IPv6 protocol stacks simultaneously.
- **Tunneling** A method of transporting an IPv6 packet over an IPv4 network. The IPv6 packet is encapsulated inside an IPv4 packet.
- **Translation** Network Address Translation 64 (NAT64) allows IPv6-enabled devices to communicate with IPv4-enabled devices using a translation technique similar to NAT for IPv4.

**Note:** Tunneling and translation are for transitioning to native IPv6 and should only be used where needed. The goal should be native IPv6 communications from source to destination.

# IPv6 Address Representation

# IPv6 Address Representation IPv6 Address Formats

- IPv6 addresses are 128 bits in length and written in hexadecimal.
- IPv6 addresses are not case-sensitive and can be written in either lowercase or uppercase.
- The preferred format for writing an IPv6 address is x:x:x:x:x:x:x:x; with each "x" consisting of four hexadecimal values.
- In IPv6, a hextet is the unofficial term used to refer to a segment of 16 bits, or four hexadecimal values.
- Examples of IPv6 addresses in the preferred format:

```
2001:0db8:0000:1111:0000:0000:0000:0200
2001:0db8:0000:00a3:abcd:0000:0000:1234
```



IPv6 Address Representation

Rule 1 – Omit Leading Zero

The first rule to help reduce the notation of IPv6 addresses is to omit any leading 0s (zeros).

#### **Examples:**

- 01ab can be represented as 1ab
- 09f0 can be represented as 9f0
- 0a00 can be represented as a00
- 00ab can be represented as ab

**Note**: This rule only applies to leading 0s, NOT to trailing 0s, otherwise the address would be ambiguous.

Туре	Format
Preferred	2001 : <b>0</b> db8 : <b>000</b> 0 : 1111 : <b>000</b> 0 : <b>000</b> 0 : <b>02</b> 00
No leading zeros	2001 : db8 : 0 : 1111 : 0 : 0 : 0 : 200



## official (Open) IPv6 Address Representation Rule 2 – Double Colon

A double colon (::) can replace any single, contiguous string of one or more 16-bit hextets consisting of all zeros.

#### **Example:**

2001:db8:cafe:1:0:0:0:1 (leading 0s omitted) could be represented as 2001:db8:cafe:1::1

**Note**: The double colon (::) can only be used once within an address, otherwise there would be more than one possible resulting address.

Туре	Format
Preferred	2001 : <b>0</b> db8 : <b>000</b> 0 : 1111 : <b>0000</b> : <b>0000</b> : <b>0</b> 200
Compressed	2001:db8:0:1111::200



# IPv6 Address Types

# Official (Open) IPv6 Address Types Unicast, Multicast, Anycast

There are three broad categories of IPv6 addresses:

- Unicast Unicast uniquely identifies an interface on an IPv6-enabled device.
- Multicast Multicast is used to send a single IPv6 packet to multiple destinations.
- Anycast This is any IPv6 unicast address that can be assigned to multiple devices.
   A packet sent to an anycast address is routed to the nearest device having that address.

**Note**: Unlike IPv4, IPv6 does not have a broadcast address. However, there is an IPv6 all-nodes multicast address that essentially gives the same result.




#### Types of IPv6 Addresses

#### **IPv6 Unicast Addresses**

#### **Unicast**

- Uniquely identifies an interface on a IPv6-enabled device
- A packet sent to a unicast address is received by the interface that is assigned that address.




Official (Open)

### Types of IPv6 Addresses **IPv6 Multicast Addresses**

#### **Multicast**

- one to many or controlled broadcast
- Identifies a group of interfaces
- Reserved address range starting FF00::0/8
- Host to group of hosts






Official (Open)

### Types of IPv6 Addresses IPv6 Anycast Addresses

#### **Anycast**


- one to one (anycast address), the nearest node will respond.
- Anycast IPv6 address is an unicast address that is configured at interfaces on different nodes



# IPv6 Address Types IPv6 Prefix Length

Prefix length is represented in slash notation and is used to indicate the network portion of an IPv6 address.

The IPv6 prefix length can range from 0 to 128. The recommended IPv6 prefix length for LANs and most other types of networks is /64.




**Note**: It is strongly recommended to use a 64-bit Interface ID for most networks. This is because stateless address autoconfiguration (SLAAC) uses 64 bits for the Interface ID. It also makes subnetting easier to create and manage.

# Types of IPv6 Unicast Addresses

Unlike IPv4 devices that have only a single address, IPv6 addresses typically have two unicast addresses:

- Global Unicast Address (GUA) This is similar to a public IPv4 address. These are globally unique, internet-routable addresses.
- Link-local Address (LLA) Required for every IPv6-enabled device and used to communicate with other devices on the same local link. LLAs are not routable and are confined to a single link.



### Official (Open) IPv6 Address Types

#### A Note About the Unique Local Address

The IPv6 unique local addresses (range fc00::/7 to fdff::/7) have some similarity to RFC 1918 private addresses for IPv4, but there are significant differences:

- Unique local addresses are used for local addressing within a site or between a limited number of sites.
- Unique local addresses can be used for devices that will never need to access another network.
- Unique local addresses are not globally routed or translated to a global IPv6 address.


**Note**: Many sites use the private nature of RFC 1918 addresses to attempt to secure or hide their network from potential security risks. This was never the intended use of ULAs.



## Official (Open) IPv6 Address Types IPv6 GUA

IPv6 global unicast addresses (GUAs) are globally unique and routable on the IPv6 internet.

- Currently, only GUAs with the first three bits of 001 or 2000::/3 are being assigned.
- Currently available GUAs begins with a decimal 2 or a 3 (This is only 1/8th of the total available IPv6 address space).





## official (Open) IPv6 Address Types IPv6 GUA Structure

#### **Global Routing Prefix:**

 The global routing prefix is the prefix, or network, portion of the address that is assigned by the provider, such as an ISP, to a customer or site. The global routing prefix will vary depending on ISP policies.

#### **Subnet ID:**

 The Subnet ID field is the area between the Global Routing Prefix and the Interface ID. The Subnet ID is used by an organization to identify subnets within its site.

#### **Interface ID:**


 The IPv6 interface ID is equivalent to the host portion of an IPv4 address. It is strongly recommended that in most cases /64 subnets should be used, which creates a 64-bit interface ID.

**Note**: IPv6 allows the all-0s and all-1s host addresses can be assigned to a device. The all-0s address is reserved as a Subnet-Router anycast address, and should be assigned only to routers.

## Official (Open) IPv6 Address Types IPv6 LLA

An IPv6 link-local address (LLA) enables a device to communicate with other IPv6enabled devices on the same link and only on that link (subnet).

- Packets with a source or destination LLA cannot be routed.
- Every IPv6-enabled network interface must have an LLA.
- If an LLA is not configured manually on an interface, the device will automatically create one.
- IPv6 LLAs are in the fe80::/10 range.



- 1. Routers use the LLA of neighbor routers to send routing updates.
- 2. Hosts use the LLA of a local router as the default-gateway.

# GUA Static Configuration

# GUA Static Configuration Static GUA Configuration on a Router

Most IPv6 configuration and verification commands in the Cisco IOS are similar to their IPv4 counterparts. In many cases, the only difference is the use of **ipv6** in place of **ip** within the commands.


- The command to configure an IPv6 GUA on an interface is: ipv6 address ipv6address/prefix-length.
- The example shows commands to configure a GUA on the G0/0/0 interface on R1:

```
R1(config)# interface gigabitethernet 0/0/0
R1(config-if)# ipv6 address 2001:db8:acad:1::1/64
R1(config-if)# no shutdown
R1(config-if)# exit
```

#### Static GUA Configuration on a Windows Host

- Manually configuring the IPv6 address on a host is similar to configuring an IPv4 address.
- The GUA or LLA of the router interface can be used as the default gateway. Best practice is to use the LLA.

**Note**: When DHCPv6 or SLAAC is used, the LLA of the router will automatically be specified as the default gateway address.



# GUA and LLA Static Configuration Static GUA Configuration of a Link-Local Unicast Address

Configuring the LLA manually lets you create an address that is recognizable and easier to remember.

- LLAs can be configured manually using the ipv6 address ipv6-link-local-address link-local command.
- The example shows commands to configure a LLA on the G0/0/0 interface on R1

```
R1(config)# interface gigabitethernet 0/0/0
R1(config-if)# ipv6 address fe80::1:1 link-local
R1(config-if)# no shutdown
R1(config-if)# exit
```

**Note**: The same LLA can be configured on each link as long as it is unique on that link. Common practice is to create a different LLA on each interface of the router to make it easy to identify the router and the specific interface.

# Official (Open) Dynamic Addressing for IPv6 LLAs Verify IPv6 Address Configuration

Cisco routers automatically create an IPv6 LLA whenever a GUA is assigned to the interface. By default, Cisco IOS routers use EUI-64 to generate the interface ID for all LLAs on IPv6 interfaces.

Here is an example of a LLA dynamically configured on the G0/0/0 interface of R1:

```
R1# show interface gigabitEthernet 0/0/0
GigabitEthernet0/0/0 is up, line protocol is up
Hardware is ISR4221-2x1GE, address is 7079.b392.3640 (bia 7079.b392.3640)
(Output omitted)
R1# show ipv6 interface brief
GigabitEthernet0/0/0 [up/up]
FE80::7279:B3FF:FE92:3640
2001:DB8:ACAD:1::1
```

### IPv6 Multicast Addresses

# Official (Open) IPv6 Multicast Addresses Assigned IPv6 Multicast Addresses

IPv6 multicast addresses have the prefix ff00::/8. There are two types of IPv6 multicast addresses:

- Well-Known multicast addresses
- Solicited node multicast addresses

**Note**: Multicast addresses can only be destination addresses and not source addresses.

## Official (Open) IPv6 Multicast Addresses Well-Known IPv6 Multicast Addresses


Well-known IPv6 multicast addresses are assigned and are reserved for predefined groups of devices.

There are two common IPv6 Assigned multicast groups:

- **ff02::1 All-nodes multicast group** This is a multicast group that all IPv6-enabled devices join. A packet sent to this group is received and processed by all IPv6 interfaces on the link or network.
- ff02::2 All-routers multicast group This is a multicast group that all IPv6 routers join. A
  router becomes a member of this group when it is enabled as an IPv6 router with the ipv6
  unicast-routing global configuration command.

## Official (Open) IPv6 Multicast Addresses Solicited-Node IPv6 Multicast

- A solicited-node multicast address is similar to the all-nodes multicast address.
- A solicited-node multicast address is mapped to a special Ethernet multicast address.
- The Ethernet NIC can filter the frame by examining the destination MAC address without sending it to the IPv6 process to see if the device is the intended target of the IPv6 packet.






### Subnet an IPv6 Network

# Subnet an IPv6 Network Subnet Using the Subnet ID

#### IPv6 was designed with subnetting in mind.


- A separate subnet ID field in the IPv6 GUA is used to create subnets.
- The subnet ID field is the area between the Global Routing Prefix and the interface ID.



# Subnet an IPv6 Network IPv6 Subnetting Example

Given the 2001:db8:acad::/48 global routing prefix with a 16 bit subnet ID.


- Allows 65,536 /64 subnets
- The global routing prefix is the same for all subnets.
- Only the subnet ID hextet is incremented in hexadecimal for each subnet.



## Subnet an IPv6 Network IPv6 Subnet Allocation

The example topology requires five subnets, one for each LAN as well as for the serial link between R1 and R2.

The five IPv6 subnets were allocated, with the subnet ID field 0001 through 0005. Each /64 subnet will provide more addresses than will ever be needed.





The example shows that each of the router interfaces on R1 has been configured to be on a different IPv6 subnet.

```
R1(config)# interface gigabitethernet 0/0/0
R1(config-if)# ipv6 address 2001:db8:acad:1::1/64
R1(config-if)# no shutdown
R1(config-if)# exit
R1(config)# interface gigabitethernet 0/0/1
R1(config-if)# ipv6 address 2001:db8:acad:2::1/64
R1(config-if)# no shutdown
R1(config-if)# exit
R1(config-if)# exit
R1(config)# interface serial 0/1/0
R1(config-if)# ipv6 address 2001:db8:acad:3::1/64
R1(config-if)# no shutdown
```