### PMlib 講習会

理化学研究所 計算科学研究機構 可視化技術研究グループ 2014年5月27日

## 講習会の概要

- 講義編
  - PMlibとは
  - PMlibの位置づけ
  - PMlibの入手方法
  - PMlibの利用方法
- 関連情報編(別途資料A)
  - コンピュータシステムの性能
  - アプリケーションの性能
  - 性能モニターの範囲
- 実習編
  - 実習システムへのログイン
  - PMlibのインストール
  - 例題プログラムへの組み込み
  - 実行結果の解釈
  - 例題プログラムの性能向上の検討

# 講習編

### **PMlib**

- PMlibとは
  - 計算性能モニター用クラスライブラリ
  - アプリケーションの性能を改善するための補助ツール
  - オープンソースソフトウエア(理研 AICSが開発・提供)
  - インストール・利用が容易な「軽量」ツール
  - 計測結果情報は指定区間毎に出力
    - ・出力タイプ1:全プロセスの平均した基本情報
    - ・ 出力タイプ2:ハードウエアイベント毎の情報
    - ・ 出力タイプ3:MPIランク(プロセス) 毎の情報
  - 出力タイプ1、3はLinuxシステム全般で利用可能
  - 出力タイプ2は「京」コンピュータ、X86系などで利用可能

### PMlibの位置づけ

- オープンソース性能統計ツールー般
  - Gprof: 簡易機能、コンパイラに制約
  - Scalasca: 高機能、Score-P共通インフラ
  - TAU: 高機能
  - PAPI: HWPCへのアクセス
  - など多数、、、プラス
  - PMlib

ベンダー 性能計測・統計ツール

オープンソース 性能計測・統計ツール

オープンソース コンパイラ・ライブラリ

ベンダー コンパイラ・ライブラリ

Linux系オペレーティングシステムパッケージ

- ・ ベンダーOS
- ・ オープンソースOS

ベンダーツール

#### X86系

- Intel
- PGI
- Cray

#### Sparc系

- 富士通
- Oracle

#### Power系

- 日立
- IBM その他の系

#### • GPU

- Phi
- SX

### PMlibの位置づけ

- ベンダー性能計測・統計ツール
  - 〇豊富な機能、高度なインタフェイス、システムに統合化された安心感、詳しいドキュメント、ベンダーによるサポート
  - △習熟に相当期間が必要、システム機種毎にツールが決まってしまう、それなりの価格
- オープンソース性能統計ツール
  - 〇各ツール毎に高機能、無料
  - △ユーザーインタフェイスが個性的、インストールの手間・利用方法の習熟がそれなりに大変→周囲にツールをよく知っている人がいないとハードルは高い

#### PMlib

- 機能・出力情報を絞ったコンパクトなツール
- インストール・利用方法とも簡単→手軽に利用可能
- ソースプログラム中にPMlib APIを記述して利用
- 実際の稼働ベースでアプリケーションの実行性能が測定可能

### PMlibの入手方法

- PMlibパッケージの入手方法
  - 下記から直接Download
  - https://github.com/avr-aics-riken/PMlib
- PMlibに関するドキュメント
  - パッケージに含まれるdoc/ディレクトリ以下にある
    - How\_to\_use\_PMlib.pdf : クラスライブラリの説明書
    - PMlib\_getting\_started.pdf:本資料
- PMlibのインストール方法・実例は実習編を参照

### PMlib計算性能測定機能

- プログラム実行時に測定指定区間の実行時間と性能に関連する統計情報を出力する 機能
- 各測定区間は以下のプロパティを持つ
  - キー番号:整数値
  - ラベル:統計情報出力時のラベル文字列
  - 測定対象タイプ:「計算時間」または「通信時間」
  - 排他測定フラグ:「排他測定」または「非排他測定」
- 性能統計情報
  - 計算量をユーザが明示的に申告
    - 測定区間の「計算量」を引数として自己申告。(stop メソッドのオプション)
    - 申告量の解釈は測定対象タイプがによる
      - 計算時間の場合は浮動小数点演算量:計算速度(FLOPS 値)を出力
      - 通信時間の場合は通信量バイト単位:通信速度(Byte/s 単位)を出力
  - 計算量の自動算出
    - ハードウェア性能カウンター(HWPC)のイベントを測定して出力
    - イベントグループを環境変数で動的に選択する

### PMlibのプロファイルのタイプ

- 基本プロファイル例
  - 全プロセスの平均情報
  - プログラム終了時に各MPIプロセス(ランク)の情報をマスターランクに集計。統計処理して出力
- 詳細プロファイル(1:MPIプロセス毎)
  - MPIの各プロセス毎の情報を出力
- 詳細プロファイル(2: HWPCイベント統計)
  - 計測するHWPCイベントグループを環境変数で指定
  - プロセスがOpenMPスレッドを発生した場合各プロセスのにスレッド測定値を内部で合計する。マスタープロセス (MPI rank 0)の値を出力
- スレッド中からのPMlibよびだしには未対応

### プロファイル: 明示的な自己申告

- 計算量をユーザが明示的に申告する場合
  - 実行時の各セクションのタイミングと演算数を積算して記録
    - タイミング測定区間はラベル管理で、コーディング時に指定
    - 演算数は、各関数毎にマニュアルでカウント
      - FX10のPA情報から推定. 例えば. .

-+, -, x : 1 flop

- ÷ : 8 flops(単精度), 13 flops(倍精度)

- abs() : 1 flops

- ソースプログラムの計算実行式通りの実行性能を測定可能
- FX10の詳細プロファイルとの連携
  - 同じタイミングで、FXの区間指定が可能

### プロファイル:計算量の自動算出

- 性能システムのCPUが内部に持つハードウエア性能カウンター (HWPC)のイベントを測定して出力
- HWPCのイベントリスト別表
- PMlib用にイベントの種類毎グループを定義
  - FLOPS
  - VECTOR
  - BANDWIDTH
  - CACHE
  - CYCLE
- プログラム実行時に環境変数で動的に選択する
  - マスタープロセス(MPI rank 0)の測定値を代表値として出力
  - もしOpenMPスレッド並列処理の場合はマスタープロセスが発生するスレッド群の合計値を出力

# 基本プロファイル例

Report of Timing Statistics PMIib version 2.1.2

Operator : Kenji\_Ono Host name : vsp22

Date : 2014/05/26 : 03:49:43

Parallel Mode : Hybrid (4 processes x 8 threads)

Total execution time = 4.429648e+00 [sec] Total time of measured sections = 3.695136e+00 [sec]

Statistics per MPI process [Node Average]

Label		call		accumula <sup>-</sup>		flop   messages[Bytes]			
	 _1		avr[sec]	avr [%]	sdv[sec]	avr/call[sec]	avr	sdv	speed
Poisson_SOR2_SMA	:	26200	1. 071254e+00	28. 99	6. 4536e-03	4. 088757e-05	2. 318e+10	0. 000e+00	21.64 Gflops
File_Output	:	11	8. 003855e-01	21.66	1. 3644e-02	7. 276232e-02	1. 311e+07	0.000e+00	16.38 Mflops
Poisson_Src_Norm	:	13300	7. 372693e-01	19. 95	2. 6937e-03	5. 543378e-05	4. 112e+10	0.000e+00	55.77 Gflops
Sync_Pressure	:	26200	5. 582871e-01	15. 11	7. 6391e-03	2. 130867e-05	1. 717e+09	0.000e+00	2.86 GB/sec
A_R_Poisson_Src	:	13300	2. 086478e-01	5. 65	2. 1901e-02	1.568781e-05	8. 512e+05	0.000e+00	3.89 MB/sec
Pseudo_Velocity	:	100	7. 437694e-02	2. 01	4. 6558e-04	7. 437694e-04	5. 230e+09	0.000e+00	70.31 Gflops
Projection_Velocity	:	262	7. 227474e-02	1. 96	6. 3243e-04	2. 758578e-04	1.820e+09	0.000e+00	25.18 Gflops
Poisson_BC	:	26200	5. 180532e-02	1.40	8. 1025e-04	1.977302e-06	0.000e+00	0.000e+00	0.00 Mflops
Poisson_Setup_for_Itr	:	13100	2. 677810e-02	0. 72	2. 0531e-04	2. 044130e-06	0.000e+00	0.000e+00	0.00 Mflops
Sync_Velocity	:	100	1. 325995e-02	0.36	3. 9118e-04	1.325995e-04	1. 573e+08	0.000e+00	11.05 GB/sec
Sync_Pseudo_Velocity	:	100	1.039678e-02	0. 28	7. 3619e-04	1.039678e-04	3. 932e+07	0.000e+00	3.52 GB/sec
Variation_Space	:	100	9.503841e-03	0. 26	5. 3508e-05	9.503841e-05	4. 260e+08	0.000e+00	44.82 Gflops
Force_Calculation	:	100	6. 575465e-03	0. 18	7. 8837e-03	6. 575465e-05	0.000e+00	0.000e+00	0.00 Mflops
Copy_Array	:	200	6. 332040e-03	0. 17	8. 1976e-05	3. 166020e-05	0.000e+00	0.000e+00	0.00 Mflops
Projection_Velocity_BC	:	262	6. 013393e-03	0. 16	8. 4818e-05	2. 295188e-05	0.000e+00	0.000e+00	0.00 Mflops
Divergence_of_Pvec	:	100	5. 138874e-03	0.14	5. 1616e-05	5. 138874e-05	2. 425e+08	0.000e+00	47.19 Gflops
A_R_Poisson_Norm	•	262	5. 013704e-03	0.14	6.8061e-04	1. 913628e-05	1.677e+04	0.000e+00	3.19 MB/sec
Allocate_Arrays	:	4	5.009890e-03	0. 14	2. 1477e-04	1. 252472e-03	0.000e+00	0.000e+00	0.00 Mflops

Total 3. 695136e+00 7. 225e+10 19. 55 Gflops
Performance 78. 21 Gflops

# 詳細プロファイル(1)

Elapsed ti	Elapsed time variation over MPI ranks							
*Initializat	ion_Secti	on						
MPI_rank	call	accm[s] acc	cm [%]	waiting[s]	accm/call[s]	flop msg	speed	
#0 :	1	1.623359e-01	4. 39	6. 041527e-04	1. 623359e-01	0.000e+00	0.00 Mflops	
#1 :	1	1.629400e-01	4. 41	0.000000e+00	1.629400e-01	0.000e+00	0.00 Mflops	
#2 :	1	1. 543641e-01	4. 18	8. 575916e-03	1. 543641e-01	0.000e+00	0.00 Mflops	
#3 :	1	1.500421e-01	4.06	1. 289797e-02	1.500421e-01	0.000e+00	0.00 Mflops	
Allocate_Arr	ays					_		
MPI_rank	call	accm[s] acc		waiting[s]	accm/call[s]	flop msg	speed	
#0 :	4		0. 14	9. 012222e-05	1. 286507e-03	0.000e+00	0.00 Mflops	
#1 :	4		0. 14	0. 000000e+00	1. 309037e-03	0.000e+00	0.00 Mflops	
#2 :	4		0. 13	3. 688335e-04	1. 216829e-03	0. 000e+00	0.00 Mflops	
#3 :	4	4. 790068e-03	0. 13	4. 460812e-04	1. 197517e-03	0. 000e+00	0.00 Mflops	
Wassal Duan	04:							
*Voxel_Prep_		Г . Т	Го/ Т		/	e l		
MPI_rank	call	accm[s] acc		waiting[s]	accm/call[s]	flop msg	speed	
#0 :	 		1.85	0.000000e+00	6. 849098e-02	0.000e+00	0.00 Mflops	
#1 :			1. 72	4. 950047e-03	6. 354094e-02	0.000e+00	0.00 Mflops	
#2 : #3 :	1 1		1. 64 0. 65	7. 915020e-03 4. 435182e-02	6. 057596e-02 2. 413917e-02	0. 000e+00 0. 000e+00	0.00 Mflops 0.00 Mflops	
# <b>o</b> .	1	2.4139176-02	0. 00	4. 4331026-02	2. 4139176-02	0. 000e+00	0.00 Miliops	
Restart_Proc	ess							
MPI_rank	call	accm[s] acc	cm [%]	waiting[s]	accm/call[s]	flop msg	speed	
#0 :	1		0. 00	9. 536743e-07	4. 053116e-06	0. 000e+00	0.00 Mflops	
#1 :	1		0.00	0. 000000e+00	5. 006790e-06	0. 000e+00	0.00 Mflops	
#2 :	1		0.00	1. 907349e-06	3. 099442e-06	0. 000e+00	0.00 Mflops	
#3 :	1		0.00	9. 536743e-07	4. 053116e-06	0. 000e+00	0.00 Mflops	
						_		

# 詳細プロファイル(2)

PMlib detected the CPU architecture: The available Hardware Performance Counter (HWPC) events depend on this CPU architecture. GenuineIntel Intel(R) Xeon(R) CPU E5-2670 0 @ 2.60GHz									
HWPC event values of the master rank, sum of threads. count unit in Giga (x 10e9)									
_	:	LD_INS	SR_INS	:HIT_LFB	:L1_HIT	:L2_HIT	:L3_HIT	OFFCORE	[Mem GB/s]
Initialization_Section	:	0. 702	0. 104	0.000	0. 702	0. 000	0. 000	0.000	0. 069
Allocate_Arrays	:	0. 125	0. 023	0.000	0. 125	0.000	0.000	0.000	2. 371
Voxel_Prep_Section	:	0. 126	0. 021	0.000	0. 126	0.000	0.000	0.000	0. 023
Restart_Process	:	0.000	0.000	0.000	0.000	0.000	0.000	0.000	14. 726
Time_Step_Loop_Section	:	0. 005	0. 001	0.000	0.005	0.000	0.000	0.000	0. 001
Search_Vmax	:	0. 027	0.003	0. 001	0. 026	0.000	0.000	0.002	64. 719
A_R_Vmax	:	0. 024	0. 005	0.000	0. 024	0.000	0.000	0.000	3. 541
Copy_Array	:	0. 074	0. 042	0. 022	0. 051	0.000	0.000	0.004	36. 320
assign_Const_to_Array	:	0. 010	0.005	0.000	0.009	0.000	0.000	0.000	2. 816
Flow_Section	:	0. 005	0. 001	0.000	0.005	0.000	0.000	0.000	0. 001
NSF_Step_Section	:	0.004	0. 001	0.000	0.004	0.000	0.000	0.000	0. 035
NS_F_Step_Sct_1	:	0. 005	0. 001	0.000	0. 005	0.000	0.000	0.000	0. 571
NSF_Step_Sct_2	:	0. 005	0. 001	0.000	0.005	0.000	0.000	0.000	0. 047
Pseudo_Velocity	:	0. 721	0. 363	0.002	0. 705	0.000	0.000	0.010	8. 086

## 利用するプログラム例

```
#include <PerfMonitor.h>
using namespace pm lib;
     // "Serial"; "OpenMP"; "FlatMPI"; "Hybrid";
     char parallel mode[] = "Hybrid" ;
PerfMonitor PM:
     int main (int argc, char *argv[])
     enum timing_key {tm_sec1, tm_sec2, tm_sec3, tm_END_, };
     MPI Init(&argc. &argv);
     MPI_Comm_rank(MPI_COMM_WORLD, &my_id);
     MPI Comm size (MPI COMM WORLD, &npes);
     num_threads = omp_get_max_threads();
PM. setRankInfo(my_id);
PM. initialize(tm END );
PM. setProperties (tm sec1, "section1", PerfMonitor∷CALC);
PM. setParallelMode(parallel mode, num threads, npes);
PM. start(tm sec1);
     compute some kerel();
PM. stop (tm sec1);
PM. gather ();
PM. print(stdout, "QQQ", "RRR");
PM. printDetail(stdout);
     MPI Finalize();
     return 0:
```

• 計時区間のキーと総数 tm\_END

```
enum timing key {
 tm init_sct,
    tm init alloc,
    tm voxel prep sct,
      tm voxel load,
      tm_polygon_load,
      tm cutinfo,
    tm restart,
  tm loop sct,
  tm vmax,
  tm vmax comm,
  tm END
```

プログラム中で測定する区間に対して、 enumで順に整数を割り当てる。 tm ENDで総数がわかる。

・ ラベル(測定区間名)の配列宣言とラベル指定

```
false 測定区間が重複していることを指示
 Void set timing label(void)
  set label(tm init sct,
                                 "Initialization Section", PerfMonitor::CALC, false);
  set label(tm init alloc,
                                 "Allocate Arrays",
                                                         PerfMonitor::CALC)
  set label(tm vmax,
                                 "Search Vmax",
                                                         PerfMonitor::CALC);
  set label(tm vmax comm,
                                 "A_R_Vmax",
                                                         PerfMonitor::COMM);
                                                               CALC 計算部であることを指定
                                 ラベル
                                                               COMM 通信部
                                 文字数は任意
【//@param[in] key キー番号
【 //@param[in] label ラベル
▮ //@param[in] type 測定対象タイプ(COMM or CALC)
■ //@param[in] exclusive 排他測定フラグ(ディフォルトtrue)
 Void set label(unsigned key, char* label, PerfMonitor::Type type, bool exclusive)
   // Performance Monitorへの登録
   string tmp(label);
   PM.setProperties(key, tmp, type, exclusive);
   // FX用プロファイラの文字列登録
   strcpy(tm_label_ptr[key], label);
```

• 測定区間の記述(方法1:演算数やデータ量をユーザーが登録する)

```
─ TIMING_start/_stopメソッドで区間と数量を指示
                                                              +, -, x : 1 flop
                                                              ÷:8 flops (FXの単精度)
                                                                 13 flops (FXの倍精度)
 TIMING start(tm div pvec);
                                                              abs(), max(): 1 flops
I flop count = 0.0;
l cbc div (src0, sz, gc, &coef, vc, (int*)bcv, v00, &flop count);
 TIMING_stop(tm div pvec, flop count);
                                         flop count 引数を渡して登録する
subroutine cbc div (div, sz, g, ..., flop)
I implicit none
                                                    :: i, j, k, ix, jx, kx, g
l integer
| integer, dimension(3)
                                                       SZ
∣ real
                                                    :: flop
real, dimension(1-g:sz(1)+g, 1-g:sz(2)+g, 1-g:sz(3)+g)
                                                       div
 ix = sz(1)
 jx = sz(2)
 kx = sz(3)
 flop = flop + real(ix)*real(jx)*real(kx)*49.0
                                  ループ中の浮動小数点の演算数をカウント
```

オーバーフロー防止のため、整数演算をrealにキャスト

- 測定区間の記述(方法2:演算数やデータ量をHWPCに自動算出させる)
  - TIMING\_start/\_stopメソッドで区間を指示

```
TIMING_start(tm_div_pvec);
cbc_div_(src0, sz, gc, &coef, vc, (int*)bcv, v00 );
TIMING_stop(tm_div_pvec);
```

測定メソッドの切り替え、あるいは併用

```
//@fn プロファイラのラベル取り出し
 //@param 格納番号
 inline const char* get tm label(unsigned key) {
   return (const char*)tm label ptr[key];
                                                 内蔵プロファイラとFXのプロファイラをコンパイラオプション
//@fn タイミング測定開始
                                                 -D FX FAPPで切り替え
 //@param 格納番号
 inline void TIMING start(unsigned key) {
   // Intrinsic profiler
   TIMING PM.start(key);
#ifdef FX FAPP
   fapp start( get tm label(key), 0, 0);
#endif
 //@fn タイミング測定終了
//@param 格納番号
//@param[in] flopPerTask 「タスク」あたりの計算量/通信量(バイト) (ディフォルト0)
//@param[in] iterationCount 実行「タスク」数 (ディフォルト1)
inline void TIMING stop(unsigned key, REAL TYPE flopPerTask=0.0, unsigned iterationCount=1) {
#ifdef FX FAPP
   fapp stop( get tm label(key), 0, 0);
#endif
   // Intrinsic profiler
   TIMING PM.stop(key, flopPerTask, iterationCount);
```

ヘッダのインクルード

```
#include "PerfMonitor.h" // FX用のプロファイラ
#ifdef __FX_FAPP
#include "/fj_tool/fapp.h"
#endif
```

クラスライブラリのインスタンス

```
PerfMonitor PM;
```

- 初期化
  - 並列時のランク番号の割り当て(V-Sphere利用時)?
  - 初期化(ラベルの配列数 tm\_END を渡す)

```
// タイミング測定の初期化
PM.initialize(tm_END);
PM.setRankInfo(pn.ID);
PM.setParallelMode(para_mode, C.num_thread, C.num_process);
set_timing_label();
```

• サンプリング後の統計処理

```
FILE* fp = NULL;
Hostonly_ {
  if ( !(fp=fopen("profiling.txt", "w")) ) {
    stamped printf("\tSorry, can't open 'profiling.txt' file. Write failed.\n");
    assert(0);
// 測定結果の集計(gathreメソッドは全ノードで呼ぶこと)
PM.gather();
// マスターノードでのみ結果出力(排他測定のみ)
Hostonly {
 PM.print(stdout);
 PM.print(fp);
  // 結果出力(非排他測定も)
 if ( C.Mode.Profiling == DETAIL) {
     PM.printDetail(stdout);
     PM.printDetail(fp);
   if ( !fp ) fclose(fp);
```

## 自己申告:四則以外のflop count

#### max

```
do k=1,kx
do j=1,jx
do i=1,ix
    vm = vm + max( vm, p(i,j,k) )
end do
end do
end do
```

PA情報のカウンタ値とループ数から求めると

```
max() = 1 flops
```

### 推定方法

- 1. FXのPA情報からflop countを得る.
- 2. ループカウントとflop countから、ループあたりの flop countを求める.
- 3. 加算分を差し引き, 関数のflop countを得る.

# 測定flop count(FX)

	Total flop	loop	flop count/	
function	•	count	loop	Estimated flop
add	1.84E+09	1.66E+09	1.1	1
subtract	1.84E+09	1.66E+09	1.1	1
mply_f	3.51E+09	1.66E+09	2.1	1
mply_d	3.51E+09	1.66E+09	2.1	1
div_f	1.51E+10	1.66E+09	9.1	8
div_d	2.34E+10	1.66E+09	14.1	13
abs_f	3.50E+09	1.66E+09	2.1	1
abs_d	3.50E+09	1.66E+09	2.1	1
min_f	3.22E+09	1.66E+09	1.9	1
min_d	3.32E+09	1.66E+09	2.0	1
max_f	3.32E+09	1.66E+09	2.0	1
max_d	3.32E+09	1.66E+09	2.0	1
max3_f	4.98E+09	1.66E+09	3.0	2
sign	1.86E+09	1.66E+09	1.1	0
sqrt_f	1.85E+10	1.66E+09	11.1	10
sqrt_d	3.50E+10	1.66E+09	21.1	20
sin_f	5.00E+10	1.66E+09	30.1	29
sin_d	5.33E+10	1.66E+09	32.1	31
cos_f	5.00E+10	1.66E+09	30.1	29
cos_d	5.00E+10	1.66E+09	30.1	29

単精度: \_f 倍精度: \_d

max3 : max(a, b, c)

exp_f	3.86E+10	1.66E+09	23.2	22
exp_d	4.55E+10	1.66E+09	27.4	26
log_f	3.71E+10	1.66E+09	22.3	21
log_d	4.44E+10	1.66E+09	26.7	25
log10_f	4.18E+10	1.66E+09	25.2	24
log10_d	5.28E+10	1.66E+09	31.8	30
modulo_f	1.75E+10	1.66E+09	10.5	9
modulo_d	1.74E+10	1.66E+09	10.5	9
aint	1.17E+10	1.66E+09	7.0	6
anint	1.83E+10	1.66E+09	11.0	10
ceiling	4.98E+09	1.66E+09	3.0	2
i2dble	3.46E+09	1.66E+09	2.1	1
f2dble	3.50E+09	1.66E+09	2.1	1
floor	4.98E+09	1.66E+09	3.0	2
int	1.66E+09	1.66E+09	1.0	0
nint	1.16E+10	1.66E+09	7.0	6
i2real	3.46E+09	1.66E+09	2.1	1
d2real	3.50E+09	1.66E+09	2.1	1

# 測定flop count (FX) サマリー

### 単精度と倍精度で同じ

加減乗算:1

abs, min, max: 1

sin, cos: 29

### 単精度と倍精度で異なる

除算: 8/13

sqrt: 10/20

exp: 22/26

 $\log : 21/25$ 

log10: 24/30

### 変換

aint:6 小数部切り捨て

nint:6 引数に近い整数値

anint: 10 小数部の四捨五入

ceiling: 2 引数以上で最小の整数値

floor: 2 引数以下で最大の整数値

#### Cast

\* -> real, \* -> double : 1

 $* \rightarrow int : 0$ 

### 符号

sign: 0

## Flop countの注意点

- ループ中の定数演算は外に出す
  - コンパイラが自動的に判断し、ソースを変更するので無駄な計算部分のflop countは少なくなる
  - FXのプロファイラよりPMクラスのMFLOPSが大きければ、無駄な計算をしている可能性が高い
- ループ中のif文
  - if文内の演算数がある程度多ければ(10 flop以上)カウンタを使う
    - FXでは浮動小数点で加算した方がよい(整数レジスタ利用 の弊害で最適化がされない場合がある)
  - If文内の演算数が少なければ, カウントしない. あるいは, 適当 に近似

### HWPCによる計算量の自動算出

- 性能システムのCPUが内部に持つHWPC
  - CPU種類毎に物理的なカウンタの数が異なる
  - CPU種類毎に取得可能なイベントの種類が異なる
    - papi\_avail
- 計測されるイベントの回数
  - プログラムの実行に伴う全ての処理が対象
    - ソースプログラムで書かれている計算式
    - ・プログラムの実行・制御に必要な追加処理
    - コンパイラによる最適化の副影響
    - 投機的な実行による無駄な計算
  - PMlibの区間設定で興味ある部分に焦点をあてて解釈するとわかりやすい

### ハードウエアカウンタについて

### • 京•FX10 preset event

#### Available events and hardware information.

-----

Vendor string and code : Sun (7)

Model string and code : Fujitsu SPARC64 IXfx (141)

CPU Revision : 0.000000

CPU Megahertz : 1650.000000

CPU Clock Megahertz : 1650

CPU's in this Node : 16 Nodes in this System : 1 Total CPU's : 16

Number Hardware Counters: 8

Max Multiplex Counters: 512

Name Code Deriv Description (Note)

PAPI\_L1\_DCM 0x80000000 No Level 1 data cache misses

PAPI\_L1\_ICM 0x80000001 No Level 1 instruction cache misses

PAPI\_L1\_TCM 0x80000006 Yes Level 1 cache misses

PAPI\_L2\_TCM 0x80000007 Yes Level 2 cache misses

PAPI\_CA\_INV 0x80000000 No Requests for cache line invalidation

PAPI\_CA\_ITV 0x800000014 No Data translation lookaside buffer misses

PAPI TLB IM 0x80000015 No Instruction translation lookaside buffer misses

PAPI TLB TL 0x80000016 Yes Total translation lookaside buffer misses

PAPI\_MEM\_SCY 0x80000022 No Cycles Stalled Waiting for memory accesses

PAPI\_STL\_ICY 0x80000025 No Cycles with no instruction issue

PAPI\_FUL\_ICY 0x80000026 No Cycles with maximum instruction issue

PAPI\_STL\_CCY 0x80000027 Yes Cycles with no instructions completed

PAPI\_FUL\_CCY 0x80000028 Yes Cycles with maximum instructions completed

PAPI HW INT 0x80000029 No Hardware interrupts

PAPI\_BR\_MSP 0x8000002e No Conditional branch instructions mispredicted

PAPI\_BR\_PRC 0x8000002f Yes Conditional branch instructions correctly predicted

PAPI FMA INS 0x80000030 Yes FMA instructions completed

PAPI TOT IIS 0x80000031 Yes Instructions issued

PAPI TOT INS 0x80000032 No Instructions completed

PAPI\_FP\_INS 0x80000034 Yes Floating point instructions

PAPI\_LD\_INS 0x80000035 Yes Load instructions

PAPI SR INS 0x80000036 Yes Store instructions

PAPI BR INS 0x80000037 No Branch instructions

PAPI VEC INS 0x80000038 Yes Vector/SIMD instructions

PAPI TOT CYC 0x8000003b No Total cycles

PAPI\_LST\_INS 0x8000003c No Load/store instructions completed

PAPI\_L2\_TCH 0x80000056 Yes Level 2 total cache hits

PAPI\_L2\_TCA 0x80000059 Yes Level 2 total cache accesses

PAPI\_FP\_OPS 0x80000066 Yes Floating point operations

### ハードウエアカウンタについて

#### Intel Xeon E5 preset event

Hdw Threads per core : 1

Cores per Socket : 8

Sockets : 2

NUMA Nodes : 2

CPUs per Node : 8

Total CPUs : 16

Running in a VM : no

Number Hardware Counters : 11

Max Multiplex Counters : 32

Code Deriv Description (Note) Name PAPI L1 DCM 0x80000000 No Level 1 data cache misses PAPI L1 ICM 0x80000001 No Level 1 instruction cache misses PAPI L2 DCM 0x80000002 Yes Level 2 data cache misses PAPI L2 ICM 0x80000003 No Level 2 instruction cache misses PAPI L1 TCM 0x80000006 Yes Level 1 cache misses PAPI L2 TCM 0x80000007 No Level 2 cache misses PAPI L3 TCM 0x80000008 No Level 3 cache misses PAPI TLB DM 0x80000014 Yes Data translation lookaside buffer misses PAPI TLB IM 0x80000015 No Instruction TLBmisses PAPI L1 LDM 0x80000017 No Level 1 load misses PAPI L1 STM 0x80000018 No Level 1 store misses PAPI L2 STM 0x8000001a No Level 2 store misses PAPI STL ICY 0x80000025 No Cycles with no instruction issue PAPI BR UCN 0x8000002a Yes Unconditional branch instructions PAPI BR CN 0x8000002b No Conditional branch instructions PAPI BR TKN 0x8000002c Yes Conditional branch taken PAPI BR NTK 0x8000002d No Conditional branch not taken PAPI BR MSP 0x8000002e No Conditional branch mispredicted PAPI BR PRC 0x8000002f Yes Conditional branch correctly predicted PAPI TOT INS 0x80000032 No Instructions completed

PAPI FP INS 0x80000034 Yes Floating point instructions PAPI LD INS 0x80000035 No Load instructions PAPI\_SR\_INS 0x80000036 No Store instructions PAPI BR INS 0x80000037 No Branch instructions PAPI TOT CYC 0x8000003b No Total cycles PAPI L2 DCH 0x8000003f Yes Level 2 data cache hits PAPI L2 DCA 0x80000041 No Level 2 data cache accesses PAPI L3 DCA 0x80000042 Yes Level 3 data cache accesses PAPI L2 DCR 0x80000044 No Level 2 data cache reads PAPI L3 DCR 0x80000045 No Level 3 data cache reads PAPI L2 DCW 0x80000047 No Level 2 data cache writes PAPI L3 DCW 0x80000048 No Level 3 data cache writes PAPI L2 ICH 0x8000004a No Level 2 instruction cache hits PAPI L2 ICA 0x8000004d No Level 2 instruction cache accesses PAPI L3 ICA 0x8000004e No Level 3 instruction cache accesses PAPI L2 ICR 0x80000050 No Level 2 instruction cache reads PAPI L3 ICR 0x80000051 No Level 3 instruction cache reads PAPI L2 TCA 0x80000059 Yes Level 2 total cache accesses PAPI L3 TCA 0x8000005a No Level 3 total cache accesses PAPI L2 TCR 0x8000005c Yes Level 2 total cache reads PAPI L3 TCR 0x8000005d Yes Level 3 total cache reads PAPI L2 TCW 0x8000005f No Level 2 total cache writes PAPI L3 TCW 0x80000060 No Level 3 total cache writes PAPI FDV INS 0x80000063 No Floating point divide instructions PAPI\_FP\_OPS 0x80000066 Yes Floating point operations PAPI SP OPS 0x80000067 Yes Floating point operations; optimized to count scaled single precision vector operations PAPI DP OPS 0x80000068 Yes Floating point operations; optimized to count scaled double precision vector operations PAPI VEC SP 0x80000069 Yes Single precision vector/SIMD instructions PAPI VEC DP 0x8000006a Yes Double precision vector/SIMD instructions PAPI REF CYC 0x8000006b No Reference clock cycles

# ハードウエアカウンタ Xeon E5 preset とnative

Event name: PAPI\_FP\_OPS
Event Code: 0x80000066

Intel Xeon E5ではPAPI\_FP\_OPSとPAPI\_FP\_INSは同じ内容を表示

Number of Native Events:

Short Description: | FP instructions |

Long Description: | Floating point instructions|

Developer's Notes:

Derived Type: | DERIVED\_ADD|

Postfix Processing String: ||

Native Code[0]: 0x4000001c | FP\_COMP\_OPS\_EXE:SSE\_SCALAR\_DOUBLE|

Native Event Description: | Counts number of floating point events, masks: Number of SSE double precision FP scalar uops executed |

Native Code[1]: 0x4000001d | FP COMP OPS EXE:SSE FP SCALAR SINGLE|

Native Event Description: |Counts number of floating point events, masks: Number of SSE single precision FP scalar uops executed|

\$ papi avail -e PAPI DP OPS

Event name: PAPI\_DP\_0PS
Event Code: 0x80000068

Number of Native Events: 3

Short Description: | DP operations |

Long Description: |Floating point operations; optimized to count scaled double precision vector operations|

Native Code[0]: 0x4000001c | FP\_COMP\_OPS\_EXE:SSE\_SCALAR\_DOUBLE|

Native Event Description: |Counts number of floating point events, masks: Number of SSE double precision FP scalar uops executed|

Native Code[1]: 0x40000020 | FP\_COMP\_OPS\_EXE:SSE\_FP\_PACKED\_DOUBLE |

Native Event Description: |Counts number of floating point events, masks: Number of SSE double precision FP packed uops executed|

Native Code[2]: 0x40000021 |SIMD\_FP\_256:PACKED\_DOUBLE|

Native Event Description: |Counts 256-bit packed floating point instructions, masks:Counts 256-bit packed double-precision|

\$ papi\_avail -e PAPI\_VEC\_DP

Event name: PAPI\_VEC\_DP
Event Code: 0x8000006a

Number of Native Events: 2

Short Description: | DP Vector/SIMD instr|

Long Description: | Double precision vector/SIMD instructions|

Native Code[0]: 0x40000020 | FP COMP OPS EXE:SSE FP PACKED DOUBLE

Native Code[1]: 0x40000021 | SIMD\_FP\_256:PACKED\_DOUBLE

### ハードウエアカウンタ SPARC64 VIIIfx preset とnative

\$ papi\_avail -e PAPI\_FP\_OPS

Event name: PAPI\_FP\_OPS

Number of Native Events:

Short Description: | FP operations |

Long Description: |Floating point operations|

Derived Type: | DERIVED\_POSTFIX|

Native Code[0]: 0x40000010 |FLOATING\_INSTRUCTIONS|

Native Event Description: | Counts the number of committed floating-point operation instructions. |

Native Code[1]: 0x40000011 | FMA INSTRUCTIONS|

Native Event Description: | Counts the number of committed floating-point Multiply-and-Add operation instructions. |

Native Code[2]: 0x40000008 |SIMD\_FLOATING\_INSTRUCTIONS|

Native Event Description: | Counts the number of committed floating-point SIMD instructions of one operation in SIMD. |

Native Code[3]: 0x40000009 |SIMD\_FMA\_INSTRUCTIONS|

Native Event Description: | Counts the number of committed floating-point SIMD instructions of two operation in SIMD. |

### Pmlibの動作確認がとれているシステム

- 京/FX10
  - ログインノードでのクロスコンパイル環境
  - 計算ノードでのネイティブコンパイル環境
  - 富士通コンパイラ+MPI
- Intel Xeon E5 クラスタ
  - Intelコンパイラ+IntelMPI
  - GNUコンパイラ+OpenMPI/gnu
  - PGIコンパイラ+OpenMPI/pgi
- 必要なソフトウエア環境
  - C, C++ compiler
  - PAPIを組み込む場合はLinux kernel 2.6.32+
    - (Kernel バージョンが古い場合はPerfmod組み込み必要)

PMlib実習編

### 実習編

- 実習システムへのログイン
- PMlibのインストール
- 例題プログラムへの組み込み
- ・ 実行結果の解釈
- 例題プログラムの性能向上の検討

### PMlibの入手方法

- 公式なPMlibパッケージの入手方法
  - 下記から入手(Download zipボタン)
  - https://github.com/avr-aics-riken/PMlib
- 本日の実習では例題プログラムを追加したパッケージを使用します。
  - 京コンピュータログインノード2,3,4,5,6
  - /tmp/mikami/PMlib-master.2.1.3.rev2.tar.gz

## PMlibのインストール 京コンピュータ(1)

- PMlibのインストール作業はログインノードでも計算ノードでも 可能。本日はログインノードでインストール実施
- PMlibの利用は計算ノードアプリケーションが行う
- 任意のディレクトリでパッケージを展開。インストール先のディレクトリを --prefix で指定しconfigureの実施。自動作成されるMakefileを用いて、makeの実施。

# PMlibのインストール 京コンピュータ(2)

京でのインストール時間は数分で終了。正常にインストール されると以下のファイルができている。

```
$ Is -CF install_dir
bin/ doc/ include/ lib/ share/
$ Is -go install_dir/bin install_dir/include install_dir/lib
```

#### install\_dir/bin:

total 4

-rwxr-xr-x 1 1563 May 26 19:18 pm-config

#### install dir/include:

total 28

-rw-r--r-- 1 5798 May 26 19:18 PerfMonitor.h -rw-r--r-- 1 6099 May 26 19:18 PerfWatch.h

-rw-r--r-- 1 1490 May 26 19:18 mpi\_stubs.h

-rw-r--r-- 1 627 May 26 19:18 pmVersion.h

-rw-r--r-- 1 2079 May 26 19:18 pmlib\_papi.h

#### install dir/lib:

total 4136

-rw-r--r-- 1 4219910 May 26 19:18 libPM.a

-rw-r--r-- 1 11938 May 26 19:18 libpapi\_ext.a

```
$ Is -go ./example/
total 2764
```

-rw-r--r-- 1 24025 May 26 19:17 Makefile

-rw-r--r-- 1 1649 May 23 00:14 Makefile.am

-rw-r--r-- 1 25696 May 23 00:14 Makefile.in

-rw-r--r-- 1 1130 May 23 00:14 Makefile\_hand.fx10.login

-rw-r--r-- 1 1083 May 23 00:14 Makefile\_hand.intel

-rwxr-xr-x 1 1062806 May 26 22:33 check\_new\_api

-rw-r--r-- 1 6096 May 23 00:14 check\_new\_api.c

-rwxr-xr-x 1 4409884 May 26 22:33 pmlib test

-rw-r--r-- 1 2181 May 23 00:14 pmlib\_test.cpp

-rw-r--r-- 1 1156 May 23 00:14 sub kernel.c

# PMlibを用いる 京コンピュータ(1)

• Example/以下のサンプルプログラムでPMlibを利用してみる

```
#!/bin/bash
set -x
date; hostname; /opt/FJSVXosPA/bin/xospastop
PMLIB=${HOME}/pmlib/PMlib-master
PMLIB INCLUDE=-I${PMLIB}/include
PMLIB LIB=${PMLIB}/src/libPM.a
PAPI ROOT=/usr
PAPI LIB="$PAPI ROOT/lib64/libpapi.a $PAPI ROOT/lib64/libpfm.a"
PAPI EXT="$PMLIB/src papi ext/libpapi ext.a"
CXXFLAGS="-Kfast,parallel,openmp ${PMLIB INCLUDE} ${PAPI INCLUDE}"
CCFLAGS="-std=c99 -Xg -Kfast,parallel,openmp ${PMLIB INCLUDE} ${PAPI INCLUDE}"
LDFLAGS="${PMLIB LIB} ${PAPI LIB} ${PAPI EXT}"
SRC DIR=${HOME}/pmlib/PMlib-master/example
WKDIR=/data/ra000004/a03155/tmp/check pmlib; mkdir-p $WKDIR
cd $WKDIR; if [$? != 0]; then echo '@@@ Directory error @@@'; exit; fi
cp $SRC DIR/pmlib main.cpp main.cpp
cp $SRC DIR/sub kernel.c sub.c
mpiFCC -c ${CXXFLAGS} main.cpp
mpifcc -c ${CCFLAGS} sub.c
mpiFCC ${CXXFLAGS} main.o sub.o ${LDFLAGS}
export OMP NUM THREADS=4
mpirun -np 2 ./a.out
```

## Pmlibを用いる 京実行結果例 (1)

### • 基本プロファイル+MPIプロセス毎プロファイル

```
Report of Timing Statistics PMlib version 2.1.3
      Operator: RRR
      Host name: QQQ
      Date : 2014/05/26 : 23:25:43
      Parallel Mode
                           : Hybrid (2 processes x 4 threads)
      Total execution time = 7.231672e-01 [sec]
      Total time of measured sections = 7.296531e-01 [sec]
      Statistics per MPI process [Node Average]
      Label | call | accumulated time | flop | messages[Bytes]
                  | avr[sec] avr[%] sdv[sec] avr/call[sec] | avr sdv speed
      section1: 2 4.918501e-01 67.41 2.4496e-02 2.459251e-01 0.000e+00 0.000e+00 0.00 Mflops
      section2: 1 2.378030e-01 32.59 1.9418e-03 2.378030e-01 4.000e+09 0.000e+00 16.82 Gflops
               7.296531e-01
                                                   4.000e+09 5.48 Gflops
      Total |
      Performancel
                                                                 10.96 Gflops
      Elapsed time variation over MPI ranks
section1
                  accm[s] accm[%] waiting[s] accm/call[s] flop|msg speed
MPI rank call
#0 :
          2 4.745290e-01 65.03 3.464222e-02 2.372645e-01 0.000e+00 0.00 Mflops
#1 :
          2 5.091712e-01 69.78 0.000000e+00 2.545856e-01 0.000e+00 0.00 Mflops
section2
MPI rank call
                  accm[s] accm[%] waiting[s] accm/call[s] flop|msg speed
          1 2.391760e-01 32.78 0.000000e+00 2.391760e-01 4.000e+09 16.72 Gflops
#0 :
#1 :
          1 2.364299e-01 32.40 2.746105e-03 2.364299e-01 4.000e+09 16.92 Gflops
```

## Pmlibを用いる 京実行結果例 (2)

• 環境変数を追加 export HWPC\_CHOOSER=FLOPS

```
Statistics per MPI process [Node Average]
     Label | call | accumulated time | flop | messages[Bytes]
                 | avr[sec] avr[%] sdv[sec] avr/call[sec] | avr sdv speed
      section1: 2 4.843562e-01 67.16 9.8485e-03 2.421781e 7 8.123e+09 2.828e+00 16.77 Glops
      section2: 1 2.368304e-01 32.84 2.1871e-03 2.368304e-01 4.033e+09 7.071e-01 17.03 Gflops
      Total | 7.211865e-01
                                       1.216e+10 16.86 Gflops
                                                               33.71 Gflops
      Performancel
      PMlib detected the CPU architecture:
      The available Hardware Performance Counter (HWPC) events depend on this CPU architecture.
           Sun
           Fujitsu SPARC64 VIIIfx
     HWPC event values of the master rank, sum of threads. count unit in Giga (x 10e9)
      - : FP OPS [GFlops]
      section1: 8.123 17.015
      section2: 4.033 16.919
      Elapsed time variation over MPI ranks
section1
MPI rank call accm[s] accm[%] waiting[s] accm/call[s] flopimsg speed
#0 : 2 4.773922e-01 66.20 1.392794e-02 2.386961e-01 8.123e+09 17.02 Gflops
#1 :
         2 4.913201e-01 68.13 0.000000e+00 2.456601e-01 8.123e+09 16.53 Gflops
section2
MPI rank call
                 accm[s] accm[%] waiting[s] accm/call[s] flop|msg speed
#0 : 1 2.383769e-01 33.05 0.000000e+00 2.383769e-01 4.033e+09 16.92 Gflops
          1 2.352839e-01 32.62 3.093004e-03 2.352839e-01 4.033e+09 17.14 Gflops
#1 :
```

# Pmlibを用いる 京実行結果例 (3)

• 環境変数を追加 export HWPC\_CHOOSER=FLOPS,VECTOR

```
PMlib detected the CPU architecture:
The available Hardware Performance Counter (HWPC) events depend on this CPU architecture.
      Sun
       Fujitsu SPARC64 VIIIfx
HWPC event values of the master rank, sum of threads, count unit in Giga (x 10e9)
          📮 OPS [GFlops] VEC_INS FMA_INS
                                 3.180
section1
             8.123
                      17.010
                                          0.881
                                          0.435
section2: 74.033
                      16.758
                                 1.581
      HWPC events legend: count unit in Giga (x 10e9)
             FP_OPS: floating point operations
             VEC INS: vector instructions
             FMA INS: Fused Multiply-and-Add instructions
             LD INS: memory load instructions
             SR INS: memory store instructions
             L1 TCM: level 1 cache miss
             L2 TCM: level 2 cache miss (by demand and by prefetch)
             L2 WB DM: level 2 cache miss by demand with writeback request
             L2 WB PF: level 2 cache miss by prefetch with writeback request
             TOT CYC: total cycles
              MEM SCY: Cycles Stalled Waiting for memory accesses
              STL ICY: Cycles with no instruction issue
             TOT INS: total instructions
             FP INS: floating point instructions
       Derived statistics:
              [GFlops]: floating point operations per nano seconds (10^-9)
              [Mem GB/s]: memory bandwidth in load+store GB/s
             [L1$ %]: Level 1 cache hit percentage
             [LL$ %]: Last Level cache hit percentage
```

## Pmlibを用いる 京実行結果例 (4)

● 環境変数を変更 export HWPC\_CHOOSER=BANDWIDTH

```
Statistics per MPI process [Node Average]
Label | call | accumulated time | flop | messages[Bytes]
            | avr[sec] avr[%] sdv[sec] avr/call[sec] | avr sdv speed
section1: 2 4.823370e-01 66.93 3.7025e-03 2.411685e-01 1.007e+10 6.975e+08 19.45 GB/sec
section2: 1 2.383659e-01 33.07 2.4961e-03 2.383659e-01 5.227e+09 6.785e+08 20.42 GB/sec
Total | 7.207029e-01 1.530e+10 19.77 GB/sec
Performancel
                                                            39.54 GB/sec
PMIib detected the CPU architecture:
The available Hardware Performance Counter (HWPC) events depend on this CPU architecture.
      Sun
      Fujitsu SPARC64 VIIIfx
HWPC event values of the master rank, sum of threads. count unit in Giga (x 10e9)
        L2 TCM L2 WB DM L2 WB PF [Mem GB/s]
section1: 0.082 0.000
                            0.000 22.025
section2:
           0.045 0.000
                            0.000 23.763
      HWPC events legend: count unit in Giga (x 10e9)
            FP OPS: floating point operations
            VEC INS: vector instructions
            FMA INS: Fused Multiply-and-Add instructions
            LD INS: memory load instructions
            SR INS: memory store instructions
            L1 TCM: level 1 cache miss
            L2 TCM: level 2 cache miss (by demand and by prefetch)
            L2 WB DM: level 2 cache miss by demand with writeback request
            L2 WB PF: level 2 cache miss by prefetch with writeback request
```

## プロファイルの検討と最適化への反映

- サンプルプログラムでの検討
  - STREAMベンチマークプログラムのC++ OpenMP版

• STREAMの標準出力とPmlib出力の比較・解説

## PMlibを用いる Intel Xeon(1)

- Example/以下のサンプルプログラムでPMlibを利用してみる
  - Module環境が設定されてる場合の例

```
#!/bin/bash
module load intel impi papi pmlib/intel
CFLAGS="-O3 -openmp -vec-report -openmp-report"

mpicxx -c ${CFLAGS} ${INCLUDES} main.cpp
mpicc -c ${CFLAGS} ${INCLUDES} sub.c
mpicxx ${CFLAGS} ${INCLUDES} main.o sub.o ${LDFLAGS}

export HWPC_CHOOSER=FLOPS
export OMP_NUM_THREADS=4
mpirun -np 2 ./a.out
```

### Module環境が設定されていない場合は別途変数を 指定しておく

INCLUDES=-I/usr/local/pmlib/pmlib-2.1.2-intel/include -I/usr/local/papi/papi-5.2.0/intel/include LDFLAGS=-L/usr/local/pmlib/pmlib-2.1.2-intel/lib -IPM -Ipapi\_ext -L/usr/local/papi/papi-5.2.0/intel/lib -Ipapi - Ipfm