

Lecture 4

Multiple Access (MAC) Protocols and Wired LAN Standards

ELEC 3506/9506
Communication Networks

Dr Wibowo Hardjawana
School of Electrical and Information Engineering



Topics for the Day


- Multiple Access Protocols
 - -CSMA/CD
 - -CSMA/CA

- LAN Standards
 - Ethernet
 - —Token Ring
 - -FDDI



IEEE Project 802

- IEEE started Project 802 to standardize LAN communications in 1985
- Project 802 split the data link layer into two different sub-layers:
 - Logical Link Control (LLC)
 - Media Access Control (MAC)






LLC vs. MAC

- Logical Link Control (LLC) Provides one single data link control protocol for all IEEE LANs.
 - Flow Control
 - Error Control
 - Framing (partly)
- Media Access Control (MAC) Defines and specifies the access method for LANs.
 - Different access methods (CSMA/CD, CSMA/CA Token Ring, Token Bus)
 - Framing (partly)



Multiple Access Protocols






Controlled Access Protocols



Reservation


- A station needs to make a reservation before sending data
- A reservation frame to indicate slot allocation precedes the data frames
- Each mini slot in that frame belongs to a station






Polling (Select/Poll)

- Works with topologies where one device is designated as a primary station and the other devices are secondary station (Master/Slave)
- The primary station has control of the physical link (initiates the session)



Primary to transmit to B by broadcasting

SEL containing the address of B B indicates it is ready to receive by sending **ACK**




Primary queries A and B 's transmit intention by broadcasting **Poll** to A and B A and B indicate no and yes by sending **NAK** and ⁸data



Logical Ring and Physical Topology

Ring is based on token



Physical ring: a,b,and d. Predecessor, Successor concepts w/o the need of addresses Logical ring: c. Predecessor, Successor concepts with the need of addresses



Token Passing

- When no station is transmitting a data frame, a special token frame circles a logical ring.
- This special token frame (with addresses) is repeated from station to station until arriving at a station that needs to transmit data.
- When a station needs to transmit data, it retains the token (successor) and transmit a data frame.
- No body else can transmit during this time.
- When the receiving station receives data and it then sends ACK back to the sending station.
- Once the sending station receives the ACK, it (predecessor) releases the token in to the ring and pass it to the next station (successor).
- No Contention and No Collision in the ring



Token Management

- If an error occurs, a special station referred to as the Active Monitor detects the problem and removes and/or reinserts tokens as necessary.
- On 4 Mbit/s Token Ring, only one token may circulate; on 16 Mbit/s Token Ring, there may be multiple tokens.
- The special token frame consists of three bytes.
- Stations with a high-priority transmission may request priority access to the token (priority token access)



Random Access



CSMA/CD

- Carrier Sense Multiple Access with Collision Detection (CSMA/CD) is a random access/contention based access method
- No station superior or controls others
- No scheduled time to transmit (random access)
- No rules specify who sends next
- Stations compete with each other to access the medium (contention based)
- If more than one station transmit frames, collisions may take place




CSMA/CD Algorithm

- Step 1: When a device wants to send data, it first listens to the channel (CS). This is to find out whether a frame is currently being transmitted or received
- Step 2: If no other frame is on the link, send; or if another frame is on the link, wait and then listen again
- Step 3: While sending, listen to the feedback signal for a possible collision (CD):
 - If successfully transmitted, frame cleared from memory
 - if a collision occurs, stop, send a jamming signal, wait and listen again
- Listening is is based on energy level
- Waiting duration (backoff) is randomly selected from a window 14



Collision and Abortion in CSMA/CD



- Before sending the last bit of the frame, the sending station must detect a collision.
- Therefore, frame transmission time (T_{fr}) must be at least two times the maximum propagation time (T_p)
- If two stations involved in a collision are maximum distance apart, the signal from the first takes time T_p to reach the second, and the effect of the collision takes another T_p to return to the first.
- So, the requirement is that the first station must still be transmitting after 2T_p.
- Successful transmission happens when A does not sense collision



Minimum Frame Size

Example:

- For a network using CSMA/CD that has a bandwidth of 10 Mbps, if the maximum propagation time T_p (from one end to the other) is 25.6 µs. What is the minimum size of the frame?
- The frame transmission time (slot time) $T_{fr} = 2 * T_p = 51.2 \mu s$.
- Therefore, the minimum frame size is 10 Mbps * 51.2 μ s = 512 bits or 64 bytes.
- If the first 512 bits are successfully transmitted, it is guaranteed that a collision will not happen during the transmission of this frame.
- So, the sender only needs to listen for a collision during the first 512 bits.
- The slot time is the time required for a station to transmit 512 bits; for 10Mbps traditional Ethernet it is $51.2 \, \mu s$
- What will happen if the frame size < 51.2 μs? Cant detect collision




Maximum Collision Domain Size

- The maximum length of the network (collision domain)
 - = Propagation Speed * maximum propagation time (T_p) = $(2*10^8)$ * $(25.6*10^{-6})$ = 5120 m
- Considering delay time at repeaters/hubs and network interfaces, the max. length of a traditional (10 Mbps) Ethernet network is reduced to 2500 m (48% of the theoretical calculation)
- The max. length for a 100 Mbps Ethernet network is 250 m
- Electrical signal is a copper wire travel at approx. 2/3 of the speed of light



Energy Level

- Three values of energy:
 - Zero the channel is idle
 - Normal level a station is successfully transmitting a frame
 - Abnormal level there is a collision and the level of energy is twice the normal level






CSMA/CA

- CSMA/CD cannot be used in a wireless medium because:
 - In a wireless network, collisions do not add enough energy for stations to effectively detect them
 - Collisions may not be detected because of hidden node problem
 - Distance between stations may be great and signal fading could prevent a station at one end from hearing a collision at the other end
 - Unlike non-wireless mediums, the received signal power is not known
 - Signal fade significantly in wireless medium
- Therefore, collisions are avoided by the CSMA/CA strategy



CSMA/CA (persistent method)

CW is selected from $\{0,1,...2^n-1\}*512$ bit times where n is the number of collision




1-persistent has the highest chance of collision Non-persistent has the lowest chance of collision p-persistent transmits with a probability of p and waits for a period Binary Exponential Back-off in CW \rightarrow spread collision in 2ⁿ time slots¹



CSMA/CA

- After finding an idle channel, source waits for a period of time called distributed inter frame space (DIFS)
- Then source sends a control frame to destination called request to send (RTS)
- After receiving RTS, destination waits for period of time called short inter frame space (SIFS), then sends a control frame called clear to send (CTS) to the source
- The source sends data after waiting time = SIFS
- The destination sends an ACK after waiting another time equal to SIFS




- CA uses persistent methods, randomly select CW and decrement it
- CSMA/CA waits for ACK before sending additional frames
- DIFS, SIFS and a time slot are 50μs, 20μs and 10μs, followed by CA



Hidden Node Problem

RTS contains info on the time required to transmit data and is used with CTS to reserve the wireless channel



Hidden node problem happens when B and A are simultaneously transmitting to $AP \rightarrow A$ is hidden from B (during handshake)




Network Allocation Vector (NAV)

- How is collision avoidance accomplished?
 - When a station sends a RTS/CTS frame, it includes the duration of time that it needs to occupy the channel.
 - Other stations that are affected create a timer called a Network Allocation Vector (NAV) to defer based on the information in RTS/CTS frame
 - The NAV shows the time that must pass before these stations are allowed to check/sense the channel for idleness
 - Each time a station access the system and sends a RTS frame, other stations start their NAV.
- Collision during handshake
 - Two or more stations may try to send RTS frames at the same time and these may collide
 - Sender assumes that there may have been a collision since it does not receive a CTS frame
 - Revert back to CW and the back-off strategy is employed, sender tries again



Exposed Node Problem



Exposed node problem happens when A are transmitting to B \rightarrow C is exposed to A



Summary

- CSMA/CA address collision in the wireless medium by using
 - backoff/persistent methods to spread transmission in time
 - NAV to ensure all stations are aware of on-going transmissions
 - ACK to ensure the sender are aware transmission is successful or not

RTS and CTS solve hidden node but not exposed node problems



Assessment

- Lab Reports (32%) maximum 7 pages report
 (4 labs * 8 marks each = 32 Marks)
- Quizzes (20%)
 - 30 minutes and worth 10% each
 - Quiz 1 is on Week 6, available from 4-6 September 24 (Material from Weeks 1-4)
 - Quiz 2 is on Week 10, available from 11-13 Oct 24
 - Will be in Canvas and online
 - Only allow 1 attempt to complete these quizzes
- Final Exam (48%)
 - 2 hour Essay-type Exam
 - In-person



Local Area Networks



Local Area Networks


- A data communication system that allows a number of independent devices to communicate directly with each other in a limited geographic area
- Three most popular LAN standards
 - Ethernet
 - Token ring
 - FDDI



Ethernet

"dominant" wired LAN technology:

- first widely used LAN technology
- simpler, cheap
- kept up with speed race: 10 Mbps 400 Gbps
- single chip, multiple speeds (e.g., Broadcom BCM5761)



Metcalfe's Ethernet sketch

https://www.uspto.gov/learning-and-resources/journeys-innovation/audio-stories/defying-doubters



Ethernet (IEEE 802.3)

- It is a simple LAN architecture with very little management overhead.
- Access method CSMA/CD
- Cabling is either twisted pair, fiber, thick or thin coaxial cable.
- Cable and connection types are known as 10BaseT, 10BaseF, 10Base5, 10Base2.
- Bits are coded using Manchester encoding.
- Traditional Ethernet is Half Duplex.



Ethernet: physical topology

- bus: popular through mid 90s
 - all nodes in same collision domain (can collide with each other)
- switched: prevails today
 - active link-layer 2 switch in center
 - each "spoke" runs a (separate) Ethernet protocol (nodes do not collide with each other)

bus: coaxial cable switched



Ethernet frame structure

sending interface encapsulates IP datagram (or other network layer protocol packet) in Ethernet frame




preamble:

- used to synchronize receiver, sender clock rates
- 7 bytes of 10101010 followed by one byte of 10101011



Ethernet frame structure (more)



- addresses: 6 byte source, destination MAC addresses
 - if adapter receives frame with matching destination address, or with broadcast address (e.g., ARP packet), it passes data in frame to network layer protocol
 - otherwise, adapter discards frame
- type: indicates higher layer protocol
 - mostly IP but others possible, e.g., Novell IPX, AppleTalk
 - used to demultiplex up at receiver
- CRC: cyclic redundancy check at receiver
 - error detected: frame is dropped




Ethernet: unreliable, connectionless

- connectionless: no handshaking between sending and receiving NICs
- unreliable: receiving NIC doesn't send ACKs or NAKs to sending NIC
 - data in dropped frames recovered only if initial sender uses higher layer rdt (e.g., TCP), otherwise dropped data lost
- Ethernet's MAC protocol: unslotted CSMA/CD with binary backoff



802.3 Ethernet standards: link & physical layers

- many different Ethernet standards
 - common MAC protocol and frame format
 - different speeds: 2 Mbps, 10 Mbps, 100 Mbps, 1Gbps, 10 Gbps, 40 Gbps
 - different physical layer media: fiber, cable





Bridged Ethernet


 The first step in the Ethernet evolution was the division of a LAN by bridges.

- Bridges have two effects on an Ethernet LAN:
 - Raise the bandwidth
 - Separate collision domains




Raising the Bandwidth

- In an unbridged Ethernet network, the total capacity (say 10 Mbps) is shared among all stations.
- A bridge can divide the network into two or more segments and bandwidth-wise each network becomes independent



a. Without bridging




b. With bridging




Separating Collision Domains

- A bridge can separate a collision domain
- Collision domains becomes much smaller and the probability of collisions are reduced tremendously



a. Without bridging




b. With bridging



Switched Ethernet


- A switch is a multiple-port bridge
- Instead of having 2-4 networks, why not have N networks, where is the number of nodes in the LAN?
- So an N-port switch can be used
- Bandwidth is shared only between the station and the switch (10/2 = 5) Mbps each)
- The single collision domain is divided into N domains






Full-Duplex Ethernet

- Traditional Ethernet (10Base5, 10Base2) is half-duplex
- 10BaseT is full-duplex
- Increases the capacity from 10 to 10000 Mbps
- Two separate links for transmitting and receiving are used between the station and the switch
- No need for CSMA/CD





Gigabit (1Gbps) Ethernet



Implementation	Medium	Medium Length(m)	Wires	Encoding
1000Base-SX	Fiber S-W	550 m	2	8B/10B + NRZ
1000Base-LX	Fiber L-W	5000 m	2	8B/10B + NRZ
1000Base-CX	STP	25 m	2	8B/10B + NRZ
1000Base-T4	UTP	100 m	2	4D-PAM5 42



10-Gigabit Ethernet


- IEEE Standard 802.3ae
- operates only in full-duplex mode, no contention; no CSMA/CD
- Four implementations are the most common: 10GBase-SR, 10GBase-LR, 10GBase-EW, and 10GBase-X4.

Implementation	Medium	Medium Length	Number of wires	Encoding
10GBase-SR	Fiber 850 nm	300 m	2	64B66B
10GBase-LR	Fiber 1310 nm	10 km	2	64B66B
10GBase-EW	Fiber 1350 nm	40 km	2	SONET
10GBase-X4	Fiber 1310 nm	300 m to 10 km	2	8B10B



Virtual LAN (VLAN)

- A VLAN is a LAN configured by software and not by physical wiring
- A single physical LAN can be divided into several logical LANs
- VLANs create separate broadcast domains
- Stations are grouped based on: port #, IP addresses, MAC addresses, or a combination





Token Ring – IEEE 802.5

- Token Ring has become the IEEE standard 802.5.
- It was developed by IBM for STP, IBM Type 1 cabling.
- TR is available for speeds of 4 Mbps and 16Mbps.
- Bits are Encoded using Differential Manchester Encoding.
- The typical maximum frame size is 4500 bytes.
- Some implementations allow larger frame sizes.
- Each TR card has a unique 48-bit address similar to Ethernet.



FDDI (Fiber Distributed Data Interface)

Specifications:

- FDDI is a token ring network designed to run over fiber optic cabling (Multimode Fiber).
- The data transfer rate is 100Mbps.
- It has a maximum circumference of 200km (Both Rings)
- Topology Ring based token bus network (not token ring)
- Access Control Method A timed token protocol
- More than one frame is transmitted before releasing the token
- Hence, FDDI has higher throughput than 802.5



FDDI (Fiber Distributed Data Interface)

Specifications:

- Consists of two rings (Primary and Secondary Rings)
- Each ring should be limited to 500 nodes and 100km of cable.
- Repeater is required every 2Km or less

Mechanism of Operation:

- Two counter rotating dual rings are used. Two similar data streams flow around the two counter rotating rings
- Traffic usually flows on the primary ring and if this ring fails FDDI automatically reconfigures the network so the data flows on to the secondary ring in the opposite direction.
- Advantage is Redundancy.
- This automatic reconfiguration is called as self-healing.
- Stations can be dual (Class A) or single (Class B) attached.
- When there is network failure Class A stations reconfigures but not Class B stations.



FDDI Self Healing





Fig. 4-45. (a) FDDI consists of two counterrotating rings. (b) In the event of failure of both rings at one point, the two rings can be joined together to form a single long ring.




Cable access network: FDM, TDM *and* random access!



- multiple downstream (broadcast) FDM channels: up to 1.6 Gbps/channel
 - single CMTS transmits into channels
- multiple upstream channels (up to 1 Gbps/channel)
 - multiple access: all users contend (random access) for certain upstream channel time slots request; others assigned TDM
 - Persistent method and Binary Exponential Back-off to resolve collision



Cable access network: FDM, TDM *and* random access!



DOCSIS: data over cable service interface specification

- FDM over upstream, downstream frequency channels
- TDM upstream: some slots assigned, some have contention
 - downstream MAP frame: assigns upstream slots
 - request for upstream slots (and data) transmitted random access (binary backoff) in selected slots



Recommended Reading

 Behrouz A. Forouzan, Data Communications and Networking with TCP/IP Protocol Suite, 6th ed., 2022, Chapters 3 and 4

 J. F. Kurose and K. W. Ross, Computer Networking: A Top-Down Approach, 8th ed., 2022, Chapter 6



Knowledge Test

slido

Join at slido.com #5721 256

