4. Files and troubleshooting

4.1 Where everything is kept

What	Where
The programs	`v001/out/gcc/` and `v001/out/clang/`: `treesync`, `treesync-cli`, `treesync-test`
Build and test output	`v001/out/` (`verify/` logs, `bootstrap-*.txt`); ignored by git
GUI settings	`~/.config/treesync/settings`: one option per line, as on the command line
Build page choices	`~/.config/treesync/build`
Database	`~/.local/share/treesync/treesync.db` (SQLite): runs, actions, hash cache, checks
Run logs	`~/.local/share/treesync/logs/YYYY-MM-DD_HHMMSS.log`
Results of every run	`~/.local/share/treesync/logs/Results.txt`, one line per run
AI exports	`~/.local/share/treesync/logs/ai/run-N-logs.AI.md`, `run-N-sql.AI.md`
Root runs	the same under `/root/.local/share/treesync/`
Safe-delete folder	`<target>.old` next to the target (or `--safe-delete-dir`)
Unfinished copies	`NAME.treesync-part` next to where the file goes; removed when done
This manual	`Manual/*.md` (the sources) and `Manual/pdf/` (built by `Manual/build-pdf.sh`)

`--db=PATH` puts the database (and its `logs/` folder) somewhere else.

4.2 Troubleshooting

"TreeSync is not running as root ... only inside your home directory"
: Local trees outside your home need root: tick **Sync > Run as root**, or run `sudo treesync-cli ...`. Inside your home nothing is needed.

A path is refused
: Without root, a path that leaves your home (also through `..` or a symlink) is refused. Use root, or a path inside your home.

bootstrap stops: "Still missing: ..."
: A required package did not install. Run the install command it printed by hand and read its error (often a repository that is not enabled, for example CodeReady Builder on RHEL for `gtk3-devel`), then run `./bootstrap.sh` again.

build.sh: "U++ (umk + uppsrc) not found"

Run `./bootstrap.sh`, or point to an existing U++ with `export UPP_DIR=/path/to/u++`.

A gcc release build crashes at start

The U++ heap fix is missing (`uppfix`); `./bootstrap.sh` applies it.

A test fails

`./verify.sh` stops and prints the failing checks; the full output is in `v001/out/verify/<compiler>-<type>.log`. `git push --no-verify` pushes anyway, but fix it first if you can.

A run is slow

Make sure the GUI runs a **release** build (`./verify.sh` leaves them in `out/`). Many small files: more threads (`--threads=8`) can help. Over SFTP the network is usually the limit; `--compress` helps text, not media.

"no Wayland session found" on the Build page

The GUI was started without `WAYLAND_DISPLAY`, usually through `sudo`. Start it as yourself and use **Sync > Run as root** for root runs.

The host key is refused (remote trees)

Connect once with `ssh user@host` to check and accept the key; TreeSync never accepts an unknown or changed key by itself.

A run was stopped and the target has `.treesync-part` files

Run the same sync again: it resumes, re-checks what was already copied, and removes the part files when done. `--fresh` starts over instead.

The `.old` folder keeps growing

Safe delete never deletes. **Sync > Clear .old folders...** (or `treesync-cli --clear-old --no-dry-run`) empties it when you are sure.

Something else

View > Export newest run for AI and give the files in `logs/ai/` to an AI, or read them yourself: they list every problem of the run first.