

FilingBox GIGA (ITU-T X.1223)

Installation/Configure/Manage



FILINGCLOUD



VMware Installation and
Giga OVA Import

License Registration

Setting Administrator Page

Connect Network Drive


VMware Installation and
Giga OVA Import

1. VMware Installation
2. Giga OVA Import

License Registration

Setting Administrator Page

Connect Network Drive



Install VMware Workstation Pro

Vmware Download Account Creation URL

<https://profile.broadcom.com/web/registration>

Download Giga OVA

Vmware Installation Download URL

<https://support.broadcom.com/group/ecx/productdownloads?subfamily=VMware%20Workstation%20Pro&freeDownloads=true>

Set the network of VMware

FilingBox Giga Server OVA Download URL


https://drive.google.com/file/d/10NRYTL1bhqeL51_jqqXCdkeV3ALz6RoL/view?usp=drive_link

Connecting to Giga server


FilingBox Help Center

<https://help.filingbox.com>


Set the network of VMware



Set the network of VMware



Set the network of VMware



The Virtual Network Editor window displays the following table:

Name	Type	External Connection	Host Connection	DHCP	Subnet Address
VMnet1	Host-only	-	Connected	Enabled	192.168.174.0
VMnet8	NAT	NAT	Connected	Enabled	192.168.203.0

Buttons: Add Network..., Remove Network, Rename Network...

VMnet Information

☐ Bridged (connect VMs directly to the external network)
Bridged to: Automatic Settings...

☐ NAT (shared host's IP address with VMs) NAT Settings...

☒ Host-only (connect VMs internally in a private network)

☒ Connect a host virtual adapter to this network
Host virtual adapter name: VMware Network Adapter VMnet1


☒ Use local DHCP service to distribute IP address to VMs DHCP Settings...

Subnet IP: Subnet mask:


⚠ Administrator privileges are required to modify the network configuration. [Change Settings](#)

Buttons: Restore Defaults, Import..., Export..., OK, Cancel, Apply, Help


Set the network of VMware




Set the network of VMware



Set the network of VMware



Set the network of VMware



Set the network of VM

```
Activate the web console with: systemctl enable --now cockpit.socket

localhost login: root
Password: _
```

Login

ID: root

PW: 1qaz2wsx3e#

```
ms33 flags=4163<UP,BROADCAST,RUNNING,MULTICAST> mtu 1500
    inet 192.168.205.135 netmask 255.255.255.0 broadcast 192.168.205.255
    inet6 fe80::20c:29ff:febe:ebd6 prefixlen 64 scopeid 0x20<link>
    ether 00:0c:29:be:eb:d6 txqueuelen 1000 (Ethernet)
    RX packets 29 bytes 3754 (3.6 KiB)
    RX errors 0 dropped 0 overruns 0 frame 0
    TX packets 63 bytes 6880 (6.7 KiB)
    TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0

lo: flags=73<UP,LOOPBACK,RUNNING> mtu 65536
    inet 127.0.0.1 netmask 255.0.0.0
    inet6 ::1 prefixlen 128 scopeid 0x10<host>
    loop txqueuelen 1000 (Local Loopback)
    RX packets 39 bytes 4647 (4.5 KiB)
    RX errors 0 dropped 0 overruns 0 frame 0
    TX packets 39 bytes 4647 (4.5 KiB)
    TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
```

IP check

ifconfig

Giga Installation or
VMware OVA Import

License Registration

Setting Administrator Page

Connect Network Drive

1. 2ec09d44-e04b-4b8e-b4d7-74a380895ba1
2. 17a19525-6cfa-438c-88a3-21fa88b01a6e
3. 7524f7fd-857e-4362-b4eb-fc760c075ab3
4. 65484339-26c6-4c73-88f8-307ab032aa2c
5. b49306d9-e99e-4931-8e57-6c7303139ab0
6. e33ad049-e4f3-45cb-9dcb-f1fd4ce626e6
7. 96a66638-c064-41ad-ad37-1f06b860c88c
8. 348f02fb-9805-46f0-9ace-5bb328d831cf
9. ab5ebd22-3931-44e9-bd04-89260e1bf0b0
10. d3af4510-1607-424a-9c6e-45e17e485377
11. 34dca836-5529-4194-8685-87f2b2bcd3f2
12. 1bf580e3-1684-43cd-87ad-5930bcaa3525
13. 1d956708-025c-446b-9d66-d81994e5cf2e
14. e3f5d76a-7354-4659-93a2-c85674ec9061
15. 93a451e8-106b-4fb7-be59-09d366497ed5
16. f004f235-518f-4d05-8e23-0a00851fc4a4
17. 66b68043-ee1d-4057-a5f8-51b4736e915d
18. f5922500-27b9-45b3-99c2-59d7502e89e2
19. cdc423e5-989b-4ffc-a702-2ff0d22f123e
20. 16e68e23-677b-4d0d-a6b7-eaa89b3d63fd
21. 7ff6537c-a1d8-43e1-99a5-8cf53433e387
22. 349797c1-8707-47f2-b9cf-76880f862588
23. 37ca8370-17da-435a-9652-0bc9e4d64e76
24. 80438194-30cf-4ebd-8ee1-b36aae2a216a
25. 8bf87911-5b1c-4eba-9f69-df7a0966963e
26. cfd00729-826d-4f85-b620-0921a3351983
27. 4b085eab-c078-4c60-85d6-8bb75ad101fa
28. 44b46b02-0890-41c1-adf3-6cee8ec899a6
29. 2ec09d44-e04b-4b8e-b4d7-74a380895ba1
30. 13a702e3-5c98-4238-8cbd-dd8d46776345

VMware Installation and
Giga OVA Import

License Registration

Setting Administrator Page

Connect Network Drive

1. Access Giga Admin page
2. Add Groups
3. Add Users
4. Shared Folder Management
5. Folder mode settings


① Admin Account Setting


License Key
Activation





Admin Account


ID: gigaadmin
PW: 1qaz2wsx3E#
OTP:












① Admin Account Setting


License Key
Activation





Admin Account

ID: gigaadmin
PW: 1qaz2wsx3E#
OTP:









 **Initial Setup**

1

2

3

4

5



Initiate the Initial Setup for FilingBox GIGA Products

Start

 **Register License Key**

1

2

3

4

5

License type

☒ Cloud ☐ Internal verification module

License Key

Restart Initial Setup

Register

 **Register Server Name**

1

2

3

4

5

Server Name

[Rule] Length : 3 characters or more, 10 characters or less / Allowed characters : letters, numbers, spaces / First character : letters, numbers / Last character : letters, numbers

gigaserver

Restart Initial Setup

Register

**Register Administrator**

1 2 3 4 5

Administrator Name

[Rule] Length : 3 characters or more, 55 characters or less / Allowed characters : letters, numbers, spaces / First character : letters, numbers / Last character : letters, numbers

admin

Administrator ID

[Rule] Length : 3 characters or more, 32 characters or less / Allowed characters : lowercase letters, numbers, hyphens (-), underscores (_) / First character : lowercase letters, underscores (_) / Last character : lowercase letters, numbers

gigaadmin

Administrator Password

[Rule] Length : 8 characters or more, 30 characters or less / Allowed characters : letters, numbers, allowed special characters / Required characters : allowed special characters

* Allowed special characters : ~ ! @ # \$ % ^ * - _ = /

.....

Confirm Administrator Password

.....

Restart Initial Setup

Register

**Initialization Complete**

1 2 3 4 5

Server Name

gigaserver

Administrator Name

admin

Administrator ID

gigaadmin

Move to the Administrator Console Login Screen

 **Administrator Login**

Administrator ID

Administrator Password

Login

[한국어](#) | [English](#) | [日本語](#)

2-Factor Authentication Setup

After registering the 2-factor authentication account through a smartphone OTP app, enter the 6-digit OTP code generated in the app in the OTP code verification field below to set up 2-factor authentication.



If it's difficult to scan the QR code in the app, please manually enter the code below.

Y3CBQDDQO55VZG4Y
4XVEOWHVCQH7F7H

You need to rescan the QR code after refreshing the page.

Verify OTP Code

Setting

Cancel



admin ▼

Console

Usage Summary

User Management

Domain User Management

Admin Management

Usage Log

Personal Folder Management

Shared Folder Management

Group Management

Setting

Usage Summary

14.1 GB Free of 16.9 GB

Server Name : gigaserver

Server IP : 192.168.200.141

Shared folder usage : 0 Bytes

Total Accounts : 1

Existing license expiration date : 2026-03-01

Number of existing licensed users : 5

Storage capacity status : Disabled

Permission	Name	ID	Group ID	Drive Mode	Account Status	User Folder Usage	Two-Factor Authentication
Admin	admin	gigaadmin	-	Read-Only	Normal	-	Yes

1

FilingBox GIGA v1

 FILINGBOX GIGA

admin ▼

Console

Usage Summary

User Management

Domain User Management

Admin Management

Usage Log

Personal Folder Management

Shared Folder Management

Group Management

Setting

Group Management

Criteria

ID

Description

Reset

And ▼

ID

Description

Search

ID	Description	Modify	Delete
giga	Default Group	-	-

1

Group Add

FilingBox GIGA v1

FILINGBOX GIGA

admin ▼

Console

Usage Summary

User Management

Domain User Management

Admin Management

Usage Log

Personal Folder Management

Shared Folder Management

Group Management

Setting

Group Management

Criteria

And ▼

ID

giga

1

Description

Reset

Description

Search

Description	Modify	Delete
ult Group	-	-

Group Add

Group Add

* ID

[Rules] Length: 32 bytes or less / Allowed: lowercase letters, digits, underscores (_), hyphens (-) / First character: lowercase letters / Last character: lowercase letters, digits

test_group

Description

[Rules] Length: 100 bytes or less

This group is for testing

Check

Cancel

FILINGBOX GIGA

admin ▼

Console

Usage Summary

User Management

Domain User Management

Admin Management

Usage Log

Personal Folder Management

Shared Folder Management

Group Management

Setting

User Management

Criteria

Name

ID

Group ID

Drive Mode

Reset

And ▼

Name

ID

Select ▼

Select ▼

Search

Name	ID	Group ID	Drive Mode	Group ID Modify	Account Status	Reset Password	Delete Account
No search results.							

Add Account

FilingBox GIGA v1

FILINGBOX GIGA

admin ▼

Usage Summary

User Management

Domain User Management

Admin Management

Usage Log

Personal Folder Management

Shared Folder Management

Group Management

Setting

* Name

[Rules] Length: 3-55 characters / Allowed: letters, digits, spaces / First character: letters, digits / Last character: letters, digits

* ID

[Rules] Length: 3-32 characters / Allowed: lowercase letters, digits, hyphens (-), underscores (_) / First character: lowercase letters, underscores (_) / Last character: lowercase letters, digits

* Shared folder name prefix (s_) cannot be used.

* Group ID

giga ▼

* Password

[Rules] Length: 8-30 characters / Allowed: letters, digits, allowed special characters / Required: at least one allowed special character

* Allowed special characters: ~ ! @ # \$ % ^ * - _ = /

* Password Confirm

* Drive Mode

Read-Write ▼

* Required items

Add Account

Cancel

FilingCloud © All rights Reserved.

FILINGBOX GIGA

admin

Console

Usage Summary

User Management

Domain User Management

Admin Management

Usage Log

Personal Folder Management

Shared Folder Management

Group Management

Setting

User Management

Criteria

Name

ID

Group ID

Drive Mode

Reset

And

Name

ID

Select

Select

Search

Name	ID	Group ID	Drive Mode	Group ID Modify	Account Status	Reset Password	Delete Account
devuser01	devuser01	giga	☒ Read-Write ☐ Read-Only ☐ Add-Only ☐ List-Only ☐ WORM	Modify	Yes No	Reset	Delete

1

Add Account

FilingBox GIGA v1

FILINGBOX GIGA

admin

Console

Usage Summary

User Management

Domain User Management

Admin Management

Usage Log

Personal Folder Management

Shared Folder Management

Group Management

Setting

Shared Folder Management

Shared Folder

Trash

Shared

No data exists in the shared folder.

Add Shared Folder

* Shared Folder Name

[Rules] Length: 10 characters or less / Allowed: lowercase letters, digits

s_

rules

* Drive Mode

Read-Only

* Access Permission Setting

☒ All Share

☐ Group Share

* Required items

Create

▼  Shared

 s_rules

 s_project1

* Shared Folder Name

[Rules] Length: 10 characters or less / Allowed: lowercase letters, digits

s_

rules

* Drive Mode

Read-Only ▼

* Access Permission Setting

☒ All Share

☐ Group Share


* Required items

Change

Delete

Recovery Folder

Create



✓ Shared

Folder s_rules

Folder s_project1

* Drive Mode

Read-Write

* Access Permission Setting

☐ All Share

☒ Group Share

- Group

Group ID

Add

sales

* Required items

Change Delete

Recovery Folder

Create

Give Group Permission

- Select Group ID
- Click Add Button
- Check what you want to append
- Click Change Button

Name	ID	Group ID	Drive Mode	Group ID Modify	Account Status	Reset Password	Delete Account
devuser01	devuser01	giga	☒ Read-Write ☐ Read-Only ☐ Add-Only ☐ List-Only ☐ WORM	<button>Modify</button>	<button>Yes</button> <button>No</button>	<button>Reset</button>	<button>Delete</button>

1. Change Personal Folder Mode
-> Can be modified per account on the User Account Management page.

Shared

s_shared1

* Shared Folder Name

[Rules] Length: 10 characters or less / Allowed: lowercase letters, digits

s_

shared1

* Drive Mode

Read-Write

Drive Mode

Read-Write

Read-Only

Add-Only

List-Only

WORM

Hidden-Only

Recovery Folder

Create

2. Change Shared Folder Mode
-> Can be modified per folder on Shared Folder sub-tab under the Shared Folder Management.



VMware Installation and
Giga OVA Import

License Registration

Setting Administrator Page

Connect Network Drive

1. Access Personal Folder
2. Access Shared Folders



Windows Security

Enter network credentials

Enter your credentials to connect to: 192.168.205.135

Username

account1

Password

••••••••

☐ Remember my credentials

You can't access this shared folder because your organization's security policies block unauthenticated guest access. These policies help protect your PC from unsafe or malicious devices on the network.

OK

Cancel

Network locations

 account1 (\\192.168.205.135) (Z:)

14.5 GB free of 16.9 GB

←  Map Network Drive

What network folder would you like to map?

Specify the drive letter for the connection and the folder that you want to connect to:

Drive: Y: ▾

Folder: ▾

Browse...

Example: \\server\share


☐ Reconnect at sign-in

☐ Connect using different credentials

[Connect to a website that you can use to store your documents and pictures.](#)

Finish

Cancel



FAQ)

1. Changing the Giga Allocated Capacity of the Virtual Machine



Giga test

▶ Power on this virtual machine

🔗 Edit virtual machine settings

▼ Devices

Memory

4 GB

Processors

2

Hard Disk (NVMe)

20 GB

CD/DVD (IDE)

Auto detect

Network Adapter

Bridged (Autom...

USB Controller

Present

Sound Card

Auto detect

Display

Auto detect

▼ Description



FilingCloud © All rights Reserved.

Console

- Usage Summary.
- User Management
- Domain User Management
- Admin Management
- Usage Log
- Personal Folder Management
- Shared Folder Management
- Group Management
- Setting

Usage Summary

13.9 GB Free of 16.9 GB

Server Name : gigaserver

Server IP : 192.168.200.141

Shared folder usage : 0 Bytes


Total Accounts : 1

Existing license expiration date : 2026-03-01

Number of existing licensed users : 5

Storage capacity status : Disabled

Permission	Name	ID	Group ID	Drive Mode	Account Status	User Folder Usage	Two-Factor Authentication
Admin	admin	gigaadmin	-	Read-Only	Normal	-	Yes




```
[root@localhost ~]# lsblk -o NAME,TYPE,SIZE,FSTYPE,MOUNTPOINT
NAME        TYPE  SIZE FSTYPE  MOUNTPOINT
sr0          rom   1024M
nvme0n1      disk  40G
├─nvme0n1p1  part   1G xfs     /boot
├─nvme0n1p2  part  19G LVM2_member
│   └─rl-root lvm    17G xfs     /
│       └─rl-swap lvm    2G swap    [SWAP]
[root@localhost ~]# parted /dev/nvme0n1 resizepart 2 100%
Information: You may need to update /etc/fstab.

[root@localhost ~]# partprobe
[root@localhost ~]# pvresize /dev/nvme0n1p2
Physical volume "/dev/nvme0n1p2" changed
1 physical volume(s) resized or updated / 0 physical volume(s) not resized
[root@localhost ~]# lvextend -r -l +100%FREE /dev/mapper/rl-root
Size of logical volume rl/root changed from <17.00 GiB (4351 extents) to <37.00 GiB (9471 extents).
Logical volume rl/root successfully resized.
meta-data=/dev/mapper/rl-root  isize=512    agcount=4, agsize=1113856 blks
        =                       sectsz=512   attr=2, projid32bit=1
        =                       crc=1        finobt=1, sparse=1, rmapbt=0
        =                       reflink=1    bigtime=0 inobtcount=0
data      =                       bsize=4096   blocks=4455424, imaxpct=25
        =                       sunit=0      swidth=0 blks
naming    =version 2              bsize=4096   ascii-ci=0, ftype=1
log        =internal log          bsize=4096   blocks=2560, version=2
        =                       sectsz=512   sunit=0 blks, lazy-count=1
realtime  =none                  extsz=4096   blocks=0, rtextents=0
data blocks changed from 4455424 to 9698304
[root@localhost ~]# df -h /
Filesystem      Size  Used Avail Use% Mounted on
/dev/mapper/rl-root  37G  3.2G   34G   9% /
[root@localhost ~]#
[root@localhost ~]# systemctl restart giga.service
[root@localhost ~]#
```

Execute the following script:

1. Check the current disk layout

su -

lsblk -o NAME,TYPE,SIZE,FSTYPE,MOUNTPOINT

2. Extend the partition to use the free space

(Ex: when partition 2 is an LVM2_member)

parted /dev/nvme0n1 resizepart 2 100%

partprobe

3. Resize the LVM **PV***

pvresize /dev/nvme0n1p2

4. Extend the root **LV**** and filesystem

lvextend -r -l +100%FREE /dev/mapper/rl-root

5. Verify the result

df -h /

6. Restart the GIGA service

systemctl restart giga.service

PV* : Physical Volume

LV : Logical Volume**

Console

- Usage Summary
- User Management
- Domain User Management
- Admin Management
- Usage Log
- Personal Folder Management
- Shared Folder Management
- Group Management
- Setting

Usage Summary

33.8 GB Free of 36.9 GB

Server Name : gigaserver

Server IP : 192.168.200.141

Shared folder usage : 0 Bytes

Total Accounts : 1


Existing license expiration date : 2026-03-01

Number of existing licensed users : 5

Storage capacity status : Disabled

Permission	Name	ID	Group ID	Drive Mode	Account Status	User Folder Usage	Two-Factor Authentication
Admin	admin	gigaadmin	-	Read-Only	Normal	-	Yes

1



*Caution

VMware does **not provide** a method to **reduce disk** capacity.

If a capacity smaller than the current size.
(e.g., 20 GB when the current capacity is 40 GB) is specified, the button will be disabled, as shown on the screen.

Thank you

