Electrodynamics

Joshua

Contents Introduction 4 **Basic Electrostatics** 4 2.1 5 2.2 6 2.3 2.4 7 2.5 2.6 2.7 2.8 11 2.9 12 **Potentials** 13 3.1 13 3.2 14 3.3 14 3.4

4	Ele	ctric Fields in Matter	17		
	4.1	Dipoles	17		
	4.2	Polarization	18		
	4.3	Electric Displacement Field D	19		
	4.4	Dielectrics	20		
5	Magnetostatics				
	5.1	Lorentz Law	22		
	5.2	Biot-Savart Law	24		
	5.3	Ampere's Law	24		
	5.4	Magnetic Vector Potential	25		
	5.5	Boundary Conditions	26		
	5.6	Multipole Expansion	27		
6	Magnetic Fields in Matter 2				
	6.1	Dipoles	28		
	6.2	Magnetization	29		
	6.3	Auxillary Field H	29		
	6.4	Effects of Media	30		
7	Electrodynamics 3				
	7.1	Ohm's Law	31		
	7.2	Faraday's Law	32		
	7.3	Inductance	34		
	7.4	Maxwell's Equations	36		
	1.1	Training Equations	00		

	8.1	Conservation of Energy	38
	8.2	Conservation of Momentum	39
9	Elec	tromagnetic Waves	41
	9.1	Electromagnetic Waves in Vacuum	41
	9.2	Reflection and Transmission of EM Waves	43
	9.3	Absorption and Dispersion of Electromagnetic Waves	45
	9.4	Frequency Dependence of Permittivity	47
	9.5	Guided Waves	49
10	Pote	entials and Fields	51
	10.1	Gauge Transformations	51
	10.2	Retarded Potentials	53
	10.3	Point Charges	54
11	Elec	trodynamics and Relativity	55
	11.1	How the Fields Transform	56
	11.2	Tensor Formulation of Electrodynamics	57
12	Rad	iation	59
	12.1	Dipole Radiation	60
	12.2	Magnetic Dipole Radiations	62
	12.3	Radiation from an Arbitrary Source	64
	12.4	Radiation from Point Charges	66
	12.5	Radiation Reaction	67

1. Introduction

I used Griffith's fourth edition of introduction to electrodynamics to generate this set of notes [1]. I choose this book because I used Griffiths for my undergraduate course. We used the newer version, but this is the one I have a copy of with me.

My next plan is to continue writing notes for other electrodynamics books such as Jackson which I will use this next semester. I would like to note that in my book it seems that radiation and potential and fields chapters were switched. I switched that in this current set of notes.

I skipped explaining mathematics because I want to write a completely separate set of notes on that later. I also skipped the intro to relativity because I believe that also belongs in a different set of notes.

The one of the main notations that I differ from Griffiths on is the symbol for the scalar potential. I use ϕ , while he uses V. I looked at Jackson and he uses Φ , while Pauli uses ψ . It seems there is no strict standard for the variable.

I think what these notes are mainly lacking at the current time are figures, examples, and derivations. I will try to introduce each of these things over time. I hope everyone can benefit from what I have done here so far though. Good luck reading!

2. Basic Electrostatics

In electrostatics we have some bread and butter equations. First there will be Coulomb's law which will allow us to do the basic problems involving point charges. The next big equations we will run into is Gauss's law,

Laplace's equation, and Poisson's equation. From there we will try to establish boundary conditions as well as explore work and energy for electrostatics. We will end this chapter off which talk about some rudimentary discussion of conductors and capacitors.

2.1. Coulomb's Law

The basic approach to electrostatics involves Coulomb's law,

$$\mathbf{F} = \frac{1}{4\pi\epsilon_0} \frac{qQ}{v^2} \hat{\boldsymbol{\lambda}}.\tag{1}$$

This approach deals with source charges, which are point like objects that carry some charge, q. ϵ_0 is the permittivity of free space, equal to $8.85 \times 10^{-12} \, C^2/(N \cdot m^2)$. This equation is more or less postulating and then checked via experiment. Lets use this as one of our postulates of electrostatics. Once we move to electrodynamics this can be derived from Maxwell's equations. Because this equation is linear with respect to q or Q, then the law of superposition can be used when calculating out the total force on a particular charge.

Another fundamental equation of electrostatics is the definition of the electric field,

$$\mathbf{F} \equiv q\mathbf{E}.\tag{2}$$

So combining what we have so far, the electric field for electrostatics is equal to,

$$\mathbf{E}(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \sum_{i=1}^n \frac{q_i}{2^i} \hat{\mathbf{z}}$$
 (3)

This equation can be useful for a small amount of charges, or some very symmetrical cases but for a lot of what is done in electrostatics, you will be facing continuous charge distributions rather than this discrete form.

2.2. Continuous Charge Distributions

To deal with continuous charge distributions we have to switch out the summation for an integral and what we are left with is,

$$\mathbf{E}(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int \frac{1}{2} \hat{\boldsymbol{\lambda}} \, dq. \tag{4}$$

That dq though can be a tricky thing to establish. Instead we would normally know what the charges are evenly distributed, and given what the distribution is. For one dimensional case you will be given the linear charge distribution λ , for two dimensions the surface charge density σ , and for three dimensions the volume charge density ρ . Writing these in terms of differentials,

$$dq = \frac{dq}{d\ell}d\ell = \lambda d\ell,$$

$$dq = \frac{dq}{da}da = \sigma da,$$

$$dq = \frac{dq}{d\tau}d\tau = \rho d\tau.$$
(5)

An example, is if you have a long wire, the electric field produced by it would be equal to,

$$\mathbf{E}(z) = \frac{1}{4\pi\epsilon_0} \frac{2\lambda}{z} \hat{\mathbf{z}}.\tag{6}$$

The equations for a sphere and plane will be worked out by me later and added.

2.3. Gauss's Law

One of the staples of the theory of electrodynamics is Gauss's law which relates the Electric flux to the enclosed charge. Electric flux is defined by

$$\Phi_E \equiv \int_S \mathbf{E} \cdot d\mathbf{a}.\tag{7}$$

Gauss's law states that the electric flux is related to the charge enclosed by

$$\oint \mathbf{E} \cdot d\mathbf{a} = \frac{Q_{enc}}{\epsilon_0}.$$
(8)

From this integral equation we can derive a differential equation,

$$\nabla \cdot \mathbf{E} = \frac{\rho}{\epsilon_0},\tag{9}$$

which is also called Gauss's law.

Useful results that can be calculated from Gauss's law are uniformly charged symmetrical objects. The electric field for a uniformly charged sphere is,

$$\mathbf{E} = \frac{1}{4\pi\epsilon_0} \frac{q}{r^2} \hat{\mathbf{r}}.\tag{10}$$

For a uniformly charged plane the electric field is,

$$\mathbf{E} = \frac{\sigma}{2\epsilon_0} \hat{\mathbf{n}}.\tag{11}$$

2.4. Conservative Force

Faraday's law states that for electrostatics, the electric force is conservative. In differential form this means that

$$\nabla \times \mathbf{E} = 0, \tag{12}$$

and in integral form,

$$\oint \mathbf{E} \cdot d\mathbf{l} = 0.$$
(13)

I would like to note that this does not hold for electrodynamics though which will be covered later. Because the electric field is a conservative force we can define a potential to be,

$$\mathbf{E} \equiv -\nabla \phi,\tag{14}$$

where ϕ is the electric potential or scalar potential. This potential is sometimes denoted by V instead of ϕ such as in Griffith's textbook.

The integral form of this is

$$\phi(\mathbf{r}) = -\int_{O}^{r} \mathbf{E} \cdot d\boldsymbol{\ell}. \tag{15}$$

Where O is some reference point. O is normally where one defines the zero of the potential and is frequently at infinity. A case where this does not apply is the uniform plane where the electric field is not zero at infinity.

2.5. Laplace and Poisson Equations

To try and simplify some problems, we will want to work with the potential rather than the electric field. To do so we need to convert Faraday's law and Gauss's law to be with respect to the electric potential. Taking Gauss's law and putting it in terms of the potential results in

$$\nabla^2 \phi = -\frac{\rho}{\epsilon_0}.\tag{16}$$

This is known as Poisson's equation, and when there exists no source charges then $\rho = 0$ and we get Laplace's equation,

$$\nabla^2 \phi = 0. \tag{17}$$

But what happens if we plug the potential into Faraday's law. What results is essentially a tautology because the curl of a gradient is zero. Therefore we only need a single equation to determine all of the physics rather than two.

Since the potential is useful quantity, we should have equations that allow us to solve for it that do not depend on the electric field. Taking the equation for a continuous charge distribution in three dimensions and substituting in the definition of the potential results in

$$\phi(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \int \frac{\rho(\mathbf{r'})}{\imath} d\tau'. \tag{18}$$

Sometimes it is quicker to derive the potential using this equation and then the field from that rather than jumping to the field directly.

2.6. Boundary Conditions

Electric fields always have a jump discontinuity at surface charges. How much the electric field changes depends on what component you are looking at. For the perpendicular component

$$E_{above}^{\perp} - E_{below}^{\perp} = \frac{\sigma}{\epsilon_0},\tag{19}$$

and for the parallel component,

$$E_{above}^{\parallel} = E_{below}^{\parallel}. \tag{20}$$

The potential on the other hand does not have jump discontinuities because if it did then the electric field would be infinite at that point. Instead we can use our definition of the potential and put it into the equation that has the discontinuity to get back

$$\frac{\partial \phi_{above}}{\partial n} - \frac{\partial \phi_{below}}{\partial =} - \frac{\sigma}{\epsilon_0}.$$
 (21)

I have used the notation of a normal derivative without explaining it yet. The $\frac{\partial \phi}{\partial n}$ is a normal derivative and is defined as such

$$\frac{\partial \phi}{\partial n} = \nabla \phi \cdot \hat{\mathbf{n}},\tag{22}$$

where \hat{n} is the normal to the boundary.

2.7. Work and Energy

The work it takes to move a charge from point a to point b is given by can be derived from the definition of work which is,

$$W \equiv \int_{a}^{b} \mathbf{F} \cdot d\boldsymbol{\ell}.$$
 (23)

Taking it from there and substituting the previous discussions ideas results in

$$W = q[\phi(\mathbf{b}) - \phi(\mathbf{a})] \tag{24}$$

Now let b be an arbitrary vector \mathbf{r} and let a be the reference point for where the potential is equal to zero. Then the work function takes on a different meaning and is just the potential energy of the system. Algebraically this means,

$$U = q\phi(\mathbf{r}),\tag{25}$$

where U is the potential energy of the system of this single particle. For a collection of particles the potential energy is

$$U = \frac{1}{2} \sum_{i=1}^{n} q_i \phi(\mathbf{r}_i). \tag{26}$$

The half comes from the fact that the sum double counts every interaction.

But so far all of this has been for discrete systems. What if we are dealing with the much more realistic continuous systems? Well through some mathematical manipulation the equation becomes

$$U = \frac{\epsilon_0}{2} \int E^2 d\tau, \tag{27}$$

where the bounds of integration are all of space.

2.8. Conductors

In insulators electrons must stay with their respective atoms while in conductors the electrons are free to move about. Dielectric is just another name for an insulator. Most everyday materials are either conductors or insulators.

Some of the useful properties of a conductor are that the electric field inside a conductor is zero. This means that the charge density is also zero and the potential is some constant. More useful properties are that all the charge resides on the surface and the surface is equipotential. Lastly because of the boundary conditions, the electric field just outside a conductor must be perpendicular to the conductor's surface.

An example of applying these principles would be for a neutral conductor that has a cavity in the middle of it. Then since it is neutral, any charge that's in the cavity must have an equal and opposite charge on the outside shell of the conductor due to Gauss's law. From this you could calculate the electric field outside the conductor, or even within the cavity.

Surface charges on a conductor will experience a force equal to

$$\mathbf{f} = \frac{\sigma^2}{2\epsilon_0} \hat{\mathbf{n}}.\tag{28}$$

Therefore there is an outward electrostatic pressure on the pressure equal to

$$P = \frac{\epsilon_0}{2}E^2 \tag{29}$$

2.9. Capacitors

Capacitance is defined to be

$$C \equiv \frac{Q}{\phi},\tag{30}$$

and is measured in farads. This quantity is a purely geometrical one. For a parallel-plate capacitor, each of area A and distance d apart, the voltage

$$\phi = \frac{Q}{A\epsilon_0}d,\tag{31}$$

and thus the capacitance is,

$$C = \frac{A\epsilon_0}{d}. (32)$$

What is the capacitance for two concentric spherical metal shells, with radii a and b is another example that is somewhat frequent. For this it can be found that

$$C = 4\pi\epsilon_0 \left(\frac{ab}{b-a}\right). \tag{33}$$

Another thing important for capacitors is the energy stored in one. The work to charge up a capacitor is

$$W = \frac{1}{2}C\phi^2 \tag{34}$$

3. Potentials

The main discussion of this chapter is Laplace's equation. From exploiting the uniqueness of the PDE we will then find a way of finding a solution using the method of images. To end off we will explore multipole expansion and how we can use that to simplify some problems.

3.1. Laplace's Equation

Solutions to the Laplace equation come in the form of harmonic functions. For one dimension the general solution is simply

$$\phi(x) = mx + b \tag{35}$$

Properties of the one dimensional case that generalize to the two and three dimensional case are,

$$\phi(x) = \frac{1}{2} [\phi(x+a) + \phi(x-a)], \tag{36}$$

and the solutions have no local maxima or minima; the extrema occur at the end points.

Earnshaw's Theorem states that a charged particles cannot be held in a stable equilibrium by electrostatic forces alone.

3.2. Boundary Conditions

You need boundary conditions to fully specify the solution to Laplace's equation. First uniqueness theorem states that the solution to Laplace's equation in some volume V is uniquely determined if ϕ is specified on the boundary surface S. Therefore the potential in a volume V is uniquely determined if the charge density throughout the region and the value of ϕ on all boundaries is specified. The second uniqueness theorem states that in a volume V surrounded by conductors and containing a specified charge density ρ , the electric field is uniquely determined if the total charge on each conductor is given.

3.3. Method of Images

Because of the uniqueness theorems we can devise a clever way to solve some problems that have a symmetry about them. If we are given some boundary conditions for ϕ , usually involving some long grounded planes. By putting opposite charged charges in the correct locations, you can get the same boundary value problem. From the uniqueness theorem, the solutions

to the two different problems must be the same. Therefore you just solve the simpler case with Coulomb's law and call it groovy.

For the example of a single charge +q that is located a distance d above an infinite grounded plane,

$$\phi(x,y,z) = \frac{1}{4\pi\epsilon_0} \left(\frac{q}{\sqrt{x^2 + y^2 + (z-d)^2}} + \frac{-q}{\sqrt{x^2 + y^2 + (z+d)^2}} \right). \tag{37}$$

From here you can derive the induced charge distribution σ , which comes out to be

$$\sigma(x,y) = \frac{-qd}{2\pi(x^2 + y^2 + d^2)^{\frac{3}{2}}}$$
(38)

and thus the total induced charge must be -q. Note that the force can also be calculated from the method of images BUT you can not use the method of images to calculate the energy of the problem. For this problem the energy stored would only be half of the image problem,

$$U = -\frac{1}{4\pi\epsilon_0} \frac{q^2}{4d} \tag{39}$$

3.4. Multipole Expansion

What is the potential for some $\rho \neq 0$ but $Q_{enc} = 0$? Well For cases of multipoles, and for the time being, dipoles, we can calculate it using the multipole expansion. To lay out the problem, what is the potential far away from two equal and opposite charges which are separated at a distance d from each other?

To start out with you would take the explicit formula for the potential would be

$$\phi(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \left(\frac{q}{\mathbf{r}_+} + \frac{-q}{\mathbf{r}_-} \right). \tag{40}$$

The next step is to expand out the r_{\pm} .

$$\iota_{+} = r^2 + (d/2)^2 \mp rd\cos\theta.$$
(41)

By using Taylor expansions and other basic approximation techniques you should end up at

$$\phi(\mathbf{r}) \cong \frac{1}{4\pi\epsilon_0} \frac{qd\cos\theta}{r^2} \tag{42}$$

A trick to see if your calculation is trick to see if your solution is correct, the potential should fall of like $\frac{1}{r^{n+1}}$ where n is the power of your pole. So for a hexadecapole, which is 2^4 pole, then should fall off like $\frac{1}{r^5}$.

The general equation for the multipole expansion is

$$\phi(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \sum_{n=0}^{\infty} \frac{1}{r^{n+1}} \int (r')^n P_n(\cos\alpha) \rho(\mathbf{r}') d\tau'. \tag{43}$$

Explicitly writing out the monopole and dipole terms,

$$\phi_{mon}(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \frac{Q}{r},\tag{44}$$

and,

$$\phi_{dip}(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \frac{\hat{\mathbf{r}}}{r^2} \cdot \int \mathbf{r'} \rho(\mathbf{r'}) d\tau'. \tag{45}$$

In the dipole term, the integral is called the dipole moment, and is defined

as

$$\mathbf{p} \equiv \int \mathbf{r'} \rho(\mathbf{r'}) d\tau'. \tag{46}$$

Using this definition we can rewrite the dipole's contribution as

$$\phi_{dip}(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \frac{\mathbf{p} \cdot \hat{\mathbf{r}}}{r^2}.$$
 (47)

Note that for physical dipoles, $\mathbf{p} = q\mathbf{d}$ where \mathbf{d} is the separation vector between the positive and negative points.

4. Electric Fields in Matter

The main focus of this section is establishing what happens to bulk materials when you introduce an external electric field. We will delve into polarization to start with which will lead into a discussion of the electric displacement field. We will end this chapter on a discussion of dielectrics.

4.1. Dipoles

When a neutral object such as an atom in placed into an electric field, the electrons are pushed in one direction while the nucleus is pulled in the opposite. Even though the overall charge is neutral, the atom now becomes a dipole. This is what we mean when we say an electric field induces a dipole. When this happens we say the atom is polarized. If the field is not too strong the dipole moment is proportional to the field,

$$\mathbf{p} = \alpha \mathbf{E}.\tag{48}$$

The proportionality constant α is called the atomic polarizability, which is a measured quantity. For a more general case, α is not a scalar but actually a tensor called the polarizability tensor.

What about for polar molecules? Well if a molecule already has some polarization \mathbf{p} then it will experience a torque when placed inside the external electric field. This torque is equal to

$$\mathbf{N} = \mathbf{p} \times \mathbf{E}.\tag{49}$$

This torque forces \mathbf{p} to be in the same direction as \mathbf{E} . If the field is not uniform there exists a net force on the object equal to

$$\mathbf{F} = (\mathbf{p} \cdot \nabla)\mathbf{E}.\tag{50}$$

The energy of an ideal dipole in an external electric field is

$$U = -\mathbf{p} \cdot \mathbf{E}.\tag{51}$$

4.2. Polarization

So if you put a dielectric material in an electric field, what will happen is that each molecule in the material will become polarized with a polarization **p**. When examining the bulk material it is easier to look at the dipole moment per unit volume, **P**, or polarization.

To answer the question of what type of field this produces, we need to define a surface charge density and a volume charge density. Let the surface charge density be defined as

$$\sigma_b \equiv \mathbf{P} \cdot \hat{\mathbf{n}},\tag{52}$$

and the volume charge density defined as,

$$\rho_b \equiv -\nabla \cdot \mathbf{P}.\tag{53}$$

Using these definitions, and the formula for the potential defined earlier, you can derive

$$\phi(\mathbf{r}) = \frac{1}{4\pi\epsilon_0} \oint_S \frac{\sigma_b}{\imath} da' + \frac{1}{4\pi\epsilon_0} \int_{\nu} \frac{\rho_b}{\imath} d\tau'.$$
 (54)

So to calculate the potential, and thus the electric field, all one needs to do is examine what happens to the bound charges. What is a bound charge though? Is it math or a physical reality. Well as Griffiths puts it, "there is nothing further from the truth" than viewing these bound charges as mathematical constructs. It is called bound charges because they can not be removed from their source unlike a metal. They are a bulk feature, of many dipoles cancelling each other out and just looking at what the overall effect is.

4.3. Electric Displacement Field D

So now we want to examine how the field due to bound charges interacts with everything else. We shall attribute the name free charge, or ρ_f so the "everything else." From how we defined free charge we can use that definition to say

$$\rho = \rho_b + \rho_f. \tag{55}$$

Now incorporating this definition into Gauss's law leads to

$$\epsilon_0 \nabla \cdot \mathbf{E} = -\nabla \cdot \mathbf{P} + \rho_f \tag{56}$$

Defining a new variable, the electric displacement,

$$\mathbf{D} \equiv \epsilon_0 \mathbf{E} + \mathbf{P},\tag{57}$$

then allows us to rearrange the equation to be,

$$\nabla \cdot \mathbf{D} = \rho_f. \tag{58}$$

The integral form of this is

$$\oint \mathbf{D} \cdot d\mathbf{a} = Q_{f_{enc}} \tag{59}$$

Boundary conditions for the electric displace are as follows,

$$D_{above}^{\perp} - D_{below}^{\perp} = \sigma_f \tag{60}$$

$$\mathbf{D}_{above}^{\parallel} - \mathbf{D}_{below}^{\parallel} = \mathbf{P}_{above}^{\parallel} - \mathbf{P}_{below}^{\parallel}. \tag{61}$$

4.4. Dielectrics

Just like in the atomic case, when an electric field, which is not too strong, is applied to some materials, then the polarization is proportional to the field,

$$\mathbf{P} = \epsilon_0 \chi_e \mathbf{E}. \tag{62}$$

The new proportionality constant χ_e is called the electric susceptibility, and if a material obeys this equation it is called a linear dielectric. If we were to convert the equation for electric displacement with this equation, then we would derive

$$\mathbf{D} = \epsilon_0 (1 + \chi_e) \mathbf{E} = \epsilon \mathbf{E}. \tag{63}$$

This new constant of proportionality, ϵ , is called the permittivity of the material. From this we can define can also define a new variable, the relative permittivity (or dielectric constant),

$$\epsilon_r \equiv 1 + \chi_e = \frac{\epsilon}{\epsilon_0} \tag{64}$$

If the space is entirely filled with a homogeneous linear dielectric then this simplifies a lot of our problems because now electric displacement would be irrotational. In general though, dielectrics are not isotropic. In the general case, χ_e is actually a tensor called the susceptibility tensor.

For homogeneous linear isotropic materials, the bound charge density can be related to the free charge density by

$$\rho_b = -\frac{\chi_e}{1 + \chi_e} \rho_f \tag{65}$$

To compute the energy in a dielectric system, applying the definitions applied above, simplifies the equation down to

$$U = \frac{1}{2} \int \mathbf{D} \cdot \mathbf{E} \ d\tau. \tag{66}$$

This equation ONLY works for linear homogeneous isotropic dielectrics though.

For the special case of a finite parallel plate capacitor, with separation d, and width w, the force felt on the dielectric by the fringing fields is equal to

$$F = -\frac{\epsilon_0 \chi_e w}{2d} \phi \tag{67}$$

5. Magnetostatics

Finally we are going to move onto magnetism. I will try to harken back to the concepts established for electrostatics throughout the chapter. We will establish the Lorentz force law and then groove on into the Biot-Savart law. Following this discussion we will be able to establish Ampere's law for magnetostatics. Afterwards we will explore the magnetic potential. We will end this chapter talking about boundary conditions and multipole expansion.

5.1. Lorentz Law

For electrostatics we required stationary charges, and for magnetostatics we will require steady currents.. The fundamental force law of magnetostatics is called the Lorentz force law. This law was experimentally found so I will write it as a definition,

$$\mathbf{F}_{mag} \equiv q(\mathbf{v} \times \mathbf{B}). \tag{68}$$

Combining this with the definition of the electric field results in the full electrodynamics force equation,

$$\mathbf{F} = q(\mathbf{E} + \mathbf{v} \times \mathbf{B}). \tag{69}$$

The v in this equation is the velocity of the particle moving. I guess I should say now that the "magnetic forces do no work" just to go ahead and get that out of the way. Since they do no work, the motion of a particle under just a magnetic force is a circle. Thus using equation the magnetic force to the centripetal force you can get the cyclotron formula,

$$B = \frac{mv}{qR}. (70)$$

The cyclotron frequency is thus

$$\omega = \frac{QB}{m}.\tag{71}$$

Another way of rewriting the Lorentz law in terms of current

$$\mathbf{F}_{mag} = I\boldsymbol{\ell} \times \mathbf{B}.\tag{72}$$

Instead of just talking about one dimensional currents, there are two dimensional surface currents, and three dimensional volume currents. For two dimensional currents we define them as

$$\mathbf{K} \equiv \frac{d\mathbf{I}}{d\ell_{\perp}} = \sigma \mathbf{v},\tag{73}$$

and for three dimensional currents,

$$\mathbf{J} \equiv \frac{d\mathbf{I}}{da_{\perp}} = \rho \mathbf{v}.\tag{74}$$

The continuity equation stemming from charge conservation is

$$\nabla \cdot \mathbf{J} = -\frac{\partial \rho}{\partial t}.\tag{75}$$

5.2. Biot-Savart Law

The Biot-Savart law is

$$\mathbf{B}(\mathbf{r}) = \frac{\mu_0}{4\pi} \int \frac{\mathbf{I} \times \hat{\boldsymbol{\lambda}}}{\boldsymbol{z}^2} d\ell' = \frac{\mu_0}{4\pi} I \int \frac{d\boldsymbol{\ell} \times \hat{\boldsymbol{\lambda}}}{\boldsymbol{z}^2}.$$
 (76)

Here I have introduced a new constant, μ_0 , which is called the permeability of free space. Unless you are trying to be more precise than 10^{-16} , you can simply use $\mu_0 = 4\pi \times 10^{-7} H/m$.

An example of using this would be finding the magnetic field a distance s from a long straight wire that has a current I. The magnetic field is then,

$$\mathbf{B} = \frac{\mu_0 I}{2\pi s} \hat{\boldsymbol{\phi}}.\tag{77}$$

Another common example is to find the magnetic field a distance z above the center of a circular loop of radius R, carrying a steady current I. In this case the magnetic field is

$$\mathbf{B}(\mathbf{z}) = \frac{\mu_0 I}{2} \frac{R^2}{(R^2 + z^2)^{\frac{3}{2}}} \hat{\mathbf{z}}.$$
 (78)

5.3. Ampere's Law

So we have arrived at another of Maxwell's equations, Ampere's law. Maxwell will add a correction to this equation later on but in the magnetostatics case Ampere's law works just fine. Ampere's law is analogous to Gauss's law for magnetostatics. Written in integral form it is,

$$\oint \mathbf{B} \cdot d\mathbf{l} = \mu_0 I_{enc}, \tag{79}$$

while written in differential form is,

$$\nabla \times \mathbf{B} = \mu_0 \mathbf{J}. \tag{80}$$

Like Gaussian surfaces, these one dimensional loops are called Amperian loops. This is one of the staples of magnetostatics to be able to calculate the magnetic field due to some current.

Now the divergence of the magnetic field is fairly simple, simpler in fact than the electrostatics case. This is also one of Maxwell's equations, and is

$$\nabla \cdot \mathbf{B} = 0. \tag{81}$$

All this is saying is that in nature, there does not exist magnetic point charges, i.e. magnetic monopoles.

5.4. Magnetic Vector Potential

For electrostatics we took advantage of the fact that $\nabla \times \mathbf{E} = 0$ to define a scalar potential. Now for magnetostatics we will take advantage of $\nabla \cdot \mathbf{B} = 0$ to define a vector potential. vector calculus identities allow us to define a vector such that,

$$\mathbf{B} = \nabla \times \mathbf{A}.\tag{82}$$

One of the features of this vector potential is that we can define it in such a way that it is divergenceless. Now this is picking a particular gauge is called the Coulomb gauge, or radiation gauge. What is this gauge I'm referencing? Well a gauge is just a systematic way to set a fixed point in a potential, usually the zero. There are other gauges, such as the Lorenz gauge which can be useful for relativistic problems that we will explore later. Converting

some of the previous equations into forms dependent on the vector potential we get,

$$\nabla^2 \mathbf{A} = -\mu_0 \mathbf{J},\tag{83}$$

and,

$$\mathbf{A}(\mathbf{r}) = \frac{\mu_0}{4\pi} \int \frac{\mathbf{J}(\mathbf{r}')}{\imath} d\tau'. \tag{84}$$

5.5. Boundary Conditions

Just like for electrostatics we have some boundary conditions for the magnetic field at boundaries. Very creative wording there. Anyways,

$$B_{above}^{\perp} = B_{below}^{\perp} \tag{85}$$

is the boundary condition for the perpendicular component of the magnetic field. Note that this is analogous to the boundary condition for the parallel portion of the electric field. For the parallel portion of the magnetic field,

$$B_{above}^{\parallel} - B_{below}^{\parallel} = \mu_0 K. \tag{86}$$

This reminds me of the perpendicular portion of the electric field! The boundary conditions for the magnetic and electric fields essentially flipped versions of each other. To combine the magnetic field boundary equations into a single vector equation

$$\mathbf{B}_{above} - \mathbf{B}_{below} = \mu_0(\mathbf{K} \times \hat{\mathbf{n}}). \tag{87}$$

5.6. Multipole Expansion

Harking back to electrostatics again, the magnetic vector potential can be written in terms of a multipole expansion. To show what it looks like

$$\mathbf{A}(\mathbf{r}) = \frac{\mu_0}{4\pi} I \sum_{n=0}^{\infty} \frac{1}{r^{n+1}} \oint (r')^n P_n(\cos \alpha) d\ell'. \tag{88}$$

Now something to note is that THERE IS NO MAGNETIC MONOPOLE as we stated earlier thus the first term always vanishes. So the first non-vanishing term is the dipole term which is

$$\mathbf{A}_{dip}(\mathbf{r}) = \frac{\mu_0}{4\pi} \frac{\mathbf{m} \times \hat{\mathbf{r}}}{r^2},\tag{89}$$

where \mathbf{m} is the magnetic dipole moment, which is defined to be

$$\mathbf{m} \equiv I\mathbf{a}.\tag{90}$$

a is the vector area of the loop, which for most simple cases is $a\hat{\mathbf{n}}$. From this we can derive what the magnetic field due to a dipole must be

$$\mathbf{B}_{dip}(\mathbf{r}) = \frac{\mu_0}{4\pi} \frac{1}{r^3} [3(\mathbf{m} \cdot \hat{r})\hat{r} - \mathbf{m}]. \tag{91}$$

6. Magnetic Fields in Matter

This section will follow the same formula as electric fields in matter. We will first discuss magnetic dipoles and move into magnetization. From there we can jive on into the magnetic auxiliary field. We will end this chapter talking about effects of media.

6.1. Dipoles

What do we mean when we call something magnetized? This is just lay speak for saying something is magnetically polarized. There are three main types of ways an object can be magnetized. First there are paramagnets which have a magnetization in the same direction of **B**, diamagnets which are in the opposite direction of **B**, and ferromagnets whose direction is based off the history of magnetic fields that have been applied over time, not just the current one.

All of these stem from the electrons moving around atoms, creating magnetic dipoles. Each of these dipoles has a magnetic dipole moment **m** and just like for electric dipoles the torque on one of these is

$$\mathbf{N} = \mathbf{m} \times \mathbf{B}.\tag{92}$$

Also similarly the force on a magnetic dipole in a inhomogeneous magnetic field is

$$\mathbf{F} = \nabla(\mathbf{m} \cdot \mathbf{B}). \tag{93}$$

If you apply these equations to an atom, then carrying through the calculations you end up with **m** being in the opposite direction of **B**. This is what is responsible for diamagnetism. This effect is much weaker than paramagnetism, but is present in all materials. So when paramagnetism is not present, usually with atoms with an even number of electrons, diamagnetism is the leading order effect.

6.2. Magnetization

Another analogous term to the study of electric fields is when we talk about bulk magnetization. For electrostatics there is \mathbf{P} , and for magnetostatics there is \mathbf{M} which is the magnetic dipole moment per unit volume, and is called the magnetization. Now using this definition in the equation for the vector potential from atomic magnetizations, we can define bound currents just like we defined bound charges.

$$\mathbf{J}_b \equiv \nabla \times \mathbf{M},\tag{94}$$

is a bound volume current while

$$\mathbf{K}_b \equiv \mathbf{M} \times \hat{\mathbf{n}},\tag{95}$$

is a bound surface current. From this the equation for the vector potential becomes

$$\mathbf{A}(\mathbf{r}) = \frac{\mu_0}{4\pi} \int_V \frac{\mathbf{J}_b(\mathbf{r}')}{\imath} d\tau' + \frac{\mu_0}{4\pi} \oint_S \frac{\mathbf{K}_b(\mathbf{r}')}{\imath} da'. \tag{96}$$

6.3. Auxillary Field H

Just like in electrostatics there is a secondary field that takes account for the magnetization of the material. For magnetostatics this field is called the auxillary field and is denoted by **H**. Following the same derivation that was done for electrostatics we will split up the current into the bound and free portions,

$$\mathbf{J} = \mathbf{J}_b + \mathbf{J}_f. \tag{97}$$

Then using the definition of \mathbf{J}_b we used earlier and solving for \mathbf{J}_f we arrive at

$$\nabla \times \left(\frac{1}{\mu_0} \mathbf{B} - \mathbf{M}\right) = \mathbf{J}_f. \tag{98}$$

Now we can use this to define the auxillary field,

$$\mathbf{H} \equiv \frac{1}{\mu_0} \mathbf{B} - \mathbf{M}.\tag{99}$$

Thus the differential form of Ampere's law in terms of the auxillary field is

$$\nabla \times \mathbf{H} = \mathbf{J}_f, \tag{100}$$

and the integral form is

$$\oint \mathbf{H} \cdot d\boldsymbol{\ell} = I_{f_{enc}}.$$
(101)

6.4. Effects of Media

For electrostatics we had a name for this, namely the dielectric. Magnetization does not have a good name for the effect of the actual material. What we can talk about though is the property the material changes, which is the magnetic susceptibility and permeability. Just like before, for fields that are not strong, most materials behave in a linear fashion. Unlike in electrostatics we will define the magnetic susceptibility through the auxiliary field,

$$\mathbf{M} = \chi_m \mathbf{H}. \tag{102}$$

 χ_m is called the magnetic susceptibility. Just like in electrostatics though we can define a new constant μ such that

$$\mu \equiv \mu_0 (1 + \chi_m),\tag{103}$$

and we will call it the permeability of the material. We can thus draw the parallel to bound volume charge being proportional to free volume current through the equation

$$\mathbf{J}_b = \chi_m \mathbf{J}_f. \tag{104}$$

7. Electrodynamics

Everything we have done so far has consisted of either static charges or steady currents. What if this is not the case though? Well an interesting phenomena arises that allows us to combine the theory of the electricity and magnetism into one, electromagnetism. This is where the fun begins! We will start with a generalization of Ohm's law, and then move onto Faraday's law for dynamical cases. We will end this section finally establishing Maxwell's equations.

7.1. Ohm's Law

So from beginner electromagnetism courses, there is the familiar Ohm's law

$$V = IR. (105)$$

But how does this fit into the vector formalism that we have been using so far? Well, that formula stems from the more general formula

$$\mathbf{J} = \sigma \mathbf{E},\tag{106}$$

where σ represents the conductivity of the material. How one determines the conductivity of a material is by testing the resistance ρ (or more likely just looking it up in a table) and then taking the reciprocal, $1/\rho = \sigma$. For conductors $\rho = 0$ and for insulators $\rho = \infty$.

To get the more familiar version of Ohm's law, one just uses the geometry of a given problem, and you can find the value of R algebraically in terms of σ . From this more familiar Ohm's law you can get Joule heating law which is

$$P = IV = I^2 R. (107)$$

7.2. Faraday's Law

In a circuit currents are pushed through the wires and circuit elements by some force **f**. This force can be split up into two parts, source force of course¹ such as a battery, and an electrostatics force that helps keep the current equal in all areas. Electromotive force is defined as the line integral of the total force around the circuit

$$\mathcal{E} \equiv \oint \mathbf{f} \cdot d\mathbf{\ell} = \oint \mathbf{f}_s \cdot d\mathbf{\ell}. \tag{108}$$

¹Yes I purposely wrote it this way because it is funny to say out loud. I do not mean to be condescending with my use of "of course."

The reason we are able to drop the **E** from the integral is because $\oint \mathbf{E} \cdot d\boldsymbol{\ell} = 0$. For an ideal source $\mathbf{E} = -\mathbf{F}_s$ and thus $V = \mathcal{E}$.

One source of emf is motion inside a magnetic field. This will lead us back to the more recognizable equation for emf. Let us define the magnetic flux to be

$$\Phi = \int \mathbf{B} \cdot d\mathbf{a}. \tag{109}$$

Then the emf is equal to

$$\mathcal{E} = -\frac{d\Phi}{dt}.\tag{110}$$

This is called the flux rule for motional emf. A series of experiments by Faraday showed the induced emf was the same when moving the magnetic field to the left or the wire to the right. He also showed that changing the magnetic field could cause an emf. Combining these three facts he stated that a changing magnetic field induced an electric field. Mathematically this is represented by

$$\nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t},\tag{111}$$

in its differential form, and in its integral form

$$\oint \mathbf{E} \cdot d\boldsymbol{\ell} = -\int \frac{\partial \mathbf{B}}{\partial t} \cdot d\mathbf{a} = -\frac{d\Phi}{dt}.$$
 (112)

A handy way to keep track of signs when using Faraday's law is to invoke Lenz's law which states "nature abhors a change in flux." From Faraday's law we can make an analog to the Biot-Savart law, now for electrostatics

$$\mathbf{E} = -\frac{1}{4\pi} \frac{\partial}{\partial t} \int \frac{\mathbf{B} \times \hat{\boldsymbol{\imath}}}{\boldsymbol{\imath}^2} d\tau. \tag{113}$$

To calculate **B** for this equation, you might be tempted to use magnetostatics even though the magnetic field is changing. This is fine for most cases except for electromagnetic waves or radiation. This regime is called quasistatic case.

7.3. Inductance

Imagine you have two different loops, and you run a current through one of the loops. This would cause a magnetic field, \mathbf{B}_1 , to be created which will interact with the second loop. This second loop then has some magnetic flux. This magnetic flux can be calculated through the simple equation

$$\Phi_2 = M_{21} I_1. \tag{114}$$

This new variable M_{21} is called the mutual inductance between the two loops. This can be calculated from the not so useful Neumann formula

$$M_{21} = \frac{\mu_0}{4\pi} \oint \oint \frac{d\ell_1 \cdot d\ell_2}{\imath}.$$
 (115)

While this isn't the most useful formula it does teach us a few things about mutual inductance. Firstly it is a purely geometrical quantity depending on the line integrals, and that $M_{21} = M_{12}$.

But to be honest, that part isn't to interesting in its current form. Like why would I add it to the electrodynamic chapter if I was just going to talk about a magnetostatics phenomena? Well here is the kicker, if I now vary the current through loop one over time, then I am changing the magnetic flux through the second loop and causing an emf to occur! But that induces a current in the second wire which is going to produce its own magnetic field which will then interact with the first loop. And guess what! That is going to cause another emf to be produced! How exciting, I'm sure everyone will have tons of fun calculating this all out.

To simplify the thought experiment, what if our two loops were just the same loop. When we run a changing current through the loop, it causes a magnetic field to be produced which causes a magnetic flux within the same loop. Varying this current would cause an emf to occur which is trying to fight the change in current we are supplying to the loop. This is what back emf is, because nature abhors a change in magnetic flux, then you have to provide a little extra juice to get the current you want. Self equation for self inductance boils down to

$$\mathcal{E} = -L\frac{dI}{dt},\tag{116}$$

where L is just some geometric quantity which can often be solved by solving

$$\frac{\Phi}{I} = L. \tag{117}$$

Can we calculate how much work must be done to combat this back emf? Also where does the energy go? Well the work done is

$$W = \frac{1}{2}LI^2. {(118)}$$

This work is actually just the energy stored in the magnetic field. When the circuit is turned back off, all this energy is taken away from the field and put back into trying to maintain the flow of current. A generalization of the previous equation is

$$W = \frac{1}{2\mu_0} \int B^2 d\tau, \tag{119}$$

where the bounds of integration are over all space. This represents the total energy stored in a magnetic field.

7.4. Maxwell's Equations

So at this point, I've identified four main equations throughout the text which I have referenced as Maxwell's equations in some capacity. Also all the equations have been attributed to other scientist, why is the set of them attributed to Maxwell? Why is it taking me till now to organize them all together? Well I will answer all of these questions now. You might notice an oddity in the current set of Maxwell equations. Namely, that a changing magnetic field induces an electric but not vice versa. Well this is where our homie Maxwell comes in and saves the day. Ampere's law in its current form does not not work for nonsteady current. This is because the divergence of Ampere's law states that $\mu_0 \nabla \cdot \mathbf{J} = 0$ which does not hold true in general. Adding a quick fix to this results in a new equation

$$\nabla \times \mathbf{B} = \mu_0 \mathbf{J} + \mu_0 \epsilon_0 \frac{\partial \mathbf{E}}{\partial t}.$$
 (120)

Maxwell called this fix the displacement current and defined it as

$$\mathbf{J}_d \equiv \epsilon_0 \frac{\partial \mathbf{E}}{\partial t} = \frac{\partial \mathbf{D}}{\partial t}.$$
 (121)

Now connecting all of the different phenomena and adding this fix fully unifies electricity and magnetism together. To explicitly write out all of Maxwell's equations:

$$\nabla \cdot \mathbf{E} = \frac{\rho}{\epsilon_0}$$
 Gauss's Law
$$\nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t}$$
 Faraday's Law
$$\nabla \cdot \mathbf{B} = 0,$$
 No Name
$$\nabla \times \mathbf{B} = -\mu_0 \mathbf{J}_e - \mu_0 \epsilon_0 \frac{\partial \mathbf{E}}{\partial t},$$
 Ampere's Law with Maxwell's Fix

We can take these four equations as axioms for theoretical classical electrodynamics. If we include in another axiom, the Lorentz force law, then we can derive the rest of classical electrodynamics. Pretty nifty huh? Well we can push the symmetry of these equations even further if we assumed magnetic monopoles do exist. Then Maxwell's equations would read

$$\nabla \cdot \mathbf{E} = \frac{\rho_e}{\epsilon_0}, \qquad \nabla \times \mathbf{E} = -\mu_0 \mathbf{J}_m - \frac{\partial \mathbf{B}}{\partial t}$$

$$\nabla \cdot \mathbf{B} = \mu_0 \rho_m, \quad \nabla \times \mathbf{B} = -\mu_0 \mathbf{J}_e - \mu_0 \epsilon_0 \frac{\partial \mathbf{E}}{\partial t}$$
(123)

The e and m subscripts are to differentiate electric vs magnetic charges and currents. Having the equations in this way fixes a lot of the symmetry problems but is unphysical. So I will not talk about the what-if scenario of magnetic monopoles existing further.²

²I personally do believe in the existence of magnetic monopoles, but the I do not feel

8. Conservation law

We have run into a conservation law already, the continuity equation,

$$\frac{\partial \rho}{\partial t} = -\nabla \cdot \mathbf{J}.\tag{124}$$

This tells us that there is a local charge conservation, and this is baked into Maxwell's equations. Remember, I said that the only axioms we need are Maxwell's equations and the Lorentz force law, so the local continuity of charge must stem from just those five equations. We want to derive similar equations for all of the other quantities that are normally conserved such as energy, momentum, and angular momentum. Along the way we will introduce the Maxwell stress tensor.

8.1. Conservation of Energy

We have already run into the equation for energy in electric and magnetic fields independently earlier. Harking back to them

$$W_e = \frac{\epsilon_0}{2} \int E^2 d\tau$$
 and $W_m = \frac{1}{2\mu_0} \int B^2 d\tau$.

Thus the energy density is

$$u = \frac{1}{2}(\epsilon_0 E^2 + \frac{1}{\mu_0} B^2). \tag{125}$$

This is only one half of a continuity equation though as it represents an energy "charge" density. What is the energy "current?" Well from Maxwell's equations we can derive Poynting's theorem,

like they are relevant to the discussion of classical electrodynamics.

$$\frac{dW}{dt} = -\frac{d}{dt} \int_{V} \frac{1}{2} \left(\epsilon_0 E^2 + \frac{1}{\mu_0} B^2 \right) d\tau - \frac{1}{\mu_0} \oint_{S} (\mathbf{E} \times \mathbf{B}) \cdot d\mathbf{a}. \tag{126}$$

This is simply an analogy to the work energy theorem of classical mechanics. If we look at the second integral, we can define a new vector called the Poynting vector equal to

$$\mathbf{S} \equiv \frac{1}{\mu_0} (\mathbf{E} \times \mathbf{B}). \tag{127}$$

This represent an energy flux density or energy "current." Thus combining the two quantities in this section we can create the continuity equation for energy

$$\frac{\partial u}{\partial t} = -\nabla \cdot \mathbf{S}.\tag{128}$$

8.2. Conservation of Momentum

If you look strictly at the particles in electrodynamics, it would appear they violate momentum conservation. For classical theories, this is strictly not allowed though. So what's the catch? We have to take into account the momentum carried by the fields themselves.

To carry out the calculations needed we are going to define the Maxwell stress tensor.³ When I first was introduced to it I thought it was just a big nasty mess. Let's define the Maxwell stress tensor as

³When I was first learning about this tensor my group of friends all joked that is called the Maxwell stress tensor because of how much stress it causes to undergraduates haha.

$$T_{ij} \equiv \epsilon_0 \left(E_i E_j - \frac{1}{2} \delta_{ij} E^2 \right) + \frac{1}{\mu_0} \left(B_i B_j - \frac{1}{2} \delta_{ij} B^2 \right). \tag{129}$$

Using this object we can write the total electromagnetic force on a set of charges as

$$\mathbf{F} = \oint_{S} \overset{\leftrightarrow}{\mathbf{T}} \cdot d\mathbf{a} - \epsilon_{0} \mu_{0} \frac{d}{dt} \int_{V} \mathbf{S} \ d\tau. \tag{130}$$

This shows us that the Maxwell stress tensor is like a momentum "current". It is interesting to note that the current of a vector is a tensor, while the current of scalar is a vector. Thus by using the fact that the force is simply the time derivative of the momentum we can write Equation 130 as

$$\frac{d\mathbf{p}_{mech}}{dt} = -\epsilon_0 \mu_0 \frac{d}{dt} \int_V \mathbf{S} \ d\tau + \oint_S \mathbf{T} \cdot d\mathbf{a}. \tag{131}$$

Comparing this to Poynting's equation we can identify what the momentum density should be,

$$\mathbf{g} = \mu_0 \epsilon_0 \mathbf{S}. \tag{132}$$

I would like to note again that since the quantity we are dealing with, momentum, is a vector, its density is also a vector. Now we can write the continuity equation for momentum to be

$$\frac{\partial \mathbf{g}}{\partial t} = \nabla \cdot \overset{\leftrightarrow}{\mathbf{T}}.\tag{133}$$

From here we can define angular momentum from the usual means as

$$\mathbf{L} = \mathbf{r} \times \mathbf{g}.\tag{134}$$

Angular momentum unfortunately does not have a nice neat and tidy continuity equation.⁴

9. Electromagnetic Waves

In this section we will try to decouple Maxwell's equations and along the way find ourselves with two wave equations. We will explore the physics of this to establish the theory of light as an electromagnetic waves. We will look at how these waves interact with boundaries and media. The end of this section explores guided waves, particularly in a rectangular wave guide.

9.1. Electromagnetic Waves in Vacuum

Decoupling Maxwell's equations leads to two three dimensional wave equations

$$\nabla^2 \mathbf{E} = \mu_0 \epsilon_0 \frac{\partial^2 \mathbf{E}}{\partial t^2}, \quad \text{and} \quad \nabla^2 \mathbf{E} = \mu_0 \epsilon_0 \frac{\partial^2 \mathbf{B}}{\partial t^2}.$$
 (135)

From the knowledge of wave mechanics we know that $\mu_0 \epsilon_0$ is a speed of propagation of the wave and we can see that both the electric and magnetic fields travel at this speed. If we are to plug in their values we find that

$$\frac{1}{\sqrt{\mu_0 \epsilon_0}} = 3.00 \times 10^8 m/s. \tag{136}$$

This is actually just the speed of light. This implies that light is an electromagnetic wave. From plugging the solutions of the wave equation into Maxwell's equation we find that

⁴:(.

$$\mathbf{B} = \frac{1}{c}\hat{\mathbf{k}} \times \mathbf{E},\tag{137}$$

where \mathbf{k} is the wave vector. This implies that the phase of the electric and magnetic fields are the same and that the fields are perpendicular to each other.

Plugging this equation back in Poynting vector results in

$$\mathbf{S} = \frac{1}{\mu_0 c} E^2 \hat{\mathbf{k}} = c\epsilon_0 E^2 \hat{\mathbf{k}} = cu\hat{\mathbf{k}},\tag{138}$$

where u is the energy per unit volume. Also by how we defined the momentum density, it must be equal to

$$\mathbf{g} = \frac{u}{c}\hat{\mathbf{k}} \tag{139}$$

Time averaging these values results in

$$\langle u \rangle = \frac{\epsilon_0}{2} E^2,$$

$$\langle \mathbf{S} \rangle = \frac{c\epsilon_0}{2} E^2 \hat{\mathbf{k}},$$

$$\langle \mathbf{g} \rangle = \frac{\epsilon_0}{2c} E^2 \hat{\mathbf{k}}.$$
(140)

Let us define the intensity of an electromagnetic wave as

$$I \equiv \langle \mathbf{S} \cdot \hat{\mathbf{k}} \rangle. \tag{141}$$

Thus when electromagnetic waves comes into contact with something there is some sort of radiation pressure. For a perfect absorber there this radiation pressure is equal to 1/c, and for a perfect reflector the radiation pressure is 2/c.

All of these results transfer over to if light is placed in matter with the simple switch of $\epsilon_0 \to \epsilon$ and $\mu_0 \to \mu$. The speed of the wave then is $1/\sqrt{\mu\epsilon} =$ c/n where n is the index of refraction. If μ_r is not given in the problem you should assume it to be 1.

9.2. Reflection and Transmission of EM Waves

When talking about the reflection and transmission of waves let a subscripts I, R, T represent the incident, reflected, and transmitted portions of the quantities. If the plane comes at a boundary at normal incidence then the reflection coefficient is

$$R \equiv \frac{I_R}{I_I} = \left(\frac{n_1 - n_2}{n_1 + n_2}\right)^2,\tag{142}$$

where I is the is intensity of the wave. The transmission coefficient⁵ is

$$T \equiv \frac{I_T}{I_I} = \frac{4n_1n_2}{(n_1 + n_2)^2}. (143)$$

Notice how R+T=1, which states that all of the quantities, such as energy and momentum, of the incident wave are exactly accounted for in the reflected and transmitted waves. But does all of this hold for oblique incidence? There are three laws of optics which we must take into account when talking about this.

The first law states that the incident, reflected, and transmitted wave vectors form a plane which also include the normal to the surface. What this

⁵These are very similar to a lot of wave mechanics problems such as in classical mechanics or quantum mechanics.

tells me, that if I take any two of those vectors that are linearly independent, then I have a basis that I can write the other two vectors in terms of.

The second and third law relate different angle to each other. The second law, or law of reflection, states that the angle of incidence is equal to the angle of reflection. Lastly the third law, also known as Snell's law or the law of refraction, is an equation relating the incident angle to the transmitted angle,

$$n_1 \sin \theta_I = n_2 \sin \theta_T. \tag{144}$$

Now let us define two new coefficient α and β

$$\alpha \equiv \frac{\cos \theta_T}{\cos \theta_I},\tag{145}$$

and

$$\beta \equiv \frac{\mu_1 n_2}{\mu_2 n_1}.\tag{146}$$

This allows us to concisely write Fresnel's equations for polarization in the plane of incidence.

$$E_{0_R} = \left(\frac{\alpha - \beta}{\alpha + \beta}\right) E_{0_I}, \quad \text{and} \quad E_{0_T} = \left(\frac{2}{\alpha + \beta}\right) E_{0_I}.$$
 (147)

Solving this for normal incidence we can recover the formula for Brewster's angle which in the most general form is

$$\sin^2 \theta_B = \frac{1 - \beta^2}{(n_1/n_2 - \beta^2)}. (148)$$

Making the assumption that μ_r for both material is roughly equal to one allows us to recover the simplified version of Brewster's angle

$$\tan \theta_B = \frac{n_2}{n_1}.\tag{149}$$

9.3. Absorption and Dispersion of Electromagnetic Waves

All of that is fine and dandy, but what if there actually is free charges and currents? For conductors free charges and free charge currents will spread out and form a charge distribution on the surface almost instantaneously. Maxwell's equations then become

$$\nabla \cdot \mathbf{E} = 0, \quad \nabla \times \mathbf{E} = -\frac{\partial \mathbf{B}}{\partial t},$$

$$\nabla \cdot \mathbf{B} = 0, \quad \nabla \times \mathbf{B} = \mu \epsilon \frac{\partial \mathbf{E}}{\partial t} + \mu \sigma \mathbf{E}.$$
(150)

If we try to put these into wave equation form a new term arises

$$\nabla^2 \mathbf{E} = \mu \epsilon \frac{\partial^2 \mathbf{E}}{\partial t^2} + \mu \sigma \frac{\partial \mathbf{E}}{\partial t}, \quad \text{and} \quad \nabla^2 \mathbf{B} = \mu \epsilon \frac{\partial^2 \mathbf{B}}{\partial t^2} + \mu \sigma \frac{\partial \mathbf{B}}{\partial t}.$$
 (151)

All that new term changes is the wave number in the plane wave solution to become

$$k'^2 = \mu \epsilon \omega^2 + i\mu \sigma \omega = k + i\kappa. \tag{152}$$

We define k and κ to be

$$k \equiv \omega \sqrt{\frac{\epsilon \mu}{2}} \left(\sqrt{1 + \left(\frac{\sigma}{\epsilon \omega}\right)^2} + 1 \right)^{\frac{1}{2}}, \tag{153}$$

and

$$\kappa \equiv \omega \sqrt{\frac{\epsilon \mu}{2}} \left(\sqrt{1 + \left(\frac{\sigma}{\epsilon \omega}\right)^2} - 1 \right)^{\frac{1}{2}}.$$
 (154)

Now when discussing optics a useful quantity that emerges is the skin depth which is kind of like the time constant for depth of penetration into a conductor. The amplitude of your wave will decrease by a factor of 1/e every

$$d \equiv \frac{1}{\kappa}.\tag{155}$$

If we are instead to write the complex wave vector like

$$k' = Ke^{i\phi}, \tag{156}$$

then we could find out some interesting physical phenomena about the fields inside the conductor.

First lets define K and ϕ ;

$$K \equiv \omega \sqrt{\epsilon \mu \sqrt{1 + \left(\frac{\sigma}{\epsilon \omega}\right)^2}},\tag{157}$$

and

$$\phi \equiv \tan^{-1} \frac{\kappa}{k}.\tag{158}$$

Plugging these quantities back into the initial differential equation we see that the magnetic field lags behind the electric field by a factor of ϕ . Also the proportionality factor between the fields isn't just c/n, but actually

$$\frac{B_0}{E_0} = \sqrt{\epsilon \mu \sqrt{1 + \left(\frac{\sigma}{\epsilon \omega}\right)^2}}.$$
 (159)

Looking at these equation we can see that there is a problem for perfect conductors where the charge density is infinite. In this case the wave is completely reflected and picks up a phase shift of π .

9.4. Frequency Dependence of Permittivity

So far we have assumed that ϵ and μ are just strictly scalar quantities. In general though they are more complicated, and one of these complication is that they change depending on the frequency of the light passing through the material. We can thus model them as scalar functions. Physically what happens is the electrons will get excited by different frequencies, and these different excitations cause different levels of damping to occur. We will model electrons as springs. In doing so we can then define the macroscopic polarization \mathbf{P} to be the real part of

$$\mathbf{P} = \frac{Nq^2}{m} \left(\sum_j \frac{f_j}{w_j^2 - w^2 - i\gamma_j \omega} \right) \mathbf{E}. \tag{160}$$

Here I have used f_j as the different electrons which have natural frequency ω_j , and damping γ_j . This complex polarization is proportional to the complex field which allows us to define it through the normal means as well

$$\mathbf{P} = \epsilon_0 \chi_e' \mathbf{E},\tag{161}$$

where χ'_e is the complex susceptibility. Using the manipulations we had before results in a complex dielectric constant

$$\epsilon_r' = 1 + \frac{Nq^2}{m} \left(\sum_j \frac{f_j}{w_j^2 - w^2 - i\gamma_j \omega} \right). \tag{162}$$

Looking at this equation we can see that the damping only plays a large role around the natural frequencies of the electrons. We can go through the same tricks as the last subsection and get monochromatic plane waves as solutions to the boundary conditions. Now we will define the absorption coefficient as

$$\alpha \equiv 2\kappa, \tag{163}$$

which tells us about how much the wave will become attenuated. Around the resonance the index of refraction will drop suddenly, and this phenomena is called the anomalous dispersion. In this region the material will actually become almost opaque.

If we stay away from resonance and look at transparent media, which normally have natural frequencies in the ultraviolet we can then get the formula for the index of refraction to be

$$1 + \left(\frac{Nq^2}{2m\epsilon_0} \sum_j \frac{f_j}{\omega_j^2}\right) + \omega^2 \left(\frac{Nq^2}{2m\epsilon_0} \sum_j \frac{f_j}{\omega_j^4}\right). \tag{164}$$

Then we can define new variables A and B to make this take the form of Cauchy's formula

$$n = 1 + A\left(1 + \frac{B}{\lambda^2}\right). \tag{165}$$

A is the coefficient of refraction while B is the coefficient of dispersion and this formula works best for most gases in visible wavelengths.

9.5. Guided Waves

Instead of infinite plane waves, what if our electromagnetic wave is confined to be in some wave guide. For this discussion we will assume the wave guide is a perfect conductor and thus we will use the boundary conditions of such. From working out the solutions to the boundary conditions it becomes apparent that the waves can not be strictly transverse and have some longitudinal component. In fact the transverse components can be found if we only know the longitudinal component. Let us assume that the wave is moving in the $\hat{\mathbf{z}}$ direction. Then we can write the transverse components as

$$E_{x} = \frac{i}{(\omega/c)^{2} - k^{2}} \left(k \frac{\partial E_{z}}{\partial x} + \omega \frac{\partial B_{z}}{\partial y} \right),$$

$$E_{y} = \frac{i}{(\omega/c)^{2} - k^{2}} \left(k \frac{\partial E_{z}}{\partial y} - \omega \frac{\partial B_{z}}{\partial x} \right),$$

$$B_{x} = \frac{i}{(\omega/c)^{2} - k^{2}} \left(k \frac{\partial B_{z}}{\partial x} + \frac{\omega}{c^{2}} \frac{\partial E_{z}}{\partial y} \right),$$

$$B_{y} = \frac{i}{(\omega/c)^{2} - k^{2}} \left(k \frac{\partial B_{z}}{\partial y} - \frac{\omega}{c^{2}} \frac{\partial E_{z}}{\partial x} \right).$$
(166)

Plugging all of this back into Maxwell's equation results in two coupled equations

$$\left(\frac{\partial^2}{\partial x^2} + \frac{\partial^2}{\partial y^2} + (w/c)^2 - k^2\right) E_z = 0,$$

$$\left(\frac{\partial^2}{\partial x^2} + \frac{\partial^2}{\partial y^2} + (w/c)^2 - k^2\right) B_z = 0.$$
(167)

From here we can now define what TE, TM, and TEM waves are. If the $E_z = 0$, then it is a TE (transverse electric) wave, if $B_z = 0$ then it is a TM

(transverse magnetic) wave, and if it is both then it is a TEM wave. TEM waves cannot happen if you are in a hollow wave guide.

When solving for TE waves in a rectangular wave guide, then the magnetic component will be of the form

$$B_z = B_0 \cos(m\pi x/a) \cos(n\pi y/b), \tag{168}$$

which then will be denoted as the TE_{mn} mode. The first index is conventionally related to the bigger of the two dimensions. One of the two indices must be nonzero for TE waves. If the frequency of the light is less than some cutoff frequency ω_{mn} defined to be

$$\omega_{mn} \equiv c\pi \sqrt{(m/a)^2 + (n/b)^2},\tag{169}$$

then the wave will attenuate exponentially. For the example we are working with, the lowest cutoff frequency is

$$\omega_{10} = c\pi/a. \tag{170}$$

A useful visualization that you c and o in your head is that the electromagnetic wave is travelling at some angle with the wave guide and bouncing back and forth. The allowed wavelengths are those that produce standing waves in the x-y plane.

An example of when TEM waves are allowed is a coaxial cable. In the solution for the TEM waves, it reduces back down to electrostatics and magnetostatics. Thus this example has already been solved and the solution is simply

$$\mathbf{E} = \frac{A\cos(kz - \omega t)}{s}\hat{\mathbf{s}},$$

$$\mathbf{B} = \frac{A\cos(kz - \omega t)}{cs}\hat{\boldsymbol{\phi}}.$$
(171)

10. Potentials and Fields

In this chapter we will establish what a gauge transformation is, and discuss the main two gauges.⁶ We will then discuss how, when taking into account that information travels at an finite speed, how the potentials and fields change. Finally we will look into applying the equations to point charges.

10.1. Gauge Transformations

As we move from statics into dynamics how we formulate the electric field in terms of the potentials must change. Since Faraday's Law changes when moving away from statics, let me start there and rederive what the electric field must be equal to:

$$\begin{split} \nabla \times \mathbf{E} &= -\frac{\partial \mathbf{B}}{\partial t}, \\ &= -\frac{\partial (\nabla \times \mathbf{A})}{\partial t}, \\ \nabla \times (\mathbf{E} + \frac{\partial \mathbf{A}}{\partial t}) &= 0, \\ \mathbf{E} + \frac{\partial \mathbf{A}}{\partial t} &= -\nabla \phi. \end{split}$$

⁶I actually have switched the location of this chapter, and the radiation section compared to the version of Griffiths I have. I honestly think it must have been a misprint because it does not make sense how it was set up.

Therefore the electric field can now be written as

$$\mathbf{E} = -\nabla\phi - \frac{\partial\mathbf{A}}{\partial t}.\tag{172}$$

If we use this to reduce Maxwell's equations back down to just two using the fields, they become

$$\nabla^2 \phi + \frac{\partial}{\partial t} (\nabla \cdot \mathbf{A}) = -\frac{\rho}{\epsilon_0}, \tag{173}$$

and

$$\left(\nabla^2 \mathbf{A} - \frac{1}{c^2} \frac{\partial^2 \mathbf{A}}{\partial t^2}\right) - \nabla \left(\nabla \cdot \mathbf{A} + \frac{1}{c^2} \frac{\partial \phi}{\partial t}\right) = -\mu_0 \mathbf{J}.$$
 (174)

The fields are defined through the derivatives of potentials and so there is some freedom in how we define them. It doesn't have to be just a constant though, it could just be some scalar function. Let the scalar function be denoted λ , and how it interacts with the potentials is

$$\mathbf{A}' = \mathbf{A} + \nabla \lambda,$$

$$\phi' = \phi - \frac{\partial \lambda}{\partial t}.$$
(175)

This function λ is called the gauge parameter and the change it creates for the potentials is called a gauge transformation. This gauge can greatly simplify the previous equations.

For example if we are to choose the Coulomb gauge, or sometimes called the radiation gauge, which forces the vector potential to be divergenceless, then Gauss' law reduces back to

$$\nabla^2 \phi = -\frac{\rho}{\epsilon_0}.\tag{176}$$

A paradox that arises in this gauge is that the scalar potential will instantly respond to the change of the charge distribution, no matter how far away it is. This would seem to contradict relativity, but because the scalar potential is not something you can directly measure, it can not actually allow information to travel faster than light. In this gauge ϕ is easy to calculate but **A** is difficult.

The second most prevalent gauge is called the Lorenz gauge, and is useful for relativistic problems because it preserves Lorentz invariance. The Lorenz gauge is stated as

$$\nabla \cdot \mathbf{A} = -\frac{1}{c^2} \frac{\partial \phi}{\partial t}.$$
 (177)

We saw this gauge in the relativity section before, and so I will not talk to much more about it here. Using the Lorenz gauge though boils down to just solving the inhomogeneous wave equation. We will be assuming the Lorenz gauge from here on out.

10.2. Retarded Potentials

Because information takes time to travel from one place to another, namely it travels at the speed of light, having potentials and fields respond instantaneously to the change in charges and currents is inherently wrong. Therefore lets define a retarded time that takes into account the travel of information

$$t_r \equiv t - \frac{\imath}{c}.\tag{178}$$

If we just plug these equations into the formulas for the scalar and vector potentials then we get what is called the retarded potentials. Applying this concepts to the fields gets you the wrong answer. Checking that just plugging in the retarded time into the potentials we find that we could have defined an advanced time

$$t_a \equiv t + \frac{\imath}{c},\tag{179}$$

and it would have worked as well. The problem with using advanced time is that it breaks causality which is a big no no.

Now knowing that these potentials work we can just plug them into the equations for the fields and get the solutions. In doing so we run into what is called Jefimenko's equations,

$$\mathbf{E}(\mathbf{r},t) = \frac{1}{4\pi\epsilon_0} \int \left(\frac{\rho(\mathbf{r}',t_r)}{2} \hat{\boldsymbol{\lambda}} + \frac{\dot{\rho}(\mathbf{r}',t_r)}{c^2} \hat{\boldsymbol{\lambda}} - \frac{\dot{\mathbf{J}}(\mathbf{r}',t_r)}{c^2 \lambda} \right) d\tau', \tag{180}$$

and

$$\mathbf{B}(\mathbf{r},t) = \frac{\mu_0}{4\pi} \int \left(\frac{\mathbf{J}(\mathbf{r}',t_r)}{\imath^2} + \frac{\dot{\mathbf{J}}(\mathbf{r}',t_r)}{c\imath} \right) \times \hat{\boldsymbol{\imath}} \, d\tau'.$$
 (181)

10.3. Point Charges

What are the potentials of a moving point charge? Well the answers are the Liénard-Wiechert potentials. We could try to introduce some sort of handwavey geometrical argument to derive these, but instead I will try to derive them from a distributional point of view.⁷

$$\phi(\mathbf{r},t) = \frac{1}{4\pi\epsilon_0} \frac{qc}{2c - \mathbf{z} \cdot \mathbf{v}},\tag{182}$$

and

$$\mathbf{A}(\mathbf{r},t) = \frac{\mathbf{v}}{c^2}\phi(\mathbf{r},t). \tag{183}$$

We can use the Liénard-Wiechert potentials and solve for the fields directly. The results are

$$\mathbf{E}(\mathbf{r},t)\frac{1}{4\pi\epsilon_0}\frac{q\mathbf{r}}{(\mathbf{r}\cdot\mathbf{u})^3}[(c^2-v^2)\mathbf{u}+\mathbf{r}\times(\mathbf{u}\times\mathbf{a})],\tag{184}$$

and

$$\mathbf{B}(\mathbf{r},t) = \frac{\hat{\boldsymbol{z}}}{c} \times \mathbf{E}(\mathbf{r},t). \tag{185}$$

Lets examine the electric field a little closer. The first time is called the velocity field, and it's main use is swapping the energy between the field and the particles. The second term is called the acceleration term and it introduces a way for energy to be loss from the system, i.e. radiation.

11. Electrodynamics and Relativity

I would like to note that I am not writing an introduction to special relativity. Griffiths does this but I am not going to rehash over a lot of

⁷When I say "I will," I mean I will do that later when I have more time.

information that is not specific to electrodynamics. Because of this the later half of the chapter is the only one I am going to focus on. Nothing changes when you are talking about our axioms change when talking about special relativity because relativity was brought into play by taking electrodynamics to be the correct version of classical physics and not Newton. It is possible though to use special relativity to gain insight into why certain phenomena occur. Also I will try to write down equations using tensor notation to be able to prepare people to go further in their relativity studies.

11.1. How the Fields Transform

I will start this section with a small example of how the electric field changes for a parallel plate capacitor. Let there be a parallel plate capacitor which in its rest frame generate an electric field equal to

$$\mathbf{E}_0 = \frac{\sigma_0}{\epsilon_0} \hat{\mathbf{y}}.\tag{186}$$

Charge is conserved no matter the reference frame you are looking at so if we look at a reference frame moving to the right by some factor of v then it will not change the amount of charge on the capacitors. What will change is the distance in between the charges and thus the charge density change by a factor of γ . Following suit then the field must transform like

$$\mathbf{E}^{\perp} = \gamma_0 \mathbf{E}_0^{\perp},$$

$$E^{\parallel} = E_0^{\parallel}.$$
(187)

But what about the general case? Assume that the new frame is moving in the +x direction at some speed v. Skipping the derivation for now the bread and butter of the transform is

$$E_{x} = E_{0x}, \quad B_{x} = B_{0x},$$

$$E_{y} = \gamma (E_{0y} - vB_{0z}), \quad B_{y} = \gamma \left(B_{0y} + \frac{v}{c^{2}}E_{0z}\right),$$

$$E_{z} = \gamma (E_{0z} + vB_{0y}), \quad B_{z} = \gamma \left(B_{0z} - \frac{v}{c^{2}}E_{0y}\right).$$
(188)

The two cases to note are when one of the fields start out at zero. If the magnetic field initially is zero then the new magnetic field can be related to the new electric field by

$$\mathbf{B} = -\frac{1}{c^2} (\mathbf{v} \times \mathbf{E}). \tag{189}$$

Similarly if the electric field is zero initially then the new electric field can be related to the new magnetic field by

$$\mathbf{E} = \mathbf{v} \times \mathbf{B}.\tag{190}$$

These results can generalize for more arbitrary motion but that is most easily done with tensors.

11.2. Tensor Formulation of Electrodynamics

I will not be deriving a lot of the following equations at this time but it is good to at least have them written down.

To write down the previous transformations all in one go it would be sufficient to find an anti-symmetric, second rank tensor which fulfilled those properties under a Lorentz transformation. This tensor is called the field tensor and is defined as

$$F^{\mu\nu} = \begin{pmatrix} 0 & E_x/c & E_y/c & E_z/c \\ -E_x/c & 0 & B_z & -B_y \\ -E_y/c & -B_z & 0 & B_x \\ -E_z/c & B_y & -B_x & 0 \end{pmatrix}$$
(191)

There is another tensor which can be used which is the dual of the field tensor called, the dual tensor.⁸

$$G^{\mu\nu} = \begin{pmatrix} 0 & B_x & B_y & B_z \\ -B_x & 0 & -E_z/c & E_y/c \\ -B_y & E_z/c & 0 & -E_x/c \\ -B_z & -E_y/c & E_x/c & 0 \end{pmatrix}$$
(192)

What can we use this tensor for now? Well we can define a the current density four vector as

$$J^{\mu} = (c\rho, \mathbf{J}),\tag{193}$$

which allows us to write the continuity equation as

$$\partial_{\mu}J^{\mu} = 0. \tag{194}$$

Even further Maxwell's laws can be written as just

$$\partial_{\nu}F^{\mu\nu} = \mu_0 J^{\mu}, \quad \text{and} \quad \partial_{\nu}G^{\mu\nu} = 0.$$
 (195)

The Minkowski force,

⁸Great name guys. Think this gets to the point. Definitely isn't missing a few extra words and can't get confusing for people.

$$K^{\nu} = q\eta_{\nu}F^{\mu\nu},\tag{196}$$

then also brings us back to the Lorentz force law. The potentials can also be combined into a singular four vector

$$A^{\mu} = (\phi/c, \mathbf{A}). \tag{197}$$

Using this we can write the field tensor as

$$F^{\mu\nu} = \partial_{\mu}A^{\nu} - \partial_{\nu}A^{\mu}. \tag{198}$$

Let us now also introduce a new gauge, the Lorentz gauge. This gauge is the one that works perfectly with relativity, while the Coulomb gauge does not. The Lorentz gauge is

$$\partial_{\mu}A^{\mu} = 0. \tag{199}$$

If we are in this gauge then we can combine all of Maxwell's equations into a single equation:

$$\Box^2 A^{\mu} = -\mu_0 J^{\mu}. \tag{200}$$

Griffiths calls this "the most elegant formulation of Maxwell's equations."

12. Radiation

We shall define radiation in this section as the process of the fields taking energy off to infinity due to charges accelerating.⁹ Let us say the power

 $^{^9\}mathrm{I}$ will also note again I switched this chapter and the potentials and fields chapter.

radiated through some surface is the surface integral of the Poynting vector, and thus

$$P(r,t) = \oint \mathbf{S} \cdot d\mathbf{a} = \frac{1}{\mu_0} \oint (\mathbf{E} \times \mathbf{B}) \cdot d\mathbf{a}.$$
 (201)

We want to evaluate this power at the time t_0 , but these waves left the center at a time $t_0 - \frac{r}{c}$. Thus

$$P_{rad}(t_0) = \lim_{r \to \infty} P\left(r, t_0 + \frac{r}{c}\right). \tag{202}$$

For this value to be finite¹⁰ then the fields must fall off faster than 1/r. Since this is not the case in electrostatics nor magnetostatics, there is no radiation to be had. It is only in the electrodynamic case that they arise. To start we will explore this radiation from electric and magnetic dipoles and compare the two cases. Then we will look at how to formulate the equations for an arbitrary source. We will then apply the concepts we have learned to point charges. We will end this chapter, and the entirety of these notes at this point, on a brief discussion of radiation reaction, or in other words self-force.

12.1. Dipole Radiation

For this section we are trying to avoid accelerating point charges in favor of dipoles because they are much easier to work with. The model we will use is charges driven between two metal spheres connected by a wire. Let the driving force make the charge move like

¹⁰In this context finite means non-zero.

$$q(t) = q_0 \cos(\omega t). \tag{203}$$

Thus the dipole moment is

$$\mathbf{p}(t) = p_0 \cos(\omega t) \hat{\mathbf{z}},\tag{204}$$

where

$$p_0 \equiv q_0 d. \tag{205}$$

The current through the wire is

$$\mathbf{I}(t) = -q_0 \omega \sin(\omega t) \hat{\mathbf{z}}.$$
 (206)

If we keep causality in mind, and make the following three approximations,

$$d \ll r$$
, and $d \ll \frac{c}{\omega}$, and $\frac{c}{\omega} \ll r$, (207)

then we find the potentials to be

$$\phi(r,\theta,t) = -\frac{p_0\omega}{4\pi\epsilon_0 c} \left(\frac{\cos\theta}{r}\right) \sin[\omega(t-r/c)], \qquad (208)$$

 and^{11}

$$\mathbf{A}(r,\theta,t) = -\frac{\mu_0 p_0 \omega}{4\pi r} \sin[\omega(t - r/c)]\hat{\mathbf{z}}.$$
 (209)

¹¹I actually don't use the last approximation in the equation for the vector potential.

The first approximation was to try and move away from physical dipoles to perfect dipoles. The second approximation just comes from the fact that the frequency is related to distance by the wavelength of the light, and the wavelength is much larger than d. The last approximation is because we are looking at radiation the radiation zone, which for us is towards infinity.

From the potentials the fields can be directly calculated and thus

$$\mathbf{E} = -\frac{\mu_0 p_0 \omega^2}{4\pi} \left(\frac{\sin \theta}{r} \right) \cos[\omega (t - r/c)] \hat{\boldsymbol{\theta}}, \tag{210}$$

and

$$\mathbf{B} = -\frac{\mu_0 p_0 \omega^2}{4\pi c} \left(\frac{\sin \theta}{r}\right) \cos[\omega(t - r/c)] \hat{\boldsymbol{\phi}}.$$
 (211)

Now we can finally calculate what the Poynting vector is

$$\mathbf{S}(\mathbf{r},t) = \frac{\mu_0}{c} \left(\frac{p_0 \omega^2}{4\pi} \left(\frac{\sin \theta}{r} \right) \cos[\omega(t - r/c)] \right)^2 \hat{\mathbf{r}}.$$
 (212)

Time averaging this quantity results in

$$\langle \mathbf{S} \rangle = \left(\frac{\mu_0 p_0^2 \omega^4}{32\pi c} \right) \frac{\sin^2 \theta}{r} \hat{\mathbf{r}}, \tag{213}$$

which finally allows us to find what the average radiation. Taking the formula we established at the beginning of the section

$$\langle P \rangle = \frac{\mu_0 p_0^2 \omega^4}{12\pi c}.\tag{214}$$

12.2. Magnetic Dipole Radiations

Instead of the model we used last time, lets just have a wire in the shape of a circle with radius b, and current

$$I(t) = I_0 \cos \omega t. \tag{215}$$

The magnetic dipole is then

$$\mathbf{m}(t) = m_0 \cos(\omega t) \hat{\mathbf{z}},\tag{216}$$

where I have defined m_0 to be

$$m_0 \equiv \pi b^2 I_0. \tag{217}$$

I would like to note that the total charge on the loop is zero and thus the scalar potential is zero as well. Using the same approximations as last time but now b plays the role of d, we can solve for the magnetic vector potential. The result is

$$\mathbf{A}(r,\theta,t) = -\frac{\mu_0 \omega}{4\pi c} \left(\frac{\sin \theta}{r}\right) \sin[\omega(t-r/c)]\hat{\boldsymbol{\phi}}.$$
 (218)

From here we calculate the field directly and the result is

$$\mathbf{E} = \frac{\mu_0 m_0 \omega^2}{4\pi c} \cos[\omega (t - r/c)] \hat{\boldsymbol{\phi}}, \tag{219}$$

and

$$\mathbf{B} = -\frac{\mu_0 m_0 \omega^2}{4\pi c^2} \left(\frac{\sin \theta}{r}\right) \cos[\omega(t - r/c)] \hat{\boldsymbol{\theta}}.$$
 (220)

Following the same method of calculating the average radiation as before we find

$$\langle P \rangle = \frac{\mu_0 m_0^2 \omega^4}{12\pi c^3}.\tag{221}$$

I would like to note that this is very similar to the equation for the radiation due to the electric dipole. The main difference is there is an extra factor of $1/c^2$. Therefore if they are both present the electric dipole radiation will be the dominant one. It is only in the special example we have created that there is no electric radiation that the radiation due to magnetic dipoles is important.

12.3. Radiation from an Arbitrary Source

To able to do the calculation for this section we need to establish what the potentials would be taking into account causality. The scalar potential is

$$\phi(\mathbf{r},t) = \frac{1}{4\pi\epsilon_0} \int \frac{\rho(\mathbf{r}',t-\iota/c)}{\iota} d\tau', \tag{222}$$

and the vector potential is

$$\mathbf{A}(\mathbf{r},t) = \frac{\mu_0}{4\pi} \int \frac{\mathbf{J}(\mathbf{r}', t - r/c)}{r} d\tau'. \tag{223}$$

We are going use a slightly different set of assumptions this time to take into account the arbitrary time derivatives of the charge distribution. The set of approximations we will use this time is

$$r' \ll r$$
,
$$r' \ll \frac{c}{|\ddot{\rho}/\dot{\rho}|}, \frac{c}{|\dddot{\rho}/\dot{\rho}|^{\frac{1}{2}}}, \frac{c}{|\dddot{\rho}/\dot{\rho}|^{\frac{1}{3}}}.$$

Applying these approximations to the potentials results in

$$\phi(\mathbf{r},t) = \frac{1}{4\pi\epsilon_0} \left(\frac{Q}{r} + \frac{\hat{\mathbf{r}} \cdot \mathbf{p}(t_0)}{r^2} + \frac{\hat{\mathbf{r}} \cdot \dot{\mathbf{p}}(t_0)}{rc} \right)$$
(224)

is the scalar potential while the vector potential is

$$\mathbf{A}(\mathbf{r},t) = \frac{\mu_0}{4\pi} \frac{\dot{\mathbf{p}}(t_0)}{r}.$$
 (225)

Now when we calculate the fields we will drop terms that fall of faster than 1/r. Thus the relevant fields we are interested in are

$$\mathbf{E}(\mathbf{r},t) = \frac{\mu_0}{4\pi} \frac{1}{r} [\hat{\mathbf{r}} \times (\hat{\mathbf{r}} \times \ddot{\mathbf{p}})], \tag{226}$$

and

$$\mathbf{B}(\mathbf{r},t) = -\frac{\mu_0}{4\pi} \frac{1}{rc} [\hat{\mathbf{r}} \times \ddot{\mathbf{p}}]. \tag{227}$$

Following the methods we established in the previous subsection we can calculate the total radiated power

$$P_{rad}(t_0) = \frac{\mu_0}{6\pi c} [\ddot{p}(t_0)]^2. \tag{228}$$

We can calculate the Larmor formula radiation using what we have done so far. Using $\mathbf{p}(t) = q\mathbf{d}(t)$ as our dipole moment, then the power radiated should be

$$P = \frac{\mu_0 q^2 a^2}{6\pi c},\tag{229}$$

where a^2 is the square of the acceleration, $\ddot{\mathbf{d}}$.

I would like to note from the previous section that an electric monopole moment does not radiate. If it were to radiate, it would invalidate conservation of charge. This however does not stop actual monopoles, such as electrons, from radiating if they are accelerating. Accelerating point charges actually pick up higher order moments.

12.4. Radiation from Point Charges

The electric field of for an electron moving in an arbitrary way is

$$\mathbf{E}(\mathbf{r},t) = \frac{1}{4\pi\epsilon_0} \frac{\imath}{(\mathbf{z} \cdot \mathbf{u})^3} [(c^2 - v^2)\mathbf{u} + \mathbf{z} \times (\mathbf{u} \times \mathbf{a})], \tag{230}$$

where $\mathbf{u} = c\hat{\mathbf{z}} - \mathbf{v}$. If we recall from the potentials and fields chapter, we will remember this field is broken up into the velocity and acceleration fields. The acceleration field is the one that will contribute to the radiation in the end and so is sometimes referred to as the radiation field. The reason for this is the velocity field carries around the energy, but does not take it to infinity.

The magnetic field created by this charge is

$$\mathbf{B}(\mathbf{r},t) = \frac{1}{c}\hat{\mathbf{z}} \times \mathbf{E}(\mathbf{r},t). \tag{231}$$

and thus we are able to carry out the normal process of figuring out the Poynting and calculating the radiation you would end back up at the Larmor formula if you are travelling at a non-relativistic speed. What if this was at a relativistic speed though? The relativistic equation to the Larmor formula is called Liénard's generalization and is

$$P = \frac{\mu_0 q^2 \gamma^6}{6\pi c} \left(a^2 - \frac{|\mathbf{v} \times \mathbf{a}^2|}{c^2} \right). \tag{232}$$

This is talking about the classical way of interpreting bremsstrahlung.

12.5. Radiation Reaction

When a charge accelerates it loses energy and thus does not accelerate at the level that you would anticipate normally. The way to fix this is to say that there exists a backwards force, \mathbf{F}_{rad} . Calculating what this should be, we can set the negative power radiated by the charge to be the power lost due to this force, i.e.

$$\mathbf{F}_{rad} \cdot \mathbf{v} = -\frac{\mu_0 q^2 a^2}{6\pi c}.\tag{233}$$

This equation is actually wrong because it ignores the velocity field which tells us energy in the field that is retrievable. To be more specific, you would want to look at how that energy transfer also affects the particle's motion. Let's restrict or view to motions where the particles start and end velocity is the same. That way the energy lost to the field is gained back. In doing so we find the Abraham-Lorentz formula for the radiation reaction force

$$\mathbf{F}_{rad} = \frac{\mu_0 q^2}{6\pi c} \dot{\mathbf{a}}.\tag{234}$$

Equating this to Newton's law has disturbing consequences such as breaking causality. This starts to show the breakdown of classical electromagnetism and might be an indicator needing to include quantum mechanics. According to classical electromagnetism the mechanism for this force is actually the force of the charge on itself.¹²

 $^{^{12}}$ I am giving no explanation to this at the current time. I really feel like we are pushing classical electromagnetism to its limits when we start talking about self-fields. This is covered in the last chapter of Jackson and I will write more when I get there.

References

[1] D. J. Griffiths, Introduction to Electrodynamics, Noida, IN: Pearson Education, 4th edition, 2013.