

Guide for installing, configuring and using the Mutt mail client with Proton Mail Bridge on Linux Server and Linux Desktop.

System, security and application administrators use command line mail tools like sendmail, postfix, mailx and mutt to mail out reports alerts and other material to people that presumably care. This guide describes how setup up command line mail service using Proton Mail Bridge combined with the Mutt mail client.

On Linux Desktop, Thunderbird is supported by Proton, another option for a command line client

If the requirement is only to send mail securely from a Linux computer, using postfix with Proton Mail SMTP server may be an alternative option. *To use Proton Mail as a SMTP server requires a functioning custom domain in the mail account.*

Scope limitations

- ◆ This guide only covers the basics of how to configure and use mutt. The goal is to have a workable solution that can be enhanced and tailored further for your individual requirements.
- ◆ Setting up protonmail-bridge as a daemon-like process in this guide for Linux Server is limited to the basics, full systemd implementation is out of scope. Daemonizing on Linux Desktop not covered in this guide
- ◆ These installation and configuration notes use the defaults, further modifications to permissions and security features may be required for a more secure environment.
- ◆ Software installation is out of scope. Software package management varies between Linux flavours

At time of writing; Proton Mail Bridge is not supported ARM devices other than M-series Macs. The only Proton supported email client for the Linux Proton Mail Bridge is Thunderbird.

Summary of steps

- Create user account for this installation and usage of mutt and protonmail-bridge. [Optional]
- All the following to be done in the designated user account. All software installations to be done as root.
 1. Install protonmail-bridge.
 2. Install the password manager, pass.
 3. Initialise the password manager (pass) with a gpg password.
 4. Start protonmail-bridge interactively to initialise and sync protonmail-bridge.
The protonmail-bridge is configured only for the designated Linux user account and creates a database within the home directory of that user. The sync process may take hours with large accounts that contain 10,000+ emails, resulting in taking up GiBs of disk space within the users home directory.
 5. Install w3m. Used by mutt to convert html text into easy human readable text.
 6. Create the w3m configuration file in the user's home directory.
 7. Create the mutt default configuration file in the user's home directory.
 8. Install mutt
 9. Start protonmail-bridge in the background, alternatively start it another window using the designated user account.
 10. Test mutt using the TUI interface and command line.

Steps 1 to 4 are only for Linux Server; steps 5 to 10 are for both Linux Server and Linux Desktop.

Security

Changing the Proton Mail password terminates all protonmail-bridge connections. To resume services log into the mail account within protonmail-bridge using the new password.

The IMAP/SMTP password remain unchanged. No changes to the mutt configuration file are required.

Any connection from a device to the Proton Mail account can be revoked at any time.

Proton Mail Account > Settings > Security and privacy > Session management

On computers that are shared with other system and application administrators it would be wise to restrict access to mutt when it is configured for use with protonmail-bridge. Mutt can be used for spam and other rogue activities.

The default configuration protonmail-bridge in a designated user account cannot be accessed by other users. To configure and use protonmail-bridge in another user home directory, they require the password of proton mail account.

Additional information

Proton Bridge Github <https://github.com/ProtonMail/proton-bridge#proton-mail-bridge->

Linux Server

Install **protonmail-bridge**

Install **pass**, the password manger aka password-store.

Create an account for the mutt protonmail-bridge service. Creating an account for this is optional, on shared servers it is advisable.

```
root@fred01# adduser muttpmb
```

In muttpmb set up a password manager for protonmail-bridge

```
root@fred01# su - muttpmb

$ gpg --batch --pinentry-mode loopback --passphrase "" \
  --quick-gen-key "mothra@pm.me" rsa4096 sign,encrypt,auth never
gpg: directory '/home/muttpmb/.gnupg' created
gpg: keybox '/home/muttpmb/.gnupg/pubring.kbx' created
gpg: /home/muttpmb/.gnupg/trustdb.gpg: trustdb created
gpg: directory '/home/muttpmb/.gnupg/openpgp-revocs.d' created
gpg: revocation certificate stored as '/home/muttpmb/.gnupg/openpgp-
revocs.d/75E185A9AD2F2C4B3E33F8408F5A85686211AA6D.rev'
```

Acknowledgement: Proton Support provided the gpg command line switches.

Obtain the generated key

```
$ gpg --list-secret-keys
gpg: checking the trustdb
gpg: marginals needed: 3 completes needed: 1 trust model: pgp
gpg: depth: 0 valid: 1 signed: 0 trust: 0-, 0q, 0n, 0m, 0f, 1u
/home/muttpmb/.gnupg/pubring.kbx
-----
sec   rsa4096 2026-05-20 [SCEA]
      75E185A9AD2F2C4B3E33F8408F5A85686211AA6D
uid   [ultimate] mothra@pm.me
```

Initialise the pass password manager

```
$ pass init 75E185A9AD2F2C4B3E33F8408F5A85686211AA6D
```

```
mkdir: created directory '/home/muttpmb/.password-store/'  
Password store initialized for 75E185A9AD2F2C4B3E33F8408F5A85686211AA6D
```

Start protonmail-bridge (protonmail-bridge -c)

There may be significant delays between the following actions once protonmail-bridge has started.

- It will start with warning messages about the password managers and other system warnings.
- It will check for updates; if required this can be disabled.
- Login to initialise configuration of protonmail-bridge. Logging on only occurs in the initial setup, it will not be required again.
- A sync will commence with your online account. Depending upon the amount of mail stored your account synchronisation may take hours.
- The synchronisation process is checkpointed. You can terminate anytime and when sync is resumed it will start at the same point of last termination.

```
$ protonmail-bridge -c
WARN[May 20 22:45:15.488] An issue occurred when reading the cache file error="open
/home/muttptmb/.cache/protonmail/bridge-v3/unleash_startup_cache/unleash_startup_flags.json: no
such file or directory" pkg=unleash-startup
WARN[May 20 22:45:17.513] Failed to add test credentials to keychain error="failed to open dbus
connection: exec: \"dbus-launch\": executable file not found in $PATH"
helper="*keychain.SecretServiceDBusHelper"
WARN[May 20 22:45:17.769] no vault key found, generating new error="could not get keychain item:
credentials not found in native keychain"
WARN[May 20 22:45:18.158] Requested max sync memory of 2048 MB is greater than half of system
memory (1699.427734375 MB), forcing to half of system memory
```

[illegible]

```
A new version (3.24.2) was installed.
>>> login
Username: mothra.tokyo
Password: <enter password >
Authenticating ...
Account mothra.tokyo was added successfully.
>>> A sync has begun for mothra.tokyo.
Sync (mothra.tokyo): 0.0% (Elapsed: 1.6s, ETA: 3433.1s)
Sync (mothra.tokyo): 0.1% (Elapsed: 3.3s, ETA: 3447.4s)
>>> exit
```

- The protonmail-bridge is configured only for the designated user account and creates a database within the home directory of that user.
- Synchronisation updates that database in the **.local** directory.

After initialisation protonmail-bridge checks for both *pass* and *SecretService* password managers. It only needs one, and it will always generate a warning if the other is not operational.

The size of the protonmail-bridge database could be substantial.
List all hidden files and directories that are larger than one MiB.

```
$ du --apparent-size -sk ~/.* | awk ' $1 > 1024 {printf "%10d MiB  %s\n",$1/1024,$2}'  
5135 MiB  /home/muttpmb/.local
```

Notes

- Only one instance of protonmail-bridge can be run for the designated Linux user account.
- There are three modes of starting protonmail-bridge:
 - **protonmail-bridge** with no switches. This is for desktop Linux it will start the Protonmail Bridge gui, on a Linux server it appears to do nothing.
 - **protonmail-bridge -c** The interactive shell of protonmail-bridge, enter **help** to list all options.
 - **protonmail-bridge -n** For the non-interactive running of protonmail-bridge, it can run in the foreground, background and without a terminal in a daemon-like mode.

Protonmail-bridge settings

Start **protonmail-bridge -c** and wait for sync to finish.

User account settings required for mutt.

```
>>> info
Configuration for mothra.tokyo@pm.me
IMAP Settings
Address: 127.0.0.1
IMAP port: 1143
Username: mothra@pm.me
Password: 1N9W2YBG2eXQFkeZQhHwWg
Security: STARTTLS

SMTP Settings
Address: 127.0.0.1
SMTP port: 1025
Username: mothra.tokyo@pm.me
Password: 1N9W2YBG2eXQFkeZQhHwWg
Security: STARTTLS
```

NOTE: Each protonmail-bridge installation creates its own password.

Disable autoupdates if required.

```
>>> updates autoupdates disable
Bridge is currently set to automatically install updates.
Are you sure you want to stop bridge from doing this? yes/no: y
>>>
```

Exit protonmail-bridge shell and start protommail-bridge in non-interactive mode (-n) in the background.

```
$ protonmail-bridge -n &
Alternatively, use this to avoid the intrusion of warning messages
$ protonmail-bridge -n >/dev/null 2>&1 &
```

Run the following commands to check the IMAP port (1143) and the SMTP port (1025).

```
$ (echo > /dev/tcp/127.0.0.1/1143) > /dev/null 2>&1; echo $?
$ (echo > /dev/tcp/127.0.0.1/1025) > /dev/null 2>&1; echo $?
```

If the result is **0** then protonmail-bridge is active.

if the result is **1** then protonmail-bridge is inactive

Deamonize Proton Mail Bridge – Server only

Protonmail-bridge can be run in the background without a terminal using nohup – see **Basic Scripts** section. Recommend disabling autoupdates for automated non-interactive starting of protonmail-bridge.

w3m

Install before mutt.

W3m is a web browser that will convert the html of email messages into an easily readable format. Once installed create a **.mailcap** configuration file in the home directory of the mutt user. Contents must be :

```
$ echo 'text/html; w3m -I %{charset} -T text/html -dump; copiousoutput' > .mailcap
```

mutt

In the home directory of the mutt user (muttpmb) create a /home/muttpmb/.**mutt** directory. Within the **.mutt** directory create a configuration file (**muttrc**), with the following contents, replace yellow highlighted text with relevant account names and password obtained from protonmail-bridge.

The default installation of the configuration file is /home/<user>/.mutt/muttrc

Alternative configuration files can be used with mutt **mutt -F /home/<user>/.mutt/muttrc-test5**

Contents: /home/<user>/.mutt/muttrc

```
# ===== IMAP =====
set imap_user = mothra.tokyo@pm.me # Your protonmail account
set imap_pass = 1N9W2YBG2eXQFkeZQhHwWg # Your password in protonmail-bridge
set spoolfile = "imap://localhost:1143/INBOX"
set folder = "imap://localhost:1143"
set record="+Sent"
set postponed="+Drafts"
set header_csuache = "~/mutt/cache/headers"
set message_cachedir = "~/mutt/cache/bodies"
set certificate_file = "~/mutt/certificates"
# ===== SMTP =====
set smtp_url="smtp://mothra.tokyo@pm.me@127.0.0.1:1025"
set smtp_pass = 1N9W2YBG2eXQFkeZQhHwWg
set ssl_force_tls = yes # Require encrypted connection
# ===== Composition =====
set editor = "vim" # Text editor for composing/editing messages, your choice
set edit_headers = yes # Headers visible when editing
set charset = UTF-8 # set $LANG
set write_bcc = yes
unset use_domain
set realname = "Mothra "
set from = mothra.tokyo@pm.me # must match email address in this muttrc file
set use_from = yes
set sort = threads
set sort_aux = reverse-last-date-received
set copy= no
# for viewing html e-mails inside mutt, see ~/.mailcap settings
auto_view text/html
alternative_order text/enriched text/plain text text/html
```

Install mutt

Once installed and working the relevant directories and files should be like this.

```
drwx----- 3 muttpmb muttpmb 4096 May 20 22:45 .cache
drwx----- 3 muttpmb muttpmb 4096 May 20 22:45 .config
drwx----- 4 muttpmb muttpmb 4096 May 22 09:22 .gnupg
drwx----- 3 muttpmb muttpmb 4096 May 20 22:45 .local
-rw-r--r-- 1 muttpmb muttpmb   63 May 22 09:17 .mailcap
drwxrwxr-x 2 muttpmb muttpmb 4096 May 22 09:27 .mutt
drwx----- 3 muttpmb muttpmb 4096 May 20 22:45 .password-store
drwx----- 2 muttpmb muttpmb 4096 May 22 09:15 .w3m
```

Start mutt

If screen looks like this, exit mutt

```
$ mutt

q:Quit d:Del u:Undel s:Save m:Mail r:Reply g:Group ?:Help

Empty TUI screen          Enter q to Quit

---Mutt: (no mailbox) [Msgs:0]---(threads/reverse-last-date-received)-----
Some error message here
```

Start protonmail-bridge, it may not be running . OR

Mutt cannot find its config file, run as **mutt -F** <location of config file>

First run of mutt - the initialisation

```
$ mutt

q:Exit ?:Help
This certificate belongs to:
 127.0.0.1
Proton AG
Proton Mail
CH

This certificate was issued by:
 127.0.0.1
Proton AG
Proton Mail
CH

This certificate is valid
  from Wed, 20 May 2026 22:45:17 UTC
  to Tue, 15 May 2046 22:45:17 UTC
SHA1 Fingerprint: 2E58 BFB8 CAD6 4B2D D0DC 7C8C A3C2 83EE 82F9 1967
SHA256 Fingerprint: 8EF8 4B7F ADF4 BDE7 C83B 6357 A386 12CA
                    1529 1C3B 42EA F097 8932 FF05 93EE B2B7

WARNING: Server hostname does not match certificate

-- Mutt: SSL Certificate check (certificate 1 of 1 in chain)
(r)eject, accept (o)nce, (a)ccept always
```

Push **a** *accept always*.

Note:

- The o option will result in having to do this every time mutt is started.
- The a option will result in mutt opening in the INBOX time it is started.
- If it can't store the SSL certificates. Check location of certificate file in the muttrc file against reality.

Opening screen – the INBOX

q:Quit d:Del u:Undel s:Save m:Mail r:Reply g:Group ?:Help									
1	N	May 20	Dxxx Txxxxxxxxx	(51K)	xxxxxx xxxxx xxx xxxxx xxxxxx				
2	N	May 20	Yxxxxxx Axxxxxx	(37K)	xxxx xxx xxx xxx xxxxxx xxxxxxxxxxxxxxxxxxxx				
3	N +	May 20	Hxxx	(35K)	xxx xxxxxx xxxxx xxxxxxxxxxxx				
4	N +	May 20	Hxxx	(18K)	xxx xxxxxx xxxxx xxxxxxxxxxxx				
5	N +	May 20	Sxxxx Mxxxxxxxxx	(106K)	xxxxxxxxxxx xxx xxxxxx xxxxxxxxxxx xxx xxxxx xxxxx				
6	N +	May 20	Ixxxxx	(28K)	xxxxxxxxxxx xxxxx xxxxx xxxxxxxxxxxx				
7	r +	May 17	Pxxxxxxxxxx (Pxx	(8.0K)	xxx xxxxxxxx xxxxx xxxxxxxx xxxxxx xx xxxxxxxx				
8	+	May 17	Mxxxxxx (xxxxxx	(12K)	↳				
9	r +	May 17	Lxxx (Pxxxxxx xx	(16K)	↳				
Sender name					Mail Subject				
45	N +	May 18	Sxxxxxx	(106K)	xxxxxxxx xxx xx xxxxxx xxxxxxxxxxxxxx xx xxxx				
46	r T	May 18	Vxxxxxxxx Gxxxx	(113K)	xxx xxx xxxxxxxxxxx xxxxx				
47	+	May 18	Vxxxxxxxx Gxxxx	(118K)	↳				
48	r +	May 18	Axxx Zxxxxxx	(10K)	xxxx xxxxxxxxxxxxxx xx xxxxx xxxxx				
---Mutt: =INBOX [Msgs:2167 New:1671 Flag:5 Post:589 147M]---(threads/reverse-last-date-									

Navigation between folders - Push **c** to change folder

---Mutt: =INBOX [Msgs:2167 New:1671 Flag:5 Post:589 147M]---(threads/reverse-last-date-									
Open mailbox ('?' for list):									

Enter **?** to list folders

y:Exit c:Chdir m:Mask ?:Help		
1	IMAP	All Mail
2	IMAP	Archive
3	IMAP	Drafts
4	IMAP	Folders/
5	IMAP	INBOX
6	IMAP	Labels/
7	IMAP	Sent
8	IMAP	Spam
9	IMAP	Starred
10	IMAP	Trash
-- Mutt: Directory [imap://localhost:1143/], File mask: !^\.[^.]		

- **All Mail** in Mutt, contains the contents of the INBOX, Sent and Drafts.
- **Folders/** No individuals mails are listed when Folders/ is entered into only the subfolders are visible. No mail will be listed in any subfolder within Folders/. The mail contained in **Folders/** can be accessed in the **All Mail** folder. That limitation of has observed with other mail systems.

Recovered Messages This is a mutt specific temporary container for managing emails that have failed within mutt, this container is not part of Protonmail.

4	IMAP	Folders/
5	IMAP	INBOX
6	IMAP	Labels/
7	IMAP	Recovered Messages
8	IMAP	Sent

If the container exists then it contains emails that require processing or deletion. When the container has been emptied the *Recovered Messages* folder will no longer appear on the top-level folder screen. To clear contents, go into the *Recovered Messages* folder either delete them or action as required.

Sending mail - The basics

```
q:Quit  d:Del  u:Undel  s:Save  m:Mail  r:Reply  g:Group  ?:Help
 1 N   May 20 Dxxx Txxxxxxxxx ( 51K) xxxxxx xxxxx xxx xxxxx xxxxxx
 2 N   May 20 Yxxxxxxxx Axxxxxx ( 37K) xxxx xxx xxx xxx xxxxxx xxxxxxxxxxxxxxxxxxxx
 3 N + May 20 Hxxx              ( 35K) xxx xxxxxx xxx xxxxxxxxxxxx
 4 N + May 20 Hxxx              ( 18K) xxx xxxxxx xxx xxxxxxxxxxxx
 5 N + May 20 Sxxxx Mxxxxxxxx (106K) xxxxxxxxxxx xxx xxxxxx xxxxxxxxxxx xxx xxx xxxxx
 6 N + May 20 Ixxxx              ( 28K) xxxxxxx xxx xxx xxxxxxxx
 7 r + May 17 Pxxxxxxxx (Pxx (8.0K) xxx xxxxxxx xxx xxx xxxxxx xxxxxx xx xxxxxxx
 8   + May 17 Mxxxx (xxxxxx ( 12K)  L>
 9 r + May 17 Lxxx (Pxxxx xx ( 16K)    L>

45 N + May 18 Sxxxxxx          (106K) xxxxxxx xxx xx xxxxxx xxxxxxxxxxx xxx xxxx
46 r T May 18 Vxxxxxxxx Gxxxx (113K) xxx xxxx xxxxxxxxxxx xxxxx
47   + May 18 Vxxxxxxxx Gxxxx (118K)  L>
48 r + May 18 Axxx Zxxxxxx      ( 10K) xxxx xxxxxxxxxxx xxx xxxx xxxx
---Mutt: =INBOX [Msgs:2167 New:1671 Flag:5 Post:589 147M]---(threads/reverse-last-date-
```

Push **m** to initiate mail composition.

```
45 N + May 18 Sxxxxxx          (106K) xxxxxxx xxx xx xxxxxx xxxxxxxxxxx xxx xxxx
46 r T May 18 Vxxxxxxxx Gxxxx (113K) xxx xxxx xxxxxxxxxxx xxxxx
47   + May 18 Vxxxxxxxx Gxxxx (118K)  L>
48 r + May 18 Axxx Zxxxxxx      ( 10K) xxxx xxxxxxxxxxx xxx xxxx xxxx
---Mutt: =INBOX [Msgs:2167 New:1671 Flag:5 Post:589 147M]---(threads/reverse-last-date-
Recall postponed message? ([yes]/no/?):
```

Enter **n** Fill in the **To** field and push enter.

Proton mail groups cannot be used as mail recipients.

Recipients address lists are comma separated: godzilla@overthere.com,mothra@pm.me

```
45 N + May 18 Sxxxxxx          (106K) xxxxxxx xxx xx xxxxxx xxxxxxxxxxx xxx xxxx
46 r T May 18 Vxxxxxxxx Gxxxx (113K) xxx xxxx xxxxxxxxxxx xxxxx
47   + May 18 Vxxxxxxxx Gxxxx (118K)  L>
48 r + May 18 Axxx Zxxxxxx      ( 10K) xxxx xxxxxxxxxxx xxx xxxx xxxx
---Mutt: =INBOX [Msgs:2167 New:1671 Flag:5 Post:589 147M]---(threads/reverse-last-date-
To: godzilla@overthere.com
```

Fill in the **Subject** field and push enter

```
45 N + May 18 Sxxxxxx          (106K) xxxxxxx xxx xx xxxxxx xxxxxxxxxxx xxx xxxx
46 r T May 18 Vxxxxxxxx Gxxxx (113K) xxx xxxx xxxxxxxxxxx xxxxx
47   + May 18 Vxxxxxxxx Gxxxx (118K)  L>
48 r + May 18 Axxx Zxxxxxx      ( 10K) xxxx xxxxxxxxxxx xxx xxxx xxxx
---Mutt: =INBOX [Msgs:2167 New:1671 Flag:5 Post:589 147M]---(threads/reverse-last-date-
Subject: See you in Tokyo!
```

The text editor will open, use the text editor window to compose the message.

Composing and editing email message:

- All lines can be edited except the first.
- Be aware altering the first line **Real Name** may cause problems with contact lists of the recipient(s) of email.
- *No Reply* can be used as the real name, see previous comment.
- Email address lists are comma delimited.

```
From: Mothra mothra.tokyo@pm.me
To: Godzilla@overthere.world
Cc:
Bcc:
Subject: See You in Tokyo!

Breakfast about 7:30

FYI Ghidorah will be arriving in the weekend
~
```

Within the editor save email like a regular file.

The mutt confirmation screen will automagically appear.

Files may be attached at this time.

```
y:Send q:Abort t:To c:CC s:Subj a:Attach file d:Descrip ?:Help
  From: Mothra <mothra.tokyo@pm.me>
  To: Godzilla@overthere.world
  Cc:
  Bcc:
  Subject: See you in Tokyo!
  Reply-To:
  Fcc: =Sent
  Mix: <no chain defined>
  Security: None

-- Attachments
- I      1 /var/tmp/mutt-fred01-1002-62202-85399166 [text/pl

-- Mutt: Compose [Approx. msg size: 0.1K  Atts: 1]-----
```

Push **y** to send mail.

The following messages will appear in quick succession, “Sending message” may take some time to process

```
-- Mutt: Compose [Approx. msg size: 0.1K  Atts: 1]-----
SSL/TLS connection using TLS1.3 (ECDHE-RSA/AES-128-GCM/AEAD)
```

```
Sending message ... OK/0.3K (0%)

Saving Fcc to sent

Mail sent
```

Once mail has been sent, mutt will revert to the INBOX view.

Push **q** to quit the mutt mail client

Sending mail by command line – The basics

- Only one email address for each Cc (-c) and Bcc (-b), multiple -c and -b options are permitted
- Only one attachment for the attachment option (-a), multiple -a options are permitted.
- "--" precedes the recipient email address(es) to separate it from the file names, can be used with other options.
- A multiple recipient list is a comma separated list.
- Messages without a body require **/dev/null** as the message body. If no body provided the mutt TUI window will open.
- Mutt can use an alternative configuration file(s) that are specified with the -F option.
- Message body can be a file or a heredoc.

```
$ echo "Message body goes here" | mutt -s "Subject goes here" -c tster1@lumpy.co \
    -c tster2@lumpy.co -a /tmp/attachment1 -a /tm/attachment2 - tster0@lumpy.co

$ mutt -s "Message body from a file" -c tster2@lumpy.co \
    -a /tmp/attachment1 - tster0@lumpy.co,tster1@lumpy.co < /tmp/body-text-file

$ mutt -s "No Message body" -c tster0@lumpy.com -a /tmp/attachment1 \
    -- tster1@lumpy.co,tster2@lumpy.co < /dev/null

$ mutt -F /home/muttpmb/.mutt/mutt-test1-rc -s "Using an alternative config file" \
    -c tster1@lumpy.co - tster0@lumpy.co < /dev/null

$ mutt -s "Message body from a heredoc -c tster0@lumpy.com -a /tmp/attachment1 \
    -- tster1@lumpy.co,tster2@lumpy.co << msg_end
```

The message body text will appear exactly like this section.

Commands and functions can be used in this section

See – next page for an example.

msg_end

Fun Fact:

If the Proton Mail account owner of the bridge is included in the recipients they will be alerted to mails that have been sent via protonmail-bridge. The account owner must have alerts enabled on the account.

If the Proton Mail account owner of the bridge is not included in the recipients they will only see the mail in their **Sent** folder.

Examples

```
$ df -h | mutt -s "Storage Usage on $(uname -n) at $(date)" -c tster1@lumpy.co -- tster0@lumpy.co
```

Input using a heredoc with material sourced from local function and command plus attachments

```
#!/usr/bin/bash
#Script name: mutt-pmbridge-check

log_dir=${HOME}/.local/share/protonmail/bridge-v3/logs
bri_log=$(ls -ltr $log_dir | grep '_bri_' | tail -n1)
lau_log=$(ls -ltr $log_dir | grep '_lau_' | tail -n1)

function disk_usage(){
# only list directories
  cd ~
  du --apparent-size -sh ./.*?*/ | sed 's/\.\.\/' | awk '{printf "%6s %s\n", $1, $2}'
  du --apparent-size -sh ./ */ | sed 's/\.\.\/' | awk '{printf "%6s %s\n", $1, $2}'
} #-----

msg_subject="$(uname -n) Proton Mail Bridge report"

/usr/bin/mutt -s "$msg_subject" -a ${log_dir}/${lau_log} -a ${log_dir}/${bri_log} -- tester0@lumpy.com << msg_end

$(date)

Storage usage in home directory
-----
  Size Directory
$(disk_usage)
-----

Total Storage Usage
-----
$(df -h)
-----

** Latest protonmail-bridge log files attached.

msg_end
```

pmbridge-start Start protonmail using nohup

```
#!/usr/bin/bash
now=$(date +%Y%m%d-%H%M%S)
log=${HOME}/pmbridge/pmbridge_start_${now}_log
echo "STARTED: $(date)" > $log
echo "===== " >> $log
nohup /usr/bin/protonmail-bridge -n >> $log 2>&1 &
exit $?
# Alternatively: $log can be replaced with /dev/null in the nohup line
```

pmbridge-stop Kills protonmail-bridge using the process id stored in the lock file

```
#!/usr/bin/bash
proc_id=$(cat ${HOME}/.cache/protonmail/bridge-v3/bridge-v3.lock)
pid_tmp=$(ps -o pid= $proc_id)
RC=$?
if [[ ${RC} = "0" ]]; then
    kill $proc_id
else
    echo "protonmail-bridge not active"
fi
```

pmbridge-check Checks IMAP and SMTP ports, processes and storage capacity

```
#!/usr/bin/bash
echo "-----"
(echo > /dev/tcp/127.0.0.1/1143) > /dev/null 2>&1
RC=$?
if [[ ${RC} == "0" ]]; then
    echo "IMAP port 1143 - active"
else
    echo "IMAP port 1143 - not active"
fi
(echo > /dev/tcp/127.0.0.1/1025) > /dev/null 2>&1
RC=$?
if [[ ${RC} == "0" ]]; then
    echo "SMTP port 1025 - active"
else
    echo "SMTP port 1025 - not active"
fi
echo -e "-----\n"
echo "Log files: .local/share/protonmail/bridge-v3/logs"

parent_pid="$(cat ${HOME}/.cache/protonmail/bridge-v3/bridge-v3.lock)"
parent_pgid=$(ps -o pgid= $parent_pid)
RC=$?


if [[ ${RC} = "1" ]]; then
    echo -e "-----\n"
    echo -e "protonmail-bridge not running\n"
    echo -e "NOTE: If protonmail-bridge has just started, check again soon.\n"
    exit 1
fi
echo "-----"
ps -ej | grep "$parent_pgid" | awk 'BEGIN { printf "      PID      PGID\tCMD(Short)\n"} {printf " %7s %7s\t%s\n",$1,$2,$6}'
echo "-----"
echo "Process ID to terminate protonmail-bridge: $parent_pid"
echo "-----"
echo "Directories and files larger than 1 MiB in $HOME top-level"
cd ~
du --apparent-size -sh -t 1M .??*
du --apparent-size -sh -t 1M *
```

Linux Desktop

Log into the desktop where mutt usage is required.

Install the Proton Mail Bridge GUI application and log into the Proton Mail account to update bridge and synchronise it with the Proton Mail account.

Credentials used for the configuration of mutt.



To install and use mutt follow the guide starting at page 6.

Thunderbird on Linux desktop could be a better option. Thunderbird is supported by Proton and has command line options to send mail.

Linux Test Environment

	<u>Server</u>	<u>Desktop</u>
Protonmail-bridge	3.24.2	3.24.2
Mutt	2.2.13	2.2.13
Ubuntu	26.04 LTS	--
Zorin		18.1
		VirtualBox