## RESOURCE HANDLING





## AGENDA

- A resource ?
- Fundamental SW Design challenges
- Basic building block RAII
- The full monty boost::shared\_ptr<>
- Exercise structure





# ARESOURCE?





## A RESOURCE?

- Brainstorm What do you consider a Resource Handling challenge?
  - What is a resource in sw "terms"?
  - In which situations do you foresee challenges?





# FUNDAMENTAL SW DESIGN CHALLENGE





## FUNDAMENTAL SW DESIGN CHALLENGE

- Design and implement a system that
  - Garbage collection exists and ensures that a resource is released when no one uses it (multiple parties may share a resource)
  - It must be thread-safe
    - The resource itself is NOT protected, but its destruction must be





## **ABSTRACT EXAMPLE**

- Following usage scenario must work
  - Allocate resource in Thread A
  - Pass it to Thread B while keeping it in A
  - Relinquish usage in Thread B followed by Thread A
    - or other way round not known
  - Resource is hereafter relinquished
- Usefulness?
  - Our Message Queues :)





• Problem where?

```
01 void f()
02 {
03    Client* c = new Client;
04    Data* d = acquireData(c);
05    if(...)
06     return;
07
08    if(...)
09     throw SomeError("Bad input");
10
11    delete d;
12    delete c;
13 }
```





- Problem where?
- Function throws an exception...

```
01 void f()
02 {
03    Client* c = new Client;
04    Data* d = acquireData(c);
05    if(...)
06     return;
07
08    if(...)
09     throw SomeError("Bad input");
10
11    delete d;
12    delete c;
13 }
```





- Problem where?
- Function throws an exception...
- If statement true
  - return leave function
  - Memory not deallocated

```
01  void f()
02  {
03    Client* c = new Client;
04    Data* d = acquireData(c);
05    if(...)
06    return;
07
08    if(...)
09     throw SomeError("Bad input");
10
11    delete d;
12    delete c;
13 }
```





- Problem where?
- Function throws an exception...
- If statement true
  - return leave function
  - Memory not deallocated
- If statement true
  - Exception thrown function left
  - Memory not deallocated

```
01 void f()
02 {
03    Client* c = new Client;
04    Data* d = acquireData(c);
05    if(...)
06     return;
07

08    if(...)
09     throw SomeError("Bad input");
10
11    delete d;
12    delete c;
13 }
```





- Problem where?
- Function throws an exception...
- If statement true
  - return leave function
  - Memory not deallocated
- If statement true
  - Exception thrown function left
  - Memory not deallocated
- If everything went well
  - The only path where things get cleaned up...

```
01  void f()
02  {
03    Client* c = new Client;
04    Data* d = acquireData(c);
05    if(...)
06     return;
07
08    if(...)
09     throw SomeError("Bad input");
10
11    delete d;
12    delete c;
13 }
```





# BASIC BUILDING BLOCK - RAII





## **BASIC BUILDING BLOCK - RAII**

- Managing memory is often a problem or challenge,
  - ensuring correctness forgetting to deallocate (message etc.)
  - dealing with exceptions
- Idiom: Resource Acquisition Is Initialization
  - Wrap up all resources in their own object that handles their lifetime and put object on stack





```
01 template<typename T>
02 class RAII
03 {
04 public:
05   explicit RAII( T* p = 0 ) : p_(p) {}
06
07   ~RAII() { delete p_; }
08
09   // Smart pointer idiom mixed-in!
10   T& operator*() const { return *p_; }
11   T* operator->() const { return p_; }
12 private:
13   T* p_;
14 };
```

```
01 {
02     RAII<std::vector<int> > r( new std::vector() );
03     std::cout << r->size() << std::endl;
04 }</pre>
```





RAll instance is constructed and passed instance

```
01 template<typename T>
02 class RAII
03 {
04 public:
05    explicit RAII( T* p = 0 ) : p_(p) {}
06
07    ~RAII() { delete p_; }
08
09    // Smart pointer idiom mixed-in!
10    T& operator*() const { return *p_; }
11    T* operator->() const { return p_; }
12 private:
13    T* p_;
14 };
```

```
01 {
02     RAII<std::vector<int> > r( new std::vector() );
03     std::cout << r->size() << std::endl;
04 }</pre>
```





- RAII instance is constructed and passed instance
- Arrow operator in use
  - Returns pointer to object -> method size() called on std::vector<>

```
01 template<typename T>
02 class RAII
03 {
04 public:
05    explicit RAII( T* p = 0 ) : p_(p) {}
06
07    ~RAII() { delete p_; }
08
09    // Smart pointer idiom mixed-in!
10    T& operator*() const { return *p_; }
11    T* operator->() const { return p_; }
12    private:
13    T* p_;
14 };
```

```
01 {
02     RAII<std::vector<int> > r( new std::vector() );
03     std::cout << r->size() << std::endl;
04 }</pre>
```





- RAII instance is constructed and passed instance
- Arrow operator in use
  - Returns pointer to object -> method size() called on std::vector<>
- Scope left
  - Destructor called
  - std::vector<> deleted

```
01 template<typename T>
02 class RAII
03 {
04 public:
05    explicit RAII( T* p = 0 ) : p_(p) {}
06

07    ~RAII() { delete p_; }
08

09    // Smart pointer idiom mixed-in!
10    T& operator*() const { return *p_; }
11    T* operator->() const { return p_; }
12    private:
13    T* p_;
14 };
```

```
01 {
02     RAII<std::vector<int> > r( new std::vector() );
03     std::cout << r->size() << std::endl;
04 }</pre>
```





# THE FULL MONTY BOOST::SHARED\_PTR<>





## THE FULL MONTY - BOOST::SHARED\_PTR<>

- Fixing concrete example
- More eleborate example
- Handling cyclic dependencies
- Summary (boost smart pointers)





OLD

```
NEW
```

```
01 void f()
02 {
     Client* c = new Client;
     Data* d = acquireData(c);
04
05
06
     if(...)
      return;
08
     if(...)
     throw SomeError("Bad input");
11
     delete d;
     delete c;
14 }
```

• Solved?

```
01 void f()
02 {
03    boost::shared_ptr<Client*> c(new Client);
04    boost::shared_ptr<Data*> d = acquireData(c);
05
06    if(...)
07        return;
08
09    if(...)
10        throw SomeError("Bad input");
11 }
```





OLD

```
01 void f()
02 {
03    Client* c = new Client;
04    Data* d = acquireData(c);
05
06    if(...)
07        return;
08
09    if(...)
10        throw SomeError("Bad input");
11
12    delete d;
13    delete c;
14 }
```

```
01 void f()
02 {
03    boost::shared_ptr<Client*> c(new Client);
04    boost::shared_ptr<Data*> d = acquireData(c);
05
06    if(...)
07        return;
08
09    if(...)
10        throw SomeError("Bad input");
11 }
```

- Solved?
- Both c and d are shared\_ptr<>
- Both calls to delete removed (happens indirectly)





OLD

```
01 void f()
02 {
     Client* c = new Client;
     Data* d = acquireData(c);
05
06
     if(...)
07
          return;
08
     if(...)
       throw SomeError("Bad input");
11
     delete d;
     delete c;
14 }
```

```
01 void f()
02 {
03    boost::shared_ptr<Client*> c(new Client);
04    boost::shared_ptr<Data*> d = acquireData(c);
05

06    if(...)
07        return;
08
09    if(...)
10        throw SomeError("Bad input");
11 }
```

- Solved?
- Both c and d are shared\_ptr<>
- Both calls to delete removed (happens indirectly)
- if statement true...
  - Function returns
  - shared\_ptr<> cleans up for both c and d -> YES :-)





OLD

```
01 void f()
02 {
     Client* c = new Client;
     Data* d = acquireData(c);
05
06
     if(...)
07
          return;
08
     if(...)
        throw SomeError("Bad input");
11
      delete d;
      delete c;
14 }
```

```
01 void f()
02 {
03    boost::shared_ptr<Client*> c(new Client);
04    boost::shared_ptr<Data*> d = acquireData(c);
05
06    if(...)
07        return;
08
09    if(...)
10        throw SomeError("Bad input");
11 }
```

- Solved?
- Both c and d are shared\_ptr<>
- Both calls to delete removed (happens indirectly)
- if statement true...
  - Function returns
  - shared\_ptr<> cleans up for both c and d -> YES :-)





#### CODE

```
01 boost::shared_ptr<int> ee;
02 boost::shared_ptr<int> aa(new int(42));
03
04 std::cout << aa << "\t" << *aa << "\t" << aa.use_count() << std::endl;
05 {
06    boost::shared_ptr<int> bb(aa);
07    ++(*bb);
08    std::cout << bb << "\t" << *bb << "\t" << *bb.use_count() << std::endl;
09
10    ee = bb;
11    std::cout << ee << "\t" << *ee << "\t" <<ee.use_count() << std::endl;
12  }
13
14    ee.reset();
15    std::cout << aa << "\t" << *aa << "\t" <<aa.use_count() <<std::endl;
16
17    aa.reset();
18    std::cout << aa << "\t" << "xx" << "\t" <<aa.use_count() <<std::endl;</pre>
```

01	Stdout readout:						
02		Pointer	Value	Use Count			
03	1)	003756D0	42	1			
04	2)	003756D0	43	2			
05	3)	003756D0	43	3			
06	4)	003756D0	43	1			
07	5)	00000000	XX	0			





#### **CODE**

```
01 boost::shared ptr<int> ee;
02 boost::shared ptr<int> aa(new int(42));
03
04 std::cout << aa << "\t" << *aa << "\t" << aa.use_count() << std::endl;
     boost::shared_ptr<int> bb(aa);
06
07 ++ (*bb);
     std::cout << bb << "\t" << *bb << "\t" <<bb.use_count() <<std::endl;
09
     ee = bb;
     std::cout << ee << "\t" << ee.use_count() <<std::endl;
12 }
13
14 ee.reset();
15 std::cout << aa << "\t" << *aa << "\t" <<aa.use_count() <<std::endl;
17 aa.reset();
18 std::cout << aa << "\t" << "xx" << "\t" <<aa.use_count() <<std::endl;
```

Create a shared\_ptr<>

01	Stdout readout:						
02		Pointer	Value	Use Count			
03	1)	003756D0	42	1			
04	2)	003756D0	43	2			
05	3)	003756D0	43	3			
06	4)	003756D0	43	1			
07	5)	00000000	XX	0			





#### **CODE**

```
01 boost::shared_ptr<int> ee;
02 boost::shared ptr<int> aa(new int(42));
03
04 std::cout << aa << "\t" << *aa << "\t" << aa.use count() << std::endl;
06
     boost::shared_ptr<int> bb(aa);
07 ++ (*bb);
     std::cout << bb << "\t" << *bb << "\t" <<bb.use_count() <<std::endl;
09
     ee = bb;
     std::cout << ee << "\t" << ee.use_count() <<std::endl;
12 }
13
14 ee.reset();
15 std::cout << aa << "\t" << *aa << "\t" <<aa.use_count() <<std::endl;
17 aa.reset();
18 std::cout << aa << "\t" << "xx" << "\t" <<aa.use_count() <<std::endl;
```

- Create a shared\_ptr<>
- Print out stats

01	Sto	dout reado	ut:		
02		Pointer	Value	Use Count	
03	1)	003756D0	42	1	
04	2)	003756D0	43	2	
05	3)	003756D0	43	3	
06	4)	003756D0	43	1	
07	5)	0000000	XX	0	





#### CODE

```
01 boost::shared_ptr<int> ee;
02 boost::shared_ptr<int> aa(new int(42));
03
04 std::cout << aa << "\t" << *aa << "\t" << aa.use_count() << std::endl;
05 {
06    boost::shared_ptr<int> bb(aa);
07    ++(*bb);
08    std::cout << bb << "\t" << *bb << "\t" << bb.use_count() << std::endl;
09
10    ee = bb;
11    std::cout << ee << "\t" << *ee << "\t" <<ee.use_count() << std::endl;
12  }
13
14    ee.reset();
15    std::cout << aa << "\t" << *aa << "\t" <<aa.use_count() <<std::endl;
16
17    aa.reset();
18    std::cout << aa << "\t" << "xx" << "\t" <<aa.use_count() <<std::endl;</pre>
```

- Create a shared\_ptr<>
- Print out stats
- Create a copy

01	Stdout readout:							
02		Pointer	Value	Use Count				
03	1)	003756D0	42	1				
04	2)	003756D0	43	2				
05	3)	003756D0	43	3				
06	4)	003756D0	43	1				
07	5)	0000000	XX	0				





#### CODE

```
01 boost::shared_ptr<int> ee;
02 boost::shared_ptr<int> aa(new int(42));
03
04 std::cout << aa << "\t" << *aa << "\t" << aa.use_count() << std::endl;
05 {
06 boost::shared_ptr<int> bb(aa);
07 ++(*bb);
08 std::cout << bb << "\t" << *bb << "\t" << *bb.use_count() << std::endl;
09
10 ee = bb;
11 std::cout << ee << "\t" << *ee << "\t" <<ee.use_count() << std::endl;
12 }
13
14 ee.reset();
15 std::cout << aa << "\t" << *aa << "\t" <<aa.use_count() <<std::endl;
16
17 aa.reset();
18 std::cout << aa << "\t" << "xx" << "\t" <<aa.use_count() <<std::endl;</pre>
```

- Create a shared\_ptr<>
- Print out stats
- Create a copy
- Increment *shared* integer

## AARHUS UNIVERSITY AARHUS UNIVERSITY SCHOOL OF ENGINEERING

01	Sto	Stdout readout:						
02		Pointer	Value	Use Count				
03	1)	003756D0	42	1				
04	2)	003756D0	43	2				
05	3)	003756D0	43	3				
06	4)	003756D0	43	1				
07	5)	0000000	XX	0				

#### CODE

```
01 boost::shared_ptr<int> ee;
02 boost::shared_ptr<int> aa(new int(42));
03
04 std::cout << aa << "\t" << *aa << "\t" << aa.use_count() << std::endl;
05 {
06    boost::shared_ptr<int> bb(aa);
07    ++(*bb);
08    std::cout << bb << "\t" << *bb << "\t" << bb.use_count() << std::endl;
09
10    ee = bb;
11    std::cout << ee << "\t" << *ee << "\t" <<ee.use_count() << std::endl;
12 }
13
14    ee.reset();
15    std::cout << aa << "\t" << *aa << "\t" <<aa.use_count() <<std::endl;
16
17    aa.reset();
18    std::cout << aa << "\t" << "xx" << "\t" <<aa.use_count() <<std::endl;</pre>
```

- Create a shared\_ptr<>
- Print out stats
- Create a copy
- Increment shared integer
- Print out stats



01	Sto	Stdout readout:						
02		Pointer	Value	Use	Count			
03	1)	003756D0	42		1			
04	2)	003756D0	43		2			
05	3)	003756D0	43		3			
06	4)	003756D0	43		1			
07	5)	0000000	XX		0			

#### CODE

```
01 boost::shared ptr<int> ee;
02 boost::shared ptr<int> aa(new int(42));
03
04 std::cout << aa << "\t" << *aa << "\t" << aa.use_count() << std::endl;
     boost::shared ptr<int> bb(aa);
06
07 ++ (*bb);
     std::cout << bb << "\t" << *bb << "\t" <<bb.use_count() <<std::endl;
     ee = bb;
     std::cout << ee << "\t" << ee.use_count() <<std::endl;
12 }
13
14 ee.reset();
15 std::cout << aa << "\t" << *aa << "\t" <<aa.use_count() <<std::endl;
17 aa.reset();
18 std::cout << aa << "\t" << "xx" << "\t" <<aa.use_count() <<std::endl;
```

- Create a shared\_ptr<>
- Print out stats
- Create a copy
- Increment shared integer
- Print out stats



01	Sto	dout reado	ut:		
02		Pointer	Value	Use Cou	ınt
03	1)	003756D0	42	1	
04	2)	003756D0	43	2	
05	3)	003756D0	43	3	
06	4)	003756D0	43	1	
07	5)	00000000	XX	0	



#### CODE

```
01 boost::shared ptr<int> ee;
02 boost::shared ptr<int> aa(new int(42));
03
04 std::cout << aa << "\t" << *aa << "\t" << aa.use_count() << std::endl;
     boost::shared ptr<int> bb(aa);
06
07 ++ (*bb);
     std::cout << bb << "\t" << *bb << "\t" <<bb.use_count() <<std::endl;
     ee = bb;
     std::cout << ee << "\t" << *ee << "\t" <<ee.use count() <<std::endl;
12 }
13
14 ee.reset();
15 std::cout << aa << "\t" << *aa << "\t" <<aa.use_count() <<std::endl;
17 aa.reset();
18 std::cout << aa << "\t" << "xx" << "\t" <<aa.use_count() <<std::endl;
```

- Create a shared\_ptr<>
- Print out stats
- Create a copy
- Increment shared integer
- Print out stats



01	Stdout readout:							
02		Pointer	Value	Use Count				
03	1)	003756D0	42	1				
04	2)	003756D0	43	2				
05	3)	003756D0	43	3				
06	4)	003756D0	43	1				
07	5)	0000000	XX	0				



#### CODE

```
01 boost::shared_ptr<int> ee;
02 boost::shared_ptr<int> aa(new int(42));
03
04 std::cout << aa << "\t" << *aa << "\t" << aa.use_count() << std::endl;
05 {
06    boost::shared_ptr<int> bb(aa);
07    ++(*bb);
08    std::cout << bb << "\t" << *bb << "\t" <<bb.use_count() <<std::endl;
09
10    ee = bb;
11    std::cout << ee << "\t" << *ee << "\t" <<ee.use_count() <<std::endl;
12 }
13
14    ee.reset();
15    std::cout << aa << "\t" << *aa << "\t" <<aa.use_count() <<std::endl;
16
17    aa.reset();
18    std::cout << aa << "\t" << "xx" << "\t" <<aa.use_count() <<std::endl;</pre>
```

#### **OUTPUT**

01 Stdout readout:
02 Pointer Value Use Count
03 1) 003756D0 42 1
04 2) 003756D0 43 2
05 3) 003756D0 43 3
06 4) 003756D0 43 1
07 5) 00000000 xx 0

- Create a shared\_ptr<>
- Print out stats
- Create a copy
- Increment shared integer
- Print out stats
- The charge a copy (only alive in scope)

- bb is destroyed
- ee is reset



#### CODE

```
01 boost::shared ptr<int> ee;
02 boost::shared ptr<int> aa(new int(42));
03
04 std::cout << aa << "\t" << *aa << "\t" << aa.use_count() << std::endl;
     boost::shared ptr<int> bb(aa);
06
     ++(*bb);
     std::cout << bb << "\t" << *bb << "\t" <<bb.use_count() <<std::endl;
09
     ee = bb;
     std::cout << ee << "\t" << *ee << "\t" <<ee.use_count() <<std::endl;
12 }
13
14 ee.reset();
15 std::cout << aa << "\t" << *aa << "\t" <<aa.use_count() <<std::endl;
16
17 aa.reset();
18 std::cout << aa << "\t" << "xx" << "\t" <<aa.use_count() <<std::endl;
```

#### **OUTPUT**

01 Stdout readout:
02 Pointer Value Use Count
03 1) 003756D0 42 1
04 2) 003756D0 43 2
05 3) 003756D0 43 3
06 4) 003756D0 43 1
07 5) 00000000 xx 0

- Create a shared\_ptr<>
- Print out stats
- Create a copy
- Increment shared integer
- Print out stats
- The charge a copy (only alive in scope)

- bb is destroyed
- ee is reset
- Print out stats

#### CODE

```
01 boost::shared ptr<int> ee;
02 boost::shared ptr<int> aa(new int(42));
03
04 std::cout << aa << "\t" << *aa << "\t" << aa.use_count() << std::endl;
     boost::shared ptr<int> bb(aa);
06
     ++(*bb);
     std::cout << bb << "\t" << *bb << "\t" <<bb.use_count() <<std::endl;
09
     std::cout << ee << "\t" << *ee << "\t" <<ee.use_count() <<std::endl;
12 }
13
14 ee.reset();
15 std::cout << aa << "\t" << aa.use_count() <<std::endl;
17 aa.reset();
18 std::cout << aa << "\t" << "xx" << "\t" <<aa.use_count() <<std::endl;
```

#### **OUTPUT**

01 Stdout readout:
02 Pointer Value Use Count
03 1) 003756D0 42 1
04 2) 003756D0 43 2
05 3) 003756D0 43 3
06 4) 003756D0 43 1
07 5) 00000000 xx 0

- Create a shared\_ptr<>
- Print out stats
- Create a copy
- Increment shared integer
- Print out stats
- The Chief a copy (only alive in scope)

- bb is destroyed
- ee is reset
- Print out stats
- aa is reset



#### CODE

```
01 boost::shared ptr<int> ee;
02 boost::shared ptr<int> aa(new int(42));
03
04 std::cout << aa << "\t" << *aa << "\t" << aa.use_count() << std::endl;
     boost::shared ptr<int> bb(aa);
06
     ++(*bb);
     std::cout << bb << "\t" << *bb << "\t" <<bb.use_count() <<std::endl;
09
     ee = bb;
     std::cout << ee << "\t" << ee.use_count() <<std::endl;
12 }
13
14 ee.reset();
15 std::cout << aa << "\t" << *aa << "\t" <<aa.use_count() <<std::endl;
17 aa.reset();
   std::cout << aa << "\t" << "xx" << "\t" <<aa.use count() <<std::endl;
```

#### **OUTPUT**

01	Sto	Stdout readout:							
02		Pointer	Value	Use Count					
03	1)	003756D0	42	1					
04	2)	003756D0	43	2					
05	3)	003756D0	43	3					
06	4)	003756D0	43	1					
07	5)	00000000	XX	0					

- Create a shared\_ptr<>
- Print out stats
- Create a copy
- Increment *shared* integer
- Print out stats


- bb is destroyed
- ee is reset
- Print out stats
- aa is reset
- Print out stats



Checke, a copy (only alive in scope)



- Problem
  - When objects are inter-dependent via shared pointers
- Consequence
  - Leaving scope decrements shared pointers but
    - Inter-dependies keeps them alive
    - Memory though shared pointers are used :-(







#### **CODE EXEMPLICATION**

Α	]	В
b_ : boost::shared_ptr <b></b>	]	a_ : boost::shared_ptr <a></a>
A(b_: boost::shared_ptr <b>)</b>	→	set(a : boost::shared_ptr <a>) : void</a>

```
01 struct B
02 {
03    void set(std::shared_ptr<A> a)
04    {
05         a_ = a;
06    }
07
08    std::shared_ptr<A> a_;
09 };
```

```
01 {
02    std::shared_ptr<B> tmpB(new B);
03    std::shared_ptr<A> tmpA(new A(tmpB));
04    tmpB->set(tmpA);
05 }
```

Leaves scope, but A points B and B to A => memory leak





```
01 struct A
02 {
03    A(std::shared_ptr<B> b)
04    : b_(b)
05    {
06
07    std::shared_ptr<B> b_;
08 };
```





```
01 struct A
02 {
03    A(std::shared_ptr<B> b)
04    : b_(b)
05    {
06
07    std::shared_ptr<B> b_;
08 };
```

- Create a weak\_ptr<>
  - Does *NOT* increment reference counter!
    - Whole point





- Create a weak\_ptr<>
  - Does NOT increment reference counter!
    - Whole point
- Convert weak\_ptr<> to shared\_ptr<>
  - Important to ensure it exists while using





- Create a weak\_ptr<>
  - Does *NOT* increment reference counter!
    - Whole point
- Convert weak\_ptr<> to shared\_ptr<>
  - Important to ensure it exists while using
- Remember to verify that the shared\_ptr<> actually points to something...





## SUMMARY (BOOST SMART POINTERS)

- boost::shared\_ptr & boost::shared\_array
  - A more general wrapping used in containers
  - Single object or an array of objects
  - You want it all and you are willing to pay for it
- boost::weak\_ptr
  - Typically used to break circular references
- boost::scoped\_ptr & boost::scoped\_array
  - Objects with short lifespan confined to function/object
  - Single object or an array of objects
  - Non-copyable (whole point)
- boost::intrusive\_ptr
  - Where OS or framework implement reference counting





## EXERCISE STRUCTURE





## **EXERCISE STRUCTURE**

- RAII and SmartPointer
- Counted Smart Pointer
- Templated Counted Smart Pointer (OPTIONAL)
- boost::shared\_ptr<>

Increase in feature set and complexity



