

Zurich ServiceNow AI Platform Capabilities

Last updated: January 16, 2026

Some examples and graphics depicted herein are provided for illustration only. No real association or connection to ServiceNow products or services is intended or should be inferred.

This PDF was created from content on docs.servicenow.com. The web site is updated frequently. For the most current ServiceNow product documentation, go to docs.servicenow.com.

Company Headquarters

2225 Lawson Lane
Santa Clara, CA 95054
United States
(408)501-8550

Dependency Views

ServiceNow® Dependency Views graphically displays an infrastructure view for a configuration item (CI) and the application or business services that it is part of and that it supports. Dependency Views indicates the status of its configuration items, and allows access to CIs related alerts, incidents, problems, changes, and services.

If Service Mapping is activated, Dependency Views maps are enhanced to display dependencies that reflect connections in service maps.

		Use
	Administer	• Dependency Views map
	• Create or modify map indicators • Create or modify map icons	• Dependency Views map menus and controls
Explore	• Create a predefined filter	• View a Dependency Views map
• Zurich • Domain separation and Dependency Views	• Create or modify Map Related Items • Create or modify Dependency Views menu actions • Create or edit a dependency type	• Change the layout of Dependency Views map • Filter the view of a Dependency Views map • Perform actions on nodes in a Dependency Views map

- Supported browsers for Dependency Views

Develop

- Developer training
- Developer documentation
- Properties for Dependency Views
- Components installed with Dependency Views

Integration

View metrics for CIs in a Dependency Views map

Troubleshoot and get help

- Ask or answer questions in the Now Community
- Search the Known Error Portal for known error articles
- Contact Customer Service and Support

Supported browsers for Dependency Views

The latest version or service pack of internet browsers are required to view and manipulate Dependency Views maps.

The Dependency Views module supports the latest version or service pack of the following browsers:

- Firefox with the latest ESR
- Chrome latest version
- Safari version 8 or later (latest is recommended)
- Microsoft Internet Explorer (IE) version 11 and Microsoft Edge.

The Dependency Views module is not supported on tablets and on mobile devices.

Domain separation and Dependency Views

Domain separation is unsupported in Dependency Views. Domain separation enables you to separate data, processes, and administrative tasks into logical groupings called domains. You can control several aspects of this separation, including which users can see and access data.

Support level: Basic

- Business logic: Ensure that data goes into the proper domain for the application's service provider use cases.
- The application supports domain separation at run time. The domain separation includes separation from the user interface, cache keys, reporting, rollups, and aggregations.
- The owner of the instance must set up the application to function across multiple tenants.

Sample use case: When a service provider (SP) uses chat to respond to a tenant-customer's message, the customer must be able to see the SP's response.

For more information on support levels, see [Application support for domain separation](#).

How domain separation works in Dependency Views

Dependency views are generated using both Configuration Item [cmdb_ci] and CI Relationship [cmdb_rel_ci] tables. The [cmdb_ci] table is domain separated, but the [cmdb_rel_ci] table is not. You can create relationships only by selecting two CIs. They should be in the same domain for you to be able to see them.

To be successful with domain separation in Dependency Views, make sure that relevant CIs are visible for the current domain. If the instance is domain separated, ServiceNow domain separation rules apply (see [Related information](#) link below).

Tenant domains will be able to see only their domain and global CIs.

Related topics

- [Domain separation for service providers](#)

Dependency Views map

ServiceNow® Dependency Views maps graphically display CIs that support application or business services and the relationships between the CIs.

The [CMDB Workspace](#) store app provides the [Unified Map](#) feature as an alternative to using Dependency Views. Unified Map combines the capabilities of Dependency Views and [Service Mapping](#) into a single map experience.

A ServiceNow service (application service or business service) is work or goods that are supported by an IT infrastructure. For example, delivering email service to an employee can require services such as email servers, web servers, and the work to configure the user's account.

A Dependency Views map has one starting point, called the root CI or root node of the map. The root CI is surrounded by a darker frame that repaints itself with a pulsing effect drawing the attention to the root CI. The maps can show both upstream and downstream dependencies for the root CI. By default the Dependency Views map displays 3 levels, both upstream and downstream relationships. Administrators can configure the number of levels displayed. The map collapses and expands clusters to make them easier to view. By default, clusters are collapsed.

In a Dependency Views map, map indicators indicate if a CI has any active, pending issues. You can investigate the tasks that are connected to a CI to get more details. When you return to the map from another form, the system restores the last map viewed, using the default filter and


layout settings. When you click the icon () on a CI record or on a task record that identifies a CI, the map opens.

Many of the relationships in map are created through the discovery process. You can also create, define, and delete CI relationships in the map. You can display the map from different perspectives and open specific records that relate to configuration items. The system refreshes the map automatically to reflect changes to the CMDB.

Note: CIs not extended from the Configuration Item [cmdb_ci] table, are not displayed in Dependency Views maps and in CI relation formatters.

The Dependency Views module is active in all instances, and includes demo data.

Dependency Views sample map



When you click the map icon [] on a CI record or on a task record that identify a CI, a map opens.


Roles

Users with the `itil` and `ecmdb_admin` roles can view maps and perform all actions in the map. Actions include access to the map views and saved filters, both from the lists in the map and from the **Saved Filters** module.

Dependency Views map menus and controls

Dependency Views maps contain the following menus and controls.

Dependency Views map



Map options


The following options are available across the top of the map.



Menu to save, load and export views of the map.

<Root CI>

Next to the menu icon is the name of the current root node (CI) of the map.



Enter the name of a CI, application service, or business service to load into the map. Alternatively, you can start typing to have the auto-complete feature present a list of CIs and services that match your partial value.

Vertical

Display the map in vertical view.

Horizontal

Display the map in horizontal view.

Radial	Display the map in radial view.
Force	Centers the elements around the parent CI, regardless of upstream or downstream relationships.
Group	Groups the elements according to their CI type.
Details	Displays related lists such as Problems, Changes and Related Services that are associated with the selected CI. - Click a service to highlight the CIs that are associated with that service. - Click Related Services, then double-click a service to display the map in the Event Management dashboard. If the Event Management plugin is active, then events and alerts are also displayed.
Settings	Set filters for the map. Use the navigation tools to increase or decrease the view of the map, rearrange the icons on the map, and move the map on the page. - Use the plus sign (+) to increase magnification of the map. - Use the minus sign (-) to decrease magnification of the map.



- Click the center dot to center the map on the page.
- Use the direction arrows to move the page in that direction.
- Use the selection tool under the navigation tool to toggle between moving the entire map or moving one CI on the map.

Map menu

The following options are available if you right-click the map background.

Run Layout	Redraws the map with the current layout option.
Fit To Screen	Resizes the map to fit all the nodes in the map window.
Reset Filters	Performs the same action as the Filters > Reset option.

Node menu

The following options are available if you right-click a node.

View Form	Displays the CMDB record of the selected CI in a new tab of the browser.
View Map	Reloads the map using the selected CI as the new root node, with the currently defined layout setting. This option does not display on the root node.

View Related Tasks	Displays all tasks or outages associated with the selected CI, including incidents, problems, change requests, and follow-on tasks. This option is always available, even if there are no tasks associated with the CI. This option does not appear on collapsed nodes.
View Affected CIs	Shows a list of all tasks that have the CI listed as an Affected CI. This option is only visible when you access the map from the map icon in a task record's Configuration item field.
View Related Outages	Displays all outages involving the selected CI. This option only appears when there is an outage associated with the CI. This option does not appear on collapsed nodes.
Add Relationship	This option displays a dotted green line that you can drag to another CI to create a relationship link. A popup dialog allows you to define the relationship type.
Expand	Displays all CIs and components within a clustered node, or virtual groups (virtual nodes that appear when glide.bsm.too_many_children is reached). This option appears only if the node is a cluster node or a virtual group node. If Load More was previously used, then Expand reverts the results of the Load More operation.

	The number of additional icons to display is bound by the value of the glide.bsm.max_nodes property.
Collapse	Collapses all CIs and components within a cluster node back to a single node. Also, collapses a virtual group that has been expanded. This option only appears if the node has been expanded using the Expand menu item. If Load More was previously used, then Expand reverts the results of the Load More operation.
Run Layout From Here	This option re-runs the chosen layout using the current node. Use this option to get a new or clearer view on the same map.
Load More	Starting at the selected icon, loads the next level of the map, past the setting of Max Levels. Virtual grouping is not applied at the newly loaded level even if the criteria for virtual grouping is met. The number of additional icons to display is bound by the value of the glide.bsm.max_nodes property.

Relationship menu

The following options are available if you right-click a relationship link.

View Relationship Form	Opens the CI Relationship form. You can modify the Parent , Type , and Child of the relationship from this form.
Modify Relationship	Searches for and selects a new relationship for this link.
Delete Relationship	Deletes a relationship. The relationship is deleted after prompting for confirmation.

Cluster nodes in a Dependency Views map

Dependency Views maps can display cluster group nodes alongside individual CI nodes, and the child nodes of these cluster groups.

Clusters are CIs in the Cluster [cmdb_ci_cluster] table. A cluster CI is an organized set of computer CIs that work together as a single system. Each node in a cluster group represents a CI, typically a server, that can have referenced hardware, such as disks and network adapters.

Cluster nodes on a Dependency Views map can display in two modes:

- Collapsed mode: Displays only the cluster CI node without its child CI nodes. This mode avoids unnecessary clutter in large maps.
- Expanded mode: Displays the cluster CI node and all its child CI nodes.

Menu options available for a clustered node include **Collapse** and **Expand**, which allow you to control the density on the map.


By default, Dependency Views collapses all cluster groups and displays clusters in collapsed mode on the map.

Annotation

Icons for cluster nodes and cluster group CI nodes are noted by the string "Cluster" and by a unique cluster icon. The system searches through all the component nodes in a cluster CI or collapsed node looking for tasks, outages, and trouble, such as incidents, problems, or change requests.

This search evaluates only the number of levels that are displayed in the diagram.

An expanded cluster node displaying its child nodes



Virtual grouping of nodes in a Dependency Views map

To reduce the density on a map, Dependency Views automatically groups CIs of a similar CI type from the same level.

A large number of nodes can cause a Dependency Views map to become too dense to be helpful. Therefore, if the number of nodes with a similar CI type from same level, exceeds the value of the Maximum number of nodes (of a similar CI type and at the same level) to display before applying virtual grouping property, then those nodes are automatically grouped into a virtual group. A single node, the virtual

group node is displayed to represent the virtual group, while all actual nodes in the virtual group (that are of a similar CI type), are hidden. Virtual group nodes represent CIs of a similar CI type but are not CIs by themselves and cannot have tasks assigned to them. The number of actual collapsed nodes in the virtual group is noted on the virtual group node.

By default, child nodes of a virtual group are not displayed. You can enable the Show children of virtual groups property to display child nodes underneath virtual groups.

Virtual grouping is not applied at the level underneath a virtual group even if the criteria for virtual grouping is met (the number of nodes with a similar CI type from that level exceeds the preconfigured property value). However, virtual grouping can happen at the following level if that criteria is met. This behavior does not depend on any property settings, and you cannot change it.

Menu options for a virtual group include **Expand** and **Collapse**, which allow you to apply virtual grouping and display only the virtual group node, or to undo the virtual grouping and display all actual nodes.


Virtual links

A virtual node is connected to other nodes with a virtual link. A virtual link denotes that there such link between at least one CI in the virtual group, to another CI node on the map.

Note: Predefined filters do not apply to virtual groups. Therefore a virtual group displays even if it contains CIs that a predefined filter would have excluded. Upon the expansion of a virtual group, predefined filters are applied, and any or all of the CIs that were previously virtually grouped, might no longer display on the map.

Also, when using the node menu option **Load More**, virtual grouping is not applied at the newly loaded level even the criteria for virtual grouping is met.

An expanded virtual group



Related reference

- [Properties for Dependency Views](#)

Use Dependency Views

Use the layout controls on a Dependency Views map to display elements in different configurations for easier management. Use the filter panel on the map to display fewer levels or to filter out elements you don't want to see, then save the filter for use later. Draw new relationships between elements or edit existing relationships.

- [View a Dependency Views map](#)

When you display a Dependency Views map, the map is centered on the root CI and displays the layout and number of levels defined in the map properties. If Operational Intelligence is activated, then a Dependency Views map provides a mode that lets you directly access metrics information for the CIs on the map.

- [Save or load a Dependency Views map](#)

In the **View Map** module, use the menu icon to save and load Dependency Views maps.

- [Delete a saved Dependency Views map view](#)

Use the **Saved Views** module to delete a previously saved view.

- [Change the layout of Dependency Views map](#)

You can select from different layout options for your Dependency Views map.

- [Filter the view of a Dependency Views map](#)

Filter a Dependency Views map to display specific types or categories of configuration items.

- [View metrics for CIs in a Dependency Views map](#)

Operational Intelligence processes metrics data for CIs, calculates statistics and aggregations, and detects metrics anomalies. A Dependency Views map lets you switch to metrics mode to directly access the Insights Explorer that displays metrics data for CIs on the map.

- [Perform actions on nodes in a Dependency Views map](#)

You can view various related items for the nodes in a Dependency Views map.

- [Export a Dependency Views map](#)

Export a Dependency Views map to an image in PNG format.

- [View collapsed nodes in a Dependency Views map](#)

Cluster and virtually grouped nodes can be displayed in a collapsed mode to avoid unnecessary clutter in large maps.

Related concepts

- [Domain separation and Dependency Views](#)

- [Dependency Views map](#)
- [Cluster nodes in a Dependency Views map](#)
- [Virtual grouping of nodes in a Dependency Views map](#)

Related reference

- [Supported browsers for Dependency Views](#)
- [Dependency Views map menus and controls](#)
- [Properties for Dependency Views](#)
- [Components installed with Dependency Views](#)

Related topics

- [Administer Dependency Views](#)

View a Dependency Views map

When you display a Dependency Views map, the map is centered on the root CI and displays the layout and number of levels defined in the map properties. If Operational Intelligence is activated, then a Dependency Views map provides a mode that lets you directly access metrics information for the CIs on the map.

Before you begin

Role required: `dependency_views` (see general requirements)

General role requirements:

- To access a Dependency Views map from either the navigation menu, a script API, or directly from a URL, the minimum role required is the `dependency_views`. Some operations that are related to icons, indicators, and menu actions require the `ecmdb_admin` role. Some operations that are related to properties and dependency types require the `admin` role.

- Dependency Views enforces ACL permissions on CIs, and visually hides them and their relationship from the map if the permission requirement is not met.

About this task

The maps generated by Dependency Views are based on D3 and Angular technology, providing a modern interactive graphical interface to visualize configuration items and their relationships.

If Service Mapping is activated, Dependency Views maps are enhanced to display dependencies that reflect connections in service maps. In addition, the list of related services in the **Details** section, includes application services, and technical and manual services if Event Management is activated. All CIs that are included in a service, are displayed underneath the service node on the map.

Maps provided by Service Mapping are for application services, including comprehensive maps from the perspective of application services. For more information, see [Service Mapping](#).

Administrators can configure the setting for the default layout of the map and number of levels displayed. When you access the map from a saved view, the map opens using the properties in the saved view, and not the default map properties.

Procedure

Navigate to **All > Dependency Views** and open one of these modules:

- **View Map in New Tab:** Opens the map in a new, full screen tab without the application navigator.
- **View Map:** Opens the map in the content pane of the current tab.
- **Saved Views:** Opens a view of a map that you previously saved.

Click a number in the **Version** column, and then click the Display Dependency Views map icon ().

Related tasks

- [Save or load a Dependency Views map](#)

- Delete a saved Dependency Views map view
- Change the layout of Dependency Views map
- Filter the view of a Dependency Views map
- View metrics for CIs in a Dependency Views map
- Perform actions on nodes in a Dependency Views map
- Export a Dependency Views map
- View collapsed nodes in a Dependency Views map

Save or load a Dependency Views map

In the **View Map** module, use the menu icon to save and load Dependency Views maps.

Before you begin

Role required: None

Procedure

1. Navigate to **All > Dependency Views > View Map**.
2. Click the View menu icon (.
3. Select **Save View**, **Load View**, or **Last View**.

Related tasks

- View a Dependency Views map
- Delete a saved Dependency Views map view
- Change the layout of Dependency Views map
- Filter the view of a Dependency Views map
- View metrics for CIs in a Dependency Views map

- Perform actions on nodes in a Dependency Views map
- Export a Dependency Views map
- View collapsed nodes in a Dependency Views map

Delete a saved Dependency Views map view

Use the **Saved Views** module to delete a previously saved view.

Before you begin

Role required: admin

Procedure

1. Navigate to **All > Dependency Views > Saved Views**.
2. Select the check box for map view that you want to delete.
3. Select **Delete** from the **Actions on selected rows** drop-down menu.

Related tasks

- View a Dependency Views map
- Save or load a Dependency Views map
- Change the layout of Dependency Views map
- Filter the view of a Dependency Views map
- View metrics for CIs in a Dependency Views map
- Perform actions on nodes in a Dependency Views map
- Export a Dependency Views map
- View collapsed nodes in a Dependency Views map

Change the layout of Dependency Views map

You can select from different layout options for your Dependency Views map.

Before you begin

Role required: none

Procedure

1. Navigate to **All > Dependency Views > View Map**.
2. Select one of the following layout options from the menu across the top of the view.
 - **Vertical:** Displays the elements in a vertical tree pattern according to their upstream and downstream relationships. This is the default value for the initial display of the map.
 - **Horizontal:** Displays the elements in a horizontal tree pattern according to their upstream and downstream relationships.
 - **Radial:** Displays the elements in a radial pattern according to their upstream and downstream relationships.
 - **Force:** Centers the elements around the parent CI, regardless of upstream or downstream relationships.
 - **Group:** Groups the elements according to their CI type.
 - **Details:** Displays related alerts, incidents, problems, and related services.

Related Services displays application services related to the CIs currently displaying in the map. If Event Management is activated then technical services and manual services are included. You can double-click a service to display the map in the Event Management dashboard.

Related tasks

- [View a Dependency Views map](#)
- [Save or load a Dependency Views map](#)
- [Delete a saved Dependency Views map view](#)
- [Filter the view of a Dependency Views map](#)

- View metrics for CIs in a Dependency Views map
- Perform actions on nodes in a Dependency Views map
- Export a Dependency Views map
- View collapsed nodes in a Dependency Views map

Filter the view of a Dependency Views map

Filter a Dependency Views map to display specific types or categories of configuration items.

Before you begin

Role required: admin

About this task

Use the filter panel to control which elements of the map are displayed and to save versions of a filter for later use.

Procedure

1. Navigate to **All > Dependency Views > View Map**.

2. Click the Map settings icon  to open map settings.

Map settings

Filter panel strips and options	Description
Save Custom Settings	Configure desired custom settings, then enter a name and click Save. Custom settings can be loaded by using the Load Saved Custom Settings option.

Filter panel strips and options	Description
	Navigate to Dependency Views > Saved Settings > to display all saved custom settings.
Load Custom Settings	Apply previously saved custom settings to the current map.
Predefined Filters	Apply previously defined filters consisting of configuration type, CI type, and relationship filters. You can Set a predefined filter as default. This filter is applied first, before any other filters (such as Filter CIs by Depth) are applied.
Dependency Type	Apply a filter that runs in real time and generates a custom view of a service map for a specific CI.
Max Levels	Designate how many levels from the root CI display on the map.
Filter CIs by Depth	Designate which levels of CI display on the map.
Filter CIs by CI Type	Designate what CI types display in the map.
Filter CIs By CI Location	Designate what CI locations display in the map.
Filter CIs By CI Manufacturer	Designate what CI manufacturers display in the map.

Filter panel strips and options	Description
Filter CIs By Audit Failure	Hides CIs that failed the CMDB health staleness test. This option is available only if there are any such CIs.
Filter Relationship Types	Designate what relationship types display in the map.
Map Indicators	Designate what types of tasks display and get counted in the map.
Remove Filtered Items	Off: Gray out filtered items on the map. On: Do not display filtered items on the map.
Run Layout Automatically	On: The configured layout to the map is reapplied whenever the filter is changed. Off: The map layout remains static when the filter is changed.
Fit to Screen Automatically	On: The map magnification will increase or decrease automatically to display all CIs on the map. Off: The map magnification remains unchanged when the map is reloaded.

- Click a filter strip to expand or collapse it, and to set filter items.

Related tasks

- View a Dependency Views map
- Save or load a Dependency Views map
- Delete a saved Dependency Views map view
- Change the layout of Dependency Views map
- View metrics for CIs in a Dependency Views map
- Perform actions on nodes in a Dependency Views map
- Export a Dependency Views map
- View collapsed nodes in a Dependency Views map

View metrics for CIs in a Dependency Views map

Operational Intelligence processes metrics data for CIs, calculates statistics and aggregations, and detects metrics anomalies. A Dependency Views map lets you switch to metrics mode to directly access the Insights Explorer that displays metrics data for CIs on the map.

Before you begin

The Operational Intelligence (com.snc.sa.metric) plugin must be activated to enable this functionality, and metrics data needs to be processed for the CIs on the Dependency Views map.

Role required: admin

About this task

Open a Dependency Views map in metric mode which integrates a Dependency Views map with the Insights Explorer functionality that is tailored to the map. In this mode, you can access Insights Explorer functions directly from the map, to explore metrics data for the CIs on the map. All map CIs are accessible in the right hand side pane, from where you can drill into metrics data.

Procedure

1. Navigate to **All > Dependency Views > View Map** to open a map.
2. Right-click on a CI on the map and select **View Metrics** to open the Dependency View map in metrics mode.
In the panel on the right side, the CI that you selected on the Dependency View map is selected by default, and the list of all the metrics available for that CI are displayed.
3. Click the '<' sign on the left of the CI to display all the CIs that you can explore metrics for.
The Insights Explorer is scoped for exploring only the CIs that currently display on the Dependency Views map, and you cannot add or remove CIs from the list. If you use map settings or filters to filter out CIs from the map, the same filtering will apply to the list of CIs that you can explore metrics for.
4. Click on a CI in the CIs list or right-click on a CI on the Dependency Views map, to drill down to the CI's metrics.
5. Click the **Dependencies Map** tab or the **Metrics** tab to switch modes:
 - a. In **Metrics** mode: The full functionality of the Insights Explorer is available, you can create metric charts by dragging metrics into the canvas.
You can modify chart settings, select different time ranges for the charts, and perform other actions as described in [View metric values in the Insights Explorer](#).
 - b. In **Dependencies Map** mode: Select a CI on the map to drill down to its metrics data, drop-down the **Layout** list to choose a different layout, or modify map settings.

Related tasks

- [View a Dependency Views map](#)
- [Save or load a Dependency Views map](#)
- [Delete a saved Dependency Views map view](#)
- [Change the layout of Dependency Views map](#)
- [Filter the view of a Dependency Views map](#)

- Perform actions on nodes in a Dependency Views map
- Export a Dependency Views map
- View collapsed nodes in a Dependency Views map

Perform actions on nodes in a Dependency Views map

You can view various related items for the nodes in a Dependency Views map.

Before you begin

Role required: None

About this task

If the node is a collapsed node or represents a cluster, the incidents, problems and change requests are for all the collapsed nodes.

Procedure

1. Navigate to **All > Dependency Views > View Map**.
2. Click the Node menu icon  next to a node or right-click a node on the map to access the following menu items:

Node Menu

View Form	Displays the CMDB record of the selected CI in a new tab of the browser.
View Map	Reloads the view using the selected CI as the new root node, with the currently defined layout setting. This option does not display on the root node.
View Related Tasks	Displays all tasks or outages associated with the selected CI, including incidents, problems,

	change requests, and follow-on tasks. This option is always available, even if there are no tasks associated with the CI. This option does not appear on collapsed nodes.
View Affected CIs	Shows a list of all tasks that have the CI listed as an Affected CI. This option is only visible when you access the view from the view icon in a task record's Configuration item field.
View Related Outages	Displays all outages involving the selected CI. This option only appears when there is an outage associated with the CI. This option does not appear on collapsed nodes.
Add Relationship	This option displays a dotted green line that you can drag to another CI to create a relationship link. A popup dialog allows you to define the relationship type.
Expand	Displays all CIs and components within a cluster node or a collapsed node. This option only appears if the node is a collapsed or cluster node. The number of additional icons to display is bound by the value of the glide.bsm.max_nodes property.
Collapse	Collapses all CIs and components within a cluster node or a collapsed node back to a single node. This option only

	appears if the node has been expanded using the Expand menu item.
Run Layout From Here	This option re-runs the chosen layout using the current node. Use this option to get a new or clearer view on the same map.
Load More	Starting at the selected icon, loads the next level of the map, past the setting of Max Levels . The number of additional icons to display is bound by the value of the glide.bsm.max_nodes property.

Related tasks

- [View a Dependency Views map](#)
- [Save or load a Dependency Views map](#)
- [Delete a saved Dependency Views map view](#)
- [Change the layout of Dependency Views map](#)
- [Filter the view of a Dependency Views map](#)
- [View metrics for CIs in a Dependency Views map](#)
- [Export a Dependency Views map](#)
- [View collapsed nodes in a Dependency Views map](#)

Export a Dependency Views map

Export a Dependency Views map to an image in PNG format.

Before you begin

Role required: admin

Procedure

1. Navigate to **All > Dependency Views > View Map**.
2. Configure the map view as you want the image to appear.
The exported image displays the current view of the map.

3. Click the view menu icon ().
4. Click **Export Image**.
5. Right-click the image and select **Save Image As**, **Print**, or any other menu option.

Note: You can't export images from a Dependency Views map using Internet Explorer as your browser.

6. Click the "X" button to close the **Export Image** window.

Related tasks

- [View a Dependency Views map](#)
- [Save or load a Dependency Views map](#)
- [Delete a saved Dependency Views map view](#)
- [Change the layout of Dependency Views map](#)
- [Filter the view of a Dependency Views map](#)
- [View metrics for CIs in a Dependency Views map](#)
- [Perform actions on nodes in a Dependency Views map](#)
- [View collapsed nodes in a Dependency Views map](#)

View collapsed nodes in a Dependency Views map

Cluster and virtually grouped nodes can be displayed in a collapsed mode to avoid unnecessary clutter in large maps.

Before you begin

Role required: None

Procedure

1. To expand a collapsed node, right-click the CI and select **Expand** from the context menu.
2. To collapse an expanded cluster node with children, right-click the CI and select **Collapse** from the context menu.

Related tasks

- [View a Dependency Views map](#)
- [Save or load a Dependency Views map](#)
- [Delete a saved Dependency Views map view](#)
- [Change the layout of Dependency Views map](#)
- [Filter the view of a Dependency Views map](#)
- [View metrics for CIs in a Dependency Views map](#)
- [Perform actions on nodes in a Dependency Views map](#)
- [Export a Dependency Views map](#)

Administer Dependency Views

Users with the admin role can control the appearance and behavior of Dependency Views by configuring map indicators, map related items, map icons, and menu actions.

- [Create or modify map indicators](#)

Dependency Views maps and application service maps, use icons to display additional information for a CI by displaying its related records such as alerts, outages, incidents and problems. These icons are called map indicator.

- [Create or modify map icons](#)

Upload new icons or modify existing icons to customize the icon displayed for a CI in maps in Dependency Views, Service Mapping, and Event Management.

- [Create a predefined filter](#)

Create filters to narrow down the CIs that are displayed on a Dependency Views map. You can create filters that are based on CIs' class, CIs' attributes, or CIs' relationships.

- [Set a predefined filter as default](#)

You can set a custom predefined filter as the default predefined filter for viewing maps.

- [Create or modify Map Related Items](#)

The Map Related Items module relates referenced CIs to one another, which allows them to be displayed in a Dependency Views map.

- [Create or modify Dependency Views menu actions](#)

To modify an existing menu option, first you create a copy of the original menu action record, and then you modify the copy.

- [Condition and script parameters for menu actions](#)

You can use the following condition and script parameters for menu actions.

- [Create or edit a dependency type](#)

Use one of the dependency types provided, or create a custom dependency type with a script that will execute in real time to generate a custom view of a Dependency Views map for a specific CI.

Related concepts

- [Domain separation and Dependency Views](#)
- [Dependency Views map](#)
- [Cluster nodes in a Dependency Views map](#)
- [Virtual grouping of nodes in a Dependency Views map](#)

Related reference

- [Supported browsers for Dependency Views](#)
- [Dependency Views map menus and controls](#)
- [Properties for Dependency Views](#)
- [Components installed with Dependency Views](#)

Related topics

- [Use Dependency Views](#)

Create or modify map indicators

Dependency Views maps and application service maps, use icons to display additional information for a CI by displaying its related records such as alerts, outages, incidents and problems. These icons are called map indicator.

Before you begin

Role required: admin

About this task

The default configuration includes map indicators for the following record types:

- Open incident.
- Open alert.

- Unplanned current outage.
- Planned current outage, or an open problem.
- Current, planned, or recent change request.

You can filter out the display of affected CIs, alerts, current change requests, incidents and problems from the map settings menu.

The Affected CI's map indicator appears for CIs in two related but not identical situations. It appears for CIs for which tasks such as change request, incident, or problem were directly created for, and for any CIs that were added in those tasks (parent tasks) as Affected CIs (The CI for which a task is directly created for, is automatically added as an affected CI in that task). The state of affected CI's depends on the status of the respective parent task. For as long as the parent task is active, the associated affected CIs continue to be impacted by the task issue. In a map, the Affected CI's indicator displays for all affected CIs for as long as the parent task is active. On a map, the Affected CI tooltip displays the details of the task records in which the CI was added as an affected CI. However, the **Details** pane does not contain an Affected CI's tab, and no further details about affected CIs, or the associated tasks are displayed. After the parent task is closed, the Affected CI's indicator no longer displays for any of the tasks' affected CIs. For information about affected CIs in Change Management, see [Associate CIs to a change request](#).

Note: Details about affected CIs are derived from the task and the cmdb_ci tables and their extensions. Therefore, if you use custom tables to store CIs for incidents, problems and changes, it affects the details that are displayed for affected CIs.

For more information on how map indicators are used to show tasks and outages in clusters and collapsed nodes, see [Cluster nodes in a Dependency Views map](#).

Procedure

1. Navigate to **All > Dependency Views > Map Indicators**.
2. Click **New** to create a new map indicator, or click the name of an indicator from the **Table** column to modify an existing map indicator.

3. Fill in the fields on the form, as appropriate.

Map Indicator form

Field	Description
Table	Name of the table represented by this map indicator. Note: The list shows only tables and database views that are in the same scope as the map indicator. Views are not supported, although included in the list.
Name	Name of the indicator.
Order	Priority order of the task. The highest priority task is the indicator with the lowest order number.
Icon	File name and path of the icon image file, which can be a system image. - To create a new icon, see Create or modify map icons - To create or use a system image see Storing images in the database.
CMDB CI field	Name of the field on the selected table that contains the configuration item.
Start field	Record property that determines the time-point on the metric chart timeline for placing records in the Insights Explorer.

Field	Description
	Possible values depend on the selected Table . For example, the incident indicator has values such as Actual end , Actual Start , and Approval Set .
Description field	Name of the field on the selected table that contains the description of the configuration item.
Description	Text to display when hovering over the indicator. Alphanumeric characters and spaces are valid for this field.
Conditions	Condition builder that specifies for which CIs to apply this indicator. For example, a CI that has a current past outage is highlighted for 5 days. You can configure a condition to designate a different timeframe for what is considered to be current.
Active in Service Map	Toggle that you can enable to make the specified table available in the Settings dialog box for application service maps. You can then toggle between displaying or not displaying the respective records on the map.
Active Dependencies	Toggle that you can enable to make the specified table available in the Settings dialog box for Dependency Views maps. You can then toggle

Field	Description
	between displaying or not displaying the respective records on the map.
Active in Metrics	Enable to make the toggle for the specified table available in the Settings dialog box for the Insights Explorer. You can then toggle between displaying or not displaying the respective records on the Insights Explorer.
Label	Text to display for the indicator on the map.
Tooltip Label	Prefix portion of the tooltip (Tooltip Label : Tooltip info).
Tooltip Info	Suffix portion of the tooltip (Tooltip Label : Tooltip info).

- Click **Submit** to enter a new map indicator or click **Update** to modify an existing map indicator.

Result

For an indicator to appear in a Dependency Views map, a CI must meet all filter conditions, and **Active Dependencies** must be selected.

Related tasks

- [Create or modify map icons](#)
- [Create a predefined filter](#)
- [Set a predefined filter as default](#)
- [Create or modify Map Related Items](#)
- [Create or modify Dependency Views menu actions](#)

- [Create or edit a dependency type](#)

Related reference

- [Condition and script parameters for menu actions](#)

Create or modify map icons

Upload new icons or modify existing icons to customize the icon displayed for a CI in maps in Dependency Views, Service Mapping, and Event Management.

Before you begin

Role required: admin

About this task

The icons used in Dependency Views maps are listed in the Map Icons module. Records in the **Map Icons** list are arranged by CI classes, such as `cmdb_ci_linux_server`. The path to the default image files is `https://<instance name>.service-now.com/images/app.ngbsm/<image name.svg>`. For information about uploading images to the database, see [Storing images in the database](#).

Role required: admin or `cmdb_admin` roles are required to access the records in this table [`ngbsm_icon`] to upload new icons.

Procedure

- Navigate to **All > Configuration > CI Class Manager**, and do the following actions:
 1. Click **Hierarchy** to display the CI Classes list.
 2. Select a class to modify the icon for.
 3. In the class navigator bar, expand **Class Info** and then select **Basic Info**.
 4. On the Basic Info form, click **Icon**.
 5. In the Icons dialog box, select an icon and then click **Update**.

6. On the **Basic Info** form, click **Update**.
- Navigate to **All > Dependency Views > Map Icons**, and do the following actions:
 1. Click **New** to create a new map icon or click the name of an existing icon in the **Label** column to modify an existing icon.
 2. On the form, fill in the fields.

Map Icons form

Field	Description
CI Type	Label or the informal name of the CI table that this icon represents in the view.
Icon	Name of the icon.
URL	Path to the icon image using the following format: /image name.svg Click the lock icon to enter a new path.

3. Fill in the fields on the form, as appropriate.
4. Click **Submit** to enter a new icon or click **Update** to modify an existing icon.

What to do next

You can modify a Dependency Views map indicator to use the new icon.

Related tasks

- [Create or modify map indicators](#)
- [Create a predefined filter](#)
- [Set a predefined filter as default](#)
- [Create or modify Map Related Items](#)

- Create or modify Dependency Views menu actions
- Create or edit a dependency type

Related reference

- Condition and script parameters for menu actions

Create a predefined filter

Create filters to narrow down the CIs that are displayed on a Dependency Views map. You can create filters that are based on CIs' class, CIs' attributes, or CIs' relationships.

Before you begin

Role required: `ecmdb_admin`

About this task

Create a predefined filter that you can then select to determine the scope of the CIs that are displayed in a Dependency Views map.

Configuration type filters filter by CI class, **CI filters** filter by CI attributes, and **relationship filters** filter by relationships. Only CIs that match at least one of the configuration type filters (if any exists), and at least one of the CI filters (if any exists), and at least one of the relationship type filters (if any exists) - are displayed on the map. If no filters are defined, then no filtering is applied.

Note: Predefined filters do not apply to virtual groups. Therefore a virtual group displays even if it contains CIs that a predefined filter would have not included. Upon the expansion of a virtual group, predefined filters are applied, and any or all of the CIs that were previously virtually grouped, might no longer display on the map.

Procedure

1. Navigate to **All > Dependency Views > Predefined Filters**.
2. On the **Predefined Filters** page, click **New**.

3. Type in a **Name** for the filter.
4. Click **Roles**, and in the **Roles** dialog box, select the roles that this filter will be available for.
5. Right-click on the page header, and click **Save**.
6. Create a configuration type filter:
 - a. Click **Configuration Types**, and then click **Edit**.
 - b. In the **Collection** list collector, select the classes that CIs must belong to in order to be displayed on the map, and move them to the **Configuration Types List**.
 - c. Click **Save**.
7. Create a CI filter:
 - a. Click **CI Filters**, and then click **New**.
 - b. In the **CI Filters** page enter conditions to filter CIs by specific attribute values.
 - c. Click **Submit**.
8. Create a relationship type filter:
 - a. Click **Relationship Type**, and then click **New**.
 - b. In the **Collection** list collector, select the relationships that CIs must have in order to be displayed on the map, and move them to the **Relationship Types List**.
 - c. Click **Save**.

What to do next

After creating a predefined filter, you can apply it to a map:



1. Click the Map settings icon to open **Map Settings**.
2. Select a filter from the **Predefined Filters** list.
3. Click **Apply**.

Related tasks

- Create or modify map indicators
- Create or modify map icons
- Set a predefined filter as default
- Create or modify Map Related Items
- Create or modify Dependency Views menu actions
- Create or edit a dependency type
- Filter the view of a Dependency Views map

Related reference

- Condition and script parameters for menu actions

Set a predefined filter as default

You can set a custom predefined filter as the default predefined filter for viewing maps.

Before you begin

Role required: admin

Procedure

1. Create the custom predefined filter to be used as the default predefined filter.
2. On the predefined filter form, click the context menu and select **Copy sys_id**.
3. Navigate to **User Administration > User Preferences**.
4. Click **New** and create a new user preference record using these values:

- **Name:** ecmdb.ciview
- **Type:** String
- **Value:** Paste the sys_id of the custom predefined filter
- **User:** Leave blank to create a system-wide setting
- **Description:** Description of the predefined filter
- **System:** Selected

5. Click **Submit**.

What to do next

In **Map Settings**, when you select the default option for **Predefined Filters**, the custom predefined filter that was set, will be applied.

Related tasks

- [Create or modify map indicators](#)
- [Create or modify map icons](#)
- [Create a predefined filter](#)
- [Create or modify Map Related Items](#)
- [Create or modify Dependency Views menu actions](#)
- [Create or edit a dependency type](#)
- [Filter the view of a Dependency Views map](#)

Related reference

- [Condition and script parameters for menu actions](#)

Create or modify Map Related Items

The Map Related Items module relates referenced CIs to one another, which allows them to be displayed in a Dependency Views map.

Before you begin

Role required: admin

About this task

The base system configuration includes the following tables and relates them to items in the Computer [cmdb_ci_computer] and Server [cmdb_ci_server] tables.

- Disk [cmdb_ci_disk]
- Network Adapter [cmdb_ci_network_adapter]
- Database [cmdb_ci_database]


Some additional referenced CIs that can be related in this manner are file systems and running processes.

In the following example, computer nodes in the map are related to network adapter nodes if the **Configuration Item** field of the adapter records reference the specific CI node. Access or create a network adapter record from the Network Adapter related list in the cmdb_ci_computer record.

Dependency Views Configuration Item field

The Dependency Views map for the *JEMPLOYEE-IBM computer shows the network adapter attached to the computer.

Dependency Views map Related Items example



You can configure Dependency Views to display CIs that have no relationship record, but are related to other CIs by reference fields.

Procedure

1. Navigate to **All > Dependency Views > Map Related Items**.
2. Click **New** to create a new related item, or click in the row of an existing CI to modify an existing map related item.
3. On the form, fill in the fields.
See the Related Items form table.
4. Click **Submit** to enter a new map related item or click **Update** to modify an existing map related item.

Related Items form

Control	Description
Configuration item	CI that represents the base node or a CI in a table that extends the base node table. In the base system, the configuration item that represents the base node is Computer [cmdb_ci_computer],

Control	Description
	which includes all types of workstations and servers.
Related item	Table name of the related item. Only the cmdb_ci table and tables that extend it are displayed in the choice list.
Related field	Field that links this related item to the configuration item. In many cases, the appropriate value is automatically populated in the field after the first two fields are selected. Select the drop-down menu for additional options.
Active	Check box to enable or disable this record.

Related tasks

- [Create or modify map indicators](#)
- [Create or modify map icons](#)
- [Create a predefined filter](#)
- [Set a predefined filter as default](#)
- [Create or modify Dependency Views menu actions](#)
- [Create or edit a dependency type](#)

Related reference

- [Condition and script parameters for menu actions](#)

Create or modify Dependency Views menu actions

To modify an existing menu option, first you create a copy of the original menu action record, and then you modify the copy.

Before you begin

Role required: admin

About this task

This ensures that your instance can update the record normally during the upgrade process and allows you to quickly restore the original menu option, if necessary.

Procedure

1. To create a new menu option, navigate to **Dependency Views > Map Menu Actions** and click **New**.
Fill in the fields on the form, as appropriate. See the Menu Action form table.
2. To modify an existing menu option, navigate to **Dependency Views > Map Menu Actions**.
3. Open the menu action you want to edit.
4. Right-click in the header and click **Insert and Stay**.
This step creates a duplicate copy of the menu action and leaves it open for editing.
5. Change the name of the copied record to avoid confusion.
6. Modify the form fields as necessary and save the record.
7. Open the original record and disable it by clearing the **Active** check box.

Menu Action form

Control	Description
Name	Descriptive name that appears as the menu option.

Control	Description
Active	Check box that allows you to enable or disable this record.
Condition	Condition that triggers the display of this menu option. If the condition evaluates to false the menu option does not display. Script is evaluated in JavaScript in the user's browser and does not have access to all the APIs that Business Rules do. For details on available parameters, see Condition Parameters. .
Item	Map element for which the menu option displays. Valid values are: • Canvas for the menu on the map background. • Node for the menu on a CI. • Relationship for the menu on a relationship link.
Order	Physical location of the option in the menu. The option with the lowest order number appears first in the menu. All editable and custom options appear below the permanent menu options.
Script	Script that is executed in the browser when the menu option is selected. Script is evaluated in JavaScript in the user's browser and does not have access to all the APIs that Business Rules do.

Control	Description
Type	Menu action type being created, either a menu option or a menu separator. The menu separator is a single line. When the type is a separator, the Script field is ignored.

Related tasks

- [Create or modify map indicators](#)
- [Create or modify map icons](#)
- [Create a predefined filter](#)
- [Set a predefined filter as default](#)
- [Create or modify Map Related Items](#)
- [Create or edit a dependency type](#)

Related reference

- [Condition and script parameters for menu actions](#)

Condition and script parameters for menu actions

You can use the following condition and script parameters for menu actions.

Condition parameters

Note: The usual regular expression conventions are valid in the condition field, such as ! for NOT, && for AND, and | | for OR.

The **Condition** field contains a boolean expression that evaluates to true or false. If the condition is true or if there is no condition, the specified option appears in the menu when you right-click a CI or a relationship

link. When you select the option from the menu, ServiceNow executes the associated script.

Common Elements for Building a Condition

Text	Description
item	Node or reference link's data on which you performed the right-click action.
item.label	Label of the node.
item.ci_type	CI's type (table), such as <code>cmdb_ci_service</code> .
item.name	Name of CIs. CI's type name or the table label.
item.location	Location of the CI, such as New York.
item.manufacturer_name	Name of the CI's manufacturer, such as Dell Inc.
item.id	The <code>sys_id</code> of the CI.
item.is_selected	The item that is selected in the map.
item.level	The current default level.
item.locationId	The <code>sys_id</code> of the CI node's location.
item.locationName	The full address of the location.
item.manufacturerId	The <code>sys_id</code> of the CI's manufacturer.

Valid Conditions for Condition Parameters

Condition	Description
item.is_collapsed	The node is a collapsed node.
item.is_cluster	The node is a cluster node.

Script parameters

Menu action scripts are executed on the client when a user clicks the menu option. You can use the same building blocks in scripts as in conditions. Menu action scripts do not function on separators. These are some additional, useful expressions for scripts:

Condition	Description
item.id	The sys_id of the CI node or relationship link.
item.source	The sys_id of the relationship's parent or child.
item.target	The sys_id of the relationship's parent or child.
item.label	The name of the CI node, such as IronMail-SD-02.
item.location	The sys_id of the CI node's location.
item.location_name	The full address of the location, such as 4616 Clairemont Drive, North Clairemont, San Diego CA.
item.manufacturer_id	The sys_id of the CI's manufacturer.

Related tasks

- Create or modify map indicators
- Create or modify map icons
- Create a predefined filter
- Set a predefined filter as default
- Create or modify Map Related Items
- Create or modify Dependency Views menu actions
- Create or edit a dependency type

Create or edit a dependency type

Use one of the dependency types provided, or create a custom dependency type with a script that will execute in real time to generate a custom view of a Dependency Views map for a specific CI.

Before you begin

Role required: none

About this task

Create a JavaScript to customize the map. The script must comply with JavaScript syntax guidelines and the directions in the default script template, and it can call platform APIs. Use a dependency type, for example:

- To narrow down and simplify a map, leaving out CIs that are not important for a specific task.
- To include only specific CIs that are hidden by default, such as qualifiers, end-points, and entry points.
- To display virtual relationships that are calculated, and that otherwise do not exist in the CMDB.
- As a tool to plan a new topology deployment that is based on existing resources.

The following dependency types are available in the base system:

Default

The default setting in the base system. With this setting, there is no processing of the dependency map through any dependency type scripts that might filter or modify the map.

Show All Relationships

Returns all qualifiers, end points, and entry points. This dependency type is available in the base system and is disabled by default. Typically, you would enable this dependency type for debugging and tracking purposes.

The following dependency types are available with [Service Mapping](#):

Application to Network Devices

Returns the network devices in the network paths leading to/from the given CI.

Network Device to Applications

Returns the applicative CIs which are target or source of network paths containing the given network device. In addition, returns the hosts of those applicative CIs, and for an applicative CI that is an inclusion, its parent CI is returned too.

Physical Network Connections

Returns hosts/network devices that are physically connected to the given host or network device.

Flow Dependencies

Returns all the server to server connections that were discovered using the Netflow collector. The script builds a graph based on data in the [sa_flow_server_comm] table. This table contains pairs of services represented by an IP and a listening port that are communicating with each other. For more information, see [Data collection and discovery using Netflow](#) and [Data collection and discovery using VPC Flow Logs](#).

Procedure

1. Navigate to **All > Dependency Views > Dependency Types**.
2. In the **Load Filter Scripts** list view, select an existing dependency type, or click **New**.
3. Enter or modify a script, adhering to the guidelines and requirements in the script template that is provided.
4. Click **Submit**.

Result

In a Dependency Views map, you can click **Dependency Type** to apply a custom script defined in a dependency type.

Related tasks

- [Create or modify map indicators](#)
- [Create or modify map icons](#)
- [Create a predefined filter](#)
- [Set a predefined filter as default](#)
- [Create or modify Map Related Items](#)
- [Create or modify Dependency Views menu actions](#)

Related reference

- [Condition and script parameters for menu actions](#)

Related topics

- [Data collection and discovery using Netflow](#)

Properties for Dependency Views

Use Dependency Views properties to configure how data appears in Dependency Views maps.

These properties are available for Dependency Views. To view and edit these properties, the admin role is required.

Properties for Dependency Views

Property	Description
Maximum number of CIs to display on a map at once. glide.bsm.max_nodes	The maximum number of nodes to retrieve from the database. If more nodes exist in the database, they are not displayed in the map. - Type: Integer - Default value: 1000 - Location: Dependency Views > Map Properties
Maximum level depth from the root CI that can be initially displayed in Dependency Views. glide.bsm.max_levels	Level depth is the graph distance between the root CI and a node. - Type: Integer - Default value:: 3 Other possible values: 1-49 - Location: Dependency Views > Map Properties
Display the continuation of the map underneath virtual group. Virtual links are used to connect virtual groups to their child nodes. glide.bsm.show_virtual_node_child ren	- Type: Yes No - Default value: No - Location: Dependency Views > Map Properties

Property	Description
Maximum number of child nodes to display (the rest will be collapsed). glide.bsm.too_many_children	Maximum number of nodes (of a similar CI type and at the same level) to display before applying virtual grouping. Nodes are collapsed for the map to meet this limit. - Type: Integer, valid values 1 or greater - Default value: 10 - Location: Dependency Views > Map Properties
A value of true indicates that filtered out items will be removed from the graph along with any disconnected children while a value of false indicates that the items will be dimmed in color. glide.ngbsm.filters_remove_filtered_items	- Type: Yes No - Default value: Yes - Location: Dependency Views > Map Properties
Maximum number of relations per node. glide.bsm.max_num_rels	The maximum number of relations to retrieve from the database. If more relations exist in the database, they are not displayed in the map. - Type: Integer - Default value: 100 - Other values: 1 or greater

Property	Description
	Location: Dependency Views > Map Properties
A value of true indicates that when filters are changed the graph will recalculate its layout using the currently selected layout algorithm. glide.ngbsm.filters_run_layout_automatically	- Type: Yes No - Default value: Yes - Location: Dependency Views > Map Properties
A value of true indicates that when filters are changed the graph will be fit to the screen automatically. glide.ngbsm.filters_fit_to_screen_automatically	- Type: Yes No - Default value: No - Location: Dependency Views > Map Properties
A value of true allows relationship lines to be drawn using smooth curves instead of straight line segments. These curves can be more taxing on the browser, setting to false may improve fluidity of animation and interaction for Dependency Views. glide.ngbsm.performance_allow_curves	- Type: Yes No - Default value: Yes - Location: Dependency Views > Map Properties
Amount of time in milliseconds a notification stays on the screen.	- Type: Integer - Default value: 5000

Property	Description
glide.ngbsm.notification_display_time	Location: Dependency Views > Map Properties
The maximum amount of results displayed when searching for CIs. glide.ngbsm.search_ci_limit	- Type: Integer - Default value: 10 - Location: Dependency Views > Map Properties
The maximum amount of results displayed when searching for Relationship Types. glide.ngbsm.search_rel_type_limit	- Type: Integer - Default value: 5 - Location: Dependency Views > Map Properties
When available, the map should display the class labels for each CI. glide.ngbsm.show_class_labels	- Type: Yes No - Default value: Yes - Location: Dependency Views > Map Properties
Truncate node labels to a single line and to fit available space (default). Disable to display entire labels on multiple lines and wrapped as needed. glide.ngbsm.truncate_long_labels	If glide.ngbsm.show_class_labels is enabled, then the class label always displays on top of the CI label, and wrapping applies to both the class and the CI labels. - Type: Yes No - Default value: No

Property	Description
	Location: Dependency Views > Map Properties
Minimum horizontal distance between nodes in horizontal layout. glide.bsm.layout_horizontal_spacing_x	The distance is measured in pixels between one node's center to another node's center. - Type: Integer - Default value: 200 - Location: Dependency Views > Map Properties
Minimum vertical distance between nodes in horizontal layout. glide.bsm.layout_horizontal_spacing_y	The distance is measured in pixels between one node's center to another node's center. - Type: Integer - Default value: 100 - Location: Dependency Views > Map Properties
Minimum horizontal distance between nodes in vertical layout. glide.bsm.layout_vertical_spacing_x	The distance is measured in pixels between one node's center to another node's center. - Type: Integer - Default value: 125 - Location: Dependency Views > Map Properties

Property	Description
Minimum vertical distance between nodes in vertical layout. glide.bsm.layout_vertical_spacing_y	The distance is measured in pixels between one node's center to another node's center. - Type: Integer - Default value: 125 - Location: Dependency Views > Map Properties

Components installed with Dependency Views

Several types of components are installed with the activation of the Next_Gen BSM (com.snc.ng_bsm) plugin, such as tables.

Note: The Application Files table lists the components that are installed with this application. For instructions on how to access this table, see [Find components installed with an application](#).

Tables installed

Table	Description
Available CI icons [ngbsm_ci_icons]	Stores all available CI class icons.
Icons for CI types [ngbsm_ci_type_icon]	Maps icons to CI class names.
Map Script	Custom scripts that run in real time and generate a custom view of a map for a specific CI.

Table	Description
[ngbsm_script]	
Map View [ngbsm_view]	Serialized map views saved by users.
Map Filter [ngbsm_filter]	Filters saved by users.
Menu Action [ngbsm_context_menu]	Default and custom context menu actions that appear when users right click a map.
Related Item [ngbsm_related_item]	Stores which reference fields should be treated as relationships when building the map. This allows users to include CI's that are related via a reference field instead of a relationship.
Edge Colors [bsm_edge_color]	Color definitions to use when drawing the relationships between nodes based on relationship type.
Map Indicator [bsm_indicator]	Stores all map indicators.
BSM Saved Map [bsm_graph]	Details of maps.
BSM Map Actions	Actions on the map.

Table	Description
[bsm_action]	
BSM Map View [map_view]	Parents' predefined filters.
Map View Configuration Types [map_view_ci_type]	Configuration type filters, limiting the CI class types to be displayed, per predefined filter.
Map View Relationship Types [map_view_rel_type]	Relationship type filters, limiting the links to be displayed between CIs, per each predefined filter.
[map_viewroles]	Roles that a specific predefined filter should be applied to.
CI Filters [map_filters]	CI attribute filters, limiting the CIs to be displayed, per predefined filter.