

Zurich ServiceNow AI Platform Capabilities

Last updated: January 16, 2026

Some examples and graphics depicted herein are provided for illustration only. No real association or connection to ServiceNow products or services is intended or should be inferred.

This PDF was created from content on docs.servicenow.com. The web site is updated frequently. For the most current ServiceNow product documentation, go to docs.servicenow.com.

Company Headquarters

2225 Lawson Lane
Santa Clara, CA 95054
United States
(408)501-8550

Service Graph Connector for Microsoft SCCM

Use the Service Graph Connector for Microsoft SCCM to pull data from Microsoft System Center Configuration Manager (SCCM) into your ServiceNow instance.

The Service Graph Connector for Microsoft SCCM (SG-SCCM) imports SCCM data into the ServiceNow® Configuration Management Database (CMDB) application. The integration does not write to the SCCM database and supports the Microsoft Endpoint Configuration Manager (MECM). The integration pulls data from computers, processors, operating systems, disks, networks, and software.

Request apps on the Store

Visit the [ServiceNow Store](#) website to view all the available apps and for information about submitting requests to the store. For cumulative release notes information for all released apps, see the [ServiceNow Store version history release notes](#).

Supported versions

- Supported Microsoft SCCM/MECM versions:
 - 2409
 - 2403
- Supported ServiceNow versions:
 - Xanadu
 - Yokohama
 - Zurich

Use cases

The following ServiceNow applications have features that interact with the Service Graph Connector:

- [IT Operations Management \(ITOM\) Visibility](#)
 - Ability to get visibility into your infrastructure.

- Detailed hardware and software inventory tracking. The tracking can be done with or without Software Asset Management (SAM).
- Ability to detect delta changes for efficient incremental imports from SCCM to the ServiceNow AI Platform.
- **IT Service Management (ITSM)**
 - Incidents, problems, and changes on discovered configuration items (CI).
 - Automatic device ownership assignment.
- **Software Asset Management (SAM) and IT Asset Management (ITAM)**
 - Tight integration with Software Asset Management Professional and client software distribution workflows.
 - Inventory Software package and installation tracking.
 - Software Usage tracking.
 - License reclamation by detecting removed software.
 - Support for software editions, normalizing publisher information, and normalizing product Information.
 - Support for SCCM Asset Intelligence.

Important information for upgrading Service Graph Connector for Microsoft SCCM

After you've installed the latest version of the Service Graph Connector for Microsoft SCCM, ensure that you have removed the **last_run_datetime** field value from the Data Source [sys_data_source] table for the SCCM data sources.

Configuring a connection for the connector

You can configure a connection for the connector by using the SGC Central view in the CMDB Workspace. The view enables you to discover and install connectors, and then effectively manage the full life cycle of creating, editing, monitoring, and debugging connections. To configure the connector using SGC Central, see [Configure Service Graph Connector for Microsoft SCCM using SGC Central](#).

Important: Unless there are configuration issues, use the SGC Central view in the CMDB Workspace to configure the connection for the connector, as the guided setup method is being deprecated.

CMDB integrations dashboard

The Integration Commons for CMDB store app provides a dashboard with a central view of the status, processing results, and processing errors of all installed integrations. You can see metrics for all integration runs. You can filter the view to a specific CMDB integration, a specific time duration, or a specific integration run. For more details about monitoring Microsoft SCCM integrations in the CMDB Integrations Dashboard, see [Using the CMDB Integrations Dashboard](#).

Data mapping

Data from the SCCM data sources is mapped and transformed into the ServiceNow CMDB Configuration Item (CI) class definitions using the Robust Transform Engine (RTE). Data is inserted into the ServiceNow® CMDB using the Identification and Reconciliation Engine (IRE).

The SCCM data sources include the following:

- **SG-SCCM Computer Identity**
You can see the following data if it is available in SCCM:
 - Asset Tag. If the Asset Tag data is available, the mapping can be optionally enabled via the guided setup.
 - Assigned
 - DNS Domain
- **SG-SCCM Computer OU.** This data source imports data about the Organizational Unit (OU) name. The data is stored in the SG-SCCM Computer Related [sn_sccm_integrate_sccm_2019_computer_related] table. To add the view, open the computer record, click the top header, and select **View > SG-SCCM Computer Related**.
- **SG-SCCM Disk**
- **SG-SCCM Last Discovered Update.** This data source will run at the end of the import schedules to update the last_discovered date on the Computer CI. The source will conduct a full pull of all the computers

and bring in only the ResourceID and the LastHWScan columns to update the CMDB Computer table.

- SG-SCCM Network
- SG-SCCM Operating System
- SG-SCCM Processor
- SG-SCCM Removed Software. Ensure the **Use last run datetime** option is cleared for every run.
- SG-SCCM Removed Software AI. Ensure the **Use last run datetime** option is cleared for every run.
- SG-SCCM Software
- SG-SCCM Software AI

Note: If you have Asset Intelligence on your Microsoft SCCM instance, you have to run SG-SCCM Removed Software AI and SG-SCCM Software AI. If you do not have Asset Intelligence on your instance, you have to run SG-SCCM Removed Software and SG-SCCM Software.

When you complete setting up the connection, you can configure the integration to periodically pull data from SCCM. The data is loaded into staging tables and then inserted into the following target tables:

- CI Relationship [cmdb_rel_ci]
- Computer [cmdb_ci_computer] (required)
- Disk [cmdb_ci_disk]
- IP address [cmdb_ci_ip_address]
- Network Adapter [cmdb_ci_network_adapter]
- Serial Number [cmdb_serial_number]
- Software Installation [cmdb_sam_sw_install] (If the SAM application is installed.)
- Software Instance [cmdb_software_instance] (If the SAM application is not installed.)

- Software [cmdb_ci_spkg] (If the SAM application is not installed.)
- Software Usage [samp_sw_usage]

For more information on where data is saved when pulling data from a Microsoft SCCM application, see [CMDB classes targeted in Service Graph Connector for Microsoft SCCM](#).

You can use the IntegrationHub ETL app to view the data maps. See [IntegrationHub ETL](#) for more information.

Resolving the missing IP address or MAC address issue

By default, network adapters that are missing an IP address or MAC address are not imported. To include these network adapters in the import, do the following:

1. Navigate to **Service Graph Connector for Microsoft SCCM > Data Sources**.
2. Select **SG-SCCM Network**.
3. Remove the where clause from the **SQL statement** field.

Additional resources

- [How do I configure the SG-SCCM Service Graph Connector?](#) article on the ServiceNow Community site
- [Service Graph Connector for Microsoft SCCM - FAQ and Troubleshooting](#) blog post on the ServiceNow Community site
- [Service Graph Connector for Microsoft SCCM 3.0 Setup Guidelines \[KB1001248\]](#) article in the Now Support Knowledge Base
- [Support for Removed Software functionality in Service Graph Connector for SCCM integration](#) blog post on the ServiceNow Community site

Related concepts

- [Service Graph Connectors](#)

Configure Service Graph Connector for Microsoft SCCM using SGC Central

Use the playbook available with the SGC Central application to set up the Service Graph Connector for Microsoft SCCM for pulling in Microsoft SCCM data into the CMDB.

Before you begin

Install Service Graph Connector for Microsoft SCCM version 3.5.0 or later from the ServiceNow Store. For ServiceNow Store installation steps, see [Install a ServiceNow Store application](#).

Air gap connections are available from version 3.7.0 of the Service Graph Connector for Microsoft SCCM. You can add either standard data sources or air gap data sources. Before you set up air gap data sources, you must configure the air gap solution for the Service Graph Connector for Microsoft SCCM in your high-secure server and low-secure server. See [Configuring air gap connections for Microsoft SCCM](#).

Role required: SGC-Admin (sn_cmdb_int_util.sgc_admin)

Note: The admin user role is required to run background scripts and to provide table-level access to the SGC-Admin user.

About this task

The playbook experience for onboarding connectors is activated with SGC Central in the CMDB Workspace. To configure the SGC Central application, see [Configuring SGC Central](#) and for more information on how to interact with a playbook, see [Interact with Playbook](#).

Procedure

1. Navigate to **Workspaces > CMDB Workspace**.
2. In the CMDB Workspace, select **SGC Central**.
3. On the Overview page, select **Create connection**.

Tip: Alternatively, you can select **Create connection** on the All connections page.

4. On the Create connection window, select the Microsoft SCCM connector type, and then select **Create connection**.
5. Complete the initial prerequisites when setting up a connection for the first time using a connector.

Note: This step is required only during the first-time setup. See [Perform initial setup tasks when creating a connection in SGC Central](#).

6. Select an air gap template or a template that matches the credentials for establishing a Java Database Connectivity (JDBC) connection to the SCCM database.
 - a. In the **Setup** stage of the playbook, select the **Select alias template** activity.
 - b. Select a template.
 - **SCCM JDBC Connection Credentials:** Select to use a user name and password to establish a JDBC connection to the SCCM database.
 - **SCCM Air Gap:** Select to use an air gap connection if you're working with restricted environments that don't have direct internet access.
 - **SCCM JDBC Conn Cred (Integrated Auth):** Select to use Windows JDBC-integrated authentication, which uses domain credentials, for authenticating a JDBC connection to the SCCM database.
 - c. Select **Continue**.

If you selected either **SCCM JDBC Connection Credentials** or **SCCM JDBC Conn Cred (Integrated Auth)** in step 6.b, proceed to step 8.

7. Download and run the PowerShell scripts to set up an air gap connection.

The **PowerShell Script Download** activity appears only when you select **SCCM Air Gap** as the template in step 6.b.

Note: Before you add an air gap connection, you must configure the air gap solution for the Service Graph Connector for Microsoft SCCM in your high-secure and low-secure servers. See [Configuring air gap connections for Microsoft SCCM](#).

- a. In the **Setup** stage of the playbook, select the **PowerShell Script Download** activity.
 - b. Select **Download Airgap Scripts**.
 - c. Run the PowerShell scripts.
 - d. After configuring the air gap connection, select the **I have read the instructions and executed the scripts accordingly** check box.
 - e. Select **Continue**.
8. Enter connection details and test the API connection for importing Microsoft SCCM data.
 - a. In the **Setup** stage of the playbook, select the **Create and test connection** activity.
 - b. On the form, fill in the fields.
 - For SCCM JDBC Connection Credentials and SCCM JDBC Conn Cred (Integrated Auth) templates:

Create and test connection form

Field	Description
Connection name	Name to identify the Microsoft SCCM connection record. For example, SG-SCCM connection .
Query timeout	Number of seconds the JDBC driver waits for a query to complete.

Field	Description
	0 indicates no timeout. If the timeout is exceeded, the integration considers the JDBC result inaccessible and marks the result as an error.
Connection timeout	Number of seconds before the MID Server connection cache pool closes the connection and removes the connection. 0 indicates no timeout.
Host	Network address of the server where the Microsoft SQL Server database is located.
Database name	Name of the Microsoft SQL Server database that SCCM uses.
Override default port	Custom port of the Microsoft SQL Server instance. The default port for Microsoft SQL Server is 1433
Instance name	Microsoft SQL Server instance.
MID Server	MID Server for the connection.

Field	Description
	Note: It's required to select a MID Server for an Integrated Authentication connection. For the SCCM JDBC Connection Credentials option, this field appears only when you select the Use MID Server check box.
Note: The following fields appear only when you select the SCCM JDBC Connection Credentials template in step 6.	
Format	JDBC driver used for connecting to the SCCM database. SCCM uses Microsoft SQL Server as its database backend. This field is automatically set to com.microsoft.sqlserver.jdbc.SQLServerDriver. Leave the field value as is.
Username	User name for connecting to the JDBC server.
Password	Password for the JDBC server.

Field	Description
Use MID Server	Option to use the MID Server for accessing the JDBC server.

- For the SCCM Air Gap template:

Create and test connection form

Field	Description
Connection name	Display name for the connection.
Parent directory	Path of the Microsoft SCCM directory where the data is stored in your low-secure server.
Archive data after retrieval	Option to archive data after retrieval.
Archive path [Optional]	Folder where the data is to be archived if the Archive data after retrieval check box is selected.
MID server	Name of the MID Server that you deployed in your low-secure server. See Configure air gap solution for Microsoft SCCM in a low-secure server .

- Select **Create and test connection**.
 - Once the connection test is complete, select **Continue**.
- (Optional) Configure the connection and connector properties to map attributes and manage data imports.

Note: To skip this step, select **Continue** for the **Configure properties** activity.

- a. In the **Setup** stage of the playbook, select the **Configure properties** activity.
- b. To map the asset tags from Microsoft SCCM to the asset tag attribute in the Computer [cmdb_ci_computer] class, in the Connection properties section of the Configure properties page, select the **Map asset tags** check box.
- c. To avoid creating duplicate records in the CMDB Disks [cmdb_ci_disk] table when the Discovery application is running, in the Connector properties section of the Configure properties page, select the **Avoid creating duplicate records** check box.
- d. To set the import disk name to the format starting with Disk #[disknumber], in the Connector properties section of the Configure properties page, select the **Transform disk name to disk number** check box.
Where the disknumber is the number extracted from the disk name
- e. Select **Continue**.

10. (Optional) Modify the SQL statement for a data source.

Note: To skip this step, select **Skip** for the **Customize data source SQL statement** activity.

- a. In the **Setup** stage of the playbook, select the **Customize data source SQL statement** activity.
- b. Double-click (or use the keyboard shortcut) the **Custom SQL statement** column value for a data source and enter the custom SQL statement.
- c. Repeat the step 10.b for each data source where you want to modify the SQL statement.
- d. Select **Mark Complete**.

11. Configure the import schedules to import data at regular intervals.

- a. In the **Setup** stage of the playbook, select the **Configure import schedule** activity.
- b. Expand the Parent scheduled data import within the Import schedules list to select the **Connection Name-SCCM Computer Identity** import schedule.
- c. Select the **Active** check box, and then fill in the run schedule and time details.

For more information, see [Schedule a data import](#).

- d. Select **Save**.
Alternatively, select **Execute Now** to execute the import schedule immediately.
- e. Select **Continue**.

12. In the **Setup** stage of the playbook, select the **Confirm connection creation** activity to verify whether the connection was created.

What to do next

Select **View all connections** to review the connection details. The created connection appears in the Installed connections list.

Related tasks

- [Enable Software Editions in Service Graph Connector for Microsoft SCCM](#)

Related concepts

- [Service Graph Connector for Microsoft SCCM](#)
- [Accessing the connection details of Service Graph Connector for Microsoft SCCM](#)
- [Configuring air gap connections for Microsoft SCCM](#)

Related reference

- [CMDB classes targeted in Service Graph Connector for Microsoft SCCM](#)

Configure Service Graph Connector for Microsoft SCCM using the guided setup

Set up and validate data source connection credentials to import Microsoft SCCM data into your CMDB.

Before you begin

Important: Unless there are configuration issues, use the SGC Central view in the CMDB Workspace to configure the connection for the connector, as the guided setup method is being deprecated.

Confirm that you are in the Service Graph Connector for Microsoft SCCM application scope by using the application picker.

Note: If you're currently using a version of the Microsoft SCCM plugin, see [Upgrade from the legacy SCCM plugin to the Service Graph Connector for Microsoft SCCM](#).

Dependencies and requirements:

- The [Integration Commons for CMDB](#) store app, which is automatically installed.
- The CMDB CI class models store app, which is automatically installed. See [CMDB CI Class Models](#).
- Integration - JDBC (com.snc.integration.jdbc)
- Windows MID Server required for access to the SCCM environment.

To access Microsoft SCCM data, you must have appropriate access to the Microsoft SCCM database. You must have sufficient credentials to query the SQL Server that contains the Microsoft SCCM database. You must do the following:

1. Create a SQL Server account to connect to the Microsoft SCCM database on the MID Server to use the data sources.
2. Connect to your Microsoft SCCM SQL Server and configure the following:

- a. Add a new login user name and password for SQL authentication.
- b. Choose the Microsoft SCCM database that ServiceNow data sources will connect to.
- c. Assign the db_datareader role membership to the Microsoft SCCM user.

Note: If you have the Service Graph Connector for Microsoft SCCM version 2.1.6 or earlier versions installed in your production environment, contact Customer Service and Support for additional steps to remove the SCCM Discovery Source from being included when calculating the subscription unit consumption.

Starting with Service Graph Connector for Microsoft SCCM version 3.0.4, support for multi-instance is introduced, enabling Service Graph Connector for Microsoft SCCM to connect to and import data from multiple Microsoft SCCM instances. This feature involves dynamically creating data sources and scheduled imports, requiring the granting of additional permissions. For more information about how to complete these steps, see [Service Graph Connector for Microsoft 3.0 Setup Guidelines \[KB1001248\]](#) in Now Support.

Air gap connections are available from version 3.7.0 of the Service Graph Connector for Microsoft SCCM. You can add either standard data sources or air gap data sources by using SGC Central. Before you set up air gap data sources, you must configure the air gap solution for the Service Graph Connector for Microsoft SCCM in your high-secure server and low-secure server. See [Configuring air gap connections for Microsoft SCCM](#).

Role required: SGC-Admin (sn_cmdb_int_util.sgc_admin)

Note: The admin user role is required to run background scripts and to provide table-level access to the SGC-Admin user.

Procedure

1. Navigate to **All > Service Graph Connectors > SCCM > Setup**.
2. On the Getting Started page, select **Get Started**.

3. On the Service Graph Connector for Microsoft SCCM page, in the Configure Data source and Scheduled data import access section, select the task **Configure Data source access**.
4. Update the data source access to enable creating data sources and scheduled data imports for a new connection in the Service Graph Connector for Microsoft SCCM.
 - a. For the Configure Data source access task, select **Configure**.
 - b. Select the **Global** application scope by using the application picker.
 - c. In the Application Access related list, select the **Can create**, **Can update**, and **Can delete** check boxes, if not already selected.
 - d. Select **Update** to close the tab and return to the guided setup.
 - e. Modify the application scope again to **Service Graph Connector for Microsoft SCCM** by using the application picker.
 - f. Set the **Update Data Source Access** task to complete by selecting **Mark as Complete**.
 - g. Repeat the steps 4.b to 4.e for the Update Scheduled data import access task with the Scheduled data import [scheduled_data_set] table and set the task to complete by selecting **Mark as Complete**.
5. Configure the authentication credentials and configuration used for connecting to the Microsoft SCCM database.
 - a. Use a user name and password to establish a JDBC connection to the SCCM database.

Note: Perform this step only when you want to use a user name and password to establish a JDBC connection. Otherwise, select **Skip** to skip the step.

 - a. For the Configure connection task in the Configure the connection section, select **Configure**.
 - b. Configure the connection.

- To configure the connection available by default, select **Configure** for the SCCM JDBC Connection Credentials connection.
- To create another connection, select **Add Connection**.

Note: You can create multiple connections by selecting **Add Connection**. If not redirected to the connection setup, on the Workflow Studio Integrations page search for SCCM JDBC Connection Credentials to modify the default connection or add another connection.

c. On the form, fill in the fields.

Configure Connection or Create Connection form

Field	Description
Connection Information	
Connection name	Name to identify the Microsoft SCCM connection record. For example, SG-SCCM connection .
Query timeout	Number of seconds the JDBC driver waits for a query to complete. 0 indicates no timeout. If the timeout is exceeded, the integration considers the JDBC result inaccessible and marks the result as an error.
Connection timeout	Number of seconds before the MID Server connection cache pool closes the

Field	Description
	connection and removes the connection. 0 indicates no timeout.
Format	JDBC driver used for connecting to the Microsoft SCCM database. Microsoft SCCM uses Microsoft SQL Server as its database backend. This field is automatically set to com.microsoft.sqlserver.jdbc.SQLServerDriver. Leave the field value as is.
Host	Network address of the server where the Microsoft SQL Server database is located.
Database name	Name of the Microsoft SQL Server database that Microsoft SCCM uses.
Override default port	Custom port of the Microsoft SQL Server instance. The default port for Microsoft SQL Server is 1433
Instance name	Microsoft SQL Server instance.
Use MID Server	Option to use the MID Server for accessing the JDBC server.

Field	Description
MID Server	MID Server for the connection. Note: It's required to select a MID Server for an Integrated Authentication connection. For the SCCM JDBC Connection Credentials option.
Credential Information	
Username	User name for connecting to the JDBC server.
Password	Password for the JDBC server.

- d. Save your changes.
 - For the default connection, select **Configure Connection**.
 - For a new connection, select **Create Connection**.
- e. Navigate back to the guided setup and set the Configure connection task to complete by selecting **Mark as Complete**.
- b. Use Windows JDBC-integrated authentication, which uses domain credentials, for authenticating a JDBC connection to the SCCM database.

Note: Perform this step if you need the JDBC connection with integrated authentication. Otherwise, select **Skip** to skip the step.

- a. For the Configure connection (Integrated authentication) task in the Configure the connection section, select **Configure**.
- b. Configure the connection.
 - To configure the connection available by default, select **Configure** for the SCCM JDBC Conn Cred (Integrated Auth) connection.
 - To create another connection, select **Add Connection**.

Note: You can create multiple connections by selecting **Add Connection**. If not redirected to the connection setup, on the Workflow Studio Integrations page section search for SCCM JDBC Conn Cred (Integrated Auth) to modify the default connection or add another connection.

- c. On the form, fill in the fields.

Configure Connection or Create Connection form

Field	Description
Connection name	Name to identify the Microsoft SCCM connection record.
Query timeout	Number of seconds the JDBC driver waits for a query to complete. 0 indicates no timeout. If the timeout is exceeded, the integration considers the JDBC result inaccessible and marks the result as an error.
Connection timeout	Number of seconds before the MID Server connection cache pool closes the

Field	Description
	connection and removes the connection. 0 indicates no timeout.
Host	Network address of the server where the Microsoft SQL Server database is located.
Database name	Name of the Microsoft SQL Server database that Microsoft SCCM uses.
Override default port	Custom port of the Microsoft SQL Server instance. The default port for Microsoft SQL Server is 1433
Instance name	Microsoft SQL Server instance.
MID Server	MID Server for the connection. Note: It's required to select a MID Server for an Integrated Authentication connection. For the SCCM JDBC Connection Credentials option.

d. Save your changes.

- For the default connection, select **Configure Connection**.
 - For a new connection, select **Create Connection**.
- e. Navigate back to the guided setup and set the Configure connection (Integrated authentication) task to complete by selecting **Mark as Complete**.
6. Configure the connection and connector properties to map attributes and manage data imports.
- a. (Optional) Enable mapping asset tags from Microsoft SCCM to the asset tag attribute in the Computer [cmdb_ci_computer] class.
- a. For the Configure Connection Properties task in the Configure Data Source and Scheduled Data Import section, select **Configure**.
- b. In the Name column, select the connection.
- c. In the Service Graph Connection Properties related list, select **asset_tag** in the Property column.
- d. In the **Value** field, enter `true` to enable mapping asset tags.
- e. Select **Update**.
- f. Navigate back to guided setup and set the Configure Connection Properties task to complete by selecting **Mark as Complete**.
- b. Test the Computer Identity data source to verify that all data sources are properly connected.
- a. For the Validate Data Sources task in the Configure Data Source and Scheduled Data Import section, select **Configure**.
- b. In the Name column, select the Computer Identity data source associated with the connection.
- c. Select **Test Load 20 Records**.
- d. When the **State** field is set to **Complete** and the **Completion code** field is set to **Success**, select the **Return to data source** link.

- e. Navigate back to guided setup and set the Validate Data Sources task to complete by selecting **Mark as Complete**.
 - c. Ensure that all data from the Computer Identity source is imported without the date time filtering during the next test load.
 - a. For the Reset 'Last run datetime' in test load data source task in the Configure Data Source and Scheduled Data Import section, select **Configure**.
 - b. In the Name column, select the Computer Identity data source associated with the connection.
 - c. Clear the **Use last run datetime** check box.
 - d. Select **Update**.
 - e. Navigate back to guided setup and set the Reset 'Last run datetime' in test load data source task to complete by selecting **Mark as Complete**.
7. (Optional) Configure the process for importing disk data when the Discovery application is running.
 - a. Avoid creating duplicate records in the CMDB Disks [cmdb_ci_disk] table.

Note: You can avoid creating duplicate records in the CMDB Disks [cmdb_ci_disk] table when the Discovery application is running by configuring the sn_sccm_integrate.sccm_disks_managed property and setting its value to **true**. By default, the property value is set to **false**.

 - a. For the Configure Disk Data Imports task in the Configure Disk Data Imports section, select **Configure**.
 - b. On the System Property page, set the value of the sn_sccm_integrate.sccm_disks_managed property to **true**.
 - c. Select **Update**.
 - d. Set the Configure Disk Data Imports task to complete by selecting **Mark as Complete**.

Note: Any existing disk records are updated only after the next hardware scan is executed in the Microsoft SCCM instance.

- b. (Optional) Transform imported disk name to disk number format.

Note: You can set the imported disk name to the format Disk #<disknumber>. Where <disknumber> is the number extracted from the imported disk name.

- a. Select the **Integration Commons for CMDB** application scope from the application picker.
- b. For the Configure Disk Name Transformation task in the Configure Disk Data Imports section, select **Configure**.
- c. On the System Property page, set the value of the sn_cmdb_int_util.transform_disk_name_to_discovery_format property to true.
- d. Select **Update**.
- e. From the application picker, select the Service Graph Connector for Microsoft SCCM application scope.
- f. Set the Configure Disk Name Transformation task to complete by selecting **Mark as Complete**.

8. Configure the scheduled data imports.

Note: If the **Use Integrated Authentication** check box is selected for the data source, the run as user for the scheduled data import job must have the import_admin role. For more information, see the ["Use Integrated Authentication" is being unchecked when you run the scheduled import related to SG-SCCM or SG-SCCM Computer Identity Data Source \[KB1312810\]](#) article in the Now Support Knowledge Base.

- a. For the Configure scheduled jobs task in the Configure scheduled jobs task section, select **Configure**.
- b. On the Scheduled Data Import form, verify the field values for the scheduled job.

For more information, see [Schedule a data import](#).

All other Service Graph Connector for Microsoft SCCM scheduled jobs that are active will run in their specified order after the Computer Identity scheduled job is finished running. Select the **Active** check box for a scheduled job to activate the job.

Important: If you are upgrading to the Service Graph Connector for Microsoft SCCM, deactivate the existing 'SG-SCCM Computer Identity scheduled data import'. Additionally, you cannot use the baseline scheduled data import or data sources that have a name starting with 'SG-SCCM' because they are used as templates for creating an instance of data sources and scheduled data imports.

- c. Select **Update**.
 - d. Set the Configure Scheduled data imports task to complete by selecting **Mark as Complete**.
 - e. (Optional) When upgrading the Service Graph Connector for Microsoft SCCM, deactivate the existing SG-SCCM Computer Identity scheduled data import.
For the Deactivate Legacy Scheduled Data Imports task, select **Configure**.
 - f. In the Name column, select the SG-SCCM Computer Identity scheduled data import and clear the **Active** check box.
 - g. Set the Deactivate Legacy Scheduled Data Imports task to complete by selecting **Mark as Complete**.
9. (Optional) Customize the Instance Data source SQL statement.
- a. For the Customizing Data source SQL statement task in the Customize Instance Data source SQL statement section, select **Configure**.
 - b. Select the name of the instance in which you want to customize the SQL statement.
 - c. Select **Update**.

- d. Set the Customizing Data source SQL statement task to complete by selecting **Mark as Complete**.

To resolve issues when configuring the connector, you can view the following additional resources:

- [How to identify and delete duplicate CMDB CI Relationship records or ones that have orphan or missing parent/child relationships \[KB0780988\]](#) in the Now Support Knowledge Base
- [How to delete sys_object_source records \[KB0746309 \]](#) in the Now Support Knowledge Base
- [Duplicate software installs with different Discovery Source \[KB0958768\]](#) in the Now Support Knowledge Base
- [Assigned To Field Doesn't Get Updated For Computer CIs in Service Graph Connector for SCCM \[KB1277555\]](#) in the Now Support Knowledge Base
- [Service Graph connector for Microsoft SCCM software usages data import](#) blog post on the ServiceNow Community site

Related tasks

- [Configure Service Graph Connector for Microsoft SCCM using SGC Central](#)
- [Enable Software Editions in Service Graph Connector for Microsoft SCCM](#)

Related concepts

- [Service Graph Connector for Microsoft SCCM](#)
- [Accessing the connection details of Service Graph Connector for Microsoft SCCM](#)
- [Configuring air gap connections for Microsoft SCCM](#)

Related reference

- [CMDB classes targeted in Service Graph Connector for Microsoft SCCM](#)

CMDB classes targeted in Service Graph Connector for Microsoft SCCM

When you complete setting up the connection, you can configure the integration to periodically pull data from Microsoft SCCM. The data is saved in tables that extend from the Configuration item [cmdb_ci] table.

Computer [cmdb_ci_computer]

The following attributes in the Computer [cmdb_ci_computer] table are populated by collected data:

Attribute label	Attribute name
Serial number	serial_number
CPU core count	cpu_core_count
CPU speed (MHz)	cpu_speed
CPU type	cpu_type
CPU manufacturer	cpu_manufacturer
Name	name
Asset tag	asset_tag
Assigned	assigned
Chassis type	chassis_type
Class	sys_class_name
CPU core thread	cpu_core_thread
CPU count	cpu_count
CPU name	cpu_name
Default Gateway	default_gateway

Attribute label	Attribute name
DNS Domain	dns_domain
Most recent discovery	last_discovered
Operating System	os
OS Address Width (bits)	os_address_width
OS Domain	os_domain
OS Service Pack	os_service_pack
OS Version	os_version
RAM (MB)	ram
Model ID	model_id
Manufacturer	manufacturer
Assigned to	assigned_to

Relationships created for Computer

Parent class	Relationship type	Child class
Computer [cmdb_ci_computer]	Owns::Owned by	Network Adapter [cmdb_ci_network_adapter]
Computer [cmdb_ci_computer]	Owns::Owned by	IP Address [cmdb_ci_ip_address]
Computer [cmdb_ci_computer]	Contains::Contained by	Disk [cmdb_ci_disk]
Computer [cmdb_ci_computer]	Reference	Key Value [cmdb_key_value]

Parent class	Relationship type	Child class
Computer [cmdb_ci_computer]	Reference	Software Installation [cmdb_sam_sw_install]
Computer [cmdb_ci_computer]	Reference	SG-SCCM Computer Related [sn_sccm_integrate_sccm_2019_computer_related]

Disk [cmdb_ci_disk]

The following attributes in the Disk [cmdb_ci_disk] table are populated by collected data:

Attribute label	Attribute name
Disk space (GB)	disk_space
Size bytes	size_bytes
Computer	computer
Device ID	device_id
Name	name
Description	short_description
Drive type	drive_type
Manufacturer	manufacturer
Model ID	model_id

Relationship created for Disk

Parent class	Relationship type	Child class
Disk [cmdb_ci_disk]	Reference	Computer [cmdb_ci_computer]

IP Address [cmdb_ci_ip_address]

The following attributes in the IP Address [cmdb_ci_ip_address] table are populated by collected data:

Attribute label	Attribute name
IP Address	ip_address
IP version	ip_version
Name	name
Nic	nic

Relationship created for IP Address

Parent class	Relationship type	Child class
IP Address [cmdb_ci_ip_address]	Reference	Network Adapter [cmdb_ci_network_adapter]

Key Value [cmdb_key_value]

The following attributes in the Key Value [cmdb_key_value] table are populated by collected data:

Attribute label	Attribute name
Key	key
Value	value

Network Adapter [cmdb_ci_network_adapter]

The following attributes in the Network Adapter [cmdb_ci_network_adapter] table are populated by collected data:

Attribute label	Attribute name
MAC Address	mac_address

Attribute label	Attribute name
Name	name
DHCP Enabled	dhcp_enabled
Netmask	netmask
Configuration Item	cmdb_ci

Relationship created for Network Adapter

Parent class	Relationship type	Child class
Network Adapter [cmdb_ci_network_adapter]	Reference	Computer [cmdb_ci_computer]

Serial Number [cmdb_serial_number]

The following attributes in the Serial Number [cmdb_serial_number] table are populated by collected data:

Attribute label	Attribute name
Serial Number	serial_number
Serial Number Type	serial_number_type
Valid	valid

Relationship created for Serial Number

Parent class	Relationship type	Child class
Serial Number [cmdb_serial_number]	Reference	Computer [cmdb_ci_computer]

SG-SCCM Computer Related [sn_sccm_integrate_sccm_2019_computer_related]

The following attributes in the SG-SCCM Computer Related [sn_sccm_integrate_sccm_2019_computer_related] table are populated by collected data:

Attribute label	Attribute name
Resource ID	resource_id
OU Name	ou_name

Software [cmdb_ci_spkg]

The following attributes in the Software [cmdb_ci_spkg] table are populated by collected data:

Attribute label	Attribute name
Key	key
Name	name
Version	version
Vendor	vendor
Manufacturer	manufacturer

Relationship created for Software

Parent class	Relationship type	Child class
Software [cmdb_ci_spkg]	Reference	Software Instance [cmdb_software_instance]

Software Installation [cmdb_sam_sw_install]

The following attributes in the Software Installation [cmdb_sam_sw_install] table are populated by collected data when the SAM application is installed:

Attribute label	Attribute name
Publisher	publisher
Last scanned	last_scanned
Installed on	installed_on
Display name	display_name
Discovery source	discovery_source
Install date	install_date
Prod id	prod_id
Version	version
Revision	revision
Sccm group ID	sccm_group_id
SCCM TimeStamp	sccm_timestamp
Assigned to	assigned_to

Relationship created for Software Installation

Parent class	Relationship type	Child class
Software Installation [cmdb_sam_sw_install]	Reference	Computer [cmdb_ci_computer]

Software Instance [cmdb_software_instance]

The following attributes in the Software Instance [cmdb_software_instance] table are populated by collected data:

Attribute label	Attribute name
Name	name

Attribute label	Attribute name
Installed on	installed_on
Install date	install_date
Sccm group ID	sccm_group_id
SCCM TimeStamp	sccm_timestamp

Relationship created for Software Instance

Parent class	Relationship type	Child class
Software Instance [cmdb_software_instance]	Reference	Computer [cmdb_ci_computer]

Upgrade from the legacy SCCM plugin to the Service Graph Connector for Microsoft SCCM

Deactivate the scheduled imports and pull records so that you can upgrade from the Microsoft SCCM 2016 plugin or an earlier version of the plugin to the Service Graph Connector for Microsoft SCCM.

Before you begin

Role required: none

If you are upgrading to the Service Graph Connector for Microsoft SCCM, the following steps are mandatory. The steps must be executed in any instance with an existing install of the Microsoft SCCM 2016 plugin or with an earlier version of the plugin.

Note: The Service Graph Connector for Microsoft SCCM is an independent implementation that does not reuse any components from the Microsoft SCCM 2016 plugin.

About this task

The Service Graph Connector for Microsoft SCCM is a successor to the Microsoft SCCM 2016 plugin. If you already have the Microsoft SCCM 2016 plugin or an earlier version installed in your instance, you must follow these steps to enable the successful transition from using the SCCM plugin to using the Service Graph Connector. Additionally, you can run a SG-SCCM cleanup to delete the Network Adapters and Disks created from the older SCCM plugin to make the migration faster.

When the Service Graph Connector for Microsoft SCCM is installed in an instance, you must no longer run any components from the Microsoft SCCM 2016 plugin, including Data Sources and Scheduled Data Imports. The SCCM 2016 plugin Scheduled Data Imports must be tuned off. The Service Graph Connector for Microsoft SCCM installs a new set of SG-SCCM Data Sources and Scheduled Data Imports.

Warning: This upgrade process should be performed and validated in a non-production or test instance that is based on a recent clone of the customer production instance. Failure to first validate upgrade in a non-production instance may result in unexpected outcomes and possible data loss or corruption.

Any customizations to the SCCM 2016 plugin will not automatically migrate. The customizations would have to be reimplemented in the Service Graph Connector for Microsoft SCCM, such as by using IntegrationHub-ETL.

Procedure

1. (Optional) If you are migrating from the SCCM 2016 plugin, then run the Migration Readiness Tool for Service Graph Connector for SCCM.

The plugin can be downloaded from the [ServiceNow Store](#).

The tool does not migrate any changes, but runs a series of ATF tests to identify any customizations that were done to the legacy SCCM 2016 plugin compared to the OOB SCCM 2016 plugin. It will not migrate the changes between the two plugins, but serves to alert any customizations.

2. After the tool has finished running, review the tests that were failed.

A failed test means that a customization was made in the plugin. The customization could be a transform map. For example, if a transform map was modified, then it needs to be reimplemented in the connector.

3. Deactivate the scheduled imports from the older SCCM plugin. For more information on how to deactivate scheduled imports, see [Upgrade the SCCM integration version](#).
4. (Optional) Delete duplicate OS software records in the older SCCM plugin.

Note: There is no cleanup required for Computer OS Software records if SAM is enabled.

- a. Navigate to the Software Package or Software Instance table in the older SCCM plugin.
- b. Search for the duplicate OS records that you want to delete. You can tell which records are the SG-SCCM software OS records if the version number is included in the Name or Product Name.
- c. To delete the duplicate software OS records from the Software Package table, do the following:
 - a. On the Software Package table, select the duplicate OS record that does not have **SG-SCCM** in the **Discovery Source** column.
 - b. Delete the duplicate OS record and repeat with other records as needed.
- d. To delete the duplicate software OS records from the Software Instance table, do the following:
 - a. On the Software Instance table, select the duplicate OS record that has the **SCCM group ID** column empty.
 - b. Delete the duplicate OS record and repeat with other records as needed.

Note: This step is optional because there is a difference in the way software OS records are written to the CMDB, between the legacy SCCM plugin and Service Graph Connector. The SCCM plugin did not record values to `sys_object_source`, a `discovery_source`, or a `sccm_group_id`.

5. After you are finished deactivating the scheduled imports and deleting the duplicate OS records from the older SCCM plugin, configure the connector.
For instructions, see [Configure the Service Graph Connector for Microsoft SCCM](#).
6. (Optional) Clean up the Disk and Network Adapter records created by the SCCM plugin.
 - a. Confirm that you are in the Service Graph Connector for Microsoft SCCM application scope.
 - b. Navigate to **Scheduled Job > SG-SCCM CleanupUtil**.
 - c. Select the SG-SCCM CleanupUtil scheduled job, and then switch to the global application scope.
 - d. To make a copy of the scheduled job, right-click the header of the scheduled job and select **Insert and Stay**.
 - e. Change the name to **SG-SCCM CleanupUtil Global**.
 - f. Click **Update**.
 - g. When you need to run the scheduled job, click **Execute Now**.
 - h. (Optional) To check the progress of the run, do the following:
 - a. Navigate to **System Log > All**.
 - b. To filter the records for the script run, enter `SG-sCCM CleanupUtil` under the **Message** search box.
The script will have a log message for each batch so that you know the status of the current run and its progress.

Note: The duration of the run depends on the amount of Network Adapter and Disk data in the CMDB from the previous SCCM integration. The data must meet the condition for the cleanup.

What to do next

When you execute the Service Graph Connector components, your existing CMDB data created by the SCCM plugin becomes managed and maintained by Service Graph Connector for Microsoft SCCM.

Upgrade to the latest version of Service Graph Connector for Microsoft SCCM

Upgrade your Service Graph Connector for Microsoft SCCM. When you upgrade versions, you can select the files that you want to transfer from the earlier version to the later version of the Service Graph Connector for Microsoft SCCM.

Before you begin

To avoid any serious upgrade issues, perform the upgrade in a test or development instance prior to upgrading in a production environment.

Role required: admin

About this task

When you upgrade from an earlier version to the latest version of the Service Graph Connector for Microsoft SCCM, there are Skipped Updates. The original SCCM data source files that were installed have the last run date updated as part of the data source runs. The files will be treated as custom files by the platform. When the newer version is installed, the newer data sources will not be automatically upgraded.

After you have upgraded to the newer version, you can check the upgrade status.

Procedure

1. Review all the updates from the upgrade center and select the data source files from the newer version.
You can access the upgrade history and review the updates from the Skipped Changes to Review related list. See [Review skipped records using related lists](#).
2. If you have customized the earlier version, select the changes that you need from the older file and migrate them to the new file.

Note: Repeat this migration process for all the other skipped update files.

What to do next

After the upgrade, if there are changes to the SQL in the data source files or mapping, then do the following:

1. Clear the **Use last run datetime** check box in all the data sources.
2. Perform a full pull of data from all the data sources.

Note: Upgrading from Service Graph Connector for Microsoft SCCM v2.3 to v2.3.1 requires a minimum pull of Computer and Software, because the Source Native Key for the software within the SQL was changed in the SG-SCCM Removed Software data source. Without the correct Source Native Keys, it will not be able find the software in the CMDB.

For more information on resolving any conflicts, see the following topics:

- [Revert a customization](#)
- [Resolve a skipped update and set a resolution status](#)
- [Skipped Changes to Review related list](#)

Enable Software Editions in Service Graph Connector for Microsoft SCCM

Enable software editions so that you can gather edition information for products such as Adobe Acrobat, Microsoft SQL Server, and Windows Exchange Server into the Service Graph Connector for Microsoft SCCM.

Before you begin

Note: There are two types of setup that are required, one on the SCCM Manager and the other on the ServiceNow Instance. For more information on how to set up the SCCM Manager, see the SCCM Manager Setup section of the [Custom solution to gather editions in SCCM \[KB0721360\]](#) article on the HI Knowledge Base. When you're finished setting up the SCCM Manager, refer back to this task and complete the steps.

Role required: admin

About this task

You can set up the ServiceNow Instance on the Service Graph Connector for Microsoft SCCM.

Procedure

1. Navigate to **All > Service Graph Connector Microsoft SCCM > Import Schedules**.
2. Select the Software Edition scheduled import you created to edit this import record.
3. Select the **Active** check box.
4. Click **Update**.
5. Navigate to **Service Graph Connector Microsoft SCCM > Data Sources**.
6. Select the Software Edition data source you created.
7. Under the Transforms list, select **Update software install with edition**.

8. Edit the data source and select the **Active** check box.
9. Click **Update**.

What to do next

You can verify that the edition information has been gathered by doing the following:

1. Navigate to **Service Graph Connector Microsoft SCCM > Data Sources** and the Software Edition data source you want to verify.
2. Select **Load All Records**.

Note: If the displayed completion code is Success, then the software edition data source was executed successfully. If the displayed completion code is Error, then there is an error that must be fixed.

Accessing the connection details of Service Graph Connector for Microsoft SCCM

You can access the connection details of the Service Graph Connector for Microsoft SCCM in a single view using the common connection framework (CCF) included within the Integration Commons for CMDB (sn_cmdb_int_util) store app.

With the CCF, you can access all the connections used by the Service Graph Connector for Microsoft SCCM. The connection details include the connection alias, connection properties, data sources, and scheduled data imports associated with a connection. You can also test the connection. For more information, see [Accessing the connection details of Service Graph Connectors](#).

Access the details of a Microsoft SCCM connection

Access the details of a Microsoft SCCM connection configured for the Service Graph Connector for Microsoft SCCM.

Before you begin

Role required: admin

Procedure

1. Navigate to **All > Service Graph Connectors > SCCM > Connections**.
2. From the **Name** column of the Service Graph Connections list, select a connection.
3. On the Service Graph Connections page, view the connection details such as the connection name, alias, and data sources.
4. Select a related list to view further details of the connection.
5. (Optional) Select the **Test Connection** related link to test the connection.

Configuring air gap connections for Microsoft SCCM

Air gap connections for the Service Graph Connector for Microsoft SCCM enable safe and controlled data transfer without compromising security.

An air gap is a security measure that involves isolating a computer or network and preventing it from establishing an external connection. Air-gapped networks keep critical systems secure by isolating them from external connections to protect the systems from cyber threats. Air gap connections for the Service Graph Connector for Microsoft SCCM facilitate controlled data exchange between the air-gapped networks and external systems while maintaining the integrity of the air-gapped environment.

Air gap connections are available from version 3.7.0 of the Service Graph Connector for Microsoft SCCM. You can add either standard data sources or air gap data sources by using SGC Central. To access the SGC Central setup, see [Configure Service Graph Connector for Microsoft SCCM using SGC Central](#).

Perform the following sequence of tasks to configure the air gap solution before you add air gap data sources:

1. [Configure air gap solution for Microsoft SCCM in a high-secure server](#)
2. [Configure air gap solution for Microsoft SCCM in a low-secure server](#)
3. [Configure air gap solution for Microsoft SCCM in a ServiceNow instance](#)

4. Perform a test data load for the air gap solution for Microsoft SCCM
5. Perform a full data load for the air gap solution for Microsoft SCCM

Configure air gap solution for Microsoft SCCM in a high-secure server

Configure the air gap solution for the Service Graph Connector for Microsoft SCCM in your high-secure server.

Before you begin

Role required: admin

Procedure

1. Navigate to **Workspaces > CMDB Workspace > SGC Central > Create connection**.
2. Select the air gap template.
 - a. In the **Setup** stage of the playbook, select the **Select alias template** activity.
 - b. Select **SCCM Air Gap**.
 - c. Select **Continue**.
3. Download and run the PowerShell scripts to set up an air gap connection.
 - a. In the **Setup** stage of the playbook, select the **PowerShell Script Download** activity.
 - b. Select **Download Airgap Scripts**.
 - c. Download the SgSCCMHighSecureSetup.ps1 and GetSCCMData.ps1 PowerShell scripts from the link provided in the Download Airgap Scripts section.
4. Log on to your high-secure server.
5. Create a Microsoft SCCM directory.

All the configurations required for the air gap solution are created in the Microsoft SCCM directory.

6. Copy the GetSCCMDData.ps1 and SgSCCMHighSecureSetup.ps1 PowerShell scripts that you downloaded in step 3.c to the Microsoft SCCM directory.
7. Start a PowerShell session, and run the SgSCCMHighSecureSetup.ps1 script to generate the JSON configuration file that is used by the GetSCCMDData.ps1 script.
 - a. At the prompt, enter the path for the Microsoft SCCM directory that you created in step 5.
 - b. Enter a name for the configuration file, or press the Return key to accept the default value.
 - c. Enter the values for the global properties, or press the Return key to accept the default values.
 - logDirectory: Specify the location to store the log file from the GetSCCMDData.ps1 script.
 - host: Specify the host name for your Microsoft SCCM instance.
 - dbname: Specify the SCCM database name.
 - port: Specify the port on which the Microsoft SCCM instance allows API calls.
 - pageSize: Specify the number of records to be fetched in a Microsoft SCCM API call.
 - credentialsPath: Specify the location to store the Microsoft SCCM credentials XML file.
 - d. Specify names for the data source data directories, or press the Return key to accept the default values.

The directories are created if they don't already exist.
 - e. Enter the Microsoft SCCM credentials.

Note: You can either use Windows credential manager to store the user name and password, or implement your own mechanism for storing the credentials. The GetSCCMData.ps1 script must have access to the credentials to trigger REST calls.

- f. Exit the PowerShell session.
8. Provide write and delete permissions for the Microsoft SCCM directory and the child directories.

You must provide delete permissions for old records to be cleaned up.

Related tasks

- [Configure air gap solution for Microsoft SCCM in a low-secure server](#)

Configure air gap solution for Microsoft SCCM in a low-secure server

Configure the air gap solution for the Service Graph Connector for Microsoft SCCM in your low-secure server after you finish the configuration in your high-secure server.

Before you begin

Role required: admin

Procedure

1. Navigate to **Workspaces > CMDB Workspace > SGC Central > Create connection**.
2. Select the air gap template.
 - a. In the **Setup** stage of the playbook, select the **Select alias template** activity.
 - b. Select **SCCM Air Gap**.
 - c. Select **Continue**.

3. Download and run the PowerShell scripts to set up an air gap connection.
 - a. In the **Setup** stage of the playbook, select the **PowerShell Script Download** activity.
 - b. Select **Download Airgap Scripts**.
 - c. Download the SgSCCMLowSecureSetup.ps1 PowerShell script from the link provided in the Download Airgap Scripts section.
4. Log on to your low-secure server.
5. Create a Microsoft SCCM directory.

All the configurations required for the air gap solution are created in the Microsoft SCCM directory.

6. Copy the SgSCCMLowSecureSetup.ps1 PowerShell script that you downloaded in step 3.c to the Microsoft SCCM directory.
7. Start a PowerShell session, and run the SgSCCMLowSecureSetup.ps1 script.
 - a. At the prompt, enter the path for the Microsoft SCCM directory that you created in step 5.
 - b. Specify names for the data source data directories, or press the Return key to accept the default values.

The directories are created if they don't already exist.
 - c. Exit the PowerShell session.
8. Provide read and delete permissions for the Microsoft SCCM directory.

Related tasks

- [Configure air gap solution for Microsoft SCCM in a ServiceNow instance](#)

Configure air gap solution for Microsoft SCCM in a ServiceNow instance

Configure the air gap solution for the Service Graph Connector for Microsoft SCCM in your ServiceNow instance after you finish the configuration in your high-secure and low-secure servers.

Before you begin

Role required: admin

Procedure

1. Navigate to **All > System Definition > Plugins**, and download the ServiceNow IntegrationHub Action Step – PowerShell plugin.
2. Navigate to **Workspaces > CMDB Workspace > SGC Central > Create connection**.
3. Download and run the PowerShell scripts to set up an air gap connection.
 - a. In the **Setup** stage of the playbook, select the **Select alias template** activity.
 - b. Select **SCCM Air Gap**, and then select **Continue**.
 - c. In the **Setup** stage of the playbook, select the **PowerShell Script Download** activity.
 - d. Download the scripts and configure the air gap connection.
 - e. Select the **I have read the instructions and executed the scripts accordingly** check box, and then select **Continue**.
4. In the **Setup** stage of the playbook, select the **Create and test connection** activity.
5. Fill in the fields on the Create Connection form.

Create Connection form

Field	Description
Connection Name	Display name for the connection.
MID Server	Name of the MID Server that you deployed in your low-secure server. You can obtain the sys_id of the MID Server from the ecc_agent table.
Parent Directory	Path of the Microsoft SCCM directory where the data is stored in your low-secure server. See Configure air gap solution for Microsoft SCCM in a low-secure server.
Archive Data After Retrieval	Option to archive data after retrieval.
Archive Path [Optional]	Folder where the data is to be archived if the Archive Data After Retrieval check box is selected.

6. Select **Create and test connection**.

Related tasks

- [Perform a test data load for the air gap solution for Microsoft SCCM](#)

Perform a test data load for the air gap solution for Microsoft SCCM

After you configure the air gap solution for the Service Graph Connector for Microsoft SCCM, test whether the Microsoft SCCM endpoint is accessible from the high-secure server.

Before you begin

Role required: admin

Procedure

1. Navigate to the Microsoft SCCM directory in your high-secure server.
2. Run the `.\GetSCCMDData.ps1 -configFilePath CONFIG_PATH` script, where CONFIG_PATH is the location of the JSON configuration file that is generated by the setup script. The script accesses the Microsoft SCCM API, and creates a sample file in the ComputerIdentity directory and a log file in the Logs directory.

- If the test data load is successful, the log file contains the Test Load status SUCCESS! message.
- If the test data load fails, the log file contains the Error occurred while processing ComputerIdentity StatusCode 403 message.

If the test data load fails, verify the Microsoft SCCM user credentials and ensure that the user has the required permissions to pull the data from Microsoft SCCM. If the credentials need to be updated, you must run the `SgSCCMHighSecureSetup.ps1` PowerShell script again. See [Configure air gap solution for Microsoft SCCM in a high-secure server](#).

Related tasks

- [Perform a full data load for the air gap solution for Microsoft SCCM](#)

Perform a full data load for the air gap solution for Microsoft SCCM

After you verify that the test data load for the air gap solution for the Service Graph Connector for Microsoft SCCM is successful, you can perform a full data load.

Before you begin

Role required: admin

Procedure

1. Navigate to the Microsoft SCCM directory in your high-secure server.
2. Run the `.\GetSCCMDData.ps1 -completeLoad $true -configFilePath CONFIG_PATH` script, where CONFIG_PATH is the location of the JSON configuration file that is generated by the setup script.

By default, the existing files in the data source data directories are deleted each time the `.\GetSCCMDData.ps1 -completeLoad $true -configFilePath CONFIG_PATH` script is run. You can add the `-clean $false` parameter to the script if you want to retain the existing files.

The script fetches data from all the Microsoft SCCM APIs, and stores the data in the respective directories.

3. After the data is loaded in your high-secure server, transfer the data to your low-secure server using a method of your choice.
4. Verify that the data is loaded in your low-secure server.
5. Set the full data load job (using the `.\GetSCCMDData.ps1 -completeLoad $true -configFilePath CONFIG_PATH` script) to run on a schedule based on that of the Scheduled Import Job on your Service Graph Connector for Microsoft SCCM instance.
6. Set the data transfer job (from your high-secure server to your low-secure server) on a schedule based on that of the Scheduled Import Job on your Service Graph Connector for Microsoft SCCM instance.
7. Test the air gap connection in your ServiceNow instance.

- a. Navigate to **All > Service Graph Connectors > SCCM > Connections**.
- b. Select the air gap connection that you created.
- c. Select the **Test Connection** related link.
When the connection is successful, the **Status** field is set to **success**. If the connection fails, follow the suggestions for remediation.