Docker Swarm 起手式 + Portainer

Daniel


https://ppt.cc/fgMWJx

Agenda


- 1. 前情提要
- 2. 什麼是 Docker Swarm
- 3. 為什麼我選擇 Docker Swarm?
- 4. Docker Swarm 簡介與實作
- 5. 什麼是 Portainer
- 6. Portainer 簡介與實作

前情提要 - Docker Engine

- Docker 是採用 Client-Server 架構
- Server 會起一個 daemon 叫 dockerd
- REST API 接口會跟 daemon 溝通, 並下達 指示
- Docker CLI的指令叫 docker




前情提要 - Docker Architecture



什麼是 Docker Swarm

Docker Swarm 是 Docker 官方自已發行的一個核心項目, 主要是用來提供 Docker 容器集群的服務, 也可以將多個 Docker Host 主機串成一個容器雲平台的集群。






為什麼我選擇 Docker Swarm?


- Docker 官方出品, 原生支持。
- 簡單、上手容易、架構較簡單。
- 擴展容易。
- 用於專案方便。

Docker Swarm 簡介 - 特性

- 內建 Docker Engine (Docker 1.12+)
- 分散式設計
- 聲明性服務模型
- 協調期望狀態與實際狀態之間的差異
- 多主機網路
- 服務發現、負載平衡、安全
- 滾動升級

Docker Swarm 簡介 - Architecture





Docker Swarm 簡介 - 容錯

Swarm Size	Majority	Fault Tolerance
1	1	0
2	2	0
3	2	1
4	3	1
5	3	2
6	4	2
7	4	3
8	5	3
9	5	4

Docker Swarm Hands-On Lab

Docker Swarm 初始化

- 初始化 Docker Swarm
 \$ docker swarm init --advertise-addr \${IP}
- 加入 Docker Swarm (管理群 | 工作群) \$ docker swarm join-token (manager | worker)
- 只顯示 Dcoker Swarm (管理群 | 工作群) Token
 \$ docker swarm join-token -q (manager | worker)
- 離開 Docker Swarm 集群\$ docker swarm leave -f

了解 Docker Swarm Node 的狀態

列出 node

\$ docker swarm node Is

ID	HOSTNAME	STATUS	AVAILABILITY	MANAGER STATUS	ENGINE VERSION
qe7nzq03hd3vg5v1h6z68qqnr	node1	Ready	Active	Leader	18.06.1-ce
oliksz1362cgvaklifg1rall3 *	node2	Ready	Active	Reachable	18.06.1-ce
ura30kdpij8le4hkhn4awh5mg	node3	Ready	Active	Reachable	18.06.1-ce
kd4monej7ai25jeu1oidaoivx	node4	Ready	Active		18.06.1-ce
vu7k2t8td50kvs1xvk76qzyr7	node5	Ready	Active		18.06.1-ce

Availability:

- Active: 可以分派新工作到任何節點。
- Pause: 暫停分派新工作給節點, 但不影響現有服務。
- Drain: 不會分派任何新工作給節點, 會把現有的服務移至到可使用的節點上。

Manager Status:

- 沒有值表示不是 Docker Swarm manage node。
- Leader: 主要的管理節點, 並且為整個 Docker Swarm 集群做決策。
- Reachable: 當主要的管理節點掛點,有機會成為主要的管理節點。
- Unavailable: 表示不可以用了。

操作 docker node 相關指令

更改管理節點可用性

\$ docker node update --availability (active | pause | drain) \${node_name}

工作節點變更為管理節點

\$ docker node promote \${node_name}

● 管理節點變更為工作節點

\$ docker node demote \${node_name}

● 刪除工作節點

\$ docker node rm -f \${node_name}

● 給節點新增或刪除標籤

\$ docker node update --label-add <key> or <key>=<value>
\$ docker node update --label-rm <key> or <key>=<value>

Q: Docker Swarm 管理節點壞了一個,該如何修復,並重新加回來到管理集群中?





scenario

操作 Docker Service 相關指令

• 建立容器服務

\$ docker service create --name web nginx

● 查看容器服務

\$ docker service Is

• 查看容器服務中的任務

\$ docker service ps \${SERVICE_NAME}

● 更新容器服務的埠號

\$ docker service update --publish-add local_port:container_port \${SERVICE_NAME}

● 更新容器服務的副本數

\$ docker service update --replicas number \${SERVICE_NAME}

● 刪除容器服務

\$ docker service rm \${SERVICE_NAME}

什麼是 Portainer?

MANAGE YOUR DOCKER ENVIRONMENTS WITH EASE

PORTAINER IS AN OPEN-SOURCE LIGHTWEIGHT MANAGEMENT UI WHICH ALLOWS YOU TO EASILY MANAGE YOUR DOCKER HOSTS OR SWARM CLUSTERS

AVAILABLE ON & LINUX, WINDOWS & SOSX

Q: 請使用 docker service create 來建立 portainer



scenario

\$ docker network create --driver overlay --attachable portainer_agent_network

- --driver (bridge | overlay) 決定要用哪一個 driver 來建立網路, 預設是 bridge
- --attachable 啟用手動容器附件

```
$ docker service create \
      --name portainer_agent \
      --network portainer_agent_network \
      -e AGENT_CLUSTER_ADDR=tasks.portainer_agent \
      --mode global \
      --constraint 'node.platform.os == linux' \
      --mount type=bind,src=/var/run/docker.sock,dst=/var/run/docker.sock \
      --mount type=bind,src=/var/lib/docker/volumes,dst=/var/lib/docker/volumes \
      portainer/agent
--name 給容器服務一個名字
```

- --network 使用網路附件
- -e 設定環境變數
- --mode (global | replicated)容器服務的模式, 預設是使用 replicated
- --constraint 限制要在執行的節點
- --mount 掛載檔案系統到容器服務裡

```
$ docker service create \
    --name portainer \
    --publish 9000:9000 \
    --replicas=1 \
    --constraint 'node.role == manager' \
    --mount type=bind,src=/root/portainer_data/,dst=/data \
    portainer/portainer
```

constraint

node attribute	matches	example
node.id	Node ID	node.id==2ivku8v2gvtg4
node.hostname	Node hostname	node.hostname!=node-2
node.role	Node role	node.role==manager
node.labels	user defined node labels	node.labels.security==high
engine.labels	Docker Engine's labels	engine.labels.operatingsystem==ubuntu 14.04

```
$ docker network ls
$ docker service ls
```


\$ docker service update --network-add portainer_agent_network portainer

DIFFERENCES BETWEEN "--MOUNT" AND "--VOLUME"

The --mount flag supports most options that are supported by the -v or --volume flag for docker run , with some important exceptions:

- The --mount flag allows you to specify a volume driver and volume driver options per volume, without creating the volumes in advance. In contrast, docker run allows you to specify a single volume driver which is shared by all volumes, using the --volume-driver flag.
- The --mount flag allows you to specify custom metadata ("labels") for a volume, before the volume is created.
- When you use --mount with type=bind, the host-path must refer to an existing path on the host. The path will not be created
 for you and the service will fail with an error if the path does not exist.
- The --mount flag does not allow you to relabel a volume with z or z flags, which are used for selinux labeling.

Q: 請使用 docker stack 來部署 portainer



scenario

使用 docker stack 部署 portainer

\$ curl -L https://portainer.io/download/portainer-agent-stack.yml -o portainer-agent-stack.yml

\$ docker stack deploy --compose-file=portainer-agent-stack.yml portainer

參考資料鏈結

- docker overview
- Manage nodes in a swarm
- docker service create
- change node availability
- add or remove label metadata
- change a node role
- <u>Docker Swarm strategies</u>
- docker network understanding

Image credits

- DCOS LOGO
- <u>K8S L0G0</u>
- Docker Swarm LOGO
- <u>Docker Swarm Architecture</u>
- docker logo
- <u>rocket</u>
- portainer logo

https://www.surveycake.com/s/ooPrr

Q & A