


DESIGN SYSTEM REFERENCE

SupportFlow Visual Builder

Canvas layout, node cards, connectors, color semantics, and supporting components.

CANVAS

The canvas is a fixed 1200×800 coordinate space rendered on a near-black background. Every node is absolutely positioned using the x/y values supplied in the flow data, and a single SVG layer beneath the node cards draws all connector paths. Below is the complete graph as rendered from `flow_data.json`, laid out at true relative scale.



PROPERTY	VALUE
Canvas size	1200 × 800 (logical units, matches node x/y coordinate space)
Background	#0A0A0A
Positioning model	Absolute positioning; all children positioned relative to a single relatively-positioned canvas container
Overflow	Scrollable (auto): canvas may exceed viewport at full node spread

NODE CARDS

A single component with three visual states, distinguished entirely by border color and shadow, with no layout changes between states, keeping the graph visually stable while editing.

QUESTION · #2

Have you tried restarting your router?

DEFAULT (border #333)

QUESTION · #2

Have you tried restarting your router?

SELECTED (border #6366f1 + glow)

QUESTION · #3 ⚠ broken link

Is this for a Personal or Business account?

ERROR (border #f43f5e + warning badge)


Type Strip Variants

Start node Question node End node

PROPERTY	VALUE
Card width	220px
Padding	12px
Corner radius	6px
Background	#1A1A1A

CONNECTORS

Parent-to-child relationships are drawn as cubic bezier curves rather than straight lines, giving branches a smooth "S" shape that leaves and enters each card vertically regardless of horizontal offset. Anchor points use each node's real measured DOM height, not a fixed estimate.



PROPERTY	VALUE
Stroke color	#555555
Stroke width	1.5px
Curve type	Cubic bezier, vertical control points (M x1 y1 C x1 y1+n, x2 y2-n, x2 y2)
Arrowhead	8×8 SVG marker, filled triangle, matches stroke color
Anchor points	Parent bottom-center → Child top-center, using measured DOM height

Semantic type colors identify node roles at a glance across the flowchart. All other colors define the dark canvas surface and interaction states.

Node Type Semantic Colors

Start #10B981 Top border strip, start-node accent	Question / Accent #6366F1 Question nodes, selection state, primary buttons	End / Error #F43F5E End nodes, broken-link warning state

Surface & Structure


Canvas background #0A0A0A App root / canvas surface	Card surface #1A1A1A Node cards, edit panel background	Default border #333333 Unselected node card border	Connector line #555555 SVG bezier connectors, arrowheads

Text

TOKEN	VALUE	USAGE
Primary text	#EEEEEE	Node question text, panel labels
Muted label	#EEEEEE at 60% opacity	Type/ID micro-labels above node text
Panel secondary	#888888	Secondary UI chrome, close icons


EDIT PANEL

A fixed-width side panel that appears when a node is selected. It holds the node's editable question text in a monospace textarea, with live edits reflected on the canvas immediately, with no save action required.



PROPERTY	VALUE
Panel width	280–300px, full viewport height
Background	#0E0E0E
Border	1px solid #222 (left edge, separating from canvas)
Header title	"Edit Node #[id]", 12–13px Bold
Textarea font	JetBrains Mono, 9.5–13px
Textarea background	#131313, 1px solid #333 border, 5px radius
Close control	"x" glyph, #666, top-right of header

The editor and edit panel are shown together while a node is selected:
the canvas remains fully interactive on the left, the panel occupies a
fixed column on the right, and the Preview toggle sits above the canvas.



INTERACTION	BEHAVIOR
Node click	Selects node (indigo border + glow), opens Edit Panel for that node
Canvas click (empty space)	Deselects current node, closes Edit Panel
Text edit	Updates canvas card text live, on every keystroke
Preview click	Replaces entire view with full-screen chat simulation (Preview Mode)

TYPOGRAPHY

A single sans-serif family is used throughout the interface, with a monospace family reserved for editable/technical text (IDs, textarea content). Scale is limited and functional rather than decorative.

ROLE	SIZE / WEIGHT / FAMILY	EXAMPLE USAGE
Node question text	13px / Regular / Inter	Primary content inside each node card
Micro label	10px / Regular, uppercase, 0.05em / Inter	Node type + ID (e.g. "QUESTION · #2")
Panel section label	12–13px / Bold / Inter	"Edit Node #[id]" panel header
Editable text field	13px / Regular / JetBrains Mono	Edit panel textarea content
Button label	13px / Semibold / Inter	Preview, Restart, primary actions
Warning badge	10px / Regular / Inter	Broken-link indicator text

Primary family: **Inter** (system-ui, Helvetica, Arial fallback). Monospace family: **JetBrains Mono**, used specifically to visually distinguish editable data from static labels.

SPACING GRID

All spacing in the application is built from a 4px base unit, kept to a small set of recurring values rather than arbitrary pixel choices.

4px	Micro gaps (label margin-bottom)
8px	Tight internal gaps, badge padding
12px	Node card padding
16px	Edit panel padding, button horizontal padding
24px	Section gaps, canvas padding in preview mode

Corner Radius

TOKEN	VALUE	USAGE
Card radius	6px	Node cards
Control radius	4-6px	Buttons, badges, textarea

Primary Button



PROPERTY	VALUE
Background	#6366F1
Text	#FFFFFF, 13px Semibold
Padding	8px 16px
Radius	6px

Warning Badge



PROPERTY	VALUE
Text / border	#F43F5E
Background	#1A1A1A
Font size	10px

SupportFlow Visual Builder: Design System Reference. Values shown are the colors, sizes, states, and node text used consistently across the application (NodeCard, EditPanel, Connectors, and PreviewMode components), matching flow_data.json.