Backend Environment Setup

Guide for updating the class repository's .env.example. Keep real credentials in .env; never commit them or place them in .env.example.

Suggested .env.example content

```
# Local API
NODE_ENV=development
PORT=3000
CORS_ORIGIN=http://localhost:5173

# Keep false locally; true only behind a trusted reverse proxy.
TRUST_PROXY=false

# Leave blank locally. Production rate limiting uses Redis.
RATE_LIMIT_REDIS_URL=

# Frontend pages that receive Supabase email links.
EMAIL_CONFIRMATION_REDIRECT_URL=http://localhost:5173/confirm-email
PASSWORD_RECOVERY_REDIRECT_URL=http://localhost:5173/reset-password
INVITATION_REDIRECT_URL=http://localhost:5173/accept-invitation

# Supabase project values
SUPABASE_URL=https://your-project-ref.supabase.co
SUPABASE_PUBLISHABLE_KEY=sb_publishable_replace_me

# Backend only. Never expose this to the frontend.
SUPABASE_SECRET_KEY=sb_secret_replace_me

# Planned feature; not needed for authentication.
EXCHANGE_RATE_API_KEY=
```

The class repo's src/config/env.ts must also read TRUST_PROXY and RATE_LIMIT_REDIS_URL when you add the reference security setup.

Where to get the values

Supabase URL and publishable key

Open the project dashboard's Connect dialog, or go to Settings > API Keys. For a local Supabase project, running `supabase start` prints local project keys.

Supabase secret key

Copy it from Settings > API Keys. Keep it server-side. The class gateway needs it for privileged invitation and account-deletion operations.

Email redirect URLs

Use actual frontend routes for confirmation, recovery, and invitations. Add each URL in Supabase Auth > URL Configuration > Redirect URLs. The frontend pages must exist; setting a URL here does not create a page.

CORS_ORIGIN

Use the frontend's origin. The example `http://localhost:5173` is for local Vite development.

TRUST_PROXY

Leave false locally. Set true only when the API runs behind a trusted proxy.

RATE_LIMIT_REDIS_URL

Leave blank locally. In Render, copy the internal URL from the Key Value service's Connect menu when the API and Key Value run in the same region.

Official setup references

- Supabase API keys
- Supabase Auth redirect URLs
- Render Key Value