

Google Analytics X Search

Q

juanjo@juanjofp.com Sign out

Home

Products

Conferences

Showcase

Live

Groups

Google Analytics

0

- ▶ Platform
- → Collection
 - ▶ Web Tracking
 - ▼ Android SDK

Overview

▼ Dev Guide

Advanced Configuration

Campaigns

Crashes and Exceptions

Custom Dimensions & Metrics

Dispatch

ECommerce

Events

Screens

Sessions

Social Interactions

User Timinas

- ▶ Reference
- ▶ Resources
- ▶ V1 (Legacy)
- ▶ iOS SDK
- ▶ Measurement Protocol
- ▶ Legacy Libraries
- ▶ Configuration
- ▶ Reporting
- ▶ Solutions

Community & Updates

Developer Program

Custom Dimensions & Metrics - Android SDK

This developer guide describes how to implement custom dimensions and metrics using the Google Analytics SDK for Android v2.

Overview

Custom Dimensions

Setting Values

Implementation Considerations

User and Session-level Scope

Profile filters

Automatic Screen Measurement

Personally indentifiable

information

Custom Metrics

Setting Values

Implementation Considerations

Profile filters

RELATED DOCUMENTS

Overview: Custom Dims & Mets

Platform

Reference: Custom Dims & Mets

Collection

Web Tracking: analytics.js

Android SDK

iOS SDK

Moscuroment Protoco

More

Overview

Before you implement, read the <u>Custom Dimensions and Metrics Feature Guide</u> for a detailed explanation of how custom dimensions and metrics work.

When you set a custom dimension or metric value using the Google Analytics SDK for Android , that value is sent as a parameter with the next hit that is dispatched. Those values can be applied to any Google Analytics hit type, including screen views, events, ecommerce transactions, user timings, and social interactions.

There are two main steps to implement a custom dimension or metric:

1. Define the custom dimension or metric using the Google Analytics web interface.

Set the index, name, and <u>scope</u> of the custom dimension or metric in the property settings section of the web interface.

Learn how to define a custom dimension or metric.

2. Implement code to set and collect custom dimension and metric values.

Add code to your app to set custom dimension or metric values for your Google Analytics hits at the indices you defined in the prior step.

The remainder of this article will describe how to implement the code to set and send custom dimension or metric values to Google Analytics.

Custom Dimensions

Custom dimension values can be set on all Google Analytics hit types. Set a custom dimension value just before the send call to which you want the value applied.

The defined <u>scope</u> of the custom dimension will determine at processing time which additional hits may be associated with that value.

These fields are required to set a custom dimension value:

- Integer Index the index of the custom dimension definition. This index is 1-based.
- String Value the value of the custom dimension.

Setting a Custom Dimension Value

To set a custom dimension value, call setCustomDimension before the send call with which you want to

```
// Get the tracker object.
Tracker tracker = EasyTracker.getTracker();

// Set the dimension value for index 1.
tracker.setCustomDimension(1, "myValue");

// Dimension value is associated and sent with this hit.
tracker.sendView();
```

Implementation Considerations

This section outlines additional considerations to keep in mind when implementing a custom dimension.

User and Session-Level Scopes are Greedy

Custom dimension values with <u>user or session-level scope</u> will apply to all hits in the current session, including past hits. If you don't want a custom dimension value with session or user-level scope to be applied to past hits in the current session, <u>start a new session</u> before applying the value to a hit.

For example, if you're using membership type as a user-level custom dimension, and a user upgrades their membership in the middle of a session, you may want to start a new session before you set the new custom dimension value. This ensures that the hits prior to the upgrade will be associated with the old membership value, while new hits will be associated with the new value.

Custom Dimensions and Profile Filters

User or session-level custom dimension values will still be applied to all hits in the current and/or future sessions even if the hit they are sent with is filtered from a profile.

When filtering on a custom dimension value, hits are filtered according to the scope of that custom dimension value.

Learn more about how filters and custom dimension values interact when your data is processed.

Setting Values with Automatic Screen Measurement

To apply a custom dimension value to a screen view sent via EasyTracker's automatic screen measurement, set the value before activityStart() is called during onStart().

Note that in cases where the value is not known at the time onStart() executes, it is recommended to use manual screen measurement instead.

Do not send personally identifiable information (PII) as values

The Google Analytics <u>Terms of Service</u> prohibit sending of any personally identifiable information (PII) to Google Analytics servers. For more information, please consult the <u>Terms of Service</u>.

Custom Metrics

While custom dimensions need to be carefully applied to specific hits and managed with scope, the hit to which a custom metric is applied will generally not affect reporting, and thus they can be set whenever the metric value becomes known.

These fields are required to set a custom metric value:

- Integer Index the index of the custom metric definition.
- Integer Value the value of the custom metric. Values may be negative.

Note: you may use a fixed decimal value instead of an integer for custom metrics configured as a Currency type.

Setting a Custom Metric Value

To set a custom metric value, call setCustomMetric before another send call:

```
// Get the tracker object.
Tracker tracker = EasyTracker.getTracker();

// Increment the metric at index 1.
tracker.setCustomMetric(1, 1);

// Metric value sent with this hit.
tracker.sendView();
```

Or to set a currency custom metric:

```
// Get the tracker.
Tracker tracker = EasyTracker.getTracker();

// Create a map for hit params.
HashMap params = new HashMap();
params.put(ModelFields.APP_SCREEN, "Product Page");

// Set currency value to custom metric slot 1.

// Currency values may be fixed decimal.
params.put("&cm1", "24.99");

// Send the custom metric value with a screen view.
tracker.send("appview", params);
```

Implementation Considerations

The following section outlines additional considerations to keep in mind when planning a custom dimension or metric implementation.

Custom Metric Values are Aggregated in Reports

Custom metric values are aggregated in reports just like other pre-defined metrics in Google Analytics. As a result, you would set a custom metric value of 1 to increment the metric's aggregate total in your reports.

Custom Metrics and Profile Filters

Although the custom metric values can generally be set whenever is convenient, avoid setting custom metric values on hits that are likely to be filtered from your profiles. If a hit is filtered by a profile filter, any associated custom metric values will also be filtered. Learn more about custom dimensions and metrics and profile filters.

Last updated May 10, 2013.



Google

Terms of Service

Privacy Policy

Jobs

Report a bug

English