App Widgets

App Widgets are miniature application views that can be embedded in other applications (such as the Home screen) and receive periodic updates. These views are referred to as Widgets in the user interface, and you can publish one with an App Widget provider. An application component that is able to hold other App Widgets is called an App Widget host. The screenshot below shows the Music App Widget.



This document describes how to publish an App Widget using an App Widget provider. For a discussion of creating your own AppWidgetHost

(/reference/android/appwidget/AppWidgetHost.html) to host app widgets, see App Widget Host (/guide/topics/appwidgets/host.html).

Widget Design

For information about how to design your app widget, read the <u>Widgets (/design/patterns/widgets.html)</u> design guide.

The Basics

To create an App Widget, you need the following:

<u>AppWidgetProviderInfo</u> object

Describes the metadata for an App Widget, such as the App Widget's layout, update frequency, and the AppWidgetProvider class. This should be defined in XML.

<u>AppWidgetProvider</u> class implementation

Defines the basic methods that allow you to programmatically interface with the App Widget, based on broadcast events. Through it, you will receive broadcasts when the App Widget is updated, enabled, disabled and deleted.

View layout

Defines the initial layout for the App Widget, defined in XML.

Additionally, you can implement an App Widget configuration Activity.

This is an optional <u>Activity (/reference/android/app/Activity.html)</u> that launches when the user adds your App Widget and allows him or her to modify App Widget settings at create-time.

The following sections describe how to set up each of these components.

Declaring an App Widget in the Manifest

First, declare the AppWidgetProvider (/reference/android/appwidget/AppWidgetProvider.html) class in your application's AndroidManifest.xml file. For example:

IN THIS DOCUMENT

The Basics

Declaring an App Widget in

the Manifest

Adding the

<u>AppWidgetProviderInfo</u>

Metadata

Creating the App Widget

Layout

Using the AppWidgetProvider

<u>Class</u>

Receiving App Widget broadcast Intents

<u>Creating an App Widget</u> <u>Configuration Activity</u>

> Updating the App Widget from the Configuration Activity

<u>Setting a Preview Image</u> <u>Enabling App Widgets on the</u>

Lockscreen

Sizing guidelines

<u>Using App Widgets with</u> Collections

> Sample application Implementing app widgets with collections Keeping Collection Data Fresh

KEY CLASSES

AppWidgetProvider
AppWidgetProviderInfo
AppWidgetManager

```
android:resource="@xml/example_appwidget_info" />
</receiver>
```

The < receiver > element requires the android: name attribute, which specifies the AppWidgetProvider (/reference/android/appwidget/AppWidgetProvider.html) used by the App Widget.

The <intent-filter> element must include an <action> element with the android:name attribute. This attribute specifies that the AppWidgetProvider (/reference/android/appwidget/AppWidgetProvider.html) accepts the ACTION APPWIDGET UPDATE

(/reference/android/appwidget/AppwidgetManager.html#ACTION_APPWIDGET_UPDATE) broadcast. This is the only broadcast that you must explicitly declare. The AppWidgetManager

(/reference/android/appwidget/AppwidgetManager.html) automatically sends all other App Widget broadcasts to the AppWidgetProvider as necessary.

- android: name Specifies the metadata name. Use android.appwidget.provider to identify the data as the <u>AppWidgetProviderInfo</u> descriptor.
- android:resource-Specifies the <u>AppWidgetProviderInfo</u> resource location.

Adding the AppWidgetProviderInfo Metadata

The <u>AppWidgetProviderInfo (/reference/android/appwidget/AppWidgetProviderInfo.html)</u> defines the essential qualities of an App Widget, such as its minimum layout dimensions, its initial layout resource, how often to update the App Widget, and (optionally) a configuration Activity to launch at create-time. Define the AppWidgetProviderInfo object in an XML resource using a single <appwidget-provider> element and save it in the project's res/xml/folder.

For example:

```
<appwidget-provider xmlns:android="http://schemas.android.com/apk/res/android"
    android:minWidth="40dp"
    android:minHeight="40dp"
    android:updatePeriodMillis="86400000"
    android:previewImage="@drawable/preview"
    android:initialLayout="@layout/example_appwidget"
    android:configure="com.example.android.ExampleAppWidgetConfigure"
    android:resizeMode="horizontal|vertical"
    android:widgetCategory="home_screen|keyguard"
    android:initialKeyguardLayout="@layout/example_keyguard">
</appwidget-provider>
```

Here's a summary of the <appwidget-provider> attributes:

• The values for the minWidth and minHeight attributes specify the minimum amount of space the App Widget consumes by default. The default Home screen positions App Widgets in its window based on a grid of cells that have a defined height and width. If the values for an App Widget's minimum width or height don't match the dimensions of the cells, then the App Widget dimensions round up to the nearest cell size.

See the <u>App Widget Design Guidelines (/quide/practices/ui_quidelines/widget_design.html#anatomy_determining_size)</u> for more information on sizing your App Widgets.

Note: To make your app widget portable across devices, your app widget's minimum size should never be larger than 4 x 4 cells.

• The minResizeWidth and minResizeHeight attributes specify the App Widget's absolute minimum size.

These values should specify the size below which the App Widget would be illegible or otherwise unusable.

Using these attributes allows the user to resize the widget to a size that may be smaller than the default widget

size defined by the minWidth and minHeight attributes. Introduced in Android 3.1.

See the <u>App Widget Design Guidelines (/guide/practices/ui_guidelines/widget_design.html#anatomy_determining_size)</u> for more information on sizing your App Widgets.

• The updatePeriodMillis attribute defines how often the App Widget framework should request an update from the AppWidgetProvider by calling the onUpdate() callback method. The actual update is not guaranteed to occur exactly on time with this value and we suggest updating as infrequently as possible—perhaps no more than once an hour to conserve the battery. You might also allow the user to adjust the frequency in a configuration—some people might want a stock ticker to update every 15 minutes, or maybe only four times a day.

Note: If the device is asleep when it is time for an update (as defined by updatePeriodMillis), then the device will wake up in order to perform the update. If you don't update more than once per hour, this probably won't cause significant problems for the battery life. If, however, you need to update more frequently and/or you do not need to update while the device is asleep, then you can instead perform updates based on an alarm that will not wake the device. To do so, set an alarm with an Intent that your AppWidgetProvider receives, using the AlarmManager.html). Set the alarm type to either ELAPSED_REALTIME (/reference/android/app/AlarmManager.html#ELAPSED_REALTIME)) or RTC (/reference/android/app/AlarmManager.html#RTC), which will only deliver the alarm when the device is awake. Then set updatePeriodMillis to zero ("0").

- The initialLayout attribute points to the layout resource that defines the App Widget layout.
- The configure attribute defines the <u>Activity</u> to launch when the user adds the App Widget, in order for him or her to configure App Widget properties. This is optional (read <u>Creating an App Widget Configuration Activity</u> below).
- The previewImage attribute specifies a preview of what the app widget will look like after it's configured, which the user sees when selecting the app widget. If not supplied, the user instead sees your application's launcher icon. This field corresponds to the android:previewImage attribute in the <receiver> element in the AndroidManifest.xml file. For more discussion of using previewImage, see Setting a Preview Image. Introduced in Android 3.0.
- The autoAdvanceViewId attribute specifies the view ID of the app widget subview that should be auto-advanced by the widget's host. Introduced in Android 3.0.
- The resizeMode attribute specifies the rules by which a widget can be resized. You use this attribute to make homescreen widgets resizeable—horizontally, vertically, or on both axes. Users touch-hold a widget to show its resize handles, then drag the horizontal and/or vertical handles to change the size on the layout grid. Values for the resizeMode attribute include "horizontal", "vertical", and "none". To declare a widget as resizeable horizontally and vertically, supply the value "horizontal|vertical". Introduced in Android 3.1.
- The minResizeHeight attribute specifies the minimum height (in dps) to which the widget can be resized. This field has no effect if it is greater than minHeight or if vertical resizing isn't enabled (see resizeMode). Introduced in Android 4.0.
- The minResizeWidth attribute specifies the minimum width (in dps) to which the widget can be resized. This field has no effect if it is greater than minWidth or if horizontal resizing isn't enabled (see resizeMode). Introduced in Android 4.0.
- The widgetCategory attribute declares whether your App Widget can be displayed on the home screen, the lock screen (keyguard), or both. Values for this attribute include "home_screen" and "keyguard". A widget that is displayed on both needs to ensure that it follows the design guidelines for both widget classes. For more information, see Enabling App Widgets on the Lockscreen. The default value is "home_screen". Introduced in Android 4.2.
- The initialKeyguardLayout attribute points to the layout resource that defines the lock screen App Widget
 layout. This works the same way as the android:initialLayout, in that it provides a layout that can appear
 immediately until your app widget is initialized and able to update the layout. Introduced in Android 4.2.

See the AppWidgetProviderInfo (/reference/android/appwidget/AppWidgetProviderInfo.html) class for more information on the attributes accepted by the <a pwidget-provider> element.

Creating the App Widget Layout

You must define an initial layout for your App Widget in XML and save it in the project's res/layout/ directory. You can design your App Widget using the View objects listed below, but before you begin designing your App

Widget, please read and understand the <u>App Widget Design Guidelines</u> (/quide/practices/ui_quidelines/widget_design.html).

Creating the App Widget layout is simple if you're familiar with <u>Layouts (/guide/topics/ui/declaring-layout.html)</u>. However, you must be aware that App Widget layouts are based on <u>RemoteViews</u> (/reference/android/widget/RemoteViews.html), which do not support every kind of layout or view widget.

A RemoteViews object (and, consequently, an App Widget) can support the following layout classes:

<u>FrameLayout</u>

LinearLayout

<u>RelativeLayout</u>

GridLayout

And the following widget classes:

AnalogClock

Button

Chronometer

<u>ImageButton</u>

ImageView

ProgressBar

<u>TextView</u>

ViewFlipper

<u>ListView</u>

GridView

StackView

<u>AdapterViewFlipper</u>

Descendants of these classes are not supported.

RemoteViews also supports <u>ViewStub (/reference/android/view/ViewStub.html)</u>, which is an invisible, zero-sized View you can use to lazily inflate layout resources at runtime.

Adding margins to App Widgets

Widgets should not generally extend to screen edges and should not visually be flush with other widgets, so you should add margins on all sides around your widget frame.

As of Android 4.0, app widgets are automatically given padding between the widget frame and the app widget's bounding box to provide better alignment with other widgets and icons on the user's home screen. To take advantage of this strongly recommended behavior, set your application's targetSdkVersion (/quide/topics/manifest/uses-sdk-element.html) to 14 or greater.

It's easy to write a single layout that has custom margins applied for earlier versions of the platform, and has no extra margins for Android 4.0 and greater:

- 1. Set your application's targetSdkVersion to 14 or greater.
- 2. Create a layout such as the one below, that references a <u>dimension resource</u> for its margins:

```
<FrameLayout
android:layout_width="match_parent"
android:layout_height="match_parent"
android:padding="@dimen/widget_margin">

<LinearLayout
    android:layout_width="match_parent"
    android:layout_height="match_parent"
    android:orientation="horizontal"
    android:background="@drawable/my_widget_background">
    ...
    </LinearLayout>
```

</FrameLayout>

3. Create two dimensions resources, one in res/values/ to provide the pre-Android 4.0 custom margins, and one in res/values-v14/ to provide no extra padding for Android 4.0 widgets:

res/values/dimens.xml:

```
<dimen name="widget_margin">8dp</dimen>
```

res/values-v14/dimens.xml:

```
<dimen name="widget_margin">0dp</dimen>
```

Another option is to simply build extra margins into your <u>nine-patch (/quide/topics/qraphics/2d-graphics.html#nine-patch)</u> background assets by default, and provide different nine-patches with no margins for API level 14 or later.

Using the AppWidgetProvider Class

The AppWidgetProvider

(/reference/android/appwidget/AppWidgetProvider.html) class extends BroadcastReceiver as a convenience class to handle the App Widget broadcasts. The AppWidgetProvider receives only the event broadcasts that are relevant to the App Widget, such as when the App Widget is updated, deleted, enabled, and disabled. When these broadcast events occur, the AppWidgetProvider receives the following method calls: You must declare your
AppWidgetProvider class
implementation as a broadcast receiver
using the <receiver> element in the
AndroidManifest (see <u>Declaring an App</u>
<u>Widget in the Manifest (#Manifest)</u> above).

onUpdate()

This is called to update the App Widget at intervals defined by the updatePeriodMillis attribute in the AppWidgetProviderInfo (see Adding the AppWidgetProviderInfo Metadata above). This method is also called when the user adds the App Widget, so it should perform the essential setup, such as define event handlers for Views and start a temporary Service, if necessary. However, if you have declared a configuration Activity, this method is not called when the user adds the App Widget, but is called for the subsequent updates. It is the responsibility of the configuration Activity to perform the first update when configuration is done. (See Creating an App Widget Configuration Activity below.)

onAppWidgetOptionsChanged()

This is called when the widget is first placed and any time the widget is resized. You can use this callback to show or hide content based on the widget's size ranges. You get the size ranges by calling getAppWidgetOptions(), which returns a Bundle that includes the following:

- OPTION_APPWIDGET_MIN_WIDTH—Contains the lower bound on the current width, in dp units, of a widget instance.
- OPTION_APPWIDGET_MIN_HEIGHT—Contains the lower bound on the current height, in dp units, of a widget instance.
- OPTION_APPWIDGET_MAX_WIDTH—Contains the upper bound on the current width, in dp units, of a widget instance.
- OPTION_APPWIDGET_MAX_HEIGHT—Contains the upper bound on the current width, in dp units, of a widget instance.

This callback was introduced in API Level 16 (Android 4.1). If you implement this callback, make sure that your app doesn't depend on it since it won't be called on older devices.

onDeleted(Context, int[])

This is called every time an App Widget is deleted from the App Widget host.

onEnabled(Context)

This is called when an instance the App Widget is created for the first time. For example, if the user adds two instances of your App Widget, this is only called the first time. If you need to open a new database or perform other setup that only needs to occur once for all App Widget instances, then this is a good place to do it.

onDisabled(Context)

This is called when the last instance of your App Widget is deleted from the App Widget host. This is where you should clean up any work done in onEnabled(Context), such as delete a temporary database.

onReceive(Context, Intent)

This is called for every broadcast and before each of the above callback methods. You normally don't need to implement this method because the default AppWidgetProvider implementation filters all App Widget broadcasts and calls the above methods as appropriate.

The most important AppWidgetProvider callback is onUpdate()

(/reference/android/appwidget/AppwidgetProvider.html#onUpdate(android.content.Context,

<u>android.appwidget.AppWidgetManager</u>, <u>int[])</u> because it is called when each App Widget is added to a host (unless you use a configuration Activity). If your App Widget accepts any user interaction events, then you need to register the event handlers in this callback. If your App Widget doesn't create temporary files or databases, or perform other work that requires clean-up, then <u>onUpdate()</u>

(/reference/android/appwidget/AppWidgetProvider.html#onUpdate(android.content.Context, android.appwidget.AppWidgetManager, int[])) may be the only callback method you need to define. For example, if you want an App Widget with a button that launches an Activity when clicked, you could use the following implementation of AppWidgetProvider:

```
public class ExampleAppWidgetProvider extends AppWidgetProvider {
    public void onUpdate(Context context, AppWidgetManager appWidgetManager, int[] app
        final int N = appWidgetIds.length;
        // Perform this loop procedure for each App Widget that belongs to this provide
        for (int i=0; i<N; i++) {</pre>
            int appWidgetId = appWidgetIds[i];
            // Create an Intent to launch ExampleActivity
            Intent intent = new Intent(context, ExampleActivity.class);
            PendingIntent pendingIntent = PendingIntent.getActivity(context, 0, intent
            // Get the layout for the App Widget and attach an on-click listener
            // to the button
            RemoteViews views = new RemoteViews(context.getPackageName(), R.layout.apg
            views.setOnClickPendingIntent(R.id.button, pendingIntent);
            // Tell the AppWidgetManager to perform an update on the current app widge
            appWidgetManager.updateAppWidget(appWidgetId, views);
        }
    }
}
```

This AppWidgetProvider defines only the onUpdate()

(/reference/android/appwidget/AppWidgetProvider.html#onUpdate(android.content.Context,
android.appwidget.AppWidgetManager, int[]) method for the purpose of defining a PendingIntent
(/reference/android/app/PendingIntent.html) that launches an Activity
(/reference/android/app/Activity.html) and attaching it to the App Widget's button with
setOnClickPendingIntent(int, PendingIntent)

android.app.PendingIntent)). Notice that it includes a loop that iterates through each entry in appWidgetIds, which is an array of IDs that identify each App Widget created by this provider. In this way, if the user creates more than one instance of the App Widget, then they are all updated simultaneously. However, only one updatePeriodMillis schedule will be managed for all instances of the App Widget. For example, if the update schedule is defined to be every two hours, and a second instance of the App Widget is added one hour after the first one, then they will both be updated on the period defined by the first one and the second update period will be ignored (they'll both be updated every two hours, not every hour).

Note: Because AppWidgetProvider (/reference/android/appwidget/AppWidgetProvider.html) is an extension of BroadcastReceiver (/reference/android/content/BroadcastReceiver.html), your process is not guaranteed to keep running after the callback methods return (see BroadcastReceiver (/reference/android/content/BroadcastReceiver.html) for information about the broadcast lifecycle). If your App Widget setup process can take several seconds (perhaps while performing web requests) and you require that your process continues, consider starting a Service (/reference/android/app/service.html) in the onUpdate()

 $\label{lem:content.content.content.} $$\frac{(\mbox{\sc interest} - \mbox{\sc interest} + \mbox{\sc interest} +$

 $\frac{and roid/source/browse/trunk/Wiktionary/src/com/example/and roid/wiktionary/WordWidget.\underline{iava})}{widget running a \underline{Service (/reference/and roid/app/Service.html)}}.$

Also see the ExampleAppWidgetProvider.java

(/resources/samples/ApiDemos/src/com/example/android/apis/appwidget/ExampleAppWidgetProvider.html) sample class.

Receiving App Widget broadcast Intents

AppWidgetProvider (/reference/android/appwidget/AppWidgetProvider.html) is just a convenience class. If you would like to receive the App Widget broadcasts directly, you can implement your own BroadcastReceiver (/reference/android/content/BroadcastReceiver.html) or override the ontent/BroadcastReceiver.html) or override the ontent/BroadcastReceiver.html) or override the ontent/Broadca

- ACTION APPWIDGET UPDATE
- ACTION APPWIDGET DELETED
- ACTION APPWIDGET ENABLED
- ACTION APPWIDGET DISABLED
- ACTION APPWIDGET OPTIONS CHANGED

Creating an App Widget Configuration Activity

If you would like the user to configure settings when he or she adds a new App Widget, you can create an App Widget configuration Activity. This Activity (/reference/android/app/Activity.html) will be automatically launched by the App Widget host and allows the user to configure available settings for the App Widget at create-time, such as the App Widget color, size, update period or other functionality settings.

The configuration Activity should be declared as a normal Activity in the Android manifest file. However, it will be launched by the App Widget host with the <u>ACTION_APPWIDGET_CONFIGURE</u>

(/reference/android/appwidget/AppwidgetManager.html#ACTION_APPWIDGET_CONFIGURE) action, so the Activity
needs to accept this Intent. For example:

Also, the Activity must be declared in the AppWidgetProviderInfo XML file, with the android:configure attribute (see <u>Adding the AppWidgetProviderInfo Metadata (#MetaData)</u> above). For example, the configuration Activity can be declared like this:

```
<appwidget-provider xmlns:android="http://schemas.android.com/apk/res/android"
...
android:configure="com.example.android.ExampleAppWidgetConfigure"</pre>
```

```
... >
</appwidget-provider>
```

Notice that the Activity is declared with a fully-qualified namespace, because it will be referenced from outside your package scope.

That's all you need to get started with a configuration Activity. Now all you need is the actual Activity. There are, however, two important things to remember when you implement the Activity:

- The App Widget host calls the configuration Activity and the configuration Activity should always return a result. The result should include the App Widget ID passed by the Intent that launched the Activity (saved in the Intent extras as EXTRA APPWIDGET ID).
- The onUpdate() method will not be called when the App Widget is created (the system will not send the ACTION_APPWIDGET_UPDATE broadcast when a configuration Activity is launched). It is the responsibility of the configuration Activity to request an update from the AppWidgetManager when the App Widget is first created. However, onUpdate() will be called for subsequent updates—it is only skipped the first time.

See the code snippets in the following section for an example of how to return a result from the configuration and update the App Widget.

Updating the App Widget from the configuration Activity

When an App Widget uses a configuration Activity, it is the responsibility of the Activity to update the App Widget when configuration is complete. You can do so by requesting an update directly from the AppWidgetManager (/reference/android/appwidget/AppWidgetManager.html).

Here's a summary of the procedure to properly update the App Widget and close the configuration Activity:

1. First, get the App Widget ID from the Intent that launched the Activity:

- 2. Perform your App Widget configuration.
- 3. When the configuration is complete, get an instance of the AppWidgetManager by calling getInstance(Context):

```
AppWidgetManager appWidgetManager = AppWidgetManager.getInstance(context);
```

4. Update the App Widget with a RemoteViews layout by calling updateAppWidget(int, RemoteViews):

```
RemoteViews views = new RemoteViews(context.getPackageName(),
R.layout.example_appwidget);
appWidgetManager.updateAppWidget(mAppWidgetId, views);
```

5. Finally, create the return Intent, set it with the Activity result, and finish the Activity:

```
Intent resultValue = new Intent();
resultValue.putExtra(AppWidgetManager.EXTRA_APPWIDGET_ID, mappWidgetId);
setResult(RESULT_OK, resultValue);
finish();
```

Tip: When your configuration Activity first opens, set the Activity result to RESULT_CANCELED. This way, if the user backs-out of the Activity before reaching the end, the App Widget host is notified that the configuration was cancelled and the App Widget will not be added.

See the ExampleAppWidgetConfigure.java

(/resources/samples/ApiDemos/src/com/example/android/apis/appwidget/ExampleAppWidgetConfigure.html) sample class in ApiDemos for an example.

Setting a Preview Image

Android 3.0 introduces the previewImage

<u>(/reference/android/appwidget/AppwidgetProviderInfo.html#previewImage)</u> field, which specifies a preview of what the app widget looks like. This preview is shown to the user from the widget picker. If this field is not supplied, the app widget's icon is used for the preview.

This is how you specify this setting in XML:

```
<appwidget-provider xmlns:android="http://schemas.android.com/apk/res/android"
...
android:previewImage="@drawable/preview">
</appwidget-provider>
```

To help create a preview image for your app widget (to specify in the previewImage

(/reference/android/appwidget/AppWidgetProviderInfo.html#previewImage) field), the Android emulator includes an application called "Widget Preview." To create a preview image, launch this application, select the app widget for your application and set it up how you'd like your preview image to appear, then save it and place it in your application's drawable resources.

Enabling App Widgets on the Lockscreen

Android 4.2 introduces the ability for users to add widgets to the lock screen. To indicate that your app widget is available for use on the lock screen, declare the android:widgetCategory

<u>(/reference/android/appwidget/AppWidgetProviderInfo.html#widgetCategory)</u> attribute in the XML file that specifies your <u>AppWidgetProviderInfo (/reference/android/appwidget/AppWidgetProviderInfo.html)</u>. This attribute supports two values: "home_screen" and "keyguard". An app widget can declare support for one or both.

By default, every app widget supports placement on the Home screen, so "home_screen" is the default value for the android:widgetCategory

(/reference/android/appwidqet/AppWidqetProviderInfo.html#widgetCategory) attribute. If you want your app widget to be available for the lock screen, add the "keyguard" value:

```
<appwidget-provider xmlns:android="http://schemas.android.com/apk/res/android"
...
android:widgetCategory="keyguard|home_screen">
</appwidget-provider>
```

If you declare a widget to be displayable on both keyguard (lockscreen) and home, it's likely that you'll want to customize the widget depending on where it is displayed. For example, you might create a separate layout file for keyguard vs. home. The next step is to detect the widget category at runtime and respond accordingly. You can detect whether your widget is on the lockscreen or home screen by calling qetAppWidgetOptions() (/reference/android/appwidget/AppWidgetManager.html#getAppWidgetOptions(int)) to get the widget's options as a Bundle.(/reference/android/os/Bundle.html). The returned bundle will include the key OPTION APPWIDGET HOST CATEGORY

(/reference/android/appwidget/AppWidgetManager.html#OPTION_APPWIDGET_HOST_CATEGORY), whose value will be one of WIDGET_CATEGORY_HOME_SCREEN

(/reference/android/appwidget/AppWidgetProviderInfo.html#WIDGET_CATEGORY_HOME_SCREEN) Or WIDGET_CATEGORY_KEYGUARD

(/reference/android/appwidqet/AppwidqetProviderInfo.html#WIDGET CATEGORY KEYGUARD). This value is

determined by the host into which the widget is bound. In the <u>AppWidgetProvider</u> (/reference/android/appwidget/AppWidgetProvider.html), you can then check the widget's category, for example:

```
AppWidgetManager appWidgetManager;
int widgetId;
Bundle myOptions = appWidgetManager.getAppWidgetOptions (widgetId);

// Get the value of OPTION_APPWIDGET_HOST_CATEGORY
int category = myOptions.getInt(AppWidgetManager.OPTION_APPWIDGET_HOST_CATEGORY, -1);

// If the value is WIDGET_CATEGORY_KEYGUARD, it's a lockscreen widget
boolean isKeyguard = category == AppWidgetProviderInfo.WIDGET_CATEGORY_KEYGUARD;
```

Once you know the widget's category, you can optionally load a different base layout, set different properties, and so on. For example:

```
int baseLayout = isKeyguard ? R.layout.keyguard_widget_layout : R.layout.widget_layout
```

You should also specify an initial layout for your app widget when on the lock screen with the android:initialKeyguardLayout

(/reference/android/appwidget/AppWidgetProviderInfo.html#initialLayout), in that it provides a layout that can appear immediately until your app widget is initialized and able to update the layout.

Sizing guidelines

When a widget is hosted on the lockscreen, the framework ignores the minWidth, minHeight, minResizeWidth, and minResizeHeight fields. If a widget is also a home screen widget, these parameters are still needed as they're still used on home, but they will be ignored for purposes of the lockscreen.

The width of a lockscreen widget always fills the provided space. For the height of a lockscreen widget, you have the following options:

- If the widget does not mark itself as vertically resizable (android:resizeMode="vertical"), then the widget height will always be "small":
- o On a phone in portrait mode, "small" is defined as the space remaining when an unlock UI is being displayed.
- o On tablets and landscape phones, "small" is set on a per-device basis.
- If the widget marks itself as vertically resizable, then the widget height shows up as "small" on portrait phones displaying an unlock UI. In all other cases, the widget sizes to fill the available height.

Using App Widgets with Collections

Android 3.0 introduces app widgets with collections. These kinds of App Widgets use the RemoteViewsService (/reference/android/widget/RemoteViewsService.html) to display collections that are backed by remote data, such as from a content provider (/quide/topics/providers/content-providers.html). The data provided by the RemoteViewsService (/reference/android/widget/RemoteViewsService.html) is presented in the app widget using one of the following view types, which we'll refer to as "collection views:"

<u>ListView</u>

A view that shows items in a vertically scrolling list. For an example, see the Gmail app widget.

<u>GridView</u>

A view that shows items in two-dimensional scrolling grid. For an example, see the Bookmarks app widget.

StackView

A stacked card view (kind of like a rolodex), where the user can flick the front card up/down to see the previous/next card, respectively. Examples include the YouTube and Books app widgets.

AdapterViewFlipper

An adapter-backed simple <u>ViewAnimator</u> that animates between two or more views. Only one child is shown at a time.

As stated above, these collection views display collections backed by remote data. This means that they use an Adapter (/reference/android/widget/Adapter.html) to bind their user interface to their data. An Adapter (/reference/android/widget/Adapter.html) binds individual items from a set of data into individual View (/reference/android/widget/Adapter.html) binds individual items from a set of data into individual View (/reference/android/view (/reference/android/view.html) objects. Because these collection views are backed by adapters, the Android framework must include extra architecture to support their use in app widgets. In the context of an app widget, the Adapter (/reference/android/widget/Adapter.html) is replaced by a RemoteViewsFactory (/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html), which is simply a thin wrapper around the Adapter (/reference/android/widget/Adapter.html) interface. When requested for a specific item in the collection, the RemoteViewsFactory

(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html) creates and returns the item for the collection as a RemoteViews (/reference/android/widget/RemoteViews.html) object. In order to include a collection view in your app widget, you must implement RemoteViewsService

(/reference/android/widget/RemoteViewsService.html) and RemoteViewsFactory

 $\underline{(/\texttt{reference/android/widget/RemoteViewsService.RemoteViewsFactory.html)}.$

RemoteViewsService (/reference/android/widget/RemoteViewsService.html) is a service that allows a remote adapter to request RemoteViews (/reference/android/widget/RemoteViews.html) objects.

RemoteViewsFactory (/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html) is an interface for an adapter between a collection view (such as ListView

(/reference/android/widget/ListView.html), GridView (/reference/android/widget/GridView.html), and so on) and the underlying data for that view. From the StackView Widget sample (/resources/samples/StackWidget/index.html), here is an example of the boilerplate code you use to implement this

(/resources/samples/StackWidget/index.html), here is an example of the boilerplate code you use to implement this service and interface:

```
public class StackWidgetService extends RemoteViewsService {
    @Override
    public RemoteViewsFactory onGetViewFactory(Intent intent) {
        return new StackRemoteViewsFactory(this.getApplicationContext(), intent);
    }
}
class StackRemoteViewsFactory implements RemoteViewsService.RemoteViewsFactory {
    //... include adapter-like methods here. See the StackView Widget sample.
}
```

Sample application

The code excerpts in this section are drawn from the <u>StackView Widget sample</u> (/resources/samples/StackWidget/index.html):



This sample consists of a stack of 10 views, which display the values "0!" through "9!" The sample app

widget has these primary behaviors:

- The user can vertically fling the top view in the app widget to display the next or previous view. This is a built-in StackView behavior.
- Without any user interaction, the app widget automatically advances through its views in sequence, like a slide show. This is due to the setting android:autoAdvanceViewId="@id/stack_view" in the res/xml/stackwidgetinfo.xml file. This setting applies to the view ID, which in this case is the view ID of the stack view.
- If the user touches the top view, the app widget displays the <u>Toast</u> message "Touched view *n*," where *n* is the index (position) of the touched view. For more discussion of how this is implemented, see <u>Adding behavior to</u> individual items.

Implementing app widgets with collections

To implement an app widget with collections, you follow the same basic steps you would use to implement any app widget. The following sections describe the additional steps you need to perform to implement an app widget with collections.

Manifest for app widgets with collections

In addition to the requirements listed in <u>Declaring an app widget in the Manifest (#Manifest)</u>, to make it possible for app widgets with collections to bind to your <u>RemoteViewsService</u>

(/reference/android/widget/RemoteViewsService.html), you must declare the service in your manifest file with the permission BIND_REMOTEVIEWS (/reference/android/Manifest.permission.html#BIND_REMOTEVIEWS). This prevents other applications from freely accessing your app widget's data. For example, when creating an App Widget that uses RemoteViewsService (/reference/android/widget/RemoteViewsService.html) to populate a collection view, the manifest entry may look like this:

```
<service android:name="MyWidgetService"
...
android:permission="android.permission.BIND_REMOTEVIEWS" />
```

The line android: name="MyWidgetService" refers to your subclass of <u>RemoteViewsService</u> (/reference/android/widget/RemoteViewsService.html).

Layout for app widgets with collections

The main requirement for your app widget layout XML file is that it include one of the collection views: <u>ListView (/reference/android/widget/ListView.html)</u>, <u>GridView</u>

(/reference/android/widget/GridView.html), StackView (/reference/android/widget/StackView.html), Or AdapterViewFlipper (/reference/android/widget/AdapterViewFlipper.html). Here is the widget layout.xml for the StackView Widget sample (/resources/samples/StackWidget/index.html):

```
android:background="@drawable/widget_item_background"
android:textColor="#ffffff"
android:textStyle="bold"
android:text="@string/empty_view_text"
android:textSize="20sp" />
</FrameLayout>
```

Note that empty views must be siblings of the collection view for which the empty view represents empty state.

In addition to the layout file for your entire app widget, you must create another layout file that defines the layout for each item in the collection (for example, a layout for each book in a collection of books). For example, the StackView Widget sample (/resources/samples/StackWidget/index.html) only has one layout file, widget_item.xml, since all items use the same layout. But the WeatherListWidget/index.html) has two layout files: dark_widget_item.xml and light_widget_item.xml.

AppWidgetProvider class for app widgets with collections

As with a regular app widget, the bulk of your code in your AppWidgetProvider (/reference/android/appwidget/AppWidgetProvider.html) subclass typically goes in onUpdate() (/reference/android/appwidget/AppWidgetProvider.html#onUpdate(android.content.Context, android.appwidget.AppWidgetManager, int[])). The major difference in your implementation for onUpdate() (/reference/android/appwidget/AppWidgetProvider.html#onUpdate(android.content.Context, android.appwidget.AppWidgetManager, int[])) when creating an app widget with collections is that you must call setRemoteAdapter() (/reference/android/widget/RemoteViews.html#setRemoteAdapter(int, android.content.Intent)). This tells the collection view where to get its data. The RemoteViewsService (/reference/android/widget/RemoteViewsService.html) can then return your implementation of RemoteViewsFactory (/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html), and the widget can serve up the appropriate data. When you call this method, you must pass an intent that points to your implementation of RemoteViewsService (/reference/android/widget/RemoteViewsService.html) and the app widget ID that specifies the app widget to update.

For example, here's how the StackView Widget sample implements the onUpdate(")
onUpdate(android.content.Context
android.appwidget.AppWidgetManager, int[]) callback method to set the RemoteViewsService
note:("/reference/android/widget/RemoteViewsService.html">note:("/reference/android/widget/RemoteViewsService.html">note:("/reference/android/widget/RemoteViewsService.html">note:("/reference/android/widget/RemoteViewsService.html) as the remote adapter for the app widget collection:

```
public void onUpdate(Context context, AppWidgetManager appWidgetManager,
int[] appWidgetIds) {
    // update each of the app widgets with the remote adapter
    for (int i = 0; i < appWidgetIds.length; ++i) {</pre>
        // Set up the intent that starts the StackViewService, which will
        // provide the views for this collection.
        Intent intent = new Intent(context, StackWidgetService.class);
        // Add the app widget ID to the intent extras.
        intent.putExtra(AppWidgetManager.EXTRA APPWIDGET ID, appWidgetIds[i]);
        intent.setData(Uri.parse(intent.toUri(Intent.URI INTENT SCHEME)));
        // Instantiate the RemoteViews object for the app widget layout.
        RemoteViews rv = new RemoteViews(context.getPackageName(), R.layout.widget_lay
        // Set up the RemoteViews object to use a RemoteViews adapter.
        // This adapter connects
        // to a RemoteViewsService through the specified intent.
        // This is how you populate the data.
        rv.setRemoteAdapter(appWidgetIds[i], R.id.stack view, intent);
        // The empty view is displayed when the collection has no items.
        // It should be in the same layout used to instantiate the RemoteViews
        // object above.
```

```
rv.setEmptyView(R.id.stack_view, R.id.empty_view);

//

// Do additional processing specific to this app widget...

//

appWidgetManager.updateAppWidget(appWidgetIds[i], rv);
}
super.onUpdate(context, appWidgetManager, appWidgetIds);
}
```

RemoteViewsService class

As described above, your <u>RemoteViewsService</u>
remoteViewsService.html) subclass provides the <u>RemoteViewsFactory</u>

Persisting data

You can't rely on a single instance of your service, or any data it contains, to persist. You should therefore not store any data in your

<u>RemoteViewsService</u>

(/reference/android/widget/RemoteView sservice.html) (unless it is static). If you want your app widget's data to persist, the best approach is to use a ContentProvider

(/reference/android/content/ContentPr ovider.html) whose data persists beyond the process lifecycle.

(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html) used to populate the remote collection view.

Specifically, you need to perform these steps:

- 1. Subclass <u>RemoteViewsService</u>. <u>RemoteViewsService</u> is the service through which a remote adapter can request <u>RemoteViews</u>.
- 2. In your RemoteViewsService subclass, include a class that implements the RemoteViewsFactory interface. RemoteViewsFactory is an interface for an adapter between a remote collection view (such as ListView, GridView, and so on) and the underlying data for that view. Your implementation is responsible for making a RemoteViews object for each item in the data set. This interface is a thin wrapper around Adapter.

The primary contents of the <u>RemoteViewsService (/reference/android/widget/RemoteViewsService.html)</u> implementation is its <u>RemoteViewsFactory</u>

(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html), described below.

RemoteViewsFactory interface

Your custom class that implements the RemoteViewsFactory

<u>(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html)</u> interface provides the app widget with the data for the items in its collection. To do this, it combines your app widget item XML layout file with a source of data. This source of data could be anything from a database to a simple array. In the <u>StackView Widget sample (/resources/samples/StackWidget/index.html)</u>, the data source is an array of WidgetItems. The <u>RemoteViewsFactory (/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html)</u> functions as an adapter to glue the data to the remote collection view.

The two most important methods you need to implement for your <u>RemoteViewsFactory</u>

(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html) Subclass are <u>onCreate()</u>

(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html#onCreate()) and <u>getViewAt()</u>

(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html#getViewAt(int)).

The system calls onCreate()

(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html#onCreate())
when creating your factory for the first time. This is where you set up any connections and/or cursors to your data source. For example, the StackView Widget sample (/resources/samples/StackWidget/index.html) uses onCreate()
(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html#onCreate()) to initialize an array of WidgetItem objects. When your app widget is active, the system accesses these objects using their index position in the array and the text they contain is displayed

Here is an excerpt from the <u>StackView Widget (/resources/samples/StackWidget/index.html)</u> sample's <u>RemoteViewsFactory (/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html)</u> implementation that shows portions of the <u>onCreate()</u>

(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html#onCreate()) method:

```
class StackRemoteViewsFactory implements
RemoteViewsService.RemoteViewsFactory {
   private static final int mCount = 10;
   private List<WidgetItem> mWidgetItems = new ArrayList<WidgetItem>();
   private Context mContext;
   private int mAppWidgetId;
   public StackRemoteViewsFactory(Context context, Intent intent) {
        mContext = context;
        mAppWidgetId = intent.getIntExtra(AppWidgetManager.EXTRA APPWIDGET ID,
                AppWidgetManager.INVALID APPWIDGET ID);
   }
   public void onCreate() {
        // In onCreate() you setup any connections / cursors to your data source. Heavy
        // for example downloading or creating content etc, should be deferred to onDat
        // or getViewAt(). Taking more than 20 seconds in this call will result in an A
        for (int i = 0; i < mCount; i++) {</pre>
           mWidgetItems.add(new WidgetItem(i + "!"));
        }
        . . .
    }
```

 $\label{lem:lemoteviewsFactory} The $$ $$ $$ $$ $$ $$ RemoteViewsFactory.html)$ $$ method $$ $ $ getViewAt()$ $$$

(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html#getViewAt(int)) returns a
RemoteViews (/reference/android/widget/RemoteViews.html) object corresponding to the data at the
specified position in the data set. Here is an excerpt from the StackView Widget
(http://developer.android.com/resources/samples/StackWidget/index.html) sample's RemoteViewsFactory
(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html) implementation:

```
public RemoteViews getViewAt(int position) {

    // Construct a remote views item based on the app widget item XML file,
    // and set the text based on the position.
    RemoteViews rv = new RemoteViews(mContext.getPackageName(), R.layout.widget_item);
    rv.setTextViewText(R.id.widget_item, mWidgetItems.get(position).text);

...
    // Return the remote views object.
    return rv;
}
```

The above sections show you how to bind your data to your app widget collection. But what if you want to add dynamic behavior to the individual items in your collection view?

As described in <u>Using the AppWidgetProvider Class (#AppWidgetProvider)</u>, you normally use <u>setOnClickPendingIntent()</u>

 $\frac{(/\text{reference/android/widget/RemoteViews.html\#setOnClickPendingIntent(int, android.app.PendingIntent))}{\text{to set an object's click behavior}-\text{such as to cause a button to launch an } \underline{\text{Activity}}$

(/reference/android/app/Activity.html). But this approach is not allowed for child views in an individual collection item (to clarify, you could use setOnClickPendingIntent()

(/reference/android/widget/RemoteViews.html#setOnClickPendingIntent(int, android.app.PendingIntent))
to set up a global button in the Gmail app widget that launches the app, for example, but not on the individual
list items). Instead, to add click behavior to individual items in a collection, you use
setOnClickFillInIntent() (/reference/android/widget/RemoteViews.html#setOnClickFillInIntent(int,
android.content.Intent)). This entails setting up up a pending intent template for your collection view, and
then setting a fill-in intent on each item in the collection via your RemoteViewsFactory

This section uses the <u>StackView Widget sample (/resources/samples/StackWidget/index.html)</u> to describe how to add behavior to individual items. In the <u>StackView Widget sample (/resources/samples/StackWidget/index.html)</u>, if the user touches the top view, the app widget displays the <u>Toast (/reference/android/widget/Toast.html)</u> message "Touched view n," where n is the index (position) of the touched view. This is how it works:

- The StackWidgetProvider (an <u>AppWidgetProvider</u> subclass) creates a pending intent that has a custom action called TOAST ACTION.
- When the user touches a view, the intent is fired and it broadcasts TOAST ACTION.

(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html).

 This broadcast is intercepted by the StackWidgetProvider's <u>onReceive()</u> method, and the app widget displays the <u>Toast</u> message for the touched view. The data for the collection items is provided by the <u>RemoteViewsFactory</u>, via the <u>RemoteViewsService</u>.

Note: The <u>StackView Widget sample (/resources/samples/StackWidget/index.html)</u> uses a broadcast, but typically an app widget would simply launch an activity in a scenario like this one.

Setting up the pending intent template

The StackWidgetProvider (AppWidgetProvider (/reference/android/appwidget/AppWidgetProvider.html) subclass) sets up a pending intent. Individuals items of a collection cannot set up their own pending intents. Instead, the collection as a whole sets up a pending intent template, and the individual items set a fill-in intent to create unique behavior on an item-by-item basis.

This class also receives the broadcast that is sent when the user touches a view. It processes this event in its onReceive()

(/reference/android/appwidget/AppWidgetProvider.html#onReceive(android.content.Context,
android.content.Intent)) method. If the intent's action is TOAST_ACTION, the app widget displays a Toast
(/reference/android/widget/Toast.html) message for the current view.

```
int viewIndex = intent.getIntExtra(EXTRA_ITEM, 0);
        Toast.makeText(context, "Touched view " + viewIndex, Toast.LENGTH SHORT).sho
   super.onReceive(context, intent);
}
@Override
public void onUpdate(Context context, AppWidgetManager appWidgetManager, int[] appWi
    // update each of the app widgets with the remote adapter
    for (int i = 0; i < appWidgetIds.length; ++i) {</pre>
        // Sets up the intent that points to the StackViewService that will
        // provide the views for this collection.
        Intent intent = new Intent(context, StackWidgetService.class);
        intent.putExtra(AppWidgetManager.EXTRA APPWIDGET ID, appWidgetIds[i]);
        // When intents are compared, the extras are ignored, so we need to embed the
        // into the data so that the extras will not be ignored.
        intent.setData(Uri.parse(intent.toUri(Intent.URI_INTENT_SCHEME)));
        RemoteViews rv = new RemoteViews(context.getPackageName(), R.layout.widget_1
        rv.setRemoteAdapter(appWidgetIds[i], R.id.stack_view, intent);
        // The empty view is displayed when the collection has no items. It should be
        // of the collection view.
        rv.setEmptyView(R.id.stack view, R.id.empty view);
        // This section makes it possible for items to have individualized behavior.
        // It does this by setting up a pending intent template. Individuals items
        // cannot set up their own pending intents. Instead, the collection as a who
        // up a pending intent template, and the individual items set a fillInIntent
        // to create unique behavior on an item-by-item basis.
        Intent toastIntent = new Intent(context, StackWidgetProvider.class);
        // Set the action for the intent.
        // When the user touches a particular view, it will have the effect of
        // broadcasting TOAST_ACTION.
        toastIntent.setAction(StackWidgetProvider.TOAST_ACTION);
        toastIntent.putExtra(AppWidgetManager.EXTRA APPWIDGET ID, appWidgetIds[i]);
        intent.setData(Uri.parse(intent.toUri(Intent.URI INTENT SCHEME)));
        PendingIntent toastPendingIntent = PendingIntent.getBroadcast(context, 0, to
            PendingIntent.FLAG UPDATE CURRENT);
        rv.setPendingIntentTemplate(R.id.stack view, toastPendingIntent);
        appWidgetManager.updateAppWidget(appWidgetIds[i], rv);
super.onUpdate(context, appWidgetManager, appWidgetIds);
```

Setting the fill-in Intent

Your RemoteViewsFactory (/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html) must set a fill-in intent on each item in the collection. This makes it possible to distinguish the individual onclick action of a given item. The fill-in intent is then combined with the PendingIntent (/reference/android/app/PendingIntent.html) template in order to determine the final intent that will be executed when the item is clicked.


```
public class StackWidgetService extends RemoteViewsService {
   @Override
   public RemoteViewsFactory onGetViewFactory(Intent intent) {
      return new StackRemoteViewsFactory(this.getApplicationContext(), intent);
}
```

```
}
class StackRemoteViewsFactory implements RemoteViewsService.RemoteViewsFactory {
    private static final int mCount = 10;
    private List<WidgetItem> mWidgetItems = new ArrayList<WidgetItem>();
    private Context mContext;
    private int mAppWidgetId;
    public StackRemoteViewsFactory(Context context, Intent intent) {
        mContext = context;
        mAppWidgetId = intent.getIntExtra(AppWidgetManager.EXTRA_APPWIDGET_ID,
                AppWidgetManager.INVALID_APPWIDGET_ID);
    }
    // Initialize the data set.
        public void onCreate() {
            // In onCreate() you set up any connections / cursors to your data source.
            // for example downloading or creating content etc, should be deferred to
            // or getViewAt(). Taking more than 20 seconds in this call will result in
            for (int i = 0; i < mCount; i++) {</pre>
                mWidgetItems.add(new WidgetItem(i + "!"));
            }
        }
        // Given the position (index) of a WidgetItem in the array, use the item's ter
        // combination with the app widget item XML file to construct a RemoteViews of
        public RemoteViews getViewAt(int position) {
            // position will always range from 0 to getCount() - 1.
            // Construct a RemoteViews item based on the app widget item XML file, and
            // text based on the position.
            RemoteViews rv = new RemoteViews (mContext.getPackageName(), R.layout.widge
            rv.setTextViewText(R.id.widget_item, mWidgetItems.get(position).text);
            // Next, set a fill-intent, which will be used to fill in the pending inte
            // that is set on the collection view in StackWidgetProvider.
            Bundle extras = new Bundle();
            extras.putInt(StackWidgetProvider.EXTRA ITEM, position);
            Intent fillInIntent = new Intent();
            fillInIntent.putExtras(extras);
            // Make it possible to distinguish the individual on-click
            // action of a given item
            rv.setOnClickFillInIntent(R.id.widget item, fillInIntent);
            . . .
            // Return the RemoteViews object.
            return rv:
        }
    }
```

Keeping Collection Data Fresh

The following figure illustrates the flow that occurs in an app widget that uses collections when updates occur. It shows how the app widget code interacts with the RemoteViewsFactory

(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html), and how you can trigger
updates:



One feature of app widgets that use collections is the ability to provide users with up-to-date content. For example, consider the Android 3.0 Gmail app widget, which provides users with a snapshot of their inbox. To make this possible, you need to be able to trigger your RemoteViewsFactory

(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html) and collection view to fetch and display new data. You achieve this with the AppWidgetManager

(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html#onDataSetChanged()) callback. You are guaranteed that this call will be completed before the metadata or view data is fetched from the RemoteViewsFactory (/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html). In addition, you can perform processing-intensive operations within the getViewAt()

(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html#qetViewAt(int)) method. If this
call takes a long time, the loading view (specified by the RemoteViewsFactory's getLoadingView()
(/reference/android/widget/RemoteViewsService.RemoteViewsFactory.html#getLoadingView()) method) will
be displayed in the corresponding position of the collection view until it returns.