# Operating Systems CSCI 3150

# Lecture 6: Synchronization (II) -- Condition Variables

Hong Xu

https://github.com/henryhxu/CSCI3150

## **Condition Variables**

- There are many cases where a thread wishes to <u>check</u> whether a condition is true before continuing its execution.
- Example:
  - A parent thread might wish to check whether a child thread has completed.
  - This is often called a join().

## **Condition Variables**

### A Parent Waiting For Its Child

```
1
        void *child(void *arg) {
            printf("child\n");
3
             // XXX how to indicate we are done?
            return NULL;
        int main(int argc, char *argv[]) {
8
             printf("parent: begin\n");
9
            pthread t c;
10
             Pthread create (&c, NULL, child, NULL); // create child
             // XXX how to wait for child?
11
12
            printf("parent: end\n");
13
            return 0;
14
```

#### What we would like to see here is:

```
parent: begin
  child
  parent: end
```

## Parent waiting for child: Spin-based Approach

```
1
        volatile int done = 0;
        void *child(void *arg) {
4
             printf("child\n");
5
             done = 1;
6
            return NULL;
7
8
9
         int main(int argc, char *argv[]) {
             printf("parent: begin\n");
10
11
             pthread t c;
12
             Pthread create (&c, NULL, child, NULL); // create child
13
             while (done == 0)
14
                 ; // spin
15
             printf("parent: end\n");
16
            return 0;
17
```

This is hugely <u>inefficient</u> as the parent spins and wastes CPU time.

## How to wait for a condition

- Condition variable
  - Queue of threads
  - Waiting on the condition
    - An explicit queue that threads can put themselves on when some state of execution is not as desired.
  - Signaling on the condition
    - Some other thread, when it changes it state, can wake one of those waiting threads and allow them to continue.
- Three in a package
  - condition variable c
  - state variable m
  - lock L; // to protect state variable

## **Definition and Routines**

Declare condition variable

```
pthread cond t c;
```

Proper initialization is required.

Operation (the POSIX calls)

- The wait() call takes a <u>mutex</u> as a parameter.
  - The wait() call release the lock and put the calling thread to sleep.
  - When the thread wakes up, it must re-acquire the lock.

## Parent waiting for Child: Use a condition variable

```
1
         int done = 0;
2
         pthread mutex t m = PTHREAD MUTEX INITIALIZER;
3
         pthread cond t c = PTHREAD COND INITIALIZER;
4
5
         void thr exit() {
6
                  Pthread mutex lock(&m);
                  done = 1;
8
                  Pthread cond signal (&c);
9
                  Pthread mutex unlock(&m);
10
11
12
         void *child(void *arg) {
13
                  printf("child\n");
14
                  thr exit();
15
                  return NULL;
16
17
18
         void thr join() {
19
                  Pthread mutex lock(&m);
                  while (done == 0)
20
21
                           Pthread cond wait(&c, &m);
22
                  Pthread mutex unlock(&m);
23
24
```

## Parent waiting for Child: Use a condition variable

```
(cont.)
25
         int main(int argc, char *argv[]) {
26
                 printf("parent: begin\n");
27
                 pthread t p;
28
                 Pthread create(&p, NULL, child, NULL);
29
                 thr join();
30
                 printf("parent: end\n");
31
                 return 0;
32
```

## Parent waiting for Child: Use a condition variable

#### Parent:

- Creates the child thread and continues running itself.
- Calls into thr join() to wait for the child thread to complete.
  - Acquires the lock.
  - Checks if the child is done.
  - Puts itself to sleep by calling wait().
  - Releases the lock.

#### Child:

- Prints the message "child".
- Calls thr exit() to wake up the parent thread.
  - Grabs the lock.
  - Sets the state variable done.
  - Signals the parent thus waking it.

## The importance of the state variable done

```
1     void thr_exit() {
2         Pthread_mutex_lock(&m);
3         Pthread_cond_signal(&c);
4         Pthread_mutex_unlock(&m);
5     }
6
7     void thr_join() {
8         Pthread_mutex_lock(&m);
9         Pthread_cond_wait(&c, &m);
10         Pthread_mutex_unlock(&m);
11     }
```

thr\_exit() and thr\_join() without variable done

- Imagine the case where the *child runs immediately*.
  - The child will signal, but there is no thread asleep on the condition.
  - When the parent runs, it will call wait and be stuck.
  - No thread will ever wake it.

## Another poor implementation

- The issue here is a subtle race condition.
  - The parent calls thr\_join().
    - The parent checks the value of done.
    - It will see that it is 0 and try to go to sleep.
    - Just before it calls wait to go to sleep, the parent is interrupted and the child runs.
  - The child changes the state variable done to 1 and signals.
    - But no thread is waiting and thus no thread is woken.
    - When the parent runs again, it sleeps forever.

# The Producer / Consumer (Bound Buffer) Problem

### Producer

- Produce data items
- Wish to place data items in a buffer

#### Consumer

Grab data items out of the buffer consume them in some way

- Example: Multi-threaded web server
  - A producer puts HTTP requests in to a work queue
  - Consumer threads take requests out of this queue and process them

## Bounded buffer

- A bounded buffer is used when you <u>pipe the output</u> of one program into another.
  - ◆ Example: grep foo file.txt | wc -l
    - The grep process is the producer.
    - The wc process is the consumer.
    - Between them is an in-kernel bounded buffer.
  - ◆ Bounded buffer is Shared resource → Synchronized access is required.

## The Put and Get Routines (Version 1)

```
int buffer;
1
         int count = 0; // initially, empty
3
         void put(int value) {
                  assert(count == 0);
                  count = 1;
                  buffer = value;
9
10
         int get() {
11
                  assert(count == 1);
12
                  count = 0;
13
                  return buffer;
14
```

- Only put data into the buffer when count is zero.
  - i.e., when the buffer is *empty*.
- Only get data from the buffer when count is one.
  - i.e., when the buffer is full.

# Producer/Consumer Threads (Version 1)

```
void *producer(void *arg) {
1
                   int i;
3
                   int loops = (int) arg;
                   for (i = 0; i < loops; i++) {</pre>
                            put(i);
         void *consumer(void *arg) {
10
                   int i;
                   while (1) {
11
12
                            int tmp = get();
13
                            printf("%d\n", tmp);
14
15
```

- Producer puts an integer into the shared buffer loops number of times.
- Consumer gets the data out of that shared buffer.

# Producer/Consumer: Single CV and If Statement

A single condition variable cond and associated lock mutex


```
1
         cond t cond;
         mutex t mutex;
        void *producer(void *arg) {
             int i;
             for (i = 0; i < loops; i++) {</pre>
7
                 Pthread mutex lock(&mutex);
                                                                // p1
                 if (count == 1)
                                                                // p2
                     Pthread cond wait(&cond, &mutex);
9
                                                                // p3
10
                 put(i);
                                                                // p4
                 Pthread cond signal(&cond);
11
                                                                // p5
12
                 Pthread mutex unlock(&mutex);
                                                                // p6
13
14
15
```


## Producer/Consumer: Single CV and If Statement


```
16
         void *consumer(void *arg) {
17
             int i;
18
             for (i = 0; i < loops; i++) {</pre>
19
                  Pthread mutex lock(&mutex);
                                                                  // c1
20
                  if (count == 0)
                                                                  // c2
21
                     Pthread cond wait (&cond, &mutex);
22
                  int tmp = get();
                                                                  // c4
2.3
                  Pthread cond signal (&cond);
                                                                  // c5
                  Pthread mutex unlock(&mutex);
24
                                                                  // c6
                  printf("%d\n", tmp);
2.5
26
27
```


- p1-p3: A producer waits for the buffer to be empty.
- c1-c3: A consumer waits for the buffer to be full.
- With just a single producer and a single consumer, the code works.


If we have more than one of producer and consumer?























# Thread Trace: Broken Solution (Version 1)

	State		State		State	Count	Comment
c1	Running		Ready		Ready	0	
c2	Running		Ready		Ready	0	
c3	Sleep		Ready		Ready	0	Nothing to get
	Sleep		Ready	p1	Running	0	
	Sleep		Ready	p2	Running	0	
	Sleep		Ready	p4	Running	1	Buffer now full
	Ready		Ready	р5	Running	1	awoken
	Ready		Ready	p6	Running	1	
	Ready		Ready	p1	Running	1	
	Ready		Ready	p2	Running	1	
	Ready		Ready	р3	Sleep	1	Buffer full; sleep
	Ready	c1	Running		Sleep	1	sneaks in
	Ready	c2	Running		Sleep	1	
	Ready	c4	Running		Sleep	0	and grabs data
	Ready	c5	Running		Ready	0	awoken
	Ready	c6	Running		Ready	0	
c4	Running		Ready		Ready	0	Oh oh! No data

## Thread Trace: Broken Solution (Version 1)

- The problem arises for a simple reason:
  - After the producer woke  $T_{c1}$ , but before  $T_{c1}$  ever ran, the state of the bounded buffer *changed by*  $T_{c2}$ .

- There is no guarantee that when the woken thread runs, the state will still be as desired → Mesa semantics.
  - Virtually every system ever built employs Mesa semantics.
- Hoare semantics provides a stronger guarantee that the woken thread will run immediately upon being woken.

## Producer/Consumer: Single CV and While


- **\Box** Consumer  $T_{c1}$  wakes up and re-checks the state of the shared variable.
  - If the buffer is empty, the consumer simply goes back to sleep.


```
cond t cond;
1
        mutex t mutex;
        void *producer(void *arg) {
5
             int i;
6
             for (i = 0; i < loops; i++) {
                 Pthread mutex lock(&mutex);
                                                                // p1
                 while (count == 1)
8
                                                                // p2
9
                      Pthread cond wait(&cond, &mutex);
                                                                // p3
10
                                                                // p4
                 put(i);
                                                                // p5
11
                 Pthread cond signal (&cond);
12
                 Pthread mutex unlock (&mutex);
                                                                // p6
13
14
15
```


## Producer/Consumer: Single CV and While


```
(Cont.)
        void *consumer(void *arg) {
16
17
             int i;
18
             for (i = 0; i < loops; i++) {
19
                 Pthread mutex lock(&mutex);
                                                                // c1
20
                 while (count == 0)
                                                                // c2
2.1
                      Pthread cond wait (&cond, &mutex);
                                                                // c3
22
                 int tmp = get();
                                                                // c4
23
                 Pthread cond signal (&cond);
                                                                // c5
                 Pthread mutex unlock (&mutex);
2.4
                                                               // c6
                 printf("%d\n", tmp);
25
26
27
```


- A simple rule to remember with condition variables is to always use while loops.
- However, this code still has a bug (next page).


























# Thread Trace: Broken Solution (Version 2)

	State		State		State	Count	Comment
c1	Running		Ready		Ready	0	
c2	Running		Ready		Ready	0	
c3	Sleep		Ready		Ready	0	Nothing to get
	Sleep	c1	Running		Ready	0	
	Sleep	c2	Running		Ready	0	
	Sleep	с3	Sleep		Ready	0	Nothing to get
	Sleep		Sleep	p1	Running	0	
	Sleep		Sleep	p2	Running	0	
	Sleep		Sleep	p4	Running	1	Buffer now full
	Ready		Sleep	р5	Running	1	awoken
	Ready		Sleep	р6	Running	1	
	Ready		Sleep	p1	Running	1	
	Ready		Sleep	p2	Running	1	
	Ready		Sleep	р3	Sleep	1	Must sleep (full)
c2	Running		Sleep		Sleep	1	Recheck condition
c4	Running		Sleep		Sleep	0	grabs data
c5	Running		Ready		Sleep	0	Oops! Woke

# Thread Trace: Broken Solution (Version 2) (Cont.)

	State		State	State	Count	Comment
				 		(cont.)
с6	Running		Ready	Sleep	0	
c1	Running		Ready	Sleep	0	
c2	Running		Ready	Sleep	0	
<b>c</b> 3	Sleep		Ready	Sleep	0	Nothing to get
	Sleep	c2	Running	Sleep	0	
	Sleep	c3	Sleep	Sleep	0	Everyone asleep

 A consumer should not wake other consumers, only producers, and viceversa.

## The single Buffer Producer/Consumer Solution

- Use two condition variables and while
  - Producer threads wait on the condition empty, and signals fill.
  - Consumer threads wait on fill and signal empty.

```
1
         cond t empty, fill;
         mutex t mutex;
         void *producer(void *arg) {
             int i;
             for (i = 0; i < loops; i++) {</pre>
                 Pthread mutex lock(&mutex);
                 while (count == 1)
                      Pthread cond wait (&empty, &mutex);
10
                 put(i);
                 Pthread cond signal (&fill);
11
                 Pthread mutex unlock(&mutex);
12
13
14
15
```

## The single Buffer Producer/Consumer Solution

```
(Cont.)
16
         void *consumer(void *arg) {
17
             int i;
             for (i = 0; i < loops; i++) {</pre>
18
19
                 Pthread mutex lock(&mutex);
20
                 while (count == 0)
2.1
                      Pthread cond wait(&fill, &mutex);
22
                 int tmp = get();
                 Pthread cond signal (&empty);
23
24
                 Pthread mutex unlock(&mutex);
                 printf("%d\n", tmp);
25
26
27
```

## The Final Producer/Consumer Solution

- More concurrency and efficiency → Add more buffer slots.
  - Allow concurrent production or consuming to take place.
  - Reduce context switches.

```
int buffer[MAX];
1
         int fill = 0;
3
        int use = 0;
         int count = 0;
5
6
        void put(int value) {
             buffer[fill] = value;
8
             fill = (fill + 1) % MAX;
9
             count++;
10
11
12
         int get() {
13
             int tmp = buffer[use];
14
             use = (use + 1) % MAX;
15
             count--;
16
             return tmp;
17
```

The Final Put and Get Routines

## The Final Producer/Consumer Solution (Cont.)

```
1
         cond t empty, fill;
        mutex t mutex;
        void *producer(void *arg) {
             int i;
            for (i = 0; i < loops; i++) {</pre>
                 Pthread mutex lock(&mutex);
                                                               // p1
                 while (count == MAX)
                                                               // p2
                     Pthread cond wait(&empty, &mutex);
9
                                                               // p3
10
                 put(i);
                                                               // p4
11
                 Pthread cond signal(&fill);
                                                               // p5
                 Pthread mutex unlock(&mutex);
12
                                                               // p6
13
14
15
```

## The Final Producer/Consumer Solution (Cont.)

```
void *consumer(void *arg) {
16
17
             int i;
18
             for (i = 0; i < loops; i++) {</pre>
19
                 Pthread mutex lock(&mutex);
                                                                // c1
20
                 while (count == 0)
                                                                // c2
21
                      Pthread cond wait(&fill, &mutex);
                                                                // c3
22
                                                                // c4
                 int tmp = get();
                                                                // c5
23
                 Pthread cond signal (&empty);
                 Pthread mutex unlock(&mutex);
                                                                // c6
24
                 printf("%d\n", tmp);
25
26
27
```

#### The Final Working Solution (Cont.)

- p2: A producer only sleeps if all buffers are currently filled.
- c2: A consumer only sleeps if all buffers are currently empty.