

Release 1.22

Peter Drummond

CONTENTS

1	Introduction to xSPDE	3
2	Interactive xSPDE 2.1 Stochastic equations	5 6 8 10
3	3.1 Using xsim and xgraph 3.2 Ensembles in xSPDE 3.3 xSPDE projects 3.4 Data files and batch jobs 3.5 Sequential integration	13 13 13 15 17 18 19
4	4.1 Wiener process 4.2 Harmonic oscillator 4.3 Kubo oscillator 4.4 Soliton 4.5 Gaussian with HDF5 files 4.6 Planar noise 4.7 Extensible simulations 4.8 Characteristic	21 23 26 29 32 33 44 48 51
5	5.1 How it works	55 55 56 59 60
6	6.2 Grids in x and k 6.3 Computational Fourier transforms 6.4 Graphics transforms 6.5 Fields 6.6 Data 6.7 Data 6.8 Data 6.9 Data	61 62 63 64 65 65 65

	6.8	Raw data	67				
7	Algorithms						
	7.1	Notation	69				
	7.2	xSPDE algorithms	70				
	7.3	Euler	70				
	7.4	Second order Runge-Kutta	70				
	7.5	Midpoint	71				
	7.6	Fourth order Runge-Kutta	71				
	7.7	Convergence checks	72				
	7.8	Extrapolation order and error bars	72				
	7.9	Sampling errors	73				
0	D 11						
8		ic API	75				
	8.1	High-level xSPDE functions and objects	75				
	8.2	Averages, integrals and derivatives	76				
	8.3	Grid coordinates and time	77				
	8.4	Input parameters and user functions	79				
	8.5	Parameter structure	88				
	8.6	Default functions	90				
	8.7	Frequently asked questions	91				
	8.8	High-level xSPDE functions and objects	92				
	8.9	Averages, integrals and derivatives	93				
	8.10	Grid coordinates and time	94				
	8.11	Input parameters and user functions	96				
	8.12	Parameter structure	106				
	8.13	Default functions	108				
	8.14	Frequently asked questions	108				
9	Refe	rences	111				
10	Indic	es and tables	113				
D21							
BII	Bibliography						
Ind	Index						

Peter D. Drummond, Simon Kiesewetter

xSPDE was developed at the Centre for Quantum and Optical Science, Swinburne University of Technology, Melbourne, Victoria, Australia.

Thanks for much valuable feedback and many useful suggestions from: Bogdan Opanchuk, Rodney Polkinghorne, Simon Kiesewetter, Laura Rosales-Zarate, King Ng and Run Yan Teh.

CONTENTS 1

2 CONTENTS

CHAPTER

ONE

INTRODUCTION TO XSPDE

Stochastic equations are equations with random noise terms [Gardiner2004]. They occur in in many fields of science, engineering, economics and other disciplines. xSPDE can solve both ordinary and partial differential stochastic equations. These include partial spatial derivatives, like the Maxwell or Schrödinger equations.

xSPDE: a stochastic toolbox

The xSPDE code is an extensible Stochastic Partial Differential Equation solver. It is a **stochastic toolbox** for constructing simulations, which is applicable to many stochastic problems [Gardiner2004]. It has a modular design which can be changed to suit different applications, and includes strategies for calculating errors. At a basic level just one or two lines of input are enough to specify the equation. For advanced users, the entire architecture is open and extensible in numerous ways.

Versions with an .m ending are written in Matlab, an interpreted scientific language of The Mathworks Inc, and are compatible with Octave, an open-source clone of Matlab. This version is best regarded as a prototyping platform. A code for new applications can be quickly developed and tested. This will not be quite as fast as a dedicated code but can be written easily and *understandably*.

The xSPDE logo is a three-pointed star that symbolizes that the code is suitable for all three domains: ordinary, partial or stochastic equations. Coincidentally, the logo is also similar to the three-pointed star from a Mercedes 280SE, renowned for its advanced automotive engineering.

Readers of this document may also wish to try XMDS [Colecutt2001], and its successor, XMDS2 [Dennis2013], which are similar programs using XML input files.

Applications

There are many types of stochastic equations, and xSPDE can treat a wide range. It has a configurable functional design. The general structure permits drop-in replacements of the functions provided. Different simulations can be carried out sequentially, to simulate the various stages in an experiment or other process.

The code supports parallelism at both the vector instruction level and at the thread level, using Matlab matrix instructions and the parallel toolbox. It calculates averages of arbitrary functions of any number of complex or real fields. It uses sub-ensemble averaging and extrapolation to obtain accurate error estimates.

Source code

The source code for xSPDE is available at github.com/peterddrummond/xspde_matlab.

Note: xSPDE is distributed without guarantee, under the MIT open-source license. Please test it yourself before use.

CHAPTER

TWO

INTERACTIVE XSPDE

All xSPDE simulations require parameters stored in an input structure used by the xSPDE toolbox. Inputs have default values, which can be changed by creating fields in the input structure. A complete list of parameters and their uses is given in chap-api.

The simplest way to use xSPDE is via the interactive Matlab command window, illustrated in this chapter. In this mode of operation, any required parameters are entered into the input structure in, and then the command xspde(in) runs and graphs the simulation. Note that one must enter clear first to erase previous data in the Matlab workspace, unless the previous data is being recycled.

2.1 Stochastic equations

An ordinary stochastic equation [Kloeden1995] for a real or complex vector a is:

$$\frac{\partial \boldsymbol{a}}{\partial t} = \dot{\boldsymbol{a}} = \boldsymbol{A}(\boldsymbol{a}) + \underline{\mathbf{B}}(\boldsymbol{a}) \zeta(t).$$

Here A is a vector function, $\underline{\mathbf{B}}$ a matrix, and ζ is a real Gaussian distributed noise vector such that $\langle \zeta \rangle = 0$, and :

$$\langle \zeta_i(t) \zeta_i(t) \rangle = \delta(t - t') \delta_{ij}.$$

To simulate a stochastic equation like this interactively, first make sure Matlab path is pointing to the xSPDE folder and type clear to clear old data.

Next, enter the xspde parameters (see chap-api) into the command window, as follows:

```
in.label1 = <parameter1>
in.label2 = ...
in.da = @(a,z,r) <expression for da/dt>
xspde(in)
```

- The notation in.label = parameter creates a field in the structure in (which is created dynamically, if it has not been defined before).
- The notation @ (...) is the Matlab shorthand for an anonymous function.
- The parameters passed to the *in.da* function are: a, the stochastic variable; z, the random noise; and r, the input structure with additional coordinates and parameters.
- xspde () is called with the input structure as the only argument.
- parameters or functions that are omitted are replaced with default values.
- a sequence of simulations requires an input list: {in1,in2..}.

Once the simulation is completed, xSPDE will generate graphs of averages of any required observables or moments. If needed, simulated data is stored in specified files for later use, which requires a file-name to be entered.

2.2 Interactive examples

2.2.1 The random walk

The first example is the simplest possible stochastic equation:

$$\dot{a} = \zeta(t),$$

with a complete xSPDE script in Matlab below, and output in Fig. 2.1.

$$in.da = @(a,z,r) z; xspde(in);$$

- Here in. da defines the derivative function, with z being the noise.
- The last argument of xspde user functions is r, containing the parameters required for the simulation.




Fig. 2.1: The simplest case: a random walk.

2.2.2 Laser quantum noise

Next we treat a model for the quantum noise of a single mode laser:

$$\dot{a} = \left(1 - \left|a\right|^2\right) a + b\zeta(t),$$

where $\zeta = (\zeta_1 + i\zeta_2)$, so that:

$$\langle \zeta(t)\zeta^*(t')\rangle = 2\delta(t-t').$$

Here the coefficient b describes the quantum noise of the laser, and is inversely proportional to the equilibrium photon number. An xSPDE script in Matlab is given below, for the case of b=0.01, with an output graph in Fig. 2.2. Note the use of the clear command here to clean up the Matlab workspace before the start.

```
clear
in.noises = 2;
in.observe = @(a,r) abs(a)^2;
in.olabels = '|a|^2';
in.da = @(a,z,r) (1-abs(a)^2)*a+0.01*(z(1)+i*z(2));
xspde(in)
```




Fig. 2.2: Simulation of the stochastic equation describing a laser turning on.

Note that:

- in.noises is the number of noises,
- in.observe is the graphed function,
- in.olabels gives the axis label.

2.3 Ito and Stratonovich equations

The xSPDE toolbox is primarily designed to treat Stratonovich equations [Gardiner2004], which are the broad-band limit of a finite band-width random noise equation, with derivatives evaluated at the midpoint in time of a time-step.

An equivalent type of stochastic equation is the Ito form. This is written in a similar way to a Stratonovich equation, except that this corresponds to a limit where derivatives are evaluated at the start of each step. To avoid confusion, we can write an Ito equation as a difference equation:

$$d\boldsymbol{a} = \boldsymbol{A}^{I} \left[\boldsymbol{a} \right] + \underline{\mathbf{B}} \left[\boldsymbol{a} \right] \cdot d\boldsymbol{w}(t).$$

Here:

$$\langle dw_i(\mathbf{x}) dw_j(\mathbf{x}') \rangle = \delta_{ij} dt.$$

When B is not a constant, the Ito drift term is different to the Stratonovich one. This difference occurs because the noise term is non-differentiable. The relationship is that

$$A_i = A_i^I - \frac{1}{2} \sum_{j,m} \frac{\partial B_{ij}}{\partial a_m} B_{mj}.$$

Provided the noise coefficient B is constant - which is called additive noise - there is no real difference between the two types of equation. Otherwise, it is essential to know which type of stochastic equation it is, in order to get unambiguous results!

2.3.1 Financial calculus

The Black-Scholes equation is a well-known Ito stochastic equation, used to price financial options. It describes the fluctuations in a stock value:

$$da = \mu a \, dt + \sigma a \, dw,$$

where $\langle dw^2 \rangle = dt$. Since the noise is multiplicative, the equation is different in Ito and Stratonovich forms of stochastic calculus. The corresponding Stratonovich equation, as used in xSPDE is:

$$\dot{a} = (\mu - \sigma^2/2) a + \sigma a \zeta(t).$$

An interactive xSPDE script in Matlab is given below with an output graph in Fig. 2.3, for the case of a volatile stock with $\mu=0.1$, $\sigma=1$. Note the spiky behaviour, typical of multiplicative noise, and also of the risky stocks in the small capitalization portions of the stock market.

```
clear
in.initial = @(v,r) 1;
in.da = @(a,z,r) -0.4*a+a*z;
xspde(in)
```

- Here in.initial describes the initialization function.
- The first argument of @ (v, r) is v, an initial random variable.
- The error-bars are estimates of step-size error.
- Errors can be reduced by using more time-steps: see *Averaging and projects*.

This graph is of a single stochastic realisation. Generation of averages is also straightforward. This is described in *Averaging and projects*.




Fig. 2.3: Simulation of the Black-Scholes equation describing stock prices.

2.4 Stochastic partial differential equations

More generally, xSPDE solves [Werner1997] a stochastic partial differential equation for a complex vector field defined with arbitrary transverse dimension. The total dimension is then input as d=2,3,... Equations of this type occur in many disciplines, including biology, chemistry, engineering and physics. They are in differential form as

$$\frac{\partial a}{\partial t} = A[a] + \underline{\mathbf{B}}[a] \cdot \zeta(t) + \underline{\mathbf{L}}[\nabla] \cdot a.$$

Here a is a real or complex vector or vector field. The initial conditions are arbitrary functions. A[a] and $\underline{\mathbf{B}}[a]$ are vector and matrix functions of a, $\underline{\mathbf{L}}[\nabla]$ is a matrix of linear terms and derivatives, diagonal in the vector indices, and $\boldsymbol{\zeta} = \begin{bmatrix} \boldsymbol{\zeta}^x, \boldsymbol{\zeta}^k \end{bmatrix}$ are real delta-correlated noise fields such that:

$$\left\langle \zeta_{i}^{x}\left(t,\boldsymbol{x}\right)\zeta_{j}^{x}\left(t,\boldsymbol{x}'\right)\right\rangle =\delta\left(\boldsymbol{x}-\boldsymbol{x}'\right)\delta\left(t-t'\right)\delta_{ij}$$
$$\left\langle \zeta_{i}^{k}\left(t,\boldsymbol{k}\right)\zeta_{j}^{k}\left(t,\boldsymbol{k}'\right)\right\rangle =f(\boldsymbol{k})\delta\left(\boldsymbol{k}-\boldsymbol{k}'\right)\delta\left(t-t'\right)\delta_{ij}.$$

Note that the x and k noise term for each value of the index are generated from the same underlying stochastic process. This is necessary because there are some equations that require both a filtered and unfiltered noise generated from the same underlying random number distribution. If these correlations are not wanted, and the noises are required to be independent, then different noise indices must be used.

Transverse boundary conditions are assumed periodic. The term $\underline{\mathbf{L}}\left[\boldsymbol{\nabla}\right]$ may be omitted, as space derivatives can also be treated directly in the derivative function. The momentum filter $f(\boldsymbol{k})$ is an arbitrary user-specified function, allowing for spatially correlated noise.

To treat stochastic partial differential equations or SPDEs, the equations are divided into the first two terms, which are essentially an ordinary stochastic equation, and the last term which gives a linear partial differential equation:

$$\frac{\partial \boldsymbol{a}}{\partial t} = \underline{\mathbf{L}} \left[\boldsymbol{\nabla} \right] \cdot \boldsymbol{a}$$

The *interaction picture* is a moving reference frame used to solve the linear part of the equation exactly, defined by an exponential transformation. This is carried out internally by matrix multiplications and Fourier transforms.

In more detail, in Fourier space, if $\tilde{a}(k) = \mathcal{F}[a(x)]$ is the Fourier transform of a, we simply define:

$$\tilde{\boldsymbol{a}}(\boldsymbol{k},dt) = \mathcal{P}(\boldsymbol{k},dt)\,\tilde{\mathbf{a}}_{I}(\boldsymbol{k},dt)$$

where the propagation function can be written intuitively as $\mathcal{P} = \exp\left[\underline{\mathbf{L}}(\mathbf{D})dt\right]$, where $\mathbf{D} = i\mathbf{k} \sim \nabla$. The function $\underline{\mathbf{L}}(\mathbf{D})$ is input using the xSPDE linear response function linear (). With this definition, at each step the equation that is solved can be re-written in a more readily soluble form as:

$$\frac{\partial \boldsymbol{a}_{I}}{\partial t} = \mathcal{D}\left[\mathcal{F}^{-1}\mathcal{P}\left(\mathcal{F}\boldsymbol{a}_{I}\right)\right]$$

The total derivative in the interaction picture is the xSPDE derivative function da():

$$\dot{a}_I = A + B \zeta$$

where usually A, \underline{B} are evaluated at the midpoint which is the origin in the interaction picture. For convenience, the final output is calculated in the original picture, with at least two interaction picture (IP) transformations per time-step.

Note that there are many types of partial differential equation that can be treated with xSPDE, even if the interaction picture method doesn't apply. This occurs when there are nonlinear functions with arbitrary derivatives, or derivatives that are non-diagonal in the vector indices. For these cases, the space derivatives are evaluated inside the derivative term da():. If there are higher order time derivatives as well, these can be re-expressed as a set of first-order time derivatives, provided the problem is an initial-value problem.

2.4.1 Symmetry breaking

An example of a SPDE with space-time dimensions of d=3 is the stochastic Ginzburg-Landau equation. This describes symmetry breaking, in which the system develops a spontaneous phase which can vary spatially. The model is widely used in fields ranging from lasers to magnetism, superconductivity, superfluidity and even particle physics:

$$\dot{a} = \left(1 - \left|a\right|^{2}\right) a + b\zeta(t) + ic\nabla^{2}a$$

where

$$\langle \zeta(x)\zeta^*(x')\rangle = 2\delta(t-t')\delta(x-x').$$

An xSPDE script is given below, for parameter values of b=0.001 and c=0.01, with the output graphed in Fig. 2.4. Note that in the graph, the range -5 < x < 5 is the default xSPDE coordinate range, while the .* notation is used in functions here, as fields require element-wise multiplication.

```
clear
in.noises = 2;
in.dimension = 3;
in.steps = 10;
in.linear = @(r) i*0.01*(r.Dx.^2+r.Dy.^2);
in.observe = @(a,~) abs(a).^2;
in.olabels = '|a|^2';
in.da = @(a,z,~) (1-abs(a(1,:)).^2).*a+0.001*(z(1,:)+i*z(2,:));
xspde(in)
```

Here:

- in. dimension is the space-time dimension, with an x-t plot given here.
- in. steps gives the integration steps per plot-point, for improved accuracy.
- in.linear is the linear operator an imaginary laplacian
- r.Dx indicates a derivative operation, $\partial/\partial x$. See the reference entry for in.linear for more information.




Fig. 2.4: Simulation of the stochastic equation describing symmetry breaking in two dimensions. Spatial fluctuations are caused by the different phase-domains that interfere. The graph obtained here is projected onto the y=0 plane.

CHAPTER

THREE

AVERAGING AND PROJECTS

3.1 Using xsim and xgraph

Suppose that you are not happy with the graphs in an interactive session, and want to alter them by adding a heading or some other change. For long simulations, it may be inconvenient to re-run everything. This is easy, provided the data is in the current workspace.

For example, suppose the Kubo simulation is run interactively, using an output specification so that the data file is stored locally in your Matlab workspace. After editing some inputs, the job can be repeated, with data saved to the local workspace, by running

```
[e,data] = xspde(in)
```

Alternatively, if you just want the data, and no graphs, use:

```
[e,input,data] = xsim(in)
```

Next, you should know the object label you wish to change. Note that the xsim() and xgraph() program inputs are either structure objects containing data for one simulation, or else cell arrays of structures with many simulations in sequence, which are treated later. You can use either in xSPDE.

To change the project name for the graph headings, input:

```
in.name ='My new project';
```

then replot the data using

```
xgraph(data,in)
```

More graphics information can be added, for example using

```
in.olabels = 'Intensity';
```

which inputs this additional graphics data to the in structure to xSPDE. Just plot again, using the same instructions.

3.2 Ensembles in xSPDE

Averages over stochastic ensembles are the specialty of xSPDE, which requires specification of the ensemble size. To get an average, an ensemble size is needed, to obtain more trajectories in parallel.

Ensembles are specified in three levels to allow maximum resource utilization, so that:

```
in.ensembles = [ensembles(1), ensembles(2), ensembles(3)]
```

The first, ensembles (1), gives within-thread parallelism, allowing vector instruction use for single-core efficiency. The second, ensembles (2), gives a number of independent trajectories calculated serially.

The third, ensembles (3), gives multi-core parallelism, and requires the Matlab parallel toolbox. This improves speed when there are multiple cores, and one should optimally put ensembles (3) equal to the available number of CPU cores.

The total number of stochastic trajectories or samples is ensembles(1) * ensembles(2) * ensembles(3).

However, either ensembles (2) or ensembles (3) are required if sampling error-bars are to be calculated, owing to the sub-ensemble averaging method used in xSPDE to calculate sampling errors accurately.

3.2.1 Random walk with averaging

To demonstrate this, try adding some more trajectories, points and an output label to the in parameters of the random walk example:

:: clear in.da = @(a,z,r) z; in.ensembles = [500,20]; in.points = 101; in.olabels = '<a_1>'; xspde(in)

You will see Fig. 3.1 appearing.




Fig. 3.1: The average random walk with 10^4 trajectories.

This looks like the earlier graph, but check the vertical scale. The in.ensembles = [100, 100] input gives

an average over 10^4 random trajectories. Therefore the sampling error is accordingly reduced by a factor of 100. The two lines plotted are the upper and lower one standard deviation limits.

The more detailed structure of the random walk is due to having more time-points. Of course, $\langle a \rangle = 0$ in the ideal limit.

Note that:

- in.ensembles is the number of trajectories averaged over
- in.points is the number of time-points integrated and graphed

3.3 xSPDE projects

An XPDE session can either run simulations interactively, described in *Interactive xSPDE*, or else using a function file called a project file. This allows xSPDE to run in a batch mode, as needed for longer projects which involve large ensembles. In either case, the Matlab path must include the xSPDE folder.

A minimal xSPDE project function is as follows:

```
function = project()
  in.label1 = parameter1;
  in.label2 = parameter2;
  ...
  xspde(in)
end
```

For standard graph generation, the script input or project function should end with the combined function xspde(). Alternatively, to generate simulation data and graphs separately, the function xsim() runs the simulation, and xgraph() makes the graphs. The two-stage option is better for running batch jobs, which you can graph at a later time. See the next chapter for details.

After preparing a project, type the project name into the Matlab interface, or click on the Run arrow above the editor window.

In summary:

• For medium length simulations with more control, use a function file whose last executable statement is xspde(in).

3.3.1 Kubo project

To get started on more complex stochastic programs, we next simulate the Kubo oscillator, which is a stochastic equation with multiplicative noise. It uses the Stratonovich stochastic calculus. It corresponds to an oscillator with a random frequency, with difference equation:

$$\dot{a} = ia\zeta$$

To simulate this, one can use a file, Kubo.m, which also contains definitions of user functions.

```
function [e] = Kubo()
    in.name = 'Kubo oscillator';
    in.ensembles = [400,16];
    in.initial = @(v,~) 1+0*v;
    in.da = @(a,z,r) i*a.*z;
    in.olabels = {'<a_1>'};
    e = xspde(in);
```

The resulting graph is given in Fig. 3.2, including upper and lower one standard deviation sampling error limits to indicate the accuracy of the averages. This is obtained on inputting the second number in the ensembles vector, to allow sub-ensemble averaging and sampling error estimates. Note that .* multiplication must be used because the first ensemble is stored as a matrix, to improve speed.




Fig. 3.2: The amplitude decay of a Kubo oscillator.

The other input parameters are not specified explicitly. Default values are accessed from the inpreferences function.

Here we note that:

- Kubo defines the parameters and function handles, then runs the simulation.
- in.name gives a name to identify the project.
- in.ensembles specifies 400 samples in a parallel vector, repeated 16 times in series.
- in.initial initializes the input to ones; the noise v is used as it has the same lattice dimension as the a field.
- in. da is the function, $da/dt = ia\zeta$, that specifies the equation being integrated.
- in.olabels is a cell array with a label for the variable a that is averaged.
- xspde () runs the simulation and graphics program using data from the in structure.

The function names can point to external files instead of those in the project file itself. This is useful when dealing with complex projects, or if you just want to change one function at a time. As no points or ranges were specified, here, default values of 51 points and a range of 10 are used.

3.4 Data files and batch jobs

It is often inconvenient to work interactively, especially for large simulations. To save data is very useful. This is not automatic: to create a data file, you must enter the filename - either interactively or a bath file — before running the simulation, using the in.file = filename input.

The xSPDE program allows you to specify a file name that stores data in either standard HDF5 format, or in Matlab format. It also gives multiple ways to edit data for either simulations or graphs. A simple interactive workflow is as follows:

- Create the metadata in, and include a file name, say "in.file = filename.mat ".
- Run the simulation with xsim().
- Run xgraph ('filename.mat'), and the data will be accessed and graphed.

3.4.1 Saving data files

In greater detail, first make sure you have a writable working directory with the command cd ~. Next, specify the filename using the in.file = 'name.ext' inputs, and run the simulation. All calculated data as well as the input metadata from the in object is stored.

For example,

```
in.file = 'filename.mat'
```

gives a Matlab data file — which is the simplest to edit.

Alternatively,

```
in.file = 'filename.h5'
```

gives an international standard HDF5 data file, useful for exchanging data with other programs.

To reload and reanalyze any previously saved Matlab simulation data, say Kubo.mat, at a later time, there are two possible approaches, described below.

3.4.2 Graphing saved data

If the filename is still available in an interactive session workspace, just type

```
xgraph(in.file)
```

which tells *xgraph* () to use the file-name already present in in.

More generally, one can use any file name directly in xgraph(), which works with either matlab or HDF5 file types. Once the data is saved in a file by running xsim() or xspde() with an input filename, just type:

```
xgraph('filename.mat'),
```

or for HDF5 files,

```
xgraph('filename.h5')
```

to replot the resulting data.

Note that you can use xgraph() with either Matlab or HDF5 file data inputs, and without having to specify the in structure. This metadata is automatically saved with the data in the output file. This approach has the advantage that many simulations can be saved and then graphed later. In the current version, in order to access the function handles in the saved files, Matlab needs to access the original input file. Hence, when you move the data to a new computer, it is best to include the original input file in the same directory as the data, to make the handles available.

3.4.3 Editing saved data

If the saved data was a Matlab file, one can load the simulated data and metadata by typing, for example,

```
load Kubo
```

Results can easily be replotted interactively, with changed input and new graphics details, using this method. This approach loads all the relevant saved data into your work-space.

Hence one can easily edit and change the graphics inputs in the in structure, then use the standard graphics command:

```
xgraph(data, in)
```

To change cell contents for a sequence, be aware that sequence inputs are stored in cell arrays with curly bracket indices, so you have to change them individually using an index.

3.4.4 Combining saved data with new metadata

If the graphs generated from saved data files need changing, some new input specifications may be needed.

To combine an old, saved data file, say 'Kubo.mat' with a new input specification in you have just created, type

```
xgraph('Kubo.mat', in)
```

or if the data was saved in an HDF5 file, it is:

```
xgraph('Kubo.h5', in)
```

In both cases the new in metadata is combined with the old metadata. Any new input metadata takes precedence over old, filed metadata.

This allows fonts and labels, for example, to be easily changed — without having to re-enter all the simulation input details.

3.5 Sequential integration

Sequences of calculations are available simply by adding a sequence of inputs to xSPDE, representing changed conditions or input/output processing. These are combined in a single file for data storage, then graphed separately. The results are calculated over specified ranges, with it's own parameters and function handles. In the current version of xSPDE, the numbers of ensembles must be the same throughout.

The initialization routine for the first fields in the sequence is called *in.initial*, while for subsequent initialization it is called *in.transfer*. The sequential initialization function has four input arguments, to allow noise to be combined with previous field values and input arguments, as may be required in some types of simulation. This is described in the next chapter.

In many cases, the default transfer value — which is to simply reuse the final output of the previous set of fields — is suitable. To help indicate the order of a sequence, a time origin can be included optionally with sequential plots, so that the new time is the end of the previous time, if this is required.

Suppose the project has a sequence of two simulations, with input structures of in1, in2. To run this and store the data locally, just type:

```
[e,~,data] = xspde({in1,in2})
```

To change the file headers, at a later stage, type:

```
in1.name = 'My first simulation'
in2.name = 'My next simulation'
```

This method requires that the data, in1 and in2 are already loaded into your Matlab work space so they can be edited.

Next, simply replot the data using

```
xgraph(data, {in1, in2})
```

3.6 xSPDE hints

- When using xSPDE, it is a good idea to first run the batch test script, Batchtest.m. This will perform simulations of different types, and report an error score. The final error score ought to match the number in the script comments, to show your installation is working correctly.
- xSPDE also tests your parallel toolbox installation. If you have no license for this, just omit the third ensemble setting, so that the parallel option is not used.
- To create a project file, it is often easiest to start with an existing project function with a similar equation. There are a number of these distributed with xSPDE, and these are included in the Batchtest examples.
- Just as in interactive operation, the simulation parameters and functions for a batch job are defined in the structure in. The parameters include *function handles* that point to user specified functions, which give the initial values, derivative terms and quantities measured. The function handles can point to any function declarations in the same file or Matlab path.
- Graphics parameters and a comparison function are also defined in the structure in. In each case there are default parameters in a preference file, but the user inputs will be used first if included.

The general workflow is as follows:

Create a project file, using an existing example as a template

Decide whether you want to generate graphs now (xspde()) or later (xsim() and xgraph()).

Edit the project file parameters and functions

Check that the Matlab path includes the xSPDE folder

Click Run

Save the output graphs that you want to keep

More details and examples will be given in later sections!

3.6. xSPDE hints

CHAPTER

FOUR

TUTORIAL

This chapter is a a tutorial in xSPDE functionality, giving a number of examples, and exercises. Not all the graphs generated by the scripts are included here, for space reasons. One can obtain many more graphs if desired, by generating more observables.

Vertical bars in the graphs are the step-size errors in time, calculated from setting <code>in.errorchecks</code> to 2. These are automatically omitted when the relative errors are too small to be visible. In most cases, the default ranges and step-sizes are used to keep things simple. One can improve this accuracy by using more points, as shown in the first example, or by using more steps per point.

Upper and lower solid lines are due to sampling errors. This occurs where there is statistical noise, and requires a finite number of serial (in.ensembles(2)) or parallel (in.ensembles(3)) ensembles to calculate it. One can improve this by using more ensembles. Sub-ensemble averaging with multiple sub-ensembles is used to improve the accuracy of error estimates.

There are preset preferences for all the input parameters except the derivative function, which defines the equation that is simulated. Each example in the tutorial has exercises, which are very simple. However, they help to understand xSPDE conventions, and it is recommended to try them.

Note: All the exercises, and some bonus examples, are given in the xSPDE Examples folder.

4.1 Wiener process

Try increasing the time resolution and adding a heading to the random walk example in *Interactive xSPDE*.

This requires specifying the number of points using in.points. To name the simulation, use in.name, which is stored with your simulation data. The default option is to add this heading to each graph. If no header is wanted, type in.headers = 0.

To run the xSPDE program after adding these inputs, just press the *Run* icon on the Matlab editor bar. This will run the xSPDE program, with default parameters where they are not specified in the inputs. You will see the following figure:

Exercise

Add 100 samples and 100 serial ensemble trajectories. Does the mean equal zero within the sampling error bars?




Fig. 4.1: Increasing the Wiener process resolution and adding a header.

4.2 Harmonic oscillator

The next example is the stochastic harmonic oscillator with the initial condition that

$$a(0) = 1 + v,$$

where

$$\langle v^2 \rangle = 1$$

and the differential equation:

$$\dot{a} = ia + \zeta(t).$$

4.2.1 Initial conditions and derivative

First, make sure you type clear to clear the previous example. This is good practice for all the examples. The following parameters are needed to specify the harmonic oscillator with noise. By specifying return values in square brackets, the data is made available in the user data space:

```
clear
in.initial = @(v,~) 1+v;
in.ensembles = [20,20];
in.da = @(a,z,~) i*a + z;
in.olabels = {'<a_1>'};
xspde(in);
```

Here \sim indicates an unused input to a function, while i is the Matlab codes for the unit imaginary number, i. The following graph is produced:

The plotted error-bars are suppressed, as they are too small to see, nor is there any header, since none was specified. The xsim() program reports the following error summary, using the default number of points (51):

```
- Max sampling error = 1.193890e-01
- Max step error = 1.270917e-02
```

This is an approximate upper bound on the overall integration error of the specified observable. It is calculated from comparing two solutions. In this case, the default estimates are obtained by comparing a coarse and fine step calculation at half the specified step-size. This is used to extrapolate to zero step-size. The difference between the fine result and the extrapolated result gives the error estimate.

4.2.2 Comparisons with exact results

The stochastic equation has the mean solution:

$$\langle a(t) \rangle = e^{it}$$

= $\cos(t) + i \sin(t)$

To compare the calculated solution with this exact result, just tell the graphics program that you want a comparison, by editing the project file, and adding a comparison function.

This example uses the previous inputs, together with the comparison function itself (in.compare). All functions and data relating to observables are cell arrays, hence the curly brackets: compare {1} is the first element of an array of comparison functions that might be needed if there are many observables.




Fig. 4.2: Simple harmonic oscillator amplitude

```
in.compare\{1\} = Q(t, \sim) cos(t); xspde(in);
```

With this input, xgraph gives the difference in the comparison as:

```
- Maximum comparison differences = 1.950535e-01
```

The actual error in this case is smaller than the error estimated using the sampling error estimates. However, the error-bars are very small. This is because in this case, the specified fine step-size is small enough to give excellent convergence.

Comparison graphs are also produced, including one of the relative errors:




Fig. 4.3: Simple harmonic oscillator comparison graph: exact vs computed, with error-bars.

The reported summary data is consistent with the graphs, as expected. Note that one can obtain exactly the same result in the interaction picture, by using an imaginary linear coupling of i, and a derivative term of zero. The code then reports a maximum step-size error of around $\sim 10^{-15}$, equal to the limit of IEEE arithmetic.

Exercise

Add a linear decay of -a to the differential equation, and modify the exact solution to suit, then replot. Is it exactly as you expected?

4.3 Kubo oscillator

The next example is more interesting. It is the Kubo oscillator, an oscillator with a random frequency. It is a case of multiplicative noise, but with a complex variable.

In Stratonovich stochastic calculus, its equation is:

$$\dot{a} = ia\zeta(t)$$

Given the initial condition that a(0) = 1, each trajectory has the solution:

$$a(t) = e^{iw(t)}$$

where

$$w(t) = \int_0^t \zeta(\tau)d\tau$$

The corresponding mean value is different to the instantaneous trajectory, owing to dephasing:

$$\langle a(t)\rangle = e^{-\langle w^2(t)\rangle/2} = e^{-t/2}.$$

4.3.1 Kubo initial conditions and derivative

Here more parameters are needed. One real noise term is required per integration point, specified using *in.noises*. Next, the ensemble numbers are required. Here we use 100 vector-level trajectories, and 16 sets at a higher level. In these calculations, the mean amplitude is calculated, and compared against a comparison function.

```
function e = Kubo()
   in.name = 'Kubo oscillator';
   in.ensembles = [400,16,1];
   in.initial = @(v,r) 1+0*v;
   in.da = @(a,z,r) i*z.*a;
   in.olabels = {'<a_1>'};
   in.compare{1} = @(t,~) exp(-t/2);
   e = xspde(in);
end
```

Kubo error results are reported as:

```
- Max sampling error = 1.043423e-02
- Max step error = 2.258936e-02
```

Note that these are generally consistent with the graphs below, as they should be.

Is the actual error always less than the reported maximum standard deviation? This is not always the case, for statistical reasons. The statistical estimates given are best estimates of the standard deviations of the plotted means. However, given a large enough number of means at different times, some **must** fall outside the range of a unit standard deviation.

The different time points in the Kubo oscillator trajectories become uncorrelated after a time of order one. Hence an occasional excursion with an error of 2σ can occur. In other words, the expected maximum sampling error is a multiple of the standard deviation, which should therefore be treated with some caution as a guide to statistical errors.

We see evidence here the sampling errors often exceed the step-size errors, unless large sample numbers are used.

4.3.2 Kubo graphs

The Graphics program reports the following errors when making the comparisons:

```
- Max difference in 1 = 1.294696e-02
```

With this choice of algorithm and step-size, the results of a simulation run are plotted below.




Fig. 4.4: Kubo oscillator mean amplitude

There are some interesting features here. The two solid lines indicate the sampling error. The error bars indicate the step-size error. This affects both results, but is only visible in the error graphs, which have an expanded scale.

Exercise

Add a detuning of ia to the differential equation, modify the exact solution to suit, then replot.

4.3. Kubo oscillator 27




Fig. 4.5: Kubo oscillator amplitude errors

4.4 Soliton

The third example is the soliton equation for the nonlinear Schrödinger equation, with:

$$\frac{da}{dt} = \frac{i}{2} \left[\nabla^2 a - a \right] + ia \left| a \right|^2$$

Together with the initial condition that a(0,x) = sech(x), this has an exact solution that doesn't change in time:

$$a(t,x) = sech(x)$$

The Fourier transform at k = 0 is simply:

$$\tilde{a}(t,0) = \frac{1}{\sqrt{2\pi}} \int sech(x) dx = \sqrt{\frac{\pi}{2}}$$

4.4.1 Soliton parameters and functions

The important parameters and functions in this case are:

```
function [e] = Soliton()
    in.name = 'NLS soliton';
    in.dimension = 2;
    in.initial = @(v,r) sech(r.x);
    in.da = @(a,~,r) i*a.*(conj(a).*a);
    in.linear = @(r) 0.5*i*(r.Dx.^2-1.0);
    in.olabels = {'a_1(x)'};
    in.compare{1}= @(t,~) 1;
    e = xspde(in);
end
```

The xspde program reports the following maximum errors:

```
- Max step error = 1.976729e-02
```

The output reflects the known analytic result.

4.4.2 Soliton graphs and errors

Graphs of results are given below.

The xgraph program reports that comparison errors are slightly less than the step error:

```
- Max difference in 1 = 1.761991e-02
```

This is not always the case, because the error checking does not check errors due to the lattice sizes. In general this needs to be carried out manually.

Exercise

Add an additive complex noise of $0.01(dw_1 + idw_2)$ to the differential equation, then replot with an average over 1000 samples.

4.4. Soliton 29




Fig. 4.6: Soliton amplitude versus space and time




Fig. 4.7: Soliton amplitude errors at center

4.4. Soliton 31

4.5 Gaussian with HDF5 files

The fifth example is free diffraction of a Gaussian wave-function in three dimensions, given by

$$\frac{da}{dt} = \frac{i}{2}\nabla^2 a$$

Together with the initial condition that $a(0,x) = exp(-|\mathbf{x}|^2/2)$, this has an exact solution for the diffracted intensity in either ordinary space or momentum space:

$$|a(t, \mathbf{x})|^2 = \frac{1}{(1+t^2)^{3/2}} exp(-|\mathbf{x}|^2 / (1+t^2))$$

 $|\tilde{a}(t, \mathbf{k})|^2 = exp(-|\mathbf{k}|^2)$

4.5.1 Gaussian inputs

Before running this simulation, be careful to change the Matlab working directory to your intended working directory, which must have write permission enabled. For example, type:

```
cd ~
```

A possible user set of parameters to simulate this is:

```
function [e] = Gaussian()
    in.dimension = 4;
    in.initial = @(v,r) \exp(-0.5*(r.x.^2+r.y.^2+r.z.^2));
    in.da = @(a, \sim, \sim) zeros(size(a));
    in.linear = @(r) 1i*0.05*(r.Dx.^2+r.Dy.^2+r.Dz.^2);
    in.observe = \{@(a, \sim) a.*conj(a)\};
    in.olabels = '|a(x)|^2';
    in.file = 'Gaussian.h5';
    in.images = 4;
    in.imagetype = 1;
    in.transverse = 2;
    in.headers = 1;
    in.compare{1} = @(t, \sim) [1+(t/10).^2].^(-3/2);
    [e,in] = xsim(in);
    e = e + xgraph(in.file);
end
```

Here the program writes an HDF5 data file using xsim(), and then reads it in with the stored file-name, using xgraph(). Note that xsim() may have to change the file-name to avoid overwriting any old data. In this case, it returns the new file-name is uses. The program reports the following maximum step-size errors, which in this case are negligible, as they are purely due to the interaction picture transformations:

```
- Max step error = 4.107825e-15
```

However, the finite spatial lattice size introduces errors in the on axis intensity, in coordinate space. This shows up in the comparisons:

```
- Max difference in 1 = 5.590272e-07
```

4.5.2 Gaussian graphs

With this choice of algorithm and step-size, the results of a simulation run are plotted below. The errors, of order 10^{-7} , are simply due to interference of diffracted waves caused by the periodic boundary conditions. This is sometimes

called aliasing error. One can think of this physically as being a simulation of an infinite array or periodically repeated Gaussian inputs, which can diffract and interfere.




Fig. 4.8: Image of transverse gaussian intensity at t = 0.

Exercise

Add an additive complex noise of $0.01(dw_1 + idw_2)$ to the Gaussian differential equation, then replot with an average over 10 samples.

4.6 Planar noise

The fifth example is growth of thermal noise of a two-component complex field in a plane, given by the equation

$$\frac{d\boldsymbol{a}}{dt} = \frac{i}{2}\nabla^2\boldsymbol{a} + \boldsymbol{\zeta}(t,x)$$

where ζ is a delta-correlated complex noise vector field:

$$\zeta_j(t,\mathbf{x}) = \left[\zeta_j^{re}(t,\mathbf{x}) + i\zeta_j^{im}(t,\mathbf{x})\right]/\sqrt{2},$$

4.6. Planar noise 33




Fig. 4.9: Gaussian intensity diffraction




Fig. 4.10: Gaussian intensity at r = 0.

4.6. Planar noise 35




Fig. 4.11: Gaussian, modulus-squared errors at ${m r}=0$.

with the initial condition that the initial noise is delta-correlated in position space

$$a(0, \mathbf{x}) = \boldsymbol{\zeta}^{(in)}(\boldsymbol{x})$$

where:

$$\boldsymbol{\zeta}^{(in)}(\boldsymbol{x}) = \left\lceil \boldsymbol{\zeta}^{re(in)}(\mathbf{x}) + i \boldsymbol{\zeta}^{im(in)}(\mathbf{x}) \right\rceil / \sqrt{2}$$

This has an exact solution for the noise intensity in either ordinary space or momentum space:

$$\left\langle \left| a_j \left(t, \mathbf{x} \right) \right|^2 \right\rangle = (1+t)/\Delta V$$
$$\left\langle \left| \tilde{a}_j \left(t, \mathbf{k} \right) \right|^2 \right\rangle = (1+t)/\Delta V_k$$
$$\left\langle \tilde{a}_1 \left(t, \mathbf{k} \right) \tilde{a}_2^* \left(t, \mathbf{k} \right) \right\rangle = 0$$

Here, the noise is delta-correlated, and ΔV , ΔV_k are the cartesian space and momentum space lattice cell volumes respectively. Suppose that $N=N_xN_y$ is the total number of spatial points, and $V=R_xR_y$, where there are $N_{x(y)}$ points in the x(y)-direction, with a total range of $R_{x(y)}$. Then, $\Delta x=R_x/N_x$, $\Delta k_x=2\pi/R_x$, so that:

$$\Delta V = \Delta x \Delta y = \frac{V}{N}$$
$$\Delta V_k = \Delta k_x \Delta k_y = \frac{(2\pi)^2}{V}.$$

In the simulations, two planar noise fields are propagated, one using noise generated in position space, the other with noise generated in momentum space. This example shows that, provided no filters are applied, both types of noise are identical in their effects. However, momentum space noise requires an N-dimensional inverse FFT before being added, which is slower, so this method is not recommended unless needed.

4.6.1 Planar inputs

```
function [e] = Planar()
    in.name = 'Planar noise growth';
    in.dimension = 3;
    in.fields = 2;
    in.ranges = [1, 5, 5];
    in.steps = 2;
    in.noises = [2,2];
    in.ensembles = [10,2,2];
    in.initial = @Initial;
    in.da = @D_planar;
    in.linear = @Linear;
    in.observe{1} = @(a,r) xint(a(1,:).*conj(a(1,:)),r);
    in.observe{2} = @(a,r) xint(a(2,:).*conj(a(2,:)),r.dk,r);
    in.observe{3} = @(a,r) xave(a(1,:).*conj(a(2,:)));
    in.transforms = \{[0,0,0],[0,1,1],[0,1,1]\};
    in.olabels{1} = '<\int|a_1(x)|^2 d^2x>';
    in.olabels{2} = '< int|a_2(k)|^2 d^2k >';
    in.olabels\{3\} = ' << a_1(k) a^*_2(k) >> ';
    in.compare{1} = @(t,in) [1+t]*in.nspace;
    in.compare{2} = @(t,in) [1+t]*in.nspace;
    in.compare{3} = @(t,in) 0;
    in.images = [4,2,0];
    in.transverse = [2,2,0];
    in.pdimension = [4,1,1];
    e = xspde(in);
```

4.6. Planar noise 37

```
end
function a0 = Initial(v,r)
    a0(1,:) = (v(1,:)+li*v(2,:))/sqrt(2);
    a0(2,:) = (v(3,:)+li*v(4,:))/sqrt(2);
end
function da = D_planar(a,z,r)
    da(1,:) = (z(1,:)+li*z(2,:))/sqrt(2);
    da(2,:) = (z(3,:)+li*z(4,:))/sqrt(2);
    end
function L = Linear(r)
    lap = r.Dx.^2+r.Dy.^2;
    L(1,:) = li*0.5*lap(:);
    L(2,:) = li*0.5*lap(:);
end
```

4.6.2 Planar graphs

With this choice of algorithm and step-size, the results are plotted below.




Fig. 4.12: Planar noise intensity as a transverse slice in the $t=1,\,y=0$ plane. The relatively large sampling error is because there are not many samples.




Fig. 4.13: Growth in noise intensity with time vs. x, at y = 0.

4.6. Planar noise




Fig. 4.14: Growth in planar noise intensity at x=y=0, vs. exact results.




Fig. 4.15: Errors in planar noise intensity at x = y = 0, vs. exact results. These results are averaged across the plane, as well as being ensemble averaged.

4.6. Planar noise 41




Fig. 4.16: Growth in planar noise intensity in momentum space, for the second field, at $k_x = k_y = 0$.




Fig. 4.17: Lattice averaged errors in cross-correlations in momentum space, vs. exact results.

4.6. Planar noise 43

Exercise

Add a decay rate of -a to the Planar differential equation, then replot.

4.7 Extensible simulations

Next, an extensible simulation: first a noisy absorber, then a noisy amplifier. The second part has a different differential equation, and larger graphical scales.

This is handled with the extensibility feature of xSPDE. Just enter a sequence of inputs, in the form $\{in1, in2, in3, ...\}$ with a corresponding sequence of graphs, $\{g1, g2, g3m ...\}$. Here, the first equation is:

$$\frac{da}{dt} = -a + \zeta_1(t) + i\zeta_2(t)$$

with an initial condition of a = 1. The mean intensity is constant:

$$\left\langle \left| a(t) \right|^2 \right\rangle = 1.$$

4.7.1 Input file

The full input file is given below.

```
function [e] = Gain()
    in.name = 'Loss with noise';
    in.ranges = 4;
    in.noises = [2,0];
    in.ensembles = [100, 16, 1];
    in.initial = @(v, \sim) (v(1, :) + 1i * v(2, :)) / sqrt(2);
    in.da = @(a,z,r) -a + z(1,:)+1i*z(2,:);
    in.observe{1} = @(a, \sim, \sim) a.*conj(a);
    in.olabels = {'|a|^2'};
    in.compare = \{@(t, \sim) 1 + 0 * t\};
    in2 = in;
    in2.steps = 4;
    in2.origin = in.ranges;
    in2.name = 'Gain with noise';
    in2.da = @(a,z,r) a + z(1,:)+1i*z(2,:);
    in2.compare = \{@(t, \sim) 2*exp(2*(t-4))-1\};
    e = xspde(\{in, in2\});
```

Note that the code defines in2 = in before making any changes, so that only a few additional inputs are needed. The number of in.steps is increased to improve the accuracy of the second integration, and the second time origin is chosen so that it starts from the time the first simulation is completed.

Results are graphed below.

Comparison graphs are also produced for the relative errors. In the graph given here,




Fig. 4.18: Absorber intensity

4.7.2 Extended simulations

The second differential equation has an initial condition corresponding to the solution of the first equation at t=4, and the derivative:

$$\frac{da}{dt} = a + \zeta_1(t) + i\zeta_2(t)$$

The mean intensity grows exponentially:

$$\left\langle \left|a\right|^{2}\right\rangle =1.$$

$$\left\langle \left|a(t)\right|^{2}\right\rangle =2e^{2(t-4)}-1$$

$$where$$

$$w(t) = \int_0^t \zeta(t')dt'$$

To compare the calculated solution with this exact result, there are two *in.compare* functions in the project file. The time axis in the second graph has the origin reset to zero.




Fig. 4.19: Noisy amplifier intensity

Comparison graphs of the relative errors are also produced here as well.




Fig. 4.20: Noisy amplifier intensity errors, showing how the sampling errors increase in time.

Exercise

Reverse the order of gain and loss.

4.8 Characteristic

The next example is the characteristic equation for a traveling wave at constant velocity,

$$\frac{da}{dt} + \frac{da}{dx} = 0$$

Together with the initial condition that a(0, x) = sech(2x + 5), this has an exact solution that propagates at a constant velocity:

$$a(t,x) = sech(2(x-t) + 5)$$

The time evolution at x = 0 is simply:

$$a(t,0) = sech(2(t-5/2))$$

4.8.1 Characteristic inputs

The important parameters and functions in this case are:

```
function [e] = Characteristic()
    in.name = 'Characteristic'
    in.dimension = 2;
    in.initial = @(v,r) sech(2.*(r.x+2.5));
    in.da = @(a,z,r) 0*a;
    in.linear = @(r) -r.Dx;
    in.olabels = {'a_1(x)'};
    in.compare = {@(t,in) sech(2.*(t-2.5))};
    e = xspde(in);
end
```

The simulation program reports the following maximum errors:

```
- Max step error = 5.773160e-15
```

This is slightly misleading, since while the interaction picture is essentially exact, it is solving a finite lattice problem exactly. The transverse lattice discretization does introduce errors of course, and these are seen in the comparisons with the exact results:

```
- Maximum comparison differences = 7.581817e-03
```

Graphs of results are given below.

Exercise

Recalculate with the opposite velocity, and a new exact solution.




Fig. 4.21: Characteristic traveling wave versus space and time

4.8. Characteristic 49




Fig. 4.22: Characteristic errors at center

4.9 Equilibrium

We now move on to frequency space simulations. The equation is the same as the earlier loss equation, that is

$$\frac{da}{dt} = -a + \zeta(t)$$

where $\zeta(t) = \zeta_1(t) + i\zeta_2(t)$, with an initial condition of $a = (w_1 + iw_2)/\sqrt{2}$. For sufficiently long time-intervals, the solution is given by:

$$\tilde{a}\left(\omega\right) = \frac{\tilde{\zeta}(\omega)}{1 - i\omega}$$

The expectation value of the noise Fourier transform modulus squared, in the large T limit, is therefore:

$$\left\langle \left| \tilde{a}(\omega) \right|^2 \right\rangle = \frac{1}{2\pi \left(1 + \omega^2 \right)} \int \int e^{i\omega(t - t')} \left\langle \zeta(t) \zeta^*(t') \right\rangle dt dt'.$$

$$= \frac{T}{\pi \left(1 + \omega^2 \right)}$$

4.9.1 Program inputs

The full input file is given below.

```
function e = Equilibrium()
    in.name = 'Equilibrium spectrum';
    in.points = 640;
    in.ranges = 100;
    in.noises = [2,0];
    in.ensembles = [1000,10,1];
    in.initial = @(v,~) (v(1,:)+1i*v(2,:))/sqrt(2);
    in.da = @(a,z,r) -a + z(1,:)+1i*z(2,:);
    in.observe{1} = @(a,~) a.*conj(a);
    in.observe{2} = @(a,~) a.*conj(a);
    in.transforms = {0,1};
    in.olabels = {'|a(t)|^2', '|a(w)|^2'};
    in.compare = {@(t,~) 1.+0*t, @(w,~)100./(pi*(1+w.^2))};
    e = xspde(in);
end
```

Results are graphed below. The calculated spectrum is indistinguishable from the exact result.

The xsim program reports the following error summary:

```
- Max step error = 5.856892e-02
- Max sampling error = 4.234763e-01
- Maximum comparison differences = 6.194415e-01
```

Here, the comparison differences indicate that the maximum error reported is actually about 1.5 standard deviations of the maximum sampling error. Given the large number of data points, this is a reasonable result.

4.9. Equilibrium 51




Fig. 4.23: Equilibrium spectral intensity

Exercise

Add a second field coupled to the first, so that:

$$\frac{da}{dt} = -a + \zeta(t)$$
$$\frac{db}{dt} = -b + a$$

Compare the two spectra, and calculate what the second one should look like.

4.9. Equilibrium 53

LOGIC AND SEQUENCES

The simulation program logic is straightforward. It is a very compact function called xspde(). This calls xsim(), for the simulation, then xgraph() for the graphics. Most of the work is done by other specialized functions. Input parameters come from an input array, output is saved either in a data array, or else in a specified file. When completed, timing and error results are printed.

5.1 How it works

To summarize the previous chapters, xSPDE will solve stochastic partial different equations for a vector field a(t, x) and vector noise $\zeta(t, x)$, of form:

$$\frac{\partial}{\partial t} \boldsymbol{a}(t, \boldsymbol{x}) = \mathbf{A} \left[\boldsymbol{a} \right] + \underline{\mathbf{B}} \left[\boldsymbol{a} \right] \cdot \boldsymbol{\zeta}(t, \boldsymbol{x}) + \underline{\mathbf{L}} \left[\boldsymbol{\nabla} \right] \cdot \boldsymbol{a}$$

It can also solve ordinary stochastic equations, or partial differential equations without noise. Extensive error checking outputs are available. Both initial stochastic conditions and noise can have nonlocal spatial filters applied. All inputs are entered as part of an object-oriented structure. This includes the functions used to specify the equations and the quantities to average. The outputs can be either stored, or graphed interactively. xSPDE includes built-in multidimensional graphics tools.

5.1.1 Sequences

In many types of application, a sequence of stochastic equations requires simulation. In these cases the final field value after integration of one equation becomes the initial value of the next equation in the sequence.

Sequences therefore are the basic concept used in both the input of parameters to xSPDE, and the storage of data generated.

5.1.2 Input and data arrays

To explain xSPDE in full detail,

- Simulation inputs are stored in the input cell array.
- This describes a *sequence* of simulations, so that input = {in1, in2, ...}.
- Each structure in describes a simulation (see sec-input for details), whose output is the input of the next.
- The main function is called using data = xspde (input).
- Averages are recorded sequentially in the data cell array.
- Raw trajectory data is stored in the raw cell array if required.

The sequence input has a number of individual simulation objects in. Each includes parameters that specify the simulation, with functions that give the equations and observables. If there is only one simulation, just one individual specification in is needed. In addition, xSPDE generates graphs with its own graphics program.

5.1.3 Customization options

There are a wide range of customization options available for those who wish to have the very own xSPDE version.

Customization options include functions the allow user definition of:

- inputs
- · interfaces
- · stochastic equations
- · mean observables
- · linear propagators
- · coordinate grids
- · noise correlations
- · integration methods

There are four internal options for stochastic integration methods, but arbitrary user specification is also possible.

The program will print out a record of its progress, then generate the specified graphs.

5.2 Stochastic flowchart

The main program logic is nearly self-explanatory. It has four functions and two main arrays that store results.

There are also two important computational routines behind the scenes, which need to be kept in mind. These are in.da, which is short for difference in a. This is completely user specified, and gives a local step in time. The next workhorse routine is xprop(). This is not a beefy Rugby forward, but calculates spatial propagation.

The logical order is as follows:

xsim() decides the overall workflow, and parallel operation at a high level. Here, in.ensembles (3) is used to specify parallel integration, with a parfor loop. The random seeds include data from the loop index to make sure the noise is independent for each ensemble member, including parallel ensembles.

xinpreferences()

is called by xlattice () to set the defaults that are not already entered.

xlattice()

creates a space-time lattice from the input data, which is a data-structure. This also initializes the actual data array for averaging purposes. Next, a loop is initiated over an ensemble of fields for checking and ensemble averaging. The calculations inside the loop can all be carried our in parallel, if necessary. These internal steps are actually relatively simple.

xensemble()

repeats each stochastic path for the check/ensemble loop. It is important to notice that the random seed is reset at the start of each ensemble loop. The seed has a unique value that is different for each ensemble member. Note that for successive simulations that are **not** stored in the same data array, the seed should ideally be manually chosen differently for inputs to successive integration blocks, in order to guarantee independent noise sequences. The check variable can be set to in.errorchecks = 1, 2. This is the total number of integrations carried




Fig. 5.1: xSPDE flowchart, showing the data, lattice and field processing.

out. The integration is executed once with in.errorchecks = 1. With in.errorchecks = 2, there are two integrations, using half the step-size the second time. This takes three times as long overall. The matrices used to define the interaction picture transformations are stored **for each check loop**, as they vary with step-size.

xpath()

propagates the field a over a path in time. There are <code>in.steps</code> time-steps for each point stored in time, to allow for greater accuracy without excessive data storage, where needed. This integrates the equations for a predetermined time duration. Note that the random seed has the same value for both the check loops. This is because the same number of random variates must be generated in the same order to allow accurate extrapolation. The two loops must use the same random numbers, or else the check is not accurate. For random numbers generated during the integration, the coarse step will add two fine step random noises together, to achieve the goal of identical noise behavior. Results of any required averages, variances and checks are accumulated in the data array.

xprop()

uses Fourier space to calculate a step in the interaction picture, using linear transformations that are precalculated. There are both linear transformations and momentum dependent terms available. These are precalculated by the xlattice() function, and stored in the prop arrays.

5.2.1 Simulation user functions

in.initial

is used to initialize each integration in time. This is a user-defined function, which can involve random numbers if there is an initial probability distribution. This creates a stochastic field on the lattice, called a. Initialization functions can use coordinates, r.x, r.y, r.z, or for larger dimensions, using numerical lattice labels $r.x\{1\}$, $r.x\{2\}$, $r.x\{3\}$, $r.x\{4\}$. Numerical labels can be used for any number of dimension if the switch numberaxis=1. The default is xinitial(), which sets fields to zero.

in.step

is the algorithm or method computes each space-time point in the lattice. This also generates the random numbers fields at each time-step. It can be user-modified by setting the handle in.step.

in.observe{n}

is the n-th observation function whose output is averaged over the ensembles, called from xpath(). In general, this returns an array whose first coordinate is the line-number of the n-th graph. The default, xobserve(), returns the real amplitudes. The return value is averaged over the local ensemble and stored as data, $d\{n\}$. Note that the input of in.observe $\{n\}$ () is the complete field array.

in.function{n}

is used when a graph is needed that is a function of the observed averages. The default value is simply $d\{n\}$. This is further averaged over higher ensembles to obtain sampling error estimates. Note that the input of $in.function\{n\}$ () is the complete data cell array, d, which includes all the averages for all the graphs available.

in.linear

is the linear response, including transverse derivatives in space. The default, xlinear(), sets this to zero. Derivatives are specified using arrays r.Dx, r.Dy, r.Dz, or for larger dimensions, using numerical lattice labels r.D{2}, r.D{3}, r.D{4}, r.D{5}.

in.da

is called by in.step to calculate derivatives at every step in the process, including the stochastic terms.

Details of the different parts of the program are given below. Note that the functions tic() and toc() are called to time each simulation.

5.3 Graphics function, xgraph

At the end of the loop, global averages and error-bars are calculated. The main functions involved are:

xgraph() is called by xSPDE when the ensemble loops finished. The results are graphed and output if required.

xqpreferences()

is called by xgraph () to set the graphics defaults that are not already entered.

Comparison results are calculated if available from the user-specified in.compare, an error summary is printed, and the results plotted using the xgraph() routine, which is a function that graphs the observables. It is prewritten to cover a range of useful graphs, but can be modified to suit the user. The code is intended to cascade down from higher to lower dimension, generating different types of user-defined graphs. Each type of graph is generated once for each specified graphics function.

The code is intended to cascade down from higher to lower dimension, generating different types of user-defined graphs. Each type of graph is generated once for each specified graphics function. The graphics axes that are used for plotting, and the points plotted, are defined using the optional axes input parameters, where in.axes{n} indicates the n-th specified graphics function or set of generated graphical data.

If there are no axes inputs, or the inputs are zero - for example, in.axes{1} = {0,0,0}, then only the lowest dimensions are plotted, up to 3. If the axes inputs project out a single point in a given dimension, - for example, $axes{1}={0,31,-1,0}$, these axes are suppressed in the plots. This reduces the effective dimension of the data in this case to two dimensions.

Examples:

- axes $\{1\}$ = $\{0\}$ For function 1, plot all the time points; higher dimensions get defaults.
- axes $\{2\} = \{-1, 0\}$ For function 2, plot the maximum time (the default), and all x-points.
- axes {3}={1:4:51,32,64} For function 3, plot every 4-th time point at x point 32, y point 64
- axes $\{4\} = \{0, 1: 4: 51, 0\}$ For function 4, plot all time points, every 4-th x point, and all y-points.

Note that -1 indicates a default point, which is the last point on the time axis, and the midpoint on the other axes.

The pdimension input can also be used to reduce dimensionality, as this sets the maximum effective plotted dimension. For example, $pdimension\{1\}=1$ means that only plots vs time are output for the first function plotted. Note that in the following, t,x,y,z may be replaced by corresponding higher dimensions if there are axes that are suppressed. Slices can be taken at any desired point, not just the midpoint. Using the standard notation of, for example, $axes\{1\}=\{6:3:81\}$, can be used to modify the starting, interval, and finishing points for complete control on the plot points.

Results depend on the value of in.dimension, or else the effective graphics dimension if axes are suppressed:

- 4: for the highest space dimension, only a slice through z=0 is available. This is then graphed as if it was in three dimensions.
- 3: for two dimensions, distinct graphic images of observable vs x,y are plotted at in.images time slices. Otherwise, only a slice through y = 0 is available. This is then treated as if it was in two dimensions.
- 2: for two dimensions, one three-dimensional image of observable $vs \ x,t$ is plotted. Otherwise, only a slice through x=0 is available. This is otherwise treated as in one dimension.
- 1: for one dimensions, one image of observable *vs t* is plotted, with data at each lattice point in time. Exact results, error bars and sampling error bounds are included if available.

In addition to time-dependent graphs, the *xgraph()* function can generate *in.images* (3D) and *in.transverse* (2D) plots at specified points in time, up to a maximum given by the number of time points specified. The number of these can be individually specified for each graphics output. The images available are specified in *in.imagetype*: 3D perspective plots, grey-scale colour plots and contour plots.

5.3.1 Graphics user functions

in.gfunction

This is used when a graph is needed that is a function of the data coming from the simulation package, since this data can be analysed at a later time. Error estimates are less accurate when this function is used, due to error-propagation effects that may occur after averaging, unless corrected for explicitly in the graphics function.

in.xfunctions

This is used when a graph is needed whose axes are a function of the original axes.

in.compare

This is used when a two-dimensional graph is needed with a comparison line.

5.4 Error control

The final 2D output graphs will have error-bars if <code>in.errorchecks</code> is set to 2, which is also the default parameter setting. This is to make sure the final results are accurate. Error-bars below a minimum relative size compared to the vertical range of the plot, specified by the graphics variable <code>in.minbar</code>, are not plotted. There is a clear strategy if the errors are too large.

Either increase the *in.points*, which gives more plotted points and lower errors, or increase the *in.steps*, which reduces the step size without changing the graphical resolution. The default algorithm and extrapolation order can be changed, read the xSPDE manual when doing this. Error bars on the graphs can be removed by setting <code>in.errorchecks = 1</code> or increasing <code>in.minbar</code> in final graphs.

If in.ensembles(2) > 1 or in.ensembles(3) > 1, which allows xSPDE to calculate sampling errors, it will plot upper and lower limits of one standard deviation. If the sampling errors are too large, try increasing in.ensembles(1), which increases the trajectories in a single thread. An alternative is to increase in.ensembles(2). This is slower, but is only limited by the compute time, or else to increase in.ensembles(3), which gives higher level parallelization. Each is limited in different ways; the first by memory, and the second by time, the third by the number of available cores. Sampling error control helps ensures accuracy.

Note that error bars and sampling errors are only graphed for 2D graphs of results vs time. The error-bars are not plotted when they are below a user-specified size, to improve graphics quality. Higher dimensional graphs do not include this, for visibility reasons, but they are still recorded in the data files. Errors caused by the spatial lattice are not checked automatically in the xSPDE code. They must be checked by manually, by comparing results with different transverse lattice ranges and step-size.

DATA AND ARRAYS

The xSPDE data and arrays that are user accessible are parameters r, fields a, average observables data, and raw trajectories raw. Apart from the parameters, which are Matlab structures, all fields and data are arrays. There is a unified index ordering of:

- 1. field index
- 2. ensemble or error index
- 3. time index
- 4. space index 1
- 5. space index 2
- 6. space index 3 ..

The number of space coordinates is arbitrary. However, to conserve storage, time dimensions are reduced to a single, current, index for propagating fields. The ensemble index can be adjusted to increase or decrease local memory usage. If needed, all data can be stored in 'raw' arrays.

The fields a are complex arrays stored discretely on spatial or momentum grids. Internally, the fields are matrices stored on the flattened xSPDE internal lattice. This combines a local ensemble and a spatial grid. Temporary transformations to the Fourier domain are used for calculating interaction picture propagation [Caradoc-Davies2000] and averages over Fourier space.

Two different types of Fourier representations are used. In xsim, Fourier transformations are for propagation, which requires the fastest possible methods, and uses k=0 as the first or lowest index. In xgraph, Fourier transformations are for graphical representations. Hence, the indices are re-ordered to a conventional index ordering, with negative momentum values in the first index position.

The parameters are stored in a structure called, simply, r. It is available to all user-definable routines. The label r is chosen because the parameters include the grid coordinates in space and time. These structures reside in a static internal cell array that combines both input and lattice parameters, including the interaction picture transformations, called latt. The data in latt is different for each simulation in a sequence.

Averaged results are called observables in xSPDE. For each sequence, these are stored in either space or Fourier domains, in the array data, as determined by the *in.transforms* vector for each observable. This is a vector of switches for each of the space-time coordinates. The data arrays obtained in the program as calculations progress are stored in cell arrays, cdata, indexed by a sequence index.

If required, raw ensemble data consisting of all the trajectories a developing in time can be stored and output. This is memory intensive, and is only done if the in.raw option is set to 1.

In summary, all calculated data, including fields, observables and graphics results, is stored in arrays of implicit or explicit rank (2+d), where d is the space-time dimension given in the input. The first index is a field index (i), the second a statistics/errors index (j), while the remaining indices $k \equiv k_1, \dots k_d \equiv k_1, \mathbf{k}$ are for time and space.

The space-time dimension d is unlimited. When the fields, noises or coordinates are integrated by the xSPDE integration functions, they are flattened to a matrix. The first index is the field index, and the combined second index covers all the rest.

There are several different types of arrays used. These are as follows:

- Field arrays, $a(i, j, 1, \mathbf{k})$ these have a statistics index of up to j = ensembles(1), but just a single, i.e., present time-point for efficiency.
- Random and noise arrays, $w(i, j, 1, \mathbf{k})$ these are like field arrays, except that they contain random numbers for the stochastic equations.
- Coordinate arrays $x\{l\}(1, j, 1, \mathbf{k})$ these store the values of coordinates at grid-points, depending on the axis label $l=2,\ldots d$.
- Raw arrays, $r\{e,s\}(i,j,k)$ like fields, but with all points stored. Use with care, as they take up large amounts of memory. Note that when output or saved, these have additional cell indices e=1,2 for the error-checking time-step and $s=1,\ldots S$ for the sequence number.
- Data arrays, $d\{n\}(i, j, k)$ these store the averages, or arbitrary functions of them, with a statistics index j = 1, 2, 3, to store error data at all time points.
- Graphics arrays, $g\{n\}(i,j,k)$ these store the data that is plotted, and can include further functional transformations if required.

The field index i in a graphics or data array is intended to describe different lines on a graph. There can be quite different first dimensions between fields, noises and output data, as they are specified using different input parameters. If only a single output graph is wanted, the observe cell index is not needed.

Outputs have an extra high-level cell index $\{n\}$ called the graph or function index. This corresponds to the index $\{n\}$ of the observe function used to generate averages. One can have several data arrays in a larger cell arrays to make a number of distinct output graphs labelled n, each with multiple averages.

More details of ensembles, grids and the internal lattice are given below. Note that the term lattice is used to refer to the total internal field storage. This combines the local ensemble and the spatial grid together.

6.1 Ensembles

Ensembles are used for averaging over stochastic trajectories. They come in three layers: local, serial and parallel, in order to optimize simulations for memory and for parallel operations. The in.ensembles (1) local trajectories are used for array-based parallel ensemble averaging. These trajectories are stored in one array, to allow fast on-chip parallel processing. Distinct stochastic trajectories are also organized at a higher level into a set of in.ensembles (2) serial ensembles for statistical purposes, which allows a more precise estimate of sampling error bars. For greater speed, these can be integrated using in.ensembles (3) parallel threads.

This hierarchical organization allows allows flexibility in allocating memory and optimizing parallel processing. It is usually faster to have larger values of in.ensembles(1), but more memory intensive. Using larger values of in.ensembles(2) is slower, but requires less memory. Using larger values of in.ensembles(3) is fast, but requires the Matlab parallel toolbox, and uses both threads and memory resources. It is generally not effective to increase in.ensembles(3) above the maximum number of available computational cores.

In summary, the ensembles are defined as follows:

6.1.1 Local ensemble

The first or local ensemble contains ensembles (1) trajectories stored on the xSPDE internal lattice and processed using vector or matrix operations.

6.1.2 Serial ensemble

The second or serial ensemble contains ensembles (2) of the local ensembles, processed in a sequence to conserve memory.

6.1.3 Parallel ensemble

The third or parallel ensemble contains ensembles (3) of the serial ensembles processed in parallel using different threads to allow multi-core and multi-CPU parallel operations.

6.2 Grids in x and k

The xSPDE space and momentum grid can have any dimension, provided there is enough memory. Using more than six to ten total dimensions causes large time requirements and is not very practical.

The xSPDE algorithms all use a sequence of interaction pictures. Each successive interaction picture is referenced to $t=t_n$, for the n-th step starting at $t=t_n$, so $a_I(t_n)=a(t_n)\equiv a_n$. It is possible to solve stochastic partial differential equations in xSPDE using explicit derivatives, but this is generally less efficient. To understand spatial discretization and the interaction picture, we first must understand the xSPDE spatial grids.

6.2.1 Space grid

We define the grid cell size dx_j in the j-th dimension in terms of maximum range R_j and the number of points N_j :

$$dx_j = \frac{R_j}{N_j - 1}.$$

Each grid starts at a value defined by the vector in origin. Using the default values, the time grid starts at t=0 and ends at $t=T=r_1$, for $n=1,\ldots N_j$:

$$t\left(n\right) = (n-1)dt.$$

The j-th coordinate grid starts at $-r_j/2$ and ends at $r_j/2$, so that, for $n=1,\ldots N_j$:

$$x_{i}(n) = -R_{i}/2 + (n-1)dx_{i}.$$

6.2.2 Momentum grid

The momentum space graphs use a Fourier transform definition so that, for d dimensions:

$$\tilde{\boldsymbol{a}}(\boldsymbol{k},\omega) = \frac{1}{\left(2\pi\right)^{d/2}} \int d\boldsymbol{x} e^{i(\omega t - \boldsymbol{k} \cdot \boldsymbol{x})} \boldsymbol{a}(\boldsymbol{x},t)$$

In order to match this to the standard definition of a discrete FFT, the j-th momentum lattice cell size dk_j in the j-th dimension is defined in terms of the number of points N_j :

$$dk_j = \frac{2\pi}{dx_i N_i}.$$

The momentum range is therefore

$$K_i = (N_i - 1) dk_i,$$

6.2. Grids in x and k

while the momentum lattice starts at $-k_i/2$ and ends at $k_i/2$, so that when graphing the data:

$$k_i(n) = -K_i/2 + (N_i - 1)dk_i$$
.

However, due to the standard definitions of discrete Fourier transforms, the order used during computation and stored in the data arrays is different, namely:

$$k_i(n) = 0..(N_i - 1)/2)dk_i, -(N_i - 1)/2)dk_i, -dk_i$$

6.3 Computational Fourier transforms

A conventional fast Fourier transform (FFT) is used for the interaction picture (IP) transformations used in computations, as this is fast and simple. In one dimension, this is given by a sum over indices starting with zero, rather than the Matlab convention of one. Hence, if $\tilde{m} = m - 1$:

$$\tilde{a}_{\tilde{n}} = \mathcal{F}(a) = \sum_{\tilde{m}=0}^{N-1} a_{\tilde{m}} \exp\left[-2\pi i \tilde{m} \tilde{n}/N\right]$$

Suppose the spatial grid spacing is dx, and the number of grid points is N, then the maximum range from the first to last point is:

$$R = (N-1)dx$$

We note that the momentum grid spacing is

$$dk = \frac{2\pi}{Ndx}$$

The IP Fourier transform can be written in terms of an FFT as

$$\tilde{\boldsymbol{a}}\left(\boldsymbol{k_n}\right) = \prod_{j} \left[\sum_{\tilde{m}_j} \exp\left[-i\left(dk_j dx_j\right) \tilde{m}_j \tilde{n}_j\right] \right]$$

The inverse FFT Fourier transforms automatically divide by the correct factors of $\prod_j N_j$ to ensure invertibility. Note also that due to the periodicity of the exponential function, negative momenta are obtained if we consider an ordered lattice such that:

$$k_j = (j-1)dk \ (j \le N/2)$$

 $k_j = (j-1-N)dk \ (j > N/2)$

For calculating derivatives and propagating in the interaction picture, the notation D indicates a derivative. To explain, one integrates by parts:

$$D^{p}\tilde{\boldsymbol{a}}\left(\boldsymbol{k}\right)=\left[ik_{x}\right]^{p}\tilde{\boldsymbol{a}}\left(\boldsymbol{k}\right)=\frac{1}{\left(2\pi\right)^{d/2}}\int d\boldsymbol{x}e^{-i\boldsymbol{k}\cdot\boldsymbol{x}}\left[\frac{\partial}{\partial x}\right]^{p}\boldsymbol{a}\left(\boldsymbol{x}\right)$$

This means, for example, that to calculate a one dimensional space derivative in the Linear routine, one uses:

•
$$\nabla_x
ightarrow { t r.Dx}$$

Here r.Dx returns an array of momenta in cyclic order in dimension d as defined above, suitable for an FFT calculation. The imaginary i is not needed to give the correct sign, from the equation above. Instead, it is included in the D array. In two dimensions, the code to return a full two-dimensional Laplacian is:

•
$${\bf \nabla}^2=\nabla_x^2+\nabla_y^2
ightarrow {\rm r.Dx.^2+r.Dy.^2}$$

Note that the dot in the notation of . ^ is needed to take the square of each element in the array.

6.4 Graphics transforms

All transforms defined in the observables are obtained from a cell array of vectors called *in.transforms*, which determines if a given coordinate axis is transformed prior to a given observable being measured. This can be turned on and off independently for each observable and axis. The coordinate axes are specified in the order of t, x, y, z, ...

The index ordering and normalization used in the standard discrete FFT approach is efficient for interaction picture propagation, but not useful for graphing, since graphics routines prefer the momenta to be monotonic, i.e. in the order:

$$k_j(n) = -K_j/2 + (n-1)dk_j$$
.

Accordingly, all momentum indices for observable data and axes are re-ordered when graphing, although they are initially stored in the computational order.

6.5 Fields

In the xSPDE code, the complex vector field a is genrally stored as a compressed or flattened matrix with dimensions [fields, lattice]. Here lattice is the total number of lattice points including an ensemble dimension, to increase computational efficiency:

```
lattice = in.ensembles(1) * r.nspace
```

The total number of space points r.nspace is given by:

```
r.nspace = in.points(2) * ... * in.points(in.dimension)
```

The use of a matrix for the fields is convenient in that fast matrix operations are possible in a high-level language.

In different subroutines it may be necessary to expand out this array to more easily reference the array structure. The expanded field structure a is as follows

```
[in.fields, in.ensembles(1), 1, in.points(2), ..., in.points(dimension)]
```

Note: Here, <code>in.fields</code> is the number of field components and <code>in.ensembles(1)</code> is the number of statistical samples processed as a parallel vector. This can be set to one to save data space, or increased to improve parallel efficiency. Provided no frequency information is needed, the time dimension <code>in.points(1)</code> is compressed to one during calculations. During spectral calculations, the full length of the time lattice, <code>in.points(1)</code>, is stored, which increases memory requirements.

latt

This includes a propagation array r.propagator, used in the interaction picture calculations. There are two momentum space propagators, for coarse and fine steps respectively, which are computed when they are needed.

6.6 Data

6.6.1 Observables: data

During the calculation, observables are calculated and averaged over the ensembles (1) parallel trajectories in the xpath() function. These are determined by the functions in the in.observe cell array.

The number of in.observe functions may be smaller or larger than the number of vector fields. The observable may be a scalar or vector. These include the averages over the ensembles, and can be visualized as a single graph with one or more lines.

Next, arbitrary functional transforms can be taken, using the <code>in.function</code> cell array. These functions can use as their input any of the <code>in.observe</code> output data arrays. They default to the original <code>in.observe</code> data if they are not user-defined. The results are added to the earlier results in the array <code>data</code>, to create graphs for each function. At this stage, both the first and second moment is stored, in order to allow calculation of the sampling error in each quantity. These are averaged over the higher level ensembles, to allow estimates of sampling errors.

Functional transforms are most useful if one wishes to use functions which require knowledge of normalization or ensemble averages of lower-level data.

Each resulting graph or average data is each stored in an array of size

```
[components, errors, in.points(1), in.points(2), ..., in.points(dimension)]
```

In the simplest case, there is just one vector component per average. More generally, the number of components is larger than this if there is a requirement to compare different results in one graph. Note that, unlike the propagating field, the time dimension is fully expanded. This is necessary in order to generate outputs at each of the in.points(1) time slices.

When step-size checking is turned on using the *in.errorchecks* flag set to 2, a low resolution field is stored for comparison with a high-resolution field of half the step-size, to obtain the time-step error.

The observables which are stored have three error indices which are all included in the array. These are the high resolution means, together with error-bars due to time-steps, and estimates of high-resolution standard deviations due to sampling statistics.

The observable data which is plotted automatically includes step-size error bars and plotted lines for the two estimated upper and lower standard deviations, obtained from the statistical moments.

In summary, after ensemble averaging, the second index is errors = 1, 2, 3, which is used to index over the

- 1. mean value,
- 2. time-step error-bars and
- 3. sampling errors

respectively for each space-time point and each graphed function.

Data from each simulation in a sequence is packed into successive cells of an overall cell array cdata. This is used to store the total data in a sequence of simulations.

All these fields are resident in memory. They can be re-accessed and replotted, using the xgraph() function, if required. In summary:

cdata

Cell Array, has dimension: cdata{sequence}{graph}.

observable or function

```
Array, has dimension: (components, errors, in.points(1), ...
in.points(in.dimension)).
```

The cell index enumerates first the sequence number and then the graph number. The second array index (1, 2, 3) give the error-checking status of the data. If there is no error-bar checking, the second data array is zero. If there is no sampling error checking, the third data array is zero.

6.7 Graphics Data

6.7.1 Observables: data

During the calculation, observables are calculated and averaged over the ensembles (1) parallel trajectories in the xpath () function. The results are added to the earlier results in the array data, to create graphs for each observable. At this stage, both the first and second moment is stored, in order to allow calculation of the sampling error in each quantity.

There are *in.graphs* real observables, which are typically determined by the number of functions defined in the *in.observe* cell array, unless there are further definitions of functional transformations. The number of *in.graphs* may be smaller or larger than the number of vector fields. The observable field includes all the necessary averages over the ensembles.

6.8 Raw data

If required, xSPDE can store every trajectory generated.

This raw data is stored in a cell array raw. The array is written to disk using the Matlab file-name, on completion, provided a file name is input.

The cell indices are: sequence index, error-checking index, ensemble index.

raw

```
Cell Array, has dimension: raw{seq, errcheck, in.ensemble(2) *in.ensemble(3)}
```

If thread-level parallel processing is used, these are also stored in the cell array, which is indexed over both the parallel and serial ensemble. Inside each raw cell is at least one complete space-time field stored as a complex array, with indices for the field index, the samples, the time index and the space lattice.

The sample-time-space trajectory in xSPDE is a real or complex array with (in.dimension+2) indices:

field

```
Array, has dimension: (in.fields, in.ensemble(1), in.points)
```

The main utility of raw data is for storing data-sets from large simulations for later re-analysis. It is also a platform for further development of analytic tools for third party developers, to treat statistical features not included in the functional tools provided. For example, one might need to plot histograms of distributions from this.

6.7. Graphics Data 67

ALGORITHMS

Stochastic, partial and ordinary differential equations are central to numerical mathematics. Certainly, ordinary differential equations have been known in some form ever since calculus was invented. There are a truly extraordinary number of algorithms used to solve these equations. One program cannot possibly provide all of them.

xSPDE currently provides four built-in choices of algorithm. All built-in methods are defined in an interaction picture. All can be used with any space dimension, including in.dimension = 1, which gives an ordinary stochastic equation. All can be used either with stochastic or with non-stochastic equations. When applied to stochastic equations, the Euler method requires an Ito form of stochastic equation, while the others should be used with the Stratonovich form of these equations. Each uses the interaction picture to take care of exactly soluble linear terms.

If you have a favorite integration method that isn't here, don't panic. User-defined algorithms can be added freely. You can easily add your own. The existing methods are listed below, and the corresponding .m-files can be used as a model. Call the routine, for example "myalgorithm.m", set in.step = @myalgorithm, then adjust the value of in.ipsteps if the interaction-picture transform length must be changed to a new value.

Similarly, the interaction-picture transformation, *in.prop*, can also be changed if the built-in choice is not adequate for your needs.

7.1 Notation

The general equation treated here is given in differential form as

$$rac{\partial oldsymbol{a}}{\partial t} = oldsymbol{A} \left[oldsymbol{a}, t
ight] + \mathbf{\underline{B}} \left[oldsymbol{a}, t
ight] \cdot oldsymbol{\zeta}(t) + \mathbf{\underline{L}} \left[oldsymbol{
abla}
ight] \cdot oldsymbol{a}.$$

It is convenient for the purposes of describing interaction picture methods, to introduce an abbreviated notation as:

$$\mathcal{D}\left[\mathbf{a},t\right] = \mathbf{A}\left[\mathbf{a},t\right] + \mathbf{\underline{B}}\left[\mathbf{a},t\right] \cdot \boldsymbol{\zeta}(t).$$

Hence, we can rewrite the differential equation in the form:

$$\frac{\partial \boldsymbol{a}}{\partial t} = \mathcal{D}\left[\mathbf{a}, t\right] + \underline{\mathbf{L}}\left[\boldsymbol{\nabla}\right] \cdot \boldsymbol{a}.$$

Next, we define a linear propagator. This is given formally by:

$$\mathcal{P}\left(\Delta t\right) = \exp\left(\Delta t \underline{\mathbf{L}}\left[\mathbf{\nabla}\right]\right)$$

Typically, but not necessarily, this is evaluated in Fourier space, where it should be just a diagonal term in the momentum vector conjugate to the transverse space coordinate. It will then involve a Fourier transform, multiplication by an appropriate function of the momentum, and then an inverse Fourier transform afterwards.

7.2 xSPDE algorithms

The four built-in algorithms provided are:

xEuler()

The first-order Euler method, a simple first-order explicit approach.

xRK2()

A second order Runge-Kutta method.

xMP()

The midpoint method: a semi-implicit, second order algorithm.

xRK4()

A fourth order Runge-Kutta method, which is a popular ODE solver.

For simplicity, the stochastic noise is assumed constant throughout the interval dt. The reader is referred to the literature ([Drummond1991], [Kloeden1995], [Werner1997], [Higham2001]) for more details.

However, a word of caution is in order. For stochastic equations, which are non-differentiable, the classifications of convergence order should be taken *cum grano salis*. In other words, don't believe it. Stochastic convergence is a complex issue, and the usual rules of calculus don't apply. This is because stochastic noise is non-differentiable. It has relative fluctuations proportional to $1/\sqrt{dt dV}$, for noise defined on a lattice with temporal cell-size dt and spatial cell-size dV. Hence the usual differentiability and smoothness properties required to give high-order convergence for standard Runge-Kutta methods are simply not present.

Higher order, more complex algorithms for stochastic integration do exist, but they are not included in the current xSPDE distribution. The reason for this is simply that stochastic integration errors are often dominated by the sampling error, which makes the practical advantage of using high-order algorithms less significant in most calculations.

All is not completely lost however, since xSPDE will attempt to estimate both the step-size and the sampling error, so you can check convergence yourself.

7.3 Euler

This is an explicit Ito-Euler method using an interaction picture. While very traditional, it is not generally recommended except for testing purposes. If it is used, very small step-sizes will generally be necessary to reduce errors to a usable level.

This is because it is is only convergent to first order, and therefore tends to have large errors. It is designed for use with an Ito form of stochastic equation. It requires one IP transform per step (in.ipsteps = 1). Starting from time $t = t_n$, to get the next time point at $t = t_{n+1} = t_n + \Delta t$, one calculates:

$$\Delta \mathbf{a}_n = \Delta t \mathcal{D} \left[\mathbf{a}_n, t_n \right]$$

$$\mathbf{a}_{n+1} = \mathcal{P} \left(\Delta t \right) \cdot \left[\mathbf{a}_n + \Delta \mathbf{a}_n \right]$$

7.4 Second order Runge-Kutta

This is a second order Runge-Kutta method using an interaction picture [Caradoc-Davies2000]. It is convergent to second order in time for non-stochastic equations, but for stochastic equations it can be more slowly convergent than the midpoint method. It requires two IP transforms per step, but each is a full time-step long (in.ipsteps = 1).

To get the next time point, one calculates:

$$\bar{\mathbf{a}} = \mathcal{P}(\Delta t) \cdot [\mathbf{a}_n]$$

$$\mathbf{d}^{(1)} = \Delta t \mathcal{P}(\Delta t) \cdot \mathcal{D}[\mathbf{a}_n, t_n]$$

$$\mathbf{d}^{(2)} = \Delta t \mathcal{D}\left[\bar{\mathbf{a}} + \mathbf{d}^{(1)}, t_{n+1}\right]$$

$$\mathbf{a}_{n+1} = \bar{\mathbf{a}} + \left(\mathbf{d}^{(1)} + \mathbf{d}^{(2)}\right)/2$$

7.5 Midpoint

This is an implicit midpoint method using an interaction picture. It gives good results for stochastic [Drummond1991] and stochastic partial differential equations [Werner1997]. While it is only convergent to second order in time for non-stochastic equations, it is strongly convergent and robust. It requires two half-length IP transforms per step (in.ipsteps = 2).

To get the next time point, one calculates a midpoint derivative iteratively at time to get the next time point at $t = t_{n+1/2} = t_n + \Delta t/2$, to give an estimated midpoint field $\bar{\mathbf{a}}^{(i)}$, usually with three iterations:

$$\begin{split} &\bar{\mathbf{a}}^{(0)} = \mathcal{P}\left(\frac{\Delta t}{2}\right) \cdot \left[\mathbf{a}_n\right] \\ &\bar{\mathbf{a}}^{(i)} = \bar{\mathbf{a}}^{(0)} + \frac{\Delta t}{2} \mathcal{D}\left[\bar{\mathbf{a}}^{(i-1)}, t_{n+1/2}\right] \\ &\mathbf{a}_{n+1} = \mathcal{P}\left(\frac{\Delta t}{2}\right) \cdot \left[2\bar{\mathbf{a}}^{(i)} - \bar{\mathbf{a}}^{(0)}\right] \end{split}$$

7.6 Fourth order Runge-Kutta

This is a fourth order Runge-Kutta method using an interaction picture [Caradoc-Davies2000]. It is convergent to fourth order in time for non-stochastic equations, but for stochastic equations it can be more slowly convergent than the midpoint method. It requires four half-length IP transforms per step (in.ipsteps = 2). To get the next time point, one calculates four derivatives sequentially:

$$\begin{split} \bar{\mathbf{a}} &= \mathcal{P}\left(\frac{\Delta t}{2}\right) \cdot [\mathbf{a}_n] \\ \mathbf{d}^{(1)} &= \frac{\Delta t}{2} \mathcal{P}\left(\frac{\Delta t}{2}\right) \cdot \mathcal{D}\left[\mathbf{a}_n, t_n\right] \\ \mathbf{d}^{(2)} &= \frac{\Delta t}{2} \mathcal{D}\left[\bar{\mathbf{a}} + \mathbf{d}^{(1)}, t_{n+1/2}\right] \\ \mathbf{d}^{(3)} &= \frac{\Delta t}{2} \mathcal{D}\left[\bar{\mathbf{a}} + \mathbf{d}^{(2)}, t_{n+1/2}\right] \\ \mathbf{d}^{(4)} &= \frac{\Delta t}{2} \mathcal{D}\left[\mathcal{P}\left(\frac{\Delta t}{2}\right) \left[\bar{\mathbf{a}} + 2\mathbf{d}^{(3)}, t_{n+1}\right]\right] \\ \mathbf{a}_{n+1} &= \mathcal{P}\left(\frac{\Delta t}{2}\right) \cdot \left[\bar{\mathbf{a}} + \left(\mathbf{d}^{(1)} + 2\left(\mathbf{d}^{(2)} + \mathbf{d}^{(3)}\right)\right)/3\right] + \mathbf{d}^{(4)}/3 \end{split}$$

This might seem like the obvious choice, having the highest order. However, it can actually converge at a range of apparent rates, depending on the relative importance of stochastic and non-stochastic terms. Due to its reliance on differentiability, it may converge more slowly than the midpoint method with stochastic terms present.

The actual error is best judged by measuring it, as explained next.

7.5. Midpoint 71

7.7 Convergence checks

To check convergence, xSPDE repeats the calculations at least twice for checking step-sizes, and many times more in stochastic cases. *If you think this is too boring and slow, turn it off.* However, you won't know your errors!

Whatever the application, you will find the error-estimates useful. If the errors are too large, and this is relative to the application, you should decrease the time-steps or increase the number of samples. Which to do entirely depends on the type of error. In xSPDE, the step-size error due to finite time-step sizes is called the "step" error. The sampling error due to finite samples of trajectories is called the "sample" error. The maximum value of each of these, calculated over the set of all computed observables, is printed out at the end of the run.

Where there is 2D graphical output, the error bars give the step-size error, if you have in.check = 2. To distinguish the error types, two lines are graphed for an upper and lower standard deviation departure from the mean, indicating the sampling error. This is only plotted if the total number of ensembles is greater than one, preferably at least 10–20 to give reliable estimates.

Note that the sample error is usually reasonably accurate. It occasionally may underestimate errors for pathological distributions. The step error is generally the more cautious of the two, and tends to overestimate errors. Neither should be relied as more than a rough guide.

As a check, the code allows users to graph a defined 2D exact result, if known, for comparison and testing purposes. These are graphed using dashed lines. This facility can be turned on or off for each observable using Boolean variables. This can be useful even if no exact result is known, but there is a known conservation law.

In summary, there are three types of convergence checks, all of which appear in the output as printed maximum values and projected two-dimensional graphs:

- Error bars indicate the error due to finite step-size
- Upper and lower solid lines indicate the $\pm \sigma$ sampling error bounds
- Dashed lines indicate comparison values, which are useful when there are exact results for testing

7.8 Extrapolation order and error bars

For checking step-size errors, xSPDE allows the user to specify in.errorchecks = 2, which is the default option. This gives one integration at the specified step-size, and one at half the specified step-size. The data is plotted at the fine step-size. The standard error-bar, with no extrapolation, has a half-size equal to the difference of fine and coarse step graphed results.

To allow for extrapolation, xSPDE allows user input of an assumed extrapolation order called *in.order*. If this is done, and errorchecks are set to 2 to allow successive integration with two different step-sizes, the output of all data graphed will be extrapolated to the specified order. In this case, the error bar half-size is set to the difference of the fine estimate and the *extrapolated* estimate.

Extrapolation is a well-known technique for improving the accuracy of a differential equation solver. Suppose an algorithm has a result with a known convergence order n. This means that for small enough step-size, integration results R(dt) with step-size dt have an error of size dt^n , that is:

$$R(dt) = R_0 + E(dt) = R_0 + k.dt^n$$
.

Hence, from two results at different values of dt, differing by a factor of 2, one would obtain

$$R_1 = R(dt) = R_0 + k.dt^n$$

 $R_2 = R(2dt) = R_0 + 2^n k.dt^n$.

The true result, extrapolated to the small-step size limit, is therefore given by giving more weight to the fine step-size result, while *subtracting* from this a correction due to the coarse step-size calculation:

$$R_0 = \frac{[R_1 - R_2 2^{-n}]}{[1 - 2^{-n}]}.$$

Thus, for example, if we define a factor ϵ as

$$\epsilon(n) = \frac{1}{[2^n - 1]} = \left(1, \frac{1}{3}, \frac{1}{7} \dots\right),$$

then the true results are obtained from extrapolation to zero step-size as:

$$R_0 = (1 + \epsilon) R_1 - \epsilon R_2.$$

The built-in algorithms have convergence order as ordinary differential equation integrators of 1, 2, 2, 4 respectively, and should converge to this order at small step-sizes.

However, the situation is not as straightforward for stochastic equations. First order convergence is always obtainable stochastically. In addition, second order convergence is generally obtainable with the midpoint algorithm, although this is not guaranteed: it depends on the precise noise term. However, the Runge-Kutta algorithms used do **not** converge to the standard ODE order for stochastic equations. Hence extrapolation should be used with extreme caution in stochastic calculations.

While extrapolated results are usually inside those given by the default error-bars, **extrapolation with too high an order can under-estimate the resulting error bars.** Therefore, xSPDE assumes a cautious default order of in.order = 1. Note that one can set in.order = 0 to obtain fine resolution values and error bars without extrapolation, but this is generally less accurate.

7.9 Sampling errors

Sampling error estimation in xSPDE uses sub-ensemble averaging. Ensembles are specified in three levels. The first, in.ensemble(1), is called the number of samples for brevity. All computed quantities returned by the in.observe functions are first averaged over the samples, which are calculated efficiently using a parallel vector of trajectories. By the central limit theorem, these sample averages are distributed as a normal distribution at large sample number.

Next, the sample averages are averaged **again** over the two higher level ensembles, if specified. This time, the variance is accumulated. The variance of these distributions is used to estimate a standard deviation in the mean, since each computed quantity is now a normally distributed result. This method is applied to all the *in.graphs* observables. The two lines generated represent $\bar{o} \pm \sigma$, where o is the observe function output, and σ is the standard deviation in the mean.

The highest level ensemble, in.ensemble (3), is used for parallel simulations. This requires the Matlab parallel toolbox. Either type of high-level ensemble, or both together, can be used to calculate sampling errors.

Note that one standard deviation is not a strong bound; errors are expected to exceed this value in 32% of observed measurements. Another point to remember is that stochastic errors are often correlated, so that a group of points may all have similar errors due to statistical sampling.

EIGHT

PUBLIC API

8.1 High-level xSPDE functions and objects

The high-level xSPDE functions process the input parameters, producing simulation data and graphs. Function parameters are in the order of input, which specifies the simulation, then data, which is needed for graphics output.

xspde (input)

This is the combined xSPDE function. It accepts a simulation sequence, input. This can be a single structure, in, or else a cell array of structures, $\{in1,in2,...\}$, for sequences. Output graphs are displayed. It returns the output [error, input, data,raw], where error is the sum of simulation errors in xsim(), and difference errors found in the xgraph() comparisons. If a filename is specified in the input, it writes an output data file including input and all output data. Raw data is stored on request. It calls the functions xsim() and xgraph().

xsim(input)

This is the xSPDE simulation function. Like xspde(), it accepts input parameters in input. It returns [maxerror, input, data, raw], where: maxerror is the sum of maximum step-size and maximum sampling errors, input is the full input structure or cell array for sequences, including default values, and data is a cell array of average observables. If the in.raw option is used, data for the actual trajectories is output in raw. This can be run as a stand-alone function if no graphs are required.

xgraph (data, input)

This is the xSPDE graphics function. It takes computed simulation data and input. It plots graphs, and returns the maximum difference diff from comparisons with user-specified comparison functions. The data should have as many cells as input cells, for sequences. If data = 'filename.h5' or data='filename.mat', the specified file is read both for input and data. Here .h5 indicates an HDF5 file, and .mat indicates a Matlab file. When the 'data' input is given as a filename, input parameters in the file are replaced by any of the the new input parameters that are specified. Any stored input can be overwritten, allowing graphs to be modified retrospectively. If the input is not present, a file-name must be specified in the data field.

8.1.1 Open object-oriented architecture

As well as extensibility through sequences, which was described in *Averaging and projects*, in the section *Sequential integration*, the architecture of xSPDE allows functional extensions.

The input metadata includes both data and methods acting on the data, in the tradition of object-oriented programs. Yet there is no strict class typing. Users are encouraged to adapt the xSPDE program by adding input parameters and methods to the input structures.

 $Such \ unorthodox \ object \ orientation \ is \ deliberate.$

This open extensibility permits arbitrary functions to be specified in the in structures. All functions and parameters have default values in xSPDE. It is also possible to include user defined functions, provided they satisfy the API definitions given below. This is achieved simply by including the relevant function handles and parameters in the input metadata.

Internal parameters and function handles from the in structures, together with any computed and default parameters and functions, are stored in the lattice structure r. These are available to all user-defined functions. Use of pre-existing reserved names is not advisable, and the structure $r \cdot c$ is always reserved for user constants, parameters and functions if required.

The xSPDE software architecture is intended to be easily extended, and users are strongly encouraged to develop their own libraries and contribute to the xSPDE function pool. Because this generally requires new functions and parameters, the internal data architecture is as open as possible.

For example, to define your own integration function, include in the xSPDE input the line:

```
in.step = @Mystep;
```

Next, include anywhere on your Matlab path, the function definition, for example:

8.2 Averages, integrals and derivatives

There are functions available in xSPDE for averages, integrals and derivatives. These can be used to calculate observables for plotting, but are also available for calculating stochastic derivatives as part of the stochastic equation. They operate in parallel over the local ensemble and lattice dimensions. They take a scalar quantity, for example a single field component, and return an average, a space integral, and a spatial derivative respectively. In each case the first argument is the field, the second argument is a vector defining the type of operation, and the last argument is the parameter structure, r. If there are only two arguments, the operation vector is replaced by its default value.

8.2.1 Averages

This function allows one to extract local ensemble averages which may be needed as part of an overall calculation involving a ratio or product of averages. In addition, spatial grid averages can be used to obtain stochastic results with reduced sampling errors if the overall grid is homogeneous.

An average is carried out using the xave () function, which is defined as follows:

```
xave (o[,av],r)
```

This function takes a scalar field or observable o = [1, n.lattice], defined on the xSPDE local lattice, and returns an average with dimension [1, n.lattice]. The input is a field or observable o, and an optional averaging switch av. If av (j) > 0, an average is taken over dimension j. Dimensions are labelled from $j = 1 \dots 4$ as elsewhere. The first index indicates a local ensemble average, while subsequent indices indicate averages over the spatial grid. If the av vector is omitted, the average is only taken over the local ensemble. Averages are returned at all lattice locations. To average over both the local ensemble and all space dimensions, just use xave (o).

Higher dimensional graphs of grid averages are generally not useful, as they are simply flat. The xSPDE program allows the user to remove unwanted higher dimensional graphs of average variables. This is achieved by setting the corresponding element of <code>in.pdimension</code> to the highest dimension required, which depends on which dimensions are averaged.

For example, to average over the entire ensemble plus space lattice and indicate that only time-dependent graphs are required, set av = in.dx and:

```
in.pdimension = 1
```

Note that xave() on its own gives identical results to those calculated in the in.observe functions. Its utility comes when more complex combinations or functions of ensemble averages are required.

8.2.2 Integrals

Integrals over the spatial grid allow calculation of conserved or other global quantities. To take an integral over the spatial grid, use the xSPDE xint () function:

```
xint(o[, dx], r)
```

This function takes a scalar o, and returns a space integral over selected dimensions with vector measure dx. If dx(j) > 0 an integral is taken over dimension j. Dimensions are labelled from j = 1, ... as in all xspde standards. Time integrals are ignored at present. Integrals are returned at all lattice locations. To integrate over an entire lattice, set $dx = r \cdot dx$, otherwise set $dx(j) = r \cdot dx(j)$ for selected dimensions j.

As with averages, the xSPDE program allows the user to remove unwanted higher dimensional graphs when the integrated variable is used as an observable. For example, in a four dimensional simulation with integrals taken over the y and z coordinates, only t- and x-dependent graphs are required. Hence, set dx to [0, 0, r.dx(3), r.dx(4)], and:

```
in.pdimension = 2
```

If momentum-space integrals are needed, use the transform switch to make sure that the field is Fourier transformed, and input r.dk instead of r.dx. Note that xint() returns a lattice observable, as required when used in the in.observe function. If the integral is used in another function, note that it returns a matrix of dimension [1, lattice].

8.2.3 Derivatives

The code to take a spatial derivative is carried out using the xSPDE xd () function:

This function takes a scalar o, and returns a derivative over selected dimensions with a derivative D. Set D = r.Dx for a first order x-derivative, D = r.Dy for a first order y-derivative, and similarly D = r.Dz.*r.Dy for a cross-derivative in z and y. Higher derivatives require powers of these. For higher dimensions use numerical labels, where D = r.Dx becomes $D = r.D\{1\}$, and so on. Time derivatives are ignored at present. Derivatives are returned at all lattice locations.

If the derivative D is omitted, a first order x-derivative is returned. Note that xd() returns a lattice observable, as required when used in the in.observe function. If the integral is used in another function, note that it returns a matrix of dimension [1, lattice].

8.3 Grid coordinates and time

8.3.1 Time and space

The default spatial grid for plotted output data is rectangular, with periodic boundary conditions in space, and

```
dx(i) = in.ranges(i) / (in.points(i) - 1)
```

The time index is 1, and the space index i ranges from 2 to *in.dimension*. The maximum space-time dimension is in.dimension = 4, while in.ranges(i) is the time and space duration of the simulation, and in.points(i) is the total number of plotted points in the i-th direction.

Time is advanced in basic integration steps that are equal to or smaller than dx (1), for purposes of controlling and reducing errors:

```
dt = dx(1) / (in.steps * nc)
```

Here, in.steps is the minimum number of steps used per plotted point, and nc = 1, 2 is the check number. If nc = 1, the run uses coarse time-divisions. If nc = 2 the steps are halved in size for error-checking. Error-checking can be turned off if not required.

8.3.2 Low-level functions

The xSPDE program is function oriented: low-level functions are used to define initial conditions, equations and observables, amongst many other things described below.

Functions of a single lattice have arguments in the following order:

- the field a or initial random variable v;
- the stochastic noise z or other fields;
- · non-field arguments;
- the grid structure r.

The first argument, a, is a real or complex vector field. This is a matrix whose first dimension is the field index. The second dimension is the lattice index.

The second argument, z, if needed, is a real random noise, corresponding to ζ in the mathematical notation. This is a matrix whose first dimension is the noise index. The second dimension is the lattice index.

The last function argument is the lattice structure, r. This contains data about the integration lattice. The most important constants are $r \cdot t$, the current time, and the space coordinates, $r \cdot x$, $r \cdot y$, $r \cdot z$. Other data stored in the lattice structure is explained in later chapters.

Functions of multiple lattice sequences take current arguments first, and the oldest arguments last.

8.3.3 Arrays

In all function calls, the variables used are matrices. The most important first dimension used is the field length in.fields. The second dimension in all arrays is the lattice index, with a length n.lattice = ensembles(1) * points(2) * ... * points(dimension). Here ensembles(1) is the number of stochastic samples integrated as an array.

For reference, the field dimensions are:

```
a, da, L = [r.fields, r.nlattice];
v = [r.randoms(1)+r.randoms(2), r.nlattice];
z = [r.noises(1)+r.noises(2), r.nlattice];
D.x, r.x, r.kx = [1, r.nlattice];
o = [1, r.nlattice].
```

Each observable is defined by a function in a cell array with length in . graphs.

8.3.4 Simulation parameters

For each simulation in the input sequence, the input parameters and functions are specified as a data structure, in. These can be entered either interactively or as part of a simulation function file. The function file approach allows recycling and editing, so it is better for a large project.

There are extensive default preferences to simplify the inputs. If any inputs are omitted, there are default values which are set by inpreferences in all cases. These defaults are changed by editing the inpreferences function. The xgrpreferences () function is used to supply graphics default values.

For vector or cell inputs, an input shorter than required is padded to the right using default values.

8.4 Input parameters and user functions

A sequence of simulations is obtained from inputs in a cell array, as input = $\{in1, in2, ...\}$. The input parameters of each simulation in the sequence are specified in a Matlab structure. If there is one simulation, just one structure can be input, without the braces. This data is also passed to the xgraph() function. The inputs are numbers, vectors, strings, functions and cell arrays. All xSPDE metadata has preferred values, so only changes from the preferences need to be input. The resulting data is stored internally as a sequence of structures in a cell array, to describe the simulation sequence.

The standard way to input each parameter value is:

```
in.label = parameter
```

The standard way to input each function is:

```
in.label = @function-name
```

The inputs are scalar or vector parameters or function handles. Quantities relating to graphed averages are cell arrays, indexed by the graph number. The available inputs, with their default values in brackets, are given below.

Simulation metadata, including all preferred default values that were used in a particular simulation, is also stored for reference in any xSPDE output files. This is done in both the .mat and the .h5 output files, so the entire simulation can be easily reconstructed or changed.

Note that inputs can be numbers, vectors, strings or cells arrays. To simplify the inputs, some conventions are used, as follows:

- All input data has default values
- Vector inputs of numbers are enclosed in square brackets, [...].
- Where multiple inputs of strings, functions or vectors are needed they should be enclosed in curly brackets, { . . . }, to create a cell array.
- Vector or cell array inputs with only one member don't require brackets.
- Incomplete or partial vector or cell array inputs are filled in with the last applicable default value.
- New function definitions can be just handles pointing elsewhere, or else defined inline.

8.4.1 Input parameters

in.name

Default: '

Name used to label simulation, usually corresponding to the equation or problem solved. This can be added or removed from graphs using the *in.headers* Boolean variable, as explained in the section on graphics parameters.

```
in.name = 'your project name'
```

in.dimension

Default: 1

The total space-time dimension is labelled, unsurprisingly,

```
in.dimension = 1...4
```

in.fields

Default: 1

These are real or complex variables stored at each lattice point, and are the independent variables for integration. The fields are vectors that can have any dimension.

```
in.fields = 1, 2, ...
```

in.noises

Default: in.fields

This gives the number of stochastic noises generated per lattice point, in coordinate and momentum space respectively. Set to zero (in.noises = 0) for no noises. This is the number of *rows* in the noise-vector. Noises can be correlated either in ordinary or momentum spaces. The second input is the dimension of noises in k-space. It can be left out if zero.

```
in.noises = [in.noises(1), in.noises(2)] >= 0.
```

in.randoms

Default: in.noises

This gives the number of random fields generated per lattice point for the initial noise, in coordinate and momentum space. Set to zero (in.randoms = 0) for no random fields. Random fields can be correlated either in ordinary or momentum spaces. The second input is the dimension of random fields in momentum space. It can be left out if zero.

```
in.randoms = [in.randoms(1), in.randoms(2)] >= 0
```

in.ranges

Default: [10, 10, ...]

Each lattice dimension has a coordinate range, given by:

```
in.ranges = [in.ranges(1), ..., in.ranges(dimension)]
```

In the temporal graphs, the first coordinate is plotted over 0:in.ranges(1). All other coordinates are plotted over -in.ranges(n)/2:in.ranges(n)/2. The default value is 10 in each dimension.

in.points

```
Default: [49, 35, ..., 35]
```

The rectangular lattice of points plotted for each dimension are defined by a vector giving the number of points in each dimension:

```
in.points = [in.points(1), ..., in.points(in.dimension)]
```

The default values are simply given as a rough guide for initial calculations. Large, high dimensional lattices take more time to integrate. Increasing *in.points* improves graphics resolution, and gives better accuracy in each relevant dimension as well, but requires more memory. Speed is improved when the lattice points are a product of small prime factors.

in.steps

Default: 1

Number of time-steps per plotted point. The total number of integration steps in a simulation is therefore in.steps \star (in.points(1)-1). Thus, in.steps can be increased to improve the accuracy, but gives no change in graphics resolution. **Increase** steps to give a **lower** time-discretization error:

```
in.steps = 1, 2, \ldots
```

in.ensembles

Default: [1, 1, 1]

Number of independent stochastic trajectories simulated. This is specified in three levels to allow maximum parallelism. The first gives within-thread parallelism, allowing vector instructions. The second gives a number of independent trajectories calculated serially. The third gives multi-core parallelism, and requires the Matlab parallel toolbox. Either in.ensembles(2) or in.ensembles(3) are required if sampling error-bars are to be calculated.

```
in.ensembles = [in.ensembles(1), in.ensembles(2), in.ensembles(3)] >= 1
```

The *total* number of stochastic trajectories or samples is ensembles (1) * ensembles (2) * ensembles (3).

in.transforms

Default: {0}

Cell array that defines the different transform spaces used to calculate field observables. This has the structure

```
in.transforms\{n\} = [t(1), ..., t(4)] >= 0
```

There is one transform vector per observable. The j-th index, t (j), indicates a Fourier transform on the j-th axis. The normalization of the Fourier transform is such that the k=0 value in momentum space corresponds to the integral over space, with an additional factor of $1/\sqrt{2\pi}$. This gives a Fourier integral which is symmetrically normalized in ordinary and momentum space. The Fourier transform that is graphed is such that k=0 is the *central* value.

in.olabels

```
Default: {'a_1', ...}
```

Cell array of labels for the graph axis observable functions. These are text labels that are used on the graph axes. The default value is 'a_1' if the default observable is used, otherwise it is blank. This is overwritten by any subsequent label input when the graphics program is run:

```
in.olabels{n} = 'string'
```

in.c

This starting letter is always reserved to store user-specified constants and parameters. It is passed to user functions, and can be any data. All inputs — including c data — are copied into the data files and also the lattice structure r.

```
in.c = anything
```

8.4.2 Invariant inputs

The following can't be changed during a sequence in the current xSPDE version — the specified values for the first simulation will be used:

- 1. The extrapolation order
- 2. The number of ensembles (2)
- 3. The number of ensembles (3)
- 4. The output file-name

8.4.3 Input functions

A stochastic equation solver requires the definition of an initial distribution and a time derivative. In xSPDE, the time derivatives is divided up into a linear term including space derivatives, used to define an interaction picture, and the remaining derivatives. In addition, one must define quantities to be averaged over during the simulation, called graphs in xSPDE. These are all defined as functions, specified below.

```
in.initial(v, r)
    Default: xinitial()
```

Initializes the fields a for the first simulation in a sequence. The initial Gaussian random field variable, v, has unit variance if in.dimension is 1 or else is delta-correlated in space, with variance 1/r.dV ($\equiv 1/(dx_2...dx_d)$) for d space-time dimensions. If in.randoms is specified in the input, v has a first dimension of in.randoms (1) + in.randoms (2). If not specified, the default for in.randoms is in.noises. If not specified, the default of in.initial() is a = 0.

```
in.transfer(v, r, a0, r0)
     Default: xtransfer()
```

Initializes the fields a for subsequent calculations in a sequence. Otherwise, this function behaves in a similar way to in.initial. The function includes the previous field a0 and lattice r0. The default set by xtransfer() is a = a0.

```
in.da(a, z, r)

Default: xda()
```

Calculates derivatives da of the equation. The noise vector, z, has variance $1/(dx_1..dx_d)$, for dimension $d \le 4$, and a first dimension whose default value is in.fields if in.noises are not given. Otherwise, it has a first dimension of in.noises(1) + in.noises(2). The second type of input noise allows for spatially correlated and filtered noise specified in momentum space.

```
in.linear(D, r)
    Default: xlinear()
```

A user-definable function which returns the linear coefficients L in Fourier space. This is a function of the differential operator \mathbb{D} . The default is zero. Here \mathbb{D} is a structure with components $\mathbb{D}.x$, $\mathbb{D}.y$, $\mathbb{D}.z$, which correspond to $\partial/\partial x$, $\partial/\partial y$, $\partial/\partial z$ respectively. Each component has an array dimension the same as the coordinate lattice.

```
in.observe(a, r)
    Default: cell array of xobserve()
```

Cell array of function handles that take the current field and returns a real observable o with dimension of [1, n.lattice]. The default observable is the first real field amplitude. Note the use of braces for cell arrays! One can also input these individually as in.observe{1} = @(a,r) f(a,r), using an inline anonymous function. The total number of observe functions is stored internally as in.graphs. The fields a passed in the input are transformed according to the in.transforms metadata.

in.rfilter(r)

Default: xrfilter()

Returns the momentum-space filters for the input random terms. Each component has an array dimension the same as the input random fields in momentum space, that is, the return dimension is [r.randoms(2), r.nlattice].

in.nfilter(r)

Default: xnfilter()

Returns the momentum-space filters for the propagation noise terms. Each component has an array dimension the same as the random noises in momentum space, that is, the return dimension is [r.noises(2), r.nlattice].

8.4.4 Advanced input parameters

More advanced input parameters, which don't usually need to be changed from default values, are as follows:

in.iterations

Default: 4

For iterative algorithms like the implicit midpoint method, the iteration count is set here, typically around 3-4. Will increase the integration accuracy if set higher, but it may be better to increase *in.steps* if this is needed. With non-iterated algorithms, this input is not used:

```
in.iterations = 1, 2, \ldots
```

in.errorchecks

Default: 2

This defines how many times the integration is carried out for error-checking purposes. If *in.errorchecks* is *I*, there is one integration, but no checking at smaller time-steps. For error checking, set in.errorchecks = 2, which repeats the calculation at a shorter time-step — but with identical noise — to obtain the error bars, taking three times longer overall:

```
in.errorchecks = 1, 2
```

in.order

Default: 1

This is the extrapolation order, which is **only** used if in.errorchecks = 2. The program uses the estimated convergence order to extrapolate to zero step-size, with reduced estimated error-bars. If in.order = 0, no extrapolation is used, which is the most conservative input. The default order is usually acceptable, especially when combined with the default midpoint algorithm, see next section. While any non-negative order can be input, the theoretical orders of the four preset methods used *without* stochastic noise terms are: 1 for xEuler(); 2 for xRK2(); 4 for xRK4(). Allowed values are:

```
in.order >= 0
```

in.seed

Default: 0

Random noise generation seed, for obtaining reproducible noise sequences. Only needed if in.noises > 0

```
in.seed >= 0
```

in.graphs

Default: number of observables

This gives the number of observables or graphs computed. The default is the length of the cell array of observable functions. Normally, this is not initialized, as the default is typically used. Can be used to suppress data averaging.

```
in.graphs >= 0
```

in.print

Default: 1

Print flag for output information while running xSPDE. If print = 0, most output is suppressed, while print = 1 displays a progress report, and print = 2 also generates a readable summary of the r lattice structure as a record.

```
in.print >= 0
```

in.raw

Default: 0

Flag for storing raw trajectory data. If this flag is turned on, raw trajectories are stored in memory. The raw data is returned in function calls and also written to a file on completion, if a file-name is included.

```
in.raw >= 0
```

in.origin

Default: [0, -in.ranges/2]

This displaces the graph origin for each simulation to a user-defined value. If omitted, all initial times in a sequence are zero, and the space origin is set to -in.ranges/2 to give results that are symmetric about the origin:

```
in.origin = [origin(1), ..., origin(4)]
```

in.ipsteps

```
Default: 1 for xEuler() and xRK2(), 2 for xMP() and xRK4()
```

This specifies the number of interaction picture steps needed in a full propagation time-step. Default values are chosen according to the setting of *in.step*. Can be changed for custom integration methods.

```
in.ipsteps = 1, 2, 3, ...
```

in.file

Default: ''

Matlab or *HDF5* file name for output data. Includes all data and parameter values, including raw trajectories if in.raw = 1. If not needed just omit this. A Matlab filename should end in .mat, while an HDF5 file requires the filename to end in .h5. For a sequence of inputs, the filename should be given in the first structure of the sequence, and the entire sequence is stored.

```
in.file = 'file-name'
```

8.4.5 Advanced input functions

Advanced input functions are user-definable functions which don't usually need to be changed from default values. They allow customization and extension of xSPDE. These are as follows:

```
in.grid(r)
```

Default: xgrid()

Initializes the grid of coordinates in space.

in.noisegen(r)

Default: xnoisegen()

Generates arrays of noise terms xi for each point in time.

in.randomgen(r)

```
Default: xrandomgen ()
```

Generates a set of initial random fields v to initialize the fields simulated.

```
in.step (a, z, dt, r)

Default: xMP()
```

Specifies the stochastic integration routine for the field a, given a step in time dt and noise z, together with the interaction-picture propagator r.propagator which is part of the lattice structure. It returns the new field a. This function can be set to any of the predefined stochastic integration routines provided with xSPDE, described in the *Algorithms* chapter. User-written functions can also be used. The standard method, xMP(), is a midpoint integrator.

```
in.prop (a, r)

Default: xprop()
```

Returns the fields propagated for one step in the interaction picture, depending on the initial field a, and the propagator array *r.propagator*. Note that the time-step used in *r.propagator* depends on the input time-step, the error-checking and the algorithm.

```
in.propfactor(nc, r)
    Default: xpropfactor()
```

Returns the transfer array r.propagator, used by the in.prop function. The time propagated is a fraction of the current integration time-step, r.dt. It is equal to 1 / in.ipsteps of the integration time-step.

8.4.6 Graphics inputs and functions

The graphics parameters are also stored in the cell array input as a sequence of structures in. This only need to be input when the graphs are generated, and can be changed at a later time to alter the graphics output. A sequence of simulations is graphed from input specifications.

If there is one simulation, just one structure can be input, without the sequence braces. The standard form of each parameter value, which should have the in. structure label added, is:

```
in.label = parameter
```

If any inputs are omitted, there are default values which are set by the xgrpreferences() function, in all cases except for the comparison function *in.compare()*. The defaults can be changed by editing the xgrpreferences() function.

In the following descriptions, in.graphs is the total number of graphed variables of all types. The space coordinate, image, image-type and transverse data can be omitted if there is no spatial lattice, that is, if the dimension variable is set to one.

Graphics functions

in.function(data, in)

This is a cell array of graphics function handles. Use when a graph is needed that is a function of the observed averages. The default value generates all the averages that are in the simulated data. The input is the data array of averages, and the output is the data array that is plotted.

in.xfunctions (x, in)

This is a nested cell array of graphics axis transformations. Use when a graph is needed with an axis that is a function of the original axes. The default value generates all the averages that are in the simulated data. The input of the function is the original axis coordinates, and the output is the new coordinate set. Called as in.xfunctions{n}{nd} for the n-th graph and axis nd.

```
in.compare (t, in)
```

This is a cell array of comparative functions. Each takes the time or frequency vector - or whichever is the first dimension plotted - and returns comparison results for a graphed observable, as a function versus time or frequency (etc). Comparison results are graphed with a dashed line, for the two-dimensional graphs versus the first plotted dimension. There is no default function handle.

Graphics parameters

For uniformity, the graphics parameters that reference an individual data object are cell arrays, indexed over the graph number using braces {}. If a different type of input is used, like a scalar or matrix, xSPDE will attempt to convert the type. The axis labels are cell arrays, indexed over dimension. The graph number used to index these cell arrays refers to the data object, and there can be multiple plots obtained, depending on the graphics input.

Together with default values, they are:

in.gversion

```
Default: 'xGRAPH1.1'
```

This sets the version number of the graphics output. There is typically no need to input this.

```
in.gversion = 'current version name'
```

in.graphs

```
Default: -1
```

If non-negative, this sets the maximum number of graphed datasets. Can be used to suppress unwanted graphs from an xSPDE graphics script. If omitted or set to the default value, all the graphs output from the in.grfunc graphics processing function are plotted.

```
in.graphs = -1,..
```

in.axes

```
Default: { { 0, 0, 0, . . } }
```

Gives the axis and points plotted p for each plotted function. As special cases, p=0, is the default value that gives the entire axis, while p=-1 generates one point on the axis, namely the last point for the time axis and the midpoint for the space axes. Other values are vector range indicators, for example p=5 plots the fifth point, while p=1:4:41 plots every fourth point. For each graph type n the axes can be individually specified. If more than three axes are specified, only the first three are used. The others are set to default values.

```
in.axes{n} = {p1,p2,p3,..pd}
```

in.font

```
Default: {18, ...}
```

This sets the default font size for the graph labels. This can be changed per graph.

```
in.font{n} > 0
```

in.minbar

```
Default: {0.01, ...}
```

This is the minimum relative error-bar that is plotted. Set to a large value to suppress unwanted error-bars, although its best not to ignore the error-bar information!

```
in.minbar{n} >= 0
.. attribute:: in.esample
```

```
Default: {1, ...}
```

This is the flag for plotting sampling error. Set to zero to suppress unwanted sampling error lines and just plot means, although its best not to ignore this information!

```
in.esample{n} >= 0
```

in.images

```
Default: {0, 0, 0, ...}
```

This is the number of 3D, transverse o-x-y movie images plotted as discrete time slices. Only valid if in.dimension is greater than 2. Note that, if present, the coordinates not plotted are set to their central value, for example z = 0, when plotting the transverse images. This input should have a value from in.images (n) = 0 up to a maximum value of the number of plotted time-points. It has a vector length equal to in.graphs:

```
in.images{n} = 0 ... in.points(1)
```

in.imagetype

```
Default: {1, 1, ...}
```

This is the *type* of transverse o-x-y movie images plotted. If an element is 1, a perspective surface plot is output, for 2, a gray plot with colours is output, or for 3 a contour plot with 10 equally spaced contours is generated. This has a vector length equal to *in.graphs*.

```
in.imagetype\{n\} = 1, 2, 3
```

in.transverse

```
Default: {0, 0, ...}
```

This is the number of 2D, transverse o-x images plotted as discrete time slices. Only valid if <code>in.dimension</code> is greater than 2. Note that, if present, the y,z-coordinates are set to their central values, when plotting the transverse images. Each element should be from 0 up to a maximum value of the number of plotted time-points. It has a vector length equal to <code>in.graphs</code>:

```
in.transverse{n}=0 ... in.points(1)
```

in.headers

```
Default: {'head1', 'head2', ...}
```

This is a string variable giving the graph headers for each type of function plotted. The default value is an empty string '', which gives the simulation heading. Use a space '' for no headers. It is useful to include simulation headers - which is the default - to identify graphs in preliminary stages, while they may not be needed in a published final result.

```
in.headers{n} = 'my_graph_header'
```

in.pdimension

```
Default: {3, 3, ...}
```

This is the maximum space-time grid dimension for each plotted quantity. The purpose is eliminate unwanted graphs. For example, it may be useful to reduce the maximum dimension when averaging in space. Higher dimensional graphs are not needed, as the data is duplicated. Averaging can be useful for checking conservation laws, or for averaging over homogeneous data to reduce sampling errors. All graphs are suppressed if it is set to zero. Any three dimensions can be chosen using the axes command.

```
in.pdimension{n} \ge 0
```

in.xlabels

```
Default: {'t', 'x', 'y', 'z'} or {'t', 'x_1', 'x_2', 'x_3'}
```

Labels for the graph axis independent variable labels, vector length of in. dimension. The numerical labeling default is used when the in.numberaxis option is set. Note, these are typeset in Latex mathematics mode!

```
in.xlabels = {in.xlabels(1), ..., in.xlabels(in.dimension)}
```

in.klabels

```
Default: {'\\omega', 'k\_x', 'k\_y', 'k\_z'} or {'\\omega', 'k\_1', 'k\_2', 'k\ 3'}
```

Labels for the graph axis Fourier transform labels, vector length of in.dimension. The numerical labeling default is used when the in.numberaxis option is set. Note, these are typeset in Latex mathematics mode!

```
in.klabels = {in.klabels(1), ..., in.klabels(in.dimension)}
```

Graphics projections

If there is a spatial grid, the graphics program automatically generates several graphs for each observable, depending on space dimension. The maximum dimension that is plotted as set by <code>in.pdimension</code>. In the plots, the lattice is projected down to successively lower dimensions.

For each observable, the projection sequence is as follows:

- If in. dimension is 4 or greater, a central z point nz = 1 + floor (in.points (4) / 2) is picked. For example, with 35 points, the central point is nz = 18.
- This gives a three dimensional space-time lattice, which is treated the same as if in.dimension is 3.
- If in.images are specified, two-dimensional x y plots are generated at equally spaced time intervals. If
 there is only one image, it is at the last time-point. Different plot-types are used depending on the setting of
 in.imagetype.
- A central y point ny = 1 + floor (in.points (3)/2) is picked. This gives a two dimensional spacetime lattice, which is treated the same as if in.dimension is 2. If in.transverse is specified, onedimensional x plots are generated at equally spaced time intervals, as before.
- A central x point nx = 1 + floor(in.points(2)/2) is picked. This gives a one dimensional time lattice, which is treated the same as if in.dimension is 1.
- Plots of observable vs time are obtained, including sampling errors and error bars. If comparison graphs are specified using in.compare() functions, they are plotted also, using a dotted line. A difference graph is also plotted when there is a comparison.

8.5 Parameter structure

Internally, xSPDE parameters are stored in a cell array, latt, of structures r, which is passed to functions. This includes all the data given above inside the in structure. In addition, it includes the table of computed parameters given below.

User application constants and parameters should not be reserved names; in.c and all names starting with in.c will always be available in all versions of xSPDE.

A parameter structure contains information about the space-time grid and is passed to various functions, for instance <code>in.da</code> or <code>in.step</code>. The corresponding parameter is commonly marked as r.

r.t

Current value of time, t.

- r.x
- r.y
- r.z

Coordinate grids of x, y, z.

$r.x\{n\}$

Higher dimensions are labeled numerically as x_1 ,.. x_6 , and so on. This numerical axis convention can be set even for lower dimensions if in numberaxis is set to 1.

- r.kx
- r.ky
- r.kz

Grids in momentum space: k_x , k_y , k_z .

r.k5

Higher dimensions are labeled numerically as k_5 , k_6 , and so on.

r.dt

Output time-step between stored points for data averages.

r.dtr

Current reduced time-step used for integration.

r.dx

Steps in coordinate space: $[t, x, y, z, x_5, ..]$.

r.dk

Steps in momentum space: $[\omega, k_x, k_y, k_z, k_5, ..]$.

${\tt r.propagator}$

Contains the propagator array for the interaction picture.

r.V

Spatial lattice volume.

r.K

Momentum lattice volume.

r.dV

Spatial cell volume.

r.dK

Momentum cell volume.

r.xc

Space-time coordinate axes (vector cells).

r.kc

Computational Fourier transform axes in $[\omega, k_x, k_y, k_z, k_5, ...]$ (vector cells).

r.kg

Graphics Fourier transform axes in $[\omega, k_x, k_y, k_z, k_5, ...]$ (vector cells).

r.kranges

Range in $[\omega, k_x, k_y, k_z, k_5, ...]$ (vector).

r.s.dx

Initial stochastic normalization.

r.s.dxt

Propagating stochastic normalization.

r.s.dk

Initial k stochastic normalization.

r.s.dkt

Propagating k stochastic normalization.

r.nspace

Number of spatial lattice points: in.points(2) * .. * in.points(in.dimension).

r.nlattice

Total lattice: in.ensembles(1) * r.nspace.

r.ncopies

Total copies of stochastic integrations: in.ensembles(2) * in.ensembles(3).

r.d.int

Dimensions for lattice integration (vector).

r d :

Dimensions for a field (flattened, vector).

r.d.r

Dimensions for coordinates (flattened, vector).

r.d.ft

Dimensions for field transforms (vector).

r.d.k

Dimensions for noise transforms (vector).

r.d.obs

Dimensions for observations (vector).

r.d.data

Dimensions for average data (flattened, vector).

r.d.raw

Dimensions for raw data (flattened, vector).

8.6 Default functions

These functions are used as defaults for simulations and can be overridden by the user.

$xinitial(\sim, r)$

Returns a field array filled with zeros.

$xtransfer(\sim, \sim, a, \sim)$

Returns the field a unchanged.

$xda(\sim, \sim, r)$

Returns a derivative array filled with zeros.

$xlinear(\sim, r)$

Returns a linear response array filled with zeros.

${\tt xobserve}\,(a, {\tt \sim})$

Returns the real part of a (1, :).

xrfilter(r)

Returns an array of ones.

xnfilter(r)

Returns an array of ones.

xgrid(r)

Sets grid points in lattice from coordinate vectors. Returns the r structure with added grid points.

xnoisegen(r)

Generates random noise matrix z.

xrandomgen(r)

Generates initial random field matrix v.

xpropfactor(nc, r)

Returns the interaction picture propagation factor. nc is a check index, r is a lattice structure.

8.7 Frequently asked questions

Answers to some frequent questions, and reminders of points in this chapter are:

- Can you average other stochastic quantities apart from the field?
 - Yes: just specify the functions that need to be averaged using the user function in.observe.
- Can you have functions of the current time and space coordinate?
 - Yes: xSPDE functions support this using the structure r, as r.t, r.x, r.y, r.z, or r.t, $r.x\{1\}$, and so on, for more than four space-time dimensions.
- Can you have several independent stochastic variables?
 - Yes, input this using in.fields > 1.
- Are higher dimensional differential equations possible?
 - Yes, this requires setting in.dimension > 1. This is essentially unlimited in xSPDE except for memory requirements.
- Can you have spatial partial derivatives?
 - Yes, provided they are linear in the fields; these are obtainable using the function in.linear.
- Can you delete the graph heading?
 - Yes, this is turned off if you set in. headers to 0.
- Why are there two lines in the graphs sometimes?
 - These are one standard deviation sampling error limits, generated when in ensembles (2, 3) > 1.
- Why is there just one line in some graphs, with no sampling errors indicated?
 - You need in .ensembles (2) or (3) for this; see previous question.
- What are the error bars for?
 - These are the estimated maximum errors due to finite step-sizes in time.

8.8 High-level xSPDE functions and objects

The high-level xSPDE functions process the input parameters, producing simulation data and graphs. Function parameters are in the order of input, which specifies the simulation, then data, which is needed for graphics output.

xspde (input)

This is the combined xSPDE function. It accepts a simulation sequence, input. This can be a single structure, in, or else a cell array of structures, {in1,in2,..}, for sequences. Output graphs are displayed, and it returns the output [maxerror, input, data], where maxerror is the maximum error or difference found. If a filename is specified, it generates an output data file. It calls the functions xsim() and xgraph().

xsim(input)

This is the xSPDE simulation function. Like xspde(), it accepts input parameters in input. It returns [error, input, data, raw], where: error = [error(1), error(2)] is a vector of maximum step-size and sampling errors, input is the full input structure or cell array for sequences, including default values, and data is a cell array of average observables. If the in.raw option is used, data for the actual trajectories is output in raw. This can be run as a stand-alone function if no graphs are required.

xgraph (data[, input])

This is the xSPDE graphics function. It takes computed simulation data and input. It plots graphs, and returns the maximum difference diff from comparisons with user-specified comparison functions. The data should have as many cells as input cells, for sequences. If data = 'filename.h5' or data='filename.mat', the specified file is read both for input and data. Here .h5 indicates an HDF5 file, and .mat indicates a Matlab file. When the 'data' input is given as a filename, input parameters in the file are replaced by any of the new input parameters that are specified. Any stored input can be overwritten, allowing graphs to be modified with new labels. If the input field is not present, then a file-name must be specified in the data field.

8.8.1 Open object-oriented architecture

As well as extensibility through sequences, which was described in *Averaging and projects*, in the section *Sequential integration*, the architecture of xSPDE allows functional extensions.

The input metadata includes both data and methods acting on the data, in the tradition of object-oriented programs. Yet there is no strict class typing. Users are encouraged to adapt the xSPDE program by adding input parameters and methods to the input structures.

Such unorthodox object orientation is deliberate.

This open extensibility permits arbitrary functions to be specified in the in structures. All functions and parameters have default values in xSPDE. It is also possible to include user defined functions, provided they satisfy the API definitions given below. This is achieved simply by including the relevant function handles and parameters in the input metadata.

Internal parameters and function handles from the in structures, together with any computed and default parameters and functions, are stored in the lattice structure r. These are available to all user-defined functions. Use of pre-existing reserved names is not advisable, and the structure $r \cdot c$ is always reserved for user constants, parameters and functions if required.

The xSPDE software architecture is intended to be easily extended, and users are strongly encouraged to develop their own libraries and contribute to the xSPDE function pool. Because this generally requires new functions and parameters, the internal data architecture is as open as possible.

For example, to define your own integration function, include in the xSPDE input the line:

```
in.step = @Mystep;
```

Next, include anywhere on your Matlab path, the function definition, for example:

8.9 Averages, integrals and derivatives

There are functions available in xSPDE for averages, integrals and derivatives. These can be used to calculate observables for plotting, but are also available for calculating stochastic derivatives as part of the stochastic equation. They operate in parallel over the local ensemble and lattice dimensions. They take a scalar quantity, for example a single field component, and return an average, a space integral, and a spatial derivative respectively. In each case the first argument is the field, the second argument is a vector defining the type of operation, and the last argument is the parameter structure, r. If there are only two arguments, the operation vector is replaced by its default value.

8.9.1 Averages

This function allows one to extract local ensemble averages which may be needed as part of an overall calculation involving a ratio or product of averages. In addition, spatial grid averages can be used to obtain stochastic results with reduced sampling errors if the overall grid is homogeneous.

An average is carried out using the xave () function, which is defined as follows:

```
\mathbf{xave}\left(o[,av],r\right)
```

This function takes a scalar field or observable o = [1, n.lattice], defined on the xSPDE local lattice, and returns an average with dimension [1, n.lattice]. The input is a field or observable o, and an optional averaging switch av. If av (j) > 0, an average is taken over dimension j. Dimensions are labelled from $j = 1 \dots 4$ as elsewhere. The first index indicates a local ensemble average, while subsequent indices indicate averages over the spatial grid. If the av vector is omitted, the average is only taken over the local ensemble. Averages are returned at all lattice locations. To average over both the local ensemble and all space dimensions, just use xave (o).

Higher dimensional graphs of grid averages are generally not useful, as they are simply flat. The xSPDE program allows the user to remove unwanted higher dimensional graphs of average variables. This is achieved by setting the corresponding element of <code>in.pdimension</code> to the highest dimension required, which depends on which dimensions are averaged.

For example, to average over the entire ensemble plus space lattice and indicate that only time-dependent graphs are required, set av = in.dx and:

```
in.pdimension = 1
```

Note that xave() on its own gives identical results to those calculated in the in.observe functions. Its utility comes when more complex combinations or functions of ensemble averages are required.

8.9.2 Integrals

Integrals over the spatial grid allow calculation of conserved or other global quantities. To take an integral over the spatial grid, use the xSPDE xint () function:

```
xint(o[,dx],r)
```

This function takes a scalar o, and returns a space integral over selected dimensions with vector measure dx. If dx(j) > 0 an integral is taken over dimension j. Dimensions are labelled from j = 1, ... as in all xspde standards. Time integrals are ignored at present. Integrals are returned at all lattice locations. To integrate over an entire lattice, set dx = r.dx, otherwise set dx(j) = r.dx(j) for selected dimensions j.

As with averages, the xSPDE program allows the user to remove unwanted higher dimensional graphs when the integrated variable is used as an observable. For example, in a four dimensional simulation with integrals taken over the y and z coordinates, only t- and x-dependent graphs are required. Hence, set dx to [0, 0, r.dx(3), r.dx(4)], and:

```
in.pdimension = 2
```

If momentum-space integrals are needed, use the transform switch to make sure that the field is Fourier transformed, and input r.dk instead of r.dx. Note that xint () returns a lattice observable, as required when used in the in.observe function. If the integral is used in another function, note that it returns a matrix of dimension [1, lattice].

8.9.3 Derivatives

The code to take a spatial derivative is carried out using the xSPDE xd () function:

This function takes a scalar o, and returns a derivative over selected dimensions with a derivative D. Set D = r.D.x for a first order x-derivative, D = r.D.y for a first order y-derivative, and similarly D = r.D.x.*r.D.y for a cross-derivative in x and y. Higher derivatives require powers of these. Time derivatives are ignored at present. Derivatives are returned at all lattice locations.

If the derivative D is omitted, a first order x-derivative is returned. Note that xd() returns a lattice observable, as required when used in the in.observe function. If the integral is used in another function, note that it returns a matrix of dimension [1, lattice].

8.10 Grid coordinates and time

8.10.1 Time and space

The default spatial grid for plotted output data is rectangular, with periodic boundary conditions in space, and

```
dx(i) = in.ranges(i) / (in.points(i) - 1)
```

The time index is 1, and the space index i ranges from 2 to *in.dimension*. The maximum space-time dimension is in.dimension = 4, while in.ranges(i) is the time and space duration of the simulation, and in.points(i) is the total number of plotted points in the i-th direction.

Time is advanced in basic integration steps that are equal to or smaller than dx (1), for purposes of controlling and reducing errors:

```
dt = dx(1) / (in.steps * nc)
```

Here, in.steps is the minimum number of steps used per plotted point, and nc = 1, 2 is the check number. If nc = 1, the run uses coarse time-divisions. If nc = 2 the steps are halved in size for error-checking. Error-checking can be turned off if not required.

8.10.2 Low-level functions

The xSPDE program is function oriented: low-level functions are used to define initial conditions, equations and observables, amongst many other things described below.

Functions of a single lattice have arguments in the following order:

- the field a or initial random variable v;
- the stochastic noise z or other fields;
- non-field arguments;
- the grid structure r.

The first argument, a, is a real or complex vector field. This is a matrix whose first dimension is the field index. The second dimension is the lattice index.

The second argument, z, if needed, is a real random noise, corresponding to ζ in the mathematical notation. This is a matrix whose first dimension is the noise index. The second dimension is the lattice index.

The last function argument is the lattice structure, r. This contains data about the integration lattice. The most important constants are $r \cdot t$, the current time, and the space coordinates, $r \cdot x$, $r \cdot y$, $r \cdot z$. Other data stored in the lattice structure is explained in later chapters.

Functions of multiple lattice sequences take current arguments first, and the oldest arguments last.

8.10.3 Arrays

In all function calls, the variables used are matrices. The most important first dimension used is the field length in.fields. The second dimension in all arrays is the lattice index, with a length n.lattice = ensembles(1) * points(2) * ... * points(dimension). Here ensembles(1) is the number of stochastic samples integrated as an array.

For reference, the field dimensions are:

```
a, da, L = [r.fields, r.nlattice];
v = [r.randoms(1)+r.randoms(2), r.nlattice];
z = [r.noises(1)+r.noises(2), r.nlattice];
D.x, r.x, r.kx = [1, r.nlattice];
o = [1, r.nlattice].
```

Each observable is defined by a function in a cell array with length in . graphs.

8.10.4 Simulation parameters

For each simulation in the input sequence, the input parameters and functions are specified as a data structure, in. These can be entered either interactively or as part of a simulation function file. The function file approach allows recycling and editing, so it is better for a large project.

There are extensive default preferences to simplify the inputs. If any inputs are omitted, there are default values which are set by inpreferences in all cases. These defaults are changed by editing the inpreferences function. The xqrpreferences () function is used to supply graphics default values.

For vector or cell inputs, an input shorter than required is padded to the right using default values.

8.11 Input parameters and user functions

A sequence of simulations is obtained from inputs in a cell array, as input = {in1, in2, ...}. The input parameters of each simulation in the sequence are specified in a Matlab structure. If there is one simulation, just one structure can be input, without the braces. This data is also passed to the xgraph() function. The inputs are numbers, vectors, strings, functions and cell arrays. All xSPDE metadata has preferred values, so only changes from the preferences need to be input. The resulting data is stored internally as a sequence of structures in a cell array, to describe the simulation sequence.

The standard way to input each parameter value is:

```
in.label = parameter
```

The standard way to input each function is:

```
in.label = @function-name
```

The inputs are scalar or vector parameters or function handles. Quantities relating to graphed averages are cell arrays, indexed by the graph number. The available inputs, with their default values in brackets, are given below.

Simulation metadata, including all preferred default values that were used in a particular simulation, is also stored for reference in any xSPDE output files. This is done in both the .mat and the .h5 output files, so the entire simulation can be easily reconstructed or changed.

Note that inputs can be numbers, vectors, strings or cells arrays. To simplify the inputs, some conventions are used, as follows:

- · All input data has default values
- Vector inputs of numbers are enclosed in square brackets, [...].
- Where multiple inputs of strings, functions or vectors are needed they should be enclosed in curly brackets, { . . . }, to create a cell array.
- Vector or cell array inputs with only one member don't require brackets.
- Incomplete or partial vector or cell array inputs are filled in with the last applicable default value.
- New function definitions can be just handles pointing elsewhere, or else defined inline.

8.11.1 Input parameters

```
in.name

Default: '
```

Name used to label simulation, usually corresponding to the equation or problem solved. This can be added or removed from graphs using the *in.headers* Boolean variable, as explained in the section on graphics parameters.

```
in.name = 'your project name'
```

in.dimension

Default: 1

The total space-time dimension is labelled, unsurprisingly,

```
in.dimension = 1...4
```

```
in.fields
```

Default: 1

These are real or complex variables stored at each lattice point, and are the independent variables for integration. The fields are vectors that can have any dimension.

```
in.fields = 1, 2, ...
```

in.noises

Default: in.fields

This gives the number of stochastic noises generated per lattice point, in coordinate and momentum space respectively. Set to zero (in.noises = 0) for no noises. This is the number of *rows* in the noise-vector. Noises can be delta-correlated or correlated in space. The second input is the dimension of noises in k-space. It can be left out if zero. This allows use of finite correlation lengths when needed, by including a frequency filter function that is used to multiply the noise in Fourier-space. The Fourier-space noise variance is the square of the filter function. Note that the first noise index, in.noises(1), indicates how many independent noise fields are generated, while in.noises(2) indicates how many of these are are fourier-transformed, filtered and then inverse fourier transformed to give correlations. These appear as extra noises, so the total is in.noises(1)+in.noises(2). The filtered noises have a finite correlation length. They are also correlated with the first in.noises(2) noises they are generated from, as this is sometimes useful.

```
in.noises = [in.noises(1), in.noises(2)] >= 0.
```

in.randoms

Default: in.noises

This gives the number of random fields generated per lattice point for the initial noise, in coordinate and momentum space. Set to zero (in.randoms = 0) for no random fields. Random fields can be delta-correlated or correlated in space. The second input is the dimension of random fields in momentum space. It can be left out if zero. The Fourier-space random variance is the square of the filter function. Note that the first noise index, in.randoms(1), indicates how many independent random fields are generated, while in.randoms(2) indicates how many of these are are fourier-transformed, filtered and then inverse fourier transformed. These appear as additional random fields, so the total is in.randoms(1)+in.randoms(2). The filtered noises have a finite correlation length. They are correlated with the first in.randoms(2) random fields they are generated from, as this is sometimes useful.

```
in.randoms = [in.randoms(1), in.randoms(2)] >= 0
```

in.ranges

Default: [10, 10, ...]

Each lattice dimension has a coordinate range, given by:

```
in.ranges = [in.ranges(1), ..., in.ranges(dimension)]
```

In the temporal graphs, the first coordinate is plotted over 0:in.ranges(1). All other coordinates are plotted over -in.ranges(n)/2:in.ranges(n)/2. The default value is 10 in each dimension.

in.points

Default: [49, 35, ..., 35]

The rectangular lattice of points plotted for each dimension are defined by a vector giving the number of points in each dimension:

```
in.points = [in.points(1), ..., in.points(in.dimension)]
```

The default values are simply given as a rough guide for initial calculations. Large, high dimensional lattices take more time to integrate. Increasing *in.points* improves graphics resolution, and gives better accuracy in each relevant dimension as well, but requires more memory. Speed is improved when the lattice points are a product of small prime factors.

in.steps

Default: 1

Number of time-steps per plotted point. The total number of integration steps in a simulation is therefore in.steps * (in.points(1)-1). Thus, in.steps can be increased to improve the accuracy, but gives no change in graphics resolution. **Increase** steps to give a **lower** time-discretization error:

```
in.steps = 1, 2, ...
```

in.ensembles

Default: [1, 1, 1]

Number of independent stochastic trajectories simulated. This is specified in three levels to allow maximum parallelism. The first gives within-thread parallelism, allowing vector instructions. The second gives a number of independent trajectories calculated serially. The third gives multi-core parallelism, and requires the Matlab parallel toolbox. Either in.ensembles(2) or in.ensembles(3) are required if sampling error-bars are to be calculated.

```
in.ensembles = [in.ensembles(1), in.ensembles(2), in.ensembles(3)] >= 1
```

The *total* number of stochastic trajectories or samples is ensembles (1) * ensembles (2) * ensembles (3).

in.transforms

Default: { 0 }

Cell array that defines the different transform spaces used to calculate field observables. This has the structure

```
in.transforms{n} = [t(1), ..., t(4)] >= 0
```

There is one transform vector per observable. The j-th index, t (j), indicates a Fourier transform on the j-th axis. The normalization of the Fourier transform is such that the k=0 value in momentum space corresponds to the integral over space, with an additional factor of $1/\sqrt{2\pi}$. This gives a Fourier integral which is symmetrically normalized in ordinary and momentum space. The Fourier transform that is graphed is such that k=0 is the *central* value.

in.c

This starting letter is always reserved to store user-specified constants and parameters. It is passed to user functions, and can be any data. All inputs — including \circ data — are copied into the data files and also the lattice structure \circ .

```
in.c = anything
```

8.11.2 Invariant inputs

The following can't be changed during a sequence in the current xSPDE version — the specified values for the first simulation will be used:

- 1. The extrapolation order
- 2. The number of ensembles (2)
- 3. The number of ensembles (3)
- 4. The output file-name

8.11.3 Input functions

A stochastic equation solver requires the definition of an initial distribution and a time derivative. In xSPDE, the time derivatives is divided up into a linear term including space derivatives, used to define an interaction picture, and the remaining derivatives. In addition, one must define quantities to be averaged over during the simulation, called graphs in xSPDE. These are all defined as functions, specified below.

```
in.initial(v, r)
    Default: xinitial()
```

Initializes the fields a for the first simulation in a sequence. The initial Gaussian random field variable, v, has unit variance if in.dimension is 1 or else is delta-correlated in space, with variance 1/r.dV ($\equiv 1/(dx_2...dx_d)$) for d space-time dimensions. If in.randoms is specified in the input, v has a first dimension of in.randoms (1) + in.randoms (2). If not specified, the default for in.randoms is in.noises. If not specified, the default of in.initial() is a = 0.

Initializes the fields a for subsequent calculations in a sequence. Otherwise, this function behaves in a similar way to in.initial. The function includes the previous field a0 and lattice r0. The default set by xtransfer() is a = a0.

```
in.da(a, z, r)

Default: xda()
```

Calculates derivatives da of the equation. The noise vector, z, has variance $1/(dx_1..dx_d)$, for dimension $d \le 4$, and a first dimension whose default value is in.fields if in.noises are not given. Otherwise, it has a first dimension of in.noises(1) + in.noises(2). The second type of input noise allows for spatially correlated and filtered noise specified in momentum space.

```
in.linear(r)
    Default: xlinear()
```

A user-definable function which returns the linear coefficients L in Fourier space. This is a function of the differential operator Dx, Dy, Dz, which correspond to $\partial/\partial x$, $\partial/\partial y$, $\partial/\partial z$ respectively. Each component has an array dimension the same as the coordinate lattice. If axes are numbered, use $D\{1\}$, $D\{2\}$, $D\{3\}$ etc.

```
in.observe(a, r)

Default: cell array of xobserve()
```

Cell array of function handles that take the current field and returns a real observable \circ with dimension of [1, n.lattice]. The default observable is the first real field amplitude. Note the use of braces for cell arrays! One can also input these individually as $in.observe\{1\} = @(a,r) f(a,r)$, using an inline anonymous function. The total number of observe functions is stored internally as in.graphs. The fields a passed in the input are transformed according to the in.transforms metadata.

```
in.rfilter(r)
    Default: xrfilter()
```

Returns the momentum-space filters for the input random terms. Each component has an array dimension the same as the input random fields in momentum space, that is, the return dimension is [r.randoms(2), r.nlattice].

```
in.nfilter(r)
    Default: xnfilter()
```

Returns the momentum-space filters for the propagation noise terms. Each component has an array dimension the same as the random noises in momentum space, that is, the return dimension is [r.noises(2), r.nlattice].

8.11.4 Advanced input parameters

More advanced input parameters, which don't usually need to be changed from default values, are as follows:

in.iterations

Default: 4

For iterative algorithms like the implicit midpoint method, the iteration count is set here, typically around 3-4. Will increase the integration accuracy if set higher, but it may be better to increase *in.steps* if this is needed. With non-iterated algorithms, this input is not used:

```
in.iterations = 1, 2, ...
```

in.errorchecks

Default: 2

This defines how many times the integration is carried out for error-checking purposes. If *in.errorchecks* is *I*, there is one integration, but no checking at smaller time-steps. For error checking, set in.errorchecks = 2, which repeats the calculation at a shorter time-step — but with identical noise — to obtain the error bars, taking three times longer overall:

```
in.errorchecks = 1, 2
```

in.order

Default: 1

This is the extrapolation order, which is **only** used if in.errorchecks = 2. The program uses the estimated convergence order to extrapolate to zero step-size, with reduced estimated error-bars. If in.order = 0, no extrapolation is used, which is the most conservative input. The default order is usually acceptable, especially when combined with the default midpoint algorithm, see next section. While any non-negative order can be input, the theoretical orders of the four preset methods used *without* stochastic noise terms are: 1 for xEuler(); 2 for xRK2(); 3 for xRK2(); 4 for xRK4(). Allowed values are:

```
in.order >= 0
```

in.seed

Default: 0

Random noise generation seed, for obtaining reproducible noise sequences. Only needed if in.noises > 0

```
in.seed >= 0
```

in.graphs

Default: number of observables

This gives the number of observables or graphs computed. The default is the length of the cell array of observable functions. Normally, this is not initialized, as the default is typically used. Can be used to suppress data averaging.

```
in.graphs >= 0
```

in.print

Default: 1

Print flag for output information while running xSPDE. If print = 0, most output is suppressed, while print = 1 displays a progress report, and print = 2 also generates a readable summary of the r lattice structure as a record.

```
in.print >= 0
```

in.raw

Default: 0

Flag for storing raw trajectory data. If this flag is turned on, raw trajectories are stored in memory. The raw data is returned in function calls and also written to a file on completion, if a file-name is included.

```
in.raw >= 0
```

in.origin

```
Default: [0, -in.ranges/2]
```

This displaces the graph origin for each simulation to a user-defined value. If omitted, all initial times in a sequence are zero, and the space origin is set to -in.ranges/2 to give results that are symmetric about the origin:

```
in.origin = [origin(1), ..., origin(4)]
```

in.ipsteps

```
Default: 1 for xEuler() and xRK2(), 2 for xMP() and xRK4()
```

This specifies the number of interaction picture steps needed in a full propagation time-step. Default values are chosen according to the setting of *in.step*. Can be changed for custom integration methods.

```
in.ipsteps = 1, 2, 3, ..
```

in.file

Default: ''

Matlab or *HDF5* file name for output data. Includes all data and parameter values, including raw trajectories if in.raw = 1. If not needed just omit this. A Matlab filename should end in .mat, while an HDF5 file requires the filename to end in .h5. For a sequence of inputs, the filename should be given in the first structure of the sequence, and the entire sequence is stored.

```
in.file = 'file-name'
```

8.11.5 Advanced input functions

Advanced input functions are user-definable functions which don't usually need to be changed from default values. They allow customization and extension of xSPDE. These are as follows:

```
in.function(data, in)
```

This is a cell array of graphics function handles. Use when a graph is needed that is a function of the observed local averages over <code>ensemble(1)</code>. The default value generates all the averages that are in the simulated data. The input is the data array of averages, and the output is another data array. This function can generate error-bars and sampling errors in the local averages.

```
in.grid(r)
```

```
Default: xgrid()
```

Initializes the grid of coordinates in space.

in.noisegen(r)

```
Default: xnoisegen()
```

Generates arrays of noise terms xi for each point in time.

in.randomgen(r)

```
Default: xrandomgen()
```

Generates a set of initial random fields $\ensuremath{\mathbf{v}}$ to initialize the fields simulated.

```
in.step (a, z, dt, r)

Default: xMP()
```

Specifies the stochastic integration routine for the field a, given a step in time dt and noise z, together with the interaction-picture propagator r.propagator which is part of the lattice structure. It returns the new field a. This function can be set to any of the predefined stochastic integration routines provided with xSPDE, described in the *Algorithms* chapter. User-written functions can also be used. The standard method, xMP(), is a midpoint integrator.

```
in.prop(a, r)
Default: xprop()
```

Returns the fields propagated for one step in the interaction picture, depending on the initial field a, and the propagator array *r.propagator*. Note that the time-step used in *r.propagator* depends on the input time-step, the error-checking and the algorithm.

```
in.propfactor(nc, r)
    Default: xpropfactor()
```

Returns the transfer array r.propagator, used by the in.prop function. The time propagated is a fraction of the current integration time-step, r.dt. It is equal to 1 / in.ipsteps of the integration time-step.

8.11.6 Graphics inputs and functions

The graphics parameters are also stored in the cell array input as a sequence of structures in. This only need to be input when the graphs are generated, and can be changed at a later time to alter the graphics output. A sequence of simulations is graphed from input specifications.

If there is one simulation, just one structure can be input, without the sequence braces. The standard form of each parameter value, which should have the in. structure label added, is:

```
in.label = parameter
```

If any inputs are omitted, there are default values which are set by the xgrpreferences() function, in all cases except for the comparison function *in.compare()*. The defaults can be changed by editing the xgrpreferences() function.

In the following descriptions, in .graphs is the total number of graphed variables of all types. The space coordinate, image, image-type and transverse data can be omitted if there is no spatial lattice, that is, if the dimension variable is set to one.

Graphics functions

in.gfunction(data, in)

This is a cell array of graphics function handles. Use when a graph is needed that is a function of the data generated by xsim, as a post-processing step. The default value is the simulated data. The input is the data array of averages from xsim, including error-estimates, and the output is the data array that is plotted. Any handling of error estimates must be user-provided at this stage.

```
in.xfunctions(x nd, in)
```

This is a nested cell array of graphics axis transformations. Use when a graph is needed with an axis that is a function of the original axes. The default value generates all the averages that are in the simulated data. The input of the function is the original axis coordinates, and the output is the new coordinate set. Called as $n.xfunctions\{n\}\{nd\}(x_nd,in)$ for the n-th graph and axis nd, where x_nd is a vector of axis coordinate points for that axis dimension.

in.compare (t, in)

This is a cell array of comparative functions. Each takes the time or frequency vector - or whichever is the first dimension plotted - and returns comparison results for a graphed observable, as a function versus time or frequency (etc). Comparison results are graphed with a dashed line, for the two-dimensional graphs versus the first plotted dimension. There is no default function handle.

Graphics parameters

For uniformity, the graphics parameters that reference an individual data object are cell arrays, indexed over the graph number using braces {}. If a different type of input is used, like a scalar or matrix, xSPDE will attempt to convert the type. The axis labels are cell arrays, indexed over dimension. The graph number used to index these cell arrays refers to the data object, and there can be multiple plots obtained, depending on the graphics input.

Together with default values, they are:

in.gversion

```
Default: 'xGRAPH1.1'
```

This sets the version number of the graphics output. There is typically no need to input this.

```
in.gversion = 'current version name'
```

in.graphs

Default: 1

If non-negative, this sets the maximum number of graphed datasets. Can be used to suppress unwanted graphs from an xSPDE graphics script. If omitted, all the graphs output from the graphics processing function are plotted.

```
in.graphs = 1,..
```

in.olabels

```
Default: {'a', ...}
```

Cell array of labels for the graph axis observables and functions. These are text labels that are used on the graph axes. The default value is 'a_1' if the default observable is used, otherwise it is blank. This is overwritten by any subsequent label input when the graphics program is run:

```
in.olabels{n} = 'string'
```

in.axes

```
Default: { { 0, 0, 0, ... } }
```

Gives the axis and points plotted p for each plotted function. As special cases, p=0, is the default value that gives the entire axis, while p=-1 generates one point on the axis, namely the last point for the time axis and the midpoint for the space axes. Other values are vector range indicators, for example p=5 plots the fifth point, while p=1:4:41 plots every fourth point. For each graph type n the axes can be individually specified. If more than three axes are specified, only the first three are used. The others are set to default values.

```
in.axes{n} = {p1,p2,p3,..pd}
```

in.font

Default: {18}

This sets the default font size for the graph labels. This can be changed per graph.

```
in.font{n} > 0
```

in.minbar

```
Default: {0.01}
```

This is the minimum relative error-bar that is plotted. Set to a large value to suppress unwanted error-bars, although its best not to ignore the error-bar information!

```
in.minbar{n} >= 0
.. attribute:: in.esample
```

Default: {1}

This is the flag for plotting sampling error. Set to zero to suppress unwanted sampling error lines and just plot means, although its best not to ignore this information!

```
in.esample{n} >= 0
```

in.images

```
Default: {0, 0, 0, ...}
```

This is the number of 3D, transverse o-x-y movie images plotted as discrete time slices. Only valid if in.dimension is greater than 2. Note that, if present, the coordinates not plotted are set to their central value, for example z = 0, when plotting the transverse images. This input should have a value from in.images (n) = 0 up to a maximum value of the number of plotted time-points. It has a vector length equal to in.graphs:

```
in.images{n} = 0 ... in.points(1)
```

in.imagetype

```
Default: {1, 1, ...}
```

This is the *type* of transverse o-x-y movie images plotted. If an element is 1, a perspective surface plot is output, for 2, a gray plot with colours is output, or for 3 a contour plot with 10 equally spaced contours is generated. This has a vector length equal to *in.graphs*.

```
in.imagetype{n} = 1, 2, 3
```

in.transverse

```
Default: {0, 0, ...}
```

This is the number of 2D, transverse o-x images plotted as discrete time slices. Only valid if <code>in.dimension</code> is greater than 2. Note that, if present, the y,z-coordinates are set to their central values, when plotting the transverse images. Each element should be from 0 up to a maximum value of the number of plotted time-points. It has a vector length equal to <code>in.graphs</code>:

```
in.transverse{n}=0 ... in.points(1)
```

in.headers

```
Default: {'', '', ...}
```

This is a string variable giving the graph headers for each type of function plotted. The default value is an empty string '', which gives the simulation heading. Use a space '' for no headers. It is useful to include simulation headers - which is the default - to identify graphs in preliminary stages, while they may not be needed in a published final result.

```
in.headers{n} = 'my_graph_header'
```

in.pdimension

```
Default: {3, 3, ...}
```

This is the maximum space-time grid dimension for each plotted quantity. The purpose is eliminate unwanted graphs. For example, it may be useful to reduce the maximum dimension when averaging in space. Higher

dimensional graphs are not needed, as the data is duplicated. Averaging can be useful for checking conservation laws, or for averaging over homogeneous data to reduce sampling errors. All graphs are suppressed if it is set to zero. Any three dimensions can be chosen using the axes command.

```
in.pdimension{n} \ge 0
```

in.xlabels

```
Default: {'t', 'x', 'y', 'z'} or {'t', 'x_1', 'x_2', 'x_3'}
```

Global labels for the graph axis independent variable labels, vector length of in.dimension. The numerical labeling default is used when the in.numberaxis option is set. Note, these are typeset in Latex mathematics mode!

```
in.xlabels = {in.xlabels(1), ..., in.xlabels(in.dimension)}
```

in.klabels

```
\label{lem:default: properties} \begin{center} \textit{Default:} & $$ '' \otimes $'', 'k'_2', 'k'_2', 'k'_3'$ \\ \end{center} or & $$ '' \otimes $'', 'k'_2', 'k'_2', 'k'_3'$ \\ \end{center}
```

Global labels for the graph axis Fourier transform labels, vector length of in.dimension. The numerical labeling default is used when the in.numberaxis option is set. Note, these are typeset in Latex mathematics mode!

```
in.klabels = {in.klabels(1), ..., in.klabels(in.dimension)}
.. attribute:: in.glabels
```

```
Default: {{'t', 'x', 'y', 'z'}} or {{'\omega', 'k_x', 'k_y', 'k_z'}}
```

Graph-dependent labels for the independent variable labels, nested cell array with first dimension in.graph, second dimension in.dimension.

```
in.glabels{n} = {in.xlabels(1), ..., in.xlabels(in.dimension)}
.. attribute:: in.lines
```

```
Default: " { { '-k','-k',':k','-.k','-ok','-ok',':ok','-.ok','-+k','-+k' } } "
```

Line types for each line in every two-dimensional graph plotted.

```
in.lines{n} = {linetype{1}, ..., linetype{nl}}
```

Graphics projections

If there is a spatial grid, the graphics program automatically generates several graphs for each observable, depending on space dimension. The maximum dimension that is plotted as set by <code>in.pdimension</code>. In the plots, the lattice is projected down to successively lower dimensions.

For each observable, the projection sequence is as follows:

- If in. dimension is 4 or greater, a central z point nz = 1 + floor (in.points (4) / 2) is picked. For example, with 35 points, the central point is <math>nz = 18.
- This gives a three dimensional space-time lattice, which is treated the same as if in.dimension is 3.
- If in.images are specified, two-dimensional x y plots are generated at equally spaced time intervals. If
 there is only one image, it is at the last time-point. Different plot-types are used depending on the setting of
 in.imagetype.

- A central y point ny = 1 + floor (in.points (3)/2) is picked. This gives a two dimensional spacetime lattice, which is treated the same as if in.dimension is 2. If in.transverse is specified, onedimensional x plots are generated at equally spaced time intervals, as before.
- A central x point nx = 1 + floor(in.points(2)/2) is picked. This gives a one dimensional time lattice, which is treated the same as if in.dimension is 1.
- Plots of observable vs time are obtained, including sampling errors and error bars. If comparison graphs are specified using <code>in.compare()</code> functions, they are plotted also, using a dotted line. A difference graph is also plotted when there is a comparison.

8.12 Parameter structure

Internally, xSPDE parameters are stored in a cell array, latt, of structures r, which is passed to functions. This includes all the data given above inside the in structure. In addition, it includes the table of computed parameters given below.

User application constants and parameters should not be reserved names; in.c and all names starting with in.c will always be available in all versions of xSPDE.

A parameter structure contains information about the space-time grid and is passed to various functions, for instance in.da or in.step. The corresponding parameter is commonly marked as r.

r.t

Current value of time, t.

- r.x
- r.y
- r.z

Coordinate grids of x, y, z.

 $r.x\{n\}$

Higher dimensions are labeled numerically as x_1 ,... x_6 , and so on. This numerical axis convention can be set even for lower dimensions if in numberaxis is set to 1.

- r.**kx**
- r.ky
- r.kz

Grids in momentum space: k_x , k_y , k_z .

r.**k5**

Higher dimensions are labeled numerically as k_5 , k_6 , and so on.

r.**dt**

Output time-step between stored points for data averages.

r.dtr

Current reduced time-step used for integration.

r.dx

Steps in coordinate space: $[t, x, y, z, x_5, ..]$.

r.**dk**

Steps in momentum space: $[\omega, k_x, k_y, k_z, k_5, ..]$.

r.propagator

Contains the propagator array for the interaction picture.

r.V

Spatial lattice volume.

r.K

Momentum lattice volume.

r.dV

Spatial cell volume.

r.dK

Momentum cell volume.

r.xc

Space-time coordinate axes (vector cells).

r.kc

Computational Fourier transform axes in $[\omega, k_x, k_y, k_z, k_5, ..]$ (vector cells).

r.kg

Graphics Fourier transform axes in $[\omega, k_x, k_y, k_z, k_5, ...]$ (vector cells).

r.kranges

Range in $[\omega, k_x, k_y, k_z, k_5, ...]$ (vector).

r.s.dx

Initial stochastic normalization.

r.s.dxt

Propagating stochastic normalization.

r.s.dk

Initial k stochastic normalization.

r.s.**dkt**

Propagating k stochastic normalization.

r.nspace

Number of spatial lattice points: in.points(2) * .. * in.points(in.dimension).

r.nlattice

Total lattice: in.ensembles(1) * r.nspace.

r.ncopies

Total copies of stochastic integrations: in.ensembles(2) * in.ensembles(3).

r.d.int

Dimensions for lattice integration (vector).

r.d.a

Dimensions for a field (flattened, vector).

r.d.**r**

Dimensions for coordinates (flattened, vector).

r.d.ft

Dimensions for field transforms (vector).

r.d.k

Dimensions for noise transforms (vector).

r.d.obs

Dimensions for observations (vector).

r.d.data

Dimensions for average data (flattened, vector).

r.d.raw

Dimensions for raw data (flattened, vector).

8.13 Default functions

These functions are used as defaults for simulations and can be overridden by the user.

$xinitial(\sim, r)$

Returns a field array filled with zeros.

xtransfer (~, ~, a, ~)

Returns the field a unchanged.

$xda(\sim, \sim, r)$

Returns a derivative array filled with zeros.

$xlinear(\sim, r)$

Returns a linear response array filled with zeros.

xobserve (a, ~)

Returns the real part of a (1, :).

xrfilter(r)

Returns an array of ones.

xnfilter(r)

Returns an array of ones.

xgrid(r)

Sets grid points in lattice from coordinate vectors. Returns the r structure with added grid points.

xnoisegen(r)

Generates random noise matrix z.

xrandomgen (r)

Generates initial random field matrix v.

xpropfactor(nc, r)

Returns the interaction picture propagation factor. nc is a check index, r is a lattice structure.

8.14 Frequently asked questions

Answers to some frequent questions, and reminders of points in this chapter are:

- Can you average other stochastic quantities apart from the field?
 - Yes: just specify the functions that need to be averaged using the user function in.observe.
- Can you have functions of the current time and space coordinate?
 - Yes: xSPDE functions support this using the structure r, as r.t, r.x, r.y, r.z, or r.t, $r.x\{1\}$, and so on, for more than four space-time dimensions.
- Can you have several independent stochastic variables?
 - Yes, input this using in.fields > 1.

- Are higher dimensional differential equations possible?
 - Yes, this requires setting in.dimension > 1. This is essentially unlimited in xSPDE except for memory requirements.
- Can you have spatial partial derivatives?
 - Yes, provided they are linear in the fields; these are obtainable using the function in.linear.
- Can you delete the graph heading?
 - Yes, this is turned off if you set in. headers to 0.
- Why are there two lines in the graphs sometimes?
 - These are one standard deviation sampling error limits, generated when in ensembles (2, 3) > 1.
- Why is there just one line in some graphs, with no sampling errors indicated?
 - You need in.ensembles (2) or (3) for this; see previous question.
- What are the error bars for?
 - These are the estimated maximum errors due to finite step-sizes in time.

СНАРТЕ	:R
NIN	Ε

REFERENCES

CHAPTER

TEN

INDICES AND TABLES

- genindex
- modindex
- search

- [Gardiner2004] C. W. Gardiner, *Handbook of Stochastic Methods: for Physics, Chemistry and the Natural Sciences* (Springer 2004).
- [Colecutt2001] G. R. Collecutt, P. D. Drummond, *XMDS: eXtensible multi-dimensional simulator.* Comput. Phys. Commun. **142**, 219-223 (2001).
- [Dennis2013] Graham R. Dennis, Joseph J. Hope, Mattias T. Johnsson, *XMDS2: Fast, scalable simulation of coupled stochastic partial differential equations*, Comput. Phys. Commun. **184**, 201208 (2013).
- [Drummond1991] P. D. Drummond and I. K. Mortimer, *Computer simulations of multiplicative stochastic differential equations*. J. Comp. Phys. **93**, 144-170 (1991).
- [Kloeden1995] P. E. Kloeden and E. Platen, Numerical Solution of Stochastic Differential Equations (Springer, 1995).
- [Werner1997] M. J. Werner and P. D. Drummond, *Robust algorithms for solving stochastic partial differential equations*. J. Comp. Phys. **132**, 312-326 (1997).
- [Caradoc-Davies2000] B. M. Caradoc-Davies, *Vortex dynamics in Bose-Einstein condensates* (Doctoral dissertation, PhD thesis, University of Otago (NZ), 2000).
- [Higham2001] Desmond J. Higham, An Algorithmic Introduction to Numerical Simulation of Stochastic Differential Equations, SIAM Review 43, 525546 (2001).

116 Bibliography

A	1
a (r.d attribute), 90, 107	images (in attribute), 87, 104
axes (in attribute), 86, 103	imagetype (in attribute), 87, 104 in.compare() (built-in function), 86, 102
C	in.function() (built-in function), 85, 101
c (in attribute), 81, 98	in.gfunction() (built-in function), 102
cdata (built-in variable), 66	in.xfunctions() (built-in function), 85, 102
D	initial (in attribute), 82, 99
D	int (r.d attribute), 90, 107 ipsteps (in attribute), 84, 101
da (in attribute), 82, 99	iterations (in attribute), 83, 100
data (r.d attribute), 90, 107 dimension (in attribute), 80, 96	
dK (r attribute), 89, 107	K
dk (r attribute), 89, 106	K (r attribute), 89, 107
dk (r.s attribute), 90, 107	k (r.d attribute), 90, 107
dkt (r.s attribute), 90, 107	k5 (r attribute), 89, 106 kc (r attribute), 89, 107
dt (r attribute), 89, 106	kg (r attribute), 89, 107
dtr (r attribute), 89, 106 dV (r attribute), 89, 107	klabels (in attribute), 88, 105
dx (r attribute), 89, 106	kranges (r attribute), 89, 107
dx (r.s attribute), 89, 107	kx (r attribute), 89, 106
dxt (r.s attribute), 89, 107	ky (r attribute), 89, 106
E	kz (r attribute), 89, 106
	L
ensembles (in attribute), 81, 98 errorchecks (in attribute), 83, 100	latt (built-in variable), 65
choreneeks (m attribute), 63, 100	linear (in attribute), 82, 99
F	М
field (built-in variable), 67	
fields (in attribute), 80, 96	minbar (in attribute), 86, 103
file (in attribute), 84, 101	N
font (in attribute), 86, 103	name (in attribute), 80, 96
ft (r.d attribute), 90, 107	ncopies (r attribute), 90, 107
G	nfilter (in attribute), 83, 99
graphs (in attribute), 83, 86, 100, 103	nlattice (r attribute), 90, 107
grid (in attribute), 84, 101	noisegen (in attribute), 84, 101
gversion (in attribute), 86, 103	noises (in attribute), 80, 97 nspace (r attribute), 90, 107
Н	nspace (1 autibute), 70, 107
	0
headers (in attribute), 87, 104	obs (r.d. attribute) 90, 107

xlattice() (built-in function), 56

observe (in attribute), 82, 99 olabels (in attribute), 81, 103 order (in attribute), 83, 100 origin (in attribute), 84, 101	xlinear() (built-in function), 90, 108 xMP() (built-in function), 70 xnfilter() (built-in function), 91, 108 xnoisegen() (built-in function), 91, 108 xobserve() (built-in function), 90, 108 xpath() (built-in function), 58
pdimension (in attribute), 87, 104 points (in attribute), 80, 97 print (in attribute), 84, 100 prop (in attribute), 85, 102 propagator (r attribute), 89, 106 propfactor (in attribute), 85, 102	xprop() (built-in function), 58 xpropfactor() (built-in function), 91, 108 xrandomgen() (built-in function), 91, 108 xrfilter() (built-in function), 90, 108 xRK2() (built-in function), 70 xRK4() (built-in function), 70 xsim() (built-in function), 75, 92 xspde() (built-in function), 75, 92
r (r.d attribute), 90, 107	xtransfer() (built-in function), 90, 108
randomgen (in attribute), 85, 101 randoms (in attribute), 80, 97	Υ
ranges (in attribute), 80, 97	y (r attribute), 89, 106
raw (built-in variable), 67 raw (in attribute), 84, 100	Z
raw (r.d attribute), 90, 108 rfilter (in attribute), 82, 99	z (r attribute), 89, 106
S	
seed (in attribute), 83, 100 step (in attribute), 85, 101 steps (in attribute), 81, 97	
Т	
t (r attribute), 88, 106 transfer (in attribute), 82, 99 transforms (in attribute), 81, 98 transverse (in attribute), 87, 104	
V	
V (r attribute), 89, 106	
X	
x (r attribute), 89, 106 xave() (built-in function), 76, 93 xc (r attribute), 89, 107 xd, 77, 94 xda() (built-in function), 90, 108 xensemble() (built-in function), 56	
xEuler() (built-in function), 70 xgpreferences() (built-in function), 59 xgraph() (built-in function), 75, 92 xgrid() (built-in function), 91, 108 xinitial() (built-in function), 90, 108 xinpreferences() (built-in function), 56	
xint, 77, 93 xlabels (in attribute) 88, 105	

118 Index