
(a) vs ln L: the log law is a straight line
ground state $D_{gs}(L)$
$\beta = 0.5$
$\beta = 1$
$\beta = 1.5$
$\beta = 2$
$\beta = 3$
$\overline{D_2}$
ln L
(b) log-log: strong measurement is a line of slope 4
ground state $D_{gs}(L)$
(16/81) z^2 at $\beta = 3$ ($\propto L^4$)
L
(c) fixed β: the exponent falls from 4 toward the ground-state value
ground state $d\ln D_{gs}/d\ln L$
s = 4: volume-fraction law ($z^2 \propto L^4$)
local exponent $s = d\ln\overline{D_2}/d\ln L$
L (geometric mean of the two sizes)
(d) the same exponent against z
ground state, L=6 to 36
universal strong side $2\,d\ln f/d\ln z$
volume-fraction law (z < 0.3)
ln L regime: s inside the ground-state band
$z = L^2 e^{-2\beta}$ (geometric mean of the two points)