

实验报告

院 系 数据科学与计算机学院 学 号 _17341213 姓 名 _郑康泽

【实验题目】BGP 实验(选做)

【实验目的】掌握 BGP 协议的基本配置方法。

【实验说明】

- 1、BGP.pkt 已配置了接口 IP 地址和子网掩码(PC 机配置 IP 地址--Desktop/IP Configuration)。
- 2、BGP 协议的基本配置方法:

R4(config)#router bgp 500 ! 500 为 R4 所在 AS 号

R4(config)#neighbor 172.18.1.2 remote-as 400 ! BGP 邻居的直连接口的 IP 地址和 AS 号

R4(config) #network 112.78.6.43 mask 255.255.0.0 ! 要发布的网络

【实验软件】

在上传作业的地方可以下载。

PacketTracer 6.0 没有限制(推荐使用), PacketTracer7.2.1.(非破解版,安装后只能保存三次文件)

【实验任务】

在 BGP. pkt 的基础上(也可以自己从头建立,参见 PacketTracer. mp4):

(1) PCO 是否可以 Ping 通 PC1?

否。

- (2) 为所有路由器配置 BGP 邻居(直连),并发布 PC0 和 PC1 所连的网络,此时,PC0 应该可以 ping 通 PC1。给出 RO、R1、R2 的路由表。
 - 1)R0 的路由表:

```
%SYS-5-CONFIG_I: Configured from console by console
  Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
                i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
               * - candidate default, U - per-user static route, o - ODR P - periodic downloaded static route
   Gateway of last resort is not set
            66.0.0.0/24 is subnetted, 2 subnets
                  66.1.1.0 is directly connected, FastEthernet0/1
   В
                  66.1.2.0 [20/0] via 202.16.1.2, 00:14:26
           202.16.1.0/30 is subnetted, 1 subnets
                 202.16.1.0 is directly connected, FastEthernet0/0
2) R1 的路由表:
   Router#show ip route
   ROUGE::Snow p Poute
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
NI - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
El - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, Ll - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
              P - periodic downloaded static route
   Gateway of last resort is not set
```

3) R2 的路由表:

66.0.0.0/24 is subnetted, 2 subnets

66.1.1.0 [20/0] via 202.16.1.1, 00:09:57 66.1.2.0 [20/0] via 202.16.1.6, 00:09:57 202.16.1.0/30 is subnetted, 2 subnets 202.16.1.0 is directly connected, FastEthernet0/0 202.16.1.4 is directly connected, FastEthernet0/1



实验报告

```
$SYS-5-CONFIG_I: Configured from console by console
show ip route

Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
NI - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
i - IS-IS, Li - IS-IS level-1, L2 - IS-IS level-2, La - IS-IS inter area
* - candidate default, U - per-user static route, o - ODR
P - periodic downloaded static route

Gateway of last resort is not set

66.0.0.0/24 is subnetted, 2 subnets
B 66.1.1.0 [20/0] via 202.16.1.5, 00:14:10
C 66.1.2.0 is directly connected, FastEthernet0/1
202.16.1.0/30 is subnetted, 1 subnets
C 202.16.1.4 is directly connected, FastEthernet0/0
Router$
```

(3)解释 PC1 为何 ping 不通 202.16.1.2?如何可以让它 ping 通?写出配置语句。

R1 没有发布自己两个直连网,导致 R0 的路由表没有 202. 16. 1. 4/30 的网络,R2 的路由表没有 202. 16. 1. 0/30 的网络,所以当 PC1 在 ping 202. 16. 1. 2 的时候,它先把包发给默认网关 R2,R2 通过查表,发现没有 202. 16. 1. 0/30 的网络,就把包丢了,所以 PC1 不能 ping 通 202. 16. 1. 2。要想 ping 通,需让 R1 发布自己的两个直连网,让 R0 有 202. 16. 1. 4/30 的网络,R2 有 202. 16. 1. 0/30 的网络,配置命令如下(只需要修改 R1 的配置命令):

```
Router(config) #router bgp 200
Router(config-router) #neighbor 202.16.1.6 remote-as 300
Router(config-router) #network 202.16.1.0 mask 255.255.255.252
Router(config-router) #neighbor 202.16.1.1 remote-as 100
Router(config-router) #network 202.16.1.4 mask 255.255.255.252
```