# **Summary | Fluid Mechanics**

# Introduction

Study of Fluids Mechanics include

- Fluid Statics Equilibrium
- Fluid Kinematics Physical aspects of motion
- Fluid Dynamics Physical aspects of motion and causes of motion

### **Normal Forces**

Forces acting perpendicular to the plane of a surface.

### **Shear Forces**

Forces acting in the plane of a surface. When a fluid is at rest, no shear forces act on it.

### **Fluid**

A fluid is defined as a substance which flows continuously under the action of shear forces no matter how small the forces may be.

Liquids and gasses are considered fluids. Unlike solids, fluids don't show permanent resistance to deformation. Fluids are considered a continuum (continuously filled matter). We consider their bulk behaviours to solve fluid mechanics problems.

Properties at a point - defined for a fluid particle.

### Fluid Particle

Very small volume of fluid containing the point concerned.

Average values of properties for fluid particles are considered. Properties are assumed to vary gradually between particles.

# **Properties of Fluids**

# **Mass Density**

$$ho = rac{ ext{Mass}}{ ext{Volume}} = rac{m}{v}$$

At a point:

$$ho = \lim_{\delta v o 0} rac{\delta m}{\delta v}$$

### For liquids

Varies very slightly with temperature (negligible in calculations).

Example: Water

- $100kgm^{-3}$  at  $4\degree C$
- $995.7kgm^{-3}$  at  $30\degree C$

### For gases

Highly dependent on pressure & temperature.

# Specific Weight / Unit Weight

$$\omega = \gamma = rac{ ext{Weight}}{ ext{Volume}} = rac{w}{v}$$

# **Relative Density / Specific Density**

$$s = \sigma = rac{ ext{Density of the substance}}{ ext{Density of standard substance}}$$

For solids and liquids, water is the standard substance.

### **Bulk Modulus**

$$k = rac{ ext{Change in pressure}}{ ext{Change in volume, per volume}} = -rac{\Delta p}{rac{\Delta v}{v}} = -vrac{ ext{d}p}{ ext{d}v}$$

In terms of the density:

$$k=
horac{\mathrm{d}p}{\mathrm{d}
ho}$$

High bulk modulus means hard to compress.

# **Vapour Pressure**

Vaporisation is when evaporation happens at the free surface of a liquid.

Vapour Pressure is the pressure due to liquid vapour just above the free surface of the liquid. Increases with temperature.

A liquid boils when: vapour pressure = external pressure on the liquid

### **Surface Tension**

$$\sigma = rac{ ext{Tensile Force}}{ ext{length}} = rac{F}{L}$$

Negligible in many applications. Considered in small-scale applications. Causes capillary effect.

# **Viscosity**

The force resisting the flow of a liquid.

In liquids, viscosity is mainly caused by inter-molecular attraction. Decreases slightly with temperature.

In gases, mainly due to momentum exchange between molecules. Increases with temperature.

## Newton's law of viscosity

In straight & parallel flow, the shear stress  $\tau$  (as in  $\frac{F}{A}$ ) between adjacent layers is proportional to the velocity gradient perpendicular to the layers.

$$au \propto rac{\delta v}{\delta y} (= ext{velocity gradient})$$

As  $\delta y 
ightarrow 0$ ,

$$au = \mu rac{\partial v}{\partial y}$$

## **Coefficient of dynamic viscosity**

Above,  $\mu$  is coefficient of dynamic viscosity or coefficient of absolute viscosity or coefficient of viscosity.

Fluids can be divided into 2 types:

- $\mu$  is a constant: Newtonian fluid
- $\mu$  is not a constant: Non-newtonian fluid (**not** focused on for s1)

# Coefficient of kinematic viscosity


$$v=rac{\mu}{
ho}$$


### **Pressure**

A force is exerted on all surfaces in contact with a fluid. A scalar.

$$P = rac{ ext{Normal Force}}{ ext{Area}} = rac{F}{A}$$

# **Hydrostatic Pressure**





At a point,


$$P = \lim_{\delta A o 0} rac{\delta F}{\delta A}$$

## Pascal's law

The hydrostatic pressure at a point is the same from all directions. Applies only for hydrostatic pressure.

#### **Proof**

Consider the fluid element shown, containing the point  $oldsymbol{A}.$ 



From the image:  $\sin \theta = \frac{\Delta z}{\Delta s} \ \land \ \cos \theta = \frac{\Delta x}{\Delta s}$ 

For equilibrium:

$$P_x(\Delta y \Delta z) - P_s(\Delta y \Delta s) \sin \theta = 0 \implies P_x = P_s$$

$$P_z(\Delta x \Delta y) - P_s(\Delta y \Delta s) \cos heta - rac{1}{2} \Delta x \Delta y \Delta z 
ho g = 0 \implies P_z = P_s + rac{1}{2} \Delta z 
ho g$$

As all  $\Delta x, \Delta y, \Delta z$  approaches 0:  $P_z = P_s$ . Therefore  $P_x = P_z = P_s$ 

# Variation along directions


#### **Proof**

Let p be the pressure at the point  $A\equiv (x,y,z)$ .

$$p = f(x, y, z)$$

$$dp = \frac{\partial p}{\partial x} dx + \frac{\partial p}{\partial y} dy + \frac{\partial p}{\partial z} dz$$

By considering equilibrium of this fluid element containing  $m{A}$ .



In the x direction,

$$egin{split} igg(p-rac{\partial p}{\partial x}rac{\Delta x}{2}igg)\Delta y\Delta z - igg(p+rac{\partial p}{\partial x}rac{\Delta x}{2}igg)\Delta y\Delta z = 0 \ & rac{\partial p}{\partial x} = 0 \end{split}$$

Similarly  $rac{\partial p}{\partial y}=0$  can be proven.

In the z direction,

$$\left(p - rac{\partial p}{\partial z} rac{\Delta z}{2}
ight) \Delta x \Delta y - \left(p + rac{\partial p}{\partial z} rac{\Delta z}{2}
ight) \Delta x \Delta y - \Delta x \Delta y \Delta z 
ho g = 0$$
  $rac{\partial p}{\partial z} = -
ho g$   $dp = -
ho g \, dz$   $p = -\int 
ho g \, dz$ 

## (i) For incompressible fluids

$$ho$$
 is constant.  $p=-
ho g\int \mathrm{d}z=-
ho gz+c=f(z)$  .

# Piezometric pressure


$$P = -\rho gz + c$$

$$P + \rho gz = c = P^*$$

# Isobar

Surface of constant pressure.

# Pressure difference between 2 points



$$P_1=-
ho g z_1+c$$
  $P_2=-
ho g z_2+c$   $P_2-P_1=-
ho g (z_2-z_1)=-
ho g (-h)=h
ho g$   $P_2=P_1+h
ho g$ 

In a homogenous, incompressible fluid in equilibrium:

- 1. Piezometric pressure is constant throughout the fluid
- 2. Pressure varies linearly with depth only
- 3. Isobars are horizontal

# **Pressure**

# **Atmospheric Pressure**

Pressure exerted by atmospheric air.

# **Gauge Pressure**

Measured in respect to atmospheric pressure.

### **Absolute Pressure**

Measured in respect to perfect vaccum.

 ${\bf Absolute\ Pressure = Armospheric\ Pressure + Guage\ Pressure}$ 

# **Pressure diagram**

A diagram showing the variation of pressure along a submerged surface.


## **Pressure Head**

Height of a particular fluid column that will produce the pressure at a point.

$$\text{Pressure head} = h = \frac{p}{\gamma}$$

# **Pressure Measurements**


## **Barometer**



# Piezometer

Open-ended tube connected to a vessel / pipe containing a liquid.

Measures the pressure head of a liquid.




### **Advantages**

- Simple
- Small pressure differences can be measured

## **Disadvantages**

- · Only for liquids
- Long tube required to measure even moderate pressures

### **Manometer**




Hydrostatic principle is used here. Measures absolute pressue. Manometer liquid should not mix with the liquid in which the pressure is to be measured.

$$P_x = P_y$$
  $P_A + a
ho g = P_{
m atm} + h
ho_m g$   $P_A = P_{
m atm} + h
ho_m - a
ho g$ 

If  $P_{
m atm}=0$ ,  $P_A=h
ho_m-a
ho g$ . That's gauge pressure.

### **Differential Manometer**



Used to measure pressure difference between two points. Can be used for both liquids and gases. Difficult to measure small pressure differences (because small displacement of manometer liquid).

# **Pressure Gauges**

## **Bourdon Pressure Gauge**

### **Advantages**

- Easy to use
- Wide range of pressures can be measured

### **Disadvantages**

- Not very accurate
- Needs to be calibrated regularly

# **Hydrostatic Thrust**

### On a Plane Surface

Acts **normal to the surface** on the point on the surface known as **the Centre of Pressure** with a magnitude of:

Thrust = submerged area 
$$\times P_c$$

 ${m C}$  is the centroid of the submerged area.  ${m P_c}$  is the pressure at the centroid.

#### **Centre of Pressure**

$$y_p = y_c + rac{I_{
m cc}}{A \cdot y_c}$$


Here:

- $oldsymbol{\cdot}$  A Total submerged area
- $oldsymbol{y_p}$  Distance to centre of pressure measured along the submerged surface from the free surface
- $y_c$  Distance to  $\it C$  measured along the submerged surface from the free surface
- $I_{
  m cc}$  Second moment of submerged area about the centroidal axis parallel to the free surface

# (i) For a plane surface

$$\frac{\text{Hydrostatic thrust}}{\text{Unit length}} = \text{Area of the pressure diagram}$$

#### **Proof**



### (i) Note

OO' is the free surface (waterline plane). It is not a surface inside the fluid. It's drawn like that for ease of reference.

#### **Direction**

All forces acting on the surface is normal to the surface. Therefore  $m{F}$  is normal to the surface.

### Magnitude

$$F=\int_A \mathrm{d}F=\int_A p \mathrm{d}A=\int_A y sin heta 
ho g\,\mathrm{d}A$$
 $F=sin heta 
ho g\int_A y\,\mathrm{d}A=sin heta 
ho g\cdot Ay_c=A\cdot y_c sin heta 
ho g$  $F=AP_c$ 

#### Line of action


$$F \cdot y_p = \int_A y \, \mathrm{d}F \ y_p = \int_A y \, \mathrm{d}F$$
  $y_p = rac{\int_A y \, \mathrm{d}F}{\int_A y \, \mathrm{d}F} = rac{\int_A y (y sin heta 
ho g) \, \mathrm{d}A}{\int_A y sin heta 
ho g \, \mathrm{d}A} = rac{\int_A y^2 \, \mathrm{d}A}{\int_A y \, \mathrm{d}A} \ y_p = rac{I_{oo}}{Ay_c} = y_c + rac{I_{cc}}{Ay_c}$ 

## On a Curved Surface

 $F_x =$  Thrust exerted on the vertical projection of the submerged surface

 $F_y =$ Weight of the fluid above submerged surface

### **Proof**



For the equilibrium of the fluid volume ABCDA.

$$F_y = W_{ABCDA}$$

For the equilibrium of the fluid volume ABEA.

$$F_x = F_{AE}$$

### (i) Tensile stress in pipe

For a pipe with inner diameter d and thickness t containing a liquid under pressure p, experiences a tensile stress  $f=rac{pd}{2t}$ .

# **Centre of Pressure Derivations**

Shape	Description	$y_p$
Rectangle or Parallelogram	Base $m{b}$ . Height $m{h}$ . Base is at the free surface.	$\frac{2h}{3}$
Triangle	Base $m{b}$ . Height $m{h}$ . Base is at the free surface.	$\frac{5h}{6}$

# **Buoyancy**

Thrust exerted on a submerged object in a liquid. Direction is vertically upwards. Line of action passes through center of buoyancy.

$$u= ext{weight of the fluid volume displaced}=v
ho g$$

Here:

- $oldsymbol{u}$  the upthrust
- $oldsymbol{v}$  the submerged volume
- $\rho$  density of the fluid

# **Center of buoyancy**

Center of gravity of the displaced fluid volume. **NOT** the center of gravity of the submerged object.

### **Proof**

Forces exerted on the submerged object is equivalent to forces exerted on the displaced volume before it was displaced.

Consider the equilibrium of displaced volume before it was displaced:

Weight 
$$= W = \text{Resultant}$$
 force exerted by surrounding liquid  $= F$ 

 $m{F}$  must be equal to  $m{W}$ , opposite to  $m{W}$  and acts through  $m{G}$  of the considered volume of fluid.

# Stability of fully submerged bodies

Equilibrium type	Description
Stable	$oldsymbol{B}$ is above $oldsymbol{G}$
Unstable	$oldsymbol{B}$ is below $oldsymbol{G}$
Neutral	$B\equiv G$

# Stability of floating bodies

Suppose a body of weight W acting through the centre of gravity G is floating in a fluid is at equilibrium. The buoyancy U acts through the centre of buoyancy B.

#### Metacentre

Intersection point between the line of action of  $\emph{U}$  through  $\emph{B}$  AND the axis  $\emph{BG}$ . Denoted by  $\emph{M}$ .

For small displacements  $oldsymbol{M}$  is fixed in position relative to the body.

# **Stability conditions**

Equilibrium type	Description	Condition
Stable	$oldsymbol{M}$ is above $oldsymbol{G}$	GM>0
Unstable	$oldsymbol{M}$ is below $oldsymbol{G}$	GM < 0

Equilibrium type	Description	Condition
Neutral	$M\equiv G$	GM=0

## **Metacentric height**

The distance GM. Measured upwards from G.

### **Metacentric radius**

The distance BM. Measured upwards from B.




Metacentric height and metacentric radius are related by: BM = BG + GM.

# **Determination of metacentric height**

## **Experimental value**

The metacentric height of a floating body can be determined experimentally by shifting a known weight by a known distance and measuring the angle of tilt.



In the above picture

- $oldsymbol{\cdot}$  P a small mass
- $m{G}$  initial centre of mass
- $oldsymbol{\cdot}$   $oldsymbol{B}$  initial centre of buoyancy
- $oldsymbol{\cdot}$   $oldsymbol{W}$  total weight of floating body
- $oldsymbol{U}$  upthrust exerted on floating body
- $G^\prime$  new centre of mass
- $B^\prime$  new centre of buoyancy
- $m{x}$  small displacement applied to  $m{P}$

Considering the shift in centre of gravity:


$$W(GG') = Px + 0(W-P) \implies GG' = rac{Px}{W}$$

When heta is very small:  $GG' = rac{Px}{W} pprox (GM) heta \implies GM pprox rac{Px}{W heta}$ 

$$GM = \lim_{ heta o 0} rac{Px}{W heta}$$

### **Theoretical value**

If the shape of the submerged volume is known, the metacentric height can theoretically be determined.



### Rotation is about centroidal axis of waterline plane

As the submerged volume remains unchanged during angular displacement, it can be derived that the rotation occurs about the centroidal axis of the waterline plane.

$$\int_O^C x an heta \, \mathrm{d}A = \int_O^A x an heta \, \mathrm{d}A \implies \int_O^C x \, \mathrm{d}A = 0 = A \overline{x}$$

Here,

- $oldsymbol{\cdot}$  A area of waterline plane
- $\overline{x}$  distance to the centroid from axis OO

### **Equation for metacentric radius**

Considering the shift in centre of buoyancy:

$$U(BB') = \int_O^C x heta 
ho g \cdot x \, \mathrm{d}A - \int_O^A x heta 
ho g \cdot x \, \mathrm{d}A$$

$$V
ho g(BB') = heta 
ho g \Bigg( \int_O^C x^2 \, \mathrm{d}A - \int_O^A x^2 \, \mathrm{d}A \Bigg)$$

$$V(BB') = hetaigg(\int_A^C x^2\,\mathrm{d}Aigg) = I heta$$

Here


- $oldsymbol{\cdot}$  V submerged volume
- I second moment of area of the waterline plane about the centroidal axis  $\it OO$

$$BB' = \frac{I\theta}{V} \approx (BM)\theta \implies BM = \frac{I}{V}$$

### (i) Note

This result is restricted to small angular displacements — usually up to about  $8^{\circ}$ — and the restriction is particularly important when the sides of the floating body are not vertical.

# **Types of tilting**



- Pitching tilting about transverse axis
- · Rolling tilting about longitudinal axis

# Time period of oscillation

Below equation can be derived by using  $T=I\ddot{ heta}$  (for small heta):

$$T=-W(\mathrm{GM})\sin heta=I_G\ddot{ heta}$$

$$rac{\mathrm{d}^2 heta}{\mathrm{d}t^2} = -rac{W(\mathrm{GM})}{I_G} heta = -rac{Mg(\mathrm{GM})}{Mk^2} heta$$

Here

- $m{k}$  Radius of gyration
- $m{M}$  Total mass
- $I_G$  Moment of inertia of the floating body about  $\,G\,$

Period of time of oscillation is given by:

$$T=rac{2\pi k}{\sqrt{g({
m GM})}}$$

# Liquid cargo in a vessel

- Liquid cargo in a vessel reduces its geocentric height.
- When the cargo is contained in 1 compartment:

$$\Delta ext{GM}_1 = rac{
ho_1 I_1}{
ho v}$$

- When the liquid cargo is contained in  $\, n \,$  compartments:

$$\Delta \mathrm{GM} = rac{1}{n^2} (\Delta \mathrm{GM}_1)$$

# **Relative Equilibrium**

When a fluid-contained vessel moves with a constant acceleration it will be transmitted to the fluid. The fluid particles will move to a new position and remain in such position in equilibrium, relative to the vessel. Such equilibrium is known as the Relative Equilibrium of a fluid.

### **Under linear acceleration**


No flow of the fluid (relative to the fluid particles). No shear forces, and all forces are normal to the surface they act on. Hence, fluid statics equations can be used in relative equilibrium.

### Variation of pressure

Let 
$$P = f(x, y, z)$$
.

$$\mathrm{d}p = rac{\partial p}{\partial x} \mathrm{d}x + rac{\partial p}{\partial y} \mathrm{d}y + rac{\partial p}{\partial z} \mathrm{d}z$$

Consider the fluid element containing point A which is under an acceleration of  $a_x, a_y, a_z$  in the x, y, z directions.



By applying Newton's second law of motion in all 3 directions:

$$rac{\partial p}{\partial x} = -
ho a_x \ \wedge \ rac{\partial p}{\partial y} = -
ho a_y$$
  $rac{\partial p}{\partial z} = -
ho (a_z + g)$ 

Substituting all the terms:

$$\mathrm{d}p = -
ho a_x \mathrm{d}x - 
ho a_y \mathrm{d}y - 
ho (a_z + g) \mathrm{d}z$$

Integrating both sides:

$$P = -\rho a_x x - \rho a_y y - \rho (a_z + g) z + c_1$$

# **Shape of free surface**

On the free surface P=0 as gauge pressure is considered.

$$ho a_x x + 
ho a_y y + 
ho (a_z + g) z = c_1$$

Free surface is a plane surface in 3D.

### Inclination with horizontal plane

### **∴** Caution

I am unsure whether this section is 100% correct.

Suppose a vessel is in acceleration in  $a_x,a_z$  in x,z directions and  $a_y=0$ . If  $heta_x, heta_y$  are the angles in x,y directions.

$$an\left( heta_{x}
ight)=rac{\mathrm{d}z}{\mathrm{d}x}\ \wedge\ an\left( heta_{y}
ight)=rac{\mathrm{d}z}{\mathrm{d}y}$$

Differentiating the equation of the free surface with respect to x.

$$ho a_x + 
ho (a_z + g) rac{\mathrm{d}z}{\mathrm{d}x} = 0 \implies an \left( heta_x
ight) = rac{-a_x}{a_z + g}$$

And similarly for y:

$$ho a_y + 
ho (a_z + g) rac{\mathrm{d}z}{\mathrm{d}y} = 0 \implies an \left( heta_y
ight) = rac{-a_y}{a_z + g}$$

# **Under Horizontal Acceleration**

$$a_x \neq 0 \ \land \ a_y = a_z = 0$$


# **Equation of the free surface**

$$\rho a_x x + \rho g z = c_1$$

Is a straight line in x,z axes. The straight line is at an inclination of  $heta_x$ :

$$an\left( heta_{x}
ight)=rac{-a_{x}}{a}$$

## **Vertical Pressure Distribution**



# **Under Vertical Acceleration**


$$a_z \neq 0 \ \land \ a_x = a_y = 0$$

# **Equation of the free surface**

$$\rho(a_z + g)z = c_1$$

Horizontal straight line.

## **Vertical Pressure Distribution**



$$P_1 = -
ho(a_z+g)z_1 + c_1$$
  $P_2 = -
ho(a_z+g)z_2 + c_1$   $P_2 - P_1 = -
ho(a_z+g)(z_2-z_1)$   $P_2 = h
ho(a_z+g)$ 

Here:

- h
  ho g hydrostatic pressure
- $h
  ho a_z$  due to  $a_z$


Varies only in z direction. Increases with height. Isobars are horizontal.

# **Forced Vortex Motion**

Another type of relative equilibrium. If a fluid-contained vessel is rotating at a constant angular velocity, the fluid will reach a relative equilibrium position and rotate with the vessel. Under this condition, the fluid is said to be in Forced Vortex Motion.

# (i) Note

For S1, forced vortex motion, only about vertical axis, is required.



$$P=rac{1}{2}
ho\omega^2r^2-
ho gz+c$$

#### Here:

•  $\omega$  - angular velocity



## **⚠ TODO**

Explain how to derive the above equation.

# **Equation of the free surface**

On the free surface P=0.


$$z=rac{\omega^2}{2g}r^2+c_0$$

The free surface is **parabolic**. The constant part  $c_0$  can be found by a known point of the free surface. For ease of calculations, the axes can be chosen so that the free surface passes through (0,0). In that case,  $c_0=0$ .

## **Vertical Pressure Distribution**

Pressure increases linearly with height. Increases exponentially with radial distance. Isobars are parabolic.

# Volume of the fluid



Total volume of the fluid is:

$$V=\pi R^2h_0+rac{1}{2}\pi R^2(H-h_0)=\pi R^2h$$
  $\Longrightarrow V=rac{1}{2}\pi R^2(H+h_0)=\pi R^2h$   $\Longrightarrow H+h_0=2h$ 

This PDF is saved from https://s1.sahithyan.dev