Summary | Fluid Mechanics

Introduction

Study of Fluids Mechanics include

- Fluid Statics Equilibrium
- Fluid Kinematics Physical aspects of motion
- Fluid Dynamics Physical aspects of motion and causes of motion

Normal Forces

Forces acting perpendicular to the plane of a surface.

Shear Forces

Forces acting in the plane of a surface. When a fluid is at rest, no shear forces act on it.

Fluid

A fluid is defined as a substance which flows continuously under the action of shear forces no matter how small the forces may be.

Liquids and gasses are considered fluids. Unlike solids, fluids don't show permanent resistance to deformation. Fluids are considered a continuum (continuously filled matter). We consider their bulk behaviours to solve fluid mechanics problems.

Properties at a point - defined for a fluid particle.

Fluid Particle

Very small volume of fluid containing the point concerned.

Average values of properties for fluid particles are considered. Properties are assumed to vary gradually between particles.

Properties of Fluids

Mass Density

$$ho = rac{ ext{Mass}}{ ext{Volume}} = rac{m}{v}$$

At a point:

$$ho = \lim_{\delta v o 0} rac{\delta m}{\delta v}$$

For liquids

Varies very slightly with temperature (negligible in calculations).

Example: Water

- $100kgm^{-3}$ at $4\degree C$
- $995.7kgm^{-3}$ at $30\degree C$

For gases

Highly dependent on pressure & temperature.

Specific Weight / Unit Weight

$$\omega = \gamma = rac{ ext{Weight}}{ ext{Volume}} = rac{w}{v}$$

Relative Density / Specific Density

$$s=\sigma=rac{ ext{Density of the substance}}{ ext{Density of standard substance}}$$

For solids and liquids, water is the standard substance.

Bulk Modulus

$$k=rac{ ext{Change in pressure}}{ ext{Change in volume, per volume}}=-rac{\Delta p}{rac{\Delta v}{v}}=-vrac{ ext{d}p}{ ext{d}v}$$

In terms of the density:

$$k=
horac{\mathrm{d}p}{\mathrm{d}
ho}$$

High bulk modulus means hard to compress.

Vapour Pressure

Vaporisation is when evaporation happens at the free surface of a liquid.

Vapour Pressure is the pressure due to liquid vapour just above the free surface of the liquid. Increases with temperature.

A liquid boils when: vapour pressures = external pressure on the liquid

Surface Tension

$$\sigma = rac{ ext{Tensile Force}}{ ext{length}} = rac{F}{L}$$

Negligible in many applications. Considered in small-scale applications. Causes capillary effect.

Viscosity

The force resisting the flow of a liquid.

In liquids, viscosity is mainly caused by inter-molecular attraction. Decreases slightly with temperature.

In gases, mainly due to momentum exchange between molecules. Increases with temperature.

Newton's law of viscosity

In straight & parallel flow, the shear stress between adjacent layers is proportional to the velocity gradient perpendicular to the layers.

$$au \propto rac{\delta v}{\delta y} (= ext{velocity gradient})$$

Here, au is stress. Force per unit area (as in $\frac{F}{A}$).

$$au = \mu rac{\delta v}{\delta y}$$

Finally we will get Newton's law of viscosity as $\delta y
ightarrow 0$,

$$au = \mu rac{\partial v}{\partial y}$$

Coefficient of dynamic viscosity

Above, μ is coefficient of dynamic viscosity or coefficient of absolute viscosity or coefficient of viscosity.

Fluids can be divided into 2 parts:

- $oldsymbol{\mu}$ is a constant: Newtonian fluid
- μ is not a constant: Non-newtonian fluid

Only Newtonian fluids are focused on for s1.

Coefficient of kinematic viscosity


$$v = rac{\mu}{
ho}$$


Pressure

A force is exerted on all surfaces in contact with a fluid. A scalar.

$$P = rac{ ext{Normal Force}}{ ext{Area}} = rac{F}{A}$$

Hydrostatic Pressure





At a point,


$$P = \lim_{\delta A o 0} rac{\delta F}{\delta A}$$

Pascal's law

The hydrostatic pressure at a point is the same from all directions. Applies only for hydrostatic pressure.

Proof

Consider the fluid element shown, containing the point $oldsymbol{A}$.



From the image: $\sin \theta = \frac{\Delta z}{\Delta s} \ \land \ \cos \theta = \frac{\Delta x}{\Delta s}$

For equilibrium:

$$P_x(\Delta y \Delta z) - P_s(\Delta y \Delta s) \sin \theta = 0 \implies P_x = P_s$$

$$P_z(\Delta x \Delta y) - P_s(\Delta y \Delta s) \cos heta - rac{1}{2} \Delta x \Delta y \Delta z
ho g = 0 \implies P_z = P_s + rac{1}{2} \Delta z
ho g$$

As all $\Delta x, \Delta y, \Delta z$ approaches 0: $P_z = P_s$. Therefore $P_x = P_z = P_s$

Variation along directions


Proof

Let p be the pressure at the point $A \equiv (x,y,z)$.

$$p = f(x, y, z)$$

$$dp = rac{\partial p}{\partial x} \mathrm{d}x + rac{\partial p}{\partial y} \mathrm{d}y + rac{\partial p}{\partial z} \mathrm{d}z$$

By considering equilibrium of this fluid element containing $oldsymbol{A}$.



In the $oldsymbol{x}$ direction,

$$egin{split} igg(p-rac{\partial p}{\partial x}rac{\Delta x}{2}igg)\Delta y\Delta z - igg(p+rac{\partial p}{\partial x}rac{\Delta x}{2}igg)\Delta y\Delta z = 0 \ & rac{\partial p}{\partial x} = 0 \end{split}$$

Similarly $rac{\partial p}{\partial y}=0$ can be proven.

In the z direction,

$$\left(p - rac{\partial p}{\partial z} rac{\Delta z}{2}
ight) \Delta x \Delta y - \left(p + rac{\partial p}{\partial z} rac{\Delta z}{2}
ight) \Delta x \Delta y - \Delta x \Delta y \Delta z
ho g = 0$$
 $rac{\partial p}{\partial z} = -
ho g$ $dp = -
ho g \, dz$ $p = -\int
ho g \, dz$


$$\odot$$
 For incompressible fluids ho is constant. $p=-
ho g\int \mathrm{d}z=-
ho gz+c=f(z)$.

Piezometric pressure

$$P = -\rho gz + c$$

$$P + \rho gz = c = P^*$$

Pressure difference between 2 points



$$P_1=-
ho gz_1+c$$
 $P_2=-
ho gz_2+c$ $P_2-P_1=-
ho g(z_2-z_1)=-
ho g(-h)=h
ho g$ $P_2=P_1+h
ho g$

In a homogenous, incompressible fluid in equilibrium:

- 1. Piezometric pressure is constant throughout the fluid
- 2. Pressure varies linearly with depth only
- 3. Isobars (surface of constant pressure) are horizontal.

Pressure

Atmospheric Pressure

Pressure exerted by atmospheric air.

Gauge Pressure

Measured in respect to atmospheric pressure.

Absolute Pressure

Measured in respect to perfect vaccum.

$Absolute\ Pressure = Armospheric\ Pressure + Guage\ Pressure$

Pressure diagram


A diagram showing the variation of pressure along a submerged surface.

Uses in real life

Hydraulic jack

Pressure Measurements


Barometer



Piezometer

Open-ended tube connected to a vessel / pipe containing a liquid.

Measures the pressure head of a liquid.




Advantages

- Simple
- Small pressure differences can be measured

Disadvantages

- Only for liquids
- Long tube required to measure even moderate pressures

Manometer




Hydrostatic principle is used here. Measures absolute pressue. Manometer liquid should not mix with the liquid in which the pressure is to be measured.

$$P_x = P_y$$
 $P_A + a
ho g = P_{
m atm} + h
ho_m g$ $P_A = P_{
m atm} + h
ho_m - a
ho g$

If $P_{
m atm}=0$, $P_A=h
ho_m-a
ho g$. That's gauge pressure.

Differential Manometer



Used to measure pressure difference between two points. Can be used for both liquids and gases. Difficult to measure small pressure differences (because small displacement of manometer liquid).

Pressure Gauges

Bourdon Pressure Gauge

Advantages

- Easy to use
- Wide range of pressures can be measured

Disadvantages

- Not very accurate
- Needs to be calibrated regularly

Pressure Head

Pressure head is the height of a particular fluid column that will produce the pressure at a point.

Pressure head =
$$h = \frac{p}{\gamma}$$

Hydrostatic Thrust

On a Plane Surface

Acts **normal to the surface** on the point on the surface known as **the Centre of Pressure** with a magnitude of:

Thrust = submerged area
$$\times P_c$$

 ${m C}$ is the centroid of the submerged area. ${m P}_c$ is the pressure at the centroid.

Centre of Pressure

$$y_p = y_c + rac{I_{
m cc}}{A \cdot y_c}$$


Here:

- $oldsymbol{\cdot}$ A Total submerged area
- $oldsymbol{y}_p$ Distance to centre of pressure measured along the submerged surface from the free surface
- y_c Distance to $\it C$ measured along the submerged surface from the free surface
- $I_{
 m cc}$ Second moment of submerged area about the centroidal surface parallel to the free surface

(i) For a plane surface

$$\frac{\text{Hydrostatic thrust}}{\text{Unit length}} = \text{Area of the pressure diagram}$$

Proof



(i) Note

OO' is the free surface (waterline plane). It is not a surface inside the fluid. It's drawn like that for ease of reference.

Direction

All forces acting on the surface is normal to the surface. Therefore $m{F}$ is normal to the surface.

Magnitude

$$F=\int_A \mathrm{d}F=\int_A p \mathrm{d}A=\int_A y sin heta
ho g\,\mathrm{d}A$$

$$F=sin heta
ho g\int_{A}y\,\mathrm{d}A=sin heta
ho g\cdot Ay_{c}=A\cdot y_{c}sin heta
ho g$$
 $F=AP_{c}$

Line of action


$$F \cdot y_p = \int_A y \, \mathrm{d}F \ y_p = \int_A y \, \mathrm{d}F \ y_p = rac{\int_A y \, \mathrm{d}F}{\int_A y \, \mathrm{d}F} = rac{\int_A y (y sin heta
ho g) \, \mathrm{d}A}{\int_A y sin heta
ho g \, \mathrm{d}A} = rac{\int_A y^2 \, \mathrm{d}A}{\int_A y \, \mathrm{d}A} \ y_p = rac{I_{oo}}{Ay_c} = y_c + rac{I_{cc}}{Ay_c}$$

On a Curved Surface

 $F_x =$ Thrust exerted on the vertical projection of the submerged surface

 $F_y =$ Weight of the fluid above submerged surface

Proof



For the equilibrium of the fluid volume ABCDA.

$$F_y = W_{ABCDA}$$

For the equilibrium of the fluid volume ABEA.

$$F_x = F_{AE}$$

(i) Tensile stress in pipe

For a pipe with inner diameter d and thickness t containing a liquid under pressure p, experiences a tensile stress $f=rac{pd}{2t}$.

Buoyancy

Thrust exerted on a submerged object in a liquid. Direction is vertically upwards. Line of action passes through center of buoyancy.

$$u= ext{weight of the fluid volume displaced}=v
ho g$$

Here:

- $oldsymbol{u}$ the upthrust
- $oldsymbol{v}$ the submerged volume
- ρ density of the fluid

Center of buoyancy

Center of gravity of the displaced fluid volume. *NOT* the center of gravity of the submerged object.

Proof

Forces exerted on the submerged object is equivalent to forces exerted on the displaced volume before it was displaced.

Consider the equilibrium of displaced volume before it was displaced:

Weight
$$= W = \text{Resultant force exerted by surrounding liquid} = F$$

 $m{F}$ must be equal to $m{W}$, opposite to $m{W}$ and acts through $m{G}$ of the considered volume of fluid.

Stability of fully submerged bodies

Equilibrium type	Description
Stable	$oldsymbol{B}$ is above $oldsymbol{G}$
Unstable	$oldsymbol{B}$ is below $oldsymbol{G}$
Neutral	$B\equiv G$

Stability of floating bodies

Suppose a body of weight W acting through the centre of gravity G is floating in a fluid is at equilibrium. The buoyancy U acts through the centre of buoyancy B.

Metacentre

Intersection point of the line of action of $oldsymbol{U}$ through $oldsymbol{B}$ and the axis $oldsymbol{B}oldsymbol{G}$.



For small displacements $oldsymbol{M}$ is fixed in position relative to the body.

Stability conditions

Equilibrium type	Description	Condition
Stable	$oldsymbol{M}$ is above $oldsymbol{G}$	GM>0
Unstable	$oldsymbol{M}$ is below $oldsymbol{G}$	GM < 0
Neutral	$M\equiv G$	GM=0

Metacentric height

The distance GM. Measured upwards from G.

Metacentric radius

The distance BM. Measured upwards from B.


(i) Note

Metacentric height and metacentric radius are related by: $\emph{GM} = \emph{BM} - \emph{BG}$.

Determination of metacentric height

Experimental value

The metacentric height of a floating body can be determined experimentally by shifting a known weight by a known distance and measuring the angle of tilt.



In the above picture

- $oldsymbol{\cdot}$ P a small mass
- $m{G}$ initial centre of mass
- $oldsymbol{\cdot}$ $oldsymbol{B}$ initial centre of buoyancy
- $oldsymbol{\cdot}$ $oldsymbol{W}$ total weight of floating body
- $oldsymbol{\cdot}$ U upthrust exerted on floating body
- $oldsymbol{G'}$ new centre of mass
- B^\prime new centre of buoyancy
- $m{x}$ small displacement applied to $m{P}$

Considering the shift in centre of gravity:


$$W(GG') = Px + 0(W-P) \implies GG' = rac{Px}{W}$$

When heta is very small: $GG' = rac{Px}{W} pprox (GM) heta \implies GM pprox rac{Px}{W heta}$

$$GM = \lim_{ heta o 0} rac{Px}{W heta}$$

Theoretical value

If the shape of the submerged volume is known, the metacentric height can theoretically be determined.



Rotation is about centroidal axis of waterline plane

As the submerged volume remains unchanged during angular displacement, we can derive that the rotation occurs about the centroidal axis of the waterline plane.

$$\int_{O}^{C} x an heta \, \mathrm{d}A = \int_{O}^{A} x an heta \, \mathrm{d}A \implies \int_{O}^{C} x \, \mathrm{d}A = 0 = A \overline{x}$$

Here,

- $oldsymbol{A}$ area of waterline plane
- \overline{x} distance to the centroid from axis OO

Equation for metacentric radius

Considering the shift in centre of buoyancy:

$$U(BB') = \int_O^C x heta
ho g \cdot x \, \mathrm{d}A - \int_O^A x heta
ho g \cdot x \, \mathrm{d}A$$

$$V
ho g(BB') = heta
ho gigg(\int_O^C x^2\,\mathrm{d}A - \int_O^A x^2\,\mathrm{d}Aigg)$$

$$V(BB') = hetaigg(\int_A^C x^2\,\mathrm{d}Aigg) = I heta$$


Here

- $oldsymbol{\cdot}$ V submerged volume
- I second moment of area of the waterline plane about the centroidal axis OO

$$BB' = rac{I heta}{V} pprox (BM) heta \implies BM = rac{I}{V}$$

This result is restricted to small angular displacements — usually up to about 8°— and the restriction is particularly important when the sides of the floating body are not vertical.

Types of tilting



- Pitching tilting about transverse axis
- · Rolling tilting about longitudinal axis

Time period of oscillation

Below equation can be derived by using $T=I\ddot{ heta}$ (for small heta):

$$T = -W(\mathrm{GM})\sin{ heta} = I_G\ddot{ heta}$$

$$rac{\mathrm{d}^2 heta}{\mathrm{d}t^2} = -rac{W(\mathrm{GM})}{I_G} heta = -rac{Mg(\mathrm{GM})}{Mk^2} heta$$

Here

- $m{k}$ Radius of gyration
- M Total mass
- I_G Moment of inertia of the floating body about $\,G\,$

Period of time of oscillation is given by:

$$T=rac{2\pi k}{\sqrt{g({
m GM})}}$$

Liquid cargo in a vessel

- Liquid cargo in a vessel reduces its geocentric height.
- When the cargo is contained in 1 compartment:

$$\Delta ext{GM}_1 = rac{
ho_1 I_1}{
ho v}$$

• When the liquid cargo is contained in $\, n \,$ compartments:

$$\Delta ext{GM} = rac{1}{n^2} (\Delta ext{GM}_1)$$

Equilibrium of Submerged Bodies

Two types.

- · Fully submerged bodies
- · Partially submerged bodies

For equilibrium of such body:

- Weight of the object must be equal to upthrust.
- Center of buoyancy and center of gravity of the submerged body must be on a vertical line.

Relative Equilibrium

When a fluid-contained vessel moves with a constant acceleration it will be transmitted to the fluid. The fluid particles will move to a new position and remain in such position in equilibrium, relative to the vessel. Such equilibrium is known as the Relative Equilibrium of a fluid.

Relative Equilibrium under linear acceleration


No flow of the fluid (relative to the fluid particles). No shear forces, and all forces are normal to the surface they act on. Hence, fluid statics equations can be used in relative equilibrium.

Variation of pressure

Let
$$P = f(x, y, z)$$
.

$$\mathrm{d}p = \frac{\partial p}{\partial x} \mathrm{d}x + \frac{\partial p}{\partial y} \mathrm{d}y + \frac{\partial p}{\partial z} \mathrm{d}z$$

Consider the fluid element containing point A which is under an acceleration of a_x,a_y,a_z in the x,y,z directions.



By applying Newton's second law of motion in all 3 directions:

$$rac{\partial p}{\partial x} = -
ho a_x \ \wedge \ rac{\partial p}{\partial y} = -
ho a_y$$

$$\frac{\partial p}{\partial z} = -
ho(a_z + g)$$

Substituting all the terms:

$$\mathrm{d}p = -\rho a_x \mathrm{d}x - \rho a_y \mathrm{d}y - \rho (a_z + g) \mathrm{d}z$$

Integrating both sides:

$$P = -\rho a_x x - \rho a_y y - \rho (a_z + g) z + c_1$$

Shape of free surface

On the free surface P=0 because gauge pressure is considered.

$$\rho a_x x + \rho a_y y + \rho (a_z + g) z = c_1$$

Free surface is a plane surface in 3D.

Inclination with horizontal plane

Let a vessel be in acceleration in a_x,a_z in x,z directions. $a_y=0$. If $heta_x, heta_y$ are the angles in x,y directions.

$$an\left(heta_{x}
ight)=rac{\mathrm{d}z}{\mathrm{d}x} \ \wedge \ an\left(heta_{y}
ight)=rac{\mathrm{d}z}{\mathrm{d}y}$$

Differentiating the equation of the free surface with respect to x.

$$ho a_x +
ho (a_z + g) rac{\mathrm{d}z}{\mathrm{d}x} = 0 \implies an (heta_x) = rac{-a_x}{a_z + g}$$

$$ho a_y +
ho (a_z + g) rac{\mathrm{d}z}{\mathrm{d}y} = 0 \implies an \left(heta_y
ight) = rac{-a_y}{a_z + g}$$

Relative Equilibrium under Horizontal Acceleration

$$a_x \neq 0 \ \land \ a_y = a_z = 0$$

Equation of the free surface

$$\rho a_x x + \rho g z = c_1$$

Is a straight line in x,z axes. The straight line is at an inclination of $heta_x$:

$$an\left(heta_{x}
ight)=rac{-a_{x}}{g}$$

Vertical Pressure Distribution

Varies only in z direction. Increases with height. Isobars are horizontal.

Relative Equilibrium under Vertical Acceleration


$$a_z \neq 0 \ \land \ a_x = a_y = 0$$

Equation of the free surface

$$\rho(a_z+g)z=c_1$$

Horizontal straight line.

Vertical Pressure Distribution



$$P_1 = -
ho(a_z+g)z_1 + c_1$$
 $P_2 = -
ho(a_z+g)z_2 + c_1$ $P_2 - P_1 = -
ho(a_z+g)(z_2-z_1)$ $P_2 = h
ho(a_z+g)$

Here:

- h
 ho g hydrostatic pressure
- $h
 ho a_z$ due to a_z


Varies only in \boldsymbol{z} direction. Increases with height. Isobars are horizontal.

Forced Vortex Motion

Another type of relative equilibrium. If a fluid-contained vessel is rotating at a constant angular velocity, the fluid will reach a relative equilibrium position and rotate with the vessel. Under this condition, the fluid is said to be in Forced Vortex Motion.

(i) Note

For S1, forced vortex motion, only about vertical axis, is required.



$$P=rac{1}{2}
ho\omega^2r^2-
ho gz+c$$

⚠ TODO

Explain how to derive the above equation.

Equation of the free surface

On the free surface P=0.

$$z=rac{\omega^2}{2g}r^2+c_0$$


The free surface is **parabolic**. The constant part c_0 can be found by a known point of the free surface. For simplicity we can choose the axes so that the free surface passes through (0,0). In that case, equation of the free surface is:

$$z=rac{\omega^2}{2g}r^2$$

Vertical Pressure Distribution

Pressure increases with height. Isobars are parabolic.

Volume of the fluid



Total volume of the fluid is:

$$V = \pi R^2 h_0 + rac{1}{2} \pi R^2 (H - h_0)$$

$$V=rac{1}{2}\pi R^2(H+h_0)$$

Fluids in Motion

Flow

Motion with relative movement between fluid particles where continuous deformation happens.

Classification of fluid flow

Density

Incompressible

Density doesn't vary significantly.

Examples:

- Pipe and channel flows of liquids
- Gas flows in pipes

$$\frac{|\Delta\rho|}{\rho}\ll 1$$

Compressible

Density varies significantly.

Examples:

• Pressure surges in pipes

Viscosity

Non-viscous

Fluid doesn't show any resistance to the flow.

Viscous

Fluid shows any resistance to the flow.

• Newtonian: μ is constant

Examples: Water

• Non-newtonian: μ is not constant

Examples: Paints, Clay, Plastics

Variation of parameters

The parameters:

- Velocity $oldsymbol{V}$
- ullet Pressure $oldsymbol{P}$
- ullet Flow rate Q

Temporal Variation

The variation of the parameters with time.

• Steady: no variation with time

$$V = f(x, y, z)$$

• Unsteady: variation of flow parameters with time

$$V = f(t, x, y, z)$$

Spatial Variation

The variation of the parameters with coordinates.

• Uniform: no variation with spatial parameters

$$V = f(t)$$

• Non-uniform: spatial variation of flow parameters

$$V = f(t, x, y, z)$$

Dimensional

If a variation of flow parameter in a certain direction can be neglected, that can reduce the calculations.

Nature of movement

- Orderly (aka. Laminar)
- Disorderly (aka. Turbulent)

Rotation of particles

- Rotational
 - Usually due to shear forces. Flow of real fluids.
- Non-rotational Flow of frictionless forces.

Flow patterns

Streamline

A line tangential to the flow velocity.

Streamtube

A passage enclosed by a collection of streamlines.

Pathline

Path traced by an individual fluid particle.

Streakline

Suppose a dye is injected into a fluid flow. Streakline indicates the positions of all particles passed through the point of injection.



In steady flow: streamline, pathline and streakline all coincide.

This PDF is saved from https://s1.sahithyan.dev