


SHEET		KALA CARE ERP · PMS	
00		INDEX	
PART A HOW PMS WORKS			
01		Overall Flow	
02		File Map — which file feeds which report	
PART B SETUP AND DATA IN			
03		AOP and Master — nine tabs	
04		Upload and Dedupe	
PART C REVENUE REPORT			
05		Sales and Labour Report	
PART D ENGINEER REPORTS			
06		Employee Productivity	
07		SR Allocation	
08		Training Report	
PART E ANNUAL REPORTS			
09		Service Penetration	
10		AMC and Bandhan Projection	
11		AMC — monthly tab	
12		Customer Delight Index	
13		Service Load and Response	
UPLOADED IN PMS 3 FILES			
Part Sale Detailed ReportLabour Revenue Detailed ReportTraining Report			
VIA DATA UPLOAD 11 FILES			
Response Time & MaxTTR DetailsEFSR ReportCDI Detail ReportLMS Data for ERPAsset Detailed ReportAMC Population ReportAMC Agreement Expiry PlannerAnubandhan Plus QuotesAnubandhan QuotesBandhanPlus QuotesRegular Bandhan Customers			
MASTERS BRIDGES			
SE UID MasterSR Type Master — Sales and LabourSR Type Master — MaxTTRSR Type Master — EFSRSR Type Master — Service LoadLead Category MasterCity Master			
Start / Finish Decision		A person acts Report output	
		System does it Stopped / excluded	

OVERALL FLOW



WHO CAN OPEN PMS

- **PMS Access** opens the module
- **AOP and Master** is granted tab by tab
- Each tab is **view** or **edit**
- Excel export needs its own right

UPLOADED INSIDE PMS – 3

- Part Sale Detailed Report
- Labour Revenue Detailed Report
- Training Report

VIA DATA UPLOAD – 11

- Response Time and MaxTTR Details
- EFSR Report
- CDI Detail Report
- LMS Data for ERP
- Asset Detailed Report
- AMC Population Report
- AMC Agreement Expiry Planner
- Anubandhan Plus Quotes
- Anubandhan Quotes
- BandhanPlus Quotes
- Regular Bandhan Customers


THE SIX PMS PAGES

- AOP and Master
- Sales and Labour Report
- Employee Productivity
- SR Allocation Report
- Training Report
- Annual Reports, five sheets

ORDER THAT MATTERS

- Targets **before** uploads, or there is nothing to measure against
- Masters **before** reports, or rows land in the unmapped bucket

FILE MAP — WHICH FILE FEEDS WHICH REPORT



TOTALS

- **14** source files
- **9** reports
- 3 uploaded in PMS, 11 through Data Upload

FILES FEEDING MORE THAN ONE REPORT

- **MaxTTR Details** → 06, 09, 13
- **EFSR Report** → 06, 07
- **CDI Detail Report** → 06, 12
- **AMC Population** → 10, 11
- **Bandhan Quotes** → 10, 11

SINGLE REPORT FILES

- Part Sale and Labour → 05
- LMS Data for ERP → 06
- Training Report → 08
- Asset Detailed → 09
- AMC Expiry Planner → 11

REPORTS READING TWO OR MORE FILES

- **06 Employee Productivity** — four
- **11 AMC monthly** — three
- **05, 09, 10** — two each


READING THE DRAWING

- A file feeds a report only where a line is drawn. There is no hidden path.

Uploaded inside PMS

Arrives through the Data Upload module

AOP AND MASTER – NINE TABS



FEEDS

- **Target Master** → sheets 05, 06
- **Working days** → sheet 06 productivity
- **SR Type, Sales and Labour** → 05
- **SR Type, MaxTTR** → 06
- **SR Type, EFSR** → 06, 07
- **SR Type, Service Load** → 13
- **Lead Category Master** → 06
- **CDI Target Master** → 12
- **AMC and Bandhan AOP** → 10
- **City Master** → 10
- **Service Load AOP** → 13

SALES AND LABOUR HEADS


- Warranty Post Warranty AMC KOEL AMC OTC Order

RIGHTS


- PMS Access opens the module
- AOP is granted **tab by tab**
- Each tab is **view** or **edit**
- The server checks the same per tab

BRANCHES

- MH – 6 branches KA – 7 branches 420435_1 .. 420435_14



SALES AND LABOUR REPORT



SOURCE FILES

Part Sale Detailed Report

uploaded **inside PMS**

Labour Revenue Detailed Report

uploaded **inside PMS**

PART SALE COLUMNS

ZONE NAME	SD ID	SD NAME	BRANCH ID	BRANCH NAME
INSTANCE ID	SEGMENT	PRODUCT SEGMENT	APPLICATION CODE	
ENGINE SERIAL NO	CLAIM INVOICE NUMBER	CLAIM INVOICE DATE		
CLAIM INVOICE SR TYPE	CLAIM INVOICE SR SUB TYPE	CATEGORY		
PART CATEGORY	PART NUMBER	PART DESCRIPTION	QUANTITY	
NET TAXABLE AMOUNT				

LABOUR COLUMNS

ZONE NAME	SD ID	SD NAME	BRANCH ID	BRANCH NAME
CLAIM INVOICE NUMBER	CLAIM INVOICE DATE	PRODUCT SEGMENT		
SEGMENT	SERIES	SR NUMBER	SR TYPE	SR SUBTYPE
NET TAXABLE AMOUNT				

FORMULAS

Target (period) = Σ full monthly targets of the months touched
Daily Target = Target / days in those months
Target till = Σ monthly target x days in period / days in month
% Achieved = Achi. till / Target x 100

MASTERS USED

Target Master	SR Type Master – Sales and Labour
---------------	-----------------------------------

SHEET

06

KALA CARE ERP · PMS · REPORT

EMPLOYEE PRODUCTIVITY

Open Employee Productivity

Base: every SR with a close date and SE name

Engineer from SE NAME, branch from BRANCH ID

UID known in the SE UID Master?

Yes

Counted under the file's own name

No

Close SR, split by MaxTTR master

Allocate SR, EFSR, TASK ASSIGNED DATE

Days present: distinct TASK END DATE

Working days from AOP, prorated

CDI on ACTIVITY END DATE

Pick period and branches

Per engineer scorecard

Leads on LEAD CREATED DATE

Split by Lead Category Master

Conversion: part and labour amounts

Productivity = total SR / working days

BASE FILE – CLOSE SR

Response Time and MaxTTR Details

via Data Upload

SR NUMBER

SR CLOSE DATE

SE NAME

BRANCH ID

SR TYPE

SR TASK END DATE

ALLOCATE SR

EFSR Report

SERVICE ENGINEER UID

TASK ASSIGNED DATE

SR TYPE

CDI

CDI Detail Report

X TECHNICIAN NAME

ACTIVITY END DATE

CDI CATEGORY

LEADS AND CONVERSION

LMS Data for ERP

LEAD NUMBER

SERVICE ENGINEER UID

LEAD CREATED DATE

LEAD RAISED FOR

PART INVOICE AMOUNT

LABOUR INVOICE AMOUNT

FORMULAS

Productivity = Total SR / Working Days
CDI % = (Promotor - Detractor) / all feedback x 100

MASTERS USED

SE UID Master


SR Type Master – MaxTTR

SR Type Master – EFSR

Lead Category Master

Target Master working days

SR ALLOCATION



SOURCE FILE – THE ONLY ONE

EFSR Report

via **Data Upload**

COLUMNS USED

SERVICE ENGINEER UID	SERVICE ENGINEER NAME	
TASK ASSIGNED DATE	TASK END DATE	SD BRANCH CODE
SR TYPE		

THE TWO MEASURES

- **Allocated** — on TASK ASSIGNED DATE. No close date needed, so an open SR still counts the day it was given out.
- **Closed** — on TASK END DATE, the day the engineer finished. **Not** SR CLOSED DATE, which is the back office closing days later.

FORMULAS

```
Allocated = rows with a UID,
counted on TASK ASSIGNED DATE
Closed = rows with a UID,
counted on TASK END DATE
Closure % = Closed / Allocated x 100
Carry over = Allocated - Closed
```


TIES UP WITH

- Allocated here is the **same figure, same column** as Allocate SR on sheet 06

MASTERS USED

SE UID Master	SR Type Master – EFSR
---------------	-----------------------

TRAINING REPORT



SOURCE FILE

Training Report

uploaded **inside PMS**

THE EIGHT FIXED COLUMNS

UID NO	EMPLOYEE TICKET NUMBER	FULL NAME	OCCUPATION
SKILL	BRANCH NAME	BRANCH ID	HIRE DATE

RECORD KEY

UID NO	SKILL	TRAINING DATE	CATEGORY
--------	-------	---------------	----------

EVERYTHING ELSE IS DYNAMIC

- ZONE NAME, JOB TITLE, TRAINING END DATE, SD NAME, SD ID and the rest are kept **verbatim**
- The file can gain or lose columns and still import

FORMULAS

Record key = UID NO + SKILL
+ TRAINING DATE + CATEGORY
Skills of an engineer
= distinct SKILL for that UID NO
Engineers holding a skill
= distinct UID NO for that SKILL


WHY ALL FOUR KEY PARTS

- UID and SKILL alone collapsed **114 rows** of 407
- Adding TRAINING DATE still collapsed **107**
- All four together drop none

NOT A PERIOD REPORT

- Rows accumulate; the page always shows the **whole history**

SERVICE PENETRATION



POPULATION – LEFT HALF

Asset Detailed Report

via Data Upload

BRANCH ID

SEGMENT

COMMISSIONING DATE

ASSET OPERATIONAL STATUS

SERVICED – MIDDLE

Response Time and MaxTTR Details

INSTANCE ID

ENGINE SERIAL NO

SR CLOSE DATE

BRANCH ID

SEGMENT


FORMULAS

Population = assets commissioned
up to the period end, still active
UNQ AST SR CLOSED = distinct assets
with at least 1 SR closed
PEN % = UNQ AST SR CLOSED
/ Population x 100

COUNTING RULES

- Population is **cumulative as on** the period end, not what was commissioned inside it
- An asset with five closed SRs counts **once**
- Inactive assets are excluded
- Rows: IND, PG, Grand Total

AMC AND BANDHAN PROJECTION



LIVE AMC – F27 YTD ACT AMC NOS

AMC Population Report

AGREEMENT STATUS

AGREEMENT TYPE

BRANCH ID

THE MONTH'S BUSINESS

Anubandhan Plus Quotes

Anubandhan Quotes

BandhanPlus Quotes

Regular Bandhan Customers

PAYMENT UPDATE DATE AND TIME

CITY

WHY CITY, NOT BRANCH

- The quote files are KOEL's, and their branch column follows **KOEL's** structure, not this dealership's
- City to branch is **typed** in the City Master, never guessed

FORMULAS

Live AMC = Active agreements,
every type except KOEL Agreement
Month business = quotes paid
on PAYMENT UPDATE DATE
Achievement % = Live AMC
/ AOP projection x 100
Growth = Live AMC - last year actual

TYPED IN AOP, NEVER COUNTED

Last year actual

AOP projection

Best month of the year

ONLY THE LAST COLUMN MOVES

- The month picker affects the **payments column only**. The population has no month.

SHEET
11

KALA CARE ERP · PMS · ANNUAL REPORTS

AMC — MONTHLY TAB

Open the AMC tab

Which category row?

Bandhan

Bandhan MH and Bandhan KAR

Quote rows with a payment date, split on STATE

No status filter on the Bandhan rows

AMC live

KALA AMC and KOEL Corp

Active, on AGREEMENT START DATE

Expired or Renewed

From the AMC Agreement Expiry Planner

Has an end date?

No

No date: reported in meta

Yes

Expired, on AGREEMENT END DATE

Bought again in a quote file?

No

Yes

Paid, status Payment Success?

No

Not a renewal

Yes

Renewed, in the EXPIRY month

Stored per day, not per month

Working month opens into Monday to Sunday weeks

Year picker uses the START span

Six category rows, month by month

SOURCE FILES — THREE

AMC Agreement Expiry Planner

Expired and Renewed

AMC Population Report

KALA AMC and KOEL Corp

Four Bandhan Quote files

Bandhan MH / KAR, and the renewal match

THE SIX CATEGORY ROWS

Bandhan MHBandhan KARKALA AMCKOEL CorpExpiredRenewed

COLUMNS — EXPIRY PLANNER

INSTANCE IDAGREEMENT NUMBERAGREEMENT END DATE

COLUMNS — AMC POPULATION

AGREEMENT START DATEAGREEMENT STATUSAGREEMENT TYPE

COLUMNS — BANDHAN QUOTES

PAYMENT UPDATE DATE TIMESTATEPULSE INSTANCE IDSTATUS

FORMULAS

Renewal rate = Renewed / Expired x 100
Expiry Planner key
= INSTANCE ID + AGREEMENT NUMBER


THE RENEWAL RULE

- An expiring genset counts as renewed only when its **INSTANCE ID** appears as a quote's **PULSE INSTANCE ID** with a payment date **and** status **Payment Success**
- Counted in the **expiry** month, not the payment month, so the two rows read as "M of the N that expired in April have renewed"
- The Bandhan rows apply **no** status filter; only the renewal match does

WHY THE FY LIST IS SHORT

- Expiries run **years ahead**, so the year picker uses the start dates. Otherwise it would offer years in which nothing was ever sold.

CUSTOMER DELIGHT INDEX



SOURCE FILE — THE ONLY ONE

CDI Detail Report

via **Data Upload**, a standalone file

COLUMNS USED

CDI CATEGORY	ACTIVITY END DATE	BRANCH NAME
X TECHNICIAN NAME		

THE THREE BUCKETS

- **Promotor** — CDI category 09 to 10
- **Detractor** — 00 to 06
- **Passive** — everything else

FORMULAS

```
CDI % = (Promotor - Detractor)
        / (Promotor + Passive
            + Detractor) x 100
```


ALSO FEEDS

- The per engineer CDI column on **sheet 06**, matched on X TECHNICIAN NAME

MASTER USED

CDI Target Master

SERVICE LOAD AND RESPONSE



SOURCE FILE – THE ONLY ONE

Response Time and MaxTTR Details

via **Data Upload**

COLUMNS USED

BRANCH ID	SR CLOSE DATE	SR TYPE	SE NAME
RESPONSE WITHIN 4 HRS	CLOSED IN 24 HRS	CLOSED IN 48 HRS	
CLOSED IN ZERO HRS			

FORMULAS

Response % = within 4 hrs / SR x 100
Closure 24 % = closed in 24 hrs / SR x 100
Closure 48 % = closed in 48 hrs / SR x 100
Productivity = SR closed / distinct engineers in the window
Achievement % = SR / AOP x 100

WHY THE FILE'S OWN COLUMNS

- SR open date in the data is unreliable, so response and turnaround are read from the **file's own SLA columns** rather than recomputed

PRODUCTIVITY DENOMINATOR

- A **distinct engineer count**, which cannot be summed across days, so it is counted inside each window

MASTERS USED

SR Type Master – Service Load	Service Load AOP
-------------------------------	------------------