


CCNAv7 ITN Skills Assessment – ITN Final Skills Exam (Equipment)

Your exam may be different

Topology



CCNAv7 ITN Skills Assessment

Assessment Objectives

- **Part 1: Develop an IP Addressing Scheme** (20 points, 25 minutes)
- **Part 2: Initialize and Reload Devices** (10 points, 20 minutes)
- **Part 3: Configure Device IP address and Security Settings** (45 points, 35 minutes)
- **Part 4: Test and Verify IPv4 and IPv6 End-to-End Connectivity** (15 points, 20 minutes)
- **Part 5: Use the IOS CLI to Gather Device Information** (10 points, 10 minutes)

Scenario

In this Skills Assessment (SA) you will configure the devices in a small network. You must configure a router, switch and PCs to support both IPv4 and IPv6 connectivity. You will configure security, including SSH, on the router. In addition, you will test and document the network using common CLI commands.

Required Resources

- 1 Router (Cisco 4221 with Cisco IOS XE Release 16.9.4 universal image or comparable)
- 1 Switch (Cisco 2960 with Cisco IOS Release 15.2(2) Ianbasek9 image or comparable)
- 2 PCs (Windows with a terminal emulation program, such as Tera Term)
- Console cables to configure the Cisco IOS devices via the console ports
- Ethernet cables as shown in the topology

Instructions

Part 1: Develop an IP Addressing Scheme

- **Total points: 20**
- **Time: 25 minutes**

a. Your instructor will assign one of the IPv4 networks from the table below. You will subnet it to provide IP addresses to two subnets that will support the required number of hosts. No subnet calculators may be used. All work must be shown using the IP Addressing worksheet below.

| Network | Number of Hosts in Subnet A | Number of Hosts in Subnet B |
|------------------|-----------------------------|-----------------------------|
| 192.168.10.0/24 | 100 | 50 |
| 172.16.1.0/25 | 60 | 20 |
| 209.165.201.0/27 | 12 | 5 |

IP Addressing Worksheet

- [Type 1](#)
- [Type 2](#)
- [Type 3](#)

| Specification | Subnet A | Subnet B |
|---|---|---|
| Number of bits in the subnet | 25 | 26 |
| IP mask (binary) | 11111111.11111111. 11111111.10000000 | 11111111.11111111. 11111111.11000000 |
| New IP mask (decimal) | 255.255.255.128 | 255.255.255.192 |
| Maximum number of usable subnets (including the 0 th subnet) | 2 | 4 |
| Number of usable hosts per subnet | 126 | 62 |
| IP Subnet | 192.168.10.0 | 192.168.10.128 |
| First IP Host address | 192.168.10.1 | 192.168.10.129 |
| Last IP Host address | 192.168.10.126 | 192.168.10.190 |

b. Record your subnet assignment in the table below.

- 1) Assign the first IPv4 address of each subnet to a router interface
 - (i) subnet A is hosted on R1 G0/0/1
 - (ii) subnet B is hosted on R1 G0/0/0
- 2) Assign the last IPv4 address of each subnet to the PC NIC
- 3) Assign the second IPv4 address of subnet A to S1
- 4) List the maximum number of useable hosts per subnet

| Description | Subnet A | Subnet B |
|-------------------------|-----------------------|-----------------------|
| First IP address | 192.168.10.1 | 192.168.10.129 |
| Last IP address | 192.168.10.126 | 192.168.10.190 |
| Maximum number of hosts | 126 | 62 |

c. Record the IP address information for each device:

| Device | IP address | Subnet Mask | Gateway | Points |
|-----------|-----------------------|------------------------|------------------------|----------|
| PC-A | 192.168.10.126 | 255.255.255.128 | 192.168.10.1 | 2 points |
| R1-G0/0/0 | 192.168.10.129 | 255.255.255.192 | N/A | 2 points |
| R1-G0/0/1 | 192.168.10.1 | 255.255.255.128 | N/A | 2 points |
| S1 | 192.168.10.2 | 192.168.10.1 | 255.255.255.128 | 2 points |
| PC-B | 192.168.10.190 | 255.255.255.192 | 192.168.10.129 | 2 points |

d. Use the IPv6 address 2001:db8:acad::/48 and create two subnets for use in this network. Record the IPv6 addresses in the table.

| Assigned to Interface | IPv6 Subnet Address | Prefix Length |
|-----------------------|-----------------------------|---------------|
| G0/0/1 | 2001:db8:acad:a::/64 | 64 |
| G0/0/0 | 2001:db8:acad:b::/64 | 64 |

e. Record the IPv6 address information for each device.

Note: Use FE80::1 as the link-local address on both router interfaces.

| Device | IPv6 address | Prefix Length | Gateway | Points |
|------------------|---------------------------|---------------|---------|--------|
| R1-G0/0/0 | 2001:db8:acad:b::1 | 64 | N/A | 3 pts |

| Device | IPv6 address | Prefix Length | Gateway | Points |
|-----------|--------------------|---------------|--------------------|--------|
| R1-G0/0/1 | 2001:db8:acad:a::1 | 64 | N/A | 3 pts |
| S1 | 2001:db8:acad:a::2 | 64 | 2001:db8:acad:a::1 | 4 pts |

Before proceeding, verify your IP addressing scheme with the instructor.

Instructor Sign-off Part 1:

Instructor Sign-off

Total Points for Part 1 (20 points):

Enter score here.

Part 2: Initialize and Reload Devices

- Total points: 10
- Time: 20 minutes
- Erase the startup configurations and VLANs from the router and switch and reload the devices.

On Switch

- Switch>**enable**
- Switch#**erase startup-config**
- Erasing the nvram filesystem will remove all configuration files!
Continue? [confirm]
- [OK]
- Erase of nvram: complete
- %SYS-7-NV_BLOCK_INIT: Initialized the geometry of nvram
- Switch#**delete vlan.dat**
- Switch#**reload**

Proceed with reload? [confirm]

On Router

```
Router>enable
Router#erase startup-config
Erasing the nvram filesystem will remove all configuration files!
Continue? [confirm]
[OK]
Erase of nvram: complete
%SYS-7-NV_BLOCK_INIT: Initialized the geometry of nvram
Router#reload
Proceed with reload? [confirm]
Initializing Hardware ...
```

Would you like to enter the initial configuration dialog? [yes/no] :

no

- After the switch is reloaded, change the SDM template to one that supports IPv6 as necessary, and reload the switch again.

On Switch:

- Switch>
- Switch>enable
- Switch#configure terminal
-
- Switch(config) #**sdm prefer dual-ipv4-and-ipv6 default**
- Changes to the running SDM preferences have been stored, but cannot take effect until the next reload.
- Use 'show sdm prefer' to see what SDM preference is currently active.
- Switch(config) #**exit**
-

Switch#**reload**

Before proceeding, ask your instructor verify device initializations.

Instructor Sign-off Part 2:

Instructor Sign-off

Total points (10 points):

Enter score here.

Part 3: Configure Device IP Address and Security Settings

- **Total points: 45**
- **Time: 35 minutes**

Step 1: Configure R1.

Configuration tasks for R1 include the following:

| Task | Specification | Points |
|--------------------|---------------|---------|
| Disable DNS lookup | | |
| Router name | R1 | 1 point |
| Domain name | ccna-lab.com | 1 point |

| Task | Specification | Points |
|---|--|----------|
| Encrypted privileged EXEC password | ciscoenpass | 1 point |
| Console access password | ciscoconpass | 1 point |
| Set the minimum length for passwords | 10 characters | 2 points |
| Create an administrative user in the local database | Username: admin Password: admin1pass | 2 points |
| Set login on vty lines to use local database | | 1 point |
| Set vty lines to accept SSH connections only | | 1 point |
| Encrypt the clear text passwords | | 1 point |
| Configure an MOTD Banner | | 1 point |
| Enable IPv6 Routing | | 1 point |
| Configure Interface G0/0/0 | Set the description Set the Layer 3 IPv4 address Set the IPv6 Link Local Address as FE80::1 Set the Layer 3 IPv6 address Activate Interface | 6 points |
| Configure Interface G0/0/1 | Set the description Set the Layer 3 IPv4 address Set the IPv6 Link Local Address as FE80::1 Set the Layer 3 IPv6 address Activate Interface | 6 points |
| Generate an RSA crypto key | 1024 bits modulus | 2 points |

On Router

```
Router>enable  
Router#configure terminal  
  
Router(config)#no ip domain lookup  
  
Router(config)#hostname R1  
  
R1(config)#ip domain-name ccna-lab.com  
  
R1(config)#enable secret ciscoenpass  
  
R1(config)#line console 0  
  
R1(config-line)#password ciscoconpass  
R1(config-line)#login  
R1(config-line)#exit  
  
R1(config)#security passwords min-length 10  
  
R1(config)#username admin secret admin1pass  
  
R1(config)#line vty 0 15  
R1(config-line)#login local  
R1(config-line)#transport input ssh
```

```
R1 (config-line) #exit

R1 (config) #service password-encryption

R1 (config) #banner motd #Unauthorized Access is Prohibited!#

R1 (config) # ipv6 unicast-routing

R1 (config) #interface g0/0/0
R1 (config-if) #description Connect to Subnet B
R1 (config-if) #ip address 192.168.10.129 255.255.255.192
R1 (config-if) #ipv6 address FE80::1 link-local
R1 (config-if) #ipv6 address 2001:db8:acad:b::1/64
R1 (config-if) #no shutdown
R1 (config-if) #exit

R1 (config) #interface g0/0/1
R1 (config-if) #description Connect to Subnet A
R1 (config-if) #ip address 192.168.10.1 255.255.255.128
R1 (config-if) #ipv6 address FE80::1 link-local
R1 (config-if) #ipv6 address 2001:db8:acad:a::1/64
R1 (config-if) #no shutdown
R1 (config-if) #exit
```

```
R1 (config) #crypto key generate rsa
```

The name for the keys will be: R1.ccna-lab.com

Choose the size of the key modulus in the range of 360 to 2048 for your

General Purpose Keys. Choosing a key modulus greater than 512 may take a few minutes.

How many bits in the modulus [512]: **1024**

% Generating 1024 bit RSA keys, keys will be non-exportable...[OK]

Step 2: Configure S1.

Configuration tasks for S1 include the following:

| Task | Specification | Points |
|---|---|---------|
| Disable DNS lookup | | 1 point |
| Switch name | S1 | 1 point |
| Domain name | ccna-lab.com | 1 point |
| Encrypted privileged EXEC password | ciscoenpass | 1 point |
| Console access password | ciscoconpass | 1 point |
| Shutdown all unused interfaces | F0/1-4, F0/7-24, G0/1-2 | 1 point |
| Create an administrative user in the local database | Username: admin Password: admin1pass | 1 point |
| Set login on vty lines to use local database | | 1 point |
| Set vty lines to accept SSH connections only | | 1 point |
| Encrypt the clear text passwords | | 1 point |

| Task | Specification | Points |
|---|--|----------|
| Configure an MOTD Banner | | 1 point |
| Generate an RSA crypto key | 1024 bits modulus | 2 points |
| Configure Management Interface (SVI) on VLAN1 | Set the description Set the Layer 3 IPv4 address Set the IPv6 Link Local Address as FE80::2 Set the Layer 3 IPv6 address | 2 points |

```
Switch>enable
```

```
Switch#configure terminal
```

```
Switch(config)#no ip domain lookup
```

```
Switch(config)#hostname S1
```

```
S1(config)#ip domain-name ccna-lab.com
```

```
S1(config)#enable secret ciscoenpass
```

```
S1(config)#line console 0
```

```
S1(config-line)#password ciscoconpass
```

```
S1(config-line)#login
```

```
S1(config-line)#exit
```

```
S1(config)#interface range f0/1-4, f0/7-24, g0/1-2
S1(config-if-range)#shutdown

S1(config)#username admin secret admin1pass

S1(config)#line vty 0 15
S1(config-line)#login local
S1(config-line)#transport input ssh
S1(config-line)#exit

S1(config)#service password-encryption

S1(config)#banner motd #Unauthorized Access is Prohibited!#
S1(config)#crypto key generate rsa
The name for the keys will be: S1.ccna-lab.com
Choose the size of the key modulus in the range of 360 to
2048 for your
    General Purpose Keys. Choosing a key modulus greater than
512 may take
    a few minutes.

How many bits in the modulus [512]: 1024
% Generating 1024 bit RSA keys, keys will be non-
exportable...[OK]

S1(config)#interface vlan 1
S1(config-if)#description Switch Subnet A
S1(config-if)#ip address 192.168.10.2 255.255.255.128
S1(config-if)#ipv6 address FE80::2 link-local
S1(config-if)#ipv6 address 2001:db8:acad:a::2/64
```


```
S1(config-if)#no shutdown  
S1(config-if)#exit  
  
S1(config)#ip default-gateway 192.168.10.1
```

Step 3: Configure host computers.

After configuring each host computer, record the host network settings with the `ipconfig /all` command. (2 points)

| PC-A Network Configuration (1 point) | |
|--------------------------------------|---------------------------|
| Description | |
| Physical Address | 00E0.F9BB.3B05 |
| IPv4 Address | 192.168.10.126 |
| Subnet Mask | 255.255.255.128 |
| IPv4 Default Gateway | 192.168.10.1 |
| IPv6 Address | 2001:DB8:ACAD:A::A |
| IPv6 Default Gateway | FE80::1 |

PC-A



```
C:\>ipconfig /all
```

```
FastEthernet0 Connection: (default port)
```

```
Connection-specific DNS Suffix...:
```

```
Physical Address.....: 00E0.F9BB.3B05
```

```
Link-local IPv6 Address.....:
```

```
FE80::2E0:F9FF:FEBB:3B05
```

```
IPv6 Address.....: 2001:DB8:ACAD:A::A
```

```
IPv4 Address.....: 192.168.10.126
```

```

Subnet Mask.....: 255.255.255.128
Default Gateway.....: FE80::1
                                192.168.10.1

DHCP Servers.....: 0.0.0.0

DHCPv6 IAID.....:

DHCPv6 Client DUID.....: 00-01-00-01-32-43-85-
90-00-E0-F9-BB-3B-05


DNS Servers.....: ::

                                0.0.0.0

```

| PC-B Network Configuration (1 point) | |
|--------------------------------------|---------------------------|
| Description | |
| Physical Address | 00E0.B026.E358 |
| IPv4 Address | 192.168.10.190 |
| Subnet Mask | 255.255.255.192 |
| IPv4 Default Gateway | 192.168.10.129 |
| IPv6 Address | 2001:DB8:ACAD:B::B |
| IPv6 Default Gateway | FE80::1 |

PC-B



```
C:\>ipconfig /all
```

```
FastEthernet0 Connection: (default port)
```

```
Connection-specific DNS Suffix...:
```

```
Physical Address.....: 00E0.B026.E358
```

```
Link-local IPv6 Address.....:
```

```
FE80::2E0:B0FF:FE26:E358
```

```
IPv6 Address.....: 2001:DB8:ACAD:B::B  
IPv4 Address.....: 192.168.10.190  
Subnet Mask.....: 255.255.255.192  
Default Gateway.....: FE80::1  
                                192.168.10.129  
DHCP Servers.....: 0.0.0.0  
DHCPv6 IAID.....:  
DHCPv6 Client DUID.....: 00-01-00-01-A3-07-96-  
75-00-E0-B0-26-E3-58  
DNS Servers.....: ::  
                                0.0.0.0
```

Points for Step 1 (28 points):

Enter score here.

Points for Step 2 (15 points):

Enter score here.

Points for Step 3 (2 points):

Enter score here.

Instructor Sign-off Part 4:

Instructor Sign-off

Total Points for Part 3 (45 points)

Enter score here.

Part 4: Test and Verify End-to-End Connectivity

- **Total points: 15**
- **Time: 10 minutes**

Use the ping command to test IPv4 and IPv6 connectivity between all network devices.

Note: If pings to host computers fail, temporarily disable the computer firewall and retest.

Use the following table to methodically verify connectivity with each network device. Take corrective action to establish connectivity if a test fails:

| From | To | Protocol | IP Address | Ping Results | Points |
|------|-----------|----------|--------------------|--------------|---------|
| PC-A | R1 G0/0/0 | IPv4 | 192.168.10.129 | success | 1 point |
| | | IPv6 | 2001:DB8:ACAD:B::1 | success | 1 point |
| | R1 G0/0/1 | IPv4 | 192.168.10.1 | success | 1 point |
| | | IPv6 | 2001:DB8:ACAD:A::1 | success | 1 point |
| | S1 VLAN 1 | IPv4 | 192.168.10.2 | success | 1 point |
| | | IPv6 | 2001:db8:acad:a::2 | success | 1 point |
| | PC-B | IPv4 | 192.168.10.190 | success | 1 point |
| | | IPv6 | 2001:DB8:ACAD:B::B | success | 1 point |
| PC-B | R1 G0/0/0 | IPv4 | 192.168.10.129 | success | 1 point |
| | | IPv6 | 2001:DB8:ACAD:B::1 | success | 1 point |
| | R1 G0/0/1 | IPv4 | 192.168.10.1 | success | 1 point |
| | | IPv6 | 2001:DB8:ACAD:A::1 | success | 1 point |
| | S1 VLAN 1 | IPv4 | 192.168.10.2 | success | 1 point |
| | | IPv6 | 2001:db8:acad:a::2 | success | 1 point |

In addition to the ping command, what other command is useful in displaying network delay and breaks in the path to the destination? (1 point)

tracert or traceroute

Instructor Sign-off Part 4:

Instructor Sign-off

Total points for Part 4 (15 points):

Enter score here.

Part 5: Use the IOS CLI to Gather Device Information

- Total points: 10
- Time: 10 minutes

Step 1: Issue the appropriate command to discover the following information: `show version`

| Description | Command | Points |
|------------------------|---------|-----------|
| Router Model | blank | 1/3 point |
| IOS Image File | blank | 1/3 point |
| Total RAM | blank | 1/3 point |
| Total Flash Memory | blank | 1/3 point |
| Configuration Register | blank | 1/3 point |
| CLI Command Used | blank | 1/3 point |

Step 2: Enter the appropriate CLI command needed to display the following on R1:

| Command Description | Command | Points |
|---|---------|---------|
| Display a summary of important information about the IPv4 interfaces on R1. | blank | 1 point |
| Display the IPv4 routing table. | blank | 1 point |
| Display the Layer 2 to Layer 3 mapping of addresses on R1. | blank | 1 point |
| Display detailed IPv4 information about interface G0/0/0 on R1. | blank | 1 point |
| Display the IPv6 routing table. | blank | 1 point |

| Command Description | Command | Points |
|---|---------|---------|
| Display a summary of IPv6 interface addresses and status. | blank | 1 point |
| Display information about the devices connected to R1. Information should include Device ID, Local Interface, Hold time, Capability, Platform, and Port ID. | blank | 1 point |
| Save the current configuration so it will be used the next time the router is started. | blank | 1 point |

Instructor Sign-off Part 5:

Instructor Sign-off

Total points for Part 5 (10 points):

Enter score here.

Part 6: Cleanup

NOTE: DO NOT PROCEED WITH CLEANUP UNTIL YOUR INSTRUCTOR HAS GRADED YOUR SKILLS EXAM AND HAS INFORMED YOU THAT YOU MAY BEGIN CLEANUP.

Unless directed otherwise by the instructor, restore host computer network connectivity, and then turn off power to the host computers.

Before turning off power to the router and switch, remove the NVRAM configuration files (if saved) from both devices.

Disconnect and neatly put away all LAN cables that were used in the Final.

Router Interface Summary Table

| Router Model | Ethernet Interface #1 | Ethernet Interface #2 | Serial Interface #1 | Serial Interface #2 |
|--------------|--------------------------------|--------------------------------|--------------------------|--------------------------|
| 1800 | Fast Ethernet 0/0 (F0/0) | Fast Ethernet 0/1 (F0/1) | Serial 0/0/0 (S0/0/0) | Serial 0/0/1 (S0/0/1) |
| 1900 | Gigabit Ethernet 0/0 (G0/0) | Gigabit Ethernet 0/1 (G0/1) | Serial 0/0/0 (S0/0/0) | Serial 0/0/1 (S0/0/1) |

| Router Model | Ethernet Interface #1 | Ethernet Interface #2 | Serial Interface #1 | Serial Interface #2 |
|--------------|---------------------------------|---------------------------------|-----------------------|-----------------------|
| 2801 | Fast Ethernet 0/0 (F0/0) | Fast Ethernet 0/1 (F0/1) | Serial 0/1/0 (S0/1/0) | Serial 0/1/1 (S0/1/1) |
| 2811 | Fast Ethernet 0/0 (F0/0) | Fast Ethernet 0/1 (F0/1) | Serial 0/0/0 (S0/0/0) | Serial 0/0/1 (S0/0/1) |
| 2900 | Gigabit Ethernet 0/0 (G0/0) | Gigabit Ethernet 0/1 (G0/1) | Serial 0/0/0 (S0/0/0) | Serial 0/0/1 (S0/0/1) |
| 4221 | Gigabit Ethernet 0/0/0 (G0/0/0) | Gigabit Ethernet 0/0/1 (G0/0/1) | Serial 0/1/0 (S0/1/0) | Serial 0/1/1 (S0/1/1) |
| 4300 | Gigabit Ethernet 0/0/0 (G0/0/0) | Gigabit Ethernet 0/0/1 (G0/0/1) | Serial 0/1/0 (S0/1/0) | Serial 0/1/1 (S0/1/1) |

Note: To find out how the router is configured, look at the interfaces to identify the type of router and how many interfaces the router has. There is no way to effectively list all the combinations of configurations for each router class. This table includes identifiers for the possible combinations of Ethernet and Serial interfaces in the device.

The table does not include any other type of interface, even though a specific router may contain one. An example of this might be an ISDN BRI interface. The string in parenthesis is the legal abbreviation that can be used in Cisco IOS commands to represent the interface.