Turner Lab Notebook

Callum Malcolm

Contents

Wednesday 15-03-2023 Cell Culture	2
N2 Growth Curve	2
Thursday 16-03-2023 N2/BLLW Growth Curve Day 1	 9
Friday 17-03-2023 N2/BLLW Growth Curve Day 2	
Saturday 18-03-2023 N2/BLLW Growth Curve Day 3	 4
Sunday 18-03-2023 N2/BLLW Growth Curve Day 4	 4
Monday 20-03-2023 N2 Growth Curve Day 5 Split Cells Seed BLLW	 4 4 4
Tuesday 21-03-2023	4
Friday 24-03-2023 Seed Cells - N2/RBL1/JIRE	 4
Tuesday 02-05-2023 Seeding Cells - N2/RBL1/RAMOS	
Wednesday 03-05-2023 Split Cells	 E .
Thursday 04-05-2023	Ę
Monday 19-06-2023 Split Cells Seed EC50	E .
Tuesday 20-06-2023 RNA Extraction for SP Test 3 Sample	 8

Wednesday 21-06-2023	9
Tapestation_230619_SPTest3_cDNA	9
Thursday 22-06-2023	10
Collect EC50 Plate	10
Friday 23-06-23	10
Split Cells	10
Seed EC50	10
Monday 26-06-23	11
Collect EC50 Plate	11
Monday 24-07-2023	12
Seeding Cells - RAMOS/FDC	12
Tuesday 25-07-2023	13

Wednesday 15-03-2023

Cell Culture


- Given N2/RBL1/BLLW PDX line from Chris Steele

N2 Growth Curve

Looking to compare N2 growth on and off feeders $\,$

1. Seeded 2mL of N2/BLLW cell suspension at $0.25\mathrm{x}10^6\mathrm{cells/mL}$

96 Well Plate Map



Thursday 16-03-2023

N2/BLLW Growth Curve Day 1

- Cells gently mixed
- 30 μL cell suspension taken and counted
- Only counted 1 square and multiplied by 4

Cell Line	FDC Status	Count	Cell Number
N2	+ FDC	25	2000000
N2	+ FDC	26	2080000
N2	+ FDC	12	960000
N2	- FDC	15	1200000
N2	- FDC	14	1120000
N2	- FDC	6	480000
BLLW	+ FDC	6	480000
BLLW	+ FDC	6	480000
BLLW	+ FDC	5	400000
BLLW	- FDC	3	240000
BLLW	- FDC	3	240000
BLLW	- FDC	6	480000

Friday 17-03-2023

N2/BLLW Growth Curve Day 2

- Cells gently mixed
- 30 μL cell suspension taken and counted
- Only counted 1 square and multiplied by 4

FDC Status	Count	Cell Number
+ FDC	36	2880000
+ FDC	28	2240000
+ FDC	38	3040000
- FDC	61	4880000
- FDC	38	3040000
- FDC	16	1280000
+ FDC	3	240000
+ FDC	5	400000
+ FDC	5	400000
- FDC	1	80000
- FDC	0	0
- FDC	1	80000
	+ FDC + FDC - FDC - FDC - FDC + FDC + FDC + FDC - FDC - FDC	+ FDC 36 + FDC 28 + FDC 38 - FDC 61 - FDC 38 - FDC 16 + FDC 3 + FDC 5 - FDC 1 - FDC 0

Split Cells

Cell Line	$\mathrm{Cells/mL}$	Cells/mL Seeded	CS volume	Final Volume	Seeded Cells/mL
N2 RBL1	$8.8 \text{x} 10^5 \\ 8.6 \text{x} 10^5$	$3x10^5$. $3x10^5$.	$\begin{array}{c} 6.8~\mathrm{mL} \\ 11.6~\mathrm{mL} \end{array}$	$12~\mathrm{mL}$ $12~\mathrm{mL}$	$3x10^5 \\ 5x10^5$

Saturday 18-03-2023

N2/BLLW Growth Curve Day 3

• Counted by Chris

Sunday 18-03-2023

N2/BLLW Growth Curve Day 4

• Counted by Chris

Monday 20-03-2023

N2 Growth Curve Day 5

- BLLW were all dead, experiment stopped
- Cells gently mixed
- 30 μ L cell suspension taken and counted
- ullet Only counted 1 square and multiplied by 4

Cell Line	FDC Status	Count	Cell Number
N2	+ FDC	146	11680000
N2	+ FDC	112	8960000
N2	+ FDC	132	10560000
N2	- FDC	112	8960000
N2	- FDC	155	12400000
N2	- FDC	141	11280000

Split Cells

- Split cell lines N2/RBL1/JIRE
- Dirty split 1:2

Seed BLLW

- Given BLLW aliquot from Chris Steel
- Thawed and resuspended in 12 mL media
- Added to T75 pre-seeded with FDC cells (from Chris Steel)

Tuesday 21-03-2023

Large Infection in TC

- N2 Growth Curve stopped

Friday 24-03-2023

Seed Cells - N2/RBL1/JIRE

- Vials given by Chris Steel
- Thawed and resuspended in 12 mL media
- Added to T75 pre-seeded with FDC cells (from Chris Steel)

Tuesday 02-05-2023

Seeding Cells - N2/RBL1/RAMOS

1. Thawed N2, RBL1, and RAMOS into T75 flasks Note: N2 and RBL1 flaskes seeded with feeders

Wednesday 03-05-2023

Split Cells

Cell Line	Cells/mL	Cells/mL Seeded	CS volume	Final Volume	Last day split	P number
N2	$8.93 \text{x} 10^5$	$3x10^{5}$.	$6.71~\mathrm{mL}$	$12 \mathrm{mL}$	Tues 02-05-23	2
RBL1	$7.73 \text{x} 10^5$	$3x10^{5}$.	$7.76~\mathrm{mL}$	$12 \mathrm{mL}$	Tues $02-05-23$	2

- $2.\ \,$ Expanded N2-Barcodes to T175
- 3. Seeded feeders into 96-well
 - a. Diluted feeders to $3.2\mathrm{x}10^4~\mathrm{cells/mL}$
 - b. Add $100\mu\mathrm{L}$ cell suspension to each well

Thursday 04-05-2023

Monday 19-06-2023


Split Cells

- Split N2/RBL1/JIRE
- Added 10 mL media to BLLW
 - * Lots of dead cells observed

Seed EC50

- Plate ID: EC50_230619_Plate1
- Cylophosphamide (Stock: 20mM) EC50 for N2 and RBL1

96 Well Plate Map EC50_230619_plate1



Drug Dilutions

Drug	Dilution	Concentration	Units	Starting_Concentration
Cyclophosphamide	1	20	uM	20000
Cyclophosphamide	2	2	uM	2000
Cyclophosphamide	3	0.2	uM	200
Cyclophosphamide	4	0.02	uM	20
Cyclophosphamide	5	0.002	uM	2
Cyclophosphamide	6	0.0002	uM	0.2
Cyclophosphamide	7	2e-05	uM	0.02
Cyclophosphamide	8	2e-06	uM	0.002
Cyclophosphamide	9	2e-07	uM	0.0002

Tuesday 20-06-2023

RNA Extraction for SP Test 3 Sample

- Sample collected:
- Low number of cells so used Pico-Pure Kit
- 1 sample (n = 1)

Note before starting:

- Pre-heat block to $42\mathrm{C}$
- Pre-make DNAse treatment master mix (1.1n)

Volume	MM volume
$5 \mu L$ $35 \mu L$	$5.5 \ \mu L \\ 38.5 \ \mu L$
	$5 \mu L$

RNA Extraction Pico-Pure Protocol

- 1. Extract cells with 100 μ L of Extraction Buffer (XB)
 - Resuspend the cell pellet gently by pipetting
 - DO NOT VORTEX
- 2. Incubate at 42C for 30min
- 3. Centrifuge sample at 3000xg for two minutes
- 4. Collect supernatant
 - Can stop here and freeze RNA at 70C
- 5. Pre-condition the RNA Purification Column
 - Add 250 μ L Conditioning Buffer onto the purification column filter membrane
 - Incubate RNA Purification Column with CB for 5min at RT
 - Centrifuge purification column at 16000xg for 1 min
- 6. Pipette 100 μ L of 70% Ethanol (EtOH) into cell extract
 - Mix well by pipetting
 - DO NOT VORTEX
- 7. Add cell extract to column
- 8. Centrifuge column for 2 minutes at 100 x g and then 16000 x g for 30s
- 9. Pipette 100 μ L Wash Buffer 1 (W1) into the purification column and centrifuge for 1min at 8000 x g
- 10. Add 40 μ L of DNAse treatment master mix to purification tube
- Add directly onto membrane
- 11. Incubate at RT for 15 min
- 12. Pipette 40 μ L Wash Buffer 1 (W1) onto purification column membrane and centrifuge at 8000 x g for 15 seconds
- 13. Pipette 100 μ L Wash Buffer 1 (W2) into purification column membrane and centriguge for one minute at 8000 x g
- 14. Pipette 100 μ L Wash Buffer 1 (W2) into purification column membrane and centriguge for two minutes at 16000 x g
 - Check if any wash buffer remains in column and centrifuge again at $16000 \times g$ for one minute to clear all the liquid
- 15. Transfer purification column to new 0.5mL tube
 - Insert purification column/0.5mL assembly into 1.5mL tube for centrifugation
- 16. Pipette EB directly onto membrane of the purification column
 - Gently touch tip to surface of membrane to ensure maximum absorption of EB into membrane
 - Use 11 μL to 30 μL EB
- 17. Incubate purification column for one minute at room temperature

- 18. Centrifuge column for one minute at 1000 x g to distribute EB in column
- 19. Centrifuge column for one minute at 16000 x g to elute RNA
- 20. Started PCR and completed Tapestation

Tapestation_230620

High-Sensitivity RNA ScreenTape Protocol

Results

- Inconclusive, proceeded with PCR

Reverse Transcription

Notes Before Starting:

- Label PCR strip tubes
- Thaw RT reagents
- Uses WILDseq specific RT primer
- Dilute RT primer to $2\mu M$
 - Do this in a PCR hood
 - IMPORTANT Do not mix primers and carefully note which RT primer is added to which sample
- Make RT and ExoI master mixes (MM) before starting
 - MM amounts are 1.1n

Protocol:

Note: Used "rt" protocol in callum folder on thermocycler for heating steps

- 1. In PCR strip tubes diluted 1-5ug RNA in a total volume of 10 μ L of RNAse/DNAse-free water
- $2.\ {\rm Added}\ 1$ ul of RT primer
- 3. Added 1 ul of dNTPs
- 4. Denatured at 65 C for 5 mins in PCR machine
- 5. Added straight to ice for 2 mins
- 6. Spun to get liquid to bottom of tube
- 7. Prepared master mix of RT enzyme and buffers (Made prior to starting)

Component	Volume	MM volume
Component	vorume	wiwi volume
5x SSIV Buffer	$4~\mu { m L}$	$4.4~\mu\mathrm{L}$
SSIV RT	$1~\mu { m L}$	$1.1~\mu\mathrm{L}$
$100~\mathrm{mM}~\mathrm{DTT}$	$1~\mu { m L}$	$1.1~\mu\mathrm{L}$
RNAse Out	$1~\mu L$	$1.1~\mu\mathrm{L}$

- 8. Added 7 μL of RT MM prepared above to each sample and mix
 - Spun briefly to get liquid to bottom of the tube
- 9. In PCR Machine: incubated at 53C for 10 mins followed by 80C for 10 mins
- 10. Added 3 μ L of ExoI MM to each sample

Component	Volume	MM volume
Thermolabile Exonuclease I NEBuffer r3.1*	$\begin{array}{cc} 1~\mu \mathrm{L} \\ 2~\mu \mathrm{L} \end{array}$	$1.1 \ \mu L \\ 2.2 \ \mu L$

- Most PCR buffers are compatible
- 11. In PCR Machine: heat at 37C for 4 mins followed by 80C for 1 min
 - Spin briefly to get liquid to bottom of the tube
- 12. Add 1 μL of RNAse H and incubate at 37C for 20 mins
- 13. Dilute final cDNA 1 in 2 with DNAse/RNAse-free water

PCR Amplification of cDNA

1. Prepare mastermix of below reagents at 1.1x the number of samples

Component	Volume	MM volume
Q5 Master Mix	$25 \mu L$	
$P5_R1_fwd (100\mu M)$	$2.5~\mu\mathrm{L}$	
P7_rev	$2.5~\mu\mathrm{L}$	
DNAse/RNAse H20	$13.5~\mu\mathrm{L}$	
Q5 polymerase	$0.5~\mu\mathrm{L}$	
Total Master Mix volume	40 μ L	
cDNA from above	$10~\mu\mathrm{L}$	

2. Perform PCR using the following parameters:

Steps	Time
Step 1: 98C	30s
Step 2: 98C	10s
Step 3: 61C	30s
Step 4: 72C	30s
Step 5: 72C	$2 \min$
Step 6: 12C	Hold

20-25 cycles of steps 2-4

Ran overnight and left at 12C

Wednesday 21-06-2023

$Tape station _230619 _SPTest3 _cDNA$

High-Sensitivity DNA ScreenTape Protocol


Results

- * Did not work, bands present but faint and not at 200bp
- * Potential solutions:
- Repeat PCR with increased cycles
- Repeat RNA extration with trizol protocol (Anna)

Thursday 22-06-2023

Collect EC50 Plate

- Plate ID: EC50_230619_Plate1



Friday 23-06-23

Split Cells


- 1. Threw out BLLW (all dead)
- 2. Split JIRE 1/2
- 3. Split N2/RBL1 1/4

Seed EC50

• EC50 Plate ID: EC50_230623_Plate1

96 Well Plate Map

EC50_230623_plate1




Drug Dilutions

Drug	Dilution	Concentration	Units	Starting_Concentration
Cyclophosphamide	1	20	uM	20000
Cyclophosphamide	2	13.3	uM	13300
Cyclophosphamide	3	8.89	uM	8890
Cyclophosphamide	4	5.93	uM	5930
Cyclophosphamide	5	3.95	uM	3950
Cyclophosphamide	6	2.63	uM	2630
Cyclophosphamide	7	1.76	uM	1760
Cyclophosphamide	8	1.17	uM	1170
Cyclophosphamide	9	0.78	uM	780

Monday 26-06-23

Collect EC50 Plate

- Plate ID: EC50_230623_Plate1



Break for writing MRes Report: 27/06/2023 - 24/07/2023

Monday 24-07-2023

Seeding Cells - RAMOS/FDC

1. Made new media: AR-1

Solution	ID code	Volume	% Total volume
Advanced RMPI		500 mL	78%
Glutamax	—–	$6.5~\mathrm{mL}$	20%
Pen-Strep	—-	$6.5~\mathrm{mL}$	1%
FBS	—-	$128~\mathrm{mL}$	1%

2. Seeded Feeders

- 2 vial of FDC cells thawed
- 6 mL of FDC cell suspension were added to 2 seperate T75 flasks (Seeding RBL1/BLLW on 25-07-2023)
- Remaining 12 mL of Media were added to T175 (Seeding N2 on 25-07-2023)
- 3. Seeded Ramos WILDseq Barcode Pool 2
- Thawed a vial of RAMOS pool 2 (previously barcorded DATE)
- Resuspended in 5 mL
- Spun down 90* for 5min
- Resuspended in 12 mL of AR-1 media
- Seeded into T75

Experimental Plans

- $1. \ \, {\rm Barcode\ BLLW/RBL1}$
- 2. Set up Drug pressure experiement for RAMOS barcoded cells
- EC50's for cyclophosphamide and methotrexate need to be completed
- Drugs to test (EC50):

Drug	Concentration	Replicates
DMSO	1%	3
Doxorubicin	$200\mathrm{nM}$	3
Methotrexate	$100\mathrm{nM}$	3
Vincristine	$1 \mathrm{nM}$	3

- 3. Do Side Population Experiement for N2 Barcoded Cells
- Grow up sorted side pop to avoid issues with low cell numbers

Tuesday 25-07-2023