'xdg-open' does not open the default browser

Asked 6 years, 1 month ago Modified 3 months ago Viewed 45k times



I have the following scenario:

27

<u>Ubuntu 16.04</u> (Xenial Xerus) machine with Firefox and Google Chrome installed, Chrome being my default browser.



I check these actions in the shell:



cat /usr/share/applications/defaults.list
cat /etc/mailcap
cat /.config/mimeapps.list
cat /.local/share/applications/mimeinfo.cache
x-www-browser-> chrome is launch
xdg-mime query default text/html
response:
google-chrome.desktop

And it does not appear Firefox by any side, always Chrome. This is fine. Also check:

Click on a desktop file *file.html* \rightarrow Chrome is launched.

And now comes the strange behaviour. Say I run:

```
xdg-open "http://www.example.com"
```

For some strange reason, it always opens Firefox. What should I do?

default-browser

Share Improve this question Follow

edited Oct 9, 2022 at 20:15

Peter Mortensen

30.9k 21 104 125

asked Dec 15, 2016 at 20:19

mike 385 1 3 6

What is meant by "it does not appear Firefox by any side"? A machine translation masterpiece? – Peter Mortensen Oct 9, 2022 at 20:16

3 Answers

Highest score (default)

Sorted by:



To set a default browser, make sure that a .desktop file exists for your preferred browser. I'll be setting Mozilla Iceweasel for this example:



Output:

```
iceweasel.desktop
```

Assured you have the file, run:

```
xdg-settings set default-web-browser iceweasel.desktop
# Test that it works
xdg-open "http://example.com"
```

If you don't have a .desktop file:

I use the program <code>surf</code> , which doesn't have a .desktop file. To set this as your web browser, first create the file ~/.local/share/applications/surf.desktop with this following content:

[Desktop Entry]
Type=Application
Name=surf
Comment=Surf minimal web browser
Terminal=false
Exec=surf
Categories=Network;WebBrowser

While not all of this content is required, it helps categorize the file for any future use.

Set the default browser like normal:

```
xdg-settings set default-web-browser surf.desktop
```

And now you're good to go!

Share Improve this answer Follow

edited Oct 9, 2022 at 19:59



Peter Mortensen

30.9k 21 104 125

answered Jun 17, 2018 at 4:51



Nolan Akash **919** 8 21

For me "xdg-settings get default-web-browser" returned "firefox.desktop" already. But running "xdg-settings set default-web-browser firefox.desktop" fixed my problem anyway. – user2707671 Jan 27, 2019 at 22:47

I faced with same problem after adding Postman .desktop file following their doc xdg-settings get default-webbrowser returned proper value. Running @user2707671 advice to try to setup proper browser again fixed the problem – Pavlo Zhukov Apr 30, 2019 at 20:31

I use Luuntu and still cannot fix this. xdg-open always open Firefox. - Minh Nghĩa Feb 18, 2020 at 8:24

1 on kde, if set fails, try: askubuntu.com/questions/62182/... - geekley Sep 1, 2020 at 6:34

Also if you're on Ubuntu and your browser is packaged using a Snap, your application's desktop is *not* named like firefox.desktop (as you see under /snap/), it's like firefox_firefox.desktop or



text/html is for HTML files, i.e., if you open an HTML file then it would open in Google Chrome. For opening URLs, you need to have the x-scheme-handler/https and x-scheme-handler/http entries.

6



You can set that either with xdg-mime. For example, to set Google Chrome as the default browser for xdgopen:

```
xdg-mime default google-chrome.desktop x-scheme-handler/https
xdg-mime default google-chrome.desktop x-scheme-handler/http
```

Or you can add the following lines in file ~/.config/mimeapps.list:

```
x-scheme-handler/http=google-chrome.desktop
x-scheme-handler/https=google-chrome.desktop
```

The above commands basically insert these lines into that file.

Note: you should obviously have the *google-chrome.desktop* file under ~/.local/share/applications or the system-wide alternative location - /usr/share/applications.

For changing the default browser overall, you also have to use xdq-settings as shown by Nolan Akash. xdqsettings changes the value of \$BROWSER, so another way to change it is to explicitly assign the program (not the .desktop file) to the \$BROWSER environment variable and export it.

```
export BROWSER=google-chrome
```

You usually would want to keep this like in ~/.bashrc file (or the equivalent for the shell you use) or in the ~/.profile file and log out and log in to have the environment updated and available for other programs to see.

Share Improve this answer Follow

edited Oct 9, 2022 at 20:08



Peter Mortensen **30.9k** 21 104 125 answered Apr 20, 2021 at 19:56





Just open the Chrome browser and set as the default browser.



Share Improve this answer Follow

edited Oct 9, 2022 at 19:56 Peter Mortensen



104 125

answered Dec 17, 2016 at 9:40





