FEBRUARY 12, 2021 / #NETWORK ENGINEERING

Subnet Cheat Sheet – 24 Subnet Mask, 30, 26, 27, 29, and other IP Address CIDR Network References



Kris Koishigawa

As a developer or network engineer, you may need to occasionally look up subnet mask values and figure out what they mean.

To make your life easier, the freeCodeCamp community has made this simple cheat sheet. Just scroll or use Ctrl/Cmd + f to find the value you're looking for.

Here are the charts, followed by some explanations of what they mean.

CIDR	SUBNET MASK	WILDCARD MASK	# OF IP ADDRESSES	# OF USABLE IP ADDRESS
/32	255.255.255.255	0.0.0.0	1	1
/31	255.255.255.254	0.0.0.1	2	2*
/30	255.255.255.252	0.0.0.3	4	2

/28	255.255.255.240	0.0.0.15	16	14
/27	255.255.255.224	0.0.0.31	32	30
/26	255.255.255.192	0.0.0.63	64	62
/25	255.255.255.128	0.0.0.127	128	126
/24	255.255.255.0	0.0.0.255	256	254
/23	255.255.254.0	0.0.1.255	512	510
/22	255.255.252.0	0.0.3.255	1,024	1,022
/21	255.255.248.0	0.0.7.255	2,048	2,046
/20	255.255.240.0	0.0.15.255	4,096	4,094
/19	255.255.224.0	0.0.31.255	8,192	8,190
/18	255.255.192.0	0.0.63.255	16,384	16,382
/17	255.255.128.0	0.0.127.255	32,768	32,766
/16	255.255.0.0	0.0.255.255	65,536	65,534
/15	255.254.0.0	0.1.255.255	131,072	131,070
/14	255.252.0.0	0.3.255.255	262,144	262,142
/13	255.248.0.0	0.7.255.255	524,288	524,286
/12	255.240.0.0	0.15.255.255	1,048,576	1,048,574
/11	255.224.0.0	0.31.255.255	2,097,152	2,097,150
/10	255.192.0.0	0.63.255.255	4,194,304	4,194,302
/9	255.128.0.0	0.127.255.255	8,388,608	8,388,606
/8	255.0.0.0	0.255.255.255	16,777,216	16,777,214
<i>[</i> 7	254.0.0.0	1.255.255.255	33,554,432	33,554,430

/5	248.0.0.0	7.255.255.255	134,217,728	134,217,726
/4	240.0.0.0	15.255.255.255	268,435,456	268,435,454
/3	224.0.0.0	31.255.255.255	536,870,912	536,870,910
/2	192.0.0.0	63.255.255.255	1,073,741,824	1,073,741,822
/1	128.0.0.0	127.255.255.255	2,147,483,648	2,147,483,646
/0	0.0.0.0	255.255.255.255	4,294,967,296	4,294,967,294

And here's a table of the decimal to binary conversions for subnet mask and wildcard octets:

	SUBNET MASK		WIII DCARD
	SUBNET MASK		WILDCARD
0	00000000	255	11111111
128	10000000	127	01111111
192	11000000	63	00111111
224	11100000	31	00011111
240	11110000	15	00001111
248	11111000	7	00000111
252	11111100	3	00000011
254	11111110	1	00000001
255	11111111	0	00000000

 $^{^*}$ /31 is a special case detailed in <u>RFC 3021</u> where networks with this type of subnet mask can assign two IP addresses as a point-to-point link.

computer networks work here.

Finally, this cheat sheet and the rest of the article is focused on IPv4 addresses, not the newer IPv6 protocol. If you'd like to learn more about IPv6, check out the article on computer networks above.


How Do IP Address Blocks Work?

IPv4 addresses like 192.168.0.1 are really just decimal representations of four binary blocks.

Each block is 8 bits, and represents numbers from 0-255. Because the blocks are groups of 8 bits, each block is known as an **octet**. And since there are four blocks of 8 bits, every IPv4 address is 32 bits.

For example, here's what the IP address 172.16.254.1 looks like in binary:

IPv4 address in dotted-decimal notation



Source: <u>IPv4</u>

128	64	32	16	8	4	2	1
Х	×	X	Х	x	х	x	x

The chart above represents one 8 bit octive.

Now lets say you want to convert the IP address 168.210.225.206. All you need to do is break the address into four blocks (168, 210, 225, and 206), and convert each into binary using the chart above.

Remember that in binary, 1 is the equivalent to "on" and 0 is "off". So to convert the first block, 168, into binary, just start from the beginning of the chart and place a 1 or 0 in that cell until you get a sum of 168.

For example:

128	64	32	16	8	4	2	1
1	0	1	0	1	0	0	0

128 + 32 + 8 = 168, which in binary is 10101000.

If you do this for the rest of the blocks, you'd get 10101000.11010010.11100001.11001110.


What is Subnetting?

If you look at the table above, it can seem like the number of IP addresses is practically unlimited. After all, there are almost 4.2 billion possible IPv4 addresses available.

Because the shortage was recognized years ago, developers came up with a way to split up an IP address into smaller networks called subnets.

This process, called subnetting, uses the host section of the IP address to break it down into those smaller networks or subnets.

Generally, an IP address is made up of network bits and host bits:



Source: What is IPv4


So generally, subnetting does two things: it gives us a way to break up networks into subnets, and allows devices to determine whether another device/IP address is on the same local network or not.

A good way to think about subnetting is to picture your wireless network at home.

Without subnetting, every internet connected device would need its own unique IP address.

But since you have a wireless router, you just need one IP address for your router. This public or external IP address is usually handled automatically,

IP address:



Source: What Is My IP Address?

Now if your device with the internal IP address 192.168.1.101 wants to communicate with another device, it'll use the IP address of the other device and the subnet mask.

The combination of the IP addresses and subnet mask allows the device at 192.168.1.101 to figure out if the other device is on the same network (like the device at 192.168.1.103), or on a completely different network somewhere else online.

Interestingly, the external IP address assigned to your router by your ISP is probably part of a subnet, which might include many other IP addresses for nearby homes or businesses. And just like internal IP addresses, it also needs a subnet mask to work.

mask, devices can look at an IP address, and figure out which parts are the network bits and which are the host bits.

Then using those things, it can figure out the best way for those devices to communicate.

If you've poked around the network settings on your router or computer, you've likely seen this number: 255.255.25.0.

If so, you've seen a very common subnet mask for simple home networks.

Like IPv4 addresses, subnet masks are 32 bits. And just like converting an IP address into binary, you can do the same thing with a subnet mask.

For example, here's our chart from earlier:

128	64	32	16	8	4	2	1
х	X	X	X	x	х	x	x

Now let's convert the first octet, 255:

128	64	32	16	8	4	2	1
1	1	1	1	1	1	1	1

Pretty simple, right? So any octet that's 255 is just 11111111 in binary. This means that 255.255.255.0 is really 11111111.11111111.11111111.000000000 in binary.

Here are the two in both decimal and binary:

TYPE	DECIMAL	BINARY
IP address	192.168.0.101	11000000.10101000.00000000.01100101
Subnet mask	255.255.255.0	11111111.11111111.11111111.00000000

With the two laid out like this, it's easy to separate 192.168.0.101 into network bits and host bits.

Whenever a bit in a binary subnet mask is 1, then the same bit in a binary IP address is part of the network, not the host.


Since the octet 255 is 11111111 in binary, that whole octet in the IP address is part of the network. So the first three octets, 192.168.0, is the network portion of the IP address, and 101 is the host portion.

In other words, if the device at 192.168.0.101 wants to communicate with another device, using the subnet mask it knows that anything with the IP address 192.168.0.xxx is on the same local network.

Another way to express this is with a network ID, which is just the network portion of the IP address. So the network ID of the address 192.168.0.101 with a subnet mask of 255.255.255.0 is 192.168.0.0.

And it's the same for the other devices on the local network (192.168.0.102, 192.168.0.103, and so on).

What Does CIDR Mean and What is CIDR Notation?



Source: Classless Inter-Domain Routing

CIDR was introduced in 1993 as a way to slow the usage of IPv4 addresses, which were quickly being exhausted under the older Classful IP addressing system that the internet was first built on.

CIDR encompasses a couple of major concepts.

The second major concept CIDR introduced is CIDR notation.

CIDR notation is really just shorthand for the subnet mask, and represents the number of bits available to the IP address. For instance, the /24 in 192.168.0.101/24 is equivalent to the IP address 192.168.0.101 and the subnet mask 255.255.255.0.

How to Calculate CIDR Noation

To figure out the CIDR notation for a given subnet mask, all you need to do is convert the subnet mask into binary, then count the number of ones or "on" digits. For example:

TYPE	DECIMAL	BINARY
Subnet mask	255.255.255.0	11111111.11111111.11111111.00000000

Because there's three octets of ones, there are 24 "on" bits meaning that the CIDR notation is /24.

You can write it either way, but I'm sure you'll agree that /24 is a whole lot easier to write than 255.255.255.0.

This is usually done with an IP address, so let's take a look at the same subnet mask with an IP address:

TYPE	DECIMAL	BINARY
IP address	192.168.0.101	11000000.10101000.00000000.01100101
Subnet mask	255.255.255.0	1111111.11111111.1111111.00000000

Let's take a look at the last forth octet in a bit more detail:

TYPE	DECIMAL	BINARY
IP address	101	01100101
Subnet mask	0	00000000

In this case, because all the bits for this octet in the subnet mask are "off", we can be certain that all of the corresponding bits for this octet in the IP address are part of the host.

When you write CIDR notation it's usually done with the network ID. So the CIDR notation of the IP address 192.168.0.101 with a subnet mask of 255.255.255.0 is 192.168.0.0/24.


To see more examples of how to calculate the CIDR notation and network ID for a given IP address and subnet mask, check out this video:

IPv4 Addressing Lesson 2: Network IDs and Subnet Masks



let's zoom out and look at what's known as Classful IP addressing.

Back before subnetting was developed, all IP addresses fell into a particular class:



Source: Subnetting for dummies

Note that there are class D and E IP addresses, but we'll go into these in more detail a bit later.

Classful IP addresses gave network engineers a way to provide different organizations with a range of valid IP addresses.

There were a lot of issues with this approach that eventually lead to subnetting. But before we get into those, let's take a closer look at the different classes.

Class A IP Addresses

- - -

Class A IP addresses range from 1.0.0.0 to 127.255.255.255, with a default mask of 255.0.0.0 (or /8 in CIDR).

This means that Class A addressing can have a total of 128 (2^7) networks and 16,777,214 (2^{24} -2) usable addresses per network.

Also, note that the range 127.0.0.0 to 127.255.255.255 within the Class A range is reserved for host loopback address (see RFC5735).

Class B IP Addresses

For Class B IP addresses, the first two octets (16 bits / 2 bytes) represent the network ID and the remaining two octets (16 bits / 2 bytes) are the host ID.

Class B IP addresses range from 128.0.0.0 to 191.255.255.255, with a default subnet mask of 255.255.0.0 (or /16 in CIDR).

Class B addressing can have 16,384 (2^{14}) network addresses and 65,534 (2^{16}) usable addresses per network.

Class C IP Addresses

For Class C IP addresses, the first three octets (24 bits / 3 bytes) represent the network ID and the last octet (8 bits / 1 bytes) is the host ID.

Class C IP Addresses range from 192.0.0.0 to 223.255.255.255, with a default subnet mask of 255.255.255.0 (or /24 in CIDR).

Class C translates to 2,097,152 (2^{21}) networks and 254 (2^{8} -2) usable addresses per network.

Class D IP addresses are reserved for multicasts. They occupy the range from 224.0.0.0 through 239.255.255.255.

Class E IP addresses are experimental, and are anything over 240.0.0.0.

The Issue with Classful IP Addresses

The main issue with classful IP addresses is that it wasn't efficient, and could lead to a lot of wasted IP addresses.

For example, imagine that you're part of a large organization back then. Your company has 1,000 employees, meaning that it would fall into class B.

But if you look above, you'll see that a class B network can support up to 65,534 usable addresses. That's way more than your organization would likely need, even if each employee had multiple devices with a unique address.

And there was no way your organization could fall back to class C – there just wouldn't be enough usable IP addresses.

So while classful IP addresses were used around the time IPv4 addresses became widespread, it quickly became clear that a better system would be necessary to ensure we wouldn't use up all of the ~4.2 billion usable addresses.

Classful IP addresses haven't been used since they were replaced by CIDR in 1993, and are mostly studied to understand early internet architecture, and why subnetting is important.

If you found this helpful, please share it with your friends so more people can benefit from it.

Also, feel free to reach out on <u>Twitter</u> and let me know what you think.



Kris Koishigawa

Read more posts.

If you read this far, tweet to the author to show them you care.

Tweet a thanks

Learn to code for free. freeCodeCamp's open source curriculum has helped more than 40,000 people get jobs as developers. Get started

ADVERTISEMENT

Video over IP FPGA Cores

Our FPGA cores are JT-NM Tested for proven interoporal Reference designs included.

Nextera Video

. , . .

Donations to freeCodeCamp go toward our education initiatives, and help pay for servers, services, and staff.

You can <u>make a tax-deductible donation here</u>.

Trending Guides

Python list .append() C++ Operators

Python .zip() Function Excel Formulas

What is a QA Engineer? Break in Python

Python Print Same Line Text Align in CSS

Rename Branches in Git How to Minify CSS

What Does Coding Mean? Python Split String

What is Data Analysis? Python List insert()

How to Comment Out CSS Merge Sort Algorithm

Double vs Float in C++ What is an SVG File?

Python Global Variables RGB Colors Explained

How Vectors Work in C++ Square a Number in Python

JavaScript .setTimeout() How to Lock Cells in Excel

Excel Keyboard Shortcuts Python Delete Key from Dict

Excel Absolute Reference Beginner Tech Jobs Examples

Insert Checkbox in Excel Crow's Foot Notation

Our Charity

About Alumni Network Open Source Shop Support Sponsors Academic Honesty

Code of Conduct Privacy Policy Terms of Service Copyright Policy